Add a new distribution to the GAS package

This short note illustrates how to add a new distribution in the **GAS** package. Changes have to be made in the .R files inside the R folder and in the .cpp and .h files inside the src folder of the package tarball, respectively.

The following guidelines apply when:

- 1 You want to add an univariate distribution.
- 2 Your distribution has maximum 5 parameters.

If you want to add a multivariate distribution, most of the following points apply as well. However, additional changes have to be included in order to have a proper implementation. You can email the package maintainer for possible inclusion of your multivariate distribution in the package. Changes with regards to R files are:

- 1 Distribution.R:DistLabels(),DistName(),DistNote(),DistReference(),DistParameters(),DistType(),DistScalingType().
- 2 ParameterConstraints.R: include the possible constraints to the parameters dynamic. Look at the function GetFixedPar_Uni() and GetFixedPar_Multi() for univariate and multivariate distributions, respectively.
- 3 ParNames.R: FullNamesUni(). Choose the labels for the parameters of the distribution between: "location", "scale", "skewness", "shape" and "shape2". These are only names, *i.e.*, the label "location" does not necessarily represent a location parameter.
- 4 StartingValue.R: StaticStarting_Uni(). Use Method of Moments when possible. If you want to add a multivariate distribution, you need to create a new function StartingValues_dist() and link to the MultiGAS_Starting() function. Note that, in the multivariate case, the output of the new StartingValues_dist(), needs to be consistent with that of, for example, of StartingValues_mvt().

Assuming that the label of the new distribution is "poi". Changes with regards to the C++ files are:

- 1 Create poi. cpp with the functions:
 - double dPOI(), probability density function: it accepts the additional boolean argument: bLog, by default bLog = false.
 - double pPOI(), cumulative density function.

- double qPOI(), quantile function.
- double rPOI(), random generator.
- arma::vec mPOI(), it returns an arma::vec with 4 entries containing: the mean, the variance, the skewness coefficient, the kurtosis coefficient (not excess of kurtosis).
- arma::vec poi_Score(), score function.
- arma::mat poi_IM(), information matrix. If the information matrix is not available, then the output of arma::mat poi_IM() is the identity matrix of dimension equal to the number of parameters.

All the function of poi.cpp accept double arguments, expect poi_Score() and poi_IM() that accept an arma::vec argument. See, for example, the file std.cpp.

- 2 Create the header poi.h with all the functions in poi.cpp.
- 3 Modify DistWrap.cpp to include poi.h, add if (Dist == "poi") to all the functions.
- 4 Modify IMWrap.cpp to include poi.h, add if (Dist == "poi") to arma::mat IM_univ().
- 5 Modify Mapping.cpp, the functions: MapParameters_univ()/MapParameters_multi(), UnmapParameters_univ()/UnmapParameters_multi(), MapParametersJacobian_univ()/ MapParametersJacobian_multi(). Use the same structure of the other distributions. If necessary, create global variables as const double dLowerShape and const double dUpperShape to determine the numerical upper and lower bounds for your parameters. You can use the modified logistic mapping function transformation (double Map()), its inverse (double Unmap()) and its derivative (double MapDeriv()).
- 6 Modify ScoreWrap.cpp to include poi.h: add if (Dist == "poi") to arma::vec Score_univ()/arma::vec Score_multi().
- 7 Modify Utils.cpp, functions: int NumberParameters() which returns an integer indicating the number of parameters of your distribution.

If everything have been done correctly you can now compile the package through R CMD BUILD and use all the package functionalities.