Table of Contents:

Table of Contents:	1
Introduction to Batch Processing	4
Enterprise Data Processing	4
Mainframe Data Processing	4
Data Types:	4
Online and Batch Processing	5
Benefits of Batch Processing	5
Working with Batch Processing	6
Examples:	6
Running a Batch Job	6
Other terminology: Batch Job Automation	6
	7
Batch Job Scheduling Batch Processing Prerequisites	8
JCL z/OS 2.4 Update	8
·	
Coding Requirements	9
JCL Coding Rules	9
Planning Processing Requirements	9
Reality of JCL Coding	9
How to copy JCL:	9
Identifying JCL code	10
The empty // curse	10 11
Uppercase Characters	11
Record Length Continuing a statement	12
Statement Breakdown	13
Statement Names	13
Statement Types	13
Parameters	14
Positional Parameters	14
Example:	14
Keyword Parameters	15
Example:	15
Comments	15
JOB Statement Basics	16
Statement Requirements	16
JOB Statement Importance	16
JOB Name Standards	16
Running a JOB Multiple Times	17
Multiple JOB Statements	17

Incorrect JOB Name	18
Statement Positional Parameters	18
Accounting Information:	19
Programmer's Name:	20
Some or No Positional Parameters	20
Statement Keyword Parameters	21
CLASS Parameter	21
MSGCLASS Parameter	21
MSGLEVEL Parameter	23
REGION Parameter	25
NOTIFY Parameter	25
Additional JOB Statement Parameters	27
Popular Statement Parameters	27
TYPRUN Parameter	27
Scenario 1 - TYPRUN HOLD:	27
Scenario 2 - TYPRUN SCAN:	28
Scenario 3 - TYPRUN COPY:	28
Scenario 4 - TYPRUN JCLHOLD:	29
TIME Parameter	29
COND Parameter	30
PRTY Parameter	31
Other JOB Statement Parameters	32
RESTART Parameter	32
Memory-Related Parameters:	32
Output-Related Parameters:	33
SYSAFF Job Processing Environment Parameter	34
SYSTEM Job Processing Environment Parameter	35
SCHENV Job Processing Environment Parameter	35
Identification-Related Parameters	36
Running a Program using EXEC Statements	37
EXEC Statement Basics	37
No JOB without Steps	37
Statement Name - EXEC	38
EXEC Operation	38
Programs	39
JOBLIB and STEPLIB Statements	39
Program Referback	40
Procedures	40
Calling a Procedure	41
Locating a Procedure	41
EXEC Statement Parameters	42
REGION Parameter	42
COND Parameter	43

PARM Parameter	44
Syntax Rules:	44
PARMDD Parameter	45
Defining Symbol Values	46
TIME Parameter	46
DD Statements	47
DD Statement Basics	47
Using DD Statements	47
DD Statement Name:	47
Referencing the DD Statement	48
DD Statement Type	48
Input Data Type	48
DSN Parameter	48
Data Name	49
Data - Partitioned Data Sets	50
Data - z/OS UNIX Flles	50
DISP Parameter	50
DISP Sub Parameters	51
Forgetting to use DISP	51
PATHOPTS Parameter	52
Referencing Existing Data	52

Introduction to Batch Processing

Enterprise Data Processing

Mainframe Data Processing

Data on the mainframe does not come in one shape. For example, every record within a data set containing daily transactions will need to be processed, while other data sets provide the ability to update individual records only.

Data Types:

- Partitioned Data Set
 - Contains individual members.
 - An example of this is individual compiled programs residing in a production partitioned data set.
- Sequential Data Set
 - o Contains data that is stored sequentially, one record following the next.
 - An example of this would be performance data that will later be printed or a list of transactions that will be applied to a master file.
- VSAM Data Set
 - There are several types of VSAM data set that can be created in a z/OS environment.
 - These are more complex than other types of data sets as they can consist of indexes or keys, to access and retrieve data records.
 - An example of data that would be stored in a VSAM structure would be system catalogs or customer data containing fields such as name, or ID that need to be referenced using that information as a key.

• z/OS UNIX File

- JCL can be used to run shell scripts or z/OS UNIX application programs against z/OS UNIX data.
- o A wide range of data can be stored in several types of z/OS UNIX files.


Database File

- They provide many features and capabilities that can be applied to data stored within them.
- They are generally used where there is a large amount of data and specific information needs to be accessed quickly.
- An example of data that would be stored in a database table would be results of research experiments or records of organizational purchases.

Online and Batch Processing

Due to the mainframe containing several types of data with numerous people needing access to it the z/OS needs a way to manage this.

There are two methods for how this can be achieved - online and batch



With online processing you simply enter a request from a screen and press Enter, the relevant data is accessed, and a response is returned to your screen. Online processing is usually reserved for simple, quick tasks.

Batch processing is often used when large amounts of data need to be accessed and worked on, usually at a predetermined time, unlike online processing which is immediate. Batch processing uses JCL to identify the programs to be run, what is to be used as input data, and what needs to be produced as a result.

Benefits of Batch Processing

If online processing can perform tasks instantly, why is there a need for batch processing? This is due to how the cost to make resources available to that extent is not yet economically viable. Hence, batch processing is the perfect solution for situations where there is repetitious, high volume work.

- Updates to data can be performed at a time that is suitable to the organisation.
- It is suitable for large amounts of repeated work i.e. master file updates.
- Dollar costs per workload are significantly less because of the characteristics above.
- Less user interaction is required to schedule and run batch jobs.

Working with Batch Processing

Depending on one's role, our relationship to batch processing is likely to differ. However, regardless of its application if the JCL is not coded correctly, it can have some drastic consequences.


Examples:

- An incorrect version of a master file is being used as input, resulting in overpayment notices being sent to some customers.
- Some parameters that you passed to a sort program have accidentally deleted data that is normally used as input to a later program you have to run.
- The management report that is supposed to be created from your batch job is not being produced.

Running a Batch Job

Understanding how the process works allows one to better diagnose JCL error messages at a later stage.

- Submit the Job
 - JES interprets JCL and places it on an input queue, making it available to a z/OS initiator.
- z/OS manages each step of execution
 - Required resources are allocated programs, memory, files
 - Resources are freed when the program is finished
- Output time
 - JES collects the output and information about the job
 - JES prints output
- User views and interprets output



Other terminology:

- ISPF to access the JCL code that is used for a batch job
- JES you will need some background on how JES, JES2, or JES3 is going to handle your submitted batch job
- SDSF or similar output viewing software to display the results following the completion of your batch job

Batch Job Automation


Many larger organizations have implemented automated batch scheduling software that is capable of handling complex batch job scheduling requirements. For example, batch processing may need to run at a specific time, once other data has become available, when a resource becomes free, or simply triggered once another batch job has completed.

Some examples of scheduling products used:

- BMC Control-M Product
- IBM Workload Scheduler
- CA Workload Automation CA 7 Edition


Batch Job Scheduling

Since z/OS 2.2, we can create simple scheduling for batch jobs within the batch job itself. The JCL code is referenced by JES which can run jobs at specific times or after other jobs have completed.



Batch Processing Prerequisites

The data set used for storing batch jobs is the partitioned data set (PDS) This is because it contains individual members, thus, making it an ideal location to store all batch jobs belonging to you or your group.



JCL z/OS 2.4 Update

There are only minor changes made to JCL with the introduction of z/OS 2.4, with one being included here.

A new NULLOVRD parameter can be used when performing overrides of DD * or DD DATA statements.

Coding Requirements

JCL Coding Rules

Planning Processing Requirements

Before writing any JCL, one must first plan out the batch processing that is to be performed.

- Take a backup of a data set before you work on it
- Run a COBOL program you have been working on, against the data set you copied
- Create a report that identifies discrepancies between the result of your program, and another set of data

Reality of JCL Coding

It's extremely unlikely that one will ever write out JCL for a job from scratch as it is much easier to copy it from a similar job and modify it.

How to copy JCL:

- Create an empty PDS member
- Type Copy [Other file's name] into the command line
- Place an A in the empty PDS member's line right at the top then hit enter
- Make your changes then submit it once you're ready

Identifying JCL code

JCL statements begin with a double slash within columns 1 and 2. This is how the system is able to interpret the data that is submitted to the system as JCL. Do note that there are, however, some exceptions to this double slash rule.

```
<u>F</u>ile
        Edit Edit_Settings Menu Utilities
                                                 Compilers
                                                            Test
                                                                   Help
EDIT
           IBMUSER.JCL(COPYSMF) - Ø1.Ø5
                                                               Columns ØØØØ1 ØØØ72
Command ===> SUBMIT
                                                                  Scroll ===>
                                                    --+---5---+---6--
=COLS> ----+---1----+---2----+----3----+-
                                      Top of Data ****
ØØØ1ØØ COPYSMF JOB MSGCLASS=C, MSGLEVEL=(1,1), NOTIFY=IBMUSER
000200
         STEP1
                   EXEC PGM=ICEGENER
øøø3øø
3ØØ4ØØ
         SYSPRINT
                  DD SYSOUT=
                   DD DSN=MVS1.SMF.RECORDS(Ø),DISP=SHR
øøø5øø
                  DD DSN=IBMUSER.TEST.MVS.DATA,DISP=(,CATLG),
SPACE=(TRK,(10,10),RLSE)
øøø6øø
øøø61ø
         SYSIN
øøø7øø
                        ************ Bottom of Data ******
IKJ567ØØA ENTER JOBNAME CHARACTER(S) -
```

In the example above, the system cannot determine the name of the job because it does not recognise the first line due to the lack of double slash (//) at the beginning of the line.

```
IKJ567ØØA ENTER JOBNAME CHARACTER(S) -
COPYSMF
IKJ56254I JOBNAME TRUNCATED+
IKJ5625ØI JOB IBMUSERC(JOBØ9296) SUBMITTED
***
```

What the initial prompt did not not mention was that it will use one's user ID (IBMUSER) as part of the job name and that one needs to add characters to append to it. Since the name of the job can only be eight characters, it has truncated the response using the C only.

The empty // curse

A common mistake for new JCL users is to submit a job that contains a line where the only data is //. This type of statement is called a null statement and indicates that this is the end of your JCL.

In the example here, the user wanted to remove the content from a JCL statement, but left // by itself on line 000500. Even though JCL statements appear after this line, the system will not recognize them.

```
000400 //
000400 // SET MEM=COMPUTE2
000500 //
000600 //COMP1 EXEC PGM=IGYCRCTL,REGION=0M,
000700 // PARM='LIST,XREF'
000800 //* SCHEDULE STARTBY='+00:05'
```

Uppercase Characters

JCL is coded in uppercase characters and you can use the PROF command in the CLI to check whether you have caps set to on or off.

 This can be fixed by using CAPS ON in the command line to automatically have your input converted to uppercase whenever you hit enter.

```
Edit Edit_Settings Menu Utilities
                                                     Help
         IBMUSER.JCL(CSFSMFJ) - Ø1.ØØ
EDIT
                                                 Columns ØØØØ1 ØØØ72
Command ===> PROF
                                                    Scroll ===> CSR
            øøøøø1
øøøøø2
øøøøø3
ØØØØØ4
          UNLOAD SMF RECORDS TO PRINT
000005
øøøøø6
       SMFDMP
               EXEC PGM=IFASMFDP
               DD DISP=SHR,DSN=SYS1.SØW1.MAN1.DATA
000007
       /DUMPIN
     //DUMPOUT
øøøøø8
               DD SYSOUT=*
              DD SYSOUT=*
øøøøø9
       SYSPRINT
000010 //
               DD
         INDD(DUMPIN,OPTIONS(DUMP))
ØØØØ11
         OUTDD(DUMPOUT, TYPE(82))
ØØØØ12
                              Bottom of Data *********
```

However, not everything has to be in uppercase; there are a few exceptions where you'll need to use lowercase characters enclosed within single quotes. The example shown below showcases this concept through a z/OS UNIX file being referenced.

```
Edit Edit_Settings Menu Utilities
                                                         Compilers
                                                                              Help
             IBMUSER.JCL(A#UXØ1) - Ø1.Ø1
EDIT
                                                                          Columns ØØØØ1 ØØØ72
         Command =
                      JOB MSGCLASS=C,MSGLEVEL=(1,1),NOTIFY=IBMUSER,REGION=ØM

EXEC PGM=IEFBR14

DD PATH='<mark>/u/ibmuser/account2</mark>',

FILEDATA=BINARY,
øøøøø2
000003 //DD1
000004 /
                        FILEDATA=BINARY,
PATHMODE=(SIRUSR,SIWUSR,SIRGRP,SIROTH),
PATHDISP=(KEEP,DELETE),
PATHOPTS=(OCREAT,ORDWR)
øøøøø5 /
аааааа6
ดดดดด7
```


Record Length

Within the PDS member that stores one's JCL code, it has a record length of 80 - based on punch cards from the early days of computing. Columns 73 - 80 are ignored when a job is submitted as they were traditionally used for sequence numbers. Thus, avoid code that overruns into these columns to prevent errors popping up when the job is submitted.

Continuing a statement

Since you cannot extend your JCL statement past column 72, how do you handle a JCL statement that contains lots of information? To continue a statement, you code a comma at the end of the parameter being specified on that line, and on the following line the double slash (//) characters must be in columns 1 and 2, and your continued information can appear anywhere between columns 4 and 16 (inclusive).

Often you will see for readability purposes that continued line data is aligned with previous lines.




Additionally, one should avoid putting any code in column 72 itself as traditionally this column was used to indicate a continuation but today is generally no longer used for this purpose and needs to be blank.

Statement Breakdown

Statement Names

When creating JCL, you will need to tell the system the type of statement you are providing, and in most cases, provide a name for that statement. The name you provide for each statement is one to eight characters and appears immediately after the double slash (//) characters. This name must start with an alpha or national character (\$, #, @), while the remaining characters can also contain numbers.



Statement Types

Associated with the name is the statement type. Common statements used include JOB, EXEC, and DD (as seen in the image below). At least one space must be coded following the name before this statement type is entered.

If you are working on an existing JCL you will often see several spaces between the name and the statement type. This is for readability purposes as it aligns important information.

```
<u>F</u>ile
       Edit Edit_Settings
                            Menu Utilities
                                              Compilers
                                                         Test
                                                               Help
          IBMUSER.JCL(FAMXTGH) - Ø1.ØØ
                                                           Columns ØØØØ1 ØØØ72
                                                              Scroll ===> <u>CSR</u>
       JOB MSGCLASS=C, MSGLEVEL=(1,1), NOTIFY=IBMUSER
                      PGM=ICEGENER
                    SYSOUT=
                    DSN=GHMAST.FAMAPS.D256,DISP=OLD
DSN=GHMAST.FAMAPS.D256.BACKUP,
         SYSUT1
øøø5øø
øøø6øø
         SYSUT2
                 DISP=(,CATLG)
øøø7øø
                  DD DUMMY
øøø8øø
        /SYSIN
                   **************** Bottom of Data ******
```

Parameters

Every statement will have some parameters that describe requirements, or attributes, to be associated with that statement. There may be many associated with that statement, though in reality you are only likely to use a subset of them regularly. If parameters are specified, at least one space must follow the statement type - JOB, EXEC, or DD - before they are entered.

```
Edit_Settings
                              Menu
                                    Utilities
                                                Compilers
                                                           Test
                                                                  Help
           IBMUSER.JCL(FAMXTGH) - Ø1.Ø2
EDIT
                                                              Columns ØØØØ1 ØØØ72
                                                                Scroll ===> <u>CSR</u>
Command ===>
                                      Top of Data *********
       ******
                  JOB MSGCLASS=C, MSGLEVEL=(1,1), NOTIFY=IBMUSER
øøø1øø
        /FAMXTGH
øøø2øø
                        PGM=ICEGENER
         STEP1
øøø3øø
000400
         SYSPRINT
                  DD SYSOU
                                       S.D256,DISP=OL
S.D256.BACKUP,
                  DD DSN=G
                            MAST.FAMAF
ØØØ5ØØ
         SYSUT1
                            MAST.FAMAF
                      DSN=G
                   DISP=(,C
                            (TLG
øø8øø
       //SYSIN
                     DUMMY
                                     Bottom of Data
```

Where there are multiple parameters for a statement, they must be separated by commas, and if the parameter itself contains a space, it needs to be enclosed in single quotes.

Positional Parameters

The parameters for each statement are separated into positional and keyword. If used, a positional parameter must appear in a specific area of the code, and if it is not required, a comma is often used to indicate it being bypassed, although this is not always the case.

```
Edit Edit_Settings Menu Utilities Compilers
 File
                                                             Help
                                                       Test
          IBMUSER.JCL(FAMXTGH) - Ø1.Ø3
                                                         Columns ØØØØ1 ØØØ72
Command ==
                                                            Scroll ===> CSR
                 000100
                 CLASS=K A
MSGCLASS=X
øøø2øø
øøø3øø
                 NOTIFY=IBMUSER
000400
øøø5øø
        STEP1
                      PGM=ICEGENER
øøø6øø
øøø7øø
        SYSPRINT
                 DD SYSOU
         SYSUT1
                 DD DSN=GHMAST.FAMAPS.D256,DISP=OLD
øøø8øø
                          MAST.FAMAPS.D256.BACKUP,
øøø9øø
         SYSUT2
                    DSN=G
001000
                 DISP=(,CATLG)
        SYSIN
                   DUM
                          ****** Bottom of Data ******
```

Example:

- Left arrow: If this accounting information was not required but the programmer's name was, then a comma would need to be coded to signify that the accounting information was being bypassed.
- Right arrow: Even though this is a positional parameter, if it is not required and the
 accounting information is, then you do not need to code a comma to indicate its
 absence. Note that in this example, because the value contains a space, it needs to
 be encased in single quotes.

Keyword Parameters

Keyword parameters are more common and can appear in any order within the statement, following the statement type. Their name is followed by an equals (=) sign and then the value assigned to that keyword parameter.

```
File Edit Edit_Settings Menu Utilities Compilers Test Help
            IBMUSER.JCL(FAMXTGH) - 01.04
EDIT
                                                                    Columns 00001 00072
                                                                        Scroll ===> <u>CSR</u>
        JOB 'GREG HAMLYN',
CLASS=K,
MSGCLASS=X,
000200
000300
                    NOTIFY=IBMUSER
000500 //*
       //STEP1 EX
//SYSPRINT DD
//SYSUT1 DD
                    EXEC PGM=ICEGENER
000600
000700
                       SYSOUT=*
DISP=OLD,DSN=GHMAST.FAMAPS.D256
DSN=GHMAST.FAMAPS.D256.BACKUP,DISP=(,CATLG)
                         SN==0107837777
UMMY
**************** Bottom of Data ***************
```

Example:

Line 000800 shows a DISP parameter first, and then a DSN parameter. On the line
after this, these two parameters appear in the opposite order. As DISP and DSN are
keyword parameters this coding is acceptable.

Comments

There are two ways of coding comments in JCL. The more common method is to code a //* statement such as on lines 000500 to 000800. Any text that then appears after this is considered a comment. Another method is to leave at least one space at the end of a line and type your comment, such as on the end of line 001100.

```
File Edit Edit_Settings Menu Utilities Compilers
                                                                       Test Help
             IBMUSER.JCL(FAMXTGH) - 01.04
                                                                          Columns 00001 00072
                                                                             Scroll ===
        ******
                                              Top of Data **********
       //FAMXTGH JOB 'GREG HAMLYN',
// CLASS=K,
// MSGCLASS=X,
// NOTIFY=IBMUSER
000100
000200 /
000400
000500
000300 //*
000600 //*
000700 //*
000800 //*
              THE FIRST STEP IS USED FOR RECOVERY PURPOSES CHANGE THE SYSUT1 AND SYSUT2 DATA SETS AS REQUIRED
                      EXEC PGM=ICEGENER
DD SYSOUT=*
DD DISP=OLD,DSN=GHMAST.FAMAPS.D256 * INPUT DATA SET *
DD DSN=GHMAST.FAMAPS.D256.BACKUP,DISP=(,CATLG)
001000
001100
        //SYSUT1
001200
```

JOB Statement Basics

Statement Requirements

JOB Statement Importance

The JOB statement is typically the first statement encountered in your job, it is used to specify attributes to be associated with your job when it is submitted to the system. The JOB statement is important and if not coded correctly, can have major ramifications on the success of your job.

```
<u>F</u>ile
          Edit Edit_Settings Menu Utilities
                                                             Compilers .
                                                                                   <u>H</u>elp
EDIT
              IBMUSER.JCL(IBMJOB) - Ø1.Ø6
                                                                               Columns ØØØØ1 ØØØ72
                                                                                  Scroll ===> <u>CSR</u>
                                  ******** Top of Data
                                                                *******
                              (), 'GMH', CLASS=A, MSGCLASS=X, NOTIFY=IBMUSER
øøø1øø
         //GMHUNØ1
                       EXEC PGM=BPXBATCH,TIME=NOLIMIT,REGION=ØM
DD PATH='/u/ibmuser/gethob',
PATHOPTS=(ORDONLY)
øøø2øø
000300
000400
            STER1
                           THOPTS=(ORDONLY)
SYSOUT=*
øøø5øø
øøø6øø
                            SYSOL
øøø7øø
           /STDERR
                 RINT DD
øøø8øø
           /SYSF
                           SYSOL
øøø9øø
                 DUMP
                            SYSOL
ØØ11ØØ
                           (STEF1.RC = \emptyset) THEN
øø12øø
                        SET PARMPEN=DAILY
                              PGM
                                   =IEBGENER
øø14øø
                       DD DSN=IBMUSER.SALESIN,DISP=OLD
DD DSN=IBMUSER.PEN.TRANS.&PARMPEN,
DCB=(RECFM=FB,LRECL=80,BLKSIZE=32720),
øø15øø
            SYSUT2
øø16øø
øø17øø
                        SPACE=(QL, (1,1), RLSE), UNIT=SYSDA, DISP=(, CATLG)
001800
```

The name you specify on this statement is the one that the system uses to reference your job when it is submitted. The PDS member name you are using to store your JCL can be the same or different to the job name and has no relationship with it.

JOB Name Standards

Mentioned previously in a section above, a statement name needs to meet specific rules - it should be between one and eight characters in length and begin with an alpha or national character. It can contain a number as long as it is not the first character.

Each organization will probably have its own standards regarding job names. This allows the organization to more clearly identify to whoever is looking at the job, what group, or individual it belongs to.

Running a JOB Multiple Times

To submit a job several times, for testing purposes for example, you can code your user ID as the job's name. When you submit your job, it will prompt you for a character to be added to the end of this name before it is submitted.

The A character has been appended to IBMUSER, which was specified in the JOB statement, to create the job name that the system will use. You can now use the same job, changing the name of the generation data set to S0B1, and when you submit the job you can use B for the appended job name character. When you check the output from these jobs, it is easy to determine which output belongs to which job.

Note that to use this option, one's user ID needs to be a maximum of seven characters, because a maximum of eight characters are allowed for a job name.

Multiple JOB Statements

Normally, there is just a single JOB statement followed by one or more steps used to execute programs. However, in some situations there might be several JOB statements coded within a PDS member. When submitted to the system, it will detect the JOB statement and submit the statements following it as a separate job.

```
File Edit Edit_Settings Menu Utilities Compilers
                                                                      Test
                                                                              He1p
             IBMUSER.JCL(SUPJOBS) - 01.01
EDIT
                                                                         Columns 00001 00072
                       Scroll ===>
        ===> SUBMIT
                      JOB MSGCLASS=X,CLASS=C
000100
                      DD DSN=PROD.D112Y17.PENTRANS,DISP=OLD
DD DSN=IBMUSER.TOTAL.PENTRANS,DISP=(,CATLG),
UNIT=SYSDA,SPACE=(CYL,(10,10,RLSE))
000400
000500
000600
000700
          SYSPRINT
                         SYSOUT=*
SYSOUT=*
           SY50UT
                      DO SYSOUT=*
DD SYSOUT=*
DD DSN=IBMUSER.TOTAL.PENTRANS,DISP=SHR
000800
000900
001000
001100
          /INDD1
         RECORDS=10000
                         ************** Bottom of Data **********
           JOB SUPAPDO5(JOBO9358) SUBMITTED JOB SUPXTD10(JOBO9359) SUBMITTED
```

Incorrect JOB Name

Depending on the problem, the system may prompt you for some input that it will use with system defaults, to build a JOB statement for you, or it may fail indicating that it has an invalid name. In this example it failed because the job name did not start with an alpha or national character.

```
File Edit Edit_Settings Menu Utilities Compilers Test Help

EDIT IBMUSER.JCL(IBMJOB3) - 01.05 Columns 00001 00072
Command ===> Scroll ===> CSR

000100 //IDAYMOD JOB ,'GMH',CLASS=C,MSGCLASS=X,NOTIFY=IBMUSER
000200 //*
000300 // SET WDAY=THURS
000400 //STEP1 EXEC PGM=IEBGENER
000500 //SYSUT1 DD DSN=IBMUSER.JSONDATA,DISP=SHR
```

Statement Positional Parameters

With a correct job name and type of statement defined, you now need to look at the types of parameters that can be coded on a JOB statement.

There are two positional parameters that can be specified on a JOB statement - **accounting information**, and the **programmer's name**. As discussed previously, positional parameters, if used, need to appear in a specific order.

The value for these two parameters may be enforced through organizational standards, therefore supplying them in the JOB statement could be optional or mandatory.

```
File Edit Edit_Settings Menu Utilities Compilers
                                                                Test Help
        000100 //FAMXTP15 JOB (170A80), 'GINA HARR
000200 // CLASS=K,
000300 // MSGCLASS=X,
000400
                    NOTIFY=IBMUSER
000500
             THE FIRST STEP IS USED FOR RECOVERY PURPOSES CHANGE THE SYSUT1 AND SYSUT2 DATA SETS AS REQUIRED
øøø6øø
000700
000800
øøø9øø
                         PGM=ICEGENER
                    DD SYSOUT=*
DD DSN=GHMAST.FAMAPS.D256,DISP=OLD
DD DSN=GHMAST.FAMAPS.D256.BACKUP,DISP=(,CATLG)
         /SYSPRINT
/SYSUT1
øø1øøø
øø11øø
øø12øø
         SYSUT2
                        ************* Bottom of Data *******************
```

Accounting Information:

The accounting information parameter is used generally for billing, statistical, or performance-related purposes. The use of this parameter is likely to be dictated by an organization's standards. If used, this parameter must appear before any other JOB statement parameters.

The following are some rules when coding this parameter:

- If more than one subparameter is required, you must code the sub parameters within parentheses. You may also see a single parameter here enclosed in parentheses which is also acceptable.
- If sub parameters contain special characters, with the exception of hyphens, they must appear within apostrophes.
- It cannot exceed 143 characters in length.

The accounting information parameter can consist of two sub parameters - the account number, and more granular details associated with the account. You may also see JES2 accounting information supplied here, although this is not commonly used by organizations.

Examples:

- Image 1 This is an example of an accounting code defined by the organisation.
 Even though it contains a hyphen, it does not need to be enclosed in parentheses or apostrophes, although syntactically this is allowed.
- Image 2 This is an example wherein the organization has defined their accounting information for a job must contain a code, department number, and section name. As the department number contains a slash (/), it needs to be enclosed in apostrophes. As there are three sub parameters altogether, they are enclosed in parentheses.
- Image 3 When using this parameter to supply JES2 accounting information, a range
 of sub parameters can be specified. These are positional sub parameters, in this
 example there are several commas entered to indicate values being bypassed.

Programmer's Name:

The programmer's name is another optional parameter that may be required by your organization. This field helps to provide identification about the owner of the job. This is often the name of an individual but could also be the name of your group. You can see here that the job's log at the bottom displays this information.

When coding the programmer's name parameter a maximum of 20 characters can be coded and single quotes are required if the name contains any special characters, other than hyphens (-) or periods (.).

Some or No Positional Parameters

If a positional parameter is not required, a comma is coded to signify its absence. This is required when another positional parameter immediately follows it. If no positional parameters are required at all for the statement, they can be omitted without any commas.

The example below is for when you omit the accounting information.

```
Edit Edit_Settings Menu Utilities Compilers Test
  <u>F</u>ile
                                                                                 <u>H</u>elp
             IBMUSER.JCL(FAMXTP15) - Ø1.11
EDIT
                                                                            Columns ØØØØ1 ØØØ72
         ---> Scroll ===> <u>CSR</u>
000100 //FAMXTP15 JOB ,'GINA HARRIS',
000200 // CLASS=K,
000300 // MSGCLASS=X,
000200 //
000300 //
000400 //
000500 //*
                      NOTIFY=IBMUSER
000600 //*
000700 //*
               THE FIRST STEP IS USED FOR RECOVERY PURPOSES CHANGE THE SYSUT1 AND SYSUT2 DATA SETS AS REQUIRED
ØØØ8ØØ //*
øøø9øø
                       EXEC PGM=ICEGENER
          /SYSPRINT DD SYSOUT=*
/SYSUT1 DD DSN=GHMAST.FAMAPS.D256,DISP=OLD
/SYSUT2 DD DSN=GHMAST.FAMAPS.D256.BACKUP,DISP=(,CATLG),
001000 /
001100
øø12øø
                       UNIT=SYSDA, SPACE=(CYL, (10, 10), RLSE)
ØØ121Ø
         //SYSIN
                       DD DUMMY
                             ********** Bottom of Data ************
```

Statement Keyword Parameters

CLASS Parameter

During JES initialization, organizational job classes are defined with each containing their own characteristics. These classes can be a single number (0-9), letter (A-Z), or even a one to eight-character name. The example at the bottom of this page shows attributes assigned to K class jobs during JES initialization.

```
<u>F</u>ile
        Edit
               Edit_Settings Menu Utilities
                                                   Compilers
                                                               Test
                                                                      <u>H</u>elp
            IBMUSER.JCL(FAMXTP15) - Ø1.12
EDIT
                                                                  Columns ØØØØ1 ØØØ72
       ===> <u>SUBMIT</u>
******** Top of Data
                                                      Scroll ===> <u>CSR</u>
                   JOB 6910-D112, GINA HARRIS
øøø1øø
        //FAMXTP15
ØØØ2ØØ /
                    CLASS=K
øøø3øø
000400 //*
000500 //*
000600 //*
             THE FIRST STEP IS USED FOR RECOVERY PURPOSES
             CHANGE THE SYSUT1 AND SYSUT2 DATA SETS AS REQUIRED
øøø6øø
000700 //STEP1
                    EXEC PGM=ICEGENER
  Display
            <u>F</u>ilter
                    ⊻iew
                           Print
                                   Options
                                             Search
                                                      Help
SDSF INPUT QUEUE DISPLAY ALL CLASSES
                                                             LINE 1-1 (1)
                                                                     SCROLL ===>
COMMAND INPUT ===
PREFIX=*
          DEST=(ALL)
                        OWNER=*
                                  SYSNAME=
     JOBNAME JobID
FAMXTP15 JOBØ9417
                                                  PhaseName
                                                                         Status
                         Owner
                                   JΡ
                                             Pos
                                       7 K
                         IBMUSER
                                                  AWAIT MAIN SELECT
```

One of the items you would normally code on a JOB statement is a CLASS parameter and you can see in the screen at the top that the syntax is straightforward.

 If an invalid class is specified in the JOB statement the job will be flushed or cancelled and an error message will be displayed.

MSGCLASS Parameter

The MSGCLASS parameter is used to assign the job's log to an output class. This is what you look at in SDSF to determine whether your job ran successfully. Like the CLASS parameter, the attributes associated with output classes are defined during JES initialization.

```
<u>F</u>ile
                                        Edit Edit_Settings
                                                                                                                                                  <u>M</u>enu
                                                                                                                                                                               <u>U</u>tilities
                                                                                                                                                                                                                                          Compilers
                                                                                                                                                                                                                                                                                                  Test
                                                                                                                                                                                                                                                                                                                                <u>H</u>elp
                                                        IBMUSER.JCL(FAMXTP15) - 01.12
 EDIT
                                                                                                                                                                                                                                                                                                            Columns 00001 00072
  Command
                                                                                                                                                                                                                                                                                                                           Scroll =
                                                                                                                                                                                                                                                                                                                                                                          ⇒ <u>CSR</u>
                                    ****** Top of Data
//FAMXTP15 JOB 6910-D112, 'GINA HARRIS',
// CLASS=K,
 000100
 000200
 000300
                                                                                             MSGCLA9
  000400
  000500
                                                              THE FIRST STEP IS USED FOR RECOVERY PURPOSES
                                                             CHANGE THE SYSUT1 AND SYSUT2 DATA SETS AS REQUIRED
           Display
                                                        <u>Filter</u>
                                                                                                View
                                                                                                                               Print
                                                                                                                                                                   Options 0 0 1 1 1 1 1
                                                                                                                                                                                                                Search
                                                                                                                                                                                                                                                         Help
                                                                                                                                                                                                                                                                                       LINE 1-1 (1)
SCROLL ===> CSR
 SDSF OUTPUT ALL CLASSES ALL FORMS
                                                                                                                                                                                            LINES 79
COMMAND INPUT ===>
PREFIX=FAM* DEST=(ALL)
NP JOBNAME JobID

THE TOTAL CONTROL OF THE TOTAL CO
                                                                                                                               OWNER=*
                                                                                                                                                                             SORT=CrDate/D
                                                                                                                                                                                                                                                         SYSNAME=
                                                                                                                     Owner
                                                                                                                                                                                                     Forms
                                                                                                                                                                                                                                                    Dest
                                                                                                                                                                                                                                                                                                                                                               Rec-Cnt
                                                                                                                                                                   Prty
                          FAMXTP15 JOB09420 IBMUSER
```

Note that you will again be likely to have organizational standards that specify the output class you should use.

 MSGCLASS=Z is often configured to automatically purge job log output on completion of the job.

If you do not code a MSGCLASS parameter then installation defaults will be used, so it is usually good practice to code this parameter so that you can find your output easily.

In the example from the previous page, JES initialization statements defined that X class output is not held, and this is why you found it on the SDSF output screen rather than the held output screen. This is not always going to be the case.

```
<u>E</u>dit <u>Edit_Settings Menu <u>U</u>tilities <u>C</u>ompilers</u>
                                                                                   Columns 00001 00072
Scroll ===> CSR
                   IBMUSER.JCL(FAMXTP15) - Ø1.12
                    THE FIRST STEP IS USED FOR RECOVERY PURPOSES CHANGE THE SYSUT1 AND SYSUT2 DATA SETS AS REQUIRED
                      Edit_Settings Menu Utilities
                   VENDOR.PARMLIB(JES242ØA) - Ø1.Ø1
                                                                                   Columns ØØØØ1 ØØØ72
In this example, a MSGCLASS of Z is specified in the JCL. In the JES initialization parameters, notice that for
this class it displays OUTPUT=DUMMY, which means that the output will not be available for viewing. You might
want to use this class for your job if you are running it many times and do not need to ever view its job log.

■ Previous

                                                                                                              Next ▶
                   E<u>d</u>it_Settings <u>M</u>enu <u>U</u>tilities
                                                                                    Columns ØØØØ1 ØØØ72
Scroll ===> CSR
                VENDOR.PARMLIB(JES242ØA) - Ø1.Ø1
          OUTCLASS(R) OUTDISP=(HOLD, HOLD), OUTPUT=PUNCH
           OUTCLASS(R) OUTDISP=
OUTCLASS(Z) OUTDISP=
OUTDEF COPIES=100,
   Display Filter View Print Options Search
                  TPUT DISPLAY ALL CLASSES LINES 49
 SDSF <mark>HELD OUTPUT</mark>
COMMAND INPUT ==
                                                                                         SCROLL ===> CSR
    MMMAND INPUT ===>
EFIX=FAM* DEST=(ALL) OWNER=*
' JOBNAME JOBID OWNER'
FAMXTP15 JOBØ9423 IBMUSER
                                                 SORT=CrDate/D
                                                                                              REC-Cnt
49
                                                                                                           PAGE
   You can see in the JES initialization parameters at the top that R class output is assigned a HOLD
   status. If the job had a MSGCLASS of R you would have to search the SDSF held output screen to
   find it, not the normal output screens previously used.

■ Previous
```

MSGLEVEL Parameter

A job's log output, which was discussed on the previous page, consists of a number of separate output components including the following:

- JES job log
- JCL statements
- Job-related JES and operator messages system messages

There may be times when you do not need all of this information to be made available because it can clutter the screen making it difficult for you to find what really matters to you.

```
Edit
              Edit_Settings
                             Menu Utilities
                                               Compilers
  File
                                                          Test
                                                                Help
                                                            Columns 00001 00072
Scroll ===> CSR
EDIT
           IBMUSER.JCL(FAMXTP15) - Ø1.14
Command
                                                                           CSR
       Data
ØØØ1ØØ //FAMXTP15 JOB 691Ø-D112, 'GINA HARRIS'
000200 //
000300 //
                  CLASS=K,
MSGCLASS=X,
ØØØ4ØØ /
```

```
Display
            <u>F</u>ilter
                     ⊻iew
                            Print
                                    Options [ ]
                                              <u>S</u>earch
                                                       <u>H</u>elp
SDSF JOB DATA SET DISPLAY - JOB FAMXTP15 (JOBØ9428)
                                                              LINE 1-4 (4)
COMMAND INPUT
                                                                      SCROLL
PREFIX=FAM*
              DEST=(ALL) OWNER=*
                                      SYSNAME=
     DDNAME
               StepName ProcStep DsID Owner
                                                    C Dest
                                                                            Rec-Cnt Page
     JESMSGLG JES2
                                       2 IBMUSER
                                                      LOCAL
                                                                                 18
     JESYSMSG JES2
                                       4 IBMUSER
                                                   X LOCAL
```

The MSGLEVEL parameter consists of two sub parameters. The first indicates which statement images to produce. The second sub parameter indicates which system messages to produce. The default is usually MSGLEVEL=(1,1), which will show all JCL statements and messages. A MSGLEVEL default may also be defined for each JES JOBCLASS definition.

In this example, specifying 0 for the first sub parameter will only produce the JOB statement and any comments that appear before the first step. You can see in the output produced that the number of records for the KCL messages have been reduced as a result of this.

```
Display
             <u>F</u>ilter
                       ⊻iew
                               <u>P</u>rint
                                        Options
                                                   <u>S</u>earch
                                                             <u>H</u>elp
                                                                     LINE 1-7 (7)
SCROLL ===> CSR
SDSF JOB DATA SET DISPLAY - JOB ARUNREP COMMAND INPUT ===>
                                                   (JOBØ9429)
PREFIX=ARUN*
                 DEST=(ALL)
                               OWNER=*
                                            SYSNAME=
                 StepName ProcStep DsID Owner
      DDNAME
                                                                                    Rec-Cnt
                                                                                              Page
                                                         C Dest
      JESMSGLG
                                              IBMUSER
                 1FS
                                                            LOCAL
      JESYSMSG JES2
                                                                                           67
                                            4 IBMUSER
                                                         C LOCAL
```

```
⊻iew
  Display
            <u>F</u>ilter
                            Print
                                     Options
                                               <u>S</u>earch
                                                        <u>H</u>elp
                                                               LINE 1-7 (7)
SCROLL
SDSF JOB DATA SET DISPLAY - JOB ARUNREP
                                               (JOBØ943Ø)
COMMAND INPUT
                                                                               ===> CSR
                DEST=(ALL) OWNER=*
                                        SYSNAME=
PREFIX=ARUN*
     DDNAME
                StepName ProcStep DsID Owner
                                                     C Dest
                                                                             Rec-Cnt
                                                                                      Page
      JESMSGLG
                JES
                                          IBMUSER
                                                       LOCAL
      JESYSMSG JES2
                                          IBMUSER
```

Coding 2 for the first sub parameter will produce JCL and JES statements but not procedure statements. The output at the top did not have any MSGLEVEL parameter and you can see that it produced 24 records for the JESJCL part of the output. The same job when submitted with MSGLEVEL=(2,1) produced the output at the bottom showing only 3 records being produced.

```
<u>D</u>isplay
             <u>F</u>ilter
                       ⊻iew
                               Print
                                        Options 0
                                                   <u>s</u>earch
                                                             <u>H</u>elp
                                                                     LINE 1-4 (4)
SCROLL ===> CSR
SDSF JOB DATA SET DISPLAY - JOB FAMXTP15 (JOBØ9425)
COMMAND INPUT
PREFIX=FAM* [
                DEST=(ALL) OWNER=*
                                          SYSNAME=
      DDNAME
                 StepName ProcStep DsID Owner
                                                          C Dest
                                                                                    Rec-Cnt Page
                 JES2
JES2
      JESMSGLG
                                              IBMUSER
                                                            LOCAL
                                                                                          18
      JESJCL
                                              IBMUSER
                                                            LOCAL
                                                                                          13
```

```
Options 5 4 1
                                                     <u>S</u>earch
  <u>D</u>isplay
              <u>F</u>ilter
                        <u>V</u>iew
                                Print
                                                                Help
SDSF JOB DATA SET DISPLAY - JOB FAMXTP15 (JOBØ9434)
                                                                       LINE 1-4 (4)
SCROLL
COMMAND INPUT
PREFIX=FAM* [
                DEST=(ALL)
                                OWNER=*
                                            SYSNAME=
      DDNAME
                  StepName ProcStep DsID Owner
                                                                                        Rec-Cnt Page
                                                              Dest
      JESMSGLG JES2
JESJCL JES2
                                                IBMUSER
                                                                                              18
                                                              LOCAL
                                                IBMUSER
                                                              LOCAL
                                                                                              13
                  TES
                                              4 IBMUSER
                                                            X LOCAL
                                                                                              11
```

Coding 0 for the second sub parameter will produce only JCL messages, unless the job fails, in which case JES and operator messages will also be produced. In this situation SMS messages will also be shown, if SMS has caused the job to fail. The example at the top is showing all job log output, while the one at the bottom is produced using MSGLEVEL=(1,0).

REGION Parameter

Every program you run is going to need a different amount of memory to run. Many organizations will use a REGION parameter to cap this requirement.

Coding REGION=0M or REGION=0K on the JOB statement provides every program specified in your job with as much virtual storage - memory - as it requires. Depending on your requirements, you can code a specific maximum amount of memory that can be used, in megabytes (M) or kilobytes (K). If REGION is not specified, then a JES initialization default will take effect.

NOTIFY Parameter

When you submit your job to the system, most people will want to be notified once the job has completed, so it can be checked. This task is achieved using the NOTIFY parameter.

The syntax of this command is relatively straightforward. The NOTIFY value is a TSO user ID, usually the person submitting the job.

Use &SYSUID - for anyone to use your JCL instead of specifying a specific TSO UserID.

```
<u>F</u>ile
       Edit Edit_Settings Menu Utilities Compilers Test Help
           IBMUSER.JCL(FAMXTP15) - Ø1.18
                                                            Columns 00001 00072
EDIT
000400
                  REGION=ØM.
000500
000600
                  NOTIFY=&S
            THE FIRST STEP IS USED FOR RECOVERY PURPOSES CHANGE THE SYSUT1 AND SYSUT2 DATA SETS AS REQUIRED
ggg8gg
øøø9øø
       //STEP1 EXEC PGM=ICEGENER
//SYSPRINT DD SYSOUT=*
øø11øø
                  DD DSN=GHMAST.FAMAPS.D256,DISP=OLD
DD DSN=GHMAST.FAMAPS.D256.BACKUP,DISP=(,CATLG),
UNIT=SYSDA,SPACE=(CYL,(10,10),RLSE)
øø13øø
```

The NOTIFY parameter is quite simple but has a few drawbacks, including the following:

- If the user that the message is to be sent to is not logged on, they will not receive a job completion message until they next log on
- The NOTIFY parameter can only be used to send a message to a single user
- There is no default, so if you forget to code this parameter you will need to monitor the job using other methods, to determine if it has finished

With z/OS 2.3 a new NOTIFY statement provides more flexibility in when and how job completion messages are sent. When specified, it must be placed after the JOB statement and before the first EXEC statement.



This statement name follows the standard naming syntax for other statements, as discussed previously. This is followed by at least one blank and then the statement type: NOTIFY. All parameters used in this statement are keyword, so can be specified in any order. The EMAIL parameter is used to define the email address to whom job completion details will be sent. The TYPE parameter indicates that the message is to be sent as an email message and is the default when the EMAIL parameter is used.

```
000100 //FAMXTP15 JOB 4467-D032, 'LAYLA SHULZ',
000200 // CLASS=K,
000300 // MSGCLASS=X
000400 //*
000500 //NOT1 NOTIFY USER=IBMUSER, TYPE=MSG
000600 //NOT2 NOTIFY USER=GTEDSWOT, TYPE=MSG
000700 //NOT3 NOTIFY USER=DZTPRD01, TYPE=MSG
```

A maximum of eight NOTIFY statements can be specified. In this example the USER parameter is used to identify the TSO user to whom a job completion message will be sent. The TYPE parameter indicates that the notification should be sent by using a TSO message, and is the default when the USER parameter is specified.

The WHEN parameter can be used to define conditions under which notification will be performed. In the NOT1 statement, a confirmation email will be sent only if the job completes with a maximum condition code of 4 or 8. In the NOT2 statement, if an abend occurs then a message will be sent to TSO user LAYLA. The NOT3 statement is more specific as it indicates that either of the abend codes specified need to be produced before the message is sent. In the NOT4 statement if the job did not run - for example, it had a JCL syntax error - then a TSO message will be sent to TSO user IBMUSER. The exclamation mark (!) character indicates a not operation.

Additional JOB Statement Parameters

Popular Statement Parameters

TYPRUN Parameter

Normally when you submit a job, it will run immediately if the required resources are available. There may be situations though where you need the system to handle your job differently when it is submitted.

For example, the TYPRUN parameter can be used for the following purposes:

- Holding your job, pending a manual release, either by yourself or an operator.
- Scanning the syntax of your JCL. In this scenario, no actual job processing is performed.
- Sending a copy of your JCL directly to sysout, without performing any processing, in a JES2 environment only.

Scenario 1 - TYPRUN HOLD:

You are going to be detained all afternoon with meetings but need to submit a job that must be run when a file becomes available after 1:00pm. Rather than wait until you are back in the office later in the day to submit your job, you can submit it now and instruct an operator to release it.

The TYPRUN=HOLD parameter can be used for this purpose. You can see in the SDSF screen at the bottom of the page that the job has a HOLD status. Note that if your job contains syntax errors when it is submitted, it will fail immediately and not be held.

```
File Edit Edit_Settings
                              Menu
                                    Utilities
                                               Compilers Test
                                                                  Help
           IBMUSER.JCL(BLKJET01) - 01.01
EDIT
                                                             Columns 00001 00072
                                                                Scroll =
Command
                                                                            <u>CSR</u>
       ****** Top of Data
                  JOB 6910-D112, 'GINA HARRIS'
CLASS=C,
MSGCLASS=X,
000100
       //BLKJET01
000200
000300
                  NOTIFY=IBMUSER,
000400
000500
000600
```

```
<u>D</u>isplay <u>F</u>ilter <u>V</u>iew <u>P</u>rint
                                     Options
                                                <u>S</u>earch
                                                          <u>H</u>elp
SDSF INPUT QUEUE DISPLAY ALL CLASSES
                                                                 LINE 1-1 (1)
                                                                         SCROLL ===> CSR
COMMAND INPUT
PREFIX=BL*
             DEST=(ALL)
                           OWNER=*
                                       SYSNAME=
     JOBNAME
                          0wner
                                                Pos PhaseName
                JobID
                                                                              Status
     BLKJET01 JOB09564 IBMUSER
                                                     AWAIT MAIN SELECT
```

Scenario 2 - TYPRUN SCAN:

You have been copying components of JCL from other sources to build your JCL. You still need to work on the programs that will be invoked but want to check your JCL to see whether it is syntactically correct.

The TYPRUN=SCAN parameter can be used for this purpose. You can see in the SDSF screen at the bottom that if the syntax is acceptable, there are no error-related messages. Note though that the job is not run, it is only scanned for syntax issues. Although you cannot see it here, at the bottom of the SDSF output, a copy of the JCL is also produced.

```
Edit_Settings Menu Utilities Compilers
                                                                  Test
            IBMUSER.JCL(PENEDD12) - Ø1.Ø1
                                                                     Columns ØØØØ1 ØØØ72
                                                                         Scroll ===> CSR
        ****** Top of
//PENEDD12 JOB SPEN1763, 'E KARLSSON'
                                                   Data
øøø1øø
øøø11ø
ØØØ2ØØ
øøø3øø
              THIS STEP WILL CONVERT THE PARTITIONED VB DATASET
              INTO A SEQUENTIAL VBS DATASET TO BE READY FOR
ØØØ4ØØ
              IMPORT IN NEXT STEP.
ØØØ5ØØ
øøø6øø
        //STEPØ1 EXEC PGM=IEBGENER
//SYSPRINT DD SYSOUT=7
øøø7øø
øøø8øø
   Display Filter View Print Options Search
                                                         Help
                                                                           COLUMNS Ø2- 81
 SDSF OUTPUT DISPLAY PENEDD12 JOBØ9565 DSID
                                                          2 LINE Ø
 COMMAND INPUT ===>
                                                                          SCROLL ===>
                                        TOP OF DATA ***********
                      JES2 JOB LOG --
                                                     SYSTEM SØW1 -- NODE
18.39.19 JOBØ9565 ---- TUESDAY, Ø7 NOV 2017 ----
18.39.19 JOBØ9565 IRRØ1ØI USERID IBMUSER IS ASSIGNED TO THIS JOB.
----- JES2 JOB STATISTICS ------
34 CARDS READ
             35 SYSOUT PRINT RECORDS
Ø SYSOUT PUNCH RECORDS
              3 SYSOUT SPOOL KBYTES
```

Scenario 3 - TYPRUN COPY:

TYPRUN=COPY can be used if you just need to copy your JCL directly to sysout - output that can be displayed through SDSF. If there are any syntax errors, this option will not pick them up.

```
Filter View Print
                           Options
                                          не]р
SDSF OUTPUT DISPLAY PENEDD12 JOBØ957Ø DSID
                                          1 LINE Ø
                                                       COLUMNS Ø2- 81
COMMAND INPUT ===>
                                                      SCROLL ===>
      ****** TOP OF DATA *********
                                                       ***
PENEDD12 JOB SPEN1763, 'E KARLSSON
                                                              J0BØ957Ø
                                                              ØØØ11ØØ1
   ******
                   *********
                                                              00020000
   THIS STEP WILL CONVERT THE PARTITIONED VB DATASET
                                                              ggg3gggg
   INTO A SEQUENTIAL VBS DATASET TO BE READY FOR
                                                              øøø4øøøø
                                                              00050000
   IMPORT IN NEXT STEP.
                                                              00060000
                                                              00070000
/STEPØ1
        EXEC PGM=IEBGENER
```

Scenario 4 - TYPRUN JCLHOLD:

TYPRUN=JCLHOLD is similar to TYPRUN=HOLD except that the job is held prior to the JES2 conversion stage. You will see in a later course what happens during this stage and why this option may be useful. When the job is released by the operator, if there are any JCL syntax errors, similar output to that of the TYPRUN=SCAN will be produced, otherwise the job will begin executing if resources are available.

```
Display Filter View Print Options Search Help

SDSF INPUT QUEUE DISPLAY ALL CLASSES LINE 1-1 (1)
COMMAND INPUT ===> SCROLL ===> CSR
PREFIX=PEN* DEST=(ALL) OWNER=* SYSNAME=
NP JOBNAME JOBID Owner JP C Pos PhaseName Status
PENEDD12 JOBØ9574 IBMUSER 7 * AWAIT CONV HOLD
```

If no TYPRUN parameter is specified, then the job is submitted and will run immediately if all required resources are available.

TIME Parameter

When testing any programs you are working on, you may want to ensure that they do not run longer than you think they should, for example in the case of a program looping. A TIME parameter can be coded on the JOB statement for this purpose. This is used to specify the maximum amount of CPU time, not elapsed time, that your job can execute for.

There are several values that can be specified for this parameter. In the example shown here, two positional sub parameters can be used to specify minutes and seconds.

```
File
        Edit Edit_Settings
                                                 Compilers
                              Menu Utilities
                                                             Test
                                                                   Help
           IBMUSER.JCL(DISDEVØ5) - Ø1.Ø2
                                                               Columns ØØØØ1 ØØØ72
                                                                  Scroll ===> <u>CSR</u>
       ØØØ1ØØ //DISDEVØ5 JOB MSGCLASS=C,CLASS=K,
øøø2øø
000300
000400
000500
         STEP1
                   EXEC PGM=ICEGENER
                  DD SYSOUT=*
DD DSN=IBMUSER.CCF.REPORT,DISP=OLD
DD DSN=IBMUSER.DIS.WKLY.REPTRNS(+1),
         SYSPRINT
         SYSUT1
øøø6øø
         SYSUT2
øøø8øø
                   DD DUMMY
øøø9øø
         SYSIN
001000
         STEP1
                        PGM=STRPDIS
                      DSN=IBMUSER.CCF.REPORT,DISP=OLD
DSN=IBMUSER.DIS.STRIPPED.REPDATA,
         INDD1
øø11øø
ØØ12ØØ
         OUTDD1
                   DISP=(,CATLG),UNIT=SYSDA,
SPACE=(CYL,(10,10),RLSE)
øø13øø
ดด14ดด
                      SYSOUT=
øø15øø
         SYSPRINT
                      SYSIN
```

The first sub parameter in the TIME parameter refers to minutes. This value must be between 0 and 357913. The seconds sub parameter appears after the comma and must be a value between 0 and 59 - inclusive.

- If minutes are not required just put a comma in front of the seconds like with the accounting information and programmer name combo.
- If seconds are not required, just do TIME=2 or whatever value for the CPU minutes.
- It is possible for a job to take 1 hour to run but only consume a minute of CPU time so keep this in mind when using this parameter.

There may be several areas where your systems administrator has defined the maximum amount of time that a job can run. As well as specifying minutes and seconds as shown on the previous page, there are also several other values that can be used.

```
, 'B CORNES'.
000100
         JETDEV01 JOB
                   CLASS=K,
000200
000300
                   MSGCLASS=X,
000400
                    OTIFY=IBMUSER
000500
000600
                        PGM=IEFBR14
                   JOB 6910-D112, 'GINA HARRIS',
000100 //FAMXTP15
                   CLASS=K,
MSGCLASS=X
000200
000300
                   TIME=NOLIMIT
000400
000500
                   JOB SPEN1763, 'E KARLSSON',
000100
         /PENEDD12
000300
```

COND Parameter

When your batch job runs, each step or program runs sequentially, and when it completes it produces a condition code. Following this, the next program sequentially in your JCL will be invoked, and so on. If for some reason a program completes unsuccessfully, then what usually occurs is that the job itself will fail at that point and no further processing for the job will occur.

JCL allows you to be more specific about the completion circumstances for each program and whether other programs that appear later in your job should run. One method used to achieve this is the JOB statement COND parameter.

```
Edit Edit_Settings Menu Utilities
                                                 Compilers
  File
                                                              Test
                                                                    Help
            IBMUSER.JCL(DISDEVØ5) - Ø1.Ø4
                                                                Columns 00001 00072
___ Scroll ===> <u>CSR</u>
EDIT
Command ===>
000100 //DISDEV05 JOB MSGCLASS=C,CLASS=K,
øøø2øø
øøø3øø //*
                   EXEC PGM=DISBKUP
ØØØ4ØØ
         STEP1
ØØØ5ØØ //
øøø6øø
                   EXEC PGM=DISEXT
         STEP2
000700 /
                   EXEC PGM=DISSORT
øøø8øø
         STEP3
øøø9øø //
001000
         STEP4
                   EXEC PGM=DISREP
001100 //*
                   ************ Bottom of Data *******
```

PRTY Parameter

You saw earlier that when a job is submitted, if an initiator is available then the job will begin executing. Though what happens if there are several jobs waiting to be processed and you need yours to run first once an initiator becomes available?

One of the other tasks performed by JES is to set a priority for the job. In most cases as a general user, you will not have much control of job priority, because if you did then everyone would be promoting their job to the highest level. Having said that, there is a PRTY parameter that can be coded on the JOB statement that allows you, if authorized, to define a priority for your job. In the scenario here your job would appear as a higher order on the input queue than others.

```
File Edit Edit_Settings Menu
                                                      Utilities Compilers
                                                                                         Test
                                                                                                  Help
          FDTT
Command ==
                            JOB CLASS=T, MSGCLASS=L,
000100 //PLB#115
000200
                            PRTY=15
000300
000400
                             SET MEM=SEARCH
                                I MEM=SEARCH
EC PGM=IBMZPLI,PARM=('SOURCE')
DSN=IEL450.SIBMZCMP,DISP=SHR
DSN=CEE.SCEERUN,DISP=SHR
DSN=DSNB10.SDSNLOAD,DISP=SHR
DSN=IBMUSER.OPTIONS,DISP=SHR
DSN=IBMUSER.JCL(DBRM),DISP=SHR
DSN=IBMUSER.JCL(DBRM),DISP=SHR
DISP=SHR,DSN=IBMUSER.PL1.SRC(&MEM)
DISP=SHR,DSN=IBMUSER.PL1.SRC
SYSOUT=*
000500
             /PLI
000600
             /STEPLIB
000700
000800
             OPTIONS
000900
001000
             /DRRMLTR
              SYSDEBUG DD
001100
001200
              SYSIN
              SYSLIB
001300
                                 SYSOUT=*
001400
              SYSPRINT
001500
                                 SYSOUT=*
                            DD DSN=&&LOADSET,DISP=(MOD,PASS),UNIT=SYSALLDA,
SPACE=(CYL,(1,1)),DCB=(LRECL=80,BLKSIZE=3200)
DD DSN=&&SYSUT1,UNIT=SYSALLDA,
001600
              SYSLIN
001700
001800 //SYSUT1
```

For a JES2 site, the value for this parameter is from 0 through 15, with the highest priority being 15. In a JES3 environment, the range is 0 through 14.

Depending on your organizational standards, if you have coded this parameter the system may just ignore it.

Other JOB Statement Parameters

RESTART Parameter

Normally when you submit a job, it will run from top to bottom, executing programs sequentially. However, what happens when your five-program job processes the first two programs successfully, and after 30 minutes of elapsed time processing them, fails in the third program because a data set you were trying to create already existed. To rerun it from the beginning would waste 30 minutes of previously successful processing. In this situation you may be able to use the JOB statement RESTART parameter.

In the example shown here, the RESTART parameter will begin from a step named STEP3. When the job is submitted, the DISBKP and DISEXT programs will not be run, and processing will begin from STEP3, which invokes the DISSORT program.

Memory-Related Parameters:

The REGION parameter is used to specify the maximum amount of memory that can be used by programs within the job. However, there are several other memory-related parameters that can be used to further refine memory requirements.

- REGIONX can be used if one already knows how much memory above and below the 16MB line is required
- By default, programs will utilize virtual storage which is pageable. This can be altered so all programs in the job use real, non-pageable storage.
- This last one places a limit on the total size of usable virtual storage above the bar in a single address space.

Output-Related Parameters:

Similar to MSGCLASS and MSGLEVEL parameters and how they are used when producing system output there are several other output-related parameters that can be used on the JOB statement to specifically control the maximum amount of output that should be produced. This is useful if your job creates more output than you expected. Note that like other parameters discussed, you will have an installation default for it, so coding this parameter is only useful if it varies from this value.

```
Edit Edit_Settings Menu Utilities Compilers
  File
                                                                      неІр
                                                               Test
            IBMUSER.JCL(AASORT) - Ø1.Ø3
                                                                  Columns ØØØØ1 ØØØ72
EDIT
                                                      Command ==
         /AASORT JOB 6910-D112, 'GINA HARRIS',
CLASS=C, MSGCLASS=X,
        //AASORT
ØØØ1ØØ
000300
000400 //*
000500 //STEP1
30600 //SYSOUT
                   LINES=(10, WARNING)
                    EXEC PGM=SORT
                    DD SYSOUT=*
DD DSN=IBMUSER.PEN.DAILY.TRANS,DISP=OLD
        //SORTIN
```

```
Display Filter View Print Options Search
                                           ЈОВØ961Ø
SDSF OUTPUT DISPLAY AASORT
                                                                        2 LINE Ø
                                                                                               COLUMNS 2Ø- 99
                                                                                              SCROLL ==
COMMAND INPUT ===>
J E S 2 J O B L O G -- S Y S T E M S Ø W 1 -- N O D
                                                           SØW1 -- NODE SVSCJES2
--- WEDNESDAY, Ø8 NOV 2017 ----
IRRØ1ØI USERID IBMUSER IS ASSIGNED TO THIS JOB.
ICH7ØØØII IBMUSER LAST ACCESS AT 16:14:57 ON WEDNESDAY, NOVEMBER 8, 2017
$HASP373 AASORT STARTED - INIT 1 - CLASS K - SYS SØW1
IRRØ1ØI
SHASP373 AASORT
SHASP375 AASORT
SHASP375 AASORT
SHASP375 AASORT
SHASP375 AASORT
SHASP375 AASORT
                                                                              10,000
20,000
                           ESTIMATE EXCEEDED BY
                                                                                          LINES
                           ESTIMATE EXCEEDED BY
                                                                                          LINES
                           ESTIMATE EXCEEDED BY ESTIMATE EXCEEDED BY
                                                                               30,000
$HASP375 AASORT
                                                                               40,000
                                                                                          LINES
```

The JCL at the top of this screen contains a LINES parameter, to indicate if more than ten (thousand) lines of output are produced, then a warning message will be sent to the operator. The job will continue to process the output for the job and an operator message will continue to be sent at regular intervals. The SDSF output for the job at the bottom of the screen shows these messages being produced, which are also sent to the operator.

- The warning parameter can be replaced with DUMP or CANCEL
 - DUMP will cancel the job once the maximum number of lines have been produced and request a system dump.
 - CANCEL will cancel the job without a dump.

```
000100 //BLKJET01 JOB 6910-D112, 'GINA HARRIS', 000200 // CLASS=C, 000300 // MSGCLASS=X, 000400 // NOTIFY=IBMUSER, 000500 // PAGES=(20,WARNING)

000001 //CSFSMFJ JOB (D-117), 'GMH RUN', 000002 // CLASS=A, 000003 // MSGCLASS=X, 000004 // BYTES=(5,DUMP)

000100 //DISDEV05 JOB MSGCLASS=C, 000200 // CLASS=K, 0ARDS=(500,CANCEL)
```

The LINES parameter can be substituted with the following, using a different measurement to determine the maximum amount of output to be produced:

- PAGES is the maximum number of pages of output that can be produced before action is taken.
- BYTES is the maximum number of bytes, in thousands, that can be produced before action is taken.
- CARDS is the maximum number of cards that can be punched before action is taken.

SYSAFF Job Processing Environment Parameter

When the submit command is issued for a job, the system assumes that the job is to be run on the system where it is being submitted from. If resources are not available on that system, then the job may sit and wait a considerable time before it executes.

There are several JOB statement parameters that can be used to specify that the job is run on a more appropriate system within the organization. For example, the SYSAFF parameter shown here can be used to list the JES2 members, or JES3 systems, that are allowed to process this job.

```
<u>H</u>elp
  Display
            <u>Filter</u>
                    <u>View</u>
                           Print
                                   Options
                                             <u>S</u>earch
SDSF OUTPUT DISPLAY PENEDD12 JOB09617
                                                     2 LINE
                                                              CHARS
COMMAND INPUT
    J0B09617
               $HASP373 PENEDD12 STARTED - INIT 1

    CLASS K

    J0B09617
                                                                 TTMTNGS
               -STEPNAME PROCSTEP
                                             EXCP
                                                     CONN
                                                                 TCB
    J0B09617
                                        RC
                                                                            SRB
    J0B09617
               -STEP01
                                        00
                                              108
                                                                  .00
                                                                             . 00
               -PENEDD12 ENDED.
                                   NAME-E KARLSSON
    J0B09617
                                                                TOTAL TCB CPU TIME=
               $HASP395 PENEDD12 ENDED - RC=0000
    J0B09617
  JES2 JOB STATISTICS
         JOB EXECUTION DATE
         CARDS READ
         SYSOUT PRINT
                 PUNCH RECORDS
         SYS0UT
         SYSOUT SPOOL
                       KBYTES
    0.00 MINUTES EXECUTION TIME
                 JOB SPEN1763,
                                'E KARLSSON',
       /PENEDD12
                                                                                     00
                                                                                     00
           THIS STEP WILL CONVERT THE PARTITIONED VB DATASET
                                                                                     00
```

As seen in the image above, this job output was eligible on JES2 members S0W1, S0W2 or S0W3. At the top of this output we can see that it was run on S0W1.

Several other types of values can be coded in the SYSAFF parameter such as:

- ~S0W3 which means the job can be processed on any member except S0W3
- All which means that any system can process the job

A maximum of 33 member names can be specified with this parameter.

SYSTEM Job Processing Environment Parameter

Similar to the SYSAFF parameter, the SYSTEM parameter defines the systems where the job can be processed. Up to 32 eight-character system names can be coded. A preceding hyphen (-) character can be used to identify that the job is not allowed to be processed on the specified system.

The ANY value indicates that it can run on any eligible system, while values of JGLOBAL - global processor only, and JLOCAL - local processor only, are used for JES3 environments.

SCHENV Job Processing Environment Parameter

In your Workload Management (WLM) policy you may have defined a number of scheduling environments. A scheduling environment consists of a set of resources whose state can be set depending on the system they reside on. For example, you could have a scheduling environment named DBBAT that requires a resource representing the Db2 database being available to be set to OFF, and that a batch processing window resource be set to ON. When these resources meet this requirement, the DBBAT scheduling environment is available.


```
EDIT IBMUSER.JCL(DBBAT20) - 01.02 Columns 00001 00072
Command ---> Scroll ---> CSR

000001 //DBBAT20 JOB CLASS=K,
000002 // MSGCLASS=A,
000003 // NOTIFY=IBMUSER,
000004 // SCHENV=DBBAT
000006 //ALTERTAB EXEC PGM=IKJEFT01,DYNAMNBR=20
000007 //SYSTSPRT DD SYSOUT=*
000008 //SYSTSIN DD *
000009 DSN SYSTEM(DB2)
000010 RUN PROGRAM(DSNTIAD) -
000011 PLAN(DSNTIA31) -
000012 LIB('DB310.RUNLIB.LOAD')
000013 /*
000014 //SYSPRINT DD SYSOUT=*
000015 //SYSUDMP DD SYSOUT=*
000016 //SYSDUMP DD SYSOUT=*
000016 //SYSIN DD *
000017 //SYSIN DD *
000017 ALTER TABLE OLIBRARY ADD MEMBER CHAR(16) NOT NULL WITH DEFAULT;
```

When this batch job is submitted, JES will check the scheduling environment specified and then assign the work to a system that matches that scheduling environment.

Identification-Related Parameters

Normally, the system can identify the authorization requirements for a batch job as they are taken from the user submitting the job. However, there are several other lesser used JOB statement parameters that can be used for identification and authorization purposes.



Running a Program using EXEC Statements

EXEC Statement Basics

Each EXEC statement marks the beginning of that step, which ends when another EXEC statement is encountered, or it is the end of the job. As well as informing the system of the programs to run, various parameters can be passed to the program in this statement.

A job can contain as many as 255 EXEC statements and must contain at least one, but it is rare today to see a large number of steps in a job. This is because it is more difficult to manage a job like this if a restart is required.

No JOB without Steps

A job must contain at least one step, otherwise it will fail. The SDSF output shown on the bottom screen indicates this exact problem, but it looks like there are steps in the JCL, which is shown at the top (it's the empty // curse).

```
Columns 00001 00072
Scroll ===> CSR
EDIT
              IBMUSER.JCL(FAMXTP15) - Ø1.21
Command
                      ************************ Top of Data
ØØØ1ØØ //FAMXTP15 JOB 691Ø-D112, 'GINA HARRIS'
                       CLASS=K,
MSGCLASS=X
ØØØ2ØØ /
øøø3øø
000400 /
000500 /
000600 /
               THE FIRST STEP IS USED FOR RECOVERY PURPOSES CHANGE THE SYSUT1 AND SYSUT2 DATA SETS AS REQUIRED
000700
           STEP1
                        EXEC PGM=ICEGENER
000800
           SYSURINT DD SYSOUT=*
SYSUT1 DD DSN=GHMAST.FAMAPS.D256,DISP=OLD
øøø9øø
øø1øøø
                       DD DSN=GHMAST.FAMAPS.D256.BACKUP,DISP=(,CATLG),UNIT=SYSDA,SPACE=(CYL,(10,10),RLSE)
øø11øø
øø12øø
ØØ13ØØ
                        ********* Bottom of Data *******
```

Statement Name - EXEC

In the example below, the EXEC statements do not have a name. This is because it is optional, as this statement's only purpose is to invoke a program.

```
DD DSN=PROD.D112Y17.PENTRANS.DISP=OLD
DD DSN=IBMUSER.TOTAL.PENTRANS.DISP=(,CATLG),
UNIT=SYSDA,SPACE=(CYL,(10,10,RLSE))
DD SYSOUT=*
000300 //INPUT
000500 //OUTPU
000500
000600
            OUTPUT
         //SYSPRINT
                          DD SYSOUT=*
DD SYSOUT=*
         //SYSOUT
øøø7øø
øøø8øø
ดดด9ดด
                           EXEC PGM=TRANXCT
                              SYSOUT=
ØØ11ØØ //SYSPRINT
ØØ12ØØ //INDD1
ØØ13ØØ //SYSIN
                              DSN=IBMUSER.TOTAL.PENTRANS,DISP=SHR
           RECORDS=10000
                                *********** Bottom of Data *****************
```

However, it is good practice to use them because:

- You need them for restart statements.
- It makes debugging easier.
- May have duplication issues in the long run.
- We are also able to refer back to certain statements in previous steps. To do this, we also need a statement name.

```
File Edit Edit_Settings Menu Utilities Compilers
                                                                                   Test Help
               IBMUSER.JCL(APENCHK) - Ø1.Ø1
                                                                                      Columns 00001 00072
Scroll ===> <u>CSR</u>
    mand
002000
            STEP3
                         DD DSN=IBMUSER.SALESIN,DISP=OLD
DD DSN=IBMUSER.PEN.TRANS.PARMPEN,
DCB=(RECFM=FB,LRECL=80,BLKSIZE=32720),
SPACE=(CYL.(1,1),RLSE),UNIT=SYSDA,DISP=(,CATLG)
DD SYSOUT=*
ดด21ดด
aø23øø
            SYSPRINT
002500
                         EXEC PGM=IEBGENER
DD DSN=*.STEP3.SYSUT2,DISP=SHR
DD SYSOUT=*
            /STEP4
/SYSUT1
øø29øø
            /SYSUT2
/SYSPRINT
                              SYSOUT=*
```

Although this has not yet been covered, you are also able to refer back to certain statements in previous steps. For example, to use the same data set created earlier in the job. In order to do this, you need to specify a step name. You can see in this example that on line 002900 the DSN parameter uses an asterisk (*) to indicate a referback, and what follows is the step name and DD statement name. It says to use the same data set used in STEP3 by DD statement SYSUT2. This is identified on line 002200. Do not worry too much about this parameter at this stage, it is just included here to highlight referencing of a step name.

EXEC Operation

Following the statement name, at least one space needs to be coded before entering the statement type EXEC. If the name is not specified, EXEC must appear at least one blank character after the // characters.

If there's no EXEC for a statement, an error will appear.

Programs

The next step is to tell the system the program, or programs that it needs to run. This can be as easy as coding PGM=programname. This will instruct the system to look in the system program libraries for the program specified. These programs are stored as members in partitioned data sets. Once located, the program is then loaded into memory, and begins running.

There must be a space between EXEC and PGM.

JOBLIB and STEPLIB Statements

If you are developing or testing programs there is a good chance that they will not reside in the default program libraries that the submitted JCL uses. In these situations, you can specify a JOBLIB or STEPLIB statement to instruct the system to begin the search for programs in these libraries.

- JOBLIB When this job is run, the data specified in it IBMUSER.LOAD will be searched first when there is any program request. If it is not located here, the default system libraries will then be searched.
- STEPLIB this performs the same function as JOBLIB but only for a single step. In this scenario below, IGYCRCTL program will be searched for in the data set IBMUSER.MOD first. Other programs in this job will only use the default system libraries.

Program Referback

The method shown previously is the most common way that you will see a single program being invoked. There is a possibility though that your organization may use the PGM parameter for referring back to a JCL statement earlier in your job. A scenario might be that your first step creates a temporary program which then needs to be referred to in a later step.

- The '*' in JCL the asterisk is used in several different ways; in this case it indicates a referback
- COMP A period (.) is used to separate referback data. COMP indicates the name of the previous step that will be used to obtain the program name. If SYSLMOD had not been coded, the system would have used the program from the COMP step - IEWL.
- SYSLMOD this is used to indicate the DD statement that contains the name of the program to be used - PROG.

```
/COMP
ØØ15ØØ
                                      PGM=IEWL, REGION=ØM, COND=(5, LT, COMP1),
                              PARM='LIST, XREF'
DD DSN=IGY52Ø.SIGYCOMP, DISP=SHR
DD DISP=SHR, DSN=CEE.SCEELKED
DD DISP=(OLD, DELETE), DSN=&&LOADSET
DD DISP=OLD, DSN=IBMUSER.MOD(&MEM)
øø16øø
ØØ17ØØ
              STEPLIB
ØØ18ØØ
              /SYSLIB
øø19øø
              /SYSLIN
002000
              /SYSLMOD
øø21øø
               SYSPRINT
                                   SYSOUT=A
                              DD UNIT=SYSDA, SPACE=(1024, (200, 20))
EXEC PGM=*.COMP.SYSLMOD
ØØ22ØØ
            //SYSUT1
            //G0
øø23øø
```

Procedures

Another way of providing programs to be run is through a procedure. A procedure is a set of JCL statements, multiple steps usually, stored in a separate partitioned data set. They are useful if there is some common program processing that needs to be used by a number of users. In this way, the user only needs to code the name of the procedure on a single statement, rather than enter all of this code into their JCL.

```
Edit Edit_Settings Menu Utilities Compilers Test
 <u>F</u>ile
                                                              <u>н</u>е1р
          IBMUSER.JCL(ARUNREP) - Ø1.Ø5
                                                          Columns ØØØØ1 ØØØ72
EDIT
Edit Edit_Settings Menu Utilities
                                             Compilers
                                                        Test Help
          VENDOR.PROCLIB(GHPROC) - Ø1.Ø5
                                                          Columns_00001 00072
Command =
                                    Top of Data
øøø1øø
       //STEP1
                   KEC PGM=ALBKALL, REGION=4N
         SYSPRINT
                 DD DISP=SHR,DSN=VENDOR.PARMLIB(GHPCKS1)
DD DSN=&&VOLEUR,DISP=(,PASS),
øøø3øø
        SYSIN
øøø4øø
        /OUTDD
                 UNIT=SYSDA,
SPACE=(TRK,(5,5),RLSE),
DCB=(LRECL=80,RECFM=FB)
ØØØ5ØØ
000700
000/00 //
000800 //*
000900 //STEP2
001000 //SYSIN
                 EXEC PGM=IEBGENER
        /SYSPRINT DD SYSOUT=*
```

Calling a Procedure

There are two ways of calling a procedure, using the PROC parameter and specifying the procedure name. Both of these methods perform the same task.

```
Edit Edit_Settings
 <u>F</u>ile
                     Menu Utilities Compilers
                                           Test
                                               <u>H</u>elp
EDIT
        IBMUSER.JCL(ARUNREP) - 01.05
                                            Columns 00001 00072
                                    Scroll ==> <u>CSR</u>
000100 //ARUNREP
000300 //*
     ****** Top of Data
             JOB MSGCLASS=C, NOTIFY=IBMUSER, CLASS=K
             File Edit Edit_Settings Menu Utilities Compilers Test
                                               <u>H</u>elp
        IBMUSER.JCL(ARUNREP) - 01.06
EDIT
                                            Columns 00001 00072
     //ARUNREP JOB MSGCLASS=C, NOTIFY=IBMUSER, CLASS=K
000100
000200
             //RUNGH
000300
```

Locating a Procedure

Just as programs are searched for in default system libraries when they are referenced, so too are procedures. But with these items, system procedure libraries are searched and if the procedure you are looking for is not found, then the messages highlighted here will be produced.

```
Display Filter View Print Options
                                                                <u>H</u>elp
                                                      <u>S</u>earch
 SDSF OUTPUT DISPLAY JNAPAN3Ø JOBØ9688 DSID
                                                                2 LINE Ø
                                                                                   COLUMNS Ø2- 81
COMMAND INPUT ===>
                                                                                  SCROLL ===> CS
                           ******* TOP OF DATA
                        JES2 JOB LOG
                                                           SYSTEM SØW1 --
ØØ.Ø6.21 JOBØ9688 ---- MONDAY, 13 NOV 2017 ----
ØØ.Ø6.21 JOBØ9688 IRRØ1ØI USERID IBMUSER IS ASSIGNED TO THIS JOB.
ØØ.Ø6.21 JOBØ9688 IEFC452I JNAPAN3Ø - JOB NOT RUN - JCL ERROR 77Ø
        JES2 JOB STATISTICS
              3 CARDS READ
17 SYSOUT PRINT RECORDS
               Ø SYSOUT PUNCH RECORDS
          1 SYSOUT SPOOL KBYTES

Ø.ØØ MINUTES EXECUTION TIME

1 //JNAPAN3Ø JOB MSGCLASS=C,NOTIFY=IBMUSER,CLASS=K
STMT NO. 1
            //JNSTEP1 EXEC PROC=JNENGØ5
MESSAGE
            TEFC612I PROCEDURE JNENGØ5 WAS NOT FOUND
```

EXEC Statement Parameters

REGION Parameter

As seen previously, the REGION parameter can be specified on the JOB statement, and how it defines the maximum amount of memory to be used by any program in your job. In some situations though, you may only need to specify a memory requirement for one of the programs in your job.

The REGION parameter can be used on the EXEC statement as shown here, and uses the same syntax as discussed previously

```
File Edit Edit_Settings Menu Utilities Compilers
                                                                  Test
                                                                         <u>H</u>e1p
             IBMUSER.JCL(CSFSMFJ) - Ø1.Ø4
                                                                     Columns 00001 00072
EDIT
                                                                     __ Scroll
MSGCLASS=X
øøø4øø
øøø5øø
              UNLOAD SMF RECORDS TO PRINT
øøø6øø
                    EXEC PGM=IFASMFDP, REGION=6M
DD DISP=SHR, DSN=SYS1.SØW1.MAN1.DATA
DD SYSOUT=*
DD SYSOUT=*
DD * sub
øøø7øø
000800
          /DUMPIN
          /DUMPOUT
øøø9øø
           SYSPRINT
øø11øø
             INDD(DUMPIN, OPTIONS(DUMP))
øø12øø
            INDD(DUMPIN, UPITONS (22))
OUTDD(DUMPOUT, TYPE(82))
OUTDD(DUMPOUT, TYPE(82))
OUTDD(DUMPOUT, TYPE(82))
```

- When using this parameter when specifying a procedure, then all programs within the procedure will use the REGION specification.
- If you only need to provide a memory requirement for a specific step within a
 procedure then this can be coded as shown below, it is rare to do this. In this
 example, the procedure step name is provided after coding a period (.) after
 REGION.

 In the example below, a REGION parameter is coded on both JOB and EXEC statements. This could arise if parts of the JCL have been copied from different sources. If this scenario occurs, the JOB statement REGION parameter will override any EXEC statement equivalent.

```
JOB (67103, 'DEPT/106', SECT04), 'PAOLA MASONI',
          SUPCHK
                    MSGCLASS=X,
øøø2øø
øøø3øø
                    CLASS=K,
øøø4øø
ØØØ5ØØ
          SUPERC
                    EXEC PGM=ISRSUPC, REGION=ØM
ааа6аа
                       PARM=(DELTAL,LINECMP,'')
DSN=IBMUSER.REPORT2,DISP=SHR
øøø7øø
 øø8øø
          NEWDD
                       DSN=IBMUSER.REPORT4,DISP=SHR
```

COND Parameter

The COND parameter can also be used on the EXEC statement, but is used more specifically to identify whether the step should be run.

```
Edit Edit_Settings Menu Utilities Compilers
  File
                                                                  Test
                                                                         <u>H</u>e1p
                                                                     Columns 00001 00072
____Scroll ===> <u>CSR</u>
EDIT
             IBMUSER.JCL(BLASTTØ5) - Ø1.11
Command ===>
                                           Top of Data **********
        *****
0000100 //BLASTT05 JOB ,'JANE WILLIAMS'
0000200 // CLASS=K,
0000300 // MSGCLASS=X
øøø4øø
                                          Completion code of 0
                     EXEC PGM=BLSORT
øøø5øø
          STEP1
ØØØ6ØØ /
          STEP2
                     EXEC PGM=BLSTRIP
øøø7øø
                                          Completion code of 0
øøø8øø
                     EXEC PGM=BLREPORT, COND=(Ø, NE)
          /STEP3
øøø9øø
                                          Bottom of Data
```

The example displayed here shows how a simple COND parameter is used. There are three steps defined, with the last one containing a COND parameter. After the first two steps are run - assuming they both complete with a return code of zero, successful - your last step is a management report and should only run if all preceding steps have a zero-condition code.

The COND parameter can be quite confusing to determine sometimes how it is processing step condition codes. The example used on the previous page was a relatively simple one.

```
000700 //STEP2 EXEC PGM=BLSTRIP
000800 //*
000900 //STEP3 EXEC PGM=BLREPORT,COND=(0,NE)

000700 //STEP2 EXEC PGM=BLSTRIP
000800 //*
000900 // IF (RC=0) THEN
001000 //STEP3 EXEC PGM=BLREPORT
001100 // ENDIF
```

IBM have recognized the difficulty users have with interpreting this parameter, and recommend using an IF, THEN, ELSE, ENDIF structure, which will be more familiar to programmers.

PARM Parameter

There will be times when you need to pass additional information to the program in your EXEC statement. For example, a program you have written may perform several tasks with data that is input to it, but not necessarily every time the program is run. In this scenario some parameter information can be passed to the program, which the program will use in its processing.

The EXEC statement PARM parameter can be used for this purpose.

```
Edit
                     Edit_Settings
                                           Menu
                                                     Utilities
                                                                     Compilers
                                                                                               He<sub>1</sub>p
   File
                                                                                      Test
                IBMUSER.JCL(COBCOMP) - 01.99
EDIT
                                                                                          Columns 00001 00072
                           JOB 123, 'COBOL COMPILE', CLASS=A, MSGCLASS=X,
NOTIFY=IBMUSER
Command
000100 //IBMUCOB
000300
  00400
                             ET MEM=COMPUTE2
000500
             COMP1
000600
                               DSN=IGY520. SIGYCOMP, DISP=SHR
DISP=SHR. DSN=IBMUSER.COBOL. SRC(&MEM)
DISP=SHR. DSN=IBMUSER.COBOL. SRC
DISP=SHR. DSN=CEE.ACEESRC1
000700
              STEPLIB
000800
              SYSIN
              SYSLIB
001000
                               SYSOUT=B
DISP=(MOD, PASS), DSN=&&LOADSET, SPACE=(80, (10,10)),
              SYSPRINT
  01100
001200
              SYSLIN
001300
                           UNIT=SYSDA
                               SPACE=(CYL,(1,1)),UNIT=SYSDA
SPACE=(CYL,(1,1)),UNIT=SYSDA
SPACE=(CYL,(1,1)),UNIT=SYSDA
SPACE=(CYL,(1,1)),UNIT=SYSDA
SPACE=(CYL,(1,1)),UNIT=SYSDA
001400
              SYSUT1
001500
              SYSUT2
001600
            /SYSUT3
              SYSUT4
           ///SYSUTS
001800
```

Note: The program must explicitly be written to accept and process the PARM information passed to it. As a result, the format and types of PARM data that can be passed must be documented.

Syntax Rules:

- What is the maximum length of PARM data?
 - Cannot exceed 100 characters
- What if PARM data will not fit entirely on one line?
 - You can extend the PARM data by ensuring that the sub parameters are enclosed in parentheses. At the end of a sub parameter definition, code a comma, and begin the continuation on the following line between columns 4 and 6, inclusive.

```
000400 //PLI EXEC PGM=IBMZPLI,PARM=(SOURCE,ZZED,'JK;22',GLOBAL, 000500 // 'CULLDATE - 2018/02/11',KD30)
```

- How do you separate sub parameters that are required in PARM data?
 - Separate them using commas and they must be enclosed in parentheses or single quotes

```
000500 //COMP1 EXEC PGM=IGYCRCTL,
000600 // PARM='LIST,XREF'
```

- What if you need to pass PARM data to one program within a procedure
 - The PARM.procedurestep can be used to specify that the PARM data is only passed to the specified step in that procedure. If the procedure step name is not used, then the PARM data will only be passed to the first step in the procedure.

```
000300 //INSTP01 EXEC PROC=STPOOLBK,
000400 // PARM.STEP2=(LIST,XREF)
```

- What if PARM data contains special characters of blanks
 - It needs to be enclosed in single quotes
- What if you enter incorrect PARM data?
 - The program must be defined to interpret and act on the PARM data if it is specified. If you enter incorrect data, then often the program will be designed to just ignore it.

PARMDD Parameter

Rather than having to code your parameter information directly into the EXEC statement, you can also use a PARMDD parameter for this purpose. This instructs the system to obtain parameter information from another statement within the JCL. This statement may contain a reference to a data set that contains this data.

One benefit of using this in preference to the PARM parameter is that more than 100 characters can be specified. Note that the PARMDD parameter cannot be used with the PARM parameter on the same statement.

```
Edit Edit_Settings Menu Utilities
  Eile
                                                             Compilers
                                                                             Test
                                                                                     Help
EDIT
              IBMUSER.JCL(OOCBKUP) - 01.05
                                                                                Columns 00001 00072
                       JOB D22789B, 'COBOL COMPILE', CLASS=A, MSGCLASS=X, TYPRUN=SCAN
                                                                                    Scroll ===
000100
         //OOCCOMP
000200
                             MEM=00CB00K
 00400
                            PEN=DUCEOUR

C PGM=IGYCRCTL, PARMDD=OOCPARMS

DISP=SHR, DSN=IBMUSER. MOD

DISP=SHR, DSN=CEE. SCEERUN2

DSN=IBMUSER. COBOL. SRC (OOCBOOK), DISP=SHR
            COMP1
            STEPLIB
            SYSIN
                            DISP=SHR, DSN=IBMUSER.COBOL.SRC
            SYSL TR
                            DISP=SHR, DSN=CEE.ACEESRC1
DSN=VENDOR.PARMLIB(OOCPARMS),DISP=SHR
 01000
001100
001200
001300
            SYSJAVA
                        DD PATH='/u/ibmuser/java/elpsorttbl.java',
001400
001500
                        PATHOPTS=(OWRONLY,OCREAT,OTRUNC),
PATHMODE=SIRWXU,
                        FILEDATA=TEXT
            SYSLIN DD DSNAME=&&OBJECT(TSTOOC),UNIT=SYSALLDA,DISP=(MOD,PASS),
```

Defining Symbol Values

Another item you may encounter on an EXEC statement is a symbol. These are character strings that represent variable information within the JCL. The screen at the top shows a WORK variable being passed to a procedure. In the SDSF output for the job, you can see where this value has been substituted.

```
000100 //ARUNREP JOB MSGCLASS=C,NOTIFY=IBMUSER,CLASS=K
000200 //*
000300 //INSTP01 EXEC PROC=GHPENBK,WORK='5,5'

1 //ARUNREP JOB MSGCLASS=C,NOTIFY=IBMUSER,CLASS=K
//*
2 //INSTP01 EXEC PROC=GHPENBK,WORK='5,5'
3 XXGHPENBK PROC
4 XXSTEP1 EXEC PGM=SORT
5 XXSYSOUT DD SYSOUT=*
6 XXSORTIN DD DSN=IBMUSER.PEN.TRANS.DAILY,DISP=OLD
7 XXSORTIN DD DSN=IBMUSER.SORTED.PEN.TRANZ,DISP=(,CATLG),
XX SPACE=(CYL,(10,10),RLSE),UNIT=SYSDA
8 XXSORTWK01 DD UNIT=SYSALLDA,SPACE=(CYL,(&WORK))
IEFC653I SUBSTITUTION JCL - UNIT=SYSALLDA,SPACE=(CYL,(5,5))
9 XXSORTWK02 DD UNIT=SYSALLDA,SPACE=(CYL,(&WORK))
IEFC653I SUBSTITUTION JCL - UNIT=SYSALLDA,SPACE=(CYL,(5,5))
```

TIME Parameter

This parameter can also be used on an EXEC statement, but only to specify the maximum amount of CPU time for that specific step.

```
Eile
              Edit Edit_Settings Menu Utilities
                                                                                Compilers
                                                                                                    Test
                                                                                                               He1p
                   IBMUSER.JCL(PLB#115) - 01.08
EDIT
                                                                                                        Columns 00001 00072
                                                                                                                               > <u>CSR</u>
Command =
                                                                                                              5crol1 =
            JOB CLASS=K, MSGCLASS=L
000100 //PLB#115
000200 //
000300 //*
000400 //
                                SET MEM=SEARCH
                                    TMEM=SEARCH
EC PGM=IBMZPLI,PARM=(SOURCE,LIST),TIME=(,20)
DSN=IEL450.SIBMZCMP,DISP=SHR
DSN=IBMUSER.OPTIONS,DISP=SHR
DSN=IBMUSER.JCL(DBRM),DISP=SHR
DSN=IBMUSER.SYSDEBUG,DISP=SHR
DISP=SHR,DSN=IBMUSER.PL1.SRC(&MEM)
DISP=SHR,DSN=IBMUSER.PL1.SRC
SYSOUT=*
000500
               /PLI
000600
            //STEPLIB
               OPTIONS/DBRMLIB
000700
000900
                SYSDEBUG
001000
               'SYSIN
001100
                SYSLIB
                                    5Y50UT=*
               SYSPRINT/SYSOUT
001200
                               DD SYSOUT=*
DD SYSOUT=*
DD DSN=&&LOADSET, DISP=(MOD, PASS), UNIT=SYSALLDA,
SPACE=(CYL, (1,1)), DCB=(LRECL=80, BLKSIZE=3200)
DD DSN=&&SYSUT1, UNIT=SYSALLDA,
SPACE=(1024, (200,50), CONTIG, ROUND), DCB=BLKSIZE=1024
001300
001400
001500
                SYSLIN
               'SYSUT1
```

DD Statements

DD Statement Basics

With the majority of programs, you will need to apply its processing logic against some raw data, in order to produce meaningful output.

Using DD Statements

In the COBOL program code shown, you can see where it references SALESIN and SALESOUT. The program instructs the system to look for its input data, SALESIN, and output requirements, SALESOUT, which are required by the program in order to perform its processing.

```
000500
               Environment Division.
000600
               Input-Output Section.
000700
000800
               File-Control.
                    Select Unsorted-Sales-File Assign to
000900
                                           Organization is
                    Select Sorted-Sales-File Assign to SALESOUT
001000
001100
                                           Organization is
                                                            Sequential.
001200
                    Select Sort-Work-File Assign to DISK.
001300
001400
               Data Division.
001500
               File Section.
001600
               FD Unsorted-Sales-File
```

```
000300 //RUN1 EXEC PGM=SRTSAL,REGION=OM
000310 //*
000400 //SALESIN DD DSN=IBMUSER.JUNE.SALESIN,DISP=SHR
000500 //SALESOUT DD DSN=IBMUSER.JUNE.SALESOUT,DISP=OLD
```

In the JCL example, the COBOL program - now compiled as executable program SRTSAL - is invoked through the EXEC statement, and the SALESIN and SALESOUT JCL DD statements are used to link the input and output data sets required by the program.

This means that the program's logic can be applied to different data, for example, a different month, by just changing the JCL DD statement's data reference.

DD Statement Name:

Syntax requirements include the following:

- Name must be a maximum of 8 characters and must begin with an alphabetic or national character
- Unlike the JOB and EXEC statement names, a DD statement will, in most cases, need to have a specific name. This is because the program that is invoked contains code that says to look for a specific DD name for its input and output.

Referencing the DD Statement


- Do you need to specify the DD statement in the same order that it appears in the program?
 - No, the program is designed to look for a specific DD name. As long as it appears in the step, then it will be able to locate it.
- What if one accidentally codes the same DD statement twice in the same step?
 - The system will use the first one that is encountered and ignore the other one.
- What happens if a required DD statement name does not appear at all in the step?
 - The job step will fail and produce a message indicating that there was a DD statement missing.
- What if you supply a DD statement that the program does not refer to?
 - The DD statement in this case will be ignored by the program, but the system will attempt to locate it, even though the program will not use it.

DD Statement Type

As seen with other statements, you need to specify the type of statement you are working with, which in this case is DD. This needs to be preceded and followed by at least one space.

Input Data Type

The data that needs to be accessed by the program may reside in a number of different types of mainframe files, also referred to as data sets. In turn, this data may reside in several different mediums such as tape/cartridge, or disk - also referred to as Direct Access Storage Devices (DASD).





These items are important to know because a DD statement will often need to contain details about the data.

DSN Parameter

Focusing on input, one of the most common DD statement parameters you will use is DSN or DSNAME. This keyword parameter is used to specify the name of the data that your program will process and can be placed anywhere in the statement. The syntax is straightforward, where the parameter is followed by an equals (=) character and then the name of the data source.

```
Compilers
  File Edit Edit_Settings Menu Utilities
                                                                  Test
                                                                         <u>H</u>elp
                                                                    Columns 00001 00072
EDIT
            IBMUSER.JCL(AGENER) - 01.08
                                                                        Scroll ===> CSR
Command =
       *****
                                          Top of
                                                   Data
       //AGENER
//* STEP
             STEP 1 - PEN TRANSACTION BACKUP

EP1 EXEC PGM=IEBGENER

SUT1 DD DSN=IBMUSER.PEN.TRANS.DAILY
000100
000200
000300
          STEP1
000400
                                         Bottom of Data *********
```

Data Name

Since you are looking at identifying the input data to your program, you can normally assume that the data already exists and is cataloged by the system. If you were to add a name, such as the one shown here, and submit your job, the system would know where that data is stored and prepare it for processing.

This example is referencing a simple sequential data set containing transaction records.

```
Edit
                 Edit_Settings
                                   Menu Utilities
                                                         Compilers
  <u>E</u>ile
                                                                      Test
                                                                              <u>H</u>elp
                                                                         Columns 00001 00072
EDIT
             IBMUSER.JCL(AGENER) - 01.08
                                                                             Scroll ==
                                                            Scroll ===> <u>CSR</u>
        ******* Top of Data
000200 //* STR
              NER JOB MSGCLASS=C,CLASS=K
STEP 1 - PEN TRANSACTION BACKUP
P1 EXEC PGM=IEBGENER
SUT1 DD DSN=IBMUSER.PEN.TRANS.DAILY
         //SYSUT1
000400
                                            Bottom of Data ****
```

```
<u>E</u>dit
  <u>F</u>ile
              Edit_Settings
                              <u>M</u>enu
                                    <u>U</u>tilities
                                                Compilers
                                                                  <u>H</u>elp
                                                            Test
                                                              Columns 00001 00072
EDIT
                                                                 Scroll ===> CSR
Command
                                                    *********
      *****
                                       Top of Data
000100 91163DUBE
                           JASON
                                           CHICAGO
                                                         ΙL
                           ADRIANE
000200 61535KING
                                           CINCINATTI
                                                         OH
000300 10216HOLTZ
                           RACHEL
000400 99034WAYMEL
                                           KALAMAZ00
                           WAYNE
```

Data - Partitioned Data Sets

As mentioned previously, the data may reside in various containers. For example, if your program required data from a member of a partitioned data set (PDS), it would be coded as shown here.

In this example, COBOL source code from PDS member INSPECT is going to be compiled.

```
<u>F</u>ile
           Edit_Settings
                        <u>M</u>enu
                             Utilities Compilers
                                                Test
                                                     <u>H</u>elp
         IBMUSER.JCL(COBCOMP) - 01.99
                                                  Columns 00001 00072
EDIT
Command
                                                     Scroll ===> CSR
     *********
000100
000200
000300
000400
000500
       COMP1
               EXEC
                    PGM=IGYCRCTL
               DD DSN=IBMUSER.COBOL.SRC(INSPECT)
000600
       SYSIN
```

Data - z/OS UNIX Files

JCL DD statements can be used to specify z/OS UNIX data to be used by a program. In this example, the PATH parameter is used to identify the location and file name to be used.

Notice that these statements use lower case text, so if coding something like this make sure the ISPF profile CAPS attribute is turned off, otherwise it will be converted to uppercase when you press the Enter key. Note that apart from this z/OS UNIX reference, all JCL should be coded in uppercase.

```
<u>E</u>dit
                  Edit_Settings
                                               <u>U</u>tilities
                                                              Compilers
  <u>F</u>ile
                                       <u>M</u>enu
                                                                                      <u>H</u>elp
EDIT
               IBMUSER.JCL(A#UX01) - 01.02
                                                                                Columns 00001 00072
                                                                                     Scroll =
Command
         ****** Top of Data
                        JOB MSGCLASS=C,
CLASS=K,
REGION=OM
000100
          //A#UX01
000200
000300
000400 //*
                             <mark>C PGM=IEFBR14</mark>
<mark>PATH</mark>='<mark>[/u/ibmuser</mark>/account2]
            STEP1
000500
000600
```

- The PATH parameter is only required when referencing a z/OS UNIX file.
- This is the name of the directories within the z/OS UNIX file system, where the z/OS UNIX file resides.
- This is the name of the file to be accessed; because the path name contains special characters (/), as well as lower case characters it is enclosed in single quotes (').

DISP Parameter

The DISP parameter describes the disposition, or status, of the data set. It normally consists of three sub parameters that describe the following:

- The status of the data, for example, whether it exists and whether it is required exclusively.
- How the data set is to be handled if the job step completes successfully.
- How the data set is to be handled should the step fail.

If you are dealing with an existing data set being used for input purposes, then it makes sense that regardless of the success of the program using it, that in most cases you will want the data set kept when the program completes. In this scenario, you will often see just the first subparameter used, leaving the other sub parameters to default to a status of KEEP.

```
EDIT IBMUSER.JCL(AGENER) - 01.09 Columns 00001 00072
Command ===> Scroll ===> CSR

000100 //AGENER JOB MSGCLASS=C,
000110 // CLASS=K
000200 //* STEP 1 - PEN TRANSACTION BACKUP
000210 //*
000300 //STEP1 EXEC PGM=IEBGENER
000400 //SYSUT1 DD DSN=IBMUSER.PEN.TRANS.DAILY,DISP=SHR
000500 //*
```

DISP Sub Parameters

What you will often see when referencing an existing data set for input, is a status of SHR (share), or OLD (exclusive use).

- As the names suggest, SHR allows other users or programs to access the data at the same time, as long as they do not require it exclusively. It is effectively a read-only request of that data.
- A DISP of OLD indicates that the use of the data is required exclusively by this step, making it unavailable to other programs even if they require only read access.

```
DD DSN=IBMUSER.JSON.RECS.MSTR,DISP=OLD DD SYSOUT=*

DD DSN=IBMUSER.COPY.STREAM2,DISP=SHR
```

Forgetting to use DISP

It can be easy to forget to code one of the DD statement parameters, so what will happen if you forget to code a DISP parameter?

In this scenario you want to provide some input to a sort program through the SORTIN DD statement and although the data set name is coded, there is no DISP parameter. The default when no DISP parameter is coded is (NEW,DELETE,DELETE). In this case, the job's output messages indicate that when it attempted to create the data set, which is not what you want anyway, there was no space specified for the data set, creating an error.

```
<u>Display Filter View Print Options Search Help</u>
 2 LINE 19
                                                                                                       COLUMNS 02- 81
SCROLL ===> CSR
                                  EXEC PGM=SORT
                  /STEP1
                  /SYSOUT
                                  DD SYSOUT=*
                //SORTIN DD DSN=15MUSER, PEN. DAILY, TRANS
//SORTOUT DD SYSOUT=*
//SORTWK01 DD UNIT=SYSALLDA, SPACE=(CYL, (10,10))
//SORTWK02 DD UNIT=SYSALLDA, SPACE=(CYL, (10,10))
//SORTWK03 DD UNIT=SYSALLDA, SPACE=(CYL, (10,10))
1CH70001I
                             LAST ACCESS AT 15:58:33 ON WEDNESDAY, NOVEMBER 15, 2017
P1 SORTIN - ALLOCATION FAILED DUE TO DATA FACILITY SYSTEM ERRO
IEF344I <mark>AASORT :</mark>
IGD17045I <mark>SPACE</mark>
                                    STEP WAS NOT EXECUTED.
            AASORT STEP1 -
                IBMUSER. AASORT. JOB09816. D0000102. ?
                                                                                          SYSOUT
```

PATHOPTS Parameter

When referencing an existing z/OS UNIX file, a PATHOPTS parameter can be used to specify the access type and status of the file, so it loosely correlates to the first DISP subparameter discussed earlier.

For a file being used for input purposes only, a value of ORDONLY - open the file for reading only can be used.

• If this PATHOPTS parameter is not specified, then the system assumes that it is an existing file and will search for it. If not located, the step will fail.

Referencing Existing Data

If you have been working with JCL, you are likely to have seen a data reference similar to the one shown here. These are called generation data sets.

Suppose you have the same job that needs to run every day, and it creates a sequential data set that contains daily transactions. This data set also needs to be kept for a minimum of 20 working days. You would not normally be able to run the exact same JCL everyday day because it would be trying to create a data set of that name when one already exists

```
Edit Edit_Settings
                         Menu Utilities
                                         Compilers
                                                   Test
                                                        Help
EDIT
         IBMUSER.JCL(COPYSMF) - Ø1.ØØ
                                                     Columns ØØØØ1 ØØØ72
Command ===>
                                                        Scroll ===> <u>CSR</u>
øøø2øø
        STEP1
                EXEC PGM=ICEGENER
øøø3øø
                DD SYSOUT=*
DD DSN=MVS1.SMF.RECORDS(Ø), DISP=SHR
DD DSN=IBMUSER.TEST.MVS.DATA, DISP=(,CATLG),
SPACE=(TRK,(10,10),RLSE)
        SYSPRINT
øøø4øø
        SYSUT1
øøø5øø
 øø6øø
                SYSIN
```

It is now the following day and the same job is run using the same JCL but referencing different daily transactions. It has attempted to create a data set called PEN.XTRCTED.DAILY.TRANS but because the previous day's job already did this, the job has failed indicating a data set of that name already exists.

One way around this is to define a data set name that accepts different versions, or generations, under that name. This is possible by using generation data sets. As mentioned, this topic is discussed in detail in a later course. For the time being