

### DAY-3

**Configuring RIP Theory: RIP concepts: Hop count, updates, and convergence. Practical : Configure RIP on a multi-router network. Task: Capture RIP updates using simulation tools and analyze them.**

- 1. Set up a network topology with three routers in Cisco Packet Tracer, connect them using serial or Ethernet links, and assign IP addresses to all interfaces.**

**ANS :**

➤ What is RIP?

- RIP (Routing Information Protocol) is a dynamic routing protocol that automatically shares routing information between routers. It uses hop count as its routing metric to determine the best path.
  - **Routing Protocol Type:** Distance Vector
  - **Metric:** Hop Count
  - **Maximum Hop Count:** 15
  - **Hop Count 16:** Network is unreachable
  - **Update Interval:** Every 30 seconds
  - **Administrative Distance:** 120

➤ RIP Updates

- RIP sends routing table updates every **30 seconds**.
- Updates are sent using **UDP Port 520**.
- RIP Version 2 supports:
  - Classless routing (CIDR)
  - VLSM
  - Authentication
  - Multicast address **224.0.0.9**

➤ Convergence

- **Convergence** is the time taken for all routers to update their routing tables after a network change.

❖ Example

- A link between Router1 and Router2 fails.
- RIP detects the failure.
- Routers exchange updated routing information.
- All routers learn the new route.
- The network is now converged.

| Device  | Interface | IP Address  | Subnet Mask     |
|---------|-----------|-------------|-----------------|
| Router1 | G0/0      | 192.168.1.1 | 255.255.255.0   |
| Router1 | S0/0/0    | 10.0.12.1   | 255.255.255.252 |
| Router2 | S0/0/0    | 10.0.12.2   | 255.255.255.252 |
| Router2 | S0/0/1    | 10.0.23.1   | 255.255.255.252 |
| Router2 | G0/0      | 192.168.2.1 | 255.255.255.0   |
| Router3 | S0/0/1    | 10.0.23.2   | 255.255.255.252 |
| Router3 | G0/0      | 192.168.3.1 | 255.255.255.0   |

➤ Configure RIP Version 2

▪ Router 1

```
enable
configure terminal
```

```
interface g0/0
ip address 192.168.1.1 255.255.255.0
no shutdown
exit
```

```
interface s0/0/0
ip address 10.0.12.1 255.255.255.252
clock rate 64000
no shutdown
exit
```

```
router rip
version 2
no auto-summary
network 192.168.1.0
network 10.0.12.0
```

```
end
write
```

- Router 2

```
enable
configure terminal
```

```
interface g0/0
ip address 192.168.2.1 255.255.255.0
no shutdown
exit
```

```
interface s0/0/0
ip address 10.0.12.2 255.255.255.252
no shutdown
exit
```

```
interface s0/0/1
ip address 10.0.23.1 255.255.255.252
no shutdown
exit
```

```
router rip
version 2
no auto-summary
network 192.168.2.0
network 10.0.12.0
network 10.0.23.0
```

```
end
```

- Router 3


```
enable  
configure terminal
```

```
interface g0/0  
ip address 192.168.3.1 255.255.255.0  
no shutdown  
exit
```

```
interface s0/0/1  
ip address 10.0.23.2 255.255.255.252  
no shutdown  
exit
```

```
router rip  
version 2  
no auto-summary  
network 192.168.3.0  
network 10.0.23.0
```

```
end  
write
```



➤ Increase Hop Count

Original : R1 ----- R2 ----- R3

Increase : R1 ----- R2 ----- R4 ----- R3

- Example

```
router rip
version 2
no auto-summary
network 10.0.24.0
network 10.0.34.0
```

**2. Use the simulation mode in Cisco Packet Tracer to capture and analyze RIP update packets as they are exchanged between routers. Hint: Filter for RIP packets in the simulation panel and note the source, destination, and advertised routes in each update.**

**ANS:**

➤ Capture RIP Updates in Simulation Mode

1. Open **Cisco Packet Tracer**.
2. Switch from **Real-Time** mode to **Simulation** mode.
3. Click **Edit Filters**.
4. Clear all protocol selections.
5. Select only **RIP**.
6. Click **Capture/Forward** or **Auto Capture/Play**.
7. Observe the RIP packets exchanged between routers.
8. Click on any RIP packet to inspect its details.

➤ Observation Table

| Parameter           | Observation         |
|---------------------|---------------------|
| Protocol            | RIP Version 2       |
| Transport Protocol  | UDP                 |
| Port Number         | 520                 |
| Destination Address | 224.0.0.9           |
| Update Interval     | 30 seconds          |
| Metric Used         | Hop Count           |
| Maximum Hop Count   | 15                  |
| Hop Count 16        | Network Unreachable |