

Lecture Notes on Atmospheric Thermodynamics and Cloud Physics

Harshit Prashant Dhanwalkar (SC21B164)^{1*}

Abstract

Notes of Lectures plus addional information from books.

¹ MTech, Earth System Sciences (ESS), 1st year, Department of Physics, Indian Institute Of SpaceScience and Technology (IIST)

*email: harshitpd1729@gamil.com

Contents	
1 Lecture 1 09/08/2024	4
1.1 Equilibrium State	4
1.2 Transformation	4
1.3 Exact and Inexact differentiable	4
1.4 Extensive and Intrincive variables	4
1.5 Laws of Thermodynamics	4
2 Lecture 2 14/08/2024	6
2.1 Kinetic molecular theory of gases	6
2.2 Ideal gas	6
2.3 Early experiments and laws	6
3 Lecture 3 16/08/2024	8
3.1 Another form of Gay-Lussac's Law	8
3.2 Boyle's Law	8
3.3 Avagadro's Law	8
3.4 Ideal gas Law	8
3.5 Van Der Waal's equation	9
3.6 Meteorological form of Ideal gas	9
3.7 Composition of Earth's Atmosphere	9
4 Lecture 4 19/08/2024	10
4.1 Pressure	10
4.2 Mass of the Atmosphere	10
5 Lecture 5 21/08/2024	12
5.1 Dalton's law of partial pressure	12
5.2 Humidity	12
5.3 Ideal gas equation for moist gas	12
6 Lecture 6 28/08/2024	14
6.1 Archimedes Principle	14
6.2 Buoyancy	14
6.3 Hydrostatic equation	15
7 Lecture 7 29/08/2024	16
7.1 Ideal gas equation with Hydostatic equation	16
7.2 Geopotential	16
8 Lecture 8 30/08/2024	18
Pressure profiles in the idealized atmosphere	18
8.1 Constant density atmosphere	18
8.2 Constant temperature atmosphere	19
8.3 Constant lapse rate atmosphere	19
9 Lecture 9 04/09/2024	20
9.1 First Law of Thermodynamics and Application	20
10 Lecture 10 05/09/2024	21
10.1 First Law of Thermodynamics and Application	21
10.2 Heat capacity	21
10.3 Heat capacity at constant volume	22
11 Lecture 11 06/09/2024	23
11.1 Specific heat capacity	23
11.2 Specific heat at constant volume	23
11.3 Specific heat at constant pressure	23
11.4 Special Forms of First Law of Thermodynamics	23
12 Lecture 12 11/09/2024	25
12.1 Poisson's equation for adiabatic transformation	25
13 Lecture 13 12/09/2024	27
13.1 Adiabatic transformation - Poisson's equation	27
13.2 Adiabatic Lapse Rate	27
13.3 Dry Adiabatic Lapse Rate (DALR)	27
13.4 Possion's equations	27
14 Lecture 14 20/09/2024	29
14.1 Heat Engines	29
14.2 Efficiency	29
14.3 Carnot Cycle	29
14.4 Skew T - log P diagram	30
15 Lecture 15 03/10/2024	34
15.1 Cyclones	34
15.2 Specific enthalpy	34
16 Lecture 16 07/10/2024	36
16.1 Lesson learnt from carnot cycle	36
16.2 Entropy	36
17 Lecture 17 10/10/2024	37
17.1 Entropy	37
17.2 Second Law of Themodynamics	37
18 Lecture 18 10/10/2024	38
18.1 Special Forms of Second Law of Thermodynamics	38
18.2 Moist Processes	38
18.3 Relative humidity	38
18.4 Dew point temperature	39
18.5 Latent heat	39
19 Lecture 19 21/10/2024	40
19.1 The Clausius-Clapeyron equation	40
20 Lecture 20 23/10/2024	41
20.1 Saturation mixing ratio	41
21 Lecture 21 24/10/2024	42
21.1 Lifting Conduction Level (LCL)	42
22 Lecture 22 25/10/2024	43
22.1 Saturation Adiabatic Lapse Rate	43
22.2 Equivalent Potential Temperature	43
23 Lecture 23 30/10/2024	44
23.1 Psychrometer	44
23.2 Normand's rule	44

	List of Figures
24 Lecture 24 04/11/2024	45
24.1. Adiabatic cloud water content	45
24.2. Flow over terrain	45
24.3. Atmospheric stability	45
25 Lecture 25 06/11/2024	46
25.1. Atmospheric stability	46
25.2. Equation of motion for the parcel	46
26 Lecture 26 07/11/2024	47
26.1. Stability analysis	47
26.2. Convective instability or Potential instability .	48
27 Lecture 27 08/11/2024	49
27.1. Convective Available Potential Energy (CAPE) and Convective Inhibition (CIN)	49
28 Lecture 28 11/11/2024	50
28.1. Clasitus-Clapeyron Equation	50
28.2. Weigner-Bergeron-Findeisn Theory	50
29 Lecture 29 13/11/2024	51
29.1. Classifiacion of clouds	51
29.2. Types of particles within the clouds	51
29.3. Nucleation	51
30 Lecture 30 14/11/2024	53
30.1. Supersaturation with respect to plane surface of pure water	53
30.2. Köhler Equation	53
1 Reversible and Irreversible Process	4
2 Plot of V vs. θ	7
3 Diagram illustrating different thermodynamic processes in a P - V diagram.	8
4 Carnot Cycle	29
5 Isothermal lines in Skew-T diagram	31
6 Isobaric lines in Skew-T diagram	31
7 Dry-adiabat lines in Skew-T diagram	31
8 Moist-adiabat lines in Skew-T diagram	31
9 Mixing ratio lines in Skew-T diagram	32
10 Skew-T diagram	33
11 Internal Structure of cyclone	34
12 Air circulation in cyclone	34
13 Saturated state	38
14 Sub-Saturated state	38
15 Super-Saturated state	38
16 Saturation Vapor Pressure e_s vs Temperature T	39
17 Psychrometer	44
18 Skew-T diagram with Isobars, Dry and Moist Adiabat	44
19 Skew-T diagram with Isobars, Dry and Moist Adiabat	45
20 Case 1: $\Gamma_B > \Gamma_{dA}$	47
21 Case 2: $\Gamma_B < \Gamma_{dA}$	47
22 Case 3: $\Gamma_B = \Gamma_{dA}$	48
23 Solution of Question 27.1	49

1. Lecture 1 09/08/2024

- System: Specific chunk of matter we are interested in.
- Surrounding: Everything else in the universe outside of the system.
- Air parcel: System with the following assumptions:
 - Properties within the air parcel are uniform.
 - Boundaries are closed, so that matter/mass is not exchanged with the surroundings.

Question 1.1: How do system interact with surrounding?


- Matter
- Radiation

Question 1.2: Classify system on the basis of how matter interact with surround?

⇒ We can classify system into 3 types on the basis of how matter in system interact with it's surrounding:


- Open
- Closed
- Isolated

Question 1.3: How do we characterize a system?



1.1 Equilibrium State

Equilibrium: No change in the system if the surrounding doesn't change.



1.2 Transformation





Figure 1. Reversible and Irreversible Process

1.3 Exact and Inexact differentiable

Let z be a function of x and y , exact differentiable equation:

$$dz = \left(\frac{\partial z}{\partial x} \right) dx + \left(\frac{\partial z}{\partial y} \right) dy \quad (1)$$

$$dz = \int_i^f \delta z = z(x_f, y_f) - z(x_i, y_i) \quad (2)$$

$\therefore dT, dP, dV$ are exact differentiable.

$\delta Q, \delta W$ are inexact differentiable.

line integral:

$$\oint \delta z = 0$$

→ z is stable variable and it is exact differentiable iff it's reversible

$$\therefore \oint dT = 0, \oint dP = 0, \oint dq \neq 0, \oint dw \neq 0$$

1.4 Extensive and Intrincive variables

- **Entrisive:** Depends on size of system. E.g. Volume.
- **Intrincive:** Independent of size of system. E.g. Temperature.

Any variable divided by mass gives intrincive.

For e.g. specific volume (α) = $\frac{volume}{mass}$.


Similiarly,

$$p = \frac{P}{m}, q = \frac{Q}{m}, w = \frac{W}{m}$$

1.5 Laws of Thermodynamics

1. 0th law of thermodynamics:

Temperature → Quantity that determines the direction of heat flow. If two objects are in thermal contact and there is no net heat transfer, then the system is said to be in **thermal equilibrium**.



2. Lecture 2 14/08/2024

Bulk properties → microscopic properties → which can be linked to microscopic properties

For e.g. P is exerted due to random motion and collision of molecules with each other and on the walls of container.

2.1 Kinetic molecular theory of gases

Conditions:

- Molecules are in **random motion**.
- Collisions between molecules with each other and wall of container are **elastic** in nature ensuring **no K.E. loss**.

Derivation of av. K.E.

Particles travel distance equal to length of box (L) with velocity V_x, V_y and V_z .

Force exerted by the molecules on the face:

$$F = \frac{\Delta P}{\Delta t} = \frac{\Delta mv}{\Delta t} = m \frac{\Delta v}{\Delta t} \quad (3)$$

Change in velocity

$$\Delta v_x = v_x - (-v_x) = 2v_x \quad (4)$$

$$\Delta v_y = 0 \quad (5)$$

$$\Delta v_z = 0 \quad (6)$$

$$\Rightarrow \Delta V = 2v_x \quad (7)$$

$$\therefore F = \frac{m(2v_x)}{\Delta t} \quad (8)$$

We also have,

$$\Delta t = \frac{2L}{v_x} \quad (9)$$

from Eq. (8) and Eq. (9), we get:

$$F = \frac{m(2v_x^2)}{2L} = \frac{mv_x^2}{L} \quad (10)$$

For N number of molecules and average velocity of all molecules moving in x -direction \bar{v}_x

$$\therefore F = \frac{Nm(\bar{v}_x^2)}{L} \quad (11)$$

Pressure (P) exerted on walls of container:

$$P = \frac{F}{A} = \frac{Nm(\bar{v}_x^2)}{L \times L^2} = \frac{Nm(\bar{v}_x^2)}{V} \quad (12)$$

$$\Rightarrow PV = Nm(\bar{v}_x^2) \quad (13)$$

When we consider the velocity of molecules in all directions (v_{tot}).

$$v_{tot}^2 = \bar{v}_x^2 + \bar{v}_y^2 + \bar{v}_z^2 \quad (14)$$

$$\Rightarrow \bar{v}_{tot}^2 = 3\bar{v}_x^2 \quad (15)$$

\therefore The Pressure(P) becomes:

$$PV = \frac{1}{3}Nm\bar{v}_{tot}^2 \quad (16)$$

$$3PV = Nm\bar{v}_{tot}^2 \quad (17)$$

$$\frac{3}{2}PV = \frac{1}{2}Nm\bar{v}_{tot}^2 \quad (18)$$

$$\frac{3}{2}PV = N \times \left(\frac{1}{2}m\bar{v}_{tot}^2 \right) \quad (19)$$

$$\Rightarrow \frac{3}{2}PV = N \times (K.E.)_{av} \quad (20)$$

$$(21)$$

Using Ideal gas equation : $PV = Nk_B T$, where k_B is boltzmann constant

$$\frac{3}{2}(Nk_B T) = N \times (K.E.)_{av} \quad (22)$$

$$\Rightarrow (K.E.)_{av} = \frac{3}{2}k_B T \quad (23)$$

2.2 Ideal gas

- Molecules are in random motion.
- During the motion of **molecules do not exert force, except when they collide with each other or the walls of container**. This can also be stated as there is **no force of attraction between molecules**.
- The collisions between molecules are **elastic**.
- Sum of the volume of molecules is negligible** compared to volume of container.

2.3 Early experiments and laws

First Law of Gay-Lussac

Increase of volume of an ideal gas at **constant pressure** is proportional to increase in temperature and also to the volume occupied by the gas at $0^\circ C$

$$dV \propto V_0 d\theta \quad (24)$$

$$dV = \alpha V_0 d\theta \quad (25)$$

where α is volume coefficient of thermal expansion.

$$\alpha = \frac{1}{d\theta} \frac{dV}{V_0} = \frac{1}{273} \quad (26)$$


$$\int_{V_0}^V dV = \int_{0^\circ C}^\theta \alpha V_0 d\theta \quad (27)$$

$$V - V_0 = \alpha V_0 (\theta - 0^\circ C) \quad (28)$$

$$\Rightarrow V = (1 + \alpha\theta)V_0 \quad (29)$$

2nd Law of Gay-Lussac

An Ideal gas kept at constant volume, then the increase in pressure is proportional to increase in temperature and pressure at $0^\circ C$.

**Figure 2.** Plot of V vs. θ

$$dP \propto P_0 d\theta \quad (30)$$

$$dP = \beta P_0 d\theta \quad (31)$$

where β is pressure coefficient of thermal expansion.

$$\beta = \frac{1}{d\theta} \frac{dP}{P_0} = \frac{1}{273} \quad (32)$$

$$\int_{P_0}^P dP = \int_{0^\circ C}^\theta \beta P_0 d\theta \quad (33)$$

$$P - V_0 = \beta P_0 (\theta - 0^\circ C) \quad (34)$$

$$\Rightarrow P = (1 + \beta\theta)P_0 \quad (35)$$

3. Lecture 3 16/08/2024

Question 3.1: Why do we need Kinetic theory of gases?

⇒ Kinetic theory of gases connects microscopic properties to macroscopic properties of gases.

From similarity of triangle;


$$\frac{BC}{AB} = \frac{B'C'}{AB'}$$

$$\frac{P}{T} = \frac{P'}{T'}$$

$$\frac{P}{P'} = \frac{T}{T'}$$

for V is Constant

3.1 Another form of Gay-Lussac's Law



From similarity of triangle;


$$\frac{BC}{AB} = \frac{B'C'}{AB'}$$

$$\frac{V}{T} = \frac{V'}{T'}$$

$$\frac{V}{V'} = \frac{T}{T'}$$

for P is Constant

Similarly for Pressure at constant Volume



3.2 Boyle's Law

Boyle's Law states that, at constant temperature, the pressure of a given amount of gas is inversely proportional to its volume. Mathematically, it is expressed as:

$$P \propto \frac{1}{V} \quad (36)$$

$$PV = P'V' \quad (37)$$

$$PV = \text{const.} \quad (38)$$

where P is the pressure of the gas, and V is its volume. This implies that if the volume of a gas increases, its pressure decreases, and vice versa, as long as the temperature and the amount of gas remain constant.

3.3 Avagadro's Law

Avogadro's Law states that, at the same temperature and pressure, equal volumes of all gases contain the same number of molecules. Mathematically, it is expressed as:

$$V \propto n \quad (39)$$

where V is the volume of the gas, and n is the number of moles of the gas. This implies that the volume of a gas is directly proportional to the number of moles, provided temperature and pressure are constant.

For one mole of gas contains $6.023 \times 10^{23} \text{ mol}^{-1}$ of particles.

3.4 Ideal gas Law

System defined by (P, V, T) undergo change shown in following Fig.3




Figure 3. Diagram illustrating different thermodynamic processes in a P - V diagram.

Apply Gay-Lussac law (1) → (2):

$$P_1 = P \frac{T'}{T} \quad (40)$$

Apply Boyle's law (2) → (3):

$$P'V' = P_1 V$$

from eq.40 we get

$$P'V' = \left(\frac{PT'}{T} \right) V$$

after rearranging we get:

$$\frac{P'V'}{T'} = \frac{PV}{T}$$

$$\frac{PV}{T} = \text{const}$$

$$PV = AT$$

where $A = nR^*$

R^* is universal gas constant ($8.314 \text{ J K}^{-1} \text{ mol}^{-1}$)

$$\Rightarrow PV = nR^*T \quad (41)$$

3.5 Van Der Waal's equation

$$\left[P + a \left(\frac{n}{V} \right)^2 \right] \left[V - (nb) \right] = nR^*T \quad (42)$$

Where

a = coeff. which characterises the intermolecular forces = $1.35 \times 10^5 \text{ J m}^3 \text{ K}^{-1} \text{ mol}^{-2}$

b = coeff. which accounts for effective volume occupied by molecules = $3.64 \times 10^{-2} \text{ m}^3 \text{ K}^{-1} \text{ mol}^{-1}$

When $nb \rightarrow 0$ or $\frac{n}{V} \rightarrow 0$ Van Der Waal equation → Ideal gas equation.

3.6 Meteorological form of Ideal gas

Let there be n -kilomols particles/molecules of gas.

Therefore the combination of i^{th} component of the gas can be given by:

$$n = \sum_{i=1}^k n_i \quad (43)$$

The total mass of sample in kg:

$$M = \sum_{i=1}^k n_i m_i \quad (44)$$

where m_i represents molar mass of i^{th} particle/molecule in a sample.

Using Ideal gas equation:

$$PV = nR^*T \quad (45)$$

$$\frac{PV}{M} = \frac{nR^*T}{M} \quad (46)$$

$$P\alpha = \frac{n}{M} R^* T \quad (47)$$

since $\frac{V}{M} = \alpha$, and called specific volume.

$$P\alpha = \frac{\sum_{i=1}^k n_i}{\sum_{i=1}^k n_i m_i} R^* T \quad (48)$$

$$P\alpha = \frac{R^* T}{\bar{m}} \quad (49)$$

$$\Rightarrow P\alpha = R_d T \quad (50)$$

where \bar{m} is mean molar mass and given by $\frac{\sum_{i=1}^k n_i m_i}{\sum_{i=1}^k n_i}$ and $R_d = \frac{R^*}{\bar{m}}$ and unit $\text{JKg}^{-1} \text{K}^{-1}$

Since we know $\alpha = \frac{1}{\rho}$, where ρ is density of gas.

$$P\alpha = R_d T \quad (51)$$

$$\Rightarrow P = \rho R_d T \quad (52)$$

Question 3.2: what is R_d ?

$\Rightarrow R_d \rightarrow$ is a specific gas constant where d stands for dry air and this constant is not universal, varies with time and conditons over a particular place.

$$R_d = \frac{R^*}{\bar{m}}$$

and unit $\text{JKg}^{-1} \text{K}^{-1}$

3.7 Composition of Earth's Atmosphere

Gas	Fraction/Volume	Molecular Mass
N_2	78.1%	28.01
O_2	20.9%	31.999
Ar	0.93%	39.9

Table 1. Composition of Earth's Atmosphere.

We haven't take water vaours($H_2O(v)$), Carbon diaoxide(CO_2) and Ozone(O_3) becasue these gaes are highly variable w.r.t time and geography.

Question 3.3: Find R_d for Earth Atmosphere?

$$\begin{aligned} \Rightarrow R_d &= \frac{R^*}{\bar{m}} \\ &= \frac{8.314 \times 10^3}{28.96} \\ &= 0.287085 \\ &= 287.085 \text{ J kg}^{-1} \text{ K}^{-1} \end{aligned}$$

4. Lecture 4 19/08/2024

$CO_2 \rightarrow$ radiation trapping process \rightarrow absorb radiation in IR region of spectrum.

Question 4.1:

- Determine the gas constant for the atmosphere of Venus which consists of 95% CO_2 and 5% N_2 by volume.
- The mean surface temperature of Venus is 740K as compared to 288K surface temperature of Earth. The surface pressure on Venus is 90 times that on Earth. By what factor the density of near surface Venus atmosphere is greater than the Earth?

\Rightarrow Solution:

- Mean molar mass of gases of atmosphere of Venus:

$$\bar{m} = \frac{\sum_{i=1}^k n_i m_i}{\sum_{i=1}^k n_i}$$

$$\bar{m} = 0.95 \times 46 + 0.05 \times 28$$

$$\bar{m} = 43.2$$

Calculate Specific Molar const. (R_V) for Venus:

$$R_V = \frac{R^*}{\bar{m}}$$

$$\Rightarrow R_V \approx 192 \text{ } JK^{-1} \text{ } Kg^{-1}$$

- Surface Temperature of Venus = $T_V = 740K$
Surface Temperature of Earth = $T_V = 740K$
Surface Pressure of Earth = P_E
Surface Pressure of Venus = $P_V = 90 \times P_E$

$$P_V = \rho_V R_V T_V$$

$$P_E = \rho_E R_E T_E$$

$$\frac{P_V}{P_E} = \frac{\rho_V R_V T_V}{\rho_E R_E T_E}$$

$$90 = \frac{\rho_V}{\rho_E} * \frac{192}{287} * \frac{740}{288}$$

$$\frac{\rho_V}{\rho_E} = 52.36$$

Venus's atmosphere is 52.36 times denser than Earth's atmosphere.

$$\Rightarrow \rho_E = 1.23 \text{ } kgm^{-3} \text{ and } \rho_V = 65.97 \text{ } kgm^{-3}$$

Question 4.2: Why CO_2 have radiation trapping affinity but not gases like N_2 ?

$\Rightarrow CO_2$ has radiation trapping affinity because its molecular structure allows it to absorb and re-emit IR radiation, contributing to the greenhouse effect. This is due to its vibrational modes that change the molecule's dipole moment. In contrast, N_2 , with its symmetric diatomic structure, cannot absorb infrared radiation effectively, as its vibrations do not change the dipole moment, making it non-contributory to the greenhouse effect.

4.1 Pressure

Units of Pressure

Pressure are usually expressed in the following units:

$$1 \text{ bar} = 1.013 \times 10^5 \text{ Pa}$$

$$10^5 \text{ Pa} = 1000 \text{ hPa} = 1000 \text{ mbar}$$

Question 4.3: Why does ozone layer depletion happen primarily over the South Pole in Antarctica?

\Rightarrow Ozone layer depletion happens primarily over the South Pole because of the following reasons:

- Polar Stratospheric Clouds (PSCs):** During the Antarctic winter, temperatures drop below $-75^\circ C$, leading to the formation of PSCs. These clouds facilitate chemical reactions that convert inactive chlorine compounds into reactive forms, which destroy ozone.
- Isolation of the Polar Vortex:** The strong polar vortex over Antarctica isolates air, keeping temperatures low and trapping ozone-depleting chemicals within the vortex.
- Sunlight and Ozone Destruction:** In Antarctic spring, returning sunlight provides energy for reactions between chlorine radicals and ozone, leading to significant ozone depletion and the formation of the "ozone hole."
- Comparison with the Arctic:** The Arctic has a weaker and less stable polar vortex, resulting in less dramatic ozone depletion compared to Antarctica.

4.2 Mass of the Atmosphere

At any point in the atmosphere, atmosphere above will exert a downward force due to gravitational force

$$F = \rho g \quad (53)$$

$$F = \int_0^{\infty} \rho g dz \quad (54)$$

We know $P = \text{Force}/(\text{unit area})$, assuming gravity g_0 remain constant, we get:

$$\Rightarrow P_s = g_0 \int_0^\infty pdz \quad (55)$$

where P_s is vertically integrated and have unit kgm^{-2}

Question 4.4: Globally average surface pressure of earth is 985hpa. Estimate mass of atmosphere.

\Rightarrow Given $985\text{hpa} = 985 \times 10^2 \text{Pa}$

surface area(sa) = $4\pi r^2$

where r is radius of earth = 6400km

we know, pressure(p) = $\frac{\text{force}}{\text{sa}}$

$$p = \frac{mg}{4\pi r^2}$$

$$986 \times 10^2 = \frac{m \times 9.81}{4 \times \pi \times (6400 \times 10^3)^2}$$

$$m = 5.168172908 \times 10^{18} \text{kg}$$

\therefore The approximate mass of atmosphere is equal to 5.1708×10^{15}

Question 4.5: The average atmospheric pressure on surface of Mars is 6hPa and raduis 3400km. Find mass of Mars.

\Rightarrow Given Surface pressure of Mars $P = 6\text{hPa} = 6 \times 10^2 \text{pa}$

Radius of Mars $R = 3400\text{km} = 3.4 \times 10^6 \text{m}$

surface area(sa) = $4\pi r^2$

where r is radius of earth.

we know, pressure(p) = $\frac{\text{force}}{\text{sa}}$

$$p = \frac{mg}{4\pi r^2}$$

$$986 \times 10^2 = \frac{m \times 9.81}{4 \times \pi \times (6400 \times 10^3)^2}$$


$$m = 5.168172908 \times 10^{18} \text{kg}$$

\therefore The approximate mass of atmosphere is equal to $5.168172908 \times 10^{18} \text{kg}$

5. Lecture 5 21/08/2024

In previous lecture, We got equation for Ideal gas Eq.(52), which only deals with dry air.

We didn't incorporate moisture!



where P_v is vapour pressure and given by

$$P_v = \rho_v R_v T \quad (56)$$

$$R_v = \frac{R^*}{\bar{m}} = \frac{8.314 \times 10^3}{18.01} = 461.63 \text{ J K}^{-1} \text{ kg}^{-1} \quad (57)$$

Note: Water vapour is not same as moisture, mixture is mixture of air and water vapour

5.1 Dalton's law of partial pressure

Dalton's law of partial pressure states that total pressure exerted by the mixture of gas is equal to the sum of partial pressure exerted by individual constituent at a given temperature.

$$P = P_d + e \quad (58)$$

Where

P = Total pressure exerted by all gases in mixture

P_d = Pressure exerted by dry air

$e = P_v$ = Vapour pressure

Substituting Eq.(52) and Eq.(56) in Eq.(58), we get:

$$P = \rho_d R_d T + \rho_v R_v T \quad (59)$$

$$P = (\rho_d R_d + \rho_v R_v) T \quad (60)$$

5.2 Humidity

We define humidity using following parameters:

1. Mixing ratio:

$$\omega = \frac{\text{Mass of water vapour}}{\text{Mass of dry air}} = \frac{M_v}{M_d} \quad (61)$$

$$= \frac{\text{Density of water vapour}}{\text{Density of dry air}} = \frac{\rho_v}{\rho_d} \quad (62)$$

Unit of mixing ratio is g/Kg

2. Specific humidity:

$$\omega = \frac{\text{Mass of water vapour}}{\text{Mass of dry air} + \text{Mass of water vapour}} \quad (63)$$

$$= \frac{M_v}{M_d} \quad (64)$$

$$= \frac{\text{Density of water vapour}}{\text{Density of dry air} + \text{Density of water vapour}} \quad (65)$$

$$= \frac{\rho_v}{\rho_d + \rho_v} \quad (66)$$

$$= \frac{\rho_v}{\rho} \quad (67)$$

$w \approx q$, \because mass of water vapour \ll mass of dry air

$$\omega = \frac{\rho_v}{\rho_d} \quad (68)$$

$$= \frac{e/R_v T}{P_d/R_d T} \quad (69)$$

$$= \frac{e\varepsilon}{P_d} \quad (70)$$

$$= \frac{e\varepsilon}{P - e} \quad (71)$$

$$\approx \frac{e\varepsilon}{P} \quad (72)$$

where $\varepsilon = \frac{R_d}{R_v} = 0.621$
Similiarly,

$$\begin{aligned} q &= \frac{\rho_v}{\rho_v + \rho_d} \\ &= \frac{e\varepsilon}{P - (1 - \varepsilon)e} \\ &\approx \frac{e\varepsilon}{P} \\ q &\approx w \end{aligned}$$

5.3 Ideal gas equation for moist gas

Total pressure

$$\begin{aligned} P &= P_d + e \\ &= \rho_d R_d T + \rho_v R_v T \\ &= \rho_d R_d T \left[1 + \frac{\rho_v R_v}{\rho_d R_d} \right] \\ &= \rho_d R_d T \left[1 + \frac{\rho_v}{\rho_d} \cdot \frac{R_v}{R_d} \right] \\ &= \rho_d R_d T \left[1 + \frac{\rho_v}{\rho_d} \cdot \frac{1}{\varepsilon} \right] \\ &= \rho_d R_d T \left[1 - \left(1 - \frac{1}{\varepsilon} \right) \frac{\rho_v}{\rho} \right] \end{aligned}$$


$$\therefore P = \rho_d R_d T \left[1 - \left(1 - \frac{1}{\varepsilon} \right) \cdot q \right] \quad (73)$$

Virtual Temperature

$$\Rightarrow T_v = \frac{P}{\rho_d R_d} = T \left[1 - \left(1 - \frac{1}{\varepsilon} \right) \cdot q \right] \quad (74)$$

Therefore from Eq.(73) and Eq.(74), we get:

$$P = \rho_d R_d T_v \quad (75)$$



$\rho_d > \rho_m \xrightarrow{\Delta} \rho_d = \rho_m$, where Δ represents heat.

Question 5.1: On a summer day the AC breaks down and the air in the classroom becomes warm and muggy with a vapour pressure of 20 hPa and a temperature of 25°C.

- a. If the volume of the classroom is $40m^3$. How much water is present in the room in vapour form?
- b. If pressure of the room is 900hPa then what is virtual temerature of the air?

\Rightarrow a. We have,

$$\begin{aligned} P_v &= \rho_v R_v T \\ 20 \times 10^2 &= \rho_v \times 461.62 \times 298 \\ \rho_v &= 0.0145 \text{ kg/m}^3 \\ \frac{m}{V} &= 0.0145 \\ \frac{m}{40} &= 0.0145 \\ m &\approx 0.58149 \text{ kg} \end{aligned}$$

\therefore Amount of water vapour in room is 0.58148976 kg.

\Rightarrow b. Given, $P = 900 \text{ hPa} = 90000 \text{ Pa}$

Let T_v be the virtual temperature. We know:

$$T_v = T \left(1 + 0.61 \frac{P_v}{P} \right)$$

Substituting the values:

$$T_v = 298 \left(1 + 0.61 \times \frac{2000}{90000} \right)$$

$$T_v = 298 \times 1.01356$$

$$T_v \approx 302.04 \text{ K}$$

\therefore The virtual temperature of the air is approximately 302.04 K.

6. Lecture 6 28/08/2024


6.1 Archimedes Principle

Archimedes' principle states that any object completely or partially submerged in a fluid (liquid or gas) is buoyed up by a force equal to the weight of the fluid that the object displaces.

Upward force exerted by the fluid = weight of the fluid displaced by the object

6.2 Buoyancy

Buoyancy is the upward force exerted by a fluid (liquid or gas) that opposes the weight of an object submerged in it.



Net force acting on mass(M) and density(ρ) submerged in fluid of density(ρ') is given by:

$$F_B = \rho'Vg - Mg \quad (76)$$

$$= \rho'Vg - \rho Vg \quad (77)$$

$$= (\rho' - \rho)Vg \quad (78)$$

Dividing equation with M on both side,

$$\frac{F_B}{M} = \frac{(\rho' - \rho)Vg}{M} \quad (79)$$

$$f_B = \frac{(\rho' - \rho)Vg}{\rho V} \quad (80)$$

$$= \left(\frac{\rho'}{\rho} - 1 \right) g \quad (81)$$

If Buoyant force per unit mass (f_B),

$$f_B > 0 \rightarrow \text{upward force}$$

$$f_B < 0 \rightarrow \text{downward force}$$

We don't measure density in real case scenario, so we need to convert the equation in the useful form.

Assume pressure inside air parcel and surrounding equal and process to be reversible.

Using Ideal gas equation,

$$P = \rho R_d T_v \quad (82)$$

$$P = \rho' R_d T'_v \quad (83)$$

Substituting equation Eq.(82) & (83) in Eq.(81), we get:

$$f_B = \frac{\left(\frac{P}{R_d T'_v} - \frac{P}{R_d T_v} \right)}{\frac{P}{R_d T'_v}} g \quad (84)$$

$$\Rightarrow f_B = \frac{(T_v - T'_v)}{T'_v} g \quad (85)$$

where T_v and T'_v are virtual temperature of of parcel and fluid respectively.

$$f_B > 0 \rightarrow T_v > T'_v \rightarrow \text{upward force}$$

$$f_B < 0 \rightarrow T_v < T'_v \rightarrow \text{downward force}$$

$$f_B = 0 \rightarrow T_v = T'_v \rightarrow \text{no net force}$$

Question 6.1: A parcel of air has a temperature of 29°C and specific humidity of 24g/kg . It is embedded in the environment having temperature of 30°C and specific humidity of 5g/kg

a. What is vertical acceleration?

b. If there are no forces acting on it, how long would take for the parcel to raise 10m from starting position?

\Rightarrow a. Given $T_{v,a} = 29^\circ\text{C} = 302\text{K}$ and $T_{v,s} = 30^\circ\text{C} = 303\text{K}$,

$$q_a = R.H._a = 24\text{g/kg},$$

$$q_s = R.H._s = 5\text{g/kg},$$

We know,

$$\begin{aligned} T_{v,a} &= T_a(1 + 0.61q_a) \\ &= 302(1 + 0.61 \times 24 \times 10^{-3}) \\ &= 306.42128\text{K} \end{aligned}$$

$$\begin{aligned} T_{v,s} &= T_s(1 + 0.61q_s) \\ &= 303(1 + 0.61 \times 5 \times 10^{-3}) \\ &= 303.92415\text{K} \end{aligned}$$

Buoyant force per unit mass f_B ,

$$\begin{aligned} f_B &= \left(\frac{T_{v,a} - T_{v,s}}{T_{v,s}} \right) g \\ &= \left(\frac{306.42128 - 303.92415}{303.92415} \right) \times 9.81 \\ &= 0.0806\text{m/s}^2 \end{aligned}$$

\therefore Vertical acceleration due to buoyant force is 0.0806m/s^2 .

\Rightarrow b. Given Height $h = 10\text{m}$,

Vertical acceleration $a = f_B = 0.0806\text{m/s}^2$

Using equation of motion:


$$s = \frac{1}{2}at^2$$

$$10 = \frac{1}{2} \times 0.0806 \times t^2$$

$$t = 15.7524\text{s}$$

\therefore Time taken by parcel to raise 10m due to buoyant force is 15.75 seconds.

6.3 Hydrostatic equation



1. The downward force due to gravity:

$$F_g = mg = \rho(A\delta z)g \quad (86)$$

2. The upward force due to atmosphere force acting on the bottom of the slab is given by:

$$F_{up} = Ap(z) \quad (87)$$

3. The downward force acting on parcel:

$$F_{down} = Ap(z + dz) \quad (88)$$

\therefore Net upward force will be given by Eq.(90)

$$F = F_{up} - F_{down} - F_g \quad (89)$$

$$= Ap(z) - Ap(z + dz) - \rho(A\delta z)g \quad (90)$$

Hence, Upward acceleration will be:

$$a = \frac{F}{\rho A \delta z} \quad (91)$$

$$= \frac{Ap(z) - Ap(z + \delta z) - (A\delta z)\rho g}{\rho A \delta z} \quad (92)$$

$$= -\frac{1}{\rho} \left[\frac{p(z + \delta z) - p(z)}{\delta z} \right] - g \quad (93)$$

Taking $\lim_{\delta z \rightarrow 0}$

$$\Rightarrow a + g = -\frac{1}{\rho} \frac{dp}{dz} \quad (94)$$

Eq.(94) is called Hydrostatic equation.

Question 6.2: Velocity of hyricene is 10m/s and time taken 10min find acceleration.

$$\Rightarrow \text{Acceleration } a = \frac{v}{t} = \frac{10}{10 \times 60} = \frac{10}{600} \approx 0.0167$$

From the above example question 6.2 we can infer that $a + g \approx g$,

\therefore we can rewrite Hydrostatic equation as following Eq.(95):

$$\Rightarrow g = -\frac{1}{\rho} \frac{dp}{dz} \quad (95)$$

This is called **Hydrostatic approximation**.

7. Lecture 7 29/08/2024

7.1 Ideal gas equation with Hydrostatic equation

From Ideal gas equation:

$$P = \rho R_d T_v \quad (96)$$

$$\rho = \frac{P}{R_d T_v} \quad (97)$$

Substitute ρ in hydrostatic Eq.(95), we get:

$$g = -\frac{R_d T_v}{P} \frac{\partial P}{\partial z} \quad (98)$$

$$\frac{\partial P}{\partial z} = -\frac{P}{R_d T_v} g \quad (99)$$

$$\frac{1}{P} \frac{\partial P}{\partial z} = -\frac{g}{R_d T_v} \quad (100)$$

$$\frac{\partial \ln P}{\partial z} = -\frac{g}{R_d T_v} \quad (101)$$

The rate of change of logarithm of pressure is Inversely proportional to temperature and does not depend on pressure.

7.2 Geopotential

Geopotential at any point in the atmosphere is defined as the work done against the gravitational field to raise a mass of 1kg from sea level to that point,

Represented by Eq.(102) and has unit $J kg^{-1}$

$$d\phi = gdz \quad (102)$$

From hydrostatic equation Eq.(94),

$$dp = -\rho g dz \quad (103)$$

$$gdz = -\frac{1}{\rho} dp \quad (104)$$

$$gdz = -\alpha dp \quad (105)$$

where α is specific volume.

Integrating Eq.(102), we get:

$$\int_0^{\phi(z)} d\phi = \int_0^z gdz \quad (106)$$

$$\phi(z) = \int_0^z gdz \quad (107)$$

Let g_0 be acceleration due to gravity averaged over the surface.

$$\frac{\phi(z)}{g_0} = \int_0^z \frac{g}{g_0} dz \quad (108)$$

$$\Rightarrow Z = \frac{\phi(z)}{g_0} \quad (109)$$

The Z in Eq.(109) is called Geopotential height.

z (km)	Z (km)	g (m/s²)
0	0	9.81
1	1	9.80
10	9.99	9.77
100	98.87	9.50
500	46.36	8.43

Table 2. Deviation of values of g for Geometric Height(z), Geopotential Height(Z)

$$d\phi = gdz = -\alpha dp \quad (113)$$

$$d\phi = -\frac{R_d T_v}{p} dp \quad (114)$$

Integrating from both sides, we get:

$$\int_{\phi_1}^{\phi_2} d\phi = \int_{P_1}^{P_2} -\frac{R_d T_v}{p} dp \quad (115)$$

$$\phi_2 - \phi_1 = -R_d \int_{P_1}^{P_2} T_v \frac{dp}{p} \quad (116)$$

Dividing both side with g_0 , we get:

$$\frac{(\phi_2 - \phi_1)}{g_0} = -\frac{R_d}{g_0} \int_{P_1}^{P_2} T_v \frac{dp}{p} \quad (117)$$

$$(Z_2 - Z_1) = -\frac{R_d}{g_0} \int_{P_1}^{P_2} T_v \frac{dp}{p} \quad (118)$$

By assuming isothermal atmosphere

$$(Z_2 - Z_1) = -\frac{R_d}{g_0} \int_{P_1}^{P_2} \bar{T}_v \frac{dp}{p} \quad (119)$$

$$(Z_2 - Z_1) = -\frac{R_d}{g_0} \bar{T}_v \ln\left(\frac{dp}{p}\right) \quad (120)$$

$$\Rightarrow (Z_2 - Z_1) = -H \ln\left(\frac{dp}{p}\right) \quad (121)$$

Where \bar{T}_v is average temperature of atmosphere taken over geopotential (ϕ_1 & ϕ_2) and H is scale height given by Eq.(122):

$$H = \frac{R_d T_v}{g_0} \quad (122)$$

Scale height H is defined as height at which the pressure reduces to $1/e$ times the surface pressure. It is around 7.8km for Earth's atmosphere.

Eq.(121) is called Hypsometric equation.

Simplifying Eq.(121), we get:

$$P_2 = P_1 e^{-\frac{(Z_2 - Z_1)}{H}} \quad (123)$$

$$\Rightarrow P = P_0 e^{-\frac{(Z_2 - Z_1)}{H}} \quad (124)$$

$$p = \rho R_d T_v \quad (110)$$

$$p\alpha = R_d T_v \quad (111)$$

$$\alpha = \frac{R_d T_v}{p} \quad (112)$$

Question 7.1:

⇒ Solution,

$$\begin{aligned}(Z_2 - Z_1) &= -\frac{R_d}{g_0} \bar{T}_v \ln \left(\frac{dp}{p} \right) \\&= -\frac{287 \times 255}{9.81} \ln \frac{P_2}{P_1} \\&= -7.4 \ln \frac{P_2}{P_1}\end{aligned}$$

8. Lecture 8 30/08/2024

Question 8.1: On May 20, 2020 tropical cyclone Ampan of centre pressure at ocean surface dropped to 920hPa . The surrounding region away from influence of centre of cyclone had mean sea level pressure of 1010hPa . The height depression associated with centre of cyclone vanished at height of pressure level of 150hPa . If the mean virtual temperature of the surrounding between the surface at 150hPa was -10°C . What was the corresponding mean virtual temperature in the centre of storm?

⇒ Given data:

$$\begin{aligned} P_1 &= 1010\text{hPa} = 101000\text{Pa} \\ P_2 &= 920\text{hPa} = 92000\text{Pa} \\ P_3 &= 150\text{hPa} = 15000\text{Pa} \\ T_{v,surr} &= -10^\circ\text{C} = 263.15\text{K} \\ R_d &= 287\text{J/(kgK)} \\ g_0 &= 9.81\text{m/s}^2 \end{aligned}$$

⇒ Height difference calculation in the surrounding air:

$$\begin{aligned} (Z_2 - Z_1) &= \frac{R_d T_{v,surr}}{g_0} \ln \left(\frac{P_1}{P_3} \right) \\ &= \frac{287 \times 263.15}{9.81} \ln \left(\frac{101000}{15000} \right) \\ &= 7701.43 \times 1.906 \\ &= 14681.92 \text{m} \end{aligned}$$

⇒ Solution for mean virtual temperature at the center of the storm:

$$\begin{aligned} (Z_2 - Z_1) &= -\frac{R_d}{g_0} \bar{T}_{v,center} \ln \left(\frac{P_3}{P_2} \right) \\ 14681.92 &= -\frac{287}{9.81} \bar{T}_{v,center} \ln \left(\frac{15000}{92000} \right) \\ \bar{T}_{v,center} &= -\frac{14681.92 \times 9.81}{287 \ln \left(\frac{15000}{92000} \right)} \\ &= -\frac{14681.92 \times 9.81}{287 \times (-1.7749)} \\ &= \frac{144040.6}{-509.4613} \\ &= 282.72 \text{K} \end{aligned}$$

$$T_{v,center} \approx 282.72 - 273.15$$

$$T_{v,center} \approx 9.57^\circ\text{C}$$

Question 8.2: Calculate the thickness of layer between 1000hPa and 500hPa pressure surface.

- a. At point in tropics where T_v is 15°C
- b. At point in polar where T_v is -40°C

Solution ⇒ a.

$$\begin{aligned} (Z_2 - Z_1) &= -\frac{R_d}{g_0} \bar{T}_v \ln \left(\frac{dp}{p} \right) \\ &= \frac{287 \times 288\text{K}}{9.81\text{m/s}^2} \ln \frac{1000\text{hPa}}{500\text{hPa}} \\ &= 5840.2419\text{km} \end{aligned}$$

⇒ b.

$$\begin{aligned} (Z_2 - Z_1) &= -\frac{R_d}{g_0} \bar{T}_v \ln \left(\frac{dp}{p} \right) \\ &= \frac{287 \times 233\text{K}}{9.81\text{m/s}^2} \ln \frac{1000\text{hPa}}{500\text{hPa}} \\ &= 4724.9179\text{km} \end{aligned}$$

Pressure profiles in the idealized atmosphere

8.1 Constant density atmosphere

Assume atmosphere is at hydrostatic balance and density ρ to be constant.

$$dP = -\rho g dz \quad (125)$$

$$\int_{P(0)}^{P(z)} dP = - \int_0^z \rho g dz \quad (126)$$

$$p(z) - p(0) = -\rho g z \quad (127)$$

Substituting values in above equation, we obtain:

$$(0 - 101.3) = -1.23 \times 9.8 \times z \quad (128)$$

$$z \approx 8.3952\text{km} \quad (129)$$

Using Ideal gas equation, substitute P ,

$$d(\rho RT) = -\rho g dz \quad (130)$$

$$RdT = -gdz \quad (131)$$

$$dT = -\frac{g}{R} dz \quad (132)$$

$$T(z) - T(0) = \frac{g}{R}(z - 0) \quad (133)$$

$$T(z) = T(0) - \frac{g}{R} z \quad (134)$$

$$T(z) = T(0) - 0.0341z \quad (135)$$

$$T(z) = T(0) - 34.1z \quad (136)$$

where 34.1 constant have an unit of $^\circ\text{C}/\text{km}$

$$\Rightarrow \Gamma = -\frac{dT}{dz} = -\frac{g}{R} = -34.1^\circ\text{C}/\text{km} \quad (137)$$

This is Ideal/theoretical value, but **actual/practical value for Γ is $6.5^\circ/km$** because of phenomenon called **auto-convective lapse rate** i.e. ρ varies with altitude, and warm air and cold air do vertical circulation.

8.2 Constant temperature atmosphere

Assume atmosphere is at hydrostatic balance and Temperature T to be constant.

$$dP = -\rho g dz \quad (138)$$

$$d\rho RT = -\rho g dz \quad (139)$$

$$p(z) - p(0) = -\rho g dz \quad (140)$$

$$RT d\rho = -\rho g dz \quad (141)$$

$$\frac{d\rho}{\rho} = -\frac{g}{RT} dz \quad (142)$$

$$\ln \rho|_{\rho_1}^{\rho_2} = -\frac{g}{RT} z|_0^z \quad (143)$$

$$\Rightarrow \ln \frac{\rho_2}{\rho_1} = -\frac{g}{RT} z \quad (144)$$

8.3 Constant lapse rate atmosphere

$$T = T_0 - \Gamma_z \quad (145)$$

$$dP = -\rho g dz \quad (146)$$

$$\frac{dP}{dz} = -\frac{Pg}{RT} \quad (147)$$

$$\frac{dP}{dz} = -\frac{Pg}{R(T_0 - \Gamma_z)} \quad (148)$$

$$\frac{1}{P} dP = -\frac{gdz}{R(T_0 - \Gamma_z)} \quad (149)$$

$$\int_{P_1}^{P_2} \frac{1}{P} dP = -\frac{g}{R} \int_0^z \frac{dz}{(T_0 - \Gamma_z)} \quad (150)$$

$$\Rightarrow \ln \frac{P_2}{P_1} = -\frac{g}{R\Gamma_z} \ln \left(\frac{T_0 - \Gamma_z}{T_0} \right) \quad (151)$$

9. Lecture 9 04/09/2024

9.1 First Law of Thermodynamics and Application

Pressure-volume work

Work done δw by any force F to displace object with displacement ds is equal to:

$$\delta w = F \cdot ds \quad (152)$$



Incremental Work done by Force F to increase the volume will be given as follows:

$$\delta w = F \cdot ds \quad (153)$$

$$= PA \cdot ds \quad (154)$$

$$= PdV \quad (155)$$

Assuming Pressure P constant at each step, and process is slow, incremental, i.e, reversible.



10. Lecture 10 05/09/2024

10.1 First Law of Thermodynamics and Application

$$\Delta U = Q - W \quad (156)$$

Mechanical work


$$\delta w = F \cdot ds \quad (157)$$

Pressure-volume work

$$\delta w = PA \cdot ds \quad (158)$$

$$\delta w = PdV \quad (159)$$

$$w = \int_i^f PdV \quad (160)$$



$$w = \int_i^f PdV \quad (161)$$

$$w = \int_i^f PdV + \int_f^i PdV \quad (162)$$

$$w = \left[\int_i^f PdV \right]_1 - \left[\int_i^f PdV \right]_2 \quad (163)$$

$$w \neq 0 \quad (164)$$

$$\Rightarrow \oint_C w = \oint_C Pdv \neq 0 \quad (165)$$

$$w = \int_i^f PdV \quad (166)$$

$$w = \int_i^f PdV + \int_f^i PdV \quad (167)$$

$$w = \left[\int_i^f PdV \right]_1 - \left[\int_i^f PdV \right]_2 \quad (168)$$

$$w = 0 \quad (169)$$

$$\Rightarrow \oint_C w = \oint_C Pdv = 0 \quad (170)$$

$$\delta w = PAds \quad (171)$$

$$\delta w = F \cdot ds \quad (172)$$

$$\frac{\delta w}{dt} = m \frac{dv}{dt} \frac{ds}{dt} \quad (173)$$

$$\frac{\delta w}{dt} = mv \frac{dv}{dt} \quad (174)$$

$$\frac{\delta w}{dt} = \frac{d}{dt} \left(\frac{1}{2} mv^2 \right) \quad (175)$$

$$\Rightarrow \frac{\delta w}{dt} = \frac{d}{dt} (K.E.) \quad (176)$$

Formulation of First Law of thermodynamics

Case 1: Heating

$$\Delta U = Q$$


Case 2: By doing work

$$\Delta U = -W$$

From case 1 and 2 for we can write 1st law of thermodynamics as:

$$\Delta U = Q - W \quad (177)$$

$$\delta q = du + \delta w \quad (178)$$



In terms of Intensive parameters

$$\delta q = du + pd\alpha \quad (179)$$

1. Pressuer-volume wok done by a system = reduction in internal energy + heat supplied by the environment.

2. Pressuer-volume wok done on a system = increase in internal energy + heat transferred to the environment.

10.2 Heat capacity

$$\frac{\delta q}{dT} = C \quad (180)$$

Unit $Jk^{-1}Kg^{-1}$

Ideal gas equation:

$$P\alpha = R_d T$$

Case 1: Increase in volume (If pressure is kept constant → Isobaric process)

Case 2: Increase in pressure (If volume is kept constant → Isochoric process)

Case 3: Combination of above the both cases. (i.e. increase in both pressure and volume)

10.3 . Heat capacity at constant volume

From Eq.(0)

$$\delta q = du + pd\alpha \quad (181)$$

$$\delta q = du \quad (182)$$

$$\delta q = C_v dT \quad (183)$$

$$C_v = \left(\frac{\delta q}{dT} \right)_{\alpha=\text{cont}} \quad (184)$$

$$C_v = \left(\frac{du}{dT} \right)_{\alpha=\text{cont}} \quad (185)$$

$$\Rightarrow du = C_v dt \quad (186)$$

From Kinetic theory of gas

$$U = \frac{3}{2} P \alpha = \frac{3}{2} R_d T$$

For monoatomic gas:

$$C_v = \frac{du}{dt} = \frac{3}{2} R_d = 430.5 J k^{-1} kg^{-1}$$

For diatomic gas:

$$C_v = \frac{du}{dt} = \frac{5}{2} R_d = 718 J k^{-1} kg^{-1}$$

11. Lecture 11 06/09/2024

11.1 . Specific heat capacity

$$\text{Specific heat} = \frac{\delta q}{dT}$$

$$\delta q = du + \delta w \quad (187)$$

$$\delta q = du + pd\alpha \quad (188)$$

11.2 . Specific heat at constant volume

Volume(V) is constant, i.e., specific density(α) = constant

$$\therefore d\alpha = 0$$

$$\delta q = du + pd\alpha \quad (189)$$

$$\delta q = du \quad (190)$$

$$\delta q = C_v dT \quad (191)$$

$$C_v = \left(\frac{\delta q}{dT} \right)_{\alpha=\text{cont}} \quad (192)$$

$$C_v = \left(\frac{du}{dT} \right)_{\alpha=\text{cont}} \quad (193)$$

$$du = C_v dt \quad (194)$$

$$\delta q = du + pd\alpha \quad (201)$$

$$\delta q = du \quad (202)$$

$$\delta q = C_v dT \quad (203)$$

$$C_v = \left(\frac{\delta q}{dT} \right)_{\alpha=\text{cont}} \quad (204)$$

$$C_v = \left(\frac{du}{dT} \right)_{\alpha=\text{cont}} \quad (205)$$

$$du = C_v dt \quad (206)$$

From Eq.(0) and Eq.(200)

$$\delta q = C_v dT + R_d dT - \alpha dP \quad (207)$$

$$\delta q = (C_v + R_d) dT - \alpha dP \quad (208)$$

$$\Rightarrow \delta q = C_p dT - \alpha dP \quad (209)$$


$$C_p = \begin{cases} 717.5 \text{ J} \cdot \text{kg}^{-1} \cdot \text{K}^{-1} & \text{for monoatomic gas} \\ 1005 \text{ J} \cdot \text{kg}^{-1} \cdot \text{K}^{-1} & \text{for diatomic gas} \end{cases}$$

Hence,

$$\Rightarrow \delta q = C_v dt + Pd\alpha \quad (195)$$

$$C_v = \begin{cases} \frac{3}{2}R_d & \text{for monoatomic gas,} \\ \frac{5}{2}R_d & \text{for diatomic gas.} \end{cases}$$

Rotational K.E. is significant for diaatomic gas but not for monoatomic gas.



11.3 . Specific heat at constant pressure

Pressure(P) is constant $\therefore dP = 0$

From Ideal gas eqaution

$$P\alpha = R_d T \quad (196)$$

$$dP\alpha = Pd\alpha + \alpha dP \quad (197)$$

$$Pd\alpha + \alpha dP = d(R_d T) \quad (198)$$

$$Pd\alpha + \alpha dP = R_d dT \quad (199)$$

$$Pd\alpha = R_d dT - \alpha dP \quad (200)$$

$$\delta q = du + pd\alpha \quad (201)$$

$$\delta q = du \quad (202)$$

$$\delta q = C_v dT \quad (203)$$

$$C_v = \left(\frac{\delta q}{dT} \right)_{\alpha=\text{cont}} \quad (204)$$

$$C_v = \left(\frac{du}{dT} \right)_{\alpha=\text{cont}} \quad (205)$$

$$du = C_v dt \quad (206)$$

11.4 Special Forms of First Law of Thermodynamics

I. Isobaric process

$$\delta q = C_p dT \quad (210)$$

$$= \left(\frac{C_p}{C_v} \right) C_v dT \quad (211)$$

$$= \left(\frac{C_p}{C_v} \right) dU \quad (212)$$

$$= \gamma dU \quad (213)$$

II. Isothermal process

$$\delta q = -\alpha dP = Pd\alpha = \delta w \quad (214)$$

$$q = \int_i^f \alpha dP \quad (215)$$

$$= \int_i^f \frac{R_d T}{P} dP \quad (216)$$

$$= -R_d T \ln P|_i^f \quad (217)$$

$$= R_d T \ln \alpha|_i^f = w \quad (218)$$

III. Isochoric process

$$\delta q = C_v dT = dud\alpha = 0 \quad (219)$$

$$q = \int_i^f C_v dT \quad (220)$$

$$= C_v(T_f - T_i) \quad (221)$$

$$= C_v \Delta T = U \quad (222)$$

IV. Adiabatic process

$$0 = C_v dT + P\alpha \quad (223)$$

$$0 = C_p dT - P\alpha \quad (224)$$

Question 11.1: For each of the following conditions compute:

- Mechanical work done by the sample of air.
- Heat added to the sample.
 - Isothermal compression to $1/5^{th}$ of its original volume at $15^{\circ}C$.
 - Isobaric heating from $0^{\circ}C$ to $20^{\circ}C$.
 - Adiabatic expansion to 5 times its original volume within initial temperature of $20^{\circ}C$.

⇒ Solution:

a. For Isothermal process

$$\begin{aligned} q = w &= R_d T \ln\left(\frac{1}{V}\right) \Big|_V^{V/5} \\ &= 287 \times 288 \times T \ln(5) \\ &= 133.0297 \text{ kJ} \end{aligned}$$

b. For Isobaric heating

$$\begin{aligned} q &= C_p dT \\ &= \frac{7}{2} R_d \times \Delta T \\ &= \frac{7}{2} \times 287 \times 20 \\ &= 19740 \text{ J} \\ &\approx 20 \text{ kJ} \end{aligned}$$

c. Adiabatic heating

$$\begin{aligned} w &= \frac{P_1 V_1 - P_2 V_2}{\gamma - 1} \\ &= \frac{R_d (T_1 - T_2)}{\gamma - 1} \\ &= \frac{287 \times (293 - \frac{293}{5})}{\frac{7}{5} - 1} \\ &= 168.182 \text{ kJ} \\ q &= 0 \text{ J} \end{aligned}$$

12. Lecture 12 11/09/2024

12.1 . Poisson's equation for adiabatic transformation

For adiabatic processes:

$$dq = 0 \quad (225)$$

$$c_p dT = \alpha dP \quad (226)$$

$$c_p \frac{dT}{T} = \alpha \frac{dP}{P} \quad (227)$$

From Ideal gas equations:

$$P\alpha = R_d T \quad (228)$$

$$\alpha = \frac{R_d T}{P} \quad (229)$$

$$c_p \frac{dT}{T} = \frac{R_d T}{P} \frac{dP}{T} \quad (230)$$

$$c_p \frac{dT}{T} = R_d \frac{dP}{P} \quad (231)$$

Integrating from an initial temperature T_0 and pressure P_0 to arbitrary temperature and pressure T and P , we get:

$$\int_{T_0}^T c_p \frac{dT}{T} = \int_{P_0}^P R_d \frac{dP}{P} \quad (232)$$

$$c_p \ln\left(\frac{T}{T_0}\right) = R_d \ln\left(\frac{P}{P_0}\right) \quad (233)$$


$$\left(\frac{T}{T_0}\right)^{c_p} = \left(\frac{P}{P_0}\right)^{R_d} \quad (234)$$

$$T_0 = T \left(\frac{P}{P_0}\right)^{\frac{R_d}{c_p}} \quad (235)$$

$$\Rightarrow \theta = T \left(\frac{1000}{P_0}\right)^k \quad (236)$$

where constant k is R_d/c_p which is equal to **0.286**, $P_0 = 1000\text{hPa}$ which is **near surface pressure** and θ is known as **potential temperature**.

Potential temperature(θ) in Eq.(236) is defined as a adiabatically compressed parcel is brought to 1000hPa isobar (near surface) from that leveland temperature is measure.



Let us assume that

$$\theta = ATP^{-k} \quad (237)$$

where k is $R_d/C_p = 0.286$.

Taking logarithm on both sides

$$d(\ln \theta) = d(\ln A) + d(\ln T) - kd(\ln P) \quad (238)$$

$$d(\ln \theta) = d(\ln T) - \frac{R_d}{C_p} d(\ln P) \quad (239)$$

where $A = (P_0)^k = (1000)^{0.286}$

Consider 1st law of thermodynamics

$$\delta q = C_p dT - \alpha dP \quad (240)$$

$$\frac{\delta q}{T} = C_p \frac{dT}{T} - \alpha \frac{dP}{T} \quad (241)$$

$$\frac{\delta q}{C_p T} = \frac{dT}{T} - \frac{R_d T dP}{C_p P T} \quad (242)$$

$$\frac{\delta q}{C_p T} = \frac{dT}{T} - \frac{R_d dP}{C_p P} \quad (243)$$

$$\frac{\delta q}{C_p T} = d(\ln T) - \frac{R_d}{C_p} d(\ln P) \quad (244)$$

from Eq.(239) and Eq.(244)

$$d(\ln \theta) = \frac{\delta q}{C_p T} \quad (245)$$

For adiabatic process $\delta q = 0$

$$d(\ln \theta) = 0 \quad (246)$$

θ is constant, conserved for adiabatic process.

Question 12.1: Transcontinental airline fly at an altitude of 12km where the temperature outside is $-55^{\circ}C$ and the pressure is approximately 200hPa

- Compute the potential temperature of air at this altitude.
- Cabin pressure is typically mentioned of 750hPa corresponding to pressure altitude of 2.24km. when outside air is adiabatically compressed to cabin pressure. Compute the air temperature if no corrective operation were taken.

⇒ Solution:

- Potential temperature of air

$$\begin{aligned}\theta &= T \left(\frac{1000}{P} \right)^k \\ &= 218 \left(\frac{1000}{200} \right)^{0.286} \\ &= 218(5)^{0.286} \\ &= 345.4317K \\ &= 72.43^{\circ}C\end{aligned}$$

- Potential temperature of air

$$\begin{aligned}\theta &= T \left(\frac{1000}{P} \right)^k \\ &= 218 \left(\frac{750}{200} \right)^{0.286} \\ &= 218 \left(\frac{4}{3} \right)^{0.286} \\ &= 318.14K \\ &= 45^{\circ}C\end{aligned}$$

13. Lecture 13 12/09/2024

13.1 . Adiabatic transformation - Poisson's equation

1. Case I.

$$C_p dT = \alpha dP \quad (247)$$

$$C_p \frac{dT}{T} = R_d \frac{dP}{P} \quad (248)$$

$$\frac{dT}{T} = \left(\frac{C_p - C_v}{C_p} \right) \frac{dP}{P} \quad (249)$$

$$\frac{dT}{T} = \left(1 - \frac{C_v}{C_p} \right) \frac{dP}{P} \quad (250)$$

$$\frac{dT}{T} = \left(1 - \frac{1}{\gamma} \right) \frac{dP}{P} \quad (251)$$

$$\frac{dT}{T} = \left(\frac{\gamma - 1}{\gamma} \right) \frac{dP}{P} \quad (252)$$

$$\ln T = \left(\frac{\gamma - 1}{\gamma} \right) \ln P + \ln C \quad (253)$$

$$T = CP^{\left(\frac{\gamma-1}{\gamma}\right)} \quad (254)$$

$$TP^{\left(\frac{1-\gamma}{\gamma}\right)} = C \quad (255)$$

2. Case II.

$$C_v dT = -P d\alpha \quad (256)$$

$$C_v \frac{dT}{T} = -R_d \frac{d\alpha}{\alpha} \quad (257)$$

$$\frac{dT}{T} = -\left(\frac{C_p - C_v}{C_v} \right) \frac{d\alpha}{\alpha} \quad (258)$$

$$\frac{dT}{T} = \left(1 - \frac{C_p}{C_v} \right) \frac{d\alpha}{\alpha} \quad (259)$$

$$\frac{dT}{T} = \left(1 - \gamma \right) \frac{d\alpha}{\alpha} \quad (260)$$

$$\ln T = (1 - \gamma) \ln \alpha + \ln C \quad (261)$$


$$\ln T = \ln \alpha^{(1-\gamma)} + \ln C \quad (262)$$

$$T = C \alpha^{(1-\gamma)} \quad (263)$$

$$T \alpha^{(\gamma-1)} = C \quad (264)$$

13.2 . Adiabatic Lapse Rate

Adiabatic Lapse Rate (LR)



Phase change of moisture is absent

Note: Moisture is present in dry air parcel but it is assumed that it does not show any phase change.

13.3 . Dry Adiabatic Lapse Rate (DALR)

Using the 1st law of thermodynamics

$$\delta q = C_p dT - \alpha dP \quad (265)$$

Adiabatic process:

$$\delta q = 0 \quad (266)$$

$$C_p dT = \alpha dP \quad (267)$$

Lapse rate:

$$\frac{dT}{dz} = \frac{dT}{dP} \cdot \frac{dP}{dz} \quad (268)$$

From Eq.(267) and (268)

$$\frac{dT}{dz} = \frac{R_d T}{C_p P} \cdot \frac{dP}{dz} \quad (269)$$

Note: Hydrostatic balance is applied to surrounding not on parcel.

Appling hydrostatic approximaion, the pressure of unconfined air parcel is same as that of the envirnoment (i.e. $P = P'$), we get:

$$\frac{dP}{dz} = \frac{dP'}{dz} = \rho' g = -\frac{P' g}{R_d T'} \quad (270)$$

where P' and T' are ambient pressure and temperature.

From Eq.(267), Eq.(268) and Eq.(270)

$$\frac{dT}{dz} = \frac{R_d T}{C_p P} \cdot \left(-\frac{P' g}{R_d T'} \right) \quad (271)$$

$$\frac{dT}{dz} = \frac{g}{C_p} \cdot \left(-\frac{T P'}{T' P} \right) \quad (272)$$

$$\frac{dT}{dz} = -\frac{g}{C_p} \left(\frac{T}{T'} \right) \quad (273)$$

$$\Gamma_d = -\frac{dT}{dz} = \frac{g}{C_p} \left(\frac{T}{T'} \right) \quad (274)$$

$$\Gamma_d = -\frac{dT}{dz} \approx \frac{g}{C_p} \quad (275)$$

$$\Gamma_d = -\frac{dT}{dz} \approx 9.8 \times 10^{-3} {}^\circ C/m \quad (276)$$

$$\Rightarrow \Gamma_d = -\frac{dT}{dz} \approx 9.8 {}^\circ C/km \quad (277)$$


where Γ_d is **Dry Adiabatic Lapse Rate (DALR)** which is aproximately equal to $9.8 {}^\circ C/km$, also T and T' are comparably equal.

13.4 . Possion's equations

From Eq.(236)

$$\theta = T \left(\frac{1000}{P} \right)^k \quad (278)$$

$$\Rightarrow P^k = \left(\frac{P_0^k}{\theta} \right) T \quad (279)$$



14. Lecture 14 20/09/2024

14.1 . Heat Engines

- Construct closed cycle of compression and expansion to produce net work.
- Production of work required expenditure of internal energy on heat supplied by the environment.

From 1st law of thermodynamics

$$\delta q = du + \delta w \quad (280)$$

$$\oint \delta q = \oint du + \oint \delta w \quad (281)$$

$$\oint \delta q = \oint^0 du + \oint \delta w \quad (\because u_i = u_f) \quad (282)$$

$$\oint \delta q = \oint \delta w \quad (283)$$

$$\Rightarrow q_{\text{net}} = w_{\text{net}} \quad (\text{Theoretically}) \quad (284)$$

In theory, the equality $q_{\text{net}} = w_{\text{net}}$ arises from the assumption of a perfect heat engine operating in a closed cycle. This idealized scenario implies that all the heat energy supplied to the engine is converted into mechanical work without any losses due to friction, heat dissipation, or other irreversibilities.

However, no physical engine can achieve this ideal efficiency. Real engines inevitably encounter energy losses through various mechanisms, such as:

- Heat Loss:** Part of the input heat is lost to the surroundings, decreasing the effective energy available for work.
- Friction:** Mechanical losses due to friction in moving parts result in energy dissipation as heat, further reducing the net work output.
- Non-ideal Processes:** Real thermodynamic processes often involve irreversible changes, which lead to additional energy losses that are not accounted for in the ideal model.

Thus, while $q_{\text{net}} = w_{\text{net}}$ serves as a theoretical benchmark, practical engines operate with efficiencies below this ideal, governed by real-world constraints and inefficiencies.

14.2 . Efficiency

Efficiency of heat engine,

$$\eta = \frac{q_{\text{in}} - q_{\text{out}}}{q_{\text{in}}} = \frac{w}{q_{\text{in}}} \quad (285)$$

14.3 . Carnot Cycle

The Carnot cycle consists of the following four steps, which can be seen in figure:

- Step 1:** Reversible isothermal expansion.
- Step 2:** Reversible adiabatic expansion.




Figure 4. Carnot Cycle

- Step 3:** Reversible isothermal compression.
- Step 4:** Reversible adiabatic compression.

Step 1: Reversible Isothermal Expansion

During this process, the temperature remains constant, i.e., $\Delta T = 0$, which implies that the internal energy change is zero, $\Delta u = 0$.

The work done during this process is given by:

$$w_{12} = \int \delta w = \int_{\alpha_1}^{\alpha_2} p d\alpha \quad (286)$$

$$= \int_{\alpha_1}^{\alpha_2} \frac{R_d T_1}{\alpha} d\alpha \quad (287)$$

$$= R_d T_1 \ln \frac{\alpha_2}{\alpha_1} \quad (288)$$

Since $du = 0$ (because $dT = 0$), we have:

$$du_{12} = dw_{12} \Rightarrow Q_{12} = W_{12}$$

Step 2: Reversible Adiabatic Expansion

In this step, the gas expands without heat exchange, leading to a change in internal energy. The change in internal energy is given by:

$$\Delta u_{23} = C_v(T_2 - T_1) \quad (289)$$

$$-\Delta u_{23} = w_{23} \quad (290)$$

$$w_{23} = -C_v(T_2 - T_1) \quad (291)$$

Step 3: Reversible Isothermal Compression

In this process, the gas is compressed isothermally, maintaining a constant temperature:

$$w_{34} = \int \delta w = \int_{\alpha_3}^{\alpha_4} p d\alpha \quad (292)$$

$$= \int_{\alpha_3}^{\alpha_4} \frac{R_d T_2}{\alpha} d\alpha \quad (293)$$

$$= R_d T_2 \ln \frac{\alpha_4}{\alpha_3} \quad (294)$$

Step 4: Reversible Adiabatic Compression

During this step, the gas is compressed adiabatically, resulting in a temperature increase and work done on the gas. The work can be expressed as:

$$w_{41} = C_v(T_2 - T_1) \quad (295)$$

From Poisson's equation (236), we have the following relations for the Carnot cycle:

$$T_1 \alpha_2^{\gamma-1} = T_2 \alpha_3^{\gamma-1} \quad (296)$$

$$\frac{T_1}{T_2} = \left(\frac{\alpha_3}{\alpha_2} \right)^{\gamma-1} \quad (297)$$

Similarly, for the other isentropic process:

$$T_1 \alpha_1^{\gamma-1} = T_2 \alpha_4^{\gamma-1} \quad (298)$$

$$\frac{T_1}{T_2} = \left(\frac{\alpha_4}{\alpha_1} \right)^{\gamma-1} \quad (299)$$

From these two equations, we can equate the temperature ratios:

$$\left(\frac{\alpha_3}{\alpha_2} \right)^{\gamma-1} = \left(\frac{\alpha_4}{\alpha_1} \right)^{\gamma-1} \quad (300)$$

$$\frac{\alpha_3}{\alpha_4} = \frac{\alpha_2}{\alpha_1} \quad (301)$$

Total Work:

From Eq.(288), (291), (294), and (295), the total work done in the cycle is:

$$W_{\text{Total}} = w_{12} + w_{23} + w_{34} + w_{41} \quad (302)$$

$$= R_d T_1 \ln \frac{\alpha_2}{\alpha_1} - C_v(T_2 - T_1) + \quad (303)$$

$$R_d T_2 \ln \frac{\alpha_4}{\alpha_3} + C_v(T_2 - T_1) \quad (304)$$

$$= R_d T_1 \ln \frac{\alpha_2}{\alpha_1} + R_d T_2 \ln \frac{\alpha_4}{\alpha_3} \quad (305)$$

$$= R_d \left[T_1 \ln \frac{\alpha_2}{\alpha_1} + T_2 \ln \frac{\alpha_4}{\alpha_3} \right] \quad (306)$$

$$= R_d (T_1 - T_2) \ln \left(\frac{\alpha_2}{\alpha_1} \right) \quad \text{From Eq.(301)} \quad (307)$$

Finding the efficiency of carnot cycle using Eq.(285) and Eq.(307)

$$\eta = \frac{Q_1 + Q_2}{Q_1} \quad (308)$$

$$= 1 + \frac{Q_2}{Q_1} \quad (309)$$

$$= 1 + \frac{R_d T_2 \ln \frac{\alpha_3}{\alpha_4}}{R_d T_1 \ln \frac{\alpha_2}{\alpha_1}} \quad (310)$$

$$= 1 - \frac{T_2 \ln \frac{\alpha_2}{\alpha_1}}{T_1 \ln \frac{\alpha_2}{\alpha_1}} \quad (311)$$

$$\Rightarrow \eta = 1 - \frac{T_2}{T_1} \quad (312)$$

The temperature at which carnot engine becomes 100% efficient (i.e. $\eta = 1$) is called **Absolute temeprature (0K)**
In real world scenarios 0K is not achievable and there is no process which is ideally reversible.

14.4 . Skew T - log P diagram

Skew-T plot¹ shows combined and also separate plots for Full Skew-T, Isothermal lines, Isobars, Dry Adiabats, Moist Adiabats, Mixing Ratio and Wind Staff.

¹<https://www.noaa.gov/jetstream/upperair/skew-t-log-p-diagrams>




Figure 5. Isothermal lines in Skew-T diagram




Figure 6. Isobaric lines in Skew-T diagram




Figure 7. Dry-adiabat lines in Skew-T diagram




Figure 8. Moist-adiabat lines in Skew-T diagram




Figure 9. Mixing ratio lines in Skew-T diagram




Figure 10. Skew-T diagram

15. Lecture 15 03/10/2024

15.1 . Cyclones

Properties of cyclones

1. Centre of cyclone is called Eye of cyclone.
2. Cumulonimbus clouds forms the eye ball of cyclone.
3. Maximum height to where it can reaches is Tropopause




Figure 11. Internal Structure of cyclone




Figure 12. Air circulation in cyclone

Image source: [Air circulation in cyclone²](https://www.britannica.com/science/tropical-cyclone)

15.2 . Specific enthalpy

Enthalphy is heat content of state.

$$H = U + PV \quad (313)$$

$$\Delta H = \Delta U + \Delta(PV) \quad (314)$$

$$\Delta H = \Delta U + P\Delta V + V\Delta P \quad (315)$$

$$\Delta H = Q - W + P\Delta V + V\Delta P \quad (316)$$

$$\Delta H = Q - P\Delta V + P\Delta V + V\Delta P \quad (317)$$

$$\Delta H = Q + V\Delta P \quad (318)$$

At constant pressure

$$\Delta H = Q \quad (319)$$

$$h = u + P\alpha \quad (320)$$

$$dh = du + d(PV) \quad (321)$$

$$dh = du + Pd\alpha + \alpha dP \quad (322)$$

$$dh = \delta q + \alpha dP \quad (323)$$

$$\delta q = dh - \alpha dP \text{ also,} \quad (324)$$

$$\delta q = C_p dT - \alpha dP \quad (325)$$

From Eq.(324) and Eq.(325)

$$dh - \alpha dP = C_p - \alpha dP \quad (326)$$

At constant Pressure

$$dh = C_p dT \quad (327)$$

Enthalphy is "sensible heat"

Conservative property

For a hydrostatic atmosphere:

$$\frac{dp}{dz} = \rho g \Rightarrow dp = -\rho g dz \quad (328)$$

Substitute Eq.(325) in Eq.(328)

$$\delta q = C_p dT - \alpha \rho g dz \quad (329)$$

$$\delta q = C_p dT + gdz \quad (330)$$

$$\delta q = dh + d\phi \quad (331)$$


$$\delta q = d(h + \phi) \quad (332)$$

If process is adiabatic $\delta q = 0$

$$h + \phi = \text{const} \quad (333)$$

Eq.(333) called dry static equation.

This implies that when air parcel goes up (in geopotential) by the expense of heat content (enthalphy), i.e. $[h \uparrow \phi \downarrow]$.



$$\text{Area } A \propto (T_2 - T_1)(\ln P_2 - \ln P_1) \quad (334)$$

$$\propto (T_2 - T_1) \ln \left(\frac{P_2}{P_1} \right) \quad (335)$$

²<https://www.britannica.com/science/tropical-cyclone>

Cycle 1:

$$\begin{aligned} w_1 &= \int P d\alpha \\ &= P \int_{\alpha_1}^{\alpha_2} d\alpha \\ &= P(\alpha_2 - \alpha_1) \\ &= R_d(T_2 - T_1) \end{aligned}$$

Cycle 2:

$$\begin{aligned} w_2 &= \int P d\alpha \\ &= \int_{\alpha_1}^{\alpha_2} \frac{R_d T}{\alpha} d\alpha \\ &= R_d T_2 \ln\left(\frac{\alpha_2}{\alpha_1}\right) \\ &= R_d T_2 \ln\left(\frac{P_1}{P_2}\right) \end{aligned}$$

Cycle 3:

$$\begin{aligned} w_3 &= \int P d\alpha \\ &= P \int_{\alpha_2}^{\alpha_1} d\alpha \\ &= P(\alpha_1 - \alpha_2) \\ &= R_d(T_1 - T_2) \\ &= -R_d(T_2 - T_1) \end{aligned}$$

Cycle 4:

$$\begin{aligned} w_4 &= \int P d\alpha \\ &= \int_{\alpha_2}^{\alpha_1} \frac{R_d T}{\alpha} d\alpha \\ &= R_d T_1 \ln\left(\frac{\alpha_1}{\alpha_2}\right) \\ &= R_d T_1 \ln\left(\frac{P_2}{P_1}\right) \\ &= -R_d T_1 \ln\left(\frac{P_1}{P_2}\right) \end{aligned}$$

$$\begin{aligned} w_{\text{net}} &= w_1 + w_2 + w_3 + w_4 \\ &= R_d(T_2 - T_1) + R_d T_2 \ln\left(\frac{P_1}{P_2}\right) - R_d(T_2 - T_1) - R_d T_1 \ln\left(\frac{P_1}{P_2}\right) \\ &\Rightarrow w_{\text{net}} = 0 \end{aligned}$$

16. Lecture 16 07/10/2024

16.1 . Lesson learnt from carnot cycle

16.2 . Entropy

Let's recall that,

$$q_1 = R_d T_1 \ln \left(\frac{\alpha_2}{\alpha_1} \right) \quad (336)$$

$$\frac{q_1}{T_1} = R_d \ln \left(\frac{\alpha_2}{\alpha_1} \right) \quad (337)$$

Similarly,

$$q_2 = -R_d T_2 \ln \left(\frac{\alpha_2}{\alpha_1} \right) \quad (338)$$

$$\frac{q_2}{T_2} = -R_d \ln \left(\frac{\alpha_2}{\alpha_1} \right) \quad (339)$$

$$\frac{q_1}{T_1} + \frac{q_2}{T_2} = 0, \quad q_1 > 0, q_2 < 0 \quad (340)$$

Efficency of heat engine:

$$\eta_{\text{rev}} = 1 - \frac{T_2}{T_1} \quad (341)$$

$$\eta_{\text{rev}} = \frac{T_1 - T_2}{T_1} \quad (342)$$

$$T_1 \cdot \eta_{\text{rev}} = T_1 - T_2 \quad (343)$$

Multiply and divide Eq.(340) by η_{rev}

$$\frac{q_1}{T_1} \cdot \frac{\eta_{\text{rev}}}{\eta_{\text{rev}}} + \frac{q_2}{T_2} = 0 \quad (344)$$

From Eq.(343),

$$q_1 \cdot \frac{\eta_{\text{rev}}}{(T_1 - T_2)} + \frac{q_2}{T_2} = 0 \quad (345)$$

The above expression is applicable only if process is **perfectly reversible**.

If process is not perfectly reversible, i.e., irreversible

$$q_1 \cdot \frac{\eta_{\text{irrev}}}{(T_1 - T_2)} + \frac{q_2}{T_2} < 0 \quad (346)$$

In general,

$$\sum_{i=1}^2 \frac{q_i}{T_i} \leq 0, \begin{cases} = 0 & \text{if perfectly reversible,} \\ < 0 & \text{if irreversible} \end{cases} \quad (347)$$

$$\Rightarrow \sum_{i=1}^N \frac{q_i}{T_i} \leq 0, \quad \text{for } N \text{ number of sources.} \quad (348)$$

If $N \rightarrow \infty$

$$\oint_{\text{cyclic process}} \frac{\delta q}{T} \leq 0 \rightarrow \text{Entropy} \quad (349)$$

$$\delta q = C_v dT + P d\alpha \quad (350)$$

$$\frac{\delta q}{T} = C_v \frac{dT}{T} + P \frac{d\alpha}{T} \quad (351)$$

$$\oint \frac{\delta q}{T} = C_v \oint \frac{dT}{T} + \oint \frac{RT}{\alpha T} d\alpha \quad (352)$$

$$ds = \oint \frac{\delta q}{T} = C_v \oint \frac{dT}{T} + R \oint d\ln \alpha \quad (353)$$

$$ds = \oint \frac{\delta q}{T} = C_v \oint d\ln T + R \oint d\ln \alpha \quad (354)$$

$$\Rightarrow ds = s_f - s_i = \oint_i^f \frac{\delta q}{T} \quad (355)$$

Number of states in which the system can have large disorder hence higher entropy.
(No. of molecule ↑) (No. of possible system states ↑) → (Entropy↑)

Question 16.1: Show that entropy of ideal gas depends on intial and final state of temperature and volume.

$$\begin{aligned} \Rightarrow ds &= \oint \frac{dq}{T} = C_v \oint d(\ln T) + R \oint d(\ln \alpha) \\ \Delta S &= \int_i^f ds = S_f - S_i = C_v \ln \left(\frac{T_f}{T_i} \right) + R \ln \left(\frac{\alpha_f}{\alpha_i} \right) \\ S_f &= S_i + C_v \ln \left(\frac{T_f}{T_i} \right) + R \ln \left(\frac{\alpha_f}{\alpha_i} \right) \\ S_f &= S_i + C_v \ln \left(\frac{T_f}{T_i} \right) + C_v \left(\frac{R}{C_v} \right) \ln \left(\frac{\alpha_f}{\alpha_i} \right) \\ S_f &= S_i + C_v \left[\ln \left(\frac{T_f}{T_i} \right) \times \left(\frac{\alpha_f}{\alpha_i} \right)^{\left(\frac{C_p - C_v}{C_v} \right)} \right] \\ S_f &= S_i + C_v \left[\ln \left(\frac{T_f}{T_i} \right) \times \left(\frac{\alpha_f}{\alpha_i} \right)^{(\gamma-1)} \right] \text{ where } \gamma = C_p/C_v \end{aligned}$$

17. Lecture 17 10/10/2024

17.1 . Entropy

In last lecture we derived expression of entropy, i.e.


$$\oint \frac{q}{T} \leq 0$$

→ Depends on the final and initial states of temperature and volume.

Let us consider a cyclic process with initial state i and final state f , the path through which process occur be denoted by R and I representing reversible and irreversible processes.

$$i \xrightarrow{R} f \quad \text{Reversible}$$

$$i \xrightarrow{I} f \quad \text{Irreversible}$$



As we know from any cyclic process

$$\oint \frac{q}{T} \leq 0 \quad (356)$$

$$\left[\int_i^f \frac{q}{T} \right]_R + \left[\int_f^i \frac{q}{T} \right]_I \leq 0 \quad (357)$$

Since,

$$ds = \frac{\delta q}{T} \quad (358)$$

$$S_f - S_i + \left[\int_f^i \frac{q}{T} \right]_I \leq 0 \quad (359)$$

$$S_f - S_i \geq \left[\int_i^f \frac{q}{T} \right]_I \quad (360)$$

$$ds \geq \left[\int_i^f \frac{q}{T} \right]_I \quad (361)$$

$$Tds \geq \delta q \quad (362)$$

It indicates that the upperbound of the heat absorbed by the system during a given changes.

For an isolated system,

$$\delta q = 0 \quad (363)$$

$$S_f - S_i \geq 0 \quad (364)$$

$$S_f \geq S_i \quad (365)$$

For a spontaneous irreversible transformation, occurring in an isolated system, the final entropy is greater than initial entropy.

17.2 Second Law of Themodynamics

2nd law of themodynamics can be stated as:

1. For reversible transformation, there is no change in entropy of universe.
2. The entropy of universe increase as a result of irreversible transformation.

$$\Delta S_{\text{universe}} = \Delta S_{\text{system}} + \Delta S_{\text{surrounding}}$$

$$\Delta S_{\text{surrounding}} = 0 \quad \text{For reversible transformation}$$

$$\Delta S_{\text{surrounding}} > 0 \quad \text{For irreversible transformation}$$

Recall that,

$$\theta = T \left(\frac{1000}{P} \right)^{\frac{R_d}{C_p}} \quad (366)$$

$$\ln \theta = \ln T + \frac{R_d}{C_p} \ln(1000) - \frac{R_d}{C_p} \ln P \quad (367)$$

$$C_p d(\ln \theta) = C_p d(\ln T) - R_d d(\ln P) \quad (368)$$

From 1st law of thermodynamic,

$$\delta q = C_p dT - \alpha dP \quad (369)$$

$$ds = \frac{C_p dT}{T} - \frac{\alpha dP}{T} \quad (370)$$

$$ds = \frac{C_p dT}{T} - \frac{R_d dP}{P} \quad (371)$$

$$ds = C_p d \ln(T) - R_d d \ln(P) \quad (372)$$

Comparing Eq.(368) and Eq.(368) we can find that,

$$ds = C_p d(\ln \theta) \quad (373)$$

$$S = C_p \ln \theta + \text{const.} \quad (374)$$

Therefore, lines of constant potential temperature are lines of constant entropy, but not if process becomes irreversible. Specific entropy is given by logarithm of potential temperature, when θ remains constant \Rightarrow entropy remains constant.

For irreversible transformation

$$ds > 0 \quad d\theta = 0$$

All isentropic process are adiabatic but all adiabatic process are not isentropic.

18. Lecture 18 10/10/2024

18.1 Special Forms of Second Law of Thermodynamics

1. For finite isothermal transformation

$$\Delta U = 0 \quad (375)$$

$$\Delta S \geq \int \frac{\delta q}{T} \quad (376)$$

$$\Delta S \geq \frac{1}{T} \int \delta q \quad (377)$$

$$\Delta S \geq \frac{q}{T} \quad (378)$$

$$\Delta S \geq \frac{w}{T} \quad (379)$$

2. For adiabatic transformation

$$\Delta S \geq 0 \quad (380)$$

3. For Isochoric transformation

$$\Delta S \geq C_v \frac{dT}{T} \quad (381)$$

$$\Delta S \geq C_v \ln\left(\frac{T_f}{T_i}\right) \quad (382)$$

4. For Isobaric transformation

$$\Delta S \geq C_p \frac{dT}{T} \quad (383)$$

$$\Delta S \geq C_p \ln\left(\frac{T_f}{T_i}\right) \quad (384)$$

5. Combination of 1st and 2nd law

$$\delta q = C_p dT - \alpha dp \quad (385)$$

$$ds \geq \frac{q}{T} \quad (386)$$

$$Tds \geq C_p dT - \alpha dp \quad (387)$$

$$Tds \geq dh - \alpha dp \quad (388)$$

$$(389)$$

similiarly,

$$\delta q = C_v dT - \alpha dp \quad (390)$$

$$ds \geq \frac{q}{T} \quad (391)$$

$$Tds \geq C_v dT - \alpha dp \quad (392)$$

$$Tds \geq du - \alpha dp \quad (393)$$

18.2 . Moist Processes

There are three processes in moist gases:

- Saturation
- Sub-saturation
- Supersaturation

Evaporation: Some water molecules have sufficient kinetic energy to break free from the intermolecular forces of attraction.

Condensation: When water vapor cools down, molecules lose kinetic energy and form liquid droplets due to intermolecular attractions.




Figure 13. Saturated state




Figure 14. Sub-Saturated state




Figure 15. Super-Saturated state

For saturated state rate of evaporation is equals to rate of condensation.

Saturation vapor pressure(e_s) depends only on temperature.

Boiling Point: The temperature at which vapor pressure is equal to atmospheric temperature at the pressure of 1013hPa.

18.3 . Relative humidity

Relative humidity is defined as ratio of vapor pressure to saturation vapor pressure.

$$\text{Relative humidity (RH)} = \frac{e}{e_s} \times 100\% \quad (394)$$

$$e < e_s(T) \rightarrow \text{Sub-Saturation} \quad (395)$$

$$e = e_s(T) \rightarrow \text{Saturation} \quad (396)$$

$$e > e_s(T) \rightarrow \text{Super-Saturation} \quad (397)$$

Note: Specific humidity is associated with mass




Figure 16. Saturation Vapor Pressure e_s vs Temperature T

18.4 . Dew point temperature

There are 2 ways to make sub-saturated to saturated:

1. Reduce temperature
2. Add moisture, so that vapor pressure increase.

If moisture amount remains constant and temperature is reduced, thus saturation is achieved and this temperature is called **Dew point temperature**.

18.5 . Latent heat

Total energy required to convert unit mass from one phase to another.

Specific enthalpy of phase change.

Latent heat of water at STP is $\approx 10^6 \text{ J/Kg}$ (Depends on temperature)

Latent heat of evaporation

Latent heat of evaporation of water at:

- $T = -40^\circ\text{C}$, Latent heat = $2.6 \times 10^6 \text{ J/Kg}$
- $T = 0^\circ\text{C}$, Latent heat = $2.5 \times 10^6 \text{ J/Kg}$
- $T = 40^\circ\text{C}$, Latent heat = $2.26 \times 10^6 \text{ J/Kg}$

Latent heat of fusion

Latent heat of fusion of water at STP = $3.3 \times 10^6 \text{ J/Kg}$

Latent heat of sublimation

Latent heat of sublimation of water at STP = $2.83 \times 10^6 \text{ J/Kg}$

19. Lecture 19 21/10/2024

19.1 . The Clausius-Clapeyron equation

Let L is latent heat associated with phase change of a liquid(i) to vapor(f) state:

$$L = \int dq \quad (398)$$

$$L = \int_i^f du + \int_i^f Pd\alpha \quad (399)$$

$$L = u_f - u_i + e_s(\alpha_f - \alpha_i) \quad (400)$$

where $e_s \rightarrow$ saturation vapor pressure

When phase cahnge happen, temperature remains constant, therefore

$$L = T \int \frac{\delta q}{T} \quad (401)$$

$$L = T \int_i^f ds \quad (402)$$

$$L = T(S_f - S_i) \quad (403)$$

From Eq.(400) and Eq.(403)

$$T(S_f - S_i) = U_f - U_i + e_s(\alpha_f - \alpha_i) \quad (404)$$

$$TS_f - U_f - e_s\alpha_f = TS_i - U_i - e_s\alpha_i \quad (405)$$

$$U + e_s\alpha - TS = \text{Const.} = G \quad (406)$$

where G is Gibbs energy

However, Gibbs energy is not constant when pressure and temperature changes.

$$dG = du + e_s d\alpha + \alpha de_s - Tds - sdT \quad (407)$$

$$dG = TdS + \alpha de_s - TdS - sdT \quad (408)$$

$$dG = \alpha de_s - sdT \quad (409)$$

consider a situation when liquid phase and vapor phase are in equilibrium

$$dG_1 = dG_2 \quad (410)$$

$$\alpha_i de_s - S_i dT = \alpha_f de_s - S_f dT \quad (411)$$

$$\frac{S_f - S_i}{\alpha_f - \alpha_i} = \frac{de_s}{dT} \quad (412)$$

$$\frac{L}{T(\alpha_f - \alpha_i)} = \frac{de_s}{dT} \quad (413)$$

Eq.(413) is called Clasuius-Clapeyron equation.

Let initial state(i) be liquid state and final state(f) be vapor state (evaporation)

$$\frac{e_s}{dT} = \frac{L}{T(\alpha_v - \alpha_l)} \quad (414)$$

For atmosphere $\alpha_v \ll \alpha_l$. therefore,

$$\frac{e_s}{dT} \approx \frac{L}{T\alpha_v} \quad (415)$$

Using ideal gas equation $e_s\alpha_v = R_v T$,

$$\frac{de_s}{dT} = \frac{Le_s}{R_v T^2} \quad (416)$$

Integrate form of Clausius-Clapeyron equation:

$$\int_{e_0}^{e_s} \frac{e_s}{e_s} = \int_{T_0}^T \frac{LdT}{R_v T^2} \quad (417)$$

$$\ln \frac{e_s}{e_0} = \frac{L}{R_v} \left[\frac{1}{T_0} - \frac{1}{T} \right] \quad (418)$$

$$e_s = e_0 \exp \left(\frac{L}{R_v} \left[\frac{1}{T_0} - \frac{1}{T} \right] \right) \quad (419)$$

Standard values $T_0 = 273$ K, $e_0 = 611$ Pa or 6.11 hPa,

$L = 2.5 \times 10^6$ J/kg, $R_v = 461$ JK⁻¹kg

$e_s(T) \approx Ae^{-B/T}$, where $A = 2.53 \times 10^{11}$ Pa, $B = 5420$ K.

This gives more accurate equation for temperature range from $-30^\circ\text{C} \leqslant T \leqslant 35^\circ\text{C}$

$$e_s(T) = 611.2 \left[\frac{17.69T_c}{T_c + 243.5} \right] \quad (420)$$

where T_c is temperature in celcius scale

For Ice,

$$e_i(T) = e_{i0} \exp \left(\frac{L_s}{R_v} \left[\frac{1}{T_0} - \frac{1}{T} \right] \right) \quad (421)$$

where T_c is temperature in celcius scale and L_s is latent heat of sublimation.

$e_s(T) \approx A_i e^{-B_i/T}$, where $A = 3.41 \times 10^{12}$ Pa, $B = 6130$ K.

$e_i < e_s \rightarrow$ at subfreezing temperatures, the environment that is saturated w.r.t liquid water is supersaturated w.r.t ice.

20. Lecture 20 23/10/2024

20.1 . Saturation mixing ratio

Mixing ratio:

$$\omega = \frac{m_v}{m_d} \quad (422)$$

$$\omega = \frac{\rho_v}{\rho_d} \quad (423)$$

$$\omega = \frac{\varepsilon e}{P - e} \quad (424)$$

$$\omega \approx \frac{\varepsilon e}{P} \quad (425)$$

where $e = \frac{R_d}{R_v} = 0.622$


Saturation mixing ratio:

$$\omega_s(T, P) \approx \frac{\varepsilon e_s(T)}{P} \quad \text{Unit: g/kg} \quad (426)$$

$$\omega_s(T, P = 622\text{hPa}) \approx \frac{0.622e_s(T)}{622} = 0.001 \text{ kg/kg} \quad (427)$$

$$\omega_s(T, P = 622\text{hPa}) \approx 0.001 \text{ kg/kg} \quad (428)$$

$$\omega_s(T, P = 622\text{hPa}) \approx e_s(T) \text{ g/kg} \quad (429)$$



21. Lecture 21 24/10/2024

21.1 . Lifting Conduction Level (LCL)

$$\omega_s = \frac{\varepsilon e_s(T)}{P}$$

As P decrease T decrease.

$\frac{d\omega_s}{dp}$ decides how saturation vapor pressure depends on pressure only (not on both Temperature and Pressure)

$$\frac{d\omega_s}{dP} = \frac{d}{dP} \left[\frac{\varepsilon e_s(T)}{P} \right] \quad (430)$$

$$= \varepsilon \left[\frac{1}{P} \frac{de_s(T)}{dP} - \frac{e_s}{P^2} \right] \quad (431)$$

$$= \frac{\varepsilon e_s}{P} \left[\frac{1}{e_s} \frac{de_s(T)}{dP} - \frac{1}{P} \right] \quad (432)$$

$$= \frac{\varepsilon e_s}{P} \left[\frac{1}{e_s} \frac{de_s(T)}{dT} \frac{dT}{dP} - \frac{1}{P} \right] \quad (433)$$

Using Clausius-Clapeyron equation Eq.(416)

$$\frac{d\omega_s}{dP} = \frac{\varepsilon e_s}{P} \left[\frac{1}{e_s} \frac{L \varrho_s}{R_v T^2} \frac{dT}{dP} - \frac{1}{P} \right] \quad (434)$$

$$\frac{d\omega_s}{dP} = \frac{\varepsilon e_s}{P} \left[\frac{L}{R_v T^2} \frac{dT}{dP} - \frac{1}{P} \right] \quad (435)$$

Since process is adiabatic (Lifting of moist air):

$$C_p dT - \alpha dP = 0 \quad (436)$$

$$C_p \frac{dT}{dP} - \alpha = 0 \quad (437)$$

$$\frac{dT}{dP} = \frac{\alpha}{C_p} \quad (438)$$

$$\frac{dT}{dP} = \frac{R_d T}{C_p P} \quad (439)$$

Substituting Eq.(439) in Eq.(435), we get

$$\frac{d\omega_s}{dP} = \frac{\varepsilon e_s}{P} \left[\frac{L}{R_v T^2} \frac{\alpha}{C_p} - \frac{1}{P} \right] \quad (440)$$

$$\frac{d\omega_s}{dP} = \frac{\varepsilon e_s}{P} \left[\frac{L}{R_v T^2} \frac{R_d \vartheta}{C_p P} - \frac{1}{P} \right] \quad (441)$$

$$\frac{d\omega_s}{dP} = \frac{\varepsilon e_s}{P^2} \left[\frac{L}{R_v T} \frac{R_d}{C_p} - 1 \right] \quad (442)$$


$$\frac{d\omega_s}{dP} = \frac{\omega_s}{P} \left[\frac{R_d L}{R_v C_p T} - 1 \right] \quad (443)$$

$$\frac{d\omega_s}{dP} = \frac{\omega_s}{P} \left[\frac{\varepsilon L}{C_p T} - 1 \right] \quad (444)$$

ω_s decreases w.r.t height (Since P decrease with height). ω_s decreases for any adiabatic uplift of air parcel.

Lifting Conduction Level is at $\omega = \omega_s$

Lifting Conduction Level is a level at which cloud start forming. It could be either Pressure level or Temperature level).



$$LCL(Km) \approx \frac{T - T_0}{8} \quad (445)$$

$$LCL(hPa) = p \exp(-0.044 \Delta T_d) \quad (446)$$

where ΔT_d is dew point depression which is equal to $(T - T_d)$. Just above LCL → phase change happens → release of latent heat which provides extra amount of energy, therefore, parcel will no longer follow dry adiabat, but **moist adiabatic lapse rate**. It depends upon moisture content present in air. This process is called **pseudo-adiabatic process** because mass gets lost in precipitation.

Dry adiabatic lapse rate (DALR):

$$\Gamma_d = \frac{g}{c_p} = 9.8^\circ C/km$$

Above LCL, parcel will follow **saturated adiabatic lapse rate** Γ_s which is always less than dry adiabatic lapse rate, i.e. $(\Gamma_s < \Gamma_d)$

22. Lecture 22 25/10/2024

22.1 . Saturation Adiabatic Lapse Rate

$$\delta q = C_p dT - \alpha dP \quad (447)$$

$\delta q = 0$ since process is adiabatic for dry adiabat Γ_d , but for saturation adiabatic (Γ_s) $\delta q \neq 0$

Additon of heat from latent heat of water vapor

$$\delta q = -L d\omega_s \quad (448)$$

where ω_s is saturation mixing ratio.

Therefore,

$$-L d\omega_s = C_p dT - \alpha dP \quad (449)$$

The term ω_s changes w.r.t pressure and temperature,

$$d\omega_s = \frac{\partial \omega_s}{\partial P} dP + \frac{\partial \omega_s}{\partial T} dT \quad (450)$$

Using the expression $\omega_s \approx \frac{e e_s}{P}$

$$d\omega_s = -\frac{\varepsilon e_s}{P^2} dP + \frac{\varepsilon e_s}{P} \frac{1}{e_s} \frac{de_s}{dT} dT \quad (451)$$

$$d\omega_s = -\omega_s \frac{dP}{P} + \omega_s \frac{L}{R_v T^2} dT \quad (452)$$

$$-L d\omega_s = L \omega_s \frac{dP}{P} - \omega_s \frac{L^2}{R_v T^2} dT \quad (453)$$

$$c_p dT - \alpha dP = L \omega_s \frac{dP}{P} - \frac{L^2 \omega_s}{R_v T^2} dT \quad (454)$$

Invoking hydrostatic approximation

$$\frac{\partial P}{\partial z} = -\rho g \quad (455)$$

$$gdz = -\alpha dP \quad (456)$$

$$\frac{c_p dT}{gdz} - \frac{\alpha dP}{-\alpha dP} = \frac{L \omega_s \frac{dP}{P}}{-\alpha dP} - \frac{\frac{L^2 \omega_s}{R_v T^2} dT}{gdz} \quad (457)$$

$$\frac{c_p dT}{gdz} - \frac{\alpha dP}{-\alpha dP} = \frac{L \omega_s \cancel{\frac{dP}{P}}}{-\alpha \cancel{dP}} - \frac{\frac{L^2 \omega_s}{R_v T^2} dT}{gdz} \quad (458)$$

$$\frac{c_p dT}{gdz} + 1 = \frac{L \omega_s}{-\alpha P} - \frac{L^2 \omega_s dT}{R_v T^2 gdz} \quad (459)$$

$$\left(\frac{L^2 \omega_s}{R_v g T^2} + \frac{c_p}{g} \right) \frac{dT}{dz} = \frac{L \omega_s}{\alpha P} + 1 \quad (460)$$

Recall $\Gamma_d = \frac{g}{c_p} \frac{T'}{T} \approx \frac{g}{c_p}$

where T' is temperature of parcel and T is temperature of atmosphere.

Multiplying $\frac{g}{c_p}$ to Eq.(460)

Using the ideal gas equation, $P\alpha = R_d T$,

If $\omega_s = 0$, which mean air is not moist $\rightarrow \Gamma_s = \Gamma_d = 9.8^\circ C/km$

$$\Gamma_s = \frac{d \ln T}{d \ln P} \approx \frac{\left(\frac{L \omega_s}{R_d T} + 1 \right)}{\left(\frac{L^2 \omega_s}{R_v c_p T^2} + 1 \right)} \frac{R_d}{c_p} \quad (461)$$

$\Gamma_s \approx 6.5^\circ C/km$ which can vary between 4 to 7 depending on amount of moisture content in air.

Note: Potential temperature is no more conserved quantity above LCL.

22.2 Equivalent Potential Temperature

θ_e is conserved during moist adiabatic process.

$$\theta_e = \theta \exp \left(\frac{L \omega}{c_p T_{LCL}} \right) \quad (462)$$

23. Lecture 23 30/10/2024

23.1 . Psychrometer




Figure 17. Psychrometer

At saturated air (100% moist air) $\rightarrow T_d = T_w$
 \therefore It gives information about relative humidity.




Figure 18. Skew-T diagram with Isobars, Dry and Moist Adiabat

23.2 . Normand's rule

$$T_d \leq T_w \leq T \quad (463)$$

where

T_d is dew point temperature.

T_w is wet bulb temperature.

T is parcel temperature.

24. Lecture 24 04/11/2024

24.1 . Adiabatic cloud water content

Water vapor mixing ratio:

$$\omega = \frac{m_v}{m_d} \quad (464)$$

Liquid water mixing ratio:

$$\omega_l = \frac{m_l}{m_d} \quad (465)$$


Total mixing ratio:

$$\omega_{\text{Total}} = \omega + \omega_l \quad (466)$$

Assumption considered are:

- Air contains only vapor and liquid water. There is no ice in air.
- Water does not precipitate during the process.

2. Pseudo adiabatic process



24.3 . Atmospheric stability

Hydrostatic imbalance in small-scale scenarios such as tornados.

- Stable
- Unstable
- Neutral
- Metastable





Figure 19. Skew-T diagram with Isobars, Dry and Moist Adiabat

Liquid water content (LWC)

$$\text{LWC} = (\omega_0 - \omega_1) \quad (467)$$

24.2 . Flow over terrain

1. Moist adiabatic process



25. Lecture 25 06/11/2024

25.1 . Atmospheric stability

Over large scale, atmosphere is in hydrostatic balance


$$\frac{dp}{dz} = -\rho g \quad (468)$$

Convection/small scale process

Following assumptions are made in order to assess the stability condition:

1. The environment is in hydrostatic equilibrium.
2. The parcel does not mix with surrounding.
3. The parcel movement does not disturb the surrounding.
4. The process is adiabatic.
5. At any given level, pressure inside the parcel equals to that of environment.

Three conditions



25.2 . Equation of motion for the parcel

Because the environment is in hydrostatic equilibrium given by Eq.(0) This does not hold wave equation for a parcel, i.e., Using the assumption (5):

$$\frac{d^2z}{dt^2} = -\alpha' \left(\frac{-g}{\alpha} \right) - g \quad (469)$$

$$\frac{d^2z}{dt^2} = \left(\frac{\alpha}{\alpha'} \right) g - g \quad (470)$$

$$\frac{d^2z}{dt^2} = \left(\frac{\alpha' - \alpha}{\alpha} \right) g \quad (471)$$

$$\frac{d^2z}{dt^2} = \left(\frac{\rho - \rho'}{\rho'} \right) g \quad (472)$$

Using Ideal gas equation,

$$\frac{d^2z}{dt^2} = \left(\frac{T'_v - T_v}{T_v} \right) g \quad (473)$$

We consider a displacement of a parcel from its mean position ,such that $z \ll 1$.

If for simplicity we take the level to be at $z = 0$, where temperature is T_{v0} . Express T_v and T_{v0} in terms of taylor series:

$$T_v = T_{v0} + \frac{dT_v}{dz} \frac{z}{1!} + \frac{d^2T_v}{dz^2} \frac{z^2}{2!} + \dots \quad (474)$$

$$T'_v = T_{v0} + \frac{dT'_v}{dz} \frac{z}{1!} + \frac{d^2T'_v}{dz^2} \frac{z^2}{2!} + \dots \quad (475)$$

Neglect the higher order terms;

$$T_v = T_{v0} + \frac{dT_v}{dz} z \quad (476)$$

$$T'_v = T_{v0} + \frac{dT'_v}{dz} z \quad (477)$$

$$\Gamma_v = -\frac{dT_v}{dz} \rightarrow \text{Environment lapse rate} \quad (478)$$

$$\Gamma'_v = -\frac{dT'_v}{dz} \rightarrow \text{Parcel lapse rate} \quad (479)$$

$$\frac{d^2z}{dt^2} = g \frac{(\Gamma_v - \Gamma'_v)}{(T_{v0} - \Gamma_v z)} z \quad (480)$$

Taking $\frac{1}{T_{v0} - \Gamma_v z}$ for simplification;

$$\frac{1}{T_{v0} - \Gamma_v z} = \frac{1}{T_{v0}} \left(\frac{1}{1 - \frac{\Gamma_v z}{T_{v0}}} \right) \quad (481)$$

$$\frac{1}{T_{v0} - \Gamma_v z} = \frac{1}{T_{v0}} \left(1 - \frac{\Gamma_v z}{T_{v0}} \right)^{-1} \quad (482)$$

$$\text{since, } \frac{\Gamma_v z}{T_{v0}} \ll 1, \text{ we can rewrite above equation as:} \quad (483)$$

$$\frac{1}{T_{v0} - \Gamma_v z} \approx \frac{1}{T_{v0}} \left(1 + \frac{\Gamma_v z}{T_{v0}} \right) \quad (484)$$

Therefore, Eq.(480)

$$\frac{d^2z}{dt^2} \approx g(\Gamma_v - \Gamma'_v) \times \frac{1}{T_{v0}} \left(1 + \frac{\Gamma_v z}{T_{v0}} \right) \quad (485)$$

$$\frac{d^2z}{dt^2} \approx \frac{g}{T_{v0}} \left(\Gamma_v z + \frac{\Gamma_v^2 z^2}{T_{v0}} - \Gamma'_v z - \frac{\Gamma'_v \Gamma_v z^2}{T_{v0}} \right) \quad (486)$$

Ignoring z^2 terms, we get;

$$\frac{d^2z}{dt^2} \approx \frac{g}{T_{v0}} (\Gamma_v - \Gamma'_v) z \quad (487)$$

$$\frac{d^2z}{dt^2} - \frac{g}{T_{v0}} (\Gamma_v - \Gamma'_v) z = 0 \quad (488)$$

The above Eq.(488) is 2nd order differential equation, therefore we can rewrite equation as:

$$\frac{d^2z}{dt^2} - \omega^2 z = 0 \quad (489)$$

$$\text{where } \omega = \sqrt{\frac{g}{T_{v0}} (\Gamma_v - \Gamma'_v)}$$

26. Lecture 26 07/11/2024

26.1 . Stability analysis

3 possible solutions exists:

1. Stable solution i.e. $(\Gamma'_v - \Gamma_v) > 0$

$$\frac{d^2z}{dt^2} + \omega^2 z = 0 \quad (490)$$

General solution is :

$$z(t) = A \sin \omega t + B \cos \omega t \quad (491)$$

Boundary conditions : $t = 0, z = 0 \Rightarrow B = 0$

$$z(t) = A \sin \omega t \quad (492)$$

Time period of oscillation $\Rightarrow \tau = \frac{2\pi}{\omega}$

2. Unstable solution i.e. $(\Gamma'_v - \Gamma_v) < 0$

$$\frac{d^2z}{dt^2} - \omega^2 z = 0 \quad (493)$$

General solution is :

$$z(t) = A \exp(\omega t) + B \exp(-\omega t) \quad (494)$$

Boundary conditions : $t \rightarrow \infty \Rightarrow A = B \neq 0$

$$z(t) = A \exp(\omega t) \quad (495)$$

Time period of oscillation $\rightarrow \tau = \frac{2\pi}{\omega}$

3. Neutral solution i.e. $(\Gamma'_v - \Gamma_v) = 0$

$$\frac{d^2z}{dt^2} = 0 \quad (496)$$

General solution is:

$$z(t) = At + B \quad (497)$$

Boundary conditions : $t = 0 \Rightarrow A = 0$

$$\frac{dz(t)}{dt} = A \quad (498)$$

Time period of oscillation is **not defined**.

For unsaturated air parcel :

1. $\Gamma_{EL} > \Gamma_d \rightarrow$ atmosphere becomes unstable.
2. $\Gamma_{EL} < \Gamma_d \rightarrow$ atmosphere becomes stable.

For saturated air parcel :

1. $\Gamma_{EL} > \Gamma_s \rightarrow$ atmosphere becomes unstable.
2. $\Gamma_{EL} < \Gamma_s \rightarrow$ atmosphere becomes stable.
3. $\Gamma_{EL} = \Gamma_s \rightarrow$ atmosphere becomes neutral.

where,

Γ_{EL} = environment lapse rate

$\Gamma_d = 9.8^\circ\text{C/km}$

$\Gamma_s \approx 6.5^\circ\text{C/km}$ (depends on place and humidity)

1. $\Gamma_{EL} > \Gamma_d \rightarrow$ layer is absolutely unstable.
2. $\Gamma_{EL} < \Gamma_s \rightarrow$ layer is absolutely stable.
3. $\Gamma_d < \Gamma_{EL} < \Gamma_s \rightarrow$ layer is conditionally unstable (conditionally instability).




Figure 20. Case 1: $\Gamma_B > \Gamma_{dA}$




Figure 21. Case 2: $\Gamma_B < \Gamma_{dA}$




Figure 22. Case 3: $\Gamma_B = \Gamma_{dA}$

26.2 . Convective instability or Potential instability

Potential temperature (θ_e):

$$\theta_e = T \left(\frac{1000}{P} \right)^{\frac{R_d}{C_p}} \quad (499)$$

Taking logarithm on both sides,

$$\ln \theta_e = \ln T + \frac{R_d}{C_p} \ln (1000) - \frac{R_d}{C_p} \ln P \quad (500)$$

Differentiating above Equation w.r.t z

$$\frac{1}{\theta_e} \frac{\partial \theta_e}{\partial z} = \frac{1}{T} \frac{dT}{dz} - \frac{R_d}{C_p} \left(\frac{-dp}{dz} \right) \quad (501)$$


$$\frac{1}{\theta_e} \frac{\partial \theta_e}{\partial z} = \frac{1}{T} \frac{dT}{dz} - \frac{R_d}{C_p p} \left(\frac{-pg}{R_d T} \right) \quad (502)$$

$$\frac{1}{\theta_e} \frac{\partial \theta_e}{\partial z} = \frac{1}{T} \frac{dT}{dz} + \frac{1}{T} \left(\frac{g}{C_p} \right) \quad (503)$$


$$\frac{1}{\theta_e} \frac{\partial \theta_e}{\partial z} = -\frac{1}{T} \Gamma + \frac{1}{T} \Gamma_d \quad (504)$$

$$\frac{1}{\theta_e} \frac{\partial \theta_e}{\partial z} = \frac{1}{T} (\Gamma_d - \Gamma) \quad (505)$$

1. $\frac{d\theta_e}{dz} > 0 \rightarrow$ Potentially Stable
2. $\frac{d\theta_e}{dz} < 0 \rightarrow$ Potentially Unstable
3. $\frac{d\theta_e}{dz} = 0 \rightarrow$ Potentially Neutral



Temperature (T) [°C]



Temperature (T) [°C]

27. Lecture 27 08/11/2024

27.1 . Convective Available Potential Energy (CAPE) and Convective Inhibition (CIN)

$$\delta\omega = F \cdot dz \quad (506)$$

$$\delta\omega = madz \quad (507)$$

$$\delta\omega = m \frac{d^2 z}{dt^2} dz \quad (508)$$

Integrating above equation to get total work done by the parcel and using Eq.(473);

$$W = \int_i^f mg \left(\frac{T'_v - T_v}{T_v} \right) dz \quad (509)$$

$$w = \int_i^f g \left(\frac{T'_v - T_v}{T_v} \right) dz \quad (510)$$

Using hydrostatic equation/approximation Eq.(94);

$$w = \int_i^f \frac{-1}{\rho} \left(\frac{T'_v - T_v}{T_v} \right) dp \quad (511)$$

Using Ideal equation ($P = \rho R_d T_v$);

$$w = \int_i^f - \left(\frac{R_d \bar{\rho}_v}{P} \right) \left(\frac{T'_v - T_v}{\bar{\rho}_v} \right) dp \quad (512)$$

$$w = -R_d \int_i^f (T'_v - T_v) d(\ln(P)) \quad (513)$$

Therefore,

$$\text{CAPE} = -R_d \int_{Z_{LFC}}^{Z_{EL}} (T'_v - T_v) d(\ln(P)) \quad (514)$$

$$\text{CIN} = -R_d \int_{Z=0}^{Z_{LFC}} (T'_v - T_v) d(\ln(P)) \quad (515)$$

Theoretical maximum velocity

$$\frac{1}{2} w_{\max}^2 = \text{CAPE} \quad (516)$$

$$w_{\max} = \sqrt{2 \times \text{CAPE}} \quad (517)$$

- $< 0 \rightarrow \text{stable}$
- $0 - 1000 \rightarrow \text{marginally unstable}$
- $1000 - 2500 \rightarrow \text{moderately unstable}$
- $2500 - 3500 \rightarrow \text{highly unstable}$
- $> 3500 \rightarrow \text{extremely unstable (wind speed may reach upto 50-70m/s indicating storms)}$

Pressure level	Env. Temperature
800	Data
750	Data
700	Data
650	Data
600	Data
550	Data
500	Data
450	Data
400	Data
350	Data
300	Data




Figure 23. Solution of Question 27.1

28. Lecture 28 11/11/2024

- Cloud droplet size $\approx 1\mu\text{m}$.
- Rain drop size $\approx 1\text{mm}$.

28.1 . Clasius-Clapeyron Equation

Vapor to Water, condensation:


$$\frac{e_s}{T} = \frac{L}{T(\alpha_v - \alpha_w)} \approx \frac{L}{T\alpha_v} \quad (518)$$

Vapor to Ice, sublimation:

$$\frac{e_{si}}{T} = \frac{L_s}{T(\alpha_v - \alpha_i)} \approx \frac{L_s}{T\alpha_v} \quad (519)$$

Vapor to Ice, fusion:

$$\frac{p}{T} = \frac{L_f}{T(\alpha_w - \alpha_i)} \quad (520)$$



28.2 . Weigner-Bergeron-Findeisn Theory


Theory describes a process in mixed-phase clouds where ice crystals grow at the expense of surrounding supercooled water droplets. This theory explains how precipitation forms in cold clouds (those with temperatures below freezing) through the following mechanism:

1. Different Saturation Vapor Pressures: In a cold cloud with both ice crystals and supercooled water droplets, the saturation vapor pressure over ice is lower than that over liquid water. This means that water vapor is more likely to condense onto ice than onto liquid droplets.
2. Growth of Ice Crystals: Water vapor moves from the liquid droplets (which gradually evaporate) to the ice crystals, causing the ice crystals to grow. This transfer of water vapor from droplets to ice crystals results in the gradual disappearance of liquid droplets and an increase in ice crystal size.
3. Initiation of Precipitation: As ice crystals grow, they eventually become large enough to fall from the cloud as snowflakes or, if they melt on the way down, as raindrops.

This process is particularly important in middle and high latitudes, where clouds are often mixed-phase, and it provides a primary mechanism for precipitation in cold clouds.

29. Lecture 29 13/11/2024

29.1 . Classification of clouds



29.2 . Types of particles within the clouds

Collective condensed particle within the cloud '**hydrometeous**'


1. Cloud droplets $\rightarrow \sim 400 \mu\text{m}$ to $10\mu\text{m}$.
2. Raindrops \rightarrow A few hundred of μm to $3\text{nm} \sim 1\text{nm}$.
3. Ice crystals \rightarrow Tens of μm to hundred of μm .
4. Snow flakes \rightarrow Few cm, crystalline ice particles.
5. Grapel \rightarrow Few cm, when supercooled water freezes on the surface of ice crystals.
6. Hail \rightarrow Ice, around $5\text{mm} \sim 15\text{cm}$.

29.3 . Nucleation

Fundamental process of phase change is called as Nucleation. Nucleation are of 2 types:

1. **Homogeneous** : Involve foreign particles (aerosols), CNN (Cloud Condensation Nuclei)
2. **Heterogeneous**

Small thermal perturbation/attenuation can disintegrate i-mer. Embryo \rightarrow collection of water molecule. Germ \rightarrow activated embryo (Started to show water droplet properties).



One basic assumption of classic nucleation theory is that the population of i-mer embryos follows **Boltzman's distribution**.

tion.

$$N_i = N \exp\left(\frac{-\Delta E_i}{KT}\right) \quad (521)$$

$$N_i = N \exp\left(\frac{\mu_v - \mu_l}{KT}\right) \quad (522)$$

$$e = e_{\text{sat}} \exp\left(\frac{\mu_v - \mu_l}{KT}\right) \quad (523)$$

$$\mu_v - \mu_l = KT \ln\left(\frac{e}{e_{\text{sat}}}\right) \quad (524)$$

where,

N = number of molecules

μ_v and μ_l = chemical potentials of vapor and liquid resp.

Let us suppose that a small embryonic water droplet with volume (V) and surface (A) form from a pure supersaturated water vapor.

Decrease in energy

$$\Delta E = nV(\mu_v - \mu_l) \quad (525)$$

where,

n = No. of water vapor molecule.

Work is needed to be done to create surface area:

$$A\sigma \quad (526)$$

where,

A = Area

σ = surface energy

Net increase in the energy of the system:

$$\Delta E = A\sigma - nV(\mu_v - \mu_l) \quad (527)$$


$$\Delta E = A\sigma - nVKT \ln\left(\frac{e}{e_s}\right) \quad (528)$$

If the droplet is spherical shaped with radius R .


$$\Delta E = (4\pi R^2)\sigma - \frac{4}{3}\pi R^3 nKT \ln\left(\frac{e}{e_s}\right) \quad (529)$$

Where, R^* is critical radius.

1. Under subsaturated condition ($e < e_s$) $\rightarrow \Delta E > 0$ (Droplets will never form)



2. Under supersaturated condition ($e > e_s$) $\rightarrow \Delta E > 0$ up-



till R^* then $\Delta E < 0$


To find critical radius of embryo (R^*):

$$\frac{d(\Delta E)}{dR} = \frac{d\left[(4\pi R^2)\sigma - \frac{4}{3}\pi R^3 nKT \ln\left(\frac{e}{e_s}\right)\right]}{dt} = 0 \quad (530)$$

$$\frac{d(\Delta E)}{dR} = 8\pi R\sigma - 4\pi R^2 nKT \ln\left(\frac{e}{e_s}\right) = 0 \quad (531)$$


$$R^* = \frac{2\sigma}{nKT \ln\left(\frac{e}{e_s}\right)} \quad (532)$$

Eq.(532) is called **Kelvin's equation**




30. Lecture 30 14/11/2024


30.1 . Supersaturation with respect to plane surface of pure water



1. Larger chance of escape → rate of evaporation increases.



2. Lower chance of escape → rate of evaporation decreases.



∴ Saturation vapor pressure of pure water will be different for different geometry.

The vapor pressure adjacent to solution droplet is reduced as compared to pure water droplet.

30.2 . Köhler Equation

The Köhler equation describes the equilibrium vapor pressure over a curved water droplet, accounting for both curvature and solute effects.

Fractional reduction in the vapor pressure is equivalent to mole fraction.

Mole fraction of a pure water droplet is defined as number of moles of pure water in the solution by the total number of moles of the solution.

$$\mathcal{F} = \frac{n_{PW}}{n_{PW} + n_S} \quad (533)$$

Consider a solution of droplet of radius r that contains a mass m (in kg) dissolved in material of molecular mass M_S . For example, take solution of common salt in water:



Each molecule of the material dissolves in i ions in water.
∴ Effective number of moles will be:

$$n_{eff} = n_S = i \frac{m}{M_S} \quad (534)$$

If we assume ρ' is the density of solution, number of moles of pure water in the droplet is:

$$n_{PW} = \frac{\left(\frac{4}{3}\pi r^3 \rho' - M\right)}{M_w}$$

Mole fraction (\mathcal{F}) of water droplet, substitute Eq.(534) and Eq.(535) in Eq.(533):

$$\mathcal{F} = \frac{\left(\frac{4}{3}\pi r^3 \rho' - M\right)/M_w}{\left(\frac{4}{3}\pi r^3 \rho' - M\right)/M_w + im/M_S} \quad (535)$$

$$\mathcal{F} = \left[1 + \frac{imM_w}{M_S \left(\frac{4}{3}\pi r^3 \rho' - M \right)} \right]^{-1} \quad (536)$$

$$\frac{e}{e_s} = \exp \left(\frac{2\sigma}{nkTr} \right) \quad (537)$$

$$\frac{e}{e_s} \cdot \mathcal{F} = \exp \left(\frac{2\sigma}{nkTr} \right) \left[1 + \frac{imM_w}{M_S \left(\frac{4}{3}\pi r^3 \rho' - M \right)} \right]^{-1} \quad (538)$$



