# CS241 Lec 3

# Graham Cooper

May 11th, 2015

Recall: Example 1:  $\$3 \leftarrow \$5 + \$7$ 

Ex2:  $$3 \leftarrow 42 + 52$ 

lis \$d - load immediate & skip

Location	Binary	Hex	Meaning		
00000000	0000 0000 0000 0000 0010 1000 0001 0100	0x00002814	lis \$5		
00000004	0000 0000 0000 0000 0000 0000 0010 1010	0x0000002a	.word $42$		
00000008	0000 0000 0000 0000 0011 1000 0001 0100	$0 \times 00003814$	lis \$7		
0000000c	0000 0000 0000 0000 0000 0000 0011 0100	0x00000034	.word $52$		
Then appeared code from Ev 1					

Then appaned code from Ex 1.

## Assembly Language

- replace binary/hex encodings with easier to read shorthand
- less chance of error
- translation to binary can be automated (assembler)
- one line of assembly = 1 machine instruction (1 word)

#### **EX2**:

.word is not an instruction, it is a directive that teslls the assembler that the next word in the file should be literally 42// jr \$31 is return to loader

Ex3: Compute the absolute value of \$1, store in \$1, return

- $\bullet\,$  some instructions modify PC
  - jumps, eg jr
  - branches
- beq
  - branch if 2 regs are equal
  - increment PC by the given # of words
  - can branch backwards
- also bne "Branch not equal"
- "set less than"

address	$\operatorname{code}$	literal
00000000	slt \$2, \$1, \$0	compare $$1 < 0$
00000004	beq \$2, \$0, 1	if the above is false, skip over
80000000	sub \$1, \$0, \$1	$\$1 \leftarrow -\$1$
0000000c	jr \$31	exit program

**Ex 4 (looping):** Sum 1 ... 13 store in \$3.

address	$\operatorname{code}$	literal
0	lis \$2	$$2 \leftarrow 13$
4	.word 13	
8	add \$3, \$0, \$0	$\$3 \leftarrow 0$
$\mathbf{c}$	add \$3, \$2, \$3	\$3 += \$2
10	lis \$1	$\$1 \leftarrow 1$
14	.word 1	
18	sub \$2, \$2, \$1	-\$2
1c	bne \$2, \$0, 5	if $$2 \neq $0$ back to line c
20	jr \$31	exit program
$\underline{\mathbf{RAM}}$		·

- $\bullet$ lw "load-word" from RAM to regs
  - lw \$a, i(\$b)

$$-$$
\$a  $\leftarrow MEM[$ \$b  $+ i]$ 

- $\bullet\,$  sw "store-word" from regs to RAM
  - sw \$a, i(\$b) $MEM[\$b + i] \leftarrow \$a$

**Ex 5:** \$1 = address of an array, <math>\$2 = length of the array Place element 5 (0-based) into \$3

### Easy Way:

#### Hard Way:

Suppose \$5 contains the index of the item we want to fetch

### Mult Instruction Side Lesson

- mult \$a, \$b
- product of 2 32-bit #s is 64-bits (too big for a register)
- so two special registers, hi & lo to store the result of a mult
- $a, b \equiv hi:lo \leftarrow a \times b$

#### Revisit looping example

```
ls $2
.word 13
add $3, $0, $0
add $3, $3, $2
lis $1 (move above add)
.word 1 (move above add)
sub $2, $2, $1
bne $2, $0, -5 (becomes -3)
jr $31
```

Moving instructions into/out of branches, we must update branch offsets, and can be tricky

Instead, the assembler allows labelled instructions label : instr

eg: foo: add \$1, \$2, \$3

Assembler associates the name 'foo' with the address of the command add \$1, \$2, \$3 in memory

```
ls $2
.word 13
add $3, $0, $0
top: add $3, $3, $2
lis $1
.word 1
sub $2, $2, $1
bne $2, $0, top
jr $31
```