SOAP:


1_ScriptableVariables_Example_Scene

Table of Contents


OnValueChanged Variable References	2	
		8

Direct Access

If you click on the **prefab_player** in the scene hierarchy, you can see that he has a **Health** component. This component has a reference to a scriptable variable float called "example_float_playerCurrentHealth".




Play the game, then select the example_float_playerCurrentHealth variable in your project and change its value in the inspector. You can directly modify the value of the scriptable variable **in the inspector window at runtime.**




The game reacts automatically to those changes.

You can also directly modify the variables from the **Health** component itself:




Moreover, by clicking on the small arrow you can expand the inspector showing the other Scriptable Variable parameters You can also change them at runtime:



While still in play mode, click on the **Damage** button or the **Heal** button, you can affect the health directly. Let's look at the methods tied to these buttons by finding them in the hierarchy.

UICanvas/Bottom/Buttons






Traditionally, we would call Player->TakeDamage() or Player->Heal, but we can be more direct. Instead, we **directly access** the scriptable object variable and add a value; using the Add() public method from the editor.

It's very direct, and you don't always want that, but sometimes you do (especially when making a Hypercasual games). For things like increasing the level index, or other simple things, it can be useful to access them directly.

The FloatVariable and the IntVariable have 2 extra properties:

- IsClamped: enable the variable to be clamped.
- Min Max: the minimum and maximum values that it will be clamped to.

Note: Min Max is only shown if IsClamped is true.



Go ahead and set IsClamped to true on the playerCurrentHealth variable. As you can see, the minimum for is set to 0. If you go into play mode and click on the **Damage button** or try to set the health manually in the inspector, you can observe that the health will not go below 0.

By default, min and max are set to int.MinValue & int.MaxValue for IntVariable, and to float.MinValue & float.MaxValue for FloatVariables.

OnValueChanged

You can bind callback methods when the variable value changes.

Peek at the **Health.cs** class. As you can see, you can bind yourself to a variable. You don't need to constantly check in update for its value, you can simply subscribe to the **OnValueChanged** delegate that is called every time the value changes.

```
private void Start()
{
    _currentHealth.Value = _maxHealth.Value;
    _currentHealth.OnValueChanged += OnHealthChanged;
}

private void OnDestroy()
{
    _currentHealth.OnValueChanged -= OnHealthChanged;
}

private void OnHealthChanged(float newValue)
{
    var diff = newValue - _currentHealth.PreviousValue;
    if (diff<0)
    {
        OnDamaged(Mathf.Abs(diff));
    }
    else
    {
        OnHealed(diff);
    }
}</pre>
```

If you are familiar with UniRx library, it works the same as the reactive property but, in Soap, it is a reactive property that can also solve dependencies by being an scriptable object.


The field **previous value** of a variable can be useful in some cases, like in this example to determined whether we have been healed or if we have taken damage.

Note: do not forget to unsubscribe to the event in OnDestroy() or OnDisable(). As the scriptable variable is an asset, the event is still triggered in the inspector and can trigger your callback methods, displaying an error message.

Variable References

Finally, you might have noticed that _maxHealth's type is a **FloatReference** instead of a FloatVariable. It allows you to choose between a local value or scriptable variable.

This can be useful if you have multiple objects that shared the same components, let's say different cars that share the same controller. Each car can have a reference to a FloatReference for the speed. The player car will choose a FloatVariable and the other cars can just have a local variable.




All default types included in Soap have their corresponding reference scripts.

Solving Dependencies

If you click on the "prefab_player", you can look at the **Movement** Controller and the Input Detector.

If you press play, you can move the player with WASD / Arrow keys.



Here, we are **solving the dependency** of the movement controller with a scriptable variable. Input Detector **writes** to example_vector2_inputs (ScriptableVariableVector2) and Movement Controller **reads** from example_vector2_inputs.

Those 2 classes **don't know each other** and the only thing they need, is a scriptable object to write/read their data. You can imagine how this can be useful in other cases as well. You can have entire parts of your game **independent from another one**, relying only on scriptable objects for communication.

This is particularly useful when working across different scenes. For example, your UI elements can be in their own scene and reference Scriptable variables without needing to access anything specific to a scene.