应用层的原理(标识进程、C/S模型)

应用层的原理(标识进程、C/S模型) 基本的应用层协议(HTTP、FTP、DNS等)

应用层的原理(标识进程、C/S模型) 基本的应用层协议(HTTP、FTP、DNS等) 如何开发自己的应用层协议(Socket Programming)

Chapter 3: Transport Layer

Our goals:

- understand principles behind transport layer services:
 - multiplexing/demultiplexing
 - o reliable data transfer
 - flow control
 - congestion control

- learn about transport layer protocols in the Internet:
 - UDP: connectionless transport
 - TCP: connection-oriented transport
 - TCP congestion control


Chapter 3 outline

- □ 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- □ 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - o connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

Transport services and protocols

- provide logical communication between app processes running on different hosts
- transport protocols run in end systems
 - send side: breaks app messages into segments, passes to network layer
 - rcv side: reassembles segments into messages, passes to app layer
- more than one transport protocol available to apps
 - Internet: TCP and UDP



遵循章法

• 用词准确也是章法的一部分

| 互联网的五层架构 | 数据基本单位 |
|----------|--------------------|
| 应用层 | 消息(message) |
| 传输层 | 数据段(segment) |
| 网络层 | 数据包(datagram) |
| 链路层 | 数据帧(frame) |
| 物理层 | 符号(symbol)、比特(bit) |

Transport vs. network layer


- network layer: logical communication between hosts
- transport layer: logical communication between processes
 - relies on, enhances, network layer services

Household analogy:

- 12 kids sending letters to 12 kids
- processes = kids
- app messages = letters in envelopes
- hosts = houses
- transport protocol = Ann and Bill
- network-layer protocolpostal service

Internet transport-layer protocols

- reliable, in-order delivery (TCP)
 - congestion control
 - flow control
 - connection setup
- unreliable, unordered delivery: UDP
 - no-frills extension of "best-effort" IP
- services not available:
 - delay guarantees
 - bandwidth guarantees



Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- 3.3 Connectionless transport: UDP
- 3.4 Principles of reliable data transfer

- □ 3.5 Connection-oriented transport: TCP
 - o segment structure
 - o reliable data transfer
 - flow control
 - o connection management
- 3.6 Principles of congestion control
- 3.7 TCP congestion control

Multiplexing/demultiplexing


<u>Demultiplexing at rcv host:</u>

delivering received segments to correct socket

= socket = process


Multiplexing at send host:

gathering data from multiple sockets, enveloping data with header (later used for demultiplexing)



How demultiplexing works

- host receives IP datagrams
 - each datagram has source IP address, destination IP address
 - o each datagram carries 1 transport-layer segment
 - o each segment has source, destination port number
- host uses IP addresses & port numbers to direct segment to appropriate socket



TCP/UDP segment format

Connectionless demultiplexing

Create sockets with port numbers:

```
DatagramSocket mySocket1 = new
  DatagramSocket(12534);
```


- DatagramSocket mySocket2 = new
 DatagramSocket(12535);
- □ UDP socket identified by two-tuple:

(dest IP address, dest port number)

- When host receives UDP segment:
 - checks destination port number in segment
 - directs UDP segment to socket with that port number
- IP datagrams with different source IP addresses and/or source port numbers directed to same socket

Connectionless demux (cont)

DatagramSocket serverSocket = new DatagramSocket(6428);




SP provides "return address"

Connection-oriented demux


- TCP socket identified by 4-tuple:
 - source IP address
 - source port number
 - o dest IP address
 - dest port number
- recv host uses all four values to direct segment to appropriate socket

- Server host may support many simultaneous TCP sockets:
 - each socket identified by its own 4-tuple
- Web servers have different sockets for each connecting client
 - non-persistent HTTP will have different socket for each request

Connection-oriented demux (cont)



Connection-oriented demux: Threaded Web Server



Chapter 3 outline

- □ 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- □ 3.3 Connectionless transport: UDP
- □ 3.4 Principles of reliable data transfer

- □ 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - connection management
- ☐ 3.6 Principles of congestion control
- ☐ 3.7 TCP congestion control

UDP: User Datagram Protocol [RFC 768]

- "no frills," "bare bones" Internet transport protocol
- "best effort" service, UDP segments may be:
 - o lost
 - delivered out of order to app

connectionless:

- no handshaking between UDP sender, receiver
- each UDP segment handled independently of others

Why is there a UDP?

- no connection establishment (which can add delay)
- simple: no connection state at sender, receiver
- small segment header
- no congestion control: UDP can blast away as fast as desired

UDP: more

- often used for streaming multimedia apps
 - loss tolerant
 - rate sensitive
- other UDP uses
 - DNS*
 - SNMP
- reliable transfer over UDP: add reliability at application layer
 - application-specific error recovery!

Length, in bytes of UDP segment, including header

| → 32 bits → | | |
|---------------|------------|--|
| source port # | dest port# | |
| →length | checksum | |
| | | |
| | | |
| Application | | |
| data | | |
| (message) | | |
| | | |

22 6:44

UDP segment format

关于UDP的思考

UDP 提供不可靠数据传输服务

- 为什么DNS使用UDP?
- 为什么SNMP使用UDP?

UDP checksum

Goal: detect "errors" (e.g., flipped bits) in transmitted segment

Sender:


- treat segment contents as sequence of 16-bit integers
- checksum: addition (1's complement sum) of segment contents
- sender puts checksum value into UDP checksum field

Receiver:

- compute checksum of received segment
- check if computed checksum equals checksum field value:
 - NO error detected
 - YES no error detected. But maybe errors nonetheless? More later

Internet Checksum Example


- Note
 - When adding numbers, a carryout from the most significant bit needs to be added to the result
- Example: add two 16-bit integers



关于Checksum的思考

Checksum is an error detection method.

- How many bit errors Checksum can detect at most?
- Checksum is used in IP header, TCP header, and UDP header.



看不上UDP?

看不上UDP?

UDP的自身定位与比较优势

看不上UDP?

UDP的自身定位与比较优势 UDP潜力巨大,变得越发流行


Chapter 3 outline

- □ 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- □ 3.3 Connectionless transport: UDP
- □ 3.4 Principles of reliable data transfer

- □ 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - connection management
- ☐ 3.6 Principles of congestion control
- ☐ 3.7 TCP congestion control

Principles of Reliable data transfer


- important in app., transport, link layers
- □ top-10 list of important networking topics!



- (a) provided service
- characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)

Principles of Reliable data transfer


- important in app., transport, link layers
- top-10 list of important networking topics!



 characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)


Principles of Reliable data transfer

- important in app., transport, link layers
- top-10 list of important networking topics!



 characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)

Reliable data transfer: getting started




Reliable data transfer: getting started

We'll:


- incrementally develop sender, receiver sides of reliable data transfer protocol (rdt)
- consider only unidirectional data transfer
 - but control info will flow on both directions!
- use finite state machines (FSM) to specify sender, receiver

state: when in this "state" next state uniquely determined by next event



Rdt1.0: reliable transfer over a reliable channel

- underlying channel perfectly reliable
 - no bit errors
 - no loss of packets
- separate FSMs for sender, receiver:
 - sender sends data into underlying channel
 - receiver read data from underlying channel



sender

receiver

Rdt2.0: channel with bit errors

- underlying channel may flip bits in packet
 - checksum to detect bit errors
- the question: how to recover from errors:
 - o acknowledgements (ACKs): receiver explicitly tells sender that pkt received OK
 - negative acknowledgements (NAKs): receiver explicitly tells sender that pkt had errors
 - sender retransmits pkt on receipt of NAK
- new mechanisms in rdt2.0 (beyond rdt1.0):
 - error detection
 - receiver feedback: control msgs (ACK,NAK) rcvr->sender

rdt2.0: FSM specification

rdt_send(data)
snkpkt = make_pkt(data, checksum)
udt_send(sndpkt)

Wait for
call from above

Mak isNAK(rcvpkt)

ACK or NAK

rdt_rcv(rcvpkt) && isNAK(rcvpkt)

udt_send(sndpkt)

rdt_rcv(rcvpkt) && isACK(rcvpkt)


A

sender


receiver

rdt_rcv(rcvpkt) && corrupt(rcvpkt) udt send(NAK) Wait for call from below rdt_rcv(rcvpkt) && notcorrupt(rcvpkt) extract(rcvpkt,data) deliver_data(data) udt_send(ACK)

rdt2.0: operation with no errors



rdt2.0: error scenario



rdt2.0 has a fatal flaw!

What happens if ACK/NAK corrupted?

- sender doesn't know what happened at receiver!
- can't just retransmit: possible duplicate


Handling duplicates:

- sender retransmits current pkt if ACK/NAK garbled
- sender adds sequence number to each pkt
- receiver discards (doesn't deliver up) duplicate pkt

stop and wait

Sender sends one packet, then waits for receiver response

rdt2.1: sender, handles garbled ACK/NAKs



rdt2.1: receiver, handles garbled ACK/NAKs

rdt rcv(rcvpkt) && notcorrupt(rcvpkt) && has seq0(rcvpkt) extract(rcvpkt,data) deliver_data(data) sndpkt = make pkt(ACK, chksum) udt_send(sndpkt) rdt_rcv(rcvpkt) && (corrupt(rcvpkt) rdt_rcv(rcvpkt) && (corrupt(rcvpkt) sndpkt = make_pkt(NAK, chksum) sndpkt = make_pkt(NAK, chksum) udt_send(sndpkt) udt_send(sndpkt) Wait for Wait foi 0 from 1 from rdt_rcv(rcvpkt) && rdt_rcv(rcvpkt) && below, not corrupt(rcvpkt) && below not corrupt(rcvpkt) && has seq1(rcvpkt) has_seq0(rcvpkt) sndpkt = make pkt(ACK, chksum) sndpkt = make_pkt(ACK, chksum) udt_send(sndpkt) udt send(sndpkt) rdt_rcv(rcvpkt) && notcorrupt(rcvpkt) && has_seq1(rcvpkt) extract(rcvpkt,data) deliver_data(data) sndpkt = make_pkt(ACK, chksum) udt send(sndpkt)

rdt2.1: discussion

Sender:

- seq # added to pkt
- \square two seq. #'s (0,1) will suffice. Why?
- must check if received ACK/NAK corrupted
- twice as many states
 - state must "remember" whether "current" pkt has 0 or 1 seq. #


Receiver:

- must check if received packet is duplicate
 - state indicates whether O or 1 is expected pkt seq#
- note: receiver can not know if its last ACK/NAK received OK at sender

rdt2.2: a NAK-free protocol

- □ same functionality as rdt2.1, using ACKs only
- instead of NAK, receiver sends ACK for last pkt received OK
 - receiver must explicitly include seq # of pkt being ACKed
- duplicate ACK at sender results in same action as NAK: retransmit current pkt

rdt2.2: sender, receiver fragments




rdt3.0: channels with errors and loss


New assumption:

- underlying channel can also lose packets (data or ACKs)
 - checksum, seq. #, ACKs, retransmissions will be of help, but not enough
- Approach: sender waits "reasonable" amount of time for ACK
- retransmits if no ACK received in this time
- □ if pkt (or ACK) just delayed (not lost):
 - retransmission will be duplicate, but use of seq. #'s already handles this
 - receiver must specify seq # of pkt being ACKed
- requires countdown timer


rdt3.0 sender




rdt3.0 in action



(a) operation with no loss



rdt3.0 in action



RDT小结

目标: 在不可靠的信道上实现可靠数据传输

- ■情况1——考虑数据可能出现bit错误。
 - ■要求: 1,接收端具有检查错误、ACK的能力,从而发现错误并告知发送端; 2,发送端具有重传的能力。
 - ■但是,发送端一旦具有重传的能力,就会带来新的问题——发送端重传的数据被接收端当做新的数据。因此,要引入序列号。
 - ■最终的解决方案要整合三项机制:错误检查(Checksum)、ACK、序列号。

RDT小结

目标: 在不可靠的信道上实现可靠数据传输

- ■情况2——在情况1的基础上,考虑丢包。
 - ■要求: 1, 发送端要有检查丢包的能力: 设置 定时器, 一旦定时器超时, 就认为数据包丢失, 并重传。
 - ■但是,定时器超时并不一定意味着数据包丢失,有可能是因为数据包在网络中延迟太大。这样会造成接收端接收到重复的数据,好在序列号已经解决了这一问题。
 - ■最终的解决方案要整合四项机制:错误检查(Checksum)、ACK、序列号、定时器 Ransport Layer 3-51

RDT小结

目标: 在不可靠的信道上实现可靠数据传输

- ■是否还有第三种情况? 类比一下网购快递的过程
- ■是否考虑完全?四种情况的组合:发送端发现数据损坏、接收端发现数据损坏、发送端丢包、接收端丢包。
- ■定时器应如何设定?

Checksum、ACK、Re-tran.、Seq.、Timer

分别解决什么问题

Performance of rdt3.0

- rdt3.0 works, but performance stinks
- □ ex: 1 Gbps link, 15 ms prop. delay, 8000 bit packet:


$$d_{trans} = \frac{L}{R} = \frac{8000 \text{bits}}{10^9 \text{bps}} = 8 \text{ microseconds}$$

O U sender: utilization - fraction of time sender busy sending

$$U_{\text{sender}} = \frac{L/R}{RTT + L/R} = \frac{.008}{30.008} = 0.00027$$

- 1KB pkt every 30 msec -> 33kB/sec thruput over 1 Gbps link
- o network protocol limits use of physical resources!

rdt3.0: stop-and-wait operation




$$U_{\text{sender}} = \frac{L/R}{RTT + L/R} = \frac{.008}{30.008} = 0.00027$$

Pipelined protocols

Pipelining: sender allows multiple, "in-flight", yet-tobe-acknowledged pkts

- o range of sequence numbers must be increased
- buffering at sender and/or receiver




(a) a stop-and-wait protocol in operation

(b) a pipelined protocol in operation

□ Two generic forms of pipelined protocols: go-Back-N, selective repeat

Pipelining: increased utilization



Pipelining Protocols

Go-back-N: big picture:

- Sender can have up to N unacked packets in pipeline
- Rcvr only sends cumulative acks
 - Doesn't ack packet if there's a gap
- Sender has timer for oldest unacked packet
 - If timer expires, retransmit all unacked packets

Selective Repeat: big pic

- Sender can have up to N unacked packets in pipeline
- Rcvr acks individual packets
- Sender maintains timer for each unacked packet
 - When timer expires, retransmit only unack packet


Selective repeat: big picture

- Sender can have up to N unacked packets in pipeline
- Rcvr acks individual packets
- Sender maintains timer for each unacked packet
 - When timer expires, retransmit only unack packet

Go-Back-N

Sender:

- k-bit seq # in pkt header
- "window" of up to N, consecutive unack'ed pkts allowed




- ACK(n): ACKs all pkts up to, including seq # n "cumulative ACK"
 - may receive duplicate ACKs (see receiver)
- timer for each in-flight pkt
- timeout(n): retransmit pkt n and all higher seq # pkts in window

GBN: sender extended FSM

```
rdt send(data)
                       if (nextseqnum < base+N) {
                          sndpkt[nextseqnum] = make_pkt(nextseqnum,data,chksum)
                          udt send(sndpkt[nextseqnum])
                          if (base == nextseqnum)
                            start_timer
                          nextseqnum++
                       else
   Λ
                         refuse_data(data)
  base=1
  nextseqnum=1
                                           timeout
                                           start timer
                             Wait
                                           udt_send(sndpkt[base])
                                           udt send(sndpkt[base+1])
rdt_rcv(rcvpkt)
 && corrupt(rcvpkt)
                                           udt_send(sndpkt[nextsegnum-1])
                         rdt_rcv(rcvpkt) &&
                           notcorrupt(rcvpkt)
                         base = getacknum(rcvpkt)+1
                         If (base == nextseqnum)
                           stop_timer
                          else
                           start_timer
```


GBN: receiver extended FSM



ACK-only: always send ACK for correctly-received pkt with highest in-order seq

- may generate duplicate ACKs
- o need only remember expectedseqnum
- out-of-order pkt:
 - o discard (don't buffer) -> no receiver buffering!
 - Re-ACK pkt with highest in-order seq #


GBN in action



Selective Repeat

- receiver individually acknowledges all correctly received pkts
 - buffers pkts, as needed, for eventual in-order delivery to upper layer
- sender only resends pkts for which ACK not received
 - sender timer for each unACKed pkt
- sender window
 - N consecutive seq #'s
 - again limits seq #s of sent, unACKed pkts

Selective repeat: sender, receiver windows



(b) receiver view of sequence numbers

Selective repeat

-sender

data from above:

if next available seq # in window, send pkt

timeout(n):

- resend pkt n, restart timer
- ACK(n) in [sendbase,sendbase+N]:
- mark pkt n as received
- if n smallest unACKed pkt, advance window base to next unACKed seq #

-receiver

pkt n in [rcvbase, rcvbase+N-1]

- \Box send ACK(n)
- out-of-order: buffer
- in-order: deliver (also deliver buffered, in-order pkts), advance window to next not-yet-received pkt


pkt n in [rcvbase-N,rcvbase-1]

 \Box ACK(n)

otherwise:

ignore


Selective repeat in action



Selective repeat: dilemma

Example:

- seq #'s: 0, 1, 2, 3
- window size=3
- receiver sees no difference in two scenarios!
- incorrectly passes duplicate data as new in (a)
- Q: what relationship between seq # size and window size?



GBN、SR小结

| BASIS FOR COMPARISON | GO-BACK-N | SELECTIVE REPEAT |
|--------------------------|---|---|
| Basic | Retransmits all the frames that sent after the frame which suspects to be damaged or lost. | Retransmits only those frames that are suspected to lost or damaged. |
| Bandwidth Utilization | If error rate is high, it wastes a lot of bandwidth. | Comparatively less bandwidth is wasted in retransmitting. |
| Complexity | Less complicated. | More complex as it require to apply extra logic and sorting and storage, at sender and receiver. |
| Window size | N-1 | <= (N+1)/2 |

GBN、SR小结

| Sorting | Sorting is neither required at sender side nor at receiver side. | Receiver must be able to sort as it has to maintain the sequence of the frames. |
|-------------|---|--|
| Storing | Receiver do not store the frames received after the damaged frame until the damaged frame is retransmitted. | Receiver stores the frames received after the damaged frame in the buffer until the damaged frame is replaced. |
| Searching | No searching of frame is required neither on sender side nor on receiver | The sender must be able to search and select only the requested frame. |
| ACK Numbers | NAK number refer to the next expected frame number. | NAK number refer to the frame lost. |
| Use | It more often used. | It is less in practice because |

of its complexity.

GBN、SR小结

目标:提高效率,都属于滑动窗口方法

- 与之相对, RDT可以认为是一种Stop-And-Wait方法, 窗口大小为1。
- GBN与SR的通信效率一致,GBN适用于网络条件较好的情况,SR适用于网络条件较差的情况。
- GBN与SR的动画演示: http://www.ccs-
 labs.org/teaching/rn/animations/gbn sr/

Checksum、ACK、Re-tran.、Seq.、Timer

分别解决什么问题

RDT小结

目标: 在不可靠的信道上实现可靠数据传输

- ■情况1——考虑数据可能出现bit错误。
 - ■要求: 1,接收端具有检查错误、ACK的能力,从而发现错误并告知发送端; 2,发送端具有重传的能力。
 - ■但是,发送端一旦具有重传的能力,就会带来新的问题——发送端重传的数据被接收端当做新的数据。因此,要引入序列号。
 - ■最终的解决方案要整合三项机制:错误检查(Checksum)、ACK、序列号。

RDT小结

目标: 在不可靠的信道上实现可靠数据传输

- ■情况2——在情况1的基础上,考虑丢包。
 - ■要求: 1, 发送端要有检查丢包的能力: 设置 定时器, 一旦定时器超时, 就认为数据包丢失, 并重传。
 - ■但是,定时器超时并不一定意味着数据包丢失 ,有可能是因为数据包在网络中延迟太大。这 样会造成接收端接收到重复的数据,好在序列 号已经解决了这一问题。
 - ■最终的解决方案要整合四项机制:错误检查(Checksum)、ACK、序列号、定时器_{Pansport Layer}

RDT小结

目标: 在不可靠的信道上实现可靠数据传输

- ■是否还有第三种情况? 类比一下网购快递的过程
- ■是否考虑完全?四种情况的组合:发送端发现数据损坏、接收端发现数据损坏、发送端丢包、接收端丢包。
- ■定时器应如何设定?

Performance of rdt3.0

- □ rdt3.0 works, but performance stinks
- □ ex: 1 Gbps link, 15 ms prop. delay, 8000 bit packet:


$$d_{trans} = \frac{L}{R} = \frac{8000 \text{bits}}{10^9 \text{bps}} = 8 \text{ microseconds}$$

O U sender: utilization - fraction of time sender busy sending

$$U_{\text{sender}} = \frac{L/R}{RTT + L/R} = \frac{.008}{30.008} = 0.00027$$

- 1KB pkt every 30 msec -> 33kB/sec thruput over 1 Gbps link
- o network protocol limits use of physical resources!

rdt3.0: stop-and-wait operation




$$U_{\text{sender}} = \frac{L/R}{RTT + L/R} = \frac{.008}{30.008} = 0.00027$$

Pipelined protocols

Pipelining: sender allows multiple, "in-flight", yet-tobe-acknowledged pkts

- o range of sequence numbers must be increased
- buffering at sender and/or receiver




(a) a stop-and-wait protocol in operation

(b) a pipelined protocol in operation

Two generic forms of pipelined protocols: go-Back-N, selective repeat

Pipelining: increased utilization



Pipelining Protocols

Go-back-N: big picture:

- Sender can have up to N unacked packets in pipeline
- Rcvr only sends cumulative acks
 - Doesn't ack packet if there's a gap
- Sender has timer for oldest unacked packet
 - If timer expires, retransmit all unacked packets


Selective Repeat: big pic

- Sender can have up to N unacked packets in pipeline
- Rcvr acks individual packets
- Sender maintains timer for each unacked packet
 - When timer expires, retransmit only unack packet

Go-Back-N

Sender:

- k-bit seq # in pkt header
- "window" of up to N, consecutive unack'ed pkts allowed




- ACK(n): ACKs all pkts up to, including seq # n "cumulative ACK"
 - may receive duplicate ACKs (see receiver)
- timer for the oldest pkt
- timeout(n): retransmit pkt n and all higher seq # pkts in window

GBN: sender extended FSM

```
rdt send(data)
                       if (nextseqnum < base+N) {
                          sndpkt[nextseqnum] = make_pkt(nextseqnum,data,chksum)
                          udt send(sndpkt[nextseqnum])
                          if (base == nextseqnum)
                            start timer
                          nextseqnum++
                       else
   Λ
                         refuse_data(data)
  base=1
  nextseqnum=1
                                           timeout
                                           start timer
                             Wait
                                           udt_send(sndpkt[base])
                                           udt send(sndpkt[base+1])
rdt_rcv(rcvpkt)
 && corrupt(rcvpkt)
                                           udt_send(sndpkt[nextsegnum-1])
                         rdt_rcv(rcvpkt) &&
                           notcorrupt(rcvpkt)
                         base = getacknum(rcvpkt)+1
                         If (base == nextseqnum)
                           stop_timer
                          else
                            start_timer
```

GBN: receiver extended FSM




ACK-only: always send ACK for correctly-received pkt with highest in-order seq

- may generate duplicate ACKs
- o need only remember expectedseqnum

out-of-order pkt:

- o discard (don't buffer) -> no receiver buffering!
- Re-ACK pkt with highest in-order seq #


GBN in action



Selective Repeat

- receiver individually acknowledges all correctly received pkts
 - buffers pkts, as needed, for eventual in-order delivery to upper layer
- sender only resends pkts for which ACK not received
 - sender timer for each unACKed pkt
- sender window
 - N consecutive seq #'s
 - again limits seq #s of sent, unACKed pkts

Selective repeat: sender, receiver windows



(b) receiver view of sequence numbers

Selective repeat

-sender

data from above:

if next available seq # in window, send pkt

timeout(n):

resend pkt n, restart timer

ACK(n) in [sendbase,sendbase+N]:

- mark pkt n as received
- if n smallest unACKed pkt, advance window base to next unACKed seq #

-receiver

pkt n in [rcvbase, rcvbase+N-1]

- \Box send ACK(n)
- out-of-order: buffer
- in-order: deliver (also deliver buffered, in-order pkts), advance window to next not-yet-received pkt


pkt n in [rcvbase-N,rcvbase-1]

 \Box ACK(n)

otherwise:

ignore


Selective repeat in action



Selective repeat: dilemma

Example:

- seq #'s: 0, 1, 2, 3
- window size=3
- receiver sees no difference in two scenarios!
- incorrectly passes duplicate data as new in (a)
- Q: what relationship between seq # size and window size?



GBN、SR小结

| BASIS FOR COMPARISON | GO-BACK-N | SELECTIVE REPEAT |
|--------------------------|---|---|
| Basic | Retransmits all the frames that sent after the frame which suspects to be damaged or lost. | Retransmits only those frames that are suspected to lost or damaged. |
| Bandwidth Utilization | If error rate is high, it wastes a lot of bandwidth. | Comparatively less bandwidth is wasted in retransmitting. |
| Complexity | Less complicated. | More complex as it require to apply extra logic and sorting and storage, at sender and receiver. |
| Window size | N-1 | <= (N+1)/2 |

注 意 : 表 格 中 术 语与教材不尽 致

yer 3-20

GBN、SR小结

| Sorting | Sorting is neither required at sender side nor at receiver side. | Receiver must be able to sort as it has to maintain the sequence of the frames. |
|-------------|---|--|
| Storing | Receiver do not store the frames received after the damaged frame until the damaged frame is retransmitted. | Receiver stores the frames received after the damaged frame in the buffer until the damaged frame is replaced. |
| Searching | No searching of frame is required neither on sender side nor on receiver | The sender must be able to search and select only the requested frame. |
| ACK Numbers | NAK number refer to the next expected frame number. | NAK number refer to the frame lost. |
| Use | It more often used. | It is less in practice because of its complexity. |

注 意 教 致

GBN、SR小结

目标:提高效率,都属于滑动窗口方法

- 与之相对, RDT可以认为是一种Stop-And-Wait方法, 窗口大小为1。
- GBN与SR的通信效率一致,GBN适用于网络条件较好的情况,SR适用于网络条件较差的情况。
- GBN与SR的动画演示: http://www.ccs-
 labs.org/teaching/rn/animations/gbn sr/

Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- □ 3.3 Connectionless transport: UDP
- □ 3.4 Principles of reliable data transfer


- □ 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - connection management
- ☐ 3.6 Principles of congestion control
- ☐ 3.7 TCP congestion control

TCP: Overview

RFCs: 793, 1122, 1323, 2018, 2581

- point-to-point:
 - one sender, one receiver
- reliable, in-order byte steam:
 - no "message boundaries"
- pipelined:
 - TCP congestion and flow control set window size
- send & receive buffers

- □ full duplex data:
 - bi-directional data flow in same connection
 - MSS: maximum segment size
- connection-oriented:
 - handshaking (exchange of control msgs) init's sender, receiver state before data exchange
- flow controlled:
 - sender will not overwhelm receiver



TCP segment structure


URG: urgent data (generally not used)

ACK: ACK # valid

PSH: push data now (generally not used)

RST, SYN, FIN: connection estab (setup, teardown commands)

> Internet checksum' (as in UDP)



counting
by bytes
of data
(not segments!)

bytes rcvr willing to accept


TCP seq. #'s and ACKs

<u>Seq. #'s:</u>

byte stream
 "number" of first
 byte in segment's
 data

ACKs:

- seq # of next byte expected from other side
- cumulative ACK
- Q: how receiver handles out-of-order segments
 - A: TCP spec doesn't say, - up to implementor



simple telnet scenario

TCP Round Trip Time and Timeout

- Q: how to set TCP timeout value?
- longer than RTT
 - but RTT varies
- too short: premature timeout
 - unnecessary retransmissions
- too long: slow reaction to segment loss

- Q: how to estimate RTT?
- □ SampleRTT: measured time from segment transmission until ACK receipt
 - ignore retransmissions
- SampleRTT will vary, want estimated RTT "smoother"
 - average several recent measurements, not just current SampleRTT


TCP Round Trip Time and Timeout

```
EstimatedRTT = (1-\alpha)*EstimatedRTT + \alpha*SampleRTT
```

- Exponential weighted moving average
- influence of past sample decreases exponentially fast
- \Box typical value: $\alpha = 0.125$

Example RTT estimation:

RTT: gaia.cs.umass.edu to fantasia.eurecom.fr



TCP Round Trip Time and Timeout

Setting the timeout

- EstimtedRTT plus "safety margin"
 - large variation in EstimatedRTT -> larger safety margin
- first estimate of how much SampleRTT deviates from EstimatedRTT:

```
DevRTT = (1-\beta)*DevRTT + \beta*|SampleRTT-EstimatedRTT| (typically, \beta = 0.25)
```

Then set timeout interval:

```
TimeoutInterval = EstimatedRTT + 4*DevRTT
```

Chapter 3 outline

- □ 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- □ 3.3 Connectionless transport: UDP
- □ 3.4 Principles of reliable data transfer

- □ 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - connection management
- ☐ 3.6 Principles of congestion control
- ☐ 3.7 TCP congestion control

TCP reliable data transfer

- TCP creates rdt service on top of IP's unreliable service
- Pipelined segments
- Cumulative acks
- □ TCP uses single retransmission timer

- Retransmissions are triggered by:
 - timeout events
 - duplicate acks
- Initially consider simplified TCP sender:
 - ignore duplicate acks
 - ignore flow control, congestion control

TCP sender events:

data rcvd from app:

- Create segment with seq#
- □ seq # is byte-stream number of first data byte in segment
- start timer if not already running (think of timer as for oldest unacked segment)
- expiration interval: TimeOutInterval

timeout:

- retransmit segment that caused timeout
- restart timer

Ack rcvd:

- □ If acknowledges previously unacked segments
 - update what is known to be acked
 - o start timer if there are outstanding segments


```
NextSeqNum = InitialSeqNum
SendBase = InitialSeqNum
loop (forever) {
  switch(event)
  event: data received from application above
      create TCP segment with sequence number NextSeqNum
      if (timer currently not running)
         start timer
      pass segment to IP
      NextSeqNum = NextSeqNum + length(data)
   event: timer timeout
      retransmit not-yet-acknowledged segment with
           smallest sequence number
      start timer
   event: ACK received, with ACK field value of y
      if (y > SendBase) {
         SendBase = y
         if (there are currently not-yet-acknowledged segments)
              start timer
 } /* end of loop forever */
```

TCP sender (simplified)


Comment:

- SendBase-1: last cumulatively ack'ed byte <u>Example:</u>
- SendBase-1 = 71;
 y= 73, so the rcvr
 wants 73+;
 y > SendBase, so
 that new data is
 acked

TCP: retransmission scenarios



TCP retransmission scenarios (more)



Cumulative ACK scenario

TCP ACK generation [RFC 1122, RFC 2581]

| Event at Receiver | TCP Receiver action | |
|--|--|--|
| Arrival of in-order segment with expected seq #. All data up to expected seq # already ACKed | Delayed ACK. Wait up to 500ms for next segment. If no next segment, send ACK | |
| Arrival of in-order segment with expected seq #. One other segment has ACK pending | Immediately send single cumulative ACK, ACKing both in-order segments | |
| Arrival of out-of-order segment higher-than-expect seq. # . Gap detected | Immediately send duplicate ACK, indicating seq. # of next expected byte | |
| Arrival of segment that partially or completely fills gap | Immediate send ACK, provided that segment starts at lower end of gap | |

Fast Retransmit

- □ Time-out period often relatively long:
 - long delay before resending lost packet
- Detect lost segments via duplicate ACKs.
 - Sender often sends many segments back-toback
 - If segment is lost, there will likely be many duplicate ACKs.

- ☐ If sender receives 3 duplicate ACKs for the same data, it supposes that segment after ACKed data was lost:
 - fast retransmit: resend segment before timer expires




Figure 3.37 Resending a segment after triple duplicate ACK Layer 3-39

Fast retransmit algorithm:

```
event: ACK received, with ACK field value of y
          if (y > SendBase) {
             SendBase = y
             if (there are currently not-yet-acknowledged segments)
                 start timer
          else {
               increment count of dup ACKs received for y
               if (count of dup ACKs received for y = 3) {
                   resend segment with sequence number y
```

a duplicate ACK for already ACKed segment

fast retransmit


Chapter 3 outline

- □ 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- □ 3.3 Connectionless transport: UDP
- □ 3.4 Principles of reliable data transfer

- □ 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - connection management
- ☐ 3.6 Principles of congestion control
- ☐ 3.7 TCP congestion control

TCP Flow Control

receive side of TCP connection has a receive buffer:




 app process may be slow at reading from buffer

flow control.

sender won't overflow receiver's buffer by transmitting too much, too fast

■ speed-matching service: matching the send rate to the receiving app's drain rate

TCP Flow control: how it works



- (Suppose TCP receiver discards out-of-order segments)
- spare room in buffer
- = RcvWindow

- Rcvr advertises spare room by including value of RcvWindow in segments
- Sender limits unACKed data to RcvWindow
 - guarantees receive buffer doesn't overflow

Chapter 3 outline

- 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- □ 3.3 Connectionless transport: UDP
- □ 3.4 Principles of reliable data transfer

- □ 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - connection management
- ☐ 3.6 Principles of congestion control
- ☐ 3.7 TCP congestion control

TCP Connection Management

- Recall: TCP sender, receiver establish "connection" before exchanging data segments
- initialize TCP variables:
 - o seq. #s
 - buffers, flow control info (e.g. RcvWindow)
- client: connection initiator Socket clientSocket = new Socket ("hostname", "port number");
- server: contacted by client Socket connectionSocket = welcomeSocket.accept();

Three way handshake:

- Step 1: client host sends TCP SYN segment to server
 - specifies initial seq #
 - o no data
- **Step 2:** server host receives SYN, replies with SYNACK segment
 - server allocates buffers
 - specifies server initial seq.#
- <u>Step 3:</u> client receives SYNACK, replies with ACK segment, which may contain data


TCP Connection Management (cont.)

Closing a connection:

client closes socket:
 clientSocket.close();

Step 1: client end system sends TCP FIN control segment to server

Step 2: server receives FIN, replies with ACK. Closes connection, sends FIN.




TCP Connection Management (cont.)

<u>Step 3:</u> client receives FIN, replies with ACK.


 Enters "timed wait" will respond with ACK to received FINs

Step 4: server, receives ACK. Connection closed.

Note: with small modification, can handle simultaneous FINs.



TCP Connection Management (cont)



Chapter 3 outline

- □ 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- □ 3.3 Connectionless transport: UDP
- □ 3.4 Principles of reliable data transfer


- □ 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - connection management
- ☐ 3.6 Principles of congestion control
- ☐ 3.7 TCP congestion control


Principles of Congestion Control


Congestion:

- informally: "too many sources sending too much data too fast for network to handle"
- different from flow control!
- manifestations:
 - lost packets (buffer overflow at routers)
 - long delays (queueing in router buffers)
- □ a top-10 problem!

- two senders, two receivers
- one router, infinite buffers
- no retransmission









- large delayswhen congested
- maximum achievable throughput

- one router, finite buffers
- sender retransmission of lost packet



- \square always: $\lambda_{in} = \lambda_{out}$ (goodput)
- "perfect" retransmission only when loss: $\chi' > \chi_{\rm in}$ out,
- retransmission of delayed (not lost) packet makes λ_{in} (than perfect case) for same λ





"costs" of congestion:

- more work (retrans) for given "goodput"
- unneeded retransmissions: link carries multiple copies of pkt

- four senders
- multihop paths
- timeout/retransmit

Q: what happens as λ_{in} and λ'_{in} increase ?





Another "cost" of congestion:

■ when packet dropped, any "upstream transmission capacity used for that packet was wasted!

Approaches towards congestion control

Two broad approaches towards congestion control:

End-end congestion control:

- no explicit feedback from network
- congestion inferred from end-system observed loss, delay
- approach taken by TCP

Network-assisted congestion control:

- routers provide feedback to end systems
 - single bit indicating congestion (SNA, DECbit, TCP/IP ECN, ATM)
 - explicit rate sender should send at

Case study: ATM ABR congestion control


ABR: available bit rate:

- "elastic service"
- □ if sender's path "underloaded":
 - sender should use available bandwidth
- if sender's path congested:
 - sender throttled to minimum guaranteed rate

RM (resource management) cells:

- sent by sender, interspersed with data cells
- bits in RM cell set by switches ("network-assisted")
 - NI bit: no increase in rate (mild congestion)
 - O CI bit: congestion indication
- RM cells returned to sender by receiver, with bits intact

Case study: ATM ABR congestion control



- two-byte ER (explicit rate) field in RM cell
 - o congested switch may lower ER value in cell
 - sender' send rate thus maximum supportable rate on path
- EFCI bit in data cells: set to 1 in congested switch
 - o if data cell preceding RM cell has EFCI set, sender sets CI bit in returned RM cell

Chapter 3 outline


- □ 3.1 Transport-layer services
- 3.2 Multiplexing and demultiplexing
- □ 3.3 Connectionless transport: UDP
- □ 3.4 Principles of reliable data transfer

- □ 3.5 Connection-oriented transport: TCP
 - segment structure
 - o reliable data transfer
 - flow control
 - connection management
- ☐ 3.6 Principles of congestion control
- □ 3.7 TCP congestion control

TCP congestion control: additive increase, multiplicative decrease

- Approach: increase transmission rate (window size), probing for usable bandwidth, until loss occurs
 - additive increase: increase CongWin by 1 MSS every RTT until loss detected
 - multiplicative decrease: cut CongWin in half after loss

Saw tooth behavior: probing for bandwidth



TCP Congestion Control: details

- Roughly,

rate =
$$\frac{CongWin}{RTT}$$
 Bytes/sec

CongWin is dynamic, function of perceived network congestion

How does sender perceive congestion?

- loss event = timeout or3 duplicate acks
- TCP sender reduces rate (CongWin) after loss event

three mechanisms:

- AIMD
- slow start
- conservative after timeout events


TCP Slow Start

- When connection begins, CongWin = 1 MSS
 - Example: MSS = 500 bytes & RTT = 200 msec
 - initial rate = 20 kbps
- available bandwidth may be >> MSS/RTT
 - desirable to quickly ramp up to respectable rate

When connection begins, increase rate exponentially fast until first loss event

TCP Slow Start (more)

- When connection begins, increase rate exponentially until first loss event:
 - double CongWin every RTT
 - done by incrementing CongWin for every ACK received
- Summary: initial rate is slow but ramps up exponentially fast



Refinement: inferring loss

- ☐ After 3 dup ACKs:
 - O Congwin is cut in half
 - window then grows linearly
- But after timeout event:
 - CongWin instead set to 1 MSS;
 - window then grows exponentially
 - o to a threshold, then grows linearly


Philosophy:

□ 3 dup ACKs indicates network capable of delivering some segments timeout indicates a "more alarming" congestion scenario

Refinement

Q: When should the exponential increase switch to linear?

A: When CongWin gets to 1/2 of its value before timeout.



Implementation:

- Variable Threshold
- ☐ At loss event, Threshold is set to 1/2 of CongWin just before loss event

Summary: TCP Congestion Control

- When CongWin is below Threshold, sender in slow-start phase, window grows exponentially.
- □ When CongWin is above Threshold, sender is in congestion-avoidance phase, window grows linearly.
- □ When a triple duplicate ACK occurs, Threshold set to CongWin/2 and CongWin set to Threshold.
- □ When timeout occurs, Threshold set to CongWin/2 and CongWin is set to 1 MSS.

TCP sender congestion control

| State | Event | TCP Sender Action | Commentary |
|---------------------------------|---|--|---|
| Slow Start (SS) | ACK receipt for previously unacked data | CongWin = CongWin + MSS, If (CongWin > Threshold) set state to "Congestion Avoidance" | Resulting in a doubling of CongWin every RTT |
| Congestion Avoidance (CA) | ACK receipt for previously unacked data | CongWin = CongWin+MSS * (MSS/CongWin) | Additive increase, resulting in increase of CongWin by 1 MSS every RTT |
| SS or CA | Loss event detected by triple duplicate ACK | Threshold = CongWin/2, CongWin = Threshold, Set state to "Congestion Avoidance" | Fast recovery, implementing multiplicative decrease. CongWin will not drop below 1 MSS. |
| SS or CA | Timeout | Threshold = CongWin/2, CongWin = 1 MSS, Set state to "Slow Start" | Enter slow start |
| SS or CA | Duplicate ACK | Increment duplicate ACK count for segment being acked | CongWin and Threshold not changed |

TCP sender congestion control

| State | Event | TCP Sender Action | Commentary |
|---------------------------------|---|--|---|
| Slow Start (SS) | ACK receipt for previously unacked data | CongWin = CongWil + MSS, If (CongWin > Threshold) set state to "Congestion Avoidance" | Resulting in a doubling of CongWin every R 1 Why? |
| Congestion Avoidance (CA) | ACK receipt for previously unacked data | CongWin = CongWin+MSS * (MSS/CongWin) Why? | Additive increase, resulting in increase of CongWin by 1 MSS every RTT |
| SS or CA | Loss event detected by triple duplicate ACK | Threshold = CongWin/2, CongWin = Threshold, Set state to "Congestion Avoidance" | Fast recovery, implementing multiplicative decrease. CongWin will not drop below 1 MSS. |
| SS or CA | Timeout | Threshold = CongWin/2, CongWin = 1 MSS, Set state to "Slow Start" | Enter slow start |
| SS or CA | Duplicate ACK | Increment duplicate ACK count for segment being acked | CongWin and Threshold not changed |

TCP throughput

- What's the average throughout of TCP as a function of window size and RTT?
 - Ignore slow start
- □ Let W be the window size when loss occurs.
- When window is W, throughput is W/RTT
- Just after loss, window drops to W/2, throughput to W/2RTT.
- □ Average throughout: .75 W/RTT

TCP Futures: TCP over "long, fat pipes"


- □ Example: 1500 byte segments, 100ms RTT, want 10 Gbps throughput
- □ Requires window size W = 83,333 in-flight segments
- Throughput in terms of loss rate:

$$\frac{1.22 \cdot MSS}{RTT \sqrt{L}}$$

- \Box \rightarrow L = 2·10⁻¹⁰ Wow
- □ New versions of TCP for high-speed

TCP Fairness


Fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K



Why is TCP fair?

Two competing sessions:

- Additive increase gives slope of 1, as throughout increases
- multiplicative decrease decreases throughput proportionally



Fairness (more)

Fairness and UDP

- Multimedia apps often do not use TCP
 - do not want rate throttled by congestion control
- Instead use UDP:
 - pump audio/video at constant rate, tolerate packet loss
- Research area: TCP friendly

Fairness and parallel TCP connections

- nothing prevents app from opening parallel connections between 2 hosts.
- Web browsers do this
- Example: link of rate R supporting 9 connections;
 - o new app asks for 1 TCP, gets rate R/10
 - o new app asks for 11 TCPs, gets R/2!

拥塞控制小结

目标:根据网络拥塞情况,限制发送方向网络发送数据的速率

■与流控制的异同?

■相同:限制发送方的发送速率。

■不同:流控制是根据接收端的情况来调整,拥

塞控制是根据网络的情况来调整。

目标:根据网络拥塞情况,限制发送方向网络发送数据的速率

- ■拥塞控制的两类方法
 - ■端到端的拥塞控制
 - ■网络辅助的拥塞控制
- ■TCP拥塞控制:默认的TCP采用端到端的拥塞控制,最新的TCP改进协议也能选择性的实现网络辅助拥塞控制;另有支持网络辅助控制的新型传输层协议(DCCP、DCTCP等)

TCP如何实现拥塞控制?设置CWND!

- ■如何设置CWND? 三个机制
 - ■Congestion Avoidence 冲突避免
 - ■Slow Start 慢启动
 - ■Fast Recovery 快速回复

TCP拥塞控制的演进

■基于丢包的

- Tahoe 早期版本
- Reno 经典版本,适用于低时延、低带宽
- ■Bic Kernel 2.6.18之前的默认算法,适用于高带宽、低丢包率
- Cubic Kernel 2.6.18以后的默认算法,适用于高带宽、低丢包率

■基于RTT的

- Vegas 由于抢占能力差,未能在TCP普遍采用
- FastTCP

TCP拥塞控制的演进

- ■基于链路容量的
 - ■BBR 谷歌2016年提出,已在Google、Youtube数据中心部署,延迟降低53%(全球)、80%(时延较高的国家),已集成进新版本的Linux;适用于高带宽、高时延、有一定丢包率
- ■基于学习的
 - Remy

TCP拥塞控制的改进

- ■TCP拥塞控制的改进版本太多了!
- ■通过grep TCP_CONG /boot/config-\$(uname -r) 查询系统支持的TCP拥塞控制算法

TCP拥塞控制为什么难?

- ■没有明确的拥塞状态信号,只能使用ACK或丢包, 充当隐式信号
- ■分布式

如何评价TCP拥塞控制?

- TCP拥塞控制算法(以AIMD为例)基于大量的工程见解和 在运行网络中的拥塞控制经验而开发。
- 在TCP研发后的十年,理论分析显示TCP拥塞控制算法用一 种分布式异步优化算法, 使得用户和网络性能的几个重要 方面同时被优化。
- "广受赞誉"的算法

传输层总结

logical communication between app processes running on different hosts

- ■Two Top-10 problems
 - Reliable data transfer
 - Congestion Control
- ■Two transport layer protocols
 - UDP and TCP
- ■Beyond UDP and TCP
 - DCCP、DCTCP
 - QUIC

传输层总结

TCP的先进性

- TCP/IP 的发明早于PC、服务器、智能手机和平板电脑,也早于以太网、DSL、Wi-Fi等,还早于Web、社交网络、流媒体等。TCP/IP协议预见了对于联网协议的需求,一方面为应用提供广泛支持,另一方面允许运行在各种链路层协议上。
- ■1974年TCP/IP发明;1986年遭遇网络拥塞问题,从而加入拥塞控制;拥塞控制协议一直在改进,2010年后新的联网方式推动拥塞控制协议变革。
- Vinton Cerf 与 Robert Kahn由于发明TCP/IP的贡献于 2004年获得图灵奖 Transport Layer 3-83

Chapter 3: Summary

- principles behind transport layer services:
 - o multiplexing, demultiplexing
 - o reliable data transfer
 - flow control
 - congestion control
- instantiation and implementation in the Internet
 - o UDP
 - o TCP

Next:

- leaving the network "edge" (application, transport layers)
- □ into the network "core"

思考题



- □为什么TCP是三次握手?
 - ○不是两次?
 - ○不是四次?

思考题



- □为什么TCP是四次挥手?
 - ○不是两次?
 - 为什么还有等待时间?
- ■感兴趣的同学可以把自己的思考发到我的邮箱 ,截止时间为下次上课前。
 - yangzheng@tsinghua.edu.cn