### Skew-Normal

#### Parametrisation

The Skew-Normal distribution is

$$f(y) = 2\frac{\sqrt{w\tau}}{\sqrt{2\pi}} \exp\left(-\frac{1}{2}w\tau (y-\mu)^2\right) \Phi(a \ a_{\max}[w\tau (y-\mu)])$$

for continuously responses y where  $\Phi(\cdot)$  is the cumulative distribution function for a standard Normal, and

 $\mu$ : is the the location parameter

 $\tau$ : is the inverse scale

w: is a fixed weight, w > 0,

a: is the shape parameter

 $a_{\text{max}}$ : is the (fixed) maximum value of the shape paramter (added for stability reasons). Default value is 5.

#### **Link-function**

The location parameter is linked to the linear predictor by

$$\mu = \eta$$

#### Hyperparameters

The inverse scale is represented as

$$\theta_1 = \log \tau$$

and the prior is defined on  $\theta_1$ .

The shape parameter is

$$a = 2\frac{\exp(\theta_2)}{1 + \exp(\theta_2)} - 1$$

and the prior is defined on  $\theta_2$ .

## **Specification**

- family = sn
- Required arguments: y and w (keyword weights). The weights has default value 1.
- Optional control arguments: sn.shape.max. Default value is 5.0.

### Example

This is a simulated example requiring the package sn.

library(sn)
n = 1000
z = rnorm(n)
y = z + rsn(n, shape = 2)
formula = y ~ z

# Notes

None.