# BSc (Hons) Computer Science

University of Portsmouth Third Year

## **Advanced Networks**

M21279 Semester 1

Hugh Baldwin

hugh.baldwin@myport.ac.uk

# **Contents**

1	Lecture - Introduction	2
2	Lecture - Signal Encoding	3
3	Seminar - Encoding Exercises	6
4	Lecture - Signal Encoding II	7
5	Seminar - Encoding Exercises II	10
6	Lecture - Security	11
7	Lecture - Local Area Networks	14

## **Lecture - Introduction**

11:00 30/09/24 Asim Ali

#### **Admin**

- · Lectures given by Dr Asim Ali
- Office BK 2.20
  - Monday 1300-1400
  - Thursday 1100-1200
- 2 hour lecture every week (PK 2.01)
- 1 hour seminar every week (AG 1.03)

The module information is available at the URL below:

https://course-module-catalog.port.ac.uk/#/moduleDetail/M21279/2024%2F25

#### **Assessments**

This module is assessed by one exam and one piece of coursework as below

- 60%, 90 minute Exam covering LO1,2,3&4 TB1 assessment period (January)
- 40%, Group coursework covering LO5 2-4 members *or* individual (but not recommended)
  - 5 pages maximum
  - Template provided
  - Previous samples provided

Hugh Baldwin **2** of 15 M21279

## **Lecture - Signal Encoding**

11:30 30/09/24 Asim Ali

### **Signals**

(In this context) Signals are typically electromagnetic waves that carry information using some method of encoding. This means that the 'shape' of the signal is changed to represent information. There are three main types of signal—

- Analogue Signals, which vary continuously and smoothly over time
- Digital Signals, which have only 2 levels and change near instantly
- Discrete Signals, which have 2 or more levels and change near instantly

When information is transmitted, it is often converted between many different signals before it reaches the destination. For example, if you have ADSL internet, your computer sends the data as a digital signal to the modem, which is then converted to an analogue signal before it is transmitted across a POTS network (Plain Old Telephone System), then the receiver's modem converts it back to a digital signal before it is sent on to the receiver.

## **Digital Signal Encoding**

There are many methods of encoding a digital signal, but some of the most common are-


- Non-return to Zero Level (NRZ-L)
  - 0 High voltage level
  - 1 Low voltage level
- Non-return to Zero Inverted (NRZ-I)
  - 0 No transition (high-low or low-high voltage level) on clock pulse
  - 1 Transition on clock pulse
- Bipolar-AMI
  - 0 Zero voltage
  - 1 Alternating positive or negative voltage level
- MLT-3 (Multi-Level Transmit 3)
  - 0 Remain at the same voltage level
  - 1 Transition to the next voltage level
  - Uses 3 voltage levels, named +1,0&-1 but can be any arbitrary voltages
- Manchester
  - 0 Transition from high-low voltage level in the middle of the clock interval
  - 1 Transition from low-high voltage level
- Differential Manchester

- 0 Transition (high-low or low-high voltage level) on clock pulse
- 1 No transition on clock pulse
- Always transitions in the middle of the clock interval

In this context, the high and low voltage levels can be whatever you like, but are typically either a positive and negative voltage of the same magnitude, or are a positive voltage and zero. The most common voltages used for signalling are 3.3, 5 and 12 volts. In the case of Bipolar-AMI, the 3 voltage levels can be arbitrary, and don't have to be, for example +5, 0 and -5 volts.

#### **Diagrams**

Below is the binary string 01100110 encoded using all of the above encoding schemes. This assumes that the previous state before the transmission starts is always low, and that each vertical dotted line represents a clock pulse.







Figure 2.1: Non-return to Zero Level (NRZ-L)

Figure 2.2: Non-return to Zero Inverted (NRZ-I)







Figure 2.3: Bipolar-AMI

Figure 2.4: Multi-Level Transmit 3 (MLT-3)






Figure 2.5: Manchester

Figure 2.6: Differential Manchester

#### **Carrier Waves and Modulation**

A carrier wave is a continuous waveform that, on it's own, carries no information. This carrier wave is then modified by another signal to convey information. This modification can be of it's amplitude, frequency, phase, or a combination of all 3. This is known as modulation, hence the names AM (Amplitude Modulation) and FM (Frequency Modulation) for the two types of analogue radio.

#### **Digital-to-Analogue Encoding**

There are several methods of encoding a digital signal on an analogue transmission medium. In the case of sending digital data over a POTS network, the signal is encoded onto a carrier wave in the range of 300-3400Hz using a MoDem (Modulator-Demodulator). The main methods of encoding are—

- Amplitude-Shift keying (ASK)
- Frequency-Shift keying (FSK)
  - Binary FSK (BFSK)
  - Multiple FSK (MFSK)
- Phase-Shift keying (PSK)
  - Binary PSK 1 = A sine wave, 0 = The same sine wave shifted by  $180^{\circ}$
  - Differential PSK (DPSK) 1 = The previous sine wave shifted by  $180^{\circ}$ , 0 = The previous sine wave
  - Multiple-level PSK
- Quadratic AM (Combination of ASK and PSK)

The sender and receiver may use different frequencies as to allow full-duplex data transmission on the same physical medium or radio channel. Full-duplex meaning full-speed transmission in both directions simultaneously.

#### **Diagrams**




Figure 2.7: Amplitude-Shift Keying




Figure 2.9: Binary Phase-Shift Keying




Figure 2.8: Binary Frequency-Shift Keying




Figure 2.10: Differential Phase-Shift Keying

# **Seminar - Encoding Exercises**

12:00 03/10/24 Asim Ali

Figure 3.1: Encode the binary data 11000011 with the MLT-3 encoding scheme




Figure 3.2: Encode the binary data 11000011 with the Non-Differential Manchester encoding scheme





Figure 3.3: Encode the binary data 11000011 with the Differential Manchester encoding scheme



# **Lecture - Signal Encoding II**

11:00 07/10/24 Asim Ali

#### **Transmission Media**

There are many different mediums which can be used to transmit information. In the case of networks, there are two main types, guided and unguided media.

- · Guided Media
  - The signal is contained within a medium, such as
  - Copper cable (twisted pair, coaxial, etc)
  - Fibre optics
- · Unguided Media
  - The signal is sent out without containment, through the air
  - This does not mean that the signal is not directional, microwave networks are often highly directional to reduce signal drop-off and interference
  - Microwave, Radio, Cellular and Satellite

## **Signal Properties**

- Data Rate The speed in bits per second (bps or b/s) at which data can be communicated
- Error The reception of a 1 when 0 was transmitted, or vice versa
- Error Rate The rate at which errors occur, usually as a ratio or percentage
- Frequency Bandwidth The difference between the upper and lower frequency in a continuous frequency band
- Channel Capacity The maximum rate at which data can be transmitted through a channel
- **Signal-to-Noise Ratio** The ratio of the signal power to noise power in decibels (dB)

#### **Interference and Noise**

#### Definition

**Interference** is when two signals are added together. There are two main types of interference – constructive and destructive. When two signals combine to create a signal with a higher amplitude, this is constructive interference. If the amplitude is reduced, this is destructive interference.

#### Definition

**Noise** is any other signal which interferes with the desired signal along the medium of transmission. Typically, any noise in a signal will make it more difficult to decode, since the signal may be reduced in amplitude or shifted in phase.

Hugh Baldwin **7** of 15 M21279




Figure 4.1: Constructive interference

Figure 4.2: Destructive interference

M21279

## **Securing a Signal**

When a signal is sent through any media, if a third party has access to the same media, they can intercept, block and even fake signals. This is because there is no inherent security in an electromagnetic wave, so we need to find ways of securing it.

### **Spread Spectrum**

If we were to transmit a signal using a wide range of the spectrum, rather than a single frequency, it makes it harder for a third party to entirely block the signal. This method is often used in military applications, as well as wired and wireless networks. Three common techniques are—

- Frequency Hopping Spread Spectrum (FHSS)
  - Data is sent using one of the previously discussed analogue transmission techniques, but the carrier frequency is changed rapidly across a wide spectrum, using a code or pattern known by both the transmitter and receiver
  - This makes it harder to intercept or block transmissions, as long as the pattern of frequency hopping is not known
  - It is also very resilient to narrowband interference (interference over a small band of frequencies)
- Direct Sequence Spread Spectrum (DSSS)
  - Each bit of the data is represented by multiple bits of the transmitted signal, using a spreading code
  - The bits in the PN sequence are known as chips, and the sequence of them the chip sequence
  - One technique is to combine the data with the spreading code bit stream using an exclusive-or
- Code Division Multiple Access (CDMA)

## **Multiplexing**

#### Definition

**Multiplexing** is sending multiple data streams or signals over a single transmission medium.

#### **Frequency Division**

With frequency division multiplexing, you have a transmission medium which can send data over a wide spectrum of frequencies, and multiple signals you need to send at the same time. If you modulate the different signals using a different carrier frequency for each, and leave a suitable gap between them, you can then combine the waves together to create a single composite wave which encodes the data of all the streams. The receiver then needs to know only the frequency of the signal they need to receive, and pass the composite wave through a filter for that specific frequency to recover the signal intended for them.

#### **Time Division**

With time division multiplexing, each of the signals gets a certain share of time in which it can be transmitted. This often means that the data needs to be buffered on both ends, so may be more costly to implement. This also greatly limits the bandwidth available to each signal, as it would be split between all of the signals on the same channel.

### **Code Division Multiple Access (CDMA)**

CDMA is a multiplexing technique which can be used with a spread-spectrum signal. Given a data stream of bit rate R, we assign each bit a unique user code of n according to a Walsh matrix. If a user, k, sends a 1, the transmitter sends the chip code ck, and if they send a 0, the transmitter sends the inverse of that chip code, c'k. The chip codes of all users will add up to a bipolar signal, D. The receiver decodes the signal for a specific user with a function, by taking the cartesian product of D and the specific chip code ck,  $D \times ck$ . If  $D \times ck = n$  then a 1 is received, and if  $D \times ck = -n$  then a 0 is received.

#### Example

We have 4 users, with chip codes as follows

- A: (-1, -1, -1, -1)
- B: (-1, +1, -1, +1)
- C: (-1, -1, +1, +1)
- D: (-1, +1, +1, -1)

If the users were to send 1,1,1,0 respectively, then we would add up the signals such that A+B+C+D'=(-1,-1,-1,-1)+(-1,+1,-1,+1)+(-1,-1,+1,+1)+(+1,-1,-1,+1)=(-2,-2,-2,+2)

Then, the receivers filter out each individual signal by multiplying the received signal by the chip code of the signal they're interested in. To get back the signal for A, you would do the following  $(-2,-2,-2,+2)\times(-1,-1,-1,-1)=(-2\times-1)+(-2\times-1)+(-2\times-1)+(+2\times-1)=2+2+2-2=4$ , which shows that A was sending a 1.

# **Seminar - Encoding Exercises II**

12:00 10/10/24 Asim Ali




Figure 5.1: BFSK representation of the binary number 11000011




Figure 5.2: BPSK representation of the binary number 11000011




Figure 5.3: DPSK representation of the binary number 11000011




Figure 5.4: DSSS encoding and decoding of the binary number  $1001\,$ 

## **Lecture - Security**

11:00 14/10/24 Asim Ali

### **Security Factors**

There are three main security factors we need to consider-

- · Confidentiality
  - Only authorised parties should be able to read the information
- Integrity
  - Only authorised parties should be able to modify, create and delete information
- · Availability
  - Authorised parties should always have access to the information

## **Types of Attackers**

- Passive Attackers
  - The attacker only listens to the messages, so they can only read the information
- Active Attackers
  - The attacker listens, modifies and sends messages, so they can read the information, modify it
    or fabricate it entirely

To overcome both of these types of attacker, you can encrypt the data, meaning that it is unreadable by any third parties, and if someone attempts to modify or spoof a message, it will not be encrypted with the same key and so the receiver will know it was not sent by the correct person.

## **Symmetric (Shared Key) Encryption**

Symmetric key encryption requires the sender and receiver to already have a shared key, which will then be used to both encrypt and decrypt the messages.

#### **DES (Data Encryption Standard)**

Plaintext is split into 64-bit blocks. The key is 56-bits long and 16 subkeys are generated for 16 rounds of cryptography. The subkeys are then used in reverse order to decrypt the data. Because this quickly became insecure, Triple-DES was created as a new standard, which is as literal as the name suggests. You simply encrypt the data three times with three different keys, then decrypt 3 times in reverse order.

#### **AES (Advanced Encryption Standard)**

Plaintext is split into 128-bit blocks. The key is 128,192 or 256-bits long, giving the algorithm the name AES-128/192/256. AES is a much more advanced algorithm than DES, and it was created with the express purpose of replacing DES

Hugh Baldwin **11** of 15 M21279

#### **Confidentiality**

Because the messages are encrypted, they cannot be read or examined by a third party. This does rely upon the keys being shared ahead of time, in a secure way such that no third parties know what the key is.

## **Asymmetric (Public Key) Encryption**

In asymmetric encryption, the sender and receiver have two different but related keys. The sender uses the public key of the receiver to encrypt the message, and the receiver uses their own private key to decrypt the message.

#### **RSA (Rivest-Shamir-Adleman)**

- 1. Select two large primes p and q (the larger the better)
- 2. n = pq and z = (p-1)(q-1)
- 3. Select a number relatively prime (such that they have no common divisors) to z and call it d
- 4. Find e such that  $e*d=1 \mod z$
- 5. The public key is then (e, n) and the private key (d, n)
- 6. To encrypt a message, convert the plaintext M into an integer m such that  $0 \le m < n$ , using a known and reversible padding scheme. Then compute the ciphertext c such as  $c = m^e \pmod{n}$
- 7. To then decrypt the message, you use the private key d by computing  $c^d = (m^e)^d = m \pmod{n}$ . Then given m, you recover the message M by reversing the padding scheme

Figure 6.1: Encrypt then decrypt the string 'PORT' with the public key (3,33) and the private key (7,33)

Char	Numeric	$P^3$	P <sup>3</sup> Mod 33	<b>C</b> <sup>7</sup>	C <sup>7</sup> mod 33	Char
P	16	4096	4	16384	16	Р
0	15	3375	9	4782969	15	O
R	18	5832	24	4586471424	18	R
Т	20	8000	14	105413504	20	Т
Sender				Receiver		

#### **Confidentiality**

Because the messages are encrypted, they cannot be read or examined by a third party. Since the public key can only be used to encrypt messages (theoretically it can be used to determine the private key but this is effectively impossible with current computational power), it can be sent out on the internet for anyone to use to encrypt messages for the receiver. As long as the private key is kept secret by the receiver, the messages are perfectly confidential.

## **Ensuring Integrity**

To make sure that a message was sent by the correct person, and without being modified we can use either signatures, message digests or both.

#### **Digital Signatures**

When making a digital signature, the inverse of public-key cryptography is done. This means that only the owner of the signature knows the private key, but everyone knows the public key. The private key is used to cryptographically sign a file or message, which anyone can use the public key to verify, but only the owner of the keypair can use their key to sign. This means that if a message is signed, it must've come from the correct person.

#### **Message Digests**

A message digest (or hash function) takes a message M and produces a small 'fingerprint' known as the message digest H(M). A secure hash function H encrypts a small block of the message which is produced as a function of the message, known as the authenticator. The properties of H are such that  $H(M) \neq H(M')$  and given H(M) is is computationally impossible to find M. The message digest is encrypted with the sender's private key, and serves as a signature that verifies the content and order of the message. Two popular digest functions are MD5 and SHA-1.

#### **Authentication**

Authentication verifies that a message has come from a verified source. This can be achieved using conventional encryption techniques as discussed previously. This does not protect against so-called playback attacks however. If a third party records an encrypted message, they can re-send it again at a later time, and since the message is correctly encrypted, the receiver will still believe it to be a valid message.

This can be avoided by adding a number to the cipher that relates to the time the message was sent, either directly or by using it as the seed for a random number generator. When the message is received, if the time is too far in the past, the message will either be ignored, or requested for re-sending to ensure the correct message was sent.

## **Lecture - Local Area Networks**

11:00 04/11/24 Asim Ali

### **Data Link Layer**

Within the Data Link layer of the OSI reference model, there are two control systems— the Logical Link Control and Media Access Control. The logical link control is responsible for interfacing with the layers above it, and performing flow and error control.

Media Access Control is responsible for more of the addressing and actual communications, and handles assembling and disassembling the transmission frame, which consists of

- · Receiver's address
- · Error detection data, e.g. checksum or crc

#### **Media Access Protocol**

The original ethernet protocol was designed for use in bus or star networks, and so includes error and collision handling. Since only one station is able to transmit at a time in a bus or (hub) star network, there needs to be a way to determine if a collision has occurred and how it should be resolved. This is made up of a set of rules—

- If there is already a station transmitting, do not transmit.
- If another station transmits while you are transmitting, jam the medium and wait for a random length of time, using the back-off algorithm. (Select a random length of time from 0 to  $2^n 1$  slots, where n is the number of collisions).
- If there have been an excessive number of collisions, cancel the transmission and send an error up through the layers.
- · After waiting, attempt to transmit again.

The length of one transmission slot depends upon the speed of the medium, and the minimum size of packets. If the slot size is 512bits, then at 10Mbps, the slot time is  $\frac{512}{10000000}$  or 0.0000512 seconds (or 51.2 µsec)

To determine if a collision has occurred, each station is connected to the medium with two wires, one for transmitting and one for receiving. During transmission, if the signal sent out on the transmission line is not the same as what is received, then another station is interfering with the transmission, and a collision has occurred.

## **Switching**

### Store-and-Forward

When the switch receives a packet, it waits for the entire packet to arrive and stores it in memory before forwarding it to the intended recipient. This mode of operation works for both half and full-duplex transmission.

The latency in this mode can be calculated by sender-switch transmission time (packet size / transmission speed) + switch latency + switch-recipient transmission time + propagation delay of the medium (how long the data takes to get from one end of the medium to the other).

 Hugh Baldwin
 **14** of 15
 M21279

#### **Virtual-cut Through**

When the switch receives a packet, it only buffers enough of the packet to allow it time to process the MAC header, and determine where the packet should be sent. It then just forwards the buffer and the data as it flows into the switch.

The latency here can be calculated by sender-switch transmission time + switch latency + propagation delay of the medium.

### **Ethernet Frame Format**

Each frame sent on an ethernet network contains

- Preamble A series of 56 1s and 0s, used to sync the clock of the receiver (56 bits)
- Frame Delimiter- A byte which signals the start of the frame, specifically 10101011 (8 bits)
- Source– Address of the sending station (48 bits)
- Destination Address of the recipient station (48 bits)
- Length- The length of the data in bytes (16 bits)
- Data- Up to 12000 bits (1500 bytes) of data (0 12000 bits)
- Pad- Padding added to ensure the data is at least 46 bytes long (0 -368 bits)
- CRC- Cyclic Redundancy Check information, used to detect errors in the frame, so it can be re-sent on error (32 bits)

This gives us a minimum frame length of 48 + 48 + 16 + 0 + 368 + 32 = 512 bits