Run2dmorph (Ver.2017-06) Manual

Allison Hsiang

2017-09-06

I Introduction

Run2dmorph is the 2D-data extraction module of the AutoMorph software package developed by Pincelli Hull and team [1]. AutoMorph is available for download on GitHub. The run2dmorph module is described in detail in Hsiang et al. [2].

The basic pipeline of run2dmorph is as follows: the user supplies the program with a directory of RGB images containing individual objects (one object per image; all potentially confounding information, such as labels, should be excluded). Run2dmorph expects light objects on a dark background. If the user is using run2dmorph's companion AutoMorph modules segment and focus, the 'focused_unlabeled' folder outputted by focus should be used as the input directory of images for run2dmorph. The images are run through a series of filters (Fig. 1) that converts the original color image into black and white, with black indicating background and white indicating the object. The 2D outline is then extracted from this black and white image, along with measures of enclosed area, eccentricity, major and minor axis length, perimeter length, rugosity, and aspect ratio.

II Technical Specification

Run2dmorph, like all AutoMorph modules, is run using the command line. On Mac OSX, you must install the GNU Coreutils command line tools (more information here) in order to use the essential UNIX commands (e.g., 'ls' and cat') and run the run2dmorph binary executable. If you are unfamiliar with the command line, we recommend searching for introductory tutorials online and familiarizing yourself before diving in (here are some suggestions). A good golden rule when dealing with the command line as a beginner is: never input a command if you don't know exactly what it will do!

Run2dmorph is run using a plain-text input file, referred to here as a 'control file'. Explanations for the user-controlled variables in the control file, and how to set them, are presented in section V. By default, run2dmorph will output greyscale versions of the original images with the extracted outline overlaid for checking outline extraction fidelity, a text file containing the user input parameters, and a CSV of all 2D shape measurements. Optional outputs include x,y-coordinates for the extracted outlines, an illustration of the minimum bounding box used to calculate aspect ratio, and intermediate images of the output of each image processing filter step.

If run2dmorph fails to extract an object, it is usually due to the input parameters being poorly suited to the object image. In this case, run2dmorph will skip the object and move on to the next. If any objects are skipped in this way, run2dmorph will also output a TXT file listing all skipped objects, and generate a folder nested within the output directory named 'no_outline_extracted' that contains a copy of all skipped objects to facilitate easy re-processing.

III Installation

III.1 Prerequisites

Run2dmorph is written in Python and currently is only compatible with Python 2.7. Compatibility with Python 3.x is under development for future release. Run2dmorph requires the following modules:

- numpy
- scipy
- pandas
- opency
- scikit-image
- pillow
- matplotlib

We recommend that users install Anaconda, as this is the easiest way to install these Python modules. Once Anaconda is installed, users need only manually install the opency module:

```
$ conda install opency -c conda-forge
```

Note that the -c conda-forge flag is necessary for opency to install correctly. If you run into problems installing/importing opency, consult the Troubleshooting section below.

III.2 Setup

Once you have downloaded the AutoMorph software package, you will find the run2dmorph executable in the 'run2dmorph' folder. We recommend adding the run2dmorph executable to your path, so that run2dmorph can be called from anywhere in your system. To do this on Mac OSX, open the Terminal program (located at /Applications/Utilities/Terminal), and type the following command at the prompt:

\$ ln -s AMPATH/AutoMorph/run2dmorph/run2dmorph /usr/local/bin

where AMPATH is the location of your AutoMorph installation. For example, if AutoMorph is located in /Applications, the full command would be:

\$ ln -s /Applications/AutoMorph/run2dmorph/run2dmorph /usr/local/bin

If you are using Mac OS X, you may encounter a 'Permission denied' error when attempting to create the symbolic link. If this happens, you should use the 'sudo' command like so:

\$ sudo ln -s /Applications/AutoMorph/segment/segment /usr/local/bin

You will be prompted to enter your password; once you have done so, the symbolic link will be created. Note that you should not use 'sudo' unless you know exactly what you are doing!

You can now use *run2dmorph* from any location on your computer. Note that when creating symbolic links you should always use absolute paths and not relative ones.

IV Quick Run

Once run2dmorph is installed, it can be run via the command line using the following command (assuming the run2dmorph executable in your path):

\$ run2dmorph <path to control file>

You can use either absolute or relative paths when calling *run2dmorph*. For instance, if my control file is named run2dmorph_control.txt and located in my current working directory, the full command would be:

\$ run2dmorph run2dmorph_control.txt

While running, run2dmorph will output status messages on its progress.

V Control File and Parameters

The control file serves as the means by which the user supplies the necessary parameters for run2dmorph to operate. A clean version of the control file can be found in AutoMorph/run2dmorph. Some parameters require user input while others can left blank to allow run2dmorph to use default values. It is recommended that the user read through this section and understand what all the parameters do, and how to set them, before using run2dmorph.

The control file should be edited using a plain text editor (e.g., BBEdit for Mac OSX) to avoid interpretation issues and must use Unix (LF) encoding.

For parameters that are not required, the default value can be used by leaving the parameter blank, like so:

```
out_directory =
```

The default values of run2dmorph tend to work well with the images of foraminifera produced by the Hull lab (see example files in AutoMorph/example_datasets); users are encouraged to use these as a baseline against which to test their own images and parameter values.

A listing of the parameters for *run2dmorph* follows, with required parameters marked with an *:

- * in_directory: The full path to the input directory containing the images to be processed by *run2dmorph*. This cannot be a relative path.
- * input_ext: The file extension of the images to be processed by run2dmorph. For instance, .tif or tif.
- * sampleID: A name designating the identity of the current run, which will be appended before all files that run2dmorph outputs.

out_directory: The full path of the folder to which run2dmorph's output will be saved. If the folder does not exist, run2dmorph will create it. If this parameter is left blank, run2dmorph will generate a folder named 'morph2d' inside the directory specified under 'in_directory'. This cannot be a relative path.

pixel_size_x: A number specifying a conversion factor for pixel size in the width of the input image. Run2dmorph will scale the width of all images by this factor before extracting outlines and shape measures. The default value is 1 (*i.e.*,, no conversion).

pixel_size_y: As above, but for the height of the image. The default value is 1.

get_coordinates: A boolean (*i.e.*, True or False) specifying whether run2dmorph will output x,y-coordinates for the outlines extracted from

each image. The default value is True.

draw_aspect_ratio: A boolean specifying whether run2dmorph will output PDFs illustrating the minimum bounding box around each extracted outline, which is used to calculate the aspect ratio of the object. The default value is True.

save_intermediates: A boolean that determines whether run2dmorph will output intermediate images of the output of every image processing filtering step (i.e., the images shown in Fig. 1). The default value is False; we suggest turning this option on when users are conducting initial explorations of the most appropriate filter parameter values and when troubleshooting poor outline extraction.

disk_size_opening: An integer specifying the diameter of the disk used to to perform morphological opening (erosion followed by dilation; first step in Fig. 1). In general, turning this value up will remove increasing larger patches of background noise, but will also remove morphological detail from the object itself. The default value is 10.

contrast_adjustment: An integer specifying the degree of contrast enhancement to perform in the Contrast filter (step 3 in Fig. 1). The higher the value, the higher the contrast. The default value is 3.

threshold_adjustment: A number that specifies an adjustment value that will be added to the threshold value that is automatically determined run2dmorph during conversion of the image from greyscale to black and white. A higher threshold adjustment value corresponds to higher tolerance during the conversion (i.e., a broader, lighter range of grey will be considered white in the final black and white image). Note that while this adjustment value can be negative, the total threshold adjustment value cannot be negative. Run2dmorph will thus ignore this adjustment value and use the automatically determined threshold value if the sum of the two is negative. The default value is 0.

disk_size_smoothing: An integer specifying the diameter of the disk used to smooth the edge of the extracted outline (via binary opening). The higher the value, the more smoothing is applied (*i.e.*, the more detail is removed from the outline). The default value is 20.

downsample: A boolean specifying whether the x,y-coordinates extracted by run2dmorph should be downsampled from the default number of points (equal to the number of pixels in the outline). The default value is True. This parameter is only applicable when the 'get_coordinates' parameter is True.

num_points: An integer specifying the number of x,y-coordinates to be outputted if the 'downsample' parameter is set to TRUE. For example, setting this value to 100 will result in 100 outline x,y-coordinates outputted for every object processed. The default value is 100.

VI Hands-On Example Run

A set of example images for testing run2dmorph can be dowloaded on Zenodo here. Users can also use the mini dataset provided on GitHub, which is considering smaller in size. The following tutorial assumes the user is using the larger dataset provided on Zenodo.

A control file that can be used with these images is located at AutoMorph/run2dmorph/examples/run2dmorph_control_4sq_example.txt. The user need only fill in the **in_directory** parameter to run the example. Step-by-step instructions – which assume that the user has added run2dmorph to their system's path, that AutoMorph is installed in /Applications, and that the example images are located in /Downloads – follow:

1. Open run2dmorph_control_4sq_example.txt in a plain-text editor and change the **in_directory** to the appropriate path, and then save the file:

```
in_directory = /Downloads/run2dmorph_4sq_example_EDFs
```

- 2. At the command line prompt, navigate to the folder containing the control file:
 - \$ cd /Applications/AutoMorph/run2dmorph/examples
- 3. Start run2dmorph by entering the following command:
 - \$ run2dmorph run2dmorph control 4sq example.txt

Run2dmorph will proceed to extract outlines from the example objects; when extraction is complete, the command line prompt will reappear. The output files will be located in a folder named 'morph2d' inside the folder specified under in_directory.

VII Troubleshooting

Based on in-house usage of run2dmorph, the most common issues that arise concern incorrect specification of parameters in the control file. In general, if run2dmorph encounters an error before outline extraction begins, something is likely wrong with the control file formatting or encoding. In this case, the user is advised to:

- Check that the encoding of the control file is set to Unix (LF) and that the control file is in plain text format.
- Check that the correct input directory containing the images is specified.
- Check that the parameters are formatted correctly.

If run2dmorph runs but extracts poor outlines, the problem likely lies in the image filter parameters. In this case, the user is recommended to make a test folder containing 5-10 images from their full sample, turn on the **save_intermediates** parameter, and adjust parameter values until acceptable outlines are extracted for the test objects before running run2dmorph on the entire sample.

VII.1 Issues with Installing Opency

You may run into issues installing opency with Anaconda, particularly if your system has previous installations of Python and/or other package managers such as Homebrew. The following are issues and solutions that we have come across in-house when installing opency on Mac OS X.

VII.1.1 Homebrew

If you have previously installed Homebrew, you can install opency by tapping the homebrew/science repository, like so:

```
$ brew tap homebrew/science
$ brew install opency
```

VII.1.2 ImportError

If you install opency with Anaconda, you may encounter an ImportError when trying to import the cv2 library. This may be the result of certain libraries being missing, and you will see an error message similar to the following:

```
Traceback (most recent call last):
   File "/usr/local/bin/segment", line 4, in <module>
        import images
File "/Automorph/AutoMorph-master/segment/images.py", line 9, in <module>
        import cv2
ImportError: [...] : Library not loaded: @rpath/libopenblasp-r0.2.19.dylib
        Referenced from: somepath/libopencv_hdf.3.2.0.dylib
        Reason: image not found
```

This issue occurs because the dlib library is missing. You can install this library via the following command:

```
$ conda install dlib -c conda-forge
```

You may then need to update other packages (e.g., numpy). Update all your packages like so:

```
$ conda update --all -c conda-forge
```

You should now be able to use opency without issue.

References

- [1] AutoMorph (https://github.com/HullLab/AutoMorph)
- [2] Hsiang AY, Nelson K, Elder LE, Sibert EC, Kahanamoku SS, Burke JE, Kelly A, Liu Y, Hull PM. AutoMorph: Accelerating community morphometrics with 2D and 3D image processing and shape extraction. **Methods in Ecology and Evolution**. *In revision*.




Figure 1: Visual pipeline of the image processing filters used in run2dmorph.