

# Chapter 13: I/O Systems





# Chapter 13: I/O Systems

- □ I/O Hardware
- Application I/O Interface
- Kernel I/O Subsystem
- □ Transforming I/O Requests to Hardware Operations
- STREAMS
- Performance





# **Objectives**

- Explore the structure of an operating system's I/O subsystem
- □ Discuss the principles of I/O hardware and its complexity
- □ Provide details of the performance aspects of I/O hardware and software






#### Overview

- □ I/O management is a major component of operating system design and operation
  - Important aspect of computer operation
  - I/O devices vary greatly
  - Various methods to control them
  - Performance management
  - New types of devices frequent
- □ Ports, busses, device controllers connect to various devices
- Device drivers encapsulate device details
  - Present uniform device-access interface to I/O subsystem






#### **I/O Hardware**

- ☐ Incredible variety of I/O devices
  - Storage
  - Transmission
  - Human-interface
- □ Common concepts signals from I/O devices interface with computer
  - Port connection point for device
  - Bus daisy chain or shared direct access
  - Controller (host adapter) electronics that operate port, bus, device
    - Sometimes integrated
    - Sometimes separate circuit board (host adapter)
    - Contains processor, microcode, private memory, bus controller, etc
      - Some talk to per-device controller with bus controller, microcode, memory, etc





### A Typical PC Bus Structure





## I/O Hardware (Cont.)

- I/O instructions control devices
- Devices usually have registers where device driver places commands, addresses, and data to write, or read data from registers after command execution
  - Data-in register, data-out register, status register, control register
  - Typically 1-4 bytes, or FIFO buffer
- Devices have addresses, used by
  - Direct I/O instructions
  - Memory-mapped I/O
    - Device data and command registers mapped to processor address space
    - Especially for large address spaces (graphics)






### **Device I/O Port Locations on PCs (partial)**

I/O address range (hexadecimal)	device	
000-00F	DMA controller	
020–021	interrupt controller	
040–043	timer	
200–20F	game controller	
2F8-2FF	serial port (secondary)	
320-32F	hard-disk controller	
378–37F	parallel port	
3D0-3DF	graphics controller	
3F0-3F7	diskette-drive controller	
3F8-3FF	serial port (primary)	





### **Polling**

- ☐ For each byte of I/O
  - 1. Read busy bit from status register until 0
  - 2. Host sets read or write bit and if write copies data into data-out register
  - 3. Host sets command-ready bit
  - 4. Controller sets busy bit, executes transfer
  - 5. Controller clears busy bit, error bit, command-ready bit when transfer done
- □ Step 1 is **busy-wait** cycle to wait for I/O from device
  - Reasonable if device is fast
  - But inefficient if device slow
  - CPU switches to other tasks?
    - But if miss a cycle data overwritten / lost






### Interrupts

- □ Polling can happen in 3 instruction cycles
  - Read status, logical-and to extract status bit, branch if not zero
  - How to be more efficient if non-zero infrequently?
- □ CPU Interrupt-request line triggered by I/O device
  - Checked by processor after each instruction
- □ Interrupt handler receives interrupts
  - Maskable to ignore or delay some interrupts
- □ Interrupt vector to dispatch interrupt to correct handler
  - Context switch at start and end
  - Based on priority
  - Some nonmaskable
  - Interrupt chaining if more than one device at same interrupt number





### Interrupt-Driven I/O Cycle






### **Intel Pentium Processor Event-Vector Table**

vector number	description	
0	divide error	
1	debug exception	
2	null interrupt	
3	breakpoint	
4	INTO-detected overflow	
5	bound range exception	
6	invalid opcode	
7	device not available	
8	double fault	
9	coprocessor segment overrun (reserved)	
10	invalid task state segment	
11	segment not present	
12	stack fault	
13	general protection	
14	page fault	
15	(Intel reserved, do not use)	
16	floating-point error	
17	alignment check	
18	machine check	
19–31	(Intel reserved, do not use)	
32–255	maskable interrupts	






## Interrupts (Cont.)

- ☐ Interrupt mechanism also used for exceptions
  - Terminate process, crash system due to hardware error
- □ Page fault executes when memory access error
- □ System call executes via trap to trigger kernel to execute request
- Multi-CPU systems can process interrupts concurrently
  - If operating system designed to handle it
- □ Used for time-sensitive processing, frequent, must be fast







### **Direct Memory Access**


- ☐ Used to avoid **programmed I/O** (one byte at a time) for large data movement
- □ Requires DMA controller
- □ Bypasses CPU to transfer data directly between I/O device and memory
- OS writes DMA command block into memory
  - Source and destination addresses
  - Read or write mode
  - Count of bytes
  - Writes location of command block to DMA controller
  - Bus mastering of DMA controller grabs bus from CPU
  - □ When done, interrupts to signal completion





#### Six Step Process to Perform DMA Transfer






### **Application I/O Interface**


- □ I/O system calls encapsulate device behaviors in generic classes
- □ Device-driver layer hides differences among I/O controllers from kernel
- □ New devices talking already-implemented protocols need no extra work
- □ Each OS has its own I/O subsystem structures and device driver frameworks
- Devices vary in many dimensions
  - Character-stream or block
  - Sequential or random-access
  - Synchronous or asynchronous (or both)
  - Sharable or dedicated
  - Speed of operation
  - read-write, read only, or write only





#### A Kernel I/O Structure






### **Characteristics of I/O Devices**

aspect	variation	example
data-transfer mode	character block	terminal disk
access method	sequential random	modem CD-ROM
transfer schedule	synchronous asynchronous	tape keyboard
sharing	dedicated sharable	tape keyboard
device speed	latency seek time transfer rate delay between operations	
I/O direction	read only write only read-write	CD-ROM graphics controller disk





- Subtleties of devices handled by device drivers
- □ Broadly I/O devices can be grouped by the OS into
  - Block I/O
  - Character I/O (Stream)
  - Memory-mapped file access
  - Network sockets
- □ For direct manipulation of I/O device specific characteristics, usually an escape / back door
  - □ Unix ioctl() call to send arbitrary bits to a device control register and data to device data register



#### **Block and Character Devices**

- Block devices include disk drives
  - Commands include read, write, seek
  - Raw I/O, direct I/O, or file-system access
  - Memory-mapped file access possible
    - File mapped to virtual memory and clusters brought via demand paging
  - DMA
- ☐ Character devices include keyboards, mice, serial ports
  - Commands include get(), put()
  - Libraries layered on top allow line editing






#### **Network Devices**

- □ Varying enough from block and character to have own interface
- Unix and Windows NT/9x/2000 include socket interface
  - Separates network protocol from network operation
  - Includes select() functionality
- Approaches vary widely (pipes, FIFOs, streams, queues, mailboxes)






#### **Clocks and Timers**

- □ Provide current time, elapsed time, timer
- Normal resolution about 1/60 second
- Some systems provide higher-resolution timers
- Programmable interval timer used for timings, periodic interrupts
- ioctl() (on UNIX) covers odd aspects of I/O such as clocks and timers







# Blocking and Nonblocking I/O


- □ Blocking process suspended until I/O completed
  - Easy to use and understand
  - Insufficient for some needs
- Nonblocking I/O call returns as much as available
  - □ User interface, data copy (buffered I/O)
  - Implemented via multi-threading
  - Returns quickly with count of bytes read or written
  - select() to find if data ready then read() or write() to transfer
- Asynchronous process runs while I/O executes
  - Difficult to use
  - I/O subsystem signals process when I/O completed






#### **Two I/O Methods**











### Kernel I/O Subsystem

- Scheduling
  - Some I/O request ordering via per-device queue
  - Some OSs try fairness
  - Some implement Quality Of Service (i.e. IPQOS)
- □ Buffering store data in memory while transferring between devices
  - To cope with device speed mismatch
  - To cope with device transfer size mismatch
  - To maintain "copy semantics"
  - Double buffering two copies of the data
    - Kernel and user
    - Varying sizes
    - Full / being processed and not-full / being used
    - Copy-on-write can be used for efficiency in some cases






#### **Device-status Table**





#### Sun Enterprise 6000 Device-Transfer Rates







### Kernel I/O Subsystem

- Caching faster device holding copy of data
  - Always just a copy
  - Key to performance
  - Sometimes combined with buffering
- Spooling hold output for a device
  - If device can serve only one request at a time
  - i.e., Printing
- Device reservation provides exclusive access to a device
  - System calls for allocation and de-allocation
  - Watch out for deadlock





### **Error Handling**

- OS can recover from disk read, device unavailable, transient write failures
  - Retry a read or write, for example
  - □ Some systems more advanced Solaris FMA, AIX
    - Track error frequencies, stop using device with increasing frequency of retry-able errors
- Most return an error number or code when I/O request fails
- System error logs hold problem reports






#### **I/O Protection**

- User process may accidentally or purposefully attempt to disrupt normal operation via illegal I/O instructions
  - All I/O instructions defined to be privileged
  - □ I/O must be performed via system calls
    - Memory-mapped and I/O port memory locations must be protected too






### Use of a System Call to Perform I/O









#### **Kernel Data Structures**

- □ Kernel keeps state info for I/O components, including open file tables, network connections, character device state
- ☐ Many, many complex data structures to track buffers, memory allocation, "dirty" blocks
- □ Some use object-oriented methods and message passing to implement I/O
  - Windows uses message passing
    - Message with I/O information passed from user mode into kernel
    - Message modified as it flows through to device driver and back to process
    - Pros / cons?





#### **UNIX I/O Kernel Structure**






- Consider reading a file from disk for a process:
  - Determine device holding file
  - Translate name to device representation
  - Physically read data from disk into buffer
  - Make data available to requesting process
  - Return control to process






### Life Cycle of An I/O Request









#### **STREAMS**

- STREAM a full-duplex communication channel between a user-level process and a device in Unix System V and beyond
- A STREAM consists of:
  - STREAM head interfaces with the user process
  - driver end interfaces with the device
  - zero or more STREAM modules between them
- □ Each module contains a read queue and a write queue
- Message passing is used to communicate between queues
  - Flow control option to indicate available or busy
- Asynchronous internally, synchronous where user process communicates with stream head





#### The STREAMS Structure






#### **Performance**

- □ I/O a major factor in system performance:
  - Demands CPU to execute device driver, kernel I/O code
  - Context switches due to interrupts
  - Data copying
  - Network traffic especially stressful






### Intercomputer Communications








## **Improving Performance**

- Reduce number of context switches
- Reduce data copying
- □ Reduce interrupts by using large transfers, smart controllers, polling
- Use DMA
- Use smarter hardware devices
- □ Balance CPU, memory, bus, and I/O performance for highest throughput
- Move user-mode processes / daemons to kernel threads



# **Device-Functionality Progression**





# **End of Chapter 12**

