### Hosting Environment (Daemon) Reference Manual

Generated by Doxygen 1.4.7

Mon Feb 2 23:26:10 2009

### **Contents**

| 1 | Hos  | ting Environment (Daemon) Namespace Index         | 1  |
|---|------|---|----|
|   | 1.1  | Hosting Environment (Daemon) Namespace List       | 1  |
| 2 | Hos  | ting Environment (Daemon) Hierarchical Index      | 3  |
|   | 2.1  | Hosting Environment (Daemon) Class Hierarchy      | 3  |
| 3 | Hos  | ting Environment (Daemon) Class Index             | 7  |
|   | 3.1  | Hosting Environment (Daemon) Class List           | 7  |
| 4 | Hos  | ting Environment (Daemon) Namespace Documentation | 11 |
|   | 4.1  | Arc Namespace Reference                           | 11 |
|   | 4.2  | ArcCredential Namespace Reference                 | 30 |
| 5 | Hos  | ting Environment (Daemon) Class Documentation     | 35 |
|   | 5.1  | ArcSec::AlgFactory Class Reference                | 35 |
|   | 5.2  | ARCLibError Class Reference                       | 37 |
|   | 5.3  | Arc::ArcLocation Class Reference                  | 38 |
|   | 5.4  | ArcSec::Attr Struct Reference                     | 39 |
|   | 5.5  | ArcSec::AttributeFactory Class Reference          | 40 |
|   | 5.6  | Arc::AttributeIterator Class Reference            | 41 |
|   | 5.7  | ArcSec::AttributeProxy Class Reference            | 44 |
|   | 5.8  | ArcSec::AttributeValue Class Reference            | 45 |
|   | 5.9  | ArcSec::Attrs Class Reference                     | 47 |
|   | 5.10 | ArcSec::AuthzRequestSection Struct Reference      | 48 |
|   | 5.11 | Arc::AutoPointer< T > Class Template Reference    | 49 |
|   | 5.12 | Arc::BaseConfig Class Reference                   | 51 |
|   | 5.13 | Arc::CacheParameters Struct Reference             | 53 |
|   | 5.14 | Arc::ChainContext Class Reference                 | 54 |
|   | 5.15 | Arc::CheckSum Class Reference                     | 55 |
|   | 5 16 | Arcy Chack Sum Any Class Reference                | 56 |

ii CONTENTS

| Arc::CIStringValue Class Reference  | 58  |
|---|---|
| Arc::ClientSOAP Class Reference   | 60  |
| ArcSec::CombiningAlg Class Reference  | 61  |
| Arc::Config Class Reference   | 63  |
| $Arc:: Counted Pointer < T > Class \ Template \ Reference \ . \ . \ . \ . \ . \ . \ . \ . \ . \ $ | 65  |
| Arc::Counter Class Reference  | 67  |
| Arc::CounterTicket Class Reference  | 74  |
| Arc::CRC32Sum Class Reference   | 76  |
| Arc::CredentialError Class Reference  | 77  |
| Arc::Database Class Reference   | 78  |
| Arc::DataBuffer Class Reference   | 80  |
| Arc::DataCallback Class Reference   | 87  |
| Arc::DataHandle Class Reference   | 88  |
| Arc::DataMover Class Reference  | 89  |
| Arc::DataPoint Class Reference  | 93  |
| Arc::DataPointDirect Class Reference  | 04  |
| Arc::DataPointIndex Class Reference   | 11  |
| Arc::DataSpeed Class Reference  | 18  |
| ArcSec::DateTimeAttribute Class Reference   | 22  |
| Arc::DelegationConsumer Class Reference   | 24  |
| Arc::DelegationConsumerSOAP Class Reference   | 26  |
| Arc::DelegationContainerSOAP Class Reference  | 28  |
| Arc::DelegationProvider Class Reference   | 30  |
| Arc::DelegationProviderSOAP Class Reference   | 32  |
| ArcSec::DenyOverridesCombiningAlg Class Reference   | 34  |
| ArcSec::DurationAttribute Class Reference   | 36  |
| ArcSec::EqualFunction Class Reference   | 38  |
| ArcSec::EvalResult Struct Reference   | 39  |
| ArcSec::EvaluationCtx Class Reference   | 40  |
| ArcSec::Evaluator Class Reference   | 41  |
| ArcSec::EvaluatorContext Class Reference  | 44  |
| ArcSec::EvaluatorLoader Class Reference   | 45  |
| Arc::ExpirationReminder Class Reference   | 47  |
| Arc::FileCache Class Reference  | 49  |
| FileCacheHash Class Reference   | 54  |
| Arc::FileInfo Class Reference   | 55  |
|   | Arc::ClientSOAP Class Reference ArcSec::CombiningAlg Class Reference Arc::Config Class Reference Arc::CountedPointer< T > Class Template Reference Arc::Counter Class Reference Arc::CounterTicket Class Reference Arc::CounterTicket Class Reference Arc::CredentialError Class Reference Arc::Database Class Reference Arc::DataBuffer Class Reference Arc::DataCallback Class Reference Arc::DataHandle Class Reference Arc::DataMover Class Reference |

CONTENTS

| 5.53 | ArcSec::FnFactory Class Reference          | 156 |
|------|--|-----|
| 5.54 | ArcSec::Function Class Reference           | 157 |
| 5.55 | Arc::InfoCache Class Reference             | 158 |
| 5.56 | Arc::InfoFilter Class Reference            | 159 |
| 5.57 | Arc::InfoRegister Class Reference          | 160 |
| 5.58 | Arc::InfoRegisterContainer Class Reference | 161 |
| 5.59 | Arc::InfoRegisters Class Reference         | 162 |
| 5.60 | Arc::InfoRegistrar Class Reference         | 163 |
| 5.61 | Arc::InformationContainer Class Reference  | 164 |
| 5.62 | Arc::InformationInterface Class Reference  | 166 |
| 5.63 | Arc::InformationRequest Class Reference    | 168 |
| 5.64 | Arc::InformationResponse Class Reference   | 170 |
| 5.65 | Arc::IntraProcessCounter Class Reference   | 171 |
| 5.66 | Arc::Loader Class Reference                | 175 |
| 5.67 | Arc::LogDestination Class Reference        | 177 |
| 5.68 | Arc::Logger Class Reference                | 179 |
| 5.69 | Arc::LogMessage Class Reference            | 182 |
| 5.70 | Arc::LogStream Class Reference             | 184 |
| 5.71 | ArcSec::MatchFunction Class Reference      | 186 |
| 5.72 | Arc::MCC Class Reference                   | 187 |
| 5.73 | Arc::MCC_Status Class Reference            | 190 |
| 5.74 | Arc::MCCInterface Class Reference          | 193 |
| 5.75 | Arc::MCCLoader Class Reference             | 195 |
| 5.76 | Arc::MD5Sum Class Reference                | 197 |
| 5.77 | Arc::Message Class Reference               | 198 |
| 5.78 | Arc::MessageAttributes Class Reference     | 201 |
| 5.79 | Arc::MessageAuth Class Reference           | 204 |
| 5.80 | Arc::MessageAuthContext Class Reference    | 206 |
| 5.81 | Arc::MessageContext Class Reference        | 207 |
| 5.82 | Arc::MessageContextElement Class Reference | 208 |
| 5.83 | Arc::MessagePayload Class Reference        | 209 |
| 5.84 | Arc::ModuleManager Class Reference         | 210 |
| 5.85 | Arc::MultiSecAttr Class Reference          | 212 |
| 5.86 | Arc::MySQLDatabase Class Reference         | 214 |
| 5.87 | Arc::PayloadRaw Class Reference            | 216 |
| 5.88 | Arc::PayloadRawInterface Class Reference   | 219 |
|      |  |     |

iv CONTENTS

| 5.89 Arc::PayloadSOAP Class Reference                    |
|--|
| 5.90 Arc::PayloadStream Class Reference                  |
| 5.91 Arc::PayloadStreamInterface Class Reference         |
| 5.92 Arc::PayloadWSRF Class Reference                    |
| 5.93 ArcSec::PDP Class Reference                         |
| 5.94 ArcSec::PeriodAttribute Class Reference             |
| 5.95 ArcSec::PermitOverridesCombiningAlg Class Reference |
| 5.96 Arc::Plexer Class Reference                         |
| 5.97 Arc::PlexerEntry Class Reference                    |
| 5.98 Arc::Plugin Class Reference                         |
| 5.99 Arc::PluginArgument Class Reference                 |
| 5.100 Arc::PluginDescriptor Struct Reference             |
| 5.101 Arc::PluginsFactory Class Reference                |
| 5.102ArcSec::Policy Class Reference                      |
| 5.103 ArcSec::PolicyParser Class Reference               |
| 5.104ArcSec::PolicyStore Class Reference                 |
| 5.105 Arc::RegularExpression Class Reference             |
| 5.106ArcSec::Request Class Reference                     |
| 5.107ArcSec::RequestAttribute Class Reference            |
| 5.108 ArcSec::RequestItem Class Reference                |
| 5.109ArcSec::RequestTuple Class Reference                |
| 5.110ArcSec::Response Class Reference                    |
| 5.111ArcSec::ResponseItem Struct Reference               |
| 5.112Arc::Run Class Reference                            |
| 5.113RuntimeEnvironment Class Reference                  |
| 5.114RuntimeEnvironmentError Class Reference             |
| 5.115 Arc::SAMLToken Class Reference                     |
| 5.116Arc::SecAttr Class Reference                        |
| 5.117Arc::SecAttrFormat Class Reference                  |
| 5.118Arc::SecAttrValue Class Reference                   |
| 5.119ArcSec::SecHandler Class Reference                  |
| 5.120ArcSec::Security Class Reference                    |
| 5.121 Arc::Service Class Reference                       |
| 5.122Arc::SimpleCondition Class Reference                |
| 5.123 Arc::SOAPMessage Class Reference                   |
| 5.124ArcSec::Source Class Reference                      |
|  |

CONTENTS

| 5.125ArcSec::SourceFile Class Reference                     |
|---|
| 5.126ArcSec::SourceURL Class Reference                      |
| 5.127 Arc::Time Class Reference                             |
| 5.128ArcSec::TimeAttribute Class Reference                  |
| 5.129Arc::URL Class Reference                               |
| 5.130Arc::URLLocation Class Reference                       |
| 5.131Arc::UsernameToken Class Reference                     |
| 5.132Arc::VOMSTrustList Class Reference                     |
| 5.133Arc::WSAEndpointReference Class Reference              |
| 5.134Arc::WSAHeader Class Reference                         |
| 5.135 Arc::WSRF Class Reference                             |
| 5.136Arc::WSRFBaseFault Class Reference                     |
| 5.137Arc::WSRP Class Reference                              |
| 5.138Arc::WSRPFault Class Reference                         |
| 5.139Arc::WSRPResourcePropertyChangeFailure Class Reference |
| 5.140Arc::X509Token Class Reference                         |
| 5.141 Arc::XMLNode Class Reference                          |
| 5.142Arc::XMLNodeContainer Class Reference                  |
| 5.143 Arc::XMLSecNode Class Reference                       |

## Hosting Environment (Daemon) Namespace Index

### 1.1 Hosting Environment (Daemon) Namespace List

| Here is a list of al | I documented | namespaces with | brief descriptions |  |
|----------------------|--------------|-----------------|--------------------|--|
|                      |              |                 |                    |  |

| Arc (Some utility methods for using xml security library (http://www.aleksey.com/xmlsec/)). | 11 |
|---|----|
| ArcCredential   | 30 |

| 2 | Hosting Environment (Daemon) Namespace Index |  |  |  |
|---|--|--|--|--|
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |
|   |  |  |  |  |

### Hosting Environment (Daemon) Hierarchical Index

### 2.1 Hosting Environment (Daemon) Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

| ARCLibError                                    |
|--|
| RuntimeEnvironmentError                        |
| Arc::ArcLocation                               |
| ArcSec::Attr                                   |
| Arc::AttributeIterator                         |
| ArcSec::AttributeProxy                         |
| ArcSec::AttributeValue                         |
| ArcSec::DateTimeAttribute                      |
| ArcSec::DurationAttribute                      |
| ArcSec::PeriodAttribute                        |
| ArcSec::TimeAttribute                          |
| ArcSec::Attrs                                  |
| ArcSec::AuthzRequestSection                    |
| $Arc::AutoPointer < T > \dots \qquad \qquad 4$ |
| Arc::BaseConfig                                |
| Arc::CacheParameters                           |
| Arc::ChainContext                              |
| Arc::CheckSum                                  |
| Arc::CheckSumAny                               |
| Arc::CRC32Sum                                  |
| Arc::MD5Sum                                    |
| Arc::ClientSOAP                                |
| ArcSec::CombiningAlg                           |
| ArcSec::DenyOverridesCombiningAlg              |
| ArcSec::PermitOverridesCombiningAlg            |
| Arc::CountedPointer < T >                      |
| Arc::Counter                                   |
| Arc::IntraProcessCounter                       |
| Arc::CounterTicket                             |

| Arc::CredentialError         |
|------------------------------|
| Arc::Database                |
| Arc::MySQLDatabase           |
| Arc::DataBuffer              |
| Are::DataCallback            |
| Arc::DataHandle              |
| Arc::DataMover               |
| Arc::DataPoint               |
| Arc::DataPointDirect         |
| Arc::DataPointIndex          |
| Arc::DataSpeed               |
| Arc::DelegationConsumer      |
| Arc::DelegationConsumerSOAP  |
| Arc::DelegationContainerSOAP |
| Arc::DelegationProvider      |
| Arc::DelegationProviderSOAP  |
| ArcSec::EvalResult           |
| ArcSec::EvaluationCtx        |
| ArcSec::EvaluatorContext     |
| ArcSec::EvaluatorLoader      |
| Arc::ExpirationReminder      |
| Arc::FileCache               |
| FileCacheHash                |
| Arc::FileInfo                |
| ArcSec::Function             |
| ArcSec::EqualFunction        |
| ArcSec::MatchFunction        |
| Arc::InfoCache               |
| Arc::InfoFilter              |
| Arc::InfoRegister            |
| Arc::InfoRegisterContainer   |
| Arc::InfoRegisters           |
| Arc::InfoRegistrar           |
| Arc::InformationInterface    |
| Arc::InformationContainer    |
| Arc::InformationRequest      |
| Arc::InformationResponse     |
| Arc::Loader                  |
| Arc::MCCLoader               |
| Arc::LogDestination          |
|                              |
| Arc::LogStream               |
| Arc::Logger                  |
| Arc::LogMessage              |
| Arc::MCC_Status              |
| Arc::Message                 |
| Arc::MessageAttributes       |
| Arc::MessageAuth             |
| Arc::MessageAuthContext      |
| Arc::MessageContext          |
| Arc::MessageContextElement   |
| Arc::MessagePayload          |

| Arc::PayloadRawInterface    | 219 |
|-----------------------------|-----|
| Arc::PayloadRaw             | 216 |
| Arc::PayloadSOAP            | 221 |
| Arc::PayloadStreamInterface | 225 |
| Arc::PayloadStream          | 222 |
| Arc::PayloadWSRF            | 228 |
| Arc::ModuleManager          |     |
| Arc::PluginsFactory         |     |
| Arc::PlexerEntry            |     |
| Arc::Plugin                 |     |
| Arc::MCCInterface           |     |
| Arc::MCC                    | 193 |
|                             | 235 |
| Arc::Plexer                 |     |
| Arc::Service                |     |
| ArcSec::AlgFactory          |     |
| ArcSec::AttributeFactory    |     |
| ArcSec::FnFactory           |     |
| ArcSec::PDP                 |     |
| ArcSec::Policy              |     |
| ArcSec::Request             |     |
| ArcSec::SecHandler          |     |
| Arc::PluginArgument         |     |
| Arc::PluginDescriptor       |     |
| ArcSec::PolicyParser        |     |
| ArcSec::PolicyStore         |     |
| Arc::RegularExpression      |     |
| ArcSec::RequestAttribute    |     |
| ArcSec::RequestItem         | 253 |
| ArcSec::RequestTuple        |     |
| ArcSec::Response            |     |
| ArcSec::ResponseItem        |     |
| Arc::Run                    |     |
| RuntimeEnvironment          |     |
| Arc::SAMLToken              |     |
| Arc::SecAttr                |     |
| Arc::MultiSecAttr           |     |
| Arc::SecAttrFormat          |     |
| Arc::SecAttrValue           | 271 |
| Arc::CIStringValue          | 58  |
| ArcSec::Security            | 274 |
| Arc::SimpleCondition        | 278 |
| Arc::SOAPMessage            |     |
| ArcSec::Source              | 282 |
| ArcSec::SourceFile          | 284 |
| ArcSec::SourceURL           | 285 |
| Arc::Time                   | 286 |
| Arc::URL                    | 291 |
| Arc::URLLocation            | 299 |
| Arc::UsernameToken          | 301 |
| Arc: VOMSTrust List         | 304 |

| Arc::WSAEndpointReference              | 06 |
|--|----|
| Arc::WSAHeader                         | 80 |
| Arc::WSRF                              | 11 |
| Arc::WSRFBaseFault                     | 13 |
| Arc::WSRPFault                         | 17 |
| Arc::WSRPResourcePropertyChangeFailure | 18 |
| Arc::WSRP                              | 15 |
| Arc::X509Token                         | 19 |
| Arc::XMLNode                           | 21 |
| Arc::Config                            | 63 |
| Arc::XMLSecNode                        | 33 |
| Arc.:XMI NodeContainer                 | 31 |

# **Hosting Environment (Daemon) Class Index**

### 3.1 Hosting Environment (Daemon) Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

| ArcSec::AlgFactory (Interface for algorithm factory class )  | 35         |
|--|------------|
| ARCLibError  | 37         |
| Arc::ArcLocation (Determines ARC installation location )   | 38         |
|  | 39         |
|  | 40         |
| ·  | 41         |
| ArcSec::AttributeProxy (Interface for creating the AttributeValue object, it will be used by             |            |
| ·  | 44         |
| ArcSec::AttributeValue (Interface for containing different type of <attribute> node for both</attribute> |            |
|  | 45         |
|  | 47         |
|  | 48         |
|  | 49         |
|  | 51         |
| Arc::CacheParameters   | <b>5</b> 3 |
| Arc::ChainContext (Interface to chain specific functionality )   | 54         |
|  | 55         |
|  | 56         |
|  | 58         |
|  | 60         |
| ArcSec::CombiningAlg (Interface for combining algrithm )   | 61         |
| Arc::Config (Configuration element - represents (sub)tree of ARC configuration )                         | 63         |
| Arc::CountedPointer< T > (Wrapper for pointer with automatic destruction and mutiple refer-              |            |
| ences )  | 65         |
| Arc::Counter (A class defining a common interface for counters )   | 67         |
| Arc::CounterTicket (A class for "tickets" that correspond to counter reservations )                      | 74         |
| Arc::CRC32Sum (Implementation of CRC32 checksum )  | 76         |
| Arc::CredentialError   | 77         |
| Arc::Database (Interface for calling database client library )   | 78         |
|  | 80         |
| Are::DataCallback  | 87         |

| Are::DataPoint (This base class is an abstraction of URL ) 93 Are::DataPointDirect (This is a kind of generalized file handle ) 104 Are::DataPointIndex (Complements DataPoint with attributes common for Indexing Service URLs ) 118 Are::DataSpeed (Keeps track of average and instantaneous transfer speed ) 118 Are::DataSpeed (Keeps track of average and instantaneous transfer speed ) 118 Are::DelegationConsumer 124 Are::DelegationConsumer SOAP 126 Are::DelegationConsumerSOAP 126 Are::DelegationConstainerSOAP 128 Are::DelegationContainerSOAP 133 Are::DelegationProviderSOAP 133 Are::DelegationProviderSOAP 133 AreSee::DurationAttribute 136 AreSee::DurationAttribute 136 AreSee::EvalpalFunction (Evaluate whether the two values are equal ) 138 AreSee::EvalpalFunction (Evaluate whether the two values are equal ) 138 AreSee::EvalpalFunction (Evaluate whether the two values are equal ) 139 AreSee::EvaluationCtx (EvaluationCtx, in charge of storing some context information for evaluation, including Request, current time, etc ) 140 AreSee::EvaluationCtx (EvaluationCtx, in charge of storing some context information for evaluation, including Request, current time, etc ) 140 AreSee::Evaluator (Interface for policy evaluation. Execute the policy evaluation, based on the request and policy ) 141 AreSee::EvaluatorContext (Context for evaluator. It includes the factories which will be used to create related objects ) 144 AreSee::EvaluatorOntext (Context for evaluator. It includes the factories which will be used to create related objects) 144 Are::ExpirationReminder (A class intended for internal use within counters ) 145 Are::ExpirationReminder (A class intended for internal use within counters ) 147 Are::ErileCacheHash 154 Are::ErileCacheHash 154 Are::ErileCacheHash 154 Are::Info@exiter (Registration process associated with particular ISIS ) 158 Are::Info@exiter (Registration process associated with particular ISIS ) 159 Are::Info@exiter (Registration process associated with particular ISIS ) 159 Are::Info@exiter (Registration proc | Arc::DataHandle (This class is a wrapper around the DataPoint class)                           | 88   |
|--|--|------|
| Are:BataPointDirect (This is a kind of generalized file handle) 104 Are:DataPointIndex (Complements DataPoint with attributes common for Indexing Service URLs) 111 Are:DataSpeed (Keeps track of average and instantaneous transfer speed ) 118 Are:Sec:DateTimeAttribute 122 Are:DelegationConsumer 124 Are:DelegationConsumer 124 Are:DelegationConsumerSOAP 126 Are:DelegationContainerSOAP 128 Are:DelegationProvider 138 Are:DelegationProvider 130 Are:DelegationProvider 130 Are:DelegationProvider 130 Are:DelegationProvider 131 AreSec::DurationAttribute 132 AreSec::DurationAttribute 134 AreSec::DurationAttribute 136 AreSec::EqualFunction (Evaluate whether the two values are equal ) 138 AreSec::EqualFunction (Evaluate whether the two values are equal ) 138 AreSec::EqualFunction (Evaluate whether the two values are equal ) 139 AreSec::EvaluationCtx (EvaluationCtx, in charge of storing some context information for evaluation, including Request, current time, etc ) 140 AreSec::Evaluator (Interface for policy evaluation. Execute the policy evaluation, based on the request and policy ) 141 AreSec::Evaluator (Context for evaluator. It includes the factories which will be used to create related objects ) 144 AreSec::Evaluator Context (Context for evaluator. It includes the factories which will be used to create related objects ) 144 AreSec::Evaluator Context (Context for evaluator ) 145 Are:EpsirationReminder (A class intended for internal use within counters ) 147 Are:EpsirationReminder (A class intended for internal use within counters ) 147 Are:Eplicache 149 FileCacheHash 154 Are:EplicInfo (FileInfo stores information about files (metadata) ) 155 Are:Eprilation (Registration to ISIS interface ) 160 Are:InfoRegister (A class for log message s) 173 Are:InfoRegister (A class for log messages ) 174 Are:LogDect (A l | Arc::DataMover   | 89   |
| Are:DataPointIndex (Complements DataPoint with attributes common for Indexing Service URLs)  URLs)  111  Are:DataSpeed (Keeps track of average and instantaneous transfer speed)  112  Are:DelegationConsumer  124  Are:DelegationConsumerSOAP  126  Are:DelegationConsumerSOAP  127  Are:DelegationProviderSOAP  128  Are:DelegationProviderSOAP  128  Are:DelegationProviderSOAP  139  Are:DelegationProviderSOAP  130  Are:DelegationIntribute  131  Are:See:DenyOverridesCombiningAlg (Implement the "Deny-Overrides" algorithm)  134  AreSee::DenyOverridesCombiningAlg (Implement the "Deny-Overrides" algorithm)  138  AreSee::Evallarion (Evaluate whether the two values are equal)  139  AreSee::Evallarion (Evaluate whether the two values are equal)  130  AreSee::Evallarion (Evaluation the value)  131  AreSee::Evallarion (Evaluation the value)  132  AreSee::Evaluation (EvaluationCtx, in charge of storing some context information for evaluation, including Request, current time, etc)  140  AreSee::Evaluator (Interface for policy evaluation. Execute the policy evaluation, based on the request and policy)  141  AreSee::Evaluator (Context for evaluator. It includes the factories which will be used to create related objects)  142  AreSee::Evaluator (Acader (Evaluator Loader is implemented as a helper class for loading different Evaluator objects, like AreEvaluator)  143  Are:EricCache Are:  144  Are:ErileCache  145  Are:EricCache (Filenin ostores information about files (metadata))  155  Are:Ericlarion (Filenin ostores information about files (metadata))  156  Are:Ericlarion (Filenin ostores information about files (metadata))  157  Are:InfoRegister (Registration to ISIS interface)  160  Are:InfoRegister (Registration to ISIS interface)  161  Are:InfoRegister (Registration to ISIS interface)  162  Are:InfoRegister (Handling multiple registrations to ISISes)  163  Are:InfoRegister (Handling multiple registrations to IsISes)  164  Are:InfoRegister (Handling multiple registrations to IsISes)  165  Are:InfoRegister (Handling multiple registra | Arc::DataPoint (This base class is an abstraction of URL)                                      | 93   |
| URLs) Arc:DataSpeed (Keeps track of average and instantaneous transfer speed)  118 Arc:BataSpeed (Keeps track of average and instantaneous transfer speed)  118 Arc:DelegationConsumer  124 Arc:DelegationConsumer  126 Arc:DelegationConsumerSOAP  127 Arc:DelegationProvider  130 Arc:DelegationProvider  130 Arc:DelegationProviderSOAP  132 Arc:DelegationProviderSOAP  133 Arc:DelegationProviderSOAP  134 Arc:Sec::DenyOverridesCombiningAlg (Implement the "Deny-Overrides" algorithm)  135 ArcSec::DenyOverridesCombiningAlg (Implement the "Deny-Overrides" algorithm)  136 ArcSec::EvalInsult (Struct to record the xml node and effect, which will be used by Evaluator to get the information about which rule/policy(in xmlnode) is satisfied)  139 ArcSec::EvalInsultionCix (EvaluationCix, in charge of storing some context information for evaluation, including Request, current time, etc)  140 ArcSec::Evaluator (Interface for policy evaluation. Execute the policy evaluation, based on the request and policy)  141 ArcSec::EvaluatorContext (Context for evaluator. It includes the factories which will be used to create related objects)  142 ArcSec::EvaluatorOndext (Context for evaluator. It includes the factories which will be used to create related objects)  143 Arc:ExpirationReminder (A class intended for internal use within counters)  144 Arc:ExpirationReminder (A class intended for internal use within counters)  145 Arc:Expiration (FileInfo Stores information about files (metadata))  155 ArcSec::Finactory (Interface for function, which is in charge of evaluating two Attribute Value)  157 Arc:InfoGegister (Registration to ISIS interface)  160 Arc:InfoRegister (Registration to ISIS interface)  161 Arc:InfoRegister (Registration process associated with particular ISIS)  162 Arc:InfoRegister (Registration process associated with particular ISIS)  163 Arc:InfoRegister (Registration process associated with particular ISIS)  164 Arc:InformationRequest (Request for information in InfoSystem)  176 Arc:InformationRequest (Request for information | Arc::DataPointDirect (This is a kind of generalized file handle )                              | 104  |
| Arc:DataSpeed (Keeps track of average and instantaneous transfer speed )   | Arc::DataPointIndex (Complements DataPoint with attributes common for Indexing Service         |      |
| Arc:Sec::DateTimeAttribute 122 Arc::DelegationConsumerSOAP 126 Arc::DelegationConsumerSOAP 126 Arc::DelegationContainerSOAP 128 Arc::DelegationProvider 130 Arc::DelegationProviderSOAP 132 Arc::DelegationProviderSOAP 132 Arc::DelegationProviderSOAP 132 Arc::DelegationProviderSOAP 132 ArcSec::DurationAttribute 136 ArcSec::EqualFunction (Evaluate whether the two values are equal ) 134 ArcSec::EvalResult (Struct to record the xml node and effect, which will be used by Evaluator to get the information about which rule/policy(in xmlnode) is satisfied ) 139 ArcSec::EvaluationCtx (EvaluationCtx, in charge of storing some context information for evaluation, including Request, current time, etc ) 140 ArcSec::Evaluator (Interface for policy evaluation. Execute the policy evaluation, based on the request and policy ) 141 ArcSec::Evaluator (Context for evaluator. It includes the factories which will be used to create related objects) 144 Arc::ExlpriationReminder (EvaluatorLoader is implemented as a helper class for loading different Evaluator objects, like ArcEvaluator) 145 Arc::ExlpriationReminder (A class intended for internal use within counters ) 147 Arc::FileCache 147 Arc::FileCache 148 Arc::Enlofo (FileInfo stores information about files (metadata) ) 155 ArcSec::Farcatory (Interface for function factory class ) 156 ArcSec::Function (Interface for function, which is in charge of evaluating two AttributeValue ) 157 Arc::InfoGache (Stores XML document in filesystem split into parts ) 158 Arc::InfoFilter (Filters information document according to identity of requestor ) 159 Arc::InfoRegister (Registration to ISIS interface ) 160 Arc::InfoRegister (Registration to ISIS interface ) 160 Arc::InfoRegister (Registration to ISIS interface ) 160 Arc::InfoRegister (Registration to System message processor ) 164 Arc::InformationRequest (Request for information in InfoSystem ) 170 Arc::InformationRequest (Request for information in InfoSystem ) 171 Arc::InformationRequest (Request for information in InfoSystem ) 172 Arc::LogDestina | URLs)  | 111  |
| Are::DelegationConsumer Are::DelegationConsumerSOAP Are::DelegationContainerSOAP Are::DelegationContainerSOAP Are::DelegationProvider Are::DelegationProvider Are::DelegationProviderSOAP Are::Delegat | Arc::DataSpeed (Keeps track of average and instantaneous transfer speed )                      | 118  |
| Are::DelegationConsumer Are::DelegationConsumerSOAP Are::DelegationContainerSOAP Are::DelegationProvider Are::DelegationProvider Are::DelegationProvider Are::DelegationProvider ArcSee::DenyOverridesCoMbiningAlg (Implement the "Deny-Overrides" algorithm )  134 ArcSee::DurationAttribute 136 ArcSee::EqualFunction (Evaluate whether the two values are equal ) 137 ArcSee::BalaResult (Struct to record the xml node and effect, which will be used by Evaluator to get the information about which rule/policy(in xmlnode) is satisfied ) 139 ArcSee::EvaluationCtx (EvaluationCtx, in charge of storing some context information for evaluation, including Request, current time, etc ) 140 ArcSee::Evaluator (Interface for policy evaluation. Execute the policy evaluation, based on the request and policy ) 141 ArcSee::Evaluator Context (Context for evaluator. It includes the factories which will be used to create related objects ) 142 ArcSee::Evaluator Context (Context for evaluator. It includes the factories which will be used to create related objects ) 143 ArcSee::Evaluator Onder (EvaluatorLoader is implemented as a helper class for loading different Evaluator objects, like ArcEvaluator ) 144 Arc::FileCache 149 Arc::FileInfo (FileInfo stores information about files (metadata)) 145 Arc::FileInfo (FileInfo stores information about files (metadata)) 155 ArcSee::FiFactory (Interface for function factory class) 154 Arc::InfoCache (Stores XML document in filesystem split into parts) 158 Arc::InfoCache (Stores XML document in filesystem split into parts) 158 Arc::InfoRegister (Registration to ISIS interface) 160 Arc::InfoRegister (Registration for System document container and processor) 161 Arc::InfoRegister (Registration process associated with particular ISIS) 163 Arc::InfoRegister (Registration process associated with particular ISIS) 164 Arc::InfoRegister (Registration process associated with particular ISIS) 165 Arc::InfoRegister (Registration process associated with particular ISIS) 166 Arc::InformationInterface (Information System  | ArcSec::DateTimeAttribute  | 122  |
| Are::DelegationConsumerSOAP  | Arc::DelegationConsumer  | 124  |
| Are::DelegationProvider Are::DelegationProviderSOAP Are::D | Arc::DelegationConsumerSOAP  | 126  |
| Are::DelegationProvider Are:DelegationProviderSOAP Are:Sec:DenyOverridesCombiningAlg (Implement the "Deny-Overrides" algorithm ) 134 ArcSec::DurationAttribute 136 ArcSec::EvalResult (Struct to record the xml node and effect, which will be used by Evaluator to get the information about which rule/policy(in xmlnode) is satisfied ) 139 ArcSec::EvalResult (Struct to record the xml node and effect, which will be used by Evaluator to get the information about which rule/policy(in xmlnode) is satisfied ) 139 ArcSec::EvaluationCtx (EvaluationCtx, in charge of storing some context information for evaluation, including Request, current time, etc ) 140 ArcSec::Evaluator (Interface for policy evaluation. Execute the policy evaluation, based on the request and policy ) 141 ArcSec::EvaluatorContext (Context for evaluator. It includes the factories which will be used to create related objects ) 144 ArcSec::EvaluatorContext (Context for evaluator. It includes the factories which will be used to create related objects ) 145 Arc::ExpirationReminder (A class intended for internal use within counters ) 147 Arc::FileCache Evaluator Objects, like ArcEvaluator ) 147 Arc::FileInGore (FileInfo stores information about files (metadata)) 155 ArcSec::FinFactory (Interface for function factory class ) 156 ArcSec::Function (Interface for function, which is in charge of evaluating two AttributeValue ) 157 Arc::InfoRegister (Registration to ISIS interface ) 160 Arc::InfoRegister (Registration to ISIS interface ) 160 Arc::InfoRegister (Registration process associated with particular ISIS ) 163 Arc::InfoRegister (Registration process associated with particular ISIS ) 163 Arc::InfoRegister (Registration process associated with particular ISIS ) 163 Arc::InfoRegister (Registration process associated with particular ISIS ) 163 Arc::InfoRegister (Registration of ISIS interface ) 164 Arc::InfoRegister (Registration of ISIS interface ) 166 Arc::InfoRegister (Registration of ISIS interface ) 167 Arc::InfoRegister (Registration of ISIS interface ) 167  |  |      |
| Are::DelegationProviderSOAP ArcSee::DenyOverridesCombiningAlg (Implement the "Deny-Overrides" algorithm )  |  |      |
| ArcSec::DenyOverridesCombiningAlg (Implement the "Deny-Overrides" algorithm ) 134 ArcSec::EqualFunction (Evaluate whether the two values are equal ) 138 ArcSec::Evallation(Evaluate whether the two values are equal ) 138 ArcSec::Evallation(City (Evaluate whether the two values are equal ) 138 ArcSec::Evaluation(City (EvaluationCtx, in charge of storing some context information for evaluation, including Request, current time, etc ) 140 ArcSec::Evaluator (Interface for policy evaluation. Execute the policy evaluation, based on the request and policy ) 141 ArcSec::Evaluator(Context (Context for evaluator. It includes the factories which will be used to create related objects ) 144 ArcSec::Evaluator(Jonder (Evaluator) 144 ArcSec::Evaluator(Jonder (Evaluator) 144 ArcSec::Evaluator(Jonder (Evaluator) 144 ArcSec::Evaluator objects, like ArcEvaluator ) 145 Arc::ExpirationReminder (A class intended for internal use within counters ) 147 Arc::FileIcCache 144 Arc::FileInfo (FileInfo stores information about files (metadata) ) 155 ArcSec::FireCache 145 ArcSec::FireCache 146 ArcSec::FireCache 147 Arc::InfoCache (Stores XML document in filesystem split into parts ) 157 Arc::InfoCache (Stores XML document in filesystem split into parts ) 158 Arc::InfoFilter (Filers information document according to identity of requestor ) 159 Arc::InfoRegister (Registration to ISIS interface ) 160 Arc::InfoRegister (Registration to ISIS interface ) 161 Arc::InfoRegister (Registration process associated with particular ISIS ) 163 Arc::InfoRegister (Registration system document container and processor ) 164 Arc::InformationInterface (Information System message processor ) 164 Arc::InformationResponse (Information System document container and processor ) 164 Arc::InformationResponse (Information System document container and processor ) 164 Arc::InformationResponse (Information System document container and processor ) 164 Arc::InformationResponse (Information System document container and processor ) 164 Arc::InformationResponse (Information Sy |  |      |
| ArcSec::DurationAttribute ArcSec::EvalResult (Struct to record the xml node and effect, which will be used by Evaluator to get the information about which rule/policy(in xmlnode) is satisfied)  ArcSec::EvalResult (Struct to record the xml node and effect, which will be used by Evaluator to get the information about which rule/policy(in xmlnode) is satisfied)  ArcSec::EvaluationCtx (EvaluationCtx, in charge of storing some context information for evaluation, including Request, current time, etc)  ArcSec::Evaluator (Interface for policy evaluation. Execute the policy evaluation, based on the request and policy)  ArcSec::EvaluatorContext (Context for evaluator. It includes the factories which will be used to create related objects)  ArcSec::EvaluatorTontext (EvaluatorLoader is implemented as a helper class for loading different Evaluator objects, like ArcEvaluator)  Arc::ExpirationReminder (A class intended for internal use within counters)  Arc::FileCache FileCache FileCache Hash  Arc::FileInfo (FileInfo stores information about files (metadata))  ArcSec::Finaction (Interface for function factory class)  ArcSec::Finaction (Interface for function, which is in charge of evaluating two AttributeValue)  Arc::InfoCache (Stores XML document in filesystem split into parts)  Arc::InfoCache (Stores XML document according to identity of requestor)  Arc::InfoRegister (Registration to ISIS interface)  Arc::InfoRegister (Registration formation System document container and processor)  Arc::InfoRegisters (Handling multiple registrations to ISISes)  Arc::InfoRegister (Registration formation System document container and processor)  164  Arc::InformationContainer (Information System document container and processor)  165  Arc::InformationResponse (Information System document container and processor)  166  Arc::InformationResponse (Information System document container and processor)  167  Arc::InformationReponse (Information System document container and processor)  168  Arc::Information Response (Information System document con |  |      |
| ArcSec::EqualFunction (Evaluate whether the two values are equal )   |  |      |
| ArcSec::EvalResult (Struct to record the xml node and effect, which will be used by Evaluator to get the information about which rule/policy(in xmlnode) is satisfied)   |  |      |
| get the information about which rule/policy(in xmlnode) is satisfied )   |  | 150  |
| ArcSec::EvaluationCtx (EvaluationCtx, in charge of storing some context information for evaluation, including Request, current time, etc.)   | · · · · · · · · · · · · · · · · · · ·  | 139  |
| ation, including Request, current time, etc )  |  | 137  |
| ArcSec::Evaluator (Interface for policy evaluation. Execute the policy evaluation, based on the request and policy)  |  | 140  |
| request and policy )   |  | 140  |
| ArcSec::EvaluatorContext (Context for evaluator. It includes the factories which will be used to create related objects)   |  | 141  |
| create related objects )  ArcSec::EvaluatorLoader (EvaluatorLoader is implemented as a helper class for loading different Evaluator objects, like ArcEvaluator )  Arc::ExpirationReminder (A class intended for internal use within counters )  Arc::FileCache  FileCacheHash  Arc::FileInfo (FileInfo stores information about files (metadata) )  Arc::InfoCache (Stores XML document in filesystem split into parts )  Arc::InfoCache (Stores XML document in filesystem split into parts )  Arc::InfoFilter (Filters information document according to identity of requestor )  Arc::InfoRegister (Registration to ISIS interface )  Arc::InfoRegister (Registration to ISIS interface )  Arc::InfoRegister (Registration process associated with particular ISIS )  Arc::InfoRegisters (Handling multiple registrations to ISISes )  Arc::InformationContainer (Information System document container and processor )  164  Arc::InformationRequest (Request for information in InfoSystem )  165  Arc::InformationRequest (Request for information in InfoSystem )  166  Arc::InformationResponse (Informational response from InfoSystem )  170  Arc::Loader (Plugins loader )  171  Arc::Loader (Plugins loader )  172  Arc::LogDestination (A base class for log destinations )  173  Arc::LogDestination (A base class for log destinations )  174  Arc::LogDestination (A base class for log destinations )  175  Arc::LogDestination (A class for log messages )  186  Arc::MCC (Message Chain Component - base class for every MCC plugin )  Arc::MCC (Message Chain Component - base class for every MCC plug |  | 141  |
| Arc:Sec::EvaluatorLoader (EvaluatorLoader is implemented as a helper class for loading different Evaluator objects, like ArcEvaluator)   |  | 144  |
| Evaluator objects, like ArcEvaluator )   |  | 144  |
| Arc::ExpirationReminder (A class intended for internal use within counters)  |  | 1.45 |
| Arc::FileCache FileCacheHash Arc::FileInfo (FileInfo stores information about files (metadata)) Arc::FileInfo (FileInfo stores information about files (metadata)) Arc::FileInfo (FileInfo stores information about files (metadata)) Arc:Sec::FinFactory (Interface for function factory class) ArcSec::Function (Interface for function, which is in charge of evaluating two AttributeValue) 157 Arc::InfoCache (Stores XML document in filesystem split into parts) 158 Arc::InfoFilter (Filters information document according to identity of requestor) 159 Arc::InfoRegister (Registration to ISIS interface) 160 Arc::InfoRegister (Registration to ISIS interface) 161 Arc::InfoRegisters (Handling multiple registrations to ISISes) 162 Arc::InfoRegisters (Registration process associated with particular ISIS) 163 Arc::InformationContainer (Information System document container and processor) 164 Arc::InformationInterface (Information System message processor) 166 Arc::InformationRequest (Request for information in InfoSystem) 167 Arc::InformationResponse (Informational response from InfoSystem) 170 Arc::InformationResponse (Informational response from InfoSystem) 171 Arc::Loader (Plugins loader) 172 Arc::LogDestination (A base class for counters used by threads within a single process) 173 Arc::LogDestination (A base class for log destinations) 174 Arc::LogBestination (A class for log messages) 175 Arc::LogStream (A class for log messages) 176 Arc::LogWessage (A class for log messages) 177 Arc::LogWessage (A class for log messages) 178 Arc::LogCounter (Counterface (Information of MCC processing results) 179 Arc::MCC (Message Chain Component - base class for every MCC plugin) 170 Arc::MCC (Message Chain Component - base class for every MCC plugin) 171 Arc::MCC (Interface for communication between MCC, Service and Plexer objects) 179 Arc::MCCInterface (Interface for communication between MCC, Service and Plexer objects)  |  |      |
| FileCacheHash Arc::FileInfo (FileInfo stores information about files (metadata)) 155 ArcSec::FnFactory (Interface for function factory class) 156 ArcSec::Function (Interface for function, which is in charge of evaluating two AttributeValue) 157 Arc::InfoCache (Stores XML document in filesystem split into parts) 158 Arc::InfoFilter (Filters information document according to identity of requestor) 159 Arc::InfoRegister (Registration to ISIS interface) 160 Arc::InfoRegister (Registration to ISIS interface) 161 Arc::InfoRegisters (Handling multiple registrations to ISISes) 162 Arc::InfoRegisters (Registration process associated with particular ISIS) 163 Arc::InfoRegistrar (Registration System document container and processor) 164 Arc::InformationContainer (Information System message processor) 166 Arc::InformationRequest (Request for information in InfoSystem) 168 Arc::InformationResponse (Informational response from InfoSystem) 170 Arc::IntraProcessCounter (A class for counters used by threads within a single process) 171 Arc::LogDestination (A base class for log destinations) 172 Arc::LogDestination (A base class for log destinations) 173 Arc::LogStream (A class for log messages) 174 Arc::LogStream (A class for log messages) 175 Arc::LogStream (A class for log messages) 176 Arc::LogStream (A class for log messages) 177 Arc::LogStream (A class for log messages) 178 Arc::MCC (Message Chain Component - base class for every MCC plugin) 187 Arc::MCC_Status (A class for communication between MCC, Service and Plexer objects) 198  | · · · · · · · · · · · · · · · · · · ·  |      |
| Arc::FileInfo (FileInfo stores information about files (metadata))   |  |      |
| ArcSec::FnFactory (Interface for function factory class)   |  |      |
| Arc::InfoRegister (Registration process associated with particular ISIS)   |  |      |
| Arc::InfoCache (Stores XML document in filesystem split into parts )   |  |      |
| Arc::InfoFilter (Filters information document according to identity of requestor)  |  |      |
| Arc::InfoRegister (Registration to ISIS interface)   |  |      |
| Arc::InfoRegisterContainer   |  |      |
| Arc::InfoRegisters (Handling multiple registrations to ISISes)   |  |      |
| Arc::InfoRegistrar (Registration process associated with particular ISIS)  |  |      |
| Arc::InformationContainer (Information System document container and processor)  |  |      |
| Arc::InformationInterface (Information System message processor)   |  |      |
| Arc::InformationRequest (Request for information in InfoSystem )   |  |      |
| Arc::IntraProcessCounter (A class for counters used by threads within a single process)  |  |      |
| Arc::IntraProcessCounter (A class for counters used by threads within a single process )   | •  | 168  |
| Arc::Loader (Plugins loader )  |  | 170  |
| Arc::LogDestination (A base class for log destinations)  | · · · · · · · · · · · · · · · · · · ·  | 171  |
| Arc::Logger (A logger class )  | Arc::Loader (Plugins loader )  | 175  |
| Arc::LogMessage (A class for log messages )  | Arc::LogDestination (A base class for log destinations)  | 177  |
| Arc::LogStream (A class for logging to ostreams)   | Arc::Logger (A logger class )  | 179  |
| Arc::MCC (Message Chain Component - base class for every MCC plugin)   | Arc::LogMessage (A class for log messages )  | 182  |
| in regular expression)   | Arc::LogStream (A class for logging to ostreams)   | 184  |
| in regular expression)   | ArcSec::MatchFunction (Evaluate whether arg1 (value in regular expression) matched arg0 (lable |      |
| Arc::MCC (Message Chain Component - base class for every MCC plugin)   |  | 186  |
| Arc::MCC_Status (A class for communication of MCC processing results)  | Arc::MCC (Message Chain Component - base class for every MCC plugin )                          | 187  |
| Arc::MCCInterface (Interface for communication between MCC, Service and Plexer objects ) . 193   | Arc::MCC_Status (A class for communication of MCC processing results )                         |      |
|  | Arc::MCCInterface (Interface for communication between MCC, Service and Plexer objects).       |      |
|  | Arc::MCCLoader (Creator of Message Component Chains (MCC))                                     | 195  |

| Arc::MD5Sum (Implementation of MD5 checksum)   | 197  |
|--|------|
| Arc::Message (Object being passed through chain of MCCs )  | 198  |
| Arc::MessageAttributes (A class for storage of attribute values )  | 201  |
| Arc::MessageAuth (Contains authencity information, authorization tokens and decisions)                             | 204  |
| Arc::MessageAuthContext (Handler for content of message auth* context )  | 206  |
| Arc::MessageContext (Handler for content of message context )  | 207  |
| Arc::MessageContextElement (Top class for elements contained in message context)                                   | 208  |
| Arc::MessagePayload (Base class for content of message passed through chain )                                      | 209  |
| Arc::ModuleManager (Manager of shared libraries )  | 210  |
| Arc::MultiSecAttr (Container of multiple SecAttr attributes )  |      |
| Arc::MySQLDatabase   |      |
| Arc::PayloadRaw (Raw byte multi-buffer )   |      |
| Arc::PayloadRawInterface (Random Access Payload for Message objects )  |      |
| Arc::PayloadSOAP (Payload of Message with SOAP content )   |      |
| Arc::PayloadStream (POSIX handle as Payload)   |      |
| Arc::PayloadStreamInterface (Stream-like Payload for Message object)   |      |
| Arc::PayloadWSRF (This class combines MessagePayload with WSRF)  |      |
| ArcSec::PDP (Base class for Policy Decision Point plugins)   |      |
| ArcSec::PeriodAttribute  |      |
| ArcSec::PermitOverridesCombiningAlg (Implement the "Permit-Overrides" algorithm)                                   |      |
| Arc::Plexer (The Plexer class, used for routing messages to services)  |      |
| Arc::PlexerEntry (A pair of label (regex) and pointer to service)  |      |
|  |      |
| Arc::Plugin (Base class for loadable ARC components)   |      |
| Arc::PluginArgument (Base class for passing arguments to loadable ARC components)                                  |      |
| Arc::PluginDescriptor (Description of ARC lodable component)   |      |
| Arc::PluginsFactory (Generic ARC plugins loader)   |      |
| ArcSec::Policy (Interface for containing and processing different types of policy)                                 | 243  |
| ArcSec::PolicyParser (A interface which will isolate the policy object from actual policy storage                  | 246  |
| (files, urls, database))   | 246  |
| ArcSec::PolicyStore (Storage place for policy objects )  |      |
| Arc::RegularExpression (A regular expression class )   | 248  |
| ArcSec::Request (Base class/Interface for request, includes a container for RequestItems and                       | 2.50 |
| some operations)   | 250  |
| ArcSec::RequestAttribute (Wrapper which includes AttributeValue object which is generated ac-                      |      |
| cording to date type of one spefic node in Request.xml)  | 252  |
| ArcSec::RequestItem (Interface for request item container, <subjects, actions,="" ctxs="" objects,=""></subjects,> |      |
| tuple)   | 253  |
| ArcSec::RequestTuple (RequestTuple, container which includes the )   |      |
| ArcSec::Response (Container for the evaluation results )   |      |
| ArcSec::ResponseItem (Evaluation result concerning one RequestTuple )  |      |
| Arc::Run   | 257  |
| RuntimeEnvironment   | 261  |
| RuntimeEnvironmentError  | 263  |
| Arc::SAMLToken (Class for manipulating SAML Token Profile )  | 264  |
| Arc::SecAttr (This is an abstract interface to a security attribute )  | 267  |
| Arc::SecAttrFormat (Export/import format )   | 270  |
| Arc::SecAttrValue (This is an abstract interface to a security attribute )   | 271  |
| ArcSec::SecHandler (Base class for simple security handling plugins )  | 273  |
| ArcSec::Security (Common stuff used by security related slasses )  | 274  |
| Arc::Service (Service - last component in a Message Chain )  | 275  |
| Arc::SimpleCondition (Simple triggered condition )   | 278  |
| Arc::SOAPMessage (Message restricted to SOAP payload )   | 280  |
| ArcSec::Source (Acquires and parses XML document from specified source)  |      |
| ArcSec::SourceFile (Convenience class for obtaining XML document from file )                                       |      |
|  |      |

| ArcSec::SourceURL (Convenience class for obtaining XML document from remote URL)           | 285 |
|--|-----|
| Arc::Time (A class for storing and manipulating times )                                    | 286 |
| ArcSec::TimeAttribute  | 289 |
| Arc::URL (Class to hold general URL's)   | 291 |
| Arc::URLLocation (Class to hold a resolved URL location)                                   | 299 |
| Arc::UsernameToken (Interface for manipulation of WS-Security according to Username Token  |     |
| Profile )  | 301 |
| Are::VOMSTrustList   | 304 |
| Arc::WSAEndpointReference (Interface for manipulation of WS-Adressing Endpoint Reference ) | 306 |
| Arc::WSAHeader (Interface for manipulation WS-Addressing information in SOAP header ) 3    | 308 |
| Arc::WSRF (Base class for every WSRF message )   | 311 |
| Arc::WSRFBaseFault (Base class for WSRF fault messages )                                   | 313 |
| Arc::WSRP (Base class for WS-ResourceProperties structures )                               | 315 |
| Arc::WSRPFault (Base class for WS-ResourceProperties faults )                              | 317 |
| Arc::WSRPResourcePropertyChangeFailure   | 318 |
| Arc::X509Token (Class for manipulating X.509 Token Profile )                               | 319 |
| Arc::XMLNode (Wrapper for LibXML library Tree interface )                                  | 321 |
| Arc::XMLNodeContainer  | 331 |
| Arc::XMLSecNode (Extends XMLNode class to support XML security operation)                  | 333 |

# **Hosting Environment (Daemon) Namespace Documentation**

### 4.1 Arc Namespace Reference

Some utility methods for using xml security library (http://www.aleksey.com/xmlsec/).

### Classes

- class ACC
- class ACCConfig
- class ACCPluginArgument
- · class ACCLoader
- · class Broker
- class ClientInterface
- class ClientTCP
- struct HTTPClientInfo
- class ClientHTTP
- class ClientSOAP
- class ClientHTTPwithSAML2SSO
- class ClientSOAPwithSAML2SSO
- class ClientX509Delegation
- · struct Benchmark
- struct ApplicationEnvironment
- class ExecutionTarget
- class Job
- class JobController
- class JobDescriptionError
- struct Candidate
- class StringManipulator
- class JobDescriptionParser
- · class PosixJSDLParser
- · class JSDLParser
- class XRSLParser
- class JDLParser

- class JobDescriptionOrderer
- class JobDescription
- struct ReferenceTimeType
- struct EnvironmentType
- struct XLogueType
- struct RunTimeEnvironmentType
- struct NotificationType
- struct SourceType
- struct TargetType
- struct FileType
- struct **DirectoryType**
- class JobInnerRepresentation
- class JobSupervisor
- · class Submitter
- class TargetGenerator
- class TargetRetriever
- class UserConfig
- · class Config

Configuration element - represents (sub)tree of ARC configuration.

- struct WSSInfo
- class BaseConfig
- · class ArcLocation

Determines ARC installation location.

• class RegularExpression

A regular expression class.

- class Base64
- class MemoryAllocationException
- class ByteArray
- class Counter

A class defining a common interface for counters.

class CounterTicket

A class for "tickets" that correspond to counter reservations.

• class ExpirationReminder

A class intended for internal use within counters.

- · class Period
- class Time

A class for storing and manipulating times.

• class Database

Interface for calling database client library.

- class Query
- class DItem
- class DBranch

- · class DItemString
- class FileLock
- class IntraProcessCounter

A class for counters used by threads within a single process.

- class PrintFBase
- class PrintF
- class IString
- class LogMessage

A class for log messages.

• class LogDestination

A base class for log destinations.

• class LogStream

A class for logging to ostreams.

• class Logger

A logger class.

- class MySQLDatabase
- · class MySQLQuery
- class OptionParser
- class Run
- class SimpleCondition

Simple triggered condition.

• class URL

Class to hold general URL's.

• class URLLocation

Class to hold a resolved URL location.

- class PathIterator
- class User
- class AutoPointer

Wrapper for pointer with automatic destruction.

• class CountedPointer

Wrapper for pointer with automatic destruction and mutiple references.

- class NS
- class XMLNode

Wrapper for LibXML library Tree interface.

- class XMLNodeContainer
- class CredentialError
- class Credential
- class VOMSTrustList
- class CheckSum

Defines interface for variuos checksum manipulations.

• class CRC32Sum

Implementation of CRC32 checksum.

• class MD5Sum

Implementation of MD5 checksum.

class CheckSumAny

Wraper for CheckSum class.

• class DataBuffer

Represents set of buffers.

- class DataCallback
- class DataHandle

This class is a wrapper around the DataPoint class.

- class DataMover
- class DataPoint

This base class is an abstraction of URL.

• class DataPointDirect

This is a kind of generalized file handle.

• class DataPointIndex

Complements DataPoint with attributes common for Indexing Service URLs.

class DataSpeed

Keeps track of average and instantaneous transfer speed.

- class DataStatus
- · class DMC
- class DMCConfig
- class DMCPluginArgument
- class DMCLoader
- struct CacheParameters
- class FileCache
- class FileInfo

FileInfo stores information about files (metadata).

- class URLMap
- · class XmlContainer
- class XmlDatabase
- class DelegationConsumer
- · class DelegationProvider
- class DelegationConsumerSOAP
- class DelegationProviderSOAP
- class DelegationContainerSOAP
- · class GlobusResult

- class GSSCredential
- class InfoCache

Stores XML document in filesystem split into parts.

- class InfoCacheInterface
- class InfoFilter

Filters information document according to identity of requestor.

• class InfoRegister

Registration to ISIS interface.

• class InfoRegisters

Handling multiple registrations to ISISes.

• class InfoRegistrar

Registration process associated with particular ISIS.

- class InfoRegisterContainer
- class InformationInterface

Information System message processor.

• class InformationContainer

Information System document container and processor.

• class InformationRequest

Request for information in InfoSystem.

• class InformationResponse

Informational response from InfoSystem.

class Loader

Plugins loader.

• class ModuleManager

Manager of shared libraries.

• class Plugin

Base class for loadable ARC components.

• class PluginArgument

Base class for passing arguments to loadable ARC components.

• struct PluginDescriptor

Description of ARC lodable component.

• class PluginsFactory

Generic ARC plugins loader.

• class MCCInterface

Interface for communication between MCC, Service and Plexer objects.

• class MCC

Message Chain Component - base class for every MCC plugin.

- class MCCConfig
- class MCCPluginArgument
- class MCC\_Status

A class for communication of MCC processing results.

• class MCCLoader

Creator of Message Component Chains (MCC).

class ChainContext

Interface to chain specific functionality.

· class MessagePayload

Base class for content of message passed through chain.

• class MessageContextElement

Top class for elements contained in message context.

• class MessageContext

Handler for content of message context.

class MessageAuthContext

Handler for content of message auth\* context.

• class Message

Object being passed through chain of MCCs.

• class AttributeIterator

An iterator class for accessing multiple values of an attribute.

class MessageAttributes

A class for storage of attribute values.

class MessageAuth

Contains authencity information, authorization tokens and decisions.

• class PayloadRawInterface

Random Access Payload for Message objects.

- struct PayloadRawBuf
- class PayloadRaw

Raw byte multi-buffer.

• class PayloadSOAP

Payload of Message with SOAP content.

• class PayloadStreamInterface

Stream-like Payload for Message object.

• class PayloadStream

POSIX handle as Payload.

class PlexerEntry

A pair of label (regex) and pointer to service.

class Plexer

The Plexer class, used for routing messages to services.

• class CIStringValue

This class implements case insensitive strings as security attributes.

• class SecAttrValue

This is an abstract interface to a security attribute.

• class SecAttrFormat

Export/import format.

• class SecAttr

This is an abstract interface to a security attribute.

• class MultiSecAttr

Container of multiple SecAttr attributes.

• class Service

Service - last component in a Message Chain.

- class ServicePluginArgument
- class SOAPMessage

Message restricted to SOAP payload.

- class ClassLoader
- class ClassLoaderPluginArgument
- class WSAEndpointReference

Interface for manipulation of WS-Adressing Endpoint Reference.

• class WSAHeader

Interface for manipulation WS-Addressing information in SOAP header.

• class **SAMLToken** 

Class for manipulating SAML Token Profile.

• class UsernameToken

Interface for manipulation of WS-Security according to Username Token Profile.

• class X509Token

Class for manipulating X.509 Token Profile.

class PayloadWSRF

This class combines MessagePayload with WSRF.

class WSRP

Base class for WS-ResourceProperties structures.

· class WSRPFault

Base class for WS-ResourceProperties faults.

- class WSRPInvalidResourcePropertyQNameFault
- class WSRPResourcePropertyChangeFailure
- class WSRPUnableToPutResourcePropertyDocumentFault
- class WSRPInvalidModificationFault
- class WSRPUnableToModifyResourcePropertyFault
- class WSRPSetResourcePropertyRequestFailedFault
- class WSRPInsertResourcePropertiesRequestFailedFault
- class WSRPUpdateResourcePropertiesRequestFailedFault
- class WSRPDeleteResourcePropertiesRequestFailedFault
- class WSRPGetResourcePropertyDocumentRequest
- class WSRPGetResourcePropertyDocumentResponse
- class WSRPGetResourcePropertyRequest
- class WSRPGetResourcePropertyResponse
- class WSRPGetMultipleResourcePropertiesRequest
- class WSRPGetMultipleResourcePropertiesResponse
- class WSRPPutResourcePropertyDocumentRequest
- class WSRPPutResourcePropertyDocumentResponse
- class WSRPModifyResourceProperties
- class WSRPInsertResourceProperties
- class WSRPUpdateResourceProperties
- class WSRPDeleteResourceProperties
- $\bullet \ class \ WSRPS et Resource Properties Request$
- $\bullet \ class \ WSRPS et Resource Properties Response$
- $\bullet \ class \ WSRPInsertResource Properties Request$
- class WSRPInsertResourcePropertiesResponse
- $\bullet \ class \ WSRPUp date Resource Properties Request \\$
- class WSRPUpdateResourcePropertiesResponse
   class WSRPDeleteResourcePropertiesRequest
- class WSRPDeleteResourcePropertiesResponse
- class WSRPQueryResourcePropertiesRequest
- class WSRPQueryResourcePropertiesResponse
- class WSRF

Base class for every WSRF message.

• class WSRFBaseFault

Base class for WSRF fault messages.

- class WSRFResourceUnknownFault
- class WSRFResourceUnavailableFault
- class XMLSecNode

Extends XMLNode class to support XML security operation.

### **Typedefs**

- typedef std::map< std::string, std::list< URL >> URLListMap
- typedef std::vector< std::string >> QueryArrayResult
- typedef std::vector< std::string > QueryRowResult
- typedef std::list< Arc::XMLNode > XMLNodeList
- typedef std::vector< std::string > VOMSTrustChain
- typedef std::string VOMSTrustRegex
- typedef std::map< std::string, std::string > **DelegationRestrictions**
- typedef std::list< std::pair< std::string, XMLNode >> InfoFilterPolicies
- typedef std::map< std::string, Glib::Module \* > plugin\_cache\_t
- typedef Plugin \*(\*) get\_plugin\_instance (PluginArgument \*arg)
- typedef std::multimap< std::string, std::string > AttrMap
- typedef AttrMap::const\_iterator AttrConstIter
- typedef AttrMap::iterator AttrIter
- typedef Plugin LoadableClass

### **Enumerations**

Address.

WSAFaultInvalidEPR,

WSAFaultDuplicateMessageID,

```
• enum SecurityLayer { NoSec, TLSSec, GSISec }
• enum DelegationType {
 DELEG_ARC, DELEG_GRIDSITE, DELEG_GT4, DELEG_MYPROXY,
 DELEG_UNKNOWN }
• enum WSSType {
 NONE, USERNAMETOKEN, X509TOKEN, SAMLTOKEN,
 KERBEROSTOKEN }
• enum TimeFormat {
 MDSTime, ASCTime, UserTime, ISOTime,
 UTCTime, RFC1123Time }
• enum PeriodBase {
 PeriodMiliseconds, PeriodSeconds, PeriodMinutes, PeriodHours,
 PeriodDays, PeriodWeeks }
• enum LogLevel {
 VERBOSE = 1, DEBUG = 2, INFO = 4, WARNING = 8,
 ERROR = 16, FATAL = 32 }
• enum Credformat { PEM, DER, PKCS, UNKNOWN }
enum StatusKind {
 STATUS_UNDEFINED = 0, STATUS_OK = 1, GENERIC_ERROR = 2, PARSING_ERROR = 4,
 PROTOCOL_RECOGNIZED_ERROR = 8, UNKNOWN_SERVICE_ERROR = 16, BUSY_-
 ERROR = 32, SESSION CLOSE = 64 }
• enum WSAFault {
 WSAFaultNone, WSAFaultUnknown, WSAFaultInvalidAddressingHeader, WSAFaultInvalid-
```

WSAFaultInvalidCardinality,

NonAnonymousAddressSupported, WSAFaultMessageAddressingHeaderRequired,

WSAFaultActionMismatch, WSAFaultOnlyAnonymousAddressSupported, WSAFaultOnly-

WSAFaultMissingAddressInEPR,

 $WSAF ault Destination Unreachable, WSAF ault Action Not Supported, WSAF ault Endpoint Unavailable \ \}$ 

• enum SignatureMethod { RSA\_SHA1, DSA\_SHA1 }

### **Functions**

- std::ostream & operator << (std::ostream &, const Period &)
- std::ostream & operator << (std::ostream &, const Time &)
- std::string TimeStamp (const TimeFormat &=Time::GetFormat())
- std::string TimeStamp (Time, const TimeFormat &=Time::GetFormat())
- void GUID (std::string &guid)
- std::string UUID (void)
- const char \* **FindTrans** (const char \*p)
- std::ostream & operator<< (std::ostream &os, const IString &msg)
- std::ostream & operator<< (std::ostream &os, LogLevel level)
- LogLevel string\_to\_level (const std::string &str)
- template<typename T> T stringto (const std::string &s)
- template<typename T> bool stringto (const std::string &s, T &t)
- template<typename T> std::string tostring (T t, const int width=0, const int precision=0)
- std::string upper (const std::string &s)
- void tokenize (const std::string &str, std::vector< std::string > &tokens, const std::string &delimiters="")
- std::string trim (const std::string &str, const char \*sep=NULL)
- std::string uri\_unescape (const std::string &str)
- bool CreateThreadFunction (void(\*func)(void \*), void \*arg)
- std::list< URL > ReadURLList (const URL &urllist)
- std::string GetEnv (const std::string &var)
- bool SetEnv (const std::string &var, const std::string &value)
- void UnsetEnv (const std::string &var)
- std::string StrError (int errnum=errno)
- std::ostream & operator << (std::ostream &out, const XMLNode &node)
- std::istream & operator>> (std::istream &in, XMLNode &node)
- bool MatchXMLName (const XMLNode &node1, const XMLNode &node2)
- bool MatchXMLName (const XMLNode &node, const char \*name)
- bool MatchXMLName (const XMLNode &node, const std::string &name)
- bool MatchXMLNamespace (const XMLNode &node1, const XMLNode &node2)
- bool MatchXMLNamespace (const XMLNode &node, const char \*uri)
- bool MatchXMLNamespace (const XMLNode &node, const std::string &uri)
- void InitVOMSAttribute (void)
- int createVOMSAC (X509 \*issuer, STACK\_OF(X509)\*issuerstack, X509 \*holder, EVP\_PKEY \*pkey, BIGNUM \*serialnum, std::vector< std::string > &fqan, std::vector< std::string > &targets, std::vector< std::string > &attributes, ArcCredential::AC \*\*ac, std::string voname, std::string uri, int lifetime)
- bool createVOMSAC (std::string &codedac, Arc::Credential &issuer\_cred, Arc::Credential &holder\_cred, std::vector< std::string > &fqan, std::vector< std::string > &targets, std::vector< std::string > &targets, std::vector<
- bool addVOMSAC (ArcCredential::AC \*\*&aclist, std::string &codedac)
- bool parseVOMSAC (X509 \*holder, const std::string &ca\_cert\_dir, const std::string &ca\_cert\_file, const VOMSTrustList &vomscert\_trust\_dn, std::vector< std::string > &output)

- bool parseVOMSAC (Arc::Credential &holder\_cred, const std::string &ca\_cert\_dir, const std::string &ca\_cert\_file, const VOMSTrustList &vomscert\_trust\_dn, std::vector< std::string > &output)
- std::string globus\_object\_to\_string (globus\_object\_t \*err)
- std::ostream & operator<< (std::ostream &o, globus\_object\_t \*err)
- std::ostream & operator << (std::ostream &o, const GlobusResult &res)
- template < class P > P \* **PluginCast** (**PluginArgument** \*p)
- template<class P> P \* PluginCast (Plugin \*p)
- std::string string (StatusKind kind)
- const char \* ContentFromPayload (const MessagePayload &payload)
- void WSAFaultAssign (SOAPEnvelope &mesage, WSAFault fid)
- WSAFault WSAFaultExtract (SOAPEnvelope &message)
- WSRF & CreateWSRP (SOAPEnvelope &soap)
- WSRF & CreateWSRFBaseFault (SOAPEnvelope &soap)
- std::string SignQuery (std::string query, SignatureMethod sign\_method, std::string &privkey\_file)
- bool **VerifyQuery** (const std::string query, const xmlSecKey \*sender\_public\_key)
- std::string **BuildDeflatedQuery** (const Arc::XMLNode &node)
- bool **BuildNodefromMsg** (const std::string msg, Arc::XMLNode &node)
- int passphrase\_callback (char \*buf, int size, int rwflag, void \*)
- bool init xmlsec (void)
- bool final xmlsec (void)
- std::string get\_cert\_str (const char \*certfile)
- xmlSecKey \* get key from keystr (const std::string &value)
- xmlSecKey \* get\_key\_from\_keyfile (const char \*keyfile)
- std::string get\_key\_from\_certfile (const char \*certfile)
- xmlSecKey \* get\_key\_from\_certstr (const std::string &value)
- xmlSecKeysMngrPtr load\_key\_from\_keyfile (xmlSecKeysMngrPtr \*keys\_manager, const char \*keyfile)
- xmlSecKeysMngrPtr load\_key\_from\_certfile (xmlSecKeysMngrPtr \*keys\_manager, const char \*certfile)
- xmlSecKeysMngrPtr load\_key\_from\_certstr (xmlSecKeysMngrPtr \*keys\_manager, const std::string &certstr)
- xmlSecKeysMngrPtr load\_trusted\_cert\_file (xmlSecKeysMngrPtr \*keys\_manager, const char \*cert\_file)
- xmlSecKeysMngrPtr load\_trusted\_cert\_str (xmlSecKeysMngrPtr \*keys\_manager, const std::string &cert\_str)
- xmlSecKeysMngrPtr load\_trusted\_certs (xmlSecKeysMngrPtr \*keys\_manager, const char \*cafile, const char \*capath)
- XMLNode get\_node (XMLNode &parent, const char \*name)

### **Variables**

- const Glib::TimeVal ETERNAL
- const Glib::TimeVal HISTORIC
- Logger stringLogger
- Logger CredentialLogger
- const char \* plugins\_table\_name
- const char \* WSRFBaseFaultAction

### 4.1.1 Detailed Description

Some utility methods for using xml security library (http://www.aleksey.com/xmlsec/).

Credential class covers the functionality about general processing about certificate/key files, including: 1. cerficate/key parsing, information extracting (such as subject name, issuer name, lifetime, etc.), chain verifying, extension processing about proxy certinfo, extension processing about other general certificate extension (such as voms attributes, it should be the extension-specific code itself to create, parse and verify the extension, not the Credential class. For voms, it is some code about writing and parsing vomsimplementing Attibute Certificate/ RFC3281, the voms-attibute is then be looked as a binary part and embeded into extension of X509 certificate/proxy certificate); 2. certificate request, extension emeding and certificate signing, for both proxy certificate and EEC (end entity certificate) certificate The Crendential class support PEM, DER PKCS12 credential.

### 4.1.2 Typedef Documentation

### 4.1.2.1 typedef Plugin\*(\*) Arc::get\_plugin\_instance(PluginArgument \*arg)

Constructor function of ARC lodable component.

This function is called with plugin-specific argument and should produce and return valid instance of plugin. If plugin can't be produced by any reason (for example because passed argument is not applicable) then NULL is returned. No exceptions should be raised.

### 4.1.2.2 typedef std::multimap<std::string> Arc::AttrMap

A typefed of a multimap for storage of message attributes.

This typedef is used as a shorthand for a multimap that uses strings for keys as well as values. It is used within the Messsage Attributes class for internal storage of message attributes, but is not visible externally.

### 4.1.2.3 typedef AttrMap::const\_iterator Arc::AttrConstIter

A typedef of a const\_iterator for AttrMap.

This typedef is used as a shorthand for a const\_iterator for AttrMap. It is used extensively within the MessageAttributes class as well as the AttributesIterator class, but is not visible externally.

### 4.1.2.4 typedef AttrMap::iterator Arc::AttrIter

A typedef of an (non-const) iterator for AttrMap.

This typedef is used as a shorthand for a (non-const) iterator for AttrMap. It is used in one method within the MessageAttributes class, but is not visible externally.

### **4.1.3** Enumeration Type Documentation

### 4.1.3.1 enum Arc::WSSType

Configuration information for WS-Security, including WS-Security profile type, and the information which will be used by the specific WS-Security profile.

#### 4.1.3.2 enum Arc::TimeFormat

An enumeration that contains the possible textual timeformats.

#### 4.1.3.3 enum Arc::LogLevel

Logging levels.

Logging levels for tagging and filtering log messages. FATAL level designates very severe error events that will presumably lead the application to abort. ERROR level designates error events that might still allow the application to continue running. WARNING level designates potentially harmful situations. INFO level designates informational messages that highlight the progress of the application at coarse-grained level. DEBUG level designates fine-grained informational events that are most useful to debug an application. VERBOSE level designates finer-grained informational events than the DEBUG

### 4.1.3.4 enum Arc::StatusKind

Status kinds (types).

This enum defines a set of possible status kinds.

#### **Enumerator:**

STATUS\_OK Default status - undefined error.

**GENERIC\_ERROR** No error.

PARSING\_ERROR Error does not fit any class.

**PROTOCOL\_RECOGNIZED\_ERROR** Error detected while parsing request/response.

UNKNOWN\_SERVICE\_ERROR Message does not fit into expected protocol.

**BUSY\_ERROR** There is no destination configured for this message.

SESSION\_CLOSE Message can't be processed now.

### 4.1.3.5 enum Arc::WSAFault

WS-Addressing possible faults.

### **Enumerator:**

WSAFaultUnknown This is not a fault

WSAFaultInvalidAddressingHeader This is not a WS-Addressing fault

### **4.1.4** Function Documentation

### 4.1.4.1 std::ostream& Arc::operator<< (std::ostream &, const Period &)

Prints a Period-object to the given ostream – typically cout.

#### 4.1.4.2 std::ostream& Arc::operator<< (std::ostream &, const Time &)

Prints a Time-object to the given ostream – typically cout.

### **4.1.4.3 std::string Arc::TimeStamp (const TimeFormat & =** Time::GetFormat())

Returns a time-stamp of the current time in some format.

### **4.1.4.4 std::string Arc::TimeStamp (Time, const TimeFormat & =** Time::GetFormat())

Returns a time-stamp of some specified time in some format.

### 4.1.4.5 void Arc::GUID (std::string & guid)

This function generates a random identifier which is quite unique as well.

### 4.1.4.6 std::string Arc::UUID (void)

This function generates uuid.

### 4.1.4.7 std::ostream& Arc::operator<< (std::ostream & os, LogLevel level)

Printing of LogLevel values to ostreams.

Output operator so that LogLevel values can be printed in a nicer way.

### **4.1.4.8** template<typename T> T Arc::stringto (const std::string & s)

This method converts a string to any type.

### 4.1.4.9 template<typename T> bool Arc::stringto (const std::string & s, T & t)

This method converts a string to any type but lets calling function process errors.

### **4.1.4.10** template<typename T> std::string Arc::tostring (T t, const int width = 0, const int precision = 0)

This method converts any type to a string of the width given.

### **4.1.4.11** std::string Arc::upper (const std::string & s)

This method converts to upper case of the string.

### 4.1.4.12 void Arc::tokenize (const std::string & str, std::vector< std::string > & tokens, const std::string & delimiters = " ")

This method tokenize string.

### 4.1.4.13 std::string Arc::trim (const std::string & str, const char \* sep = NULL)

This method removes given separators from the beginning and the end of the string.

### 4.1.4.14 std::string Arc::uri\_unescape (const std::string & str)

This method unescape the URI encoded string.

### **4.1.4.15** bool Arc::CreateThreadFunction (void(\*)(void \*) func, void \* arg)

Helper function to create simple thread.

It takes care of all pecularities og Glib::Thread API. As result it runs function 'func' with argument 'arg' in a separate thread. Returns true on success.

### 4.1.4.16 std::list<URL> Arc::ReadURLList (const URL & urllist)

Reads a list of URLs from a file.

### 4.1.4.17 std::string Arc::GetEnv (const std::string & var)

Portable function for getting environment variables.

#### 4.1.4.18 bool Arc::SetEnv (const std::string & var, const std::string & value)

Portable function for setting environment variables.

### 4.1.4.19 void Arc::UnsetEnv (const std::string & var)

Portable function for unsetting environment variables.

### **4.1.4.20** std::string Arc::StrError (int errnum = errno)

Portable function for obtaining description of last system error.

### 4.1.4.21 bool Arc::MatchXMLName (const XMLNode & node1, const XMLNode & node2)

Returns true if underlying XML elements have same names

### 4.1.4.22 bool Arc::MatchXMLName (const XMLNode & node, const char \* name)

Returns true if 'name' matches name of 'node'. If name contains prefix it's checked too

### 4.1.4.23 bool Arc::MatchXMLName (const XMLNode & node, const std::string & name)

Returns true if 'name' matches name of 'node'. If name contains prefix it's checked too

### 4.1.4.24 bool Arc::MatchXMLNamespace (const XMLNode & node1, const XMLNode & node2)

Returns true if underlying XML elements belong to same namespaces

### 4.1.4.25 bool Arc::MatchXMLNamespace (const XMLNode & node, const char \* uri)

Returns true if 'namespace' matches 'node's namespace.

### 4.1.4.26 bool Arc::MatchXMLNamespace (const XMLNode & node, const std::string & uri)

Returns true if 'namespace' matches 'node's namespace.

4.1.4.27 int Arc::createVOMSAC (X509 \* issuer, STACK\_OF(X509)\* issuerstack, X509 \* holder, EVP\_PKEY \* pkey, BIGNUM \* serialnum, std::vector< std::string > & fqan, std::vector< std::string > & attributes, ArcCredential::AC \*\* ac, std::string voname, std::string uri, int lifetime)

!!! TO DOCUMENT !!! Each argument MUST be explained properly. What is fqan? What is target? What attributes are supported? In worst case there must be reference to documentation.

4.1.4.28 bool Arc::createVOMSAC (std::string & codedac, Arc::Credential & issuer\_cred, Arc::Credential & holder\_cred, std::vector< std::string > & fqan, std::vector< std::string > & attributes, std::string & voname, std::string & uri, int lifetime)

Create AC(Attribute Certificate) with voms specific format.

#### **Parameters:**

codedac The coded AC as output of this methodissuer\_cred The issuer credential which is used to sign the ACholder\_cred The holder credential, the holder certificate is the one which carries ACfqan !!! TO DOCUMENT: content/meaning of arguments, missing arguments.

4.1.4.29 bool Arc::parseVOMSAC (X509 \* holder, const std::string & ca\_cert\_dir, const std::string & ca\_cert\_file, const VOMSTrustList & vomscert\_trust\_dn, std::vector < std::string > & output)

Parse the certificate, and output the attributes.

#### **Parameters:**

holder The proxy certificate which includes the voms specific formated AC.

ca\_cert\_dir The trusted certificates which are used to verify the certificate which is used to sign the
AC

ca\_cert\_file The same as ca\_cert\_dir except it is a file instead of a directory. Only one of them need to be set

vomsdir The directory which include \*.lsc file for each vo. For instance, a vo called "knowarc.eu" should have file \$prefix/vomsdir/knowarc/voms.knowarc.eu.lsc which contains on the first line the DN of the VOMS server, and on the second line the corresponding CA DN: /O=Grid/O=NorduGrid/OU=KnowARC/CN=voms.knowarc.eu /O=Grid/O=NorduGrid/CN=NorduGrid Certification Authority See more in : https://twiki.cern.ch/twiki/bin/view/LCG/VomsFAQforServiceManagers

output The parsed attributes (Role and Generic Attribute). Each attribute is stored in element of a vector as a string. It is up to the consumer to understand the meaning of the attribute. An example is as following: TO DOCUMENT: some attributes generated by this function are as stored in AC, those must be described. For example there are no VO= and grantor= in VOMS AC. grantor=knowarc://squark.uio.no:15011/knowarc:Degree=Ph-D voname=knowarc://squark.uio.no:15011 VO=knowarc VO=knowarc/Group=UiO/Role=technician

## 4.1.4.30 bool Arc::parseVOMSAC (Arc::Credential & holder\_cred, const std::string & ca\_cert\_dir, const std::string & ca\_cert\_file, const VOMSTrustList & vomscert\_trust\_dn, std::vector < std::string > & output)

Parse the certificate. The same as the above one

### 4.1.4.31 std::string Arc::string (StatusKind kind)

Conversion to string.

Conversion from StatusKind to string.

#### Parameters:

kind The StatusKind to convert.

### 4.1.4.32 const char\* Arc::ContentFromPayload (const MessagePayload & payload)

Returns pointer to main memory chunk of Message payload.

If no buffer is present or if payload is not of PayloadRawInterface type NULL is returned.

### 4.1.4.33 void Arc::WSAFaultAssign (SOAPEnvelope & mesage, WSAFault fid)

Makes WS-Addressing fault.

It fills SOAP Fault message with WS-Addressing fault related information.

### 4.1.4.34 WSAFault Arc::WSAFaultExtract (SOAPEnvelope & message)

Gets WS-addressing fault.

Analyzes SOAP Fault message and returns WS-Addressing fault it represents.

### 4.1.4.35 int Arc::passphrase\_callback (char \* buf, int size, int rwflag, void \*)

callback method for inputing passphrase of key file

### 4.1.4.36 bool Arc::init\_xmlsec (void)

Initialize the xml security library, it should be called before the xml security functionality is used.

### 4.1.4.37 bool Arc::final\_xmlsec (void)

Finalize the xml security library

### 4.1.4.38 std::string Arc::get\_cert\_str (const char \* certfile)

Get certificate in string format from certificate file

### 4.1.4.39 xmlSecKey\* Arc::get\_key\_from\_keystr (const std::string & value)

Get key in xmlSecKey structure from key in string format

### 4.1.4.40 xmlSecKey\* Arc::get\_key\_from\_keyfile (const char \* keyfile)

Get key in xmlSecKey structure from key file

### 4.1.4.41 std::string Arc::get\_key\_from\_certfile (const char \* certfile)

Get public key in string format from certificate file

### 4.1.4.42 xmlSecKey\* Arc::get\_key\_from\_certstr (const std::string & value)

Get public key in xmlSecKey structure from certificate string (the string under "—BEGIN CERTIFICATE——" and "—END CERTIFICATE——")

### 4.1.4.43 xmlSecKeysMngrPtr Arc::load\_key\_from\_keyfile (xmlSecKeysMngrPtr \* keys\_manager, const char \* keyfile)

Load private or public key from a key file into key manager

### 4.1.4.44 xmlSecKeysMngrPtr Arc::load\_key\_from\_certfile (xmlSecKeysMngrPtr \* keys\_manager, const char \* certfile)

Load public key from a certificate file into key manager

### 4.1.4.45 xmlSecKeysMngrPtr Arc::load\_key\_from\_certstr (xmlSecKeysMngrPtr \* keys\_manager, const std::string & certstr)

Load public key from a certificate string into key manager

### 4.1.4.46 xmlSecKeysMngrPtr Arc::load\_trusted\_cert\_file (xmlSecKeysMngrPtr \* keys\_manager, const char \* cert\_file)

Load trusted certificate from certificate file into key manager

# 4.1.4.47 xmlSecKeysMngrPtr Arc::load\_trusted\_cert\_str (xmlSecKeysMngrPtr \* keys\_manager, const std::string & cert\_str)

Load trusted certificate from cetrtificate string into key manager

# 4.1.4.48 xmlSecKeysMngrPtr Arc::load\_trusted\_certs (xmlSecKeysMngrPtr \* keys\_manager, const char \* cafile, const char \* capath)

Load trusted cetificates from a file or directory into key manager

### 4.1.4.49 XMLNode Arc::get\_node (XMLNode & parent, const char \* name)

Generate a new child XMLNode with specified name

#### 4.1.5 Variable Documentation

#### 4.1.5.1 const Glib::TimeVal Arc::ETERNAL

A time very far in the future.

#### 4.1.5.2 const Glib::TimeVal Arc::HISTORIC

A time very far in the past.

### 4.1.5.3 Logger Arc::CredentialLogger

Logger to be used by all modules of credentials library

### 4.1.5.4 const char\* Arc::plugins\_table\_name

Name of symbol refering to table of plugins.

This C null terminated string specifies name of symbol which shared library should export to give an access to an array of PluginDescriptor elements. The array is terminated by element with all components set to NULL.

### 4.2 ArcCredential Namespace Reference

#### Classes

- struct cert\_verify\_context
- struct PROXYPOLICY\_st
- struct PROXYCERTINFO\_st
- struct ACDIGEST
- struct ACIS
- struct ACFORM
- struct ACACI
- struct ACHOLDER
- struct ACVAL
- struct ACIETFATTR
- struct ACTARGET
- struct ACTARGETS
- struct ACATTR
- struct ACINFO
- struct ACC
- struct ACSEQ
- struct ACCERTS
- struct **ACATTRIBUTE**
- struct ACATTHOLDER
- struct ACFULLATTRIBUTES

### **Typedefs**

- typedef ArcCredential::PROXYPOLICY\_st PROXYPOLICY
- typedef ArcCredential::PROXYCERTINFO\_st PROXYCERTINFO
- typedef ArcCredential::ACDIGEST AC\_DIGEST
- typedef ArcCredential::ACIS AC\_IS
- typedef ArcCredential::ACFORM AC\_FORM
- typedef ArcCredential::ACACI AC\_ACI
- typedef ArcCredential::ACHOLDER AC\_HOLDER
- typedef ArcCredential::ACVAL AC\_VAL
- typedef asn1\_string\_st AC\_IETFATTRVAL
- typedef ArcCredential::ACIETFATTR AC\_IETFATTR
- typedef ArcCredential::ACTARGET AC\_TARGET
- typedef ArcCredential::ACTARGETS AC TARGETS
- typedef ArcCredential::ACATTR AC\_ATTR
- typedef ArcCredential::ACINFO AC\_INFO
- typedef ArcCredential::ACC AC
- typedef ArcCredential::ACSEQ AC\_SEQ
- typedef ArcCredential::ACCERTS AC\_CERTS
- typedef ArcCredential::ACATTRIBUTE AC\_ATTRIBUTE
- typedef ArcCredential::ACATTHOLDER AC\_ATT\_HOLDER
- typedef ArcCredential::ACFULLATTRIBUTES AC\_FULL\_ATTRIBUTES

#### **Enumerations**

• enum certType {

```
CERT_TYPE_EEC, CERT_TYPE_CA, CERT_TYPE_GSI_3_IMPERSONATION_PROXY, CERT_TYPE_GSI_3_INDEPENDENT_PROXY,

CERT_TYPE_GSI_3_LIMITED_PROXY, CERT_TYPE_GSI_3_RESTRICTED_PROXY, CERT_TYPE_GSI_2_PROXY, CERT_TYPE_GSI_2_LIMITED_PROXY,

CERT_TYPE_RFC_IMPERSONATION_PROXY, CERT_TYPE_RFC_INDEPENDENT_PROXY, CERT_TYPE_RFC_LIMITED_PROXY, CERT_TYPE_RFC_RESTRICTED_PROXY,

CERT_TYPE_RFC_ANYLANGUAGE_PROXY }
```

#### **Functions**

- int verify\_cert\_chain (X509 \*cert, STACK\_OF(X509)\*\*certchain, cert\_verify\_context \*vctx)
- int verify\_callback (int ok, X509\_STORE\_CTX \*store\_ctx)
- bool **check\_cert\_type** (X509 \*cert, **certType** &type)
- int check\_issued (X509\_STORE\_CTX \*ctx, X509 \*x, X509 \*issuer)
- PROXYPOLICY \* PROXYPOLICY\_new ()
- void **PROXYPOLICY\_free** (PROXYPOLICY \*proxypolicy)
- PROXYPOLICY \* **PROXYPOLICY\_dup** (PROXYPOLICY \*policy)
- int **PROXYPOLICY\_set\_policy\_language** (PROXYPOLICY \*policy, ASN1\_OBJECT \*policy\_language)
- ASN1\_OBJECT \* PROXYPOLICY\_get\_policy\_language (PROXYPOLICY \*policy)
- int **PROXYPOLICY\_set\_policy** (PROXYPOLICY \*proxypolicy, unsigned char \*policy, int length)
- unsigned char \* **PROXYPOLICY\_get\_policy** (PROXYPOLICY \*policy, int \*length)
- int i2d PROXYPOLICY (PROXYPOLICY \*policy, unsigned char \*\*pp)
- PROXYPOLICY \* d2i\_PROXYPOLICY (PROXYPOLICY \*\*policy, unsigned char \*\*pp, long length)
- X509V3\_EXT\_METHOD \* **PROXYPOLICY\_x509v3\_ext\_meth** ()
- STACK OF (CONF VALUE)\*i2v PROXYPOLICY(struct v3 ext method \*method
- PROXYCERTINFO \* PROXYCERTINFO\_new ()
- void **PROXYCERTINFO\_free** (PROXYCERTINFO \*proxycertinfo)
- int **PROXYCERTINFO\_print\_fp** (FILE \*fp, PROXYCERTINFO \*cert\_info)
- int PROXYCERTINFO\_set\_path\_length (PROXYCERTINFO \*proxycertinfo, long path\_length)
- long **PROXYCERTINFO\_get\_path\_length** (PROXYCERTINFO \*proxycertinfo)
- int **PROXYCERTINFO\_set\_proxypolicy** (PROXYCERTINFO \*proxycertinfo, PROXYPOLICY \*proxypolicy)
- PROXYPOLICY \* PROXYCERTINFO\_get\_proxypolicy (PROXYCERTINFO \*proxycertinfo)
- int i2d\_PROXYCERTINFO (PROXYCERTINFO \*proxycertinfo, unsigned char \*\*pp)
- PROXYCERTINFO \* **d2i\_PROXYCERTINFO** (PROXYCERTINFO \*\*cert\_info, unsigned char \*\*a, long length)
- int PROXYCERTINFO\_set\_version (PROXYCERTINFO \*cert\_info, int version)
- int **i2r\_PROXYCERTINFO** (X509V3\_EXT\_METHOD \*method, PROXYCERTINFO \*ext, BIO \*out, int indent)
- PROXYCERTINFO \* **r2i\_PROXYCERTINFO** (X509V3\_EXT\_METHOD \*method, X509V3\_CTX \*ctx, char \*value)
- X509V3\_EXT\_METHOD \* PROXYCERTINFO\_v3\_x509v3\_ext\_meth ()
- X509V3\_EXT\_METHOD \* PROXYCERTINFO\_v4\_x509v3\_ext\_meth ()
- int **i2d\_AC\_ATTR** (AC\_ATTR \*a, unsigned char \*\*pp)

- AC\_ATTR \* d2i\_AC\_ATTR (AC\_ATTR \*\*a, unsigned char \*\*p, long length)
- AC\_ATTR \* AC\_ATTR\_new ()
- void AC ATTR free (AC ATTR \*a)
- int i2d\_AC\_IETFATTR (AC\_IETFATTR \*a, unsigned char \*\*pp)
- AC IETFATTR \* d2i AC IETFATTR (AC IETFATTR \*\*a, unsigned char \*\*p, long length)
- AC\_IETFATTR \* AC\_IETFATTR\_new ()
- void **AC\_IETFATTR\_free** (AC\_IETFATTR \*a)
- int i2d AC IETFATTRVAL (AC IETFATTRVAL \*a, unsigned char \*\*pp)
- AC\_IETFATTRVAL \* **d2i\_AC\_IETFATTRVAL** (AC\_IETFATTRVAL \*\*a, unsigned char \*\*pp, long length)
- AC\_IETFATTRVAL \* AC\_IETFATTRVAL\_new ()
- void AC IETFATTRVAL free (AC IETFATTRVAL \*a)
- int i2d\_AC\_DIGEST (AC\_DIGEST \*a, unsigned char \*\*pp)
- AC\_DIGEST \* d2i\_AC\_DIGEST (AC\_DIGEST \*\*a, unsigned char \*\*pp, long length)
- AC DIGEST \* AC DIGEST new (void)
- void AC\_DIGEST\_free (AC\_DIGEST \*a)
- int i2d\_AC\_IS (AC\_IS \*a, unsigned char \*\*pp)
- AC\_IS \* d2i\_AC\_IS (AC\_IS \*\*a, unsigned char \*\*pp, long length)
- AC\_IS \* AC\_IS\_new (void)
- void AC\_IS\_free (AC\_IS \*a)
- int i2d\_AC\_FORM (AC\_FORM \*a, unsigned char \*\*pp)
- AC\_FORM \* d2i\_AC\_FORM (AC\_FORM \*\*a, unsigned char \*\*pp, long length)
- AC FORM \* AC FORM new (void)
- void AC\_FORM\_free (AC\_FORM \*a)
- int i2d\_AC\_ACI (AC\_ACI \*a, unsigned char \*\*pp)
- AC\_ACI \* d2i\_AC\_ACI (AC\_ACI \*\*a, unsigned char \*\*pp, long length)
- AC\_ACI \* AC\_ACI\_new (void)
- void AC ACI free (AC ACI \*a)
- int i2d\_AC\_HOLDER (AC\_HOLDER \*a, unsigned char \*\*pp)
- AC\_HOLDER \* d2i\_AC\_HOLDER (AC\_HOLDER \*\*a, unsigned char \*\*pp, long length)
- AC\_HOLDER \* AC\_HOLDER\_new (void)
- void AC\_HOLDER\_free (AC\_HOLDER \*a)
- int i2d\_AC\_VAL (AC\_VAL \*a, unsigned char \*\*pp)
- AC\_VAL \* **d2i\_AC\_VAL** (AC\_VAL \*\*a, unsigned char \*\*pp, long length)
- AC\_VAL \* AC\_VAL\_new (void)
- void **AC\_VAL\_free** (AC\_VAL \*a)
- int i2d\_AC\_INFO (AC\_INFO \*a, unsigned char \*\*pp)
- AC INFO \* d2i AC INFO (AC INFO \*\*a, unsigned char \*\*p, long length)
- AC\_INFO \* AC\_INFO\_new (void)
- void AC\_INFO\_free (AC\_INFO \*a)
- int i2d\_AC (AC \*a, unsigned char \*\*pp)
- AC \* d2i\_AC (AC \*\*a, unsigned char \*\*pp, long length)
- AC \* AC\_new (void)
- void AC free (AC \*a)
- int **i2d\_AC\_TARGETS** (AC\_TARGETS \*a, unsigned char \*\*pp)
- AC\_TARGETS \* d2i\_AC\_TARGETS (AC\_TARGETS \*\*a, unsigned char \*\*pp, long length)
- AC\_TARGETS \* AC\_TARGETS\_new (void)
- void **AC\_TARGETS\_free** (AC\_TARGETS \*a)
- int i2d\_AC\_TARGET (AC\_TARGET \*a, unsigned char \*\*pp)
- AC\_TARGET \* d2i\_AC\_TARGET (AC\_TARGET \*\*a, unsigned char \*\*pp, long length)

- AC\_TARGET \* AC\_TARGET\_new (void)
- void AC\_TARGET\_free (AC\_TARGET \*a)
- int **i2d\_AC\_SEQ** (AC\_SEQ \*a, unsigned char \*\*pp)
- AC\_SEQ \* d2i\_AC\_SEQ (AC\_SEQ \*\*a, unsigned char \*\*pp, long length)
- AC\_SEQ \* AC\_SEQ\_new (void)
- void AC\_SEQ\_free (AC\_SEQ \*a)
- int **i2d\_AC\_CERTS** (AC\_CERTS \*a, unsigned char \*\*pp)
- AC\_CERTS \* **d2i\_AC\_CERTS** (AC\_CERTS \*\*a, unsigned char \*\*pp, long length)
- AC\_CERTS \* AC\_CERTS\_new (void)
- void AC\_CERTS\_free (AC\_CERTS \*a)
- int i2d\_AC\_ATTRIBUTE (AC\_ATTRIBUTE \*, unsigned char \*\*)
- int i2d\_AC\_ATT\_HOLDER (AC\_ATT\_HOLDER \*, unsigned char \*\*)
- int i2d\_AC\_FULL\_ATTRIBUTES (AC\_FULL\_ATTRIBUTES \*, unsigned char \*\*)
- AC\_ATTRIBUTE \* d2i\_AC\_ATTRIBUTE (AC\_ATTRIBUTE \*\*, unsigned char \*\*, long)
- AC ATT HOLDER \* d2i AC ATT HOLDER (AC ATT HOLDER \*\*, unsigned char \*\*, long)
- AC\_FULL\_ATTRIBUTES \* **d2i\_AC\_FULL\_ATTRIBUTES** (AC\_FULL\_ATTRIBUTES \*\*, unsigned char \*\*, long)
- AC\_ATTRIBUTE \* AC\_ATTRIBUTE\_new ()
- $\bullet \ \ AC\_ATT\_HOLDER * AC\_ATT\_HOLDER\_new () \\$
- AC\_FULL\_ATTRIBUTES \* AC\_FULL\_ATTRIBUTES\_new ()
- void **AC\_ATTRIBUTE\_free** (AC\_ATTRIBUTE \*)
- void AC\_ATT\_HOLDER\_free (AC\_ATT\_HOLDER \*)
- void AC\_FULL\_ATTRIBUTES\_free (AC\_FULL\_ATTRIBUTES \*)
- X509V3\_EXT\_METHOD \* **VOMSAttribute\_auth\_x509v3\_ext\_meth** ()
- X509V3\_EXT\_METHOD \* VOMSAttribute\_avail\_x509v3\_ext\_meth ()
- $\bullet \ X509V3\_EXT\_METHOD * \textbf{VOMSAttribute\_targets\_x509v3\_ext\_meth} \ ()$
- $\bullet \ X509V3\_EXT\_METHOD* \textbf{VOMSAttribute\_acseq\_x509v3\_ext\_meth} \ ()$
- $\bullet \ X509V3\_EXT\_METHOD * \textbf{VOMSAttribute\_certseq\_x509v3\_ext\_meth} \ ()$
- X509V3\_EXT\_METHOD \* **VOMSAttribute\_attribs\_x509v3\_ext\_meth** ()

### **Variables**

- PROXYPOLICY \* ext
- PROXYCERTINFO \* ext

### 4.2.1 Detailed Description

The code is derived from globus gsi, voms, and openssl-0.9.8e. The existing code for maintaining proxy certificates in OpenSSL only covers standard proxies and does not cover old Globus proxies, so here the Globus code is introduced.

### **4.2.2** Enumeration Type Documentation

### 4.2.2.1 enum ArcCredential::certType

#### **Enumerator:**

*CERT\_TYPE\_EEC* A end entity certificate *CERT\_TYPE\_CA* A CA certificate

- *CERT\_TYPE\_GSI\_3\_IMPERSONATION\_PROXY* A X.509 Proxy Certificate Profile (pre-RFC) compliant impersonation proxy
- CERT\_TYPE\_GSI\_3\_INDEPENDENT\_PROXY A X.509 Proxy Certificate Profile (pre-RFC)
  compliant independent proxy
- *CERT\_TYPE\_GSI\_3\_LIMITED\_PROXY* A X.509 Proxy Certificate Profile (pre-RFC) compliant limited proxy
- CERT\_TYPE\_GSI\_3\_RESTRICTED\_PROXY A X.509 Proxy Certificate Profile (pre-RFC) compliant restricted proxy
- CERT\_TYPE\_GSI\_2\_PROXY A legacy Globus impersonation proxy
- CERT\_TYPE\_GSI\_2\_LIMITED\_PROXY A legacy Globus limited impersonation proxy
- CERT\_TYPE\_RFC\_IMPERSONATION\_PROXY A X.509 Proxy Certificate Profile RFC compliant impersonation proxy; RFC inheritAll proxy
- CERT\_TYPE\_RFC\_INDEPENDENT\_PROXY A X.509 Proxy Certificate Profile RFC compliant independent proxy; RFC independent proxy
- CERT\_TYPE\_RFC\_LIMITED\_PROXY A X.509 Proxy Certificate Profile RFC compliant limited
  proxy
- CERT\_TYPE\_RFC\_RESTRICTED\_PROXY A X.509 Proxy Certificate Profile RFC compliant restricted proxy
- CERT\_TYPE\_RFC\_ANYLANGUAGE\_PROXY RFC anyLanguage proxy

# **Chapter 5**


# **Hosting Environment (Daemon) Class Documentation**

## 5.1 ArcSec::AlgFactory Class Reference

Interface for algorithm factory class.

#include <AlgFactory.h>

Inheritance diagram for ArcSec::AlgFactory::



### **Public Member Functions**

• virtual CombiningAlg \* createAlg (const std::string &type)=0

### **Protected Attributes**

• AlgMap algmap

### **5.1.1** Detailed Description

Interface for algorithm factory class.

AlgFactory is in charge of creating CombiningAlg according to the algorithm type given as argument of method createAlg. This class can be inherited for implementing a factory class which can create some specific combining algorithm objects.

### **5.1.2** Member Function Documentation

# **5.1.2.1 virtual CombiningAlg\* ArcSec::AlgFactory::createAlg (const std::string & type)** [pure virtual]

creat algorithm object based on the type algorithm type

### **Parameters:**

type The type of combining algorithm

### **Returns:**

The object of CombiningAlg


The documentation for this class was generated from the following file:

• AlgFactory.h

### 5.2 ARCLibError Class Reference

#include <error.h>

Inheritance diagram for ARCLibError::



#### **Public Member Functions**

- ARCLibError (std::string message)
- virtual ~ARCLibError () throw ()
- virtual const char \* what () const throw ()

### **5.2.1** Detailed Description

This is the top exception for ARCLib. Every exeption in ARCLib should inherit from this. The exception inherits from the top C++ exception: std::exception.

### 5.2.2 Constructor & Destructor Documentation

### **5.2.2.1 ARCLibError::ARCLibError (std::string** *message***)** [inline]

Creates a new exception, with the mesage given as argument

### **5.2.2.2 virtual ARCLibError::**~**ARCLibError() throw()** [inline, virtual]

Destructor. Not that much to say.

### **5.2.3** Member Function Documentation

### 5.2.3.1 virtual const char\* ARCLibError::what () const throw () [inline, virtual]

Returns the message given in the constructer.

The documentation for this class was generated from the following file:

· error.h

### 5.3 Arc::ArcLocation Class Reference

Determines ARC installation location.

#include <ArcLocation.h>

### **Static Public Member Functions**

- static void Init (std::string path)
- static const std::string & Get ()
- static std::list< std::string > GetPlugins ()

### **5.3.1** Detailed Description

Determines ARC installation location.

### **5.3.2** Member Function Documentation

### **5.3.2.1 static const std::string& Arc::ArcLocation::Get** () [static]

Returns ARC installation location.

### **5.3.2.2** static std::list<std::string> Arc::ArcLocation::GetPlugins () [static]

Returns ARC plugins directory location.

Main source is value of variable ARC\_PLUGIN\_PATH, otherwise path is derived from installation location.

### **5.3.2.3 static void Arc::ArcLocation::Init (std::string** *path***)** [static]

Initializes location information.

Main source is value of variable ARC\_LOCATION, otherwise path to executable provided in is used. If nothing works then warning message is sent to logger and initial installation prefix is used.

The documentation for this class was generated from the following file:

• ArcLocation.h

### 5.4 ArcSec::Attr Struct Reference

Attr contains a tuple of attribute type and value.

```
#include <Request.h>
```

### **Public Attributes**

- std::string value
- std::string type

### **5.4.1** Detailed Description

Attr contains a tuple of attribute type and value.


The documentation for this struct was generated from the following file:

• Request.h

### 5.5 ArcSec::AttributeFactory Class Reference

#include <AttributeFactory.h>

Inheritance diagram for ArcSec::AttributeFactory::



### **Public Member Functions**

• virtual AttributeValue \* createValue (const Arc::XMLNode &node, const std::string &type)=0

### **Protected Attributes**

• AttrProxyMap apmap

### 5.5.1 Detailed Description

Base attribute factory class

The documentation for this class was generated from the following file:

• AttributeFactory.h

### 5.6 Arc::AttributeIterator Class Reference

An iterator class for accessing multiple values of an attribute.

```
#include <MessageAttributes.h>
```

### **Public Member Functions**

- AttributeIterator ()
- const std::string & operator \* () const
- const std::string \* operator → () const
- const std::string & key (void) const
- const AttributeIterator & operator++ ()
- AttributeIterator operator++ (int)
- bool hasMore () const

#### **Protected Member Functions**

• AttributeIterator (AttrConstIter begin, AttrConstIter end)

### **Protected Attributes**

- AttrConstIter current
- AttrConstIter end\_

### **Friends**

• class MessageAttributes

### **5.6.1** Detailed Description

An iterator class for accessing multiple values of an attribute.

This is an iterator class that is used when accessing multiple values of an attribute. The getAll() method of the MessageAttributes class returns an AttributeIterator object that can be used to access the values of the attribute.

Typical usage is:

```
Arc::MessageAttributes attributes;
...
for (Arc::AttributeIterator iterator=attributes.getAll("Foo:Bar");
    iterator.hasMore(); ++iterator)
std::cout << *iterator << std::endl;</pre>
```

### 5.6.2 Constructor & Destructor Documentation

### **5.6.2.1** Arc::AttributeIterator::AttributeIterator()

Default constructor.

The default constructor. Does nothing since all attributes are instances of well-behaving STL classes.

# 5.6.2.2 Arc::AttributeIterator::AttributeIterator (AttrConstIter begin, AttrConstIter end) [protected]

Protected constructor used by the MessageAttributes class.

This constructor is used to create an iterator for iteration over all values of an attribute. It is not supposed to be visible externally, but is only used from within the getAll() method of MessageAttributes class.

#### **Parameters:**

**begin** A const\_iterator pointing to the first matching key-value pair in the internal multimap of the MessageAttributes class.

end A const\_iterator pointing to the first key-value pair in the internal multimap of the Message-Attributes class where the key is larger than the key searched for.

### **5.6.3** Member Function Documentation

### 5.6.3.1 bool Arc::AttributeIterator::hasMore () const

Predicate method for iteration termination.

This method determines whether there are more values for the iterator to refer to.

#### **Returns:**

Returns true if there are more values, otherwise false.

### 5.6.3.2 const std::string& Arc::AttributeIterator::key (void) const

The key of attribute.

This method returns reference to key of attribute to which iterator refers.

### 5.6.3.3 const std::string& Arc::AttributeIterator::operator \* () const

The dereference operator.

This operator is used to access the current value referred to by the iterator.

#### **Returns:**

A (constant reference to a) string representation of the current value.

### 5.6.3.4 AttributeIterator Arc::AttributeIterator::operator++ (int)

The postfix advance operator.

Advances the iterator to the next value. Works intuitively.

#### **Returns:**

An iterator referring to the value referred to by this iterator before the advance.

#### 5.6.3.5 const AttributeIterator& Arc::AttributeIterator::operator++ ()

The prefix advance operator.

Advances the iterator to the next value. Works intuitively.

#### Returns

A const reference to this iterator.

### 5.6.3.6 const std::string\* Arc::AttributeIterator::operator $\rightarrow$ () const

The arrow operator.

Used to call methods for value objects (strings) conveniently.

#### **5.6.4** Friends And Related Function Documentation

### **5.6.4.1 friend class MessageAttributes** [friend]

The MessageAttributes class is a friend.

The constructor that creates an AttributeIterator that is connected to the internal multimap of the Message-Attributes class should not be exposed to the outside, but it still needs to be accessible from the getAll() method of the MessageAttributes class. Therefore, that class is a friend.

### **5.6.5** Member Data Documentation

#### **5.6.5.1** AttrConstIter Arc::AttributeIterator::current\_ [protected]

A const\_iterator pointing to the current key-value pair.

This iterator is the internal representation of the current value. It points to the corresponding key-value pair in the internal multimap of the MessageAttributes class.

### **5.6.5.2** AttrConstIter Arc::AttributeIterator::end\_ [protected]

A const\_iterator pointing beyond the last key-value pair.

A const\_iterator pointing to the first key-value pair in the internal multimap of the MessageAttributes class where the key is larger than the key searched for.

The documentation for this class was generated from the following file:

· MessageAttributes.h

### 5.7 ArcSec::AttributeProxy Class Reference

Interface for creating the AttributeValue object, it will be used by AttributeFactory.

#include <AttributeProxy.h>

### **Public Member Functions**

• virtual AttributeValue \* getAttribute (const Arc::XMLNode &node)=0

### **5.7.1 Detailed Description**

Interface for creating the AttributeValue object, it will be used by AttributeFactory.

The AttributeProxy object will be insert into AttributeFactoty; and the getAttribute(node) method will be called inside AttributeFacroty.createvalue(node), in order to create a specific AttributeValue

### **5.7.2** Member Function Documentation

**5.7.2.1 virtual AttributeValue\* ArcSec::AttributeProxy::getAttribute (const Arc::XMLNode & node)** [pure virtual]

Create a AttributeValue object according to the information inside the XMLNode as parameter.

The documentation for this class was generated from the following file:


• AttributeProxy.h

### 5.8 ArcSec::AttributeValue Class Reference

Interface for containing different type of <Attribute> node for both policy and request.

#include <AttributeValue.h>

Inheritance diagram for ArcSec::AttributeValue::



### **Public Member Functions**

- virtual bool equal (AttributeValue \*value)=0
- virtual std::string encode ()=0
- virtual std::string getType ()=0
- virtual std::string getId ()=0

### 5.8.1 Detailed Description

Interface for containing different type of <Attribute> node for both policy and request.

<a href="<"><Attribute</a> contains different "Type" definition; Each type of <a href="Attribute">Attribute</a> needs different approach to compare the value. Any specific class which is for processing specific "Type" should inherit this class. The "Type" supported so far is: StringAttribute, DateAttribute, TimeAttribute, DurationAttribute, Period-Attribute, AnyURIAttribute, X500NameAttribute</a>

### 5.8.2 Member Function Documentation

### **5.8.2.1 virtual std::string ArcSec::AttributeValue::encode ()** [pure virtual]

encode the value in a string format

Implemented in ArcSec::DateTimeAttribute, ArcSec::TimeAttribute, ArcSec::DurationAttribute, and ArcSec::PeriodAttribute.

### **5.8.2.2 virtual bool ArcSec::AttributeValue::equal (AttributeValue** \* value) [pure virtual]

Evluate whether "this" equale to the parameter value

Implemented in ArcSec::DateTimeAttribute, ArcSec::TimeAttribute, ArcSec::DurationAttribute, and ArcSec::PeriodAttribute.

### **5.8.2.3 virtual std::string ArcSec::AttributeValue::getId ()** [pure virtual]

Get the identifier of the <Attribute>

Implemented in ArcSec::DateTimeAttribute, ArcSec::TimeAttribute, ArcSec::DurationAttribute, and ArcSec::PeriodAttribute.

### **5.8.2.4 virtual std::string ArcSec::AttributeValue::getType** () [pure virtual]

Get the type of the <Attribute>

Implemented in ArcSec::DateTimeAttribute, ArcSec::TimeAttribute, ArcSec::DurationAttribute, and ArcSec::PeriodAttribute.

The documentation for this class was generated from the following file:

• AttributeValue.h

### 5.9 ArcSec::Attrs Class Reference

Attrs is a container for one or more Attr.

```
#include <Request.h>
```

### **Public Member Functions**

- void addItem (Attr attr)
- int **size** ()
- Attr & getItem (int n)
- Attr & operator[] (int n)

### **5.9.1 Detailed Description**

Attrs is a container for one or more Attr.

Attrs includes includes methonds for inserting, getting items, and counting size as well

The documentation for this class was generated from the following file:

• Request.h

### 5.10 ArcSec::AuthzRequestSection Struct Reference

#include <PDP.h>

### **Public Attributes**

- std::string value
- std::string id
- std::string type
- std::string issuer

### **5.10.1** Detailed Description

These structure are based on the request schema for PDP, so far it can apply to the ArcPDP's request schema, see src/hed/pdc/Request.xsd and src/hed/pdc/Request.xml. It could also apply to the XACMLPDP's request schema, since the difference is minor.

Another approach is, the service composes/marshalls the xml structure directly, then the service should use difference code to compose for ArcPDP's request schema and XACMLPDP's schema, which is not so good.

The documentation for this struct was generated from the following file:

• PDP.h

### **5.11** Arc::AutoPointer< T > Class Template Reference

Wrapper for pointer with automatic destruction.

```
#include <Utils.h>
```

### **Public Member Functions**

- AutoPointer (void)
- AutoPointer (T \*o)
- ~AutoPointer (void)
- T & operator \* (void) const
- $T * operator \rightarrow (void) const$
- operator bool (void) const
- bool operator! (void) const
- operator T \* (void) const

### **5.11.1** Detailed Description

### template<typename T> class Arc::AutoPointer< T>

Wrapper for pointer with automatic destruction.

If ordinary pointer is wrapped in instance of this class it will be automatically destroyed when instance is destroyed. This is useful for maintaing pointers in scope of one function. Only pointers returned by new() are supported.

### **5.11.2** Constructor & Destructor Documentation

### 5.11.2.1 template<typename T> Arc::AutoPointer< T>::AutoPointer (void) [inline]

NULL pointer constructor.

### 5.11.2.2 template<typename T> Arc::AutoPointer< T>::AutoPointer (T \* 0) [inline]

Constructor which wraps pointer.

### 5.11.2.3 template<typename T> Arc::AutoPointer< T>::~AutoPointer (void) [inline]

Destructor destroys wrapped object using delete().

### **5.11.3** Member Function Documentation

### 5.11.3.1 template<typename T> T& Arc::AutoPointer< T>::operator \* (void) const [inline]

For refering wrapped object.

5.11.3.2 template<typename T> Arc::AutoPointer< T>::operator bool (void) const [inline] Returns false if pointer is NULL and true otherwise.

 $\textbf{5.11.3.3} \quad \textbf{template} < \textbf{typename } T > \textbf{Arc::AutoPointer} < T > \textbf{::operator } T * \textbf{(void) const} \quad \texttt{[inline]}$  Cast to original pointer.

**5.11.3.4 template**<**typename T**> **bool Arc::AutoPointer**< **T**>**::operator!** (**void**) **const** [inline] Returns true if pointer is NULL and false otherwise.

 $5.11.3.5 \quad template < typename \ T > T* \ Arc:: AutoPointer < T > :: operator \rightarrow (void) \ const \quad \texttt{[inline]}$  For referring wrapped object.

The documentation for this class was generated from the following file:

• Utils.h

### 5.12 Arc::BaseConfig Class Reference

#include <ArcConfig.h>

### **Public Member Functions**

- void AddPluginsPath (const std::string &path)
- void AddPrivateKey (const std::string &path)
- void AddCertificate (const std::string &path)
- void AddProxy (const std::string &path)
- void AddCAFile (const std::string &path)
- void AddCADir (const std::string &path)
- void AddWSSType (const Arc::WSSType &type)
- void AddWSSInfo (const Arc::WSSInfo &info)
- void AddOverlay (XMLNode cfg)
- void GetOverlay (std::string fname)
- virtual XMLNode MakeConfig (XMLNode cfg) const

### **Public Attributes**

- std::string key
- std::string cert
- std::string proxy
- std::string cafile
- std::string cadir
- WSSType wsstype
- WSSInfo wssinfo
- XMLNode overlay

### **Protected Attributes**

• std::list< std::string > plugin\_paths

### 5.12.1 Detailed Description

Configuration for client interface. It contains information which can't be expressed in class constructor arguments. Most probably common things like software installation location, identity of user, etc.

### **5.12.2** Member Function Documentation

### 5.12.2.1 void Arc::BaseConfig::AddCADir (const std::string & path)

Add CA directory

### 5.12.2.2 void Arc::BaseConfig::AddCAFile (const std::string & path)

Add CA file

5.12.2.3 void Arc::BaseConfig::AddCertificate (const std::string & path)

Add certificate

5.12.2.4 void Arc::BaseConfig::AddOverlay (XMLNode cfg)

Add configuration overlay

5.12.2.5 void Arc::BaseConfig::AddPluginsPath (const std::string & path)

Adds non-standard location of plugins

5.12.2.6 void Arc::BaseConfig::AddPrivateKey (const std::string & path)

Add private key

5.12.2.7 void Arc::BaseConfig::AddProxy (const std::string & path)

Add credentials proxy

5.12.2.8 void Arc::BaseConfig::AddWSSInfo (const Arc::WSSInfo & info)

Add WSS information

5.12.2.9 void Arc::BaseConfig::AddWSSType (const Arc::WSSType & type)

Add WSS type

5.12.2.10 void Arc::BaseConfig::GetOverlay (std::string fname)

Read overlay from file

**5.12.2.11 virtual XMLNode Arc::BaseConfig::MakeConfig (XMLNode** *cfg***) const** [virtual]

Adds configuration part corresponding to stored information into common configuration tree supplied in 'cfg' argument.

The documentation for this class was generated from the following file:

· ArcConfig.h

### **5.13** Arc::CacheParameters Struct Reference

#include <FileCache.h>

### **Public Attributes**

- std::string cache\_path
- std::string cache\_link\_path

### **5.13.1** Detailed Description

Contains data on the parameters of a cache.

The documentation for this struct was generated from the following file:

· FileCache.h

### 5.14 Arc::ChainContext Class Reference

Interface to chain specific functionality.

#include <MCCLoader.h>

### **Public Member Functions**

• operator PluginsFactory \* ()

#### **Friends**

· class MCCLoader

### 5.14.1 Detailed Description

Interface to chain specific functionality.

Object of this class is associated with every MCCLoader object. It is accessible for MCC and Service components and provides an interface to manipulate chains stored in Loader. This makes it possible to modify chains dynamically - like deploying new services on demand.

### **5.14.2** Member Function Documentation

### **5.14.2.1** Arc::ChainContext::operator PluginsFactory \* () [inline]

Returns associated PluginsFactory object

The documentation for this class was generated from the following file:


• MCCLoader.h

### 5.15 Arc::CheckSum Class Reference

Defines interface for variuos checksum manipulations.

#include <CheckSum.h>

Inheritance diagram for Arc::CheckSum::



### **Public Member Functions**

- virtual void **start** (void)=0
- virtual void **add** (void \*buf, unsigned long long int len)=0
- virtual void **end** (void)=0
- virtual void **result** (unsigned char \*&res, unsigned int &len) const =0
- virtual int **print** (char \*buf, int len) const
- virtual void **scan** (const char \*buf)=0
- virtual operator bool (void) const
- virtual bool operator! (void) const

### **5.15.1** Detailed Description

Defines interface for variuos checksum manipulations.

This class is used during data transfers through DataBuffer class

The documentation for this class was generated from the following file:


• CheckSum.h

### 5.16 Arc::CheckSumAny Class Reference

Wraper for CheckSum class.

#include <CheckSum.h>

Inheritance diagram for Arc::CheckSumAny::



### **Public Types**

- none
- unknown
- undefined
- cksum
- md5
- enum type {none, unknown, undefined, cksum,md5 }

### **Public Member Functions**

- CheckSumAny (CheckSum \*c=NULL)
- CheckSumAny (type type)
- CheckSumAny (const char \*type)
- virtual void start (void)
- virtual void add (void \*buf, unsigned long long int len)
- virtual void end (void)
- virtual void **result** (unsigned char \*&res, unsigned int &len) const
- virtual int **print** (char \*buf, int len) const
- virtual void scan (const char \*buf)
- virtual operator bool (void) const
- virtual bool operator! (void) const
- bool active (void)
- type **Type** (void)
- void **operator=** (const char \*type)
- bool **operator==** (const char \*s)
- bool **operator==** (const CheckSumAny &ck)

### **Static Public Member Functions**

• static type **Type** (const char \*crc)

### **5.16.1** Detailed Description

Wraper for CheckSum class.

To be used for manipulation of any supported checksum type in a transparent way.

The documentation for this class was generated from the following file:


· CheckSum.h

### 5.17 Arc::CIStringValue Class Reference

This class implements case insensitive strings as security attributes.

#include <CIStringValue.h>

Inheritance diagram for Arc::CIStringValue::



### **Public Member Functions**

- CIStringValue ()
- CIStringValue (const char \*ss)
- CIStringValue (const std::string &ss)
- virtual operator bool ()

### **Protected Member Functions**

• virtual bool equal (SecAttrValue &b)

### **Protected Attributes**

• std::string s

### 5.17.1 Detailed Description

This class implements case insensitive strings as security attributes.

This is an example of how to inherit SecAttrValue. The class is meant to implement security attributes that are case insensitive strings.

### 5.17.2 Constructor & Destructor Documentation

### **5.17.2.1** Arc::CIStringValue::CIStringValue()

Default constructor

### **5.17.2.2** Arc::CIStringValue::CIStringValue (const char \* ss)

This is a constructor that takes a string litteral.

### 5.17.2.3 Arc::CIStringValue::CIStringValue (const std::string & ss)

This is a constructor that takes a string object.

### **5.17.3** Member Function Documentation

### **5.17.3.1 virtual bool Arc::CIStringValue::equal (SecAttrValue & b)** [protected, virtual]

This function returns true if two strings are the same apart from letter case Reimplemented from Arc::SecAttrValue.

### **5.17.3.2 virtual Arc::CIStringValue::operator bool** () [virtual]

This function returns false if the string is empty or uninitialized Reimplemented from Arc::SecAttrValue.

The documentation for this class was generated from the following file:

• CIStringValue.h

### 5.18 Arc::ClientSOAP Class Reference

#include <ClientInterface.h>

### **Public Member Functions**

- ClientSOAP ()
- ClientSOAP (const BaseConfig &cfg, const URL &url)
- MCC\_Status process (PayloadSOAP \*request, PayloadSOAP \*\*response)
- MCC\_Status process (const std::string &action, PayloadSOAP \*request, PayloadSOAP \*response)
- MCC \* GetEntry ()
- virtual void Load ()

#### **Protected Attributes**

• MCC \* soap\_entry

### 5.18.1 Detailed Description

Class with easy interface for sending/receiving SOAP messages over HTTP(S/G). It takes care of configuring MCC chain and making an entry point.

### 5.18.2 Constructor & Destructor Documentation

### **5.18.2.1** Arc::ClientSOAP::ClientSOAP() [inline]

Constructor creates MCC chain and connects to server.

### **5.18.3** Member Function Documentation

5.18.3.1 MCC\_Status Arc::ClientSOAP::process (const std::string & action, PayloadSOAP \* request, PayloadSOAP \*\* response)

Send SOAP request with specified SOAP action and receive response.

# 5.18.3.2 MCC\_Status Arc::ClientSOAP::process (PayloadSOAP \* request, PayloadSOAP \*\* response)

Send SOAP request and receive response.

The documentation for this class was generated from the following file:


• ClientInterface.h

### 5.19 ArcSec::CombiningAlg Class Reference

Interface for combining algrithm.

#include <CombiningAlg.h>

Inheritance diagram for ArcSec::CombiningAlg::



### **Public Member Functions**

- virtual Result combine (EvaluationCtx \*ctx, std::list< Policy \* > policies)=0
- virtual const std::string & getalgId (void) const =0

### 5.19.1 Detailed Description

Interface for combining algrithm.

This class is used to implement a specific combining algorithm for combining policies.

### **5.19.2** Member Function Documentation

# **5.19.2.1 virtual Result ArcSec::CombiningAlg::combine (EvaluationCtx** \* *ctx*, **std::list**< **Policy** \* > *policies*) [pure virtual]

Evaluate request against policy, and if there are more than one policies, combine the evaluation results according to the combing algorithm implemented inside in the method combine(ctx, policies) itself.

### **Parameters:**

ctx The information about request is included

*policies* The "match" and "eval" method inside each policy will be called, and then those results from each policy will be combined according to the combining algorithm inside CombingAlg class.

Implemented in ArcSec::DenyOverridesCombiningAlg, and ArcSec::PermitOverridesCombiningAlg.

# **5.19.2.2 virtual const std::string& ArcSec::CombiningAlg::getalgId (void) const** [pure virtual]

Get the identifier of the combining algorithm class

### **Returns:**

The identity of the algorithm

Implemented in ArcSec::DenyOverridesCombiningAlg, and ArcSec::PermitOverridesCombiningAlg.

The documentation for this class was generated from the following file:

| Hosting Environment (Daemon) Class Documentation |  |
|--|--|
|  |  |
|  |  |
|  |  |
|  |  |
|  |  |
|  |  |
|  |  |
|  |  |
|  |  |

**62** 


• CombiningAlg.h

### 5.20 Arc::Config Class Reference

Configuration element - represents (sub)tree of ARC configuration.

#include <ArcConfig.h>

Inheritance diagram for Arc::Config::



### **Public Member Functions**

- Config ()
- Config (const NS &ns)
- Config (const char \*filename)
- Config (const std::string &xml\_str)
- Config (Arc::XMLNode xml)
- Config (Arc::XMLNode xml, const std::string &filename)
- Config (long cfg\_ptr\_addr)
- Config (const Config &cfg)
- void print (void)
- void parse (const char \*filename)
- const std::string & getFileName (void)
- void setFileName (const std::string &filename)
- void save (const char \*filename)

### 5.20.1 Detailed Description

Configuration element - represents (sub)tree of ARC configuration.

This class is intended to be used to pass configuration details to various parts of HED and external modules. Currently it's just a wrapper over XML tree. But than may change in a future, although interface should be preserved. Currently it is capable of loading XML configuration document from file. In future it will be capable of loading more user-readable format and process it into tree-like structure convenient for machine processing (XML-like). So far there are no schema and/or namespaces assigned.

### **5.20.2** Constructor & Destructor Documentation

**5.20.2.1** Arc::Config::Config() [inline]

Dummy constructor - produces invalid structure

**5.20.2.2** Arc::Config::Config (const NS & ns) [inline]

Creates empty XML tree

### **5.20.2.3** Arc::Config::Config (const char \* *filename*)

Loads configuration document from file 'filename'

#### **5.20.2.4** Arc::Config::Config (const std::string & xml\_str) [inline]

Parse configuration document from memory

### **5.20.2.5** Arc::Config::Config (Arc::XMLNode xml) [inline]

Acquire existing XML (sub)tree. Content is not copied. Make sure XML tree is not destroyed while in use by this object.

### 5.20.2.6 Arc::Config::Config (long cfg\_ptr\_addr)

Copy constructor used by language bindings

### 5.20.2.7 Arc::Config::Config (const Config & cfg)

Copy constructor used by language bindings

### **5.20.3** Member Function Documentation

### 5.20.3.1 const std::string& Arc::Config::getFileName (void) [inline]

Gives back file name of config file or empty string if it was generared from the XMLNode subtree

### 5.20.3.2 void Arc::Config::parse (const char \* filename)

Parse configuration document from file 'filename'

### 5.20.3.3 void Arc::Config::print (void)

Print structure of document. For debuging purposes. Printed content is not an XML document.

### **5.20.3.4** void Arc::Config::save (const char \* filename)

Save to file

### 5.20.3.5 void Arc::Config::setFileName (const std::string & filename) [inline]

Set the file name of config file

The documentation for this class was generated from the following file:

· ArcConfig.h

# **5.21** Arc::CountedPointer< T > Class Template Reference

Wrapper for pointer with automatic destruction and mutiple references.

#include <Utils.h>

## **Public Member Functions**

- CountedPointer (T \*p)
- CountedPointer (CountedPointer< T > &p)
- CountedPointer & operator= (T \*p)
- CountedPointer & operator= (CountedPointer &p)
- T & operator \* (void) const
- $T * operator \rightarrow (void) const$
- operator bool (void) const
- bool operator! (void) const
- operator T \* (void) const

#### Classes

· class Base

## **5.21.1 Detailed Description**

template<typename T> class Arc::CountedPointer< T>

Wrapper for pointer with automatic destruction and mutiple references.

If ordinary pointer is wrapped in instance of this class it will be automatically destroyed when all instances refering to it are destroyed. This is useful for maintaing pointers refered from multiple structures with automatic destruction of original object when last reference is destroyed. It is similar to Java approach with a difference that descruction time is strictly defined. Only pointers returned by new() are supported. This class is not thread-safe

## **5.21.2** Member Function Documentation

**5.21.2.1** template<typename T> T& Arc::CountedPointer< T>::operator \* (void) const [inline]

For refering wrapped object.

**5.21.2.2** template<typename T> Arc::CountedPointer< T>::operator bool (void) const [inline]

Returns false if pointer is NULL and true otherwise.

5.21.2.3 template<typename T> Arc::CountedPointer< T>::operator T\* (void) const [inline]

Cast to original pointer.

 $\textbf{5.21.2.4} \quad \textbf{template} \small < \textbf{typename T} > \textbf{bool Arc::CountedPointer} < \textbf{T} > :: \textbf{operator! (void) const} \\ [\verb|inline||]$ 

Returns true if pointer is NULL and false otherwise.

 $\textbf{5.21.2.5} \quad \textbf{template} < \textbf{typename} \ T > T* \ \textbf{Arc::CountedPointer} < T > \textbf{::operator} \rightarrow \textbf{(void)} \ \textbf{const} \\ \texttt{[inline]}$ 

For refering wrapped object.

The documentation for this class was generated from the following file:


• Utils.h

## 5.22 Arc::Counter Class Reference

A class defining a common interface for counters.

#include <Counter.h>

Inheritance diagram for Arc::Counter::



## **Public Member Functions**

- virtual ~Counter ()
- virtual int getLimit ()=0
- virtual int setLimit (int newLimit)=0
- virtual int changeLimit (int amount)=0
- virtual int getExcess ()=0
- virtual int setExcess (int newExcess)=0
- virtual int changeExcess (int amount)=0
- virtual int getValue ()=0
- virtual CounterTicket reserve (int amount=1, Glib::TimeVal duration=ETERNAL, bool prioritized=false, Glib::TimeVal timeOut=ETERNAL)=0

## **Protected Types**

• typedef unsigned long long int IDType

#### **Protected Member Functions**

- Counter ()
- virtual void cancel (IDType reservationID)=0
- virtual void extend (IDType &reservationID, Glib::TimeVal &expiryTime, Glib::TimeVal duration=ETERNAL)=0
- Glib::TimeVal getCurrentTime ()
- Glib::TimeVal getExpiryTime (Glib::TimeVal duration)
- CounterTicket getCounterTicket (Counter::IDType reservationID, Glib::TimeVal expiryTime, Counter \*counter)
- ExpirationReminder getExpirationReminder (Glib::TimeVal expTime, Counter::IDType resID)

## **Friends**

- class CounterTicket
- class ExpirationReminder

## **5.22.1** Detailed Description

A class defining a common interface for counters.

This class defines a common interface for counters as well as some common functionality.

The purpose of a counter is to provide housekeeping some resource such as e.g. disk space, memory or network bandwidth. The counter itself will not be aware of what kind of resource it limits the use of. Neither will it be aware of what unit is being used to measure that resource. Counters are thus very similar to semaphores. Furthermore, counters are designed to handle concurrent operations from multiple threads/processes in a consistent manner.

Every counter has a limit, an excess limit and a value. The limit is a number that specify how many units are available for reservation. The value is the number of units that are currently available for reservation, i.e. has not allready been reserved. The excess limit specify how many extra units can be reserved for high priority needs even if there are no normal units available for reservation. The excess limit is similar to the credit limit of e.g. a VISA card.

The users of the resource must thus first call the counter in order to make a reservation of an appropriate amount of the resource, then allocate and use the resource and finally call the counter again to cancel the reservation.

Typical usage is:

```
// Declare a counter. Replace XYZ by some appropriate kind of
// counter and provide required parameters. Unit is MB.
Arc::XYZCounter memory(...);
...
// Make a reservation of memory for 2000000 doubles.
Arc::CounterTicket tick = memory.reserve(2*sizeof(double));
// Use the memory.
double* A=new double[2000000];
doSomething(A);
delete[] A;
// Cancel the reservation.
tick.cancel();
```

There are also alternative ways to make reservations, including self-expiring reservations, prioritized reservations and reservations that fail if they cannot be made fast enough.

For self expiring reservations, a duration is provided in the reserve call:

```
tick = memory.reserve(2*sizeof(double), Glib::TimeVal(1,0));
```

A self-expiring reservation can be cancelled explicitly before it expires, but if it is not cancelled it will expire automatically when the duration has passed. The default value for the duration is Arc::ETERNAL, which means that the reservation will not be cancelled automatically.

Prioritized reservations may use the excess limit and succeed immediately even if there are no normal units available for reservation. The value of the counter will in this case become negative. A prioritized reservation looks like this:

```
tick = memory.reserve(2*sizeof(double), Glib::TimeVal(1,0), true);
```

Finally, a time out option can be provided for a reservation. If some task should be performed within two seconds or not at all, the reservation can look like this:

## **5.22.2** Member Typedef Documentation

#### **5.22.2.1** typedef unsigned long long int Arc::Counter::IDType [protected]

A typedef of identification numbers for reservation.

This is a type that is used as identification numbers (keys) for referencing of reservations. It is used internally in counters for book keeping of reservations as well as in the CounterTicket class in order to be able to cancel and extend reservations.

## 5.22.3 Constructor & Destructor Documentation

## **5.22.3.1** Arc::Counter::Counter() [protected]

Default constructor.

This is the default constructor. Since Counter is an abstract class, it should only be used by subclasses. Therefore it is protected. Furthermore, since the Counter class has no attributes, nothing needs to be initialized and thus this constructor is empty.

## **5.22.3.2 virtual Arc::Counter::**~Counter() [virtual]

The destructor.

This is the destructor of the Counter class. Since the Counter class has no attributes, nothing needs to be cleaned up and thus the destructor is empty.

## **5.22.4** Member Function Documentation

#### **5.22.4.1 virtual void Arc::Counter::cancel (IDType** *reservationID*) [protected, pure virtual]

Cancellation of a reservation.

This method cancels a reservation. It is called by the CounterTicket that corresponds to the reservation.

## Parameters:

reservationID The identity number (key) of the reservation to cancel.

## **5.22.4.2 virtual int Arc::Counter::changeExcess (int amount)** [pure virtual]

Changes the excess limit of the counter.

Changes the excess limit of the counter by adding a certain amount to the current excess limit.

#### **Parameters:**

amount The amount by which to change the excess limit.

#### **Returns:**

The new excess limit.

Implemented in Arc::IntraProcessCounter.

## **5.22.4.3 virtual int Arc::Counter::changeLimit (int** *amount***)** [pure virtual]

Changes the limit of the counter.

Changes the limit of the counter by adding a certain amount to the current limit.

#### **Parameters:**

amount The amount by which to change the limit.

#### **Returns:**

The new limit.

Implemented in Arc::IntraProcessCounter.

# 5.22.4.4 virtual void Arc::Counter::extend (IDType & reservationID, Glib::TimeVal & expiryTime, Glib::TimeVal duration = ETERNAL) [protected, pure virtual]

Extension of a reservation.

This method extends a reservation. It is called by the CounterTicket that corresponds to the reservation.

#### **Parameters:**

**reservationID** Used for input as well as output. Contains the identification number of the original reservation on entry and the new identification number of the extended reservation on exit.

*expiryTime* Used for input as well as output. Contains the expiry time of the original reservation on entry and the new expiry time of the extended reservation on exit.

*duration* The time by which to extend the reservation. The new expiration time is computed based on the current time, NOT the previous expiration time.

# 5.22.4.5 CounterTicket Arc::Counter::getCounterTicket (Counter::IDType reservationID, Glib::TimeVal expiryTime, Counter \* counter) [protected]

A "relay method" for a constructor of the CounterTicket class.

This method acts as a relay for one of the constructors of the CounterTicket class. That constructor is private, but needs to be accessible from the subclasses of Counter (bot not from anywhere else). In order not to have to declare every possible subclass of Counter as a friend of CounterTicket, only the base class Counter is a friend and its subclasses access the constructor through this method. (If C++ had supported "package access", as Java does, this trick would not have been necessary.)

#### **Parameters:**

reservationID The identity number of the reservation corresponding to the CounterTicket.
expiryTime the expiry time of the reservation corresponding to the CounterTicket.
counter The Counter from which the reservation has been made.

#### Returns:

The counter ticket that has been created.

#### **5.22.4.6 Glib::TimeVal Arc::Counter::getCurrentTime()** [protected]

Get the current time.

Returns the current time. An "adapter method" for the assign\_current\_time() method in the Glib::TimeVal class. return The current time.

#### **5.22.4.7 virtual int Arc::Counter::getExcess ()** [pure virtual]

Returns the excess limit of the counter.

Returns the excess limit of the counter, i.e. by how much the usual limit may be exceeded by prioritized reservations.

#### **Returns:**

The excess limit.

Implemented in Arc::IntraProcessCounter.

# 5.22.4.8 ExpirationReminder Arc::Counter::getExpirationReminder (Glib::TimeVal expTime, Counter::IDType resID) [protected]

A "relay method" for the constructor of ExpirationReminder.

This method acts as a relay for one of the constructors of the ExpirationReminder class. That constructor is private, but needs to be accessible from the subclasses of Counter (bot not from anywhere else). In order not to have to declare every possible subclass of Counter as a friend of ExpirationReminder, only the base class Counter is a friend and its subclasses access the constructor through this method. (If C++ had supported "package access", as Java does, this trick would not have been necessary.)

#### **Parameters:**

 $\emph{expTime}$  the expiry time of the reservation corresponding to the ExpirationReminder.

resID The identity number of the reservation corresponding to the ExpirationReminder.

#### **Returns:**

The ExpirationReminder that has been created.

## **5.22.4.9 Glib::TimeVal Arc::Counter::getExpiryTime (Glib::TimeVal** *duration*) [protected]

Computes an expiry time.

This method computes an expiry time by adding a duration to the current time.

#### **Parameters:**

duration The duration.

#### **Returns:**

The expiry time.

## **5.22.4.10 virtual int Arc::Counter::getLimit** () [pure virtual]

Returns the current limit of the counter.

This method returns the current limit of the counter, i.e. how many units can be reserved simultaneously by different threads without claiming high priority.

#### **Returns:**

The current limit of the counter.

Implemented in Arc::IntraProcessCounter.

## **5.22.4.11 virtual int Arc::Counter::getValue** () [pure virtual]

Returns the current value of the counter.

Returns the current value of the counter, i.e. the number of unreserved units. Initially, the value is equal to the limit of the counter. When a reservation is made, the the value is decreased. Normally, the value should never be negative, but this may happen if there are prioritized reservations. It can also happen if the limit is decreased after some reservations have been made, since reservations are never revoked.

#### **Returns:**

The current value of the counter.

Implemented in Arc::IntraProcessCounter.

```
5.22.4.12 virtual CounterTicket Arc::Counter::reserve (int amount = 1, Glib::TimeVal duration = ETERNAL, bool prioritized = false, Glib::TimeVal timeOut = ETERNAL) [pure virtual]
```

Makes a reservation from the counter.

This method makes a reservation from the counter. If the current value of the counter is too low to allow for the reservation, the method blocks until the reservation is possible or times out.

#### **Parameters:**

amount The amount to reserve, default value is 1.

duration The duration of a self expiring reservation, default is that it lasts forever.

prioritized Whether this reservation is prioritized and thus allowed to use the excess limit.

*timeOut* The maximum time to block if the value of the counter is too low, default is to allow "eternal" blocking.

## **Returns:**

A CounterTicket that can be queried about the status of the reservation as well as for cancellations and extensions.

Implemented in Arc::IntraProcessCounter.

## **5.22.4.13 virtual int Arc::Counter::setExcess (int** *newExcess***)** [pure virtual]

Sets the excess limit of the counter.

This method sets a new excess limit for the counter.

## **Parameters:**

newExcess The new excess limit, an absolute number.

## **Returns:**

The new excess limit.

Implemented in Arc::IntraProcessCounter.

## **5.22.4.14 virtual int Arc::Counter::setLimit (int** *newLimit***)** [pure virtual]

Sets the limit of the counter.

This method sets a new limit for the counter.

## **Parameters:**

newLimit The new limit, an absolute number.

## **Returns:**

The new limit.

Implemented in Arc::IntraProcessCounter.

## 5.22.5 Friends And Related Function Documentation

## **5.22.5.1 friend class CounterTicket** [friend]

The CounterTicket class needs to be a friend.

## **5.22.5.2 friend class ExpirationReminder** [friend]

The ExpirationReminder class needs to be a friend.

The documentation for this class was generated from the following file:

• Counter.h

# 5.23 Arc::CounterTicket Class Reference

A class for "tickets" that correspond to counter reservations.

```
#include <Counter.h>
```

## **Public Member Functions**

- CounterTicket ()
- bool is Valid ()
- void extend (Glib::TimeVal duration)
- void cancel ()

## **Friends**

class Counter

## **5.23.1 Detailed Description**

A class for "tickets" that correspond to counter reservations.

This is a class for reservation tickets. When a reservation is made from a Counter, a ReservationTicket is returned. This ticket can then be queried about the validity of a reservation. It can also be used for cancelation and extension of reservations.

Typical usage is:

```
// Declare a counter. Replace XYZ by some appropriate kind of
// counter and provide required parameters. Unit is MB.
Arc::XYZCounter memory(...);
...
// Make a reservation of memory for 2000000 doubles.
Arc::CounterTicket tick = memory.reserve(2*sizeof(double));
// Use the memory.
double* A=new double[2000000];
doSomething(A);
delete[] A;
// Cancel the reservation.
tick.cancel();
```

## 5.23.2 Constructor & Destructor Documentation

#### 5.23.2.1 Arc::CounterTicket::CounterTicket()

The default constructor.

This is the default constructor. It creates a CounterTicket that is not valid. The ticket object that is created can later be assigned a ticket that is returned by the reserve() method of a Counter.

## **5.23.3** Member Function Documentation

#### 5.23.3.1 void Arc::CounterTicket::cancel()

Cancels a resrvation.

This method is called to cancel a reservation. It may be called also for self-expiring reservations, which will then be cancelled before they were originally planned to expire.

## 5.23.3.2 void Arc::CounterTicket::extend (Glib::TimeVal duration)

Extends a reservation.

Extends a self-expiring reservation. In order to succeed the extension should be made before the previous reservation expires.

#### **Parameters:**

*duration* The time by which to extend the reservation. The new expiration time is computed based on the current time, NOT the previous expiration time.

## 5.23.3.3 bool Arc::CounterTicket::isValid ()

Returns the validity of a CounterTicket.

This method checks whether a CounterTicket is valid. The ticket was probably returned earlier by the reserve() method of a Counter but the corresponding reservation may have expired.

#### **Returns:**

The validity of the ticket.

## **5.23.4** Friends And Related Function Documentation

#### **5.23.4.1 friend class Counter** [friend]

The Counter class needs to be a friend.

The documentation for this class was generated from the following file:


• Counter.h

# 5.24 Arc::CRC32Sum Class Reference

Implementation of CRC32 checksum.

#include <CheckSum.h>

Inheritance diagram for Arc::CRC32Sum::



## **Public Member Functions**

- virtual void start (void)
- virtual void add (void \*buf, unsigned long long int len)
- virtual void end (void)
- virtual void result (unsigned char \*&res, unsigned int &len) const
- virtual int **print** (char \*buf, int len) const
- virtual void scan (const char \*buf)
- virtual operator bool (void) const
- virtual bool operator! (void) const
- uint32\_t crc (void) const

# 5.24.1 Detailed Description

Implementation of CRC32 checksum.

The documentation for this class was generated from the following file:

· CheckSum.h

# 5.25 Arc::CredentialError Class Reference

#include <Credential.h>

## **Public Member Functions**

• CredentialError (const std::string &what="")

## **5.25.1** Detailed Description

This is an exception class that is used to handle runtime errors discovered in the Credential class.

# 5.25.2 Constructor & Destructor Documentation

## 5.25.2.1 Arc::CredentialError::CredentialError (const std::string & what = "")

This is the constructor of the CredentialError class.

#### **Parameters:**

what An explanation of the error.

The documentation for this class was generated from the following file:


• Credential.h

## 5.26 Arc::Database Class Reference

Interface for calling database client library.

#include <DBInterface.h>

Inheritance diagram for Arc::Database::



#### **Public Member Functions**

- Database ()
- Database (std::string &server, int port)
- Database (const Database &other)
- virtual ∼Database ()
- virtual bool connect (std::string &dbname, std::string &user, std::string &password)=0
- virtual bool isconnected () const =0
- virtual void close ()=0
- virtual bool enable\_ssl (const std::string keyfile="", const std::string certfile="", const std::string cafile="", const std::string capath="")=0
- virtual bool shutdown ()=0

## **5.26.1** Detailed Description

Interface for calling database client library.

For different types of database client library, different classes should be implemented by implementing this interface.

## 5.26.2 Constructor & Destructor Documentation

## **5.26.2.1** Arc::Database::Database() [inline]

Default constructor

## **5.26.2.2** Arc::Database::Database (std::string & server, int port) [inline]

Constructor which uses the server's name(or IP address) and port as parametes

## **5.26.2.3** Arc::Database::Database (const Database & other) [inline]

Copy constructor

#### **5.26.2.4 virtual Arc::Database::**~Database() [inline, virtual]

Deconstructor

### **5.26.3** Member Function Documentation

#### **5.26.3.1 virtual void Arc::Database::close ()** [pure virtual]

Close the connection with database server

Implemented in Arc::MySQLDatabase.

# 5.26.3.2 virtual bool Arc::Database::connect (std::string & dbname, std::string & user, std::string & password) [pure virtual]

Do connection with database server

#### **Parameters:**

```
dbname The database name which will be used.user The username which will be used to access database.password The password which will be used to access database.
```

Implemented in Arc::MySQLDatabase.

# 5.26.3.3 virtual bool Arc::Database::enable\_ssl (const std::string keyfile = "", const std::string capth = "") [pure virtual]

Enable ssl communication for the connection

#### **Parameters:**

```
keyfile The location of key file.certfile The location of certificate file.cafile The location of ca file.capath The location of ca directory
```

Implemented in Arc::MySQLDatabase.

## **5.26.3.4 virtual bool Arc::Database::isconnected () const** [pure virtual]

Get the connection status

Implemented in Arc::MySQLDatabase.

## **5.26.3.5 virtual bool Arc::Database::shutdown ()** [pure virtual]

Ask database server to shutdown

Implemented in Arc::MySQLDatabase.

The documentation for this class was generated from the following file:

• DBInterface.h

## 5.27 Arc::DataBuffer Class Reference

Represents set of buffers.

#include <DataBuffer.h>

#### **Public Member Functions**

- operator bool ()
- DataBuffer (unsigned int size=65536, int blocks=3)
- DataBuffer (CheckSum \*cksum, unsigned int size=65536, int blocks=3)
- ∼DataBuffer ()
- bool set (CheckSum \*cksum=NULL, unsigned int size=65536, int blocks=3)
- char \* operator[] (int n)
- bool for\_read (int &handle, unsigned int &length, bool wait)
- bool for read ()
- bool is\_read (int handle, unsigned int length, unsigned long long int offset)
- bool is\_read (char \*buf, unsigned int length, unsigned long long int offset)
- bool for\_write (int &handle, unsigned int &length, unsigned long long int &offset, bool wait)
- bool for\_write ()
- bool is\_written (int handle)
- bool is\_written (char \*buf)
- bool is\_notwritten (int handle)
- bool is\_notwritten (char \*buf)
- void eof\_read (bool v)
- void eof\_write (bool v)
- void error\_read (bool v)
- void error\_write (bool v)
- bool eof\_read ()
- bool eof\_write ()
- bool error\_read ()
- bool error\_write ()
- bool error\_transfer ()
- bool error ()
- bool wait\_any ()
- bool wait\_used ()
- bool checksum\_valid ()
- const CheckSum \* checksum\_object ()
- bool wait\_eof\_read ()
- bool wait\_read ()
- bool wait\_eof\_write ()
- bool wait\_write ()
- bool wait\_eof ()
- unsigned long long int eof\_position () const
- unsigned int buffer\_size ()

## **Public Attributes**

· DataSpeed speed

## Classes

struct buf\_desc

## 5.27.1 Detailed Description

Represents set of buffers.

This class is used used during data transfer using DataPoint classes.

## 5.27.2 Constructor & Destructor Documentation

## **5.27.2.1** Arc::DataBuffer::DataBuffer (unsigned int size = 65536, int blocks = 3)

Contructor

#### **Parameters:**

```
size size of every buffer in bytes.blocks number of buffers.
```

# 5.27.2.2 Arc::DataBuffer::DataBuffer (CheckSum \* cksum, unsigned int size = 65536, int blocks = 3)

Contructor

## **Parameters:**

```
size size of every buffer in bytes.blocks number of buffers.cksum object which will compute checksum. Should not be destroyed till DataBuffer itself.
```

#### 5.27.2.3 Arc::DataBuffer::~DataBuffer()

Destructor.

## **5.27.3** Member Function Documentation

## 5.27.3.1 unsigned int Arc::DataBuffer::buffer\_size ()

Returns size of buffer in object. If not initialized then this number represents size of default buffer.

## 5.27.3.2 const CheckSum\* Arc::DataBuffer::checksum\_object ()

Returns CheckSum object specified in constructor.

## 5.27.3.3 bool Arc::DataBuffer::checksum\_valid ()

Returns true if checksum was successfully computed.

## 5.27.3.4 unsigned long long int Arc::DataBuffer::eof\_position() const [inline]

Returns offset following last piece of data transfered.

## 5.27.3.5 bool Arc::DataBuffer::eof\_read()

Returns true if object was informed about end of transfer on 'read' side.

#### 5.27.3.6 void Arc::DataBuffer::eof\_read (bool v)

Informs object if there will be no more request for 'read' buffers. v true if no more requests.

## 5.27.3.7 bool Arc::DataBuffer::eof\_write()

Returns true if object was informed about end of transfer on 'write' side.

## 5.27.3.8 void Arc::DataBuffer::eof\_write (bool v)

Informs object if there will be no more request for 'write' buffers. v true if no more requests.

#### 5.27.3.9 bool Arc::DataBuffer::error ()

Returns true if object was informed about error or internal error occured.

## 5.27.3.10 bool Arc::DataBuffer::error\_read ()

Returns true if object was informed about error on 'read' side.

## 5.27.3.11 void Arc::DataBuffer::error\_read (bool v)

Informs object if error accured on 'read' side.

### **Parameters:**

v true if error.

#### **5.27.3.12** bool Arc::DataBuffer::error\_transfer()

Returns true if eror occured inside object.

## 5.27.3.13 bool Arc::DataBuffer::error\_write()

Returns true if object was informed about error on 'write' side.

## 5.27.3.14 void Arc::DataBuffer::error\_write (bool v)

Informs object if error accured on 'write' side.

#### **Parameters:**

v true if error.

## 5.27.3.15 bool Arc::DataBuffer::for\_read ()

Check if there are buffers which can be taken by for\_read(). This function checks only for buffers and does not take eof and error conditions into account.

## 5.27.3.16 bool Arc::DataBuffer::for\_read (int & handle, unsigned int & length, bool wait)

Request buffer for READING INTO it.

#### **Parameters:**

handle returns buffer's number.

length returns size of buffer

wait if true and there are no free buffers, method will wait for one.

#### **Returns:**

true on success

## 5.27.3.17 bool Arc::DataBuffer::for\_write()

Check if there are buffers which can be taken by for\_write(). This function checks only for buffers and does not take eof and error conditions into account.

# 5.27.3.18 bool Arc::DataBuffer::for\_write (int & handle, unsigned int & length, unsigned long long int & offset, bool wait)

Request buffer for WRITING FROM it.

#### **Parameters:**

handle returns buffer's number.

length returns size of buffer

wait if true and there are no free buffers, method will wait for one.

## 5.27.3.19 bool Arc::DataBuffer::is\_notwritten (char \* buf)

Informs object that data was NOT written from buffer (and releases buffer).

## **Parameters:**

buf - address of buffer

## 5.27.3.20 bool Arc::DataBuffer::is\_notwritten (int handle)

Informs object that data was NOT written from buffer (and releases buffer).

#### **Parameters:**

handle buffer's number.

# 5.27.3.21 bool Arc::DataBuffer::is\_read (char \* buf, unsigned int length, unsigned long long int offset)

Informs object that data was read into buffer.

#### **Parameters:**

```
buf - address of bufferlength amount of data.offset offset in stream, file, etc.
```

# 5.27.3.22 bool Arc::DataBuffer::is\_read (int *handle*, unsigned int *length*, unsigned long long int *offset*)

Informs object that data was read into buffer.

#### **Parameters:**

```
handle buffer's number.length amount of data.offset offset in stream, file, etc.
```

## 5.27.3.23 bool Arc::DataBuffer::is\_written (char \* buf)

Informs object that data was written from buffer.

#### **Parameters:**

```
buf - address of buffer
```

## 5.27.3.24 bool Arc::DataBuffer::is\_written (int handle)

Informs object that data was written from buffer.

### **Parameters:**

handle buffer's number.

## **5.27.3.25** Arc::DataBuffer::operator bool (void) [inline]

Check if DataBuffer object is initialized.

#### 5.27.3.26

char\* Arc::DataBuffer::operator[] (int n)

Direct access to buffer by number.

# 5.27.3.27 bool Arc::DataBuffer::set (CheckSum \* cksum = NULL, unsigned int size = 65536, int blocks = 3)

Reinitialize buffers with different parameters.

#### **Parameters:**

size size of every buffer in bytes.

blocks number of buffers.

cksum object which will compute checksum. Should not be destroyed till DataBuffer itself.

## 5.27.3.28 bool Arc::DataBuffer::wait\_any ()

Wait (max 60 sec.) till any action happens in object. Returns true if action is eof on any side.

## 5.27.3.29 bool Arc::DataBuffer::wait\_eof()

Wait till end of transfer happens on any side.

## 5.27.3.30 bool Arc::DataBuffer::wait\_eof\_read ()

Wait till end of transfer happens on 'read' side.

#### 5.27.3.31 bool Arc::DataBuffer::wait\_eof\_write()

Wait till end of transfer happens on 'write' side.

## 5.27.3.32 bool Arc::DataBuffer::wait\_read ()

Wait till end of transfer or error happens on 'read' side.

## 5.27.3.33 bool Arc::DataBuffer::wait\_used ()

Wait till there are no more used buffers left in object.

## 5.27.3.34 bool Arc::DataBuffer::wait\_write()

Wait till end of transfer or error happens on 'write' side.

# **5.27.4** Member Data Documentation

## 5.27.4.1 DataSpeed Arc::DataBuffer::speed

This object controls transfer speed.

The documentation for this class was generated from the following file:

• DataBuffer.h

# 5.28 Arc::DataCallback Class Reference

#include <DataCallback.h>

## **Public Member Functions**

- virtual bool **cb** (int)
- virtual bool cb (unsigned int)
- virtual bool cb (long long int)
- virtual bool **cb** (unsigned long long int)

# **5.28.1** Detailed Description

This class is used by DataHandle to report missing space on local filesystem. One of 'cb' functions here will be called if operation initiated by DataHandle::start\_reading runs out of disk space.

The documentation for this class was generated from the following file:

· DataCallback.h

# 5.29 Arc::DataHandle Class Reference

This class is a wrapper around the DataPoint class.

```
#include <DataHandle.h>
```

## **Public Member Functions**

- DataHandle (const URL &url)
- DataHandle & operator= (const URL &url)
- void Clear ()
- DataPoint \* operator → ()
- const DataPoint \* operator → () const
- DataPoint & operator \* ()
- const DataPoint & operator \* () const
- bool operator! () const
- operator bool () const

## 5.29.1 Detailed Description

This class is a wrapper around the DataPoint class.

It simplifies the construction, use and destruction of DataPoint objects.

The documentation for this class was generated from the following file:

• DataHandle.h

# 5.30 Arc::DataMover Class Reference

#include <DataMover.h>

## **Public Types**

• typedef void(\*) callback (DataMover \*, DataStatus, const std::string &, void \*)

#### **Public Member Functions**

- DataMover ()
- ∼DataMover ()
- DataStatus Transfer (DataPoint &source, DataPoint &destination, FileCache &cache, const URLMap &map, std::string &failure\_description, callback cb=NULL, void \*arg=NULL, const char \*prefix=NULL)
- DataStatus Transfer (DataPoint &source, DataPoint &destination, FileCache &cache, const URLMap &map, unsigned long long int min\_speed, time\_t min\_speed\_time, unsigned long long int min\_average\_speed, time\_t max\_inactivity\_time, std::string &failure\_description, callback cb=NULL, void \*arg=NULL, const char \*prefix=NULL)
- DataStatus Delete (DataPoint &url, bool errcont=false)
- bool verbose ()
- void verbose (bool)
- void verbose (const std::string &prefix)
- bool retry ()
- void retry (bool)
- void secure (bool)
- void passive (bool)
- void force\_to\_meta (bool)
- bool checks ()
- void checks (bool v)
- void set\_default\_min\_speed (unsigned long long int min\_speed, time\_t min\_speed\_time)
- void set\_default\_min\_average\_speed (unsigned long long int min\_average\_speed)
- void set\_default\_max\_inactivity\_time (time\_t max\_inactivity\_time)
- void **set\_progress\_indicator** (DataSpeed::show\_progress\_t func=NULL)

## 5.30.1 Detailed Description

A purpose of this class is to provide an interface that moves data between two locations specified by URLs. It's main action is represented by methods DataMover::Transfer. Instance represents only attributes used during transfer.

### 5.30.2 Constructor & Destructor Documentation

#### 5.30.2.1 Arc::DataMover::DataMover()

Constructor.

#### 5.30.2.2 Arc::DataMover::~DataMover ()

Destructor.

## 5.30.3 Member Function Documentation

## 5.30.3.1 void Arc::DataMover::checks (bool v)

Set if to make check for existance of remote file (and probably other checks too) before initiating 'reading' and 'writing' operations.

#### **Parameters:**

v true if allowed (default is true).

#### 5.30.3.2 bool Arc::DataMover::checks ()

Check if check for existance of remote file is done before initiating 'reading' and 'writing' operations.

#### 5.30.3.3 void Arc::DataMover::force\_to\_meta (bool)

Set if file should be transfered and registered even if such LFN is already registered and source is not one of registered locations.

## 5.30.3.4 void Arc::DataMover::passive (bool)

Set if passive transfer should be used for FTP-like transfers.

#### 5.30.3.5 void Arc::DataMover::retry (bool)

Set if transfer will be retried in case of failure.

## 5.30.3.6 bool Arc::DataMover::retry ()

Check if transfer will be retried in case of failure.

## 5.30.3.7 void Arc::DataMover::secure (bool)

Set if high level of security (encryption) will be used duirng transfer if available.

# **5.30.3.8 void** Arc::DataMover::set\_default\_max\_inactivity\_time (time\_t max\_inactivity\_time)

Set maximal allowed time for waiting for any data. For more information see description of DataSpeed class.

# 5.30.3.9 void Arc::DataMover::set\_default\_min\_average\_speed (unsigned long long int min\_average\_speed) [inline]

Set minimal allowed average transfer speed (default is 0 averaged over whole time of transfer. For more information see description of DataSpeed class.

# 5.30.3.10 void Arc::DataMover::set\_default\_min\_speed (unsigned long long int min\_speed, time\_t min\_speed\_time) [inline]

Set minimal allowed transfer speed (default is 0) to 'min\_speed'. If speed drops below for time longer than 'min\_speed\_time' error is raised. For more information see description of DataSpeed class.

5.30.3.11 DataStatus Arc::DataMover::Transfer (DataPoint & source, DataPoint & destination, FileCache & cache, const URLMap & map, unsigned long long int min\_speed, time\_t min\_speed\_time, unsigned long long int min\_average\_speed, time\_t max\_inactivity\_time, std::string & failure\_description, callback cb = NULL, void \* arg = NULL, const char \* prefix = NULL)

Initiates transfer from 'source' to 'destination'.

#### **Parameters:**

```
min_speed minimal allowed current speed.
min_speed_time time for which speed should be less than 'min_speed' before transfer fails.
min_average_speed minimal allowed average speed.
max inactivity time time for which should be no activity before transfer fails.
```

5.30.3.12 DataStatus Arc::DataMover::Transfer (DataPoint & source, DataPoint & destination, FileCache & cache, const URLMap & map, std::string & failure\_description, callback cb = NULL, void \* arg = NULL, const char \* prefix = NULL)

Initiates transfer from 'source' to 'destination'.

#### Parameters:

```
source source URL.
destination destination URL.
cache controls caching of downloaded files (if destination url is "file://"). If caching is not needed default constructor FileCache() can be used.
map URL mapping/convertion table (for 'source' URL).
cb if not NULL, transfer is done in separate thread and 'cb' is called after transfer completes/fails.
arg passed to 'cb'.
prefix if 'verbose' is activated this information will be printed before each line representing current transfer status.
```

## 5.30.3.13 void Arc::DataMover::verbose (const std::string & prefix)

Activate printing information about transfer status.

#### **Parameters:**

prefix use this string if 'prefix' in DataMover::Transfer is NULL.

## 5.30.3.14 void Arc::DataMover::verbose (bool)

Activate printing information about transfer status.

## 5.30.3.15 bool Arc::DataMover::verbose ()

Check if printing information about transfer status is activated.

The documentation for this class was generated from the following file:


· DataMover.h

# 5.31 Arc::DataPoint Class Reference

This base class is an abstraction of URL.

#include <DataPoint.h>

Inheritance diagram for Arc::DataPoint::



## **Public Member Functions**

- DataPoint (const URL &url)
- virtual ~DataPoint ()
- virtual const URL & GetURL () const
- virtual std::string str () const
- virtual operator bool () const
- virtual bool operator! () const
- virtual DataStatus StartReading (DataBuffer &buffer)=0
- virtual DataStatus StartWriting (DataBuffer &buffer, DataCallback \*space\_cb=NULL)=0
- virtual DataStatus StopReading ()=0
- virtual DataStatus StopWriting ()=0
- virtual DataStatus Check ()=0
- virtual DataStatus Remove ()=0
- virtual DataStatus ListFiles (std::list< FileInfo > &files, bool long\_list=false, bool resolve=false)=0
- virtual void ReadOutOfOrder (bool v)=0
- virtual bool WriteOutOfOrder ()=0
- virtual void SetAdditionalChecks (bool v)=0
- virtual bool GetAdditionalChecks () const =0
- virtual void SetSecure (bool v)=0
- virtual bool GetSecure () const =0
- virtual void Passive (bool v)=0
- virtual void Range (unsigned long long int start=0, unsigned long long int end=0)=0
- virtual DataStatus Resolve (bool source)=0
- virtual bool Registered () const =0
- virtual DataStatus PreRegister (bool replication, bool force=false)=0
- virtual DataStatus PostRegister (bool replication)=0
- virtual DataStatus PreUnregister (bool replication)=0
- virtual DataStatus Unregister (bool all)=0
- virtual bool CheckSize () const
- virtual void SetSize (const unsigned long long int val)
- virtual unsigned long long int GetSize () const
- virtual bool CheckCheckSum () const
- virtual void SetCheckSum (const std::string &val)
- virtual const std::string & GetCheckSum () const
- virtual bool CheckCreated () const

- virtual void SetCreated (const Time &val)
- virtual const Time & GetCreated () const
- virtual bool CheckValid () const
- virtual void SetValid (const Time &val)
- virtual const Time & GetValid () const
- virtual unsigned long long int BufSize () const =0
- virtual int BufNum () const =0
- virtual bool Cache () const =0
- virtual bool Local () const =0
- virtual bool **ReadOnly** () const =0
- virtual int GetTries () const
- virtual void SetTries (const int n)
- virtual bool IsIndex () const =0
- virtual bool AcceptsMeta ()=0
- virtual bool ProvidesMeta ()=0
- virtual void SetMeta (const DataPoint &p)
- virtual bool CompareMeta (const DataPoint &p) const
- virtual const URL & CurrentLocation () const =0
- virtual const std::string & CurrentLocationMetadata () const =0
- virtual bool NextLocation ()=0
- virtual bool LocationValid () const =0
- virtual bool HaveLocations () const =0
- virtual DataStatus AddLocation (const URL &url, const std::string &meta)=0
- virtual DataStatus RemoveLocation ()=0
- virtual DataStatus RemoveLocations (const DataPoint &p)=0
- void AssignCredentials (const std::string &proxyPath, const std::string &certificatePath, const std::string &keyPath, const std::string &caCertificatesDir)
- void AssignCredentials (const XMLNode &node)

## **Protected Attributes**

- URL url
- unsigned long long int size
- std::string checksum
- Time created
- Time valid
- int triesleft
- std::string proxyPath
- std::string certificatePath
- std::string keyPath
- std::string caCertificatesDir

## **Static Protected Attributes**

• static Logger logger

## **5.31.1** Detailed Description

This base class is an abstraction of URL.

Specializations should be provided for different kind of direct access URLs (file://, ftp://, gsiftp://, https://, https://, https://, ...) or indexing service URLs (rls://, lfc://, ...). DataPoint provides means to resolve an indexing service URL into multiple URLs and to loop through them.

## **5.31.2** Constructor & Destructor Documentation

#### 5.31.2.1 Arc::DataPoint::DataPoint (const URL & url)

Constructor requires URL to be provided.

#### **5.31.2.2 virtual Arc::DataPoint::~DataPoint()** [virtual]

Destructor.

## **5.31.3** Member Function Documentation

#### **5.31.3.1 virtual bool Arc::DataPoint::AcceptsMeta ()** [pure virtual]

If endpoint can have any use from meta information.

Implemented in Arc::DataPointDirect, and Arc::DataPointIndex.

# 5.31.3.2 virtual DataStatus Arc::DataPoint::AddLocation (const URL & url, const std::string & meta) [pure virtual]

Add URL to list.

#### **Parameters:**

url Location URL to add.

meta Location meta information.

Implemented in Arc::DataPointDirect, and Arc::DataPointIndex.

#### 5.31.3.3 void Arc::DataPoint::AssignCredentials (const XMLNode & node)

Assing credentials used for authentication (using XML node).

# 5.31.3.4 void Arc::DataPoint::AssignCredentials (const std::string & proxyPath, const std::string & certificatePath, const std::string & keyPath, const std::string & caCertificatesDir)

Assing credentials used for authentication.

## **5.31.3.5 virtual int Arc::DataPoint::BufNum () const** [pure virtual]

Get suggested number of buffers for transfers.

Implemented in Arc::DataPointDirect, and Arc::DataPointIndex.

## **5.31.3.6 virtual unsigned long long int Arc::DataPoint::BufSize () const** [pure virtual]

Get suggested buffer size for transfers.

Implemented in Arc::DataPointDirect, and Arc::DataPointIndex.

## **5.31.3.7 virtual bool Arc::DataPoint::Cache () const** [pure virtual]

Returns true if file is cacheable.

Implemented in Arc::DataPointDirect, and Arc::DataPointIndex.

#### **5.31.3.8 virtual DataStatus Arc::DataPoint::Check ()** [pure virtual]

Query the DataPoint to check if object is accessible.

If possible this method will also try to provide meta information about the object.

Implemented in Arc::DataPointIndex.

## **5.31.3.9 virtual bool Arc::DataPoint::CheckCheckSum () const** [virtual]

Check if meta-information 'checksum' is available.

## **5.31.3.10** virtual bool Arc::DataPoint::CheckCreated () const [virtual]

Check if meta-information 'creation/modification time' is available.

#### **5.31.3.11** virtual bool Arc::DataPoint::CheckSize () const [virtual]

Check if meta-information 'size' is available.

#### **5.31.3.12 virtual bool Arc::DataPoint::CheckValid () const** [virtual]

Check if meta-information 'validity time' is available.

## **5.31.3.13 virtual bool Arc::DataPoint::CompareMeta (const DataPoint & p) const** [virtual]

Compare meta information from another object.

Undefined values are not used for comparison.

#### **Parameters:**

**p** object to which to compare.

## 5.31.3.14 virtual const URL& Arc::DataPoint::CurrentLocation () const [pure virtual]

Returns current (resolved) URL.

Implemented in Arc::DataPointDirect, and Arc::DataPointIndex.

# **5.31.3.15 virtual const std::string& Arc::DataPoint::CurrentLocationMetadata** () **const** [pure virtual]

Returns meta information used to create current URL.

Usage differs between different indexing services.

Implemented in Arc::DataPointDirect, and Arc::DataPointIndex.

#### **5.31.3.16 virtual bool Arc::DataPoint::GetAdditionalChecks () const** [pure virtual]

Check if additional checks before will be performed.

Implemented in Arc::DataPointDirect, and Arc::DataPointIndex.

## 5.31.3.17 virtual const std::string& Arc::DataPoint::GetCheckSum () const [virtual]

Get value of meta-information 'checksum'.

#### 5.31.3.18 virtual const Time& Arc::DataPoint::GetCreated () const [virtual]

Get value of meta-information 'creation/modification time'.

#### **5.31.3.19 virtual bool Arc::DataPoint::GetSecure () const** [pure virtual]

Check if heavy security during data transfer is allowed.

Implemented in Arc::DataPointDirect, and Arc::DataPointIndex.

## **5.31.3.20 virtual unsigned long long int Arc::DataPoint::GetSize () const** [virtual]

Get value of meta-information 'size'.

#### **5.31.3.21 virtual int Arc::DataPoint::GetTries** () **const** [virtual]

Returns number of retries left.

## 5.31.3.22 virtual const URL& Arc::DataPoint::GetURL() const [virtual]

Returns the URL that was passed to the constructor.

## **5.31.3.23 virtual const Time& Arc::DataPoint::GetValid () const** [virtual]

Get value of meta-information 'validity time'.

## **5.31.3.24 virtual bool Arc::DataPoint::HaveLocations () const** [pure virtual]

Returns true if number of resolved URLs is not 0.

Implemented in Arc::DataPointDirect, and Arc::DataPointIndex.

## **5.31.3.25 virtual bool Arc::DataPoint::IsIndex () const** [pure virtual]

Check if URL is an Indexing Service.

Implemented in Arc::DataPointDirect, and Arc::DataPointIndex.

# 5.31.3.26 virtual DataStatus Arc::DataPoint::ListFiles (std::list< FileInfo > & files, bool long\_list = false, bool resolve = false) [pure virtual]

List file(s).

If the DataPoint represents a directory its contents will be listed.

#### **Parameters:**

files will contain list of file names and optionally their attributes.

*long*) *list* if true, list additional properties of each file.

resolve if true, resolve physical locations (relevant for indexing services only).

#### **5.31.3.27 virtual bool Arc::DataPoint::Local () const** [pure virtual]

Returns true if file is local, e.g. file:// urls.

Implemented in Arc::DataPointDirect, and Arc::DataPointIndex.

#### **5.31.3.28 virtual bool Arc::DataPoint::LocationValid () const** [pure virtual]

Returns false if out of retries.

Implemented in Arc::DataPointDirect, and Arc::DataPointIndex.

#### **5.31.3.29 virtual bool Arc::DataPoint::NextLocation ()** [pure virtual]

Switch to next location in list of URLs.

At last location switch to first if number of allowed retries is not exceeded. Returns false if no retries left.

Implemented in Arc::DataPointDirect, and Arc::DataPointIndex.

#### **5.31.3.30 virtual Arc::DataPoint::operator bool () const** [virtual]

Is DataPoint valid?

#### **5.31.3.31** virtual bool Arc::DataPoint::operator! () const [virtual]

Is DataPoint valid?

## **5.31.3.32 virtual void Arc::DataPoint::Passive (bool v)** [pure virtual]

Request passive transfers for FTP-like protocols.

#### **Parameters:**

true to request.

Implemented in Arc::DataPointDirect, and Arc::DataPointIndex.

## **5.31.3.33 virtual DataStatus Arc::DataPoint::PostRegister (bool** replication) [pure virtual]

Index Service postregistration.

Used for same purpose as PreRegister. Should be called after actual transfer of file successfully finished.

#### **Parameters:**

**replication** if true, the file is being replicated between two locations registered in Indexing Service under same name.

Implemented in Arc::DataPointDirect.

# **5.31.3.34 virtual DataStatus Arc::DataPoint::PreRegister (bool** *replication***, bool** *force* = false) [pure virtual]

Index service preregistration.

This function registers the physical location of a file into an indexing service. It should be called \*before\* the actual transfer to that location happens.

#### **Parameters:**

*replication* if true, the file is being replicated between two locations registered in the indexing service under same name.

*force* if true, perform registration of a new file even if it already exists. Should be used to fix failures in Indexing Service.

Implemented in Arc::DataPointDirect.

## **5.31.3.35 virtual DataStatus Arc::DataPoint::PreUnregister (bool replication)** [pure virtual]

Index Service preunregistration.

Should be called if file transfer failed. It removes changes made by PreRegister.

#### **Parameters:**

**replication** if true, the file is being replicated between two locations registered in Indexing Service under same name.

Implemented in Arc::DataPointDirect.

## **5.31.3.36 virtual bool Arc::DataPoint::ProvidesMeta** () [pure virtual]

If endpoint can provide at least some meta information directly.

Implemented in Arc::DataPointDirect, and Arc::DataPointIndex.

# **5.31.3.37 virtual void Arc::DataPoint::Range (unsigned long long int** *start* = 0, **unsigned long long int** *end* = 0) [pure virtual]

Set range of bytes to retrieve.

Default values correspond to whole file.

Implemented in Arc::DataPointDirect, and Arc::DataPointIndex.

#### **5.31.3.38 virtual void Arc::DataPoint::ReadOutOfOrder (bool v)** [pure virtual]

#### **Parameters:**

v true if allowed (default is false).

Implemented in Arc::DataPointDirect, and Arc::DataPointIndex.

## **5.31.3.39 virtual bool Arc::DataPoint::Registered () const** [pure virtual]

Check if file is registered in Indexing Service.

Proper value is obtainable only after Resolve.

Implemented in Arc::DataPointDirect, and Arc::DataPointIndex.

## **5.31.3.40 virtual DataStatus Arc::DataPoint::Remove ()** [pure virtual]

Remove/delete object at URL.

Implemented in Arc::DataPointIndex.

#### **5.31.3.41 virtual DataStatus Arc::DataPoint::RemoveLocation ()** [pure virtual]

Remove current URL from list.

Implemented in Arc::DataPointDirect, and Arc::DataPointIndex.

# **5.31.3.42 virtual DataStatus Arc::DataPoint::RemoveLocations (const DataPoint & p)** [pure virtual]

Remove locations present in another DataPoint object.

Implemented in Arc::DataPointDirect, and Arc::DataPointIndex.

#### **5.31.3.43 virtual DataStatus Arc::DataPoint::Resolve (bool source)** [pure virtual]

Resolves index service **URL** into list of ordinary URLs.

Also obtains meta information about the file.

#### **Parameters:**

source true if DataPoint object represents source of information.

Implemented in Arc::DataPointDirect.

#### 5.31.3.44 virtual void Arc::DataPoint::SetAdditionalChecks (bool v) [pure virtual]

Allow/disallow additional checks.

Check for existance of remote file (and probably other checks too) before initiating reading and writing operations.

#### **Parameters:**

v true if allowed (default is true).

Implemented in Arc::DataPointDirect, and Arc::DataPointIndex.

#### 5.31.3.45 virtual void Arc::DataPoint::SetCheckSum (const std::string & val) [virtual]

Set value of meta-information 'checksum'.

#### **5.31.3.46** virtual void Arc::DataPoint::SetCreated (const Time & val) [virtual]

Set value of meta-information 'creation/modification time'.

### **5.31.3.47 virtual void Arc::DataPoint::SetMeta (const DataPoint & p)** [virtual]

Copy meta information from another object.

Already defined values are not overwritten.

#### **Parameters:**

p object from which information is taken.

#### **5.31.3.48 virtual void Arc::DataPoint::SetSecure (bool v)** [pure virtual]

Allow/disallow heavy security during data transfer.

### **Parameters:**

v true if allowed (default depends on protocol).

Implemented in Arc::DataPointDirect, and Arc::DataPointIndex.

#### **5.31.3.49 virtual void Arc::DataPoint::SetSize (const unsigned long long int** *val***)** [virtual]

Set value of meta-information 'size'.

#### **5.31.3.50 virtual void Arc::DataPoint::SetTries (const int** *n***)** [virtual]

Set number of retries.

Reimplemented in Arc::DataPointIndex.

#### 5.31.3.51 virtual void Arc::DataPoint::SetValid (const Time & val) [virtual]

Set value of meta-information 'validity time'.

## **5.31.3.52 virtual DataStatus Arc::DataPoint::StartReading (DataBuffer & buffer)** [pure virtual]

Start reading data from URL.

Separate thread to transfer data will be created. No other operation can be performed while reading is in progress.

#### **Parameters:**

**buffer** operation will use this buffer to put information into. Should not be destroyed before stop\_reading was called and returned.

Implemented in Arc::DataPointIndex.

## 5.31.3.53 virtual DataStatus Arc::DataPoint::StartWriting (DataBuffer & buffer, DataCallback \* space\_cb = NULL) [pure virtual]

Start writing data to URL.

Separate thread to transfer data will be created. No other operation can be performed while writing is in progress.

#### **Parameters:**

**buffer** operation will use this buffer to get information from. Should not be destroyed before stop\_writing was called and returned.

space\_cb callback which is called if there is not enough space to store data. May not implemented for all protocols.

Implemented in Arc::DataPointIndex.

#### **5.31.3.54 virtual DataStatus Arc::DataPoint::StopReading ()** [pure virtual]

Stop reading.

Must be called after corresponding start\_reading method, either after all data is transferred or to cancel transfer. Use buffer object to find out when data is transferred. Must return failure if any happened during transfer.

Implemented in Arc::DataPointIndex.

#### **5.31.3.55 virtual DataStatus Arc::DataPoint::StopWriting()** [pure virtual]

Stop writing.

Must be called after corresponding start\_writing method, either after all data is transferred or to cancel transfer. Use buffer object to find out when data is transferred. Must return failure if any happened during transfer.

Implemented in Arc::DataPointIndex.

#### **5.31.3.56 virtual std::string Arc::DataPoint::str() const** [virtual]

Returns a string representation of the DataPoint.

### **5.31.3.57 virtual DataStatus Arc::DataPoint::Unregister (bool** *all***)** [pure virtual]

Index Service unregistration.

Remove information about file registered in Indexing Service.

#### **Parameters:**

**all** if true, information about file itself is (LFN) is removed. Otherwise only particular physical instance is unregistered.

Implemented in Arc::DataPointDirect.

### **5.31.3.58 virtual bool Arc::DataPoint::WriteOutOfOrder()** [pure virtual]

Returns true if URL can accept scattered data for \*writing\* operation.

Implemented in Arc::DataPointDirect, and Arc::DataPointIndex.

The documentation for this class was generated from the following file:


• DataPoint.h

## 5.32 Arc::DataPointDirect Class Reference

This is a kind of generalized file handle.

#include <DataPointDirect.h>

Inheritance diagram for Arc::DataPointDirect::



#### **Public Member Functions**

- DataPointDirect (const URL &url)
- virtual bool IsIndex () const
- virtual unsigned long long int BufSize () const
- virtual int BufNum () const
- virtual bool Cache () const
- virtual bool Local () const
- virtual bool ReadOnly () const
- virtual void ReadOutOfOrder (bool v)
- virtual bool WriteOutOfOrder ()
- virtual void SetAdditionalChecks (bool v)
- virtual bool GetAdditionalChecks () const
- virtual void SetSecure (bool v)
- virtual bool GetSecure () const
- virtual void Passive (bool v)
- virtual void Range (unsigned long long int start=0, unsigned long long int end=0)
- virtual DataStatus Resolve (bool source)
- virtual bool Registered () const
- virtual DataStatus PreRegister (bool replication, bool force=false)
- virtual DataStatus PostRegister (bool replication)
- virtual DataStatus PreUnregister (bool replication)
- virtual DataStatus Unregister (bool all)
- virtual bool AcceptsMeta ()
- virtual bool ProvidesMeta ()
- virtual const URL & CurrentLocation () const
- virtual const std::string & CurrentLocationMetadata () const
- virtual bool NextLocation ()
- virtual bool LocationValid () const
- virtual bool HaveLocations () const
- virtual DataStatus AddLocation (const URL &url, const std::string &meta)
- virtual DataStatus RemoveLocation ()
- virtual DataStatus RemoveLocations (const DataPoint &p)

#### **Protected Attributes**

- DataBuffer \* buffer
- unsigned long long int bufsize
- int bufnum
- bool cache
- bool local
- · bool readonly
- bool linkable
- bool is\_secure
- bool force\_secure
- bool **force\_passive**
- · bool additional\_checks
- bool allow out of order
- unsigned long long int range\_start
- unsigned long long int range\_end

## 5.32.1 Detailed Description

This is a kind of generalized file handle.

Differently from file handle it does not support operations read() and write(). Instead it initiates operation and uses object of class <code>DataBuffer</code> to pass actual data. It also provides other operations like querying parameters of remote object. It is used by higher-level classes <code>DataMove</code> and <code>DataMove</code>Par to provide data transfer service for application.

## **5.32.2** Member Function Documentation

## **5.32.2.1 virtual bool Arc::DataPointDirect::AcceptsMeta** () [virtual]

If endpoint can have any use from meta information.

Implements Arc::DataPoint.

## 5.32.2.2 virtual DataStatus Arc::DataPointDirect::AddLocation (const URL & url, const std::string & meta) [virtual]

Add URL to list.

#### **Parameters:**

url Location URL to add.

meta Location meta information.

Implements Arc::DataPoint.

#### **5.32.2.3 virtual int Arc::DataPointDirect::BufNum () const** [virtual]

Get suggested number of buffers for transfers.

#### **5.32.2.4 virtual unsigned long long int Arc::DataPointDirect::BufSize** () **const** [virtual]

Get suggested buffer size for transfers.

Implements Arc::DataPoint.

#### 5.32.2.5 virtual bool Arc::DataPointDirect::Cache () const [virtual]

Returns true if file is cacheable.

Implements Arc::DataPoint.

## 5.32.2.6 virtual const URL & Arc::DataPointDirect::CurrentLocation () const [virtual]

Returns current (resolved) URL.

Implements Arc::DataPoint.

# **5.32.2.7** virtual const std::string& Arc::DataPointDirect::CurrentLocationMetadata () const [virtual]

Returns meta information used to create current URL.

Usage differs between different indexing services.

Implements Arc::DataPoint.

## **5.32.2.8 virtual bool Arc::DataPointDirect::GetAdditionalChecks () const** [virtual]

Check if additional checks before will be performed.

Implements Arc::DataPoint.

#### **5.32.2.9 virtual bool Arc::DataPointDirect::GetSecure () const** [virtual]

Check if heavy security during data transfer is allowed.

Implements Arc::DataPoint.

## **5.32.2.10 virtual bool Arc::DataPointDirect::HaveLocations () const** [virtual]

Returns true if number of resolved URLs is not 0.

Implements Arc::DataPoint.

## **5.32.2.11 virtual bool Arc::DataPointDirect::IsIndex () const** [virtual]

Check if URL is an Indexing Service.

#### **5.32.2.12** virtual bool Arc::DataPointDirect::Local () const [virtual]

Returns true if file is local, e.g. file:// urls.

Implements Arc::DataPoint.

## **5.32.2.13 virtual bool Arc::DataPointDirect::LocationValid () const** [virtual]

Returns false if out of retries.

Implements Arc::DataPoint.

## **5.32.2.14 virtual bool Arc::DataPointDirect::NextLocation ()** [virtual]

Switch to next location in list of URLs.

At last location switch to first if number of allowed retries is not exceeded. Returns false if no retries left. Implements Arc::DataPoint.

## **5.32.2.15 virtual void Arc::DataPointDirect::Passive (bool v)** [virtual]

Request passive transfers for FTP-like protocols.

#### **Parameters:**

true to request.

Implements Arc::DataPoint.

#### 5.32.2.16 virtual DataStatus Arc::DataPointDirect::PostRegister (bool replication) [virtual]

Index Service postregistration.

Used for same purpose as PreRegister. Should be called after actual transfer of file successfully finished.

#### **Parameters:**

**replication** if true, the file is being replicated between two locations registered in Indexing Service under same name.

Implements Arc::DataPoint.

# **5.32.2.17 virtual DataStatus Arc::DataPointDirect::PreRegister (bool** *replication***, bool** *force* = false) [virtual]

Index service preregistration.

This function registers the physical location of a file into an indexing service. It should be called \*before\* the actual transfer to that location happens.

### **Parameters:**

*replication* if true, the file is being replicated between two locations registered in the indexing service under same name.

*force* if true, perform registration of a new file even if it already exists. Should be used to fix failures in Indexing Service.

Implements Arc::DataPoint.

#### **5.32.2.18 virtual DataStatus Arc::DataPointDirect::PreUnregister (bool** replication) [virtual]

Index Service preunregistration.

Should be called if file transfer failed. It removes changes made by PreRegister.

#### **Parameters:**

**replication** if true, the file is being replicated between two locations registered in Indexing Service under same name.

Implements Arc::DataPoint.

#### **5.32.2.19 virtual bool Arc::DataPointDirect::ProvidesMeta ()** [virtual]

If endpoint can provide at least some meta information directly.

Implements Arc::DataPoint.

# **5.32.2.20** virtual void Arc::DataPointDirect::Range (unsigned long long int *start* = 0, unsigned long long int *end* = 0) [virtual]

Set range of bytes to retrieve.

Default values correspond to whole file.

Implements Arc::DataPoint.

## **5.32.2.21 virtual void Arc::DataPointDirect::ReadOutOfOrder (bool v)** [virtual]

#### **Parameters:**

v true if allowed (default is false).

Implements Arc::DataPoint.

#### **5.32.2.22 virtual bool Arc::DataPointDirect::Registered () const** [virtual]

Check if file is registered in Indexing Service.

Proper value is obtainable only after Resolve.

Implements Arc::DataPoint.

#### 5.32.2.23 virtual DataStatus Arc::DataPointDirect::RemoveLocation () [virtual]

Remove current URL from list.

# **5.32.2.24 virtual DataStatus Arc::DataPointDirect::RemoveLocations (const DataPoint & p)** [virtual]

Remove locations present in another DataPoint object.

Implements Arc::DataPoint.

### **5.32.2.25 virtual DataStatus Arc::DataPointDirect::Resolve (bool** source) [virtual]

Resolves index service URL into list of ordinary URLs.

Also obtains meta information about the file.

#### **Parameters:**

source true if DataPoint object represents source of information.

Implements Arc::DataPoint.

#### **5.32.2.26** virtual void Arc::DataPointDirect::SetAdditionalChecks (bool v) [virtual]

Allow/disallow additional checks.

Check for existance of remote file (and probably other checks too) before initiating reading and writing operations.

#### **Parameters:**

v true if allowed (default is true).

Implements Arc::DataPoint.

#### **5.32.2.27 virtual void Arc::DataPointDirect::SetSecure (bool v)** [virtual]

Allow/disallow heavy security during data transfer.

## **Parameters:**

v true if allowed (default depends on protocol).

Implements Arc::DataPoint.

## **5.32.2.28 virtual DataStatus Arc::DataPointDirect::Unregister (bool all)** [virtual]

Index Service unregistration.

Remove information about file registered in Indexing Service.

#### Parameters:

**all** if true, information about file itself is (LFN) is removed. Otherwise only particular physical instance is unregistered.

## **5.32.2.29 virtual bool Arc::DataPointDirect::WriteOutOfOrder()** [virtual]

Returns true if URL can accept scattered data for \*writing\* operation.

Implements Arc::DataPoint.

The documentation for this class was generated from the following file:


• DataPointDirect.h

## 5.33 Arc::DataPointIndex Class Reference

Complements DataPoint with attributes common for Indexing Service URLs.

#include <DataPointIndex.h>

Inheritance diagram for Arc::DataPointIndex::



#### **Public Member Functions**

- DataPointIndex (const URL &url)
- virtual const URL & CurrentLocation () const
- virtual const std::string & CurrentLocationMetadata () const
- virtual bool NextLocation ()
- virtual bool LocationValid () const
- virtual bool HaveLocations () const
- virtual DataStatus RemoveLocation ()
- virtual DataStatus RemoveLocations (const DataPoint &p)
- virtual DataStatus AddLocation (const URL &url, const std::string &meta)
- virtual bool IsIndex () const
- virtual bool AcceptsMeta ()
- virtual bool ProvidesMeta ()
- virtual bool Registered () const
- virtual void SetTries (const int n)
- virtual unsigned long long int BufSize () const
- virtual int BufNum () const
- virtual bool Cache () const
- virtual bool Local () const
- virtual bool ReadOnly () const
- virtual DataStatus StartReading (DataBuffer &buffer)
- virtual DataStatus StartWriting (DataBuffer &buffer, DataCallback \*space\_cb=NULL)
- virtual DataStatus StopReading ()
- virtual DataStatus StopWriting ()
- virtual DataStatus Check ()
- virtual DataStatus Remove ()
- virtual void ReadOutOfOrder (bool v)
- virtual bool WriteOutOfOrder ()
- virtual void SetAdditionalChecks (bool v)
- virtual bool GetAdditionalChecks () const
- virtual void SetSecure (bool v)
- virtual bool GetSecure () const
- virtual void Passive (bool v)
- virtual void Range (unsigned long long int start=0, unsigned long long int end=0)

#### **Protected Attributes**

- std::list< URLLocation > locations
- std::list< URLLocation >::iterator location
- DataHandle h
- · bool resolved
- · bool registered

## **5.33.1** Detailed Description

Complements DataPoint with attributes common for Indexing Service URLs.

It should never be used directly. Instead inherit from it to provide a class for specific a Indexing Service.

#### **5.33.2** Member Function Documentation

## **5.33.2.1 virtual bool Arc::DataPointIndex::AcceptsMeta**() [virtual]

If endpoint can have any use from meta information.

Implements Arc::DataPoint.

# 5.33.2.2 virtual DataStatus Arc::DataPointIndex::AddLocation (const URL & url, const std::string & meta) [virtual]

Add URL to list.

#### **Parameters:**

```
url Location URL to add.
```

meta Location meta information.

Implements Arc::DataPoint.

## $\textbf{5.33.2.3} \quad \textbf{virtual int } Arc:: \textbf{DataPointIndex}:: \textbf{BufNum () const} \quad \texttt{[virtual]}$

Get suggested number of buffers for transfers.

Implements Arc::DataPoint.

#### 5.33.2.4 virtual unsigned long long int Arc::DataPointIndex::BufSize () const [virtual]

Get suggested buffer size for transfers.

Implements Arc::DataPoint.

#### **5.33.2.5** virtual bool Arc::DataPointIndex::Cache () const [virtual]

Returns true if file is cacheable.

#### 5.33.2.6 virtual DataStatus Arc::DataPointIndex::Check () [virtual]

Query the DataPoint to check if object is accessible.

If possible this method will also try to provide meta information about the object.

Implements Arc::DataPoint.

### 5.33.2.7 virtual const URL& Arc::DataPointIndex::CurrentLocation () const [virtual]

Returns current (resolved) URL.

Implements Arc::DataPoint.

## **5.33.2.8** virtual const std::string& Arc::DataPointIndex::CurrentLocationMetadata () const [virtual]

Returns meta information used to create current URL.

Usage differs between different indexing services.

Implements Arc::DataPoint.

#### **5.33.2.9 virtual bool Arc::DataPointIndex::GetAdditionalChecks () const** [virtual]

Check if additional checks before will be performed.

Implements Arc::DataPoint.

#### **5.33.2.10** virtual bool Arc::DataPointIndex::GetSecure () const [virtual]

Check if heavy security during data transfer is allowed.

Implements Arc::DataPoint.

## **5.33.2.11 virtual bool Arc::DataPointIndex::HaveLocations () const** [virtual]

Returns true if number of resolved URLs is not 0.

Implements Arc::DataPoint.

#### **5.33.2.12 virtual bool Arc::DataPointIndex::IsIndex () const** [virtual]

Check if URL is an Indexing Service.

Implements Arc::DataPoint.

### **5.33.2.13 virtual bool Arc::DataPointIndex::Local () const** [virtual]

Returns true if file is local, e.g. file:// urls.

#### **5.33.2.14 virtual bool Arc::DataPointIndex::LocationValid () const** [virtual]

Returns false if out of retries.

Implements Arc::DataPoint.

#### 5.33.2.15 virtual bool Arc::DataPointIndex::NextLocation() [virtual]

Switch to next location in list of URLs.

At last location switch to first if number of allowed retries is not exceeded. Returns false if no retries left.

Implements Arc::DataPoint.

#### **5.33.2.16 virtual void Arc::DataPointIndex::Passive (bool v)** [virtual]

Request passive transfers for FTP-like protocols.

#### **Parameters:**

true to request.

Implements Arc::DataPoint.

#### **5.33.2.17 virtual bool Arc::DataPointIndex::ProvidesMeta** () [virtual]

If endpoint can provide at least some meta information directly.

Implements Arc::DataPoint.

# **5.33.2.18** virtual void Arc::DataPointIndex::Range (unsigned long long int *start* = 0, unsigned long long int *end* = 0) [virtual]

Set range of bytes to retrieve.

Default values correspond to whole file.

Implements Arc::DataPoint.

### **5.33.2.19 virtual void Arc::DataPointIndex::ReadOutOfOrder (bool v)** [virtual]

#### **Parameters:**

v true if allowed (default is false).

Implements Arc::DataPoint.

## **5.33.2.20 virtual bool Arc::DataPointIndex::Registered () const** [virtual]

Check if file is registered in Indexing Service.

Proper value is obtainable only after Resolve.

#### **5.33.2.21 virtual DataStatus Arc::DataPointIndex::Remove ()** [virtual]

Remove/delete object at URL.

Implements Arc::DataPoint.

#### **5.33.2.22 virtual DataStatus Arc::DataPointIndex::RemoveLocation ()** [virtual]

Remove current URL from list.

Implements Arc::DataPoint.

## 5.33.2.23 virtual DataStatus Arc::DataPointIndex::RemoveLocations (const DataPoint & p)

[virtual]

Remove locations present in another DataPoint object.

Implements Arc::DataPoint.

#### **5.33.2.24 virtual void Arc::DataPointIndex::SetAdditionalChecks (bool v)** [virtual]

Allow/disallow additional checks.

Check for existance of remote file (and probably other checks too) before initiating reading and writing operations.

#### **Parameters:**

v true if allowed (default is true).

Implements Arc::DataPoint.

#### **5.33.2.25 virtual void Arc::DataPointIndex::SetSecure (bool v)** [virtual]

Allow/disallow heavy security during data transfer.

### **Parameters:**

v true if allowed (default depends on protocol).

Implements Arc::DataPoint.

### **5.33.2.26 virtual void Arc::DataPointIndex::SetTries (const int** *n***)** [virtual]

Set number of retries.

Reimplemented from Arc::DataPoint.

## 5.33.2.27 virtual DataStatus Arc::DataPointIndex::StartReading (DataBuffer & buffer)

[virtual]

Start reading data from URL.

Separate thread to transfer data will be created. No other operation can be performed while reading is in progress.

#### **Parameters:**

**buffer** operation will use this buffer to put information into. Should not be destroyed before stop\_reading was called and returned.

Implements Arc::DataPoint.

## 5.33.2.28 virtual DataStatus Arc::DataPointIndex::StartWriting (DataBuffer & buffer, DataCallback \* space\_cb = NULL) [virtual]

Start writing data to URL.

Separate thread to transfer data will be created. No other operation can be performed while writing is in progress.

#### **Parameters:**

**buffer** operation will use this buffer to get information from. Should not be destroyed before stop\_writing was called and returned.

**space\_cb** callback which is called if there is not enough space to store data. May not implemented for all protocols.

Implements Arc::DataPoint.

### **5.33.2.29 virtual DataStatus Arc::DataPointIndex::StopReading** () [virtual]

Stop reading.

Must be called after corresponding start\_reading method, either after all data is transferred or to cancel transfer. Use buffer object to find out when data is transferred. Must return failure if any happened during transfer.

Implements Arc::DataPoint.

### **5.33.2.30** virtual DataStatus Arc::DataPointIndex::StopWriting() [virtual]

Stop writing.

Must be called after corresponding start\_writing method, either after all data is transferred or to cancel transfer. Use buffer object to find out when data is transferred. Must return failure if any happened during transfer.

Implements Arc::DataPoint.

### **5.33.2.31** virtual bool Arc::DataPointIndex::WriteOutOfOrder() [virtual]

Returns true if URL can accept scattered data for \*writing\* operation.

## **5.33.3** Member Data Documentation

## **5.33.3.1** std::list<URLLocation> Arc::DataPointIndex::locations [protected]

List of locations at which file can be probably found.

The documentation for this class was generated from the following file:

• DataPointIndex.h

## 5.34 Arc::DataSpeed Class Reference

Keeps track of average and instantaneous transfer speed.

#include <DataSpeed.h>

## **Public Types**

• typedef void(\*) **show\_progress\_t** (FILE \*o, const char \*s, unsigned int t, unsigned long long int all, unsigned long long int max, double instant, double average)

#### **Public Member Functions**

- DataSpeed (time\_t base=DATASPEED\_AVERAGING\_PERIOD)
- DataSpeed (unsigned long long int min\_speed, time\_t min\_speed\_time, unsigned long long int min\_average\_speed, time\_t max\_inactivity\_time, time\_t base=DATASPEED\_AVERAGING\_PERIOD)
- ∼DataSpeed (void)
- void verbose (bool val)
- void verbose (const std::string &prefix)
- bool verbose (void)
- void set\_min\_speed (unsigned long long int min\_speed, time\_t min\_speed\_time)
- void set\_min\_average\_speed (unsigned long long int min\_average\_speed)
- void set\_max\_inactivity\_time (time\_t max\_inactivity\_time)
- void set\_base (time\_t base\_=DATASPEED\_AVERAGING\_PERIOD)
- void set\_max\_data (unsigned long long int max=0)
- void set\_progress\_indicator (show\_progress\_t func=NULL)
- void reset (void)
- bool transfer (unsigned long long int n=0)
- void hold (bool disable)
- bool min\_speed\_failure ()
- bool min\_average\_speed\_failure ()
- bool max\_inactivity\_time\_failure ()
- unsigned long long int transfered\_size (void)

#### **5.34.1** Detailed Description

Keeps track of average and instantaneous transfer speed.

Also detects data transfer inactivity and other transfer timeouts.

#### **5.34.2** Constructor & Destructor Documentation

#### **5.34.2.1** Arc::DataSpeed::DataSpeed (time\_t base = DATASPEED\_AVERAGING\_PERIOD)

Constructor

#### **Parameters:**

base time period used to average values (default 1 minute).

5.34.2.2 Arc::DataSpeed::DataSpeed (unsigned long long int min\_speed, time\_t min\_speed\_time, unsigned long long int min\_average\_speed, time\_t max\_inactivity\_time, time\_t base = DATASPEED\_AVERAGING\_PERIOD)

Constructor

#### **Parameters:**

base time period used to average values (default 1 minute).

*min\_speed* minimal allowed speed (Butes per second). If speed drops and holds below threshold for min\_speed\_time\_ seconds error is triggered.

min\_speed\_time

*min\_average\_speed\_* minimal average speed (Bytes per second) to trigger error. Averaged over whole current transfer time.

max\_inactivity\_time - if no data is passing for specified amount of time (seconds), error is triggered.

#### 5.34.2.3 Arc::DataSpeed::~DataSpeed (void)

Destructor.

#### **5.34.3** Member Function Documentation

#### 5.34.3.1 void Arc::DataSpeed::hold (bool disable)

Turn off speed control.

#### **Parameters:**

disable true to turn off.

## $\textbf{5.34.3.2} \quad \textbf{bool Arc::DataSpeed::max\_inactivity\_time\_failure ()} \quad \texttt{[inline]}$

Check if maximal inactivity time error was triggered.

## **5.34.3.3 bool Arc::DataSpeed::min\_average\_speed\_failure** () [inline]

Check if minimal average speed error was triggered.

### **5.34.3.4** bool Arc::DataSpeed::min\_speed\_failure() [inline]

Check if minimal speed error was triggered.

#### 5.34.3.5 void Arc::DataSpeed::reset (void)

Reset all counters and triggers.

#### **5.34.3.6** void Arc::DataSpeed::set\_base (time\_t base\_ = DATASPEED\_AVERAGING\_PERIOD)

Set averaging time period.

#### **Parameters:**

base time period used to average values (default 1 minute).

#### **5.34.3.7** void Arc::DataSpeed::set\_max\_data (unsigned long long int *max* = 0)

Set amount of data to be transfered. Used in verbose messages.

#### **Parameters:**

max amount of data in bytes.

#### 5.34.3.8 void Arc::DataSpeed::set\_max\_inactivity\_time (time\_t max\_inactivity\_time)

Set inactivity tiemout.

#### **Parameters:**

max\_inactivity\_time - if no data is passing for specified amount of time (seconds), error is triggered.

#### 5.34.3.9 void Arc::DataSpeed::set\_min\_average\_speed (unsigned long long int min\_average\_speed)

Set minmal avaerage speed.

#### **Parameters:**

min\_average\_speed\_ minimal average speed (Bytes per second) to trigger error. Averaged over whole current transfer time.

# 5.34.3.10 void Arc::DataSpeed::set\_min\_speed (unsigned long long int min\_speed, time\_t min\_speed\_time)

Set minimal allowed speed.

#### **Parameters:**

min\_speed minimal allowed speed (Butes per second). If speed drops and holds below threshold for min\_speed\_time\_ seconds error is triggered.min\_speed\_time

#### 5.34.3.11 void Arc::DataSpeed::set\_progress\_indicator (show\_progress\_t func = NULL)

Specify which external function will print verbose messages. If not specified internal one is used.

## **Parameters:**

pointer to function which prints information.

#### **5.34.3.12** bool Arc::DataSpeed::transfer (unsigned long long int n = 0)

Inform object, about amount of data has been transfered. All errors are triggered by this method. To make them work application must call this method periodically even with zero value.

#### **Parameters:**

**n** amount of data transfered (bytes).

#### **5.34.3.13** unsigned long long int Arc::DataSpeed::transfered\_size (void) [inline]

Returns amount of data this object knows about.

### 5.34.3.14 bool Arc::DataSpeed::verbose (void)

Check if speed information is going to be printed.

## 5.34.3.15 void Arc::DataSpeed::verbose (const std::string & prefix)

Print information about current speed and amout of data.

#### **Parameters:**

'prefix' add this string at the beginning of every string.

## 5.34.3.16 void Arc::DataSpeed::verbose (bool val)

Activate printing information about current time speeds, amount of transfered data.


The documentation for this class was generated from the following file:

• DataSpeed.h

## 5.35 ArcSec::DateTimeAttribute Class Reference

#include <DateTimeAttribute.h>

Inheritance diagram for ArcSec::DateTimeAttribute::



#### **Public Member Functions**

- DateTimeAttribute (const std::string &v, const std::string &i)
- virtual bool equal (AttributeValue \*other)
- virtual bool lessthan (Attribute Value \*other)
- virtual bool **inrange** (AttributeValue \*other)
- virtual std::string encode ()
- Arc::Time getValue ()
- virtual std::string getType ()
- virtual std::string getId ()

## **Static Public Member Functions**

• static const std::string & getIdentifier (void)

## **5.35.1** Detailed Description

Format: YYYYMMDDHHMMSSZ Day Month DD HH:MM:SS YYYY YYYY-MM-DD HH:MM:SS YYYY-MM-DDTHH:MM:SS+HH:MM YYYY-MM-DDTHH:MM:SSZ

#### **5.35.2** Member Function Documentation

#### **5.35.2.1 virtual std::string ArcSec::DateTimeAttribute::encode ()** [virtual]

encode the value in a string format

Implements ArcSec::AttributeValue.

## **5.35.2.2 virtual bool ArcSec::DateTimeAttribute::equal (AttributeValue** \* *other*) [virtual]

Evluate whether "this" equale to the parameter value

Implements ArcSec::AttributeValue.

## **5.35.2.3 virtual std::string ArcSec::DateTimeAttribute::getId ()** [inline, virtual]

Get the identifier of the <Attribute>

Implements ArcSec::AttributeValue.

## **5.35.2.4 virtual std::string ArcSec::DateTimeAttribute::getType ()** [inline, virtual]

Get the type of the <Attribute>

Implements ArcSec::AttributeValue.


The documentation for this class was generated from the following file:

• DateTimeAttribute.h

## 5.36 Arc::DelegationConsumer Class Reference

#include <DelegationInterface.h>

Inheritance diagram for Arc::DelegationConsumer::



### **Public Member Functions**

- DelegationConsumer (void)
- DelegationConsumer (const std::string &content)
- operator bool (void)
- bool operator! (void)
- const std::string & ID (void)
- bool Backup (std::string &content)
- bool Restore (const std::string &content)
- bool Request (std::string &content)
- bool Acquire (std::string &content)
- bool Acquire (std::string &content, std::string &identity)

## **Protected Member Functions**

- bool Generate (void)
- void LogError (void)

### **Protected Attributes**

• void \* **key**\_

## 5.36.1 Detailed Description

A consumer of delegated X509 credentials. During delegation procedure this class acquires delegated credentials aka proxy - certificate, private key and chain of previous certificates. Delegation procedure consists of calling Request() method for generating certificate request followed by call to Acquire() method for making complete credentials from certificate chain.

#### 5.36.2 Constructor & Destructor Documentation

#### 5.36.2.1 Arc::DelegationConsumer::DelegationConsumer (void)

Creates object with new private key

#### 5.36.2.2 Arc::DelegationConsumer::DelegationConsumer (const std::string & content)

Creates object with provided private key

### **5.36.3** Member Function Documentation

## 5.36.3.1 bool Arc::DelegationConsumer::Acquire (std::string & content, std::string & identity)

Includes the functionality in Acquire(content); pluse extracting the credential identity

#### 5.36.3.2 bool Arc::DelegationConsumer::Acquire (std::string & content)

Ads private key into certificates chain in 'content' On exit content contains complete delegated credentials.

#### 5.36.3.3 bool Arc::DelegationConsumer::Backup (std::string & content)

Stores content of this object into a string

#### **5.36.3.4 bool Arc::DelegationConsumer::Generate (void)** [protected]

Private key

## 5.36.3.5 const std::string& Arc::DelegationConsumer::ID (void)

Return identifier of this object - not implemented

### **5.36.3.6 void Arc::DelegationConsumer::LogError (void)** [protected]

Creates private key

#### 5.36.3.7 bool Arc::DelegationConsumer::Request (std::string & content)

Make X509 certificate request from internal private key

#### 5.36.3.8 bool Arc::DelegationConsumer::Restore (const std::string & content)

Restores content of object from string


The documentation for this class was generated from the following file:

• DelegationInterface.h

## 5.37 Arc::DelegationConsumerSOAP Class Reference

#include <DelegationInterface.h>

Inheritance diagram for Arc::DelegationConsumerSOAP::



#### **Public Member Functions**

- DelegationConsumerSOAP (void)
- DelegationConsumerSOAP (const std::string &content)
- bool DelegateCredentialsInit (const std::string &id, const SOAPEnvelope &in, SOAPEnvelope &out)
- bool UpdateCredentials (std::string &credentials, const SOAPEnvelope &in, SOAPEnvelope &out)
- bool UpdateCredentials (std::string &credentials, std::string &identity, const SOAPEnvelope &in, SOAPEnvelope &out)
- bool DelegatedToken (std::string &credentials, const XMLNode &token)
- bool **DelegatedToken** (std::string &credentials, std::string &identity, const XMLNode &token)

## **5.37.1 Detailed Description**

This class extends DelegationConsumer to support SOAP message exchange. Implements WS interface http://www.nordugrid.org/schemas/delegation described in delegation.wsdl.

#### 5.37.2 Constructor & Destructor Documentation

### 5.37.2.1 Arc::DelegationConsumerSOAP::DelegationConsumerSOAP (void)

Creates object with new private key

## 5.37.2.2 Arc::DelegationConsumerSOAP::DelegationConsumerSOAP (const std::string & content)

Creates object with specified private key

### 5.37.3 Member Function Documentation

# 5.37.3.1 bool Arc::DelegationConsumerSOAP::DelegateCredentialsInit (const std::string & id, const SOAPEnvelope & in, SOAPEnvelope & out)

Process SOAP message which starts delagation. Generated message in 'out' is meant to be sent back to DelagationProviderSOAP. Argument 'id' contains identifier of procedure and is used only to produce SOAP message.

## 5.37.3.2 bool Arc::DelegationConsumerSOAP::DelegatedToken (std::string & credentials, const XMLNode & token)

Similar to UpdateCredentials but takes only DelegatedToken XML element

# 5.37.3.3 bool Arc::DelegationConsumerSOAP::UpdateCredentials (std::string & credentials, std::string & identity, const SOAPEnvelope & in, SOAPEnvelope & out)

Includes the functionality in above UpdateCredentials method; plus extracting the credential identity

# 5.37.3.4 bool Arc::DelegationConsumerSOAP::UpdateCredentials (std::string & credentials, const SOAPEnvelope & in, SOAPEnvelope & out)

Accepts delegated credentials. Process 'in' SOAP message and stores full proxy credentials in 'credentials'. 'out' message is genarated for sending to DelagationProviderSOAP.

The documentation for this class was generated from the following file:

• DelegationInterface.h

## 5.38 Arc::DelegationContainerSOAP Class Reference

#include <DelegationInterface.h>

#### **Public Member Functions**

- bool DelegateCredentialsInit (const SOAPEnvelope &in, SOAPEnvelope &out)
- bool UpdateCredentials (std::string &credentials, const SOAPEnvelope &in, SOAPEnvelope &out)
- bool **UpdateCredentials** (std::string &credentials, std::string &identity, const SOAPEnvelope &in, SOAPEnvelope &out)
- bool DelegatedToken (std::string &credentials, const XMLNode &token)
- bool **DelegatedToken** (std::string &credentials, std::string &identity, const XMLNode &token)

#### **Protected Attributes**

- Glib::Mutex lock
- int max\_size\_
- int max\_duration\_
- int max\_usage\_
- bool context\_lock\_
- bool restricted

#### **5.38.1** Detailed Description

Manages multiple delegated credentials. Delegation consumers are created automatically with Delegate-CredentialsInit method up to max\_size\_ and assigned unique identifier. It's methods are similar to those of DelegationConsumerSOAP with identifier included in SOAP message used to route execution to one of managed DelegationConsumerSOAP instances.

### **5.38.2** Member Function Documentation

5.38.2.1 bool Arc::DelegationContainerSOAP::DelegateCredentialsInit (const SOAPEnvelope & in, SOAPEnvelope & out)

See DelegationConsumerSOAP::DelegateCredentialsInit

5.38.2.2 bool Arc::DelegationContainerSOAP::DelegatedToken (std::string & credentials, const XMLNode & token)

See DelegationConsumerSOAP::DelegatedToken

5.38.2.3 bool Arc::DelegationContainerSOAP::UpdateCredentials (std::string & credentials, const SOAPEnvelope & in, SOAPEnvelope & out)

See DelegationConsumerSOAP::UpdateCredentials

## 5.38.3 Member Data Documentation

## **5.38.3.1 bool Arc::DelegationContainerSOAP::context\_lock\_** [protected]

If true delegation consumer is deleted when connection context is destroyed

## **5.38.3.2** int Arc::DelegationContainerSOAP::max\_duration\_ [protected]

Lifetime of unused delegation consumer

## **5.38.3.3** int Arc::DelegationContainerSOAP::max\_size\_ [protected]

Max. number of delegation consumers

#### **5.38.3.4** int Arc::DelegationContainerSOAP::max\_usage\_ [protected]

Max. times same delegation consumer may accept credentials

#### **5.38.3.5 bool Arc::DelegationContainerSOAP::restricted** [protected]

If true all delegation phases must be performed by same identity


The documentation for this class was generated from the following file:

• DelegationInterface.h

## 5.39 Arc::DelegationProvider Class Reference

#include <DelegationInterface.h>

Inheritance diagram for Arc::DelegationProvider::



#### **Public Member Functions**

- DelegationProvider (const std::string &credentials)
- DelegationProvider (const std::string &cert\_file, const std::string &key\_file, std::istream \*inpwd=NULL)
- operator bool (void)
- bool **operator!** (void)
- std::string Delegate (const std::string &request, const DelegationRestrictions &restrictions=DelegationRestrictions())

## **5.39.1 Detailed Description**

A provider of delegated credentials. During delegation procedure this class generates new credential to be used in proxy/delegated credential.

### 5.39.2 Constructor & Destructor Documentation

#### 5.39.2.1 Arc::DelegationProvider::DelegationProvider (const std::string & credentials)

Creates instance from provided credentials. Credentials are used to sign delegated credentials. Arguments should contain PEM-encoded certificate, private key and optionally certificates chain.

# 5.39.2.2 Arc::DelegationProvider::DelegationProvider (const std::string & cert\_file, const std::string & key\_file, std::istream \* inpwd = NULL)

Creates instance from provided credentials. Credentials are used to sign delegated credentials. Arguments should contain filesystem path to PEM-encoded certificate and private key. Optionally cert\_file may contain certificates chain.

#### **5.39.3** Member Function Documentation

# 5.39.3.1 std::string Arc::DelegationProvider::Delegate (const std::string & request, const DelegationRestrictions & restrictions = DelegationRestrictions())

Perform delegation. Takes X509 certificate request and creates proxy credentials excluding private key. Result is then to be fed into DelegationConsumer::Acquire

The documentation for this class was generated from the following file:


131

• DelegationInterface.h

## 5.40 Arc::DelegationProviderSOAP Class Reference

#include <DelegationInterface.h>

Inheritance diagram for Arc::DelegationProviderSOAP::



## **Public Member Functions**

- DelegationProviderSOAP (const std::string &credentials)
- DelegationProviderSOAP (const std::string &cert\_file, const std::string &key\_file, std::istream \*inpwd=NULL)
- bool DelegateCredentialsInit (MCCInterface &mcc\_interface, MessageContext \*context)
- bool DelegateCredentialsInit (MCCInterface &mcc\_interface, MessageAttributes \*attributes\_in, MessageAttributes \*attributes\_out, MessageContext \*context)
- bool UpdateCredentials (MCCInterface &mcc\_interface, MessageContext \*context, const DelegationRestrictions &restrictions=DelegationRestrictions())
- bool UpdateCredentials (MCCInterface &mcc\_interface, MessageAttributes \*attributes\_in, MessageAttributes \*attributes\_out, MessageContext \*context, const DelegationRestrictions &restrictions=DelegationRestrictions())
- bool DelegatedToken (XMLNode &parent)
- const std::string & ID (void)

#### **Protected Attributes**

- std::string request\_
- std::string id\_

## **5.40.1 Detailed Description**

Extension of DelegationProvider with SOAP exchange interface. This class is also a temporary container for intermediate information used during delegation procedure.

#### 5.40.2 Constructor & Destructor Documentation

# 5.40.2.1 Arc::DelegationProviderSOAP::DelegationProviderSOAP (const std::string & credentials)

Creates instance from provided credentials. Credentials are used to sign delegated credentials.

## 5.40.2.2 Arc::DelegationProviderSOAP::DelegationProviderSOAP (const std::string & cert\_file, const std::string & key\_file, std::istream \* inpwd = NULL)

Creates instance from provided credentials. Credentials are used to sign delegated credentials. Arguments should contain filesystem path to PEM-encoded certificate and private key. Optionally cert\_file may contain certificates chain.

#### **5.40.3** Member Function Documentation

5.40.3.1 bool Arc::DelegationProviderSOAP::DelegateCredentialsInit (MCCInterface & mcc\_interface, MessageAttributes \* attributes\_in, MessageAttributes \* attributes\_out, MessageContext \* context)

Extended version of DelegateCredentialsInit(MCCInterface&,MessageContext\*). Additionally takes attributes for request and response message to make fine control on message processing possible.

5.40.3.2 bool Arc::DelegationProviderSOAP::DelegateCredentialsInit (MCCInterface & mcc\_interface, MessageContext \* context)

Performs DelegateCredentialsInit SOAP operation. As result request for delegated credentials is received by this instance and stored internally. Call to UpdateCredentials should follow.

#### 5.40.3.3 bool Arc::DelegationProviderSOAP::DelegatedToken (XMLNode & parent)

Generates DelegatedToken element. Element is created as child of provided XML element and contains structure described in delegation.wsdl.

#### 5.40.3.4 const std::string& Arc::DelegationProviderSOAP::ID (void) [inline]

Returns the identifier by service accepting delegated credentials. This identifier may then be used to refer to credentials stored at service.

5.40.3.5 bool Arc::DelegationProviderSOAP::UpdateCredentials (MCCInterface & mcc\_interface, MessageAttributes \* attributes\_in, MessageAttributes \* attributes\_out, MessageContext \* context, const DelegationRestrictions & restrictions = DelegationRestrictions())

Extended version of UpdateCredentials(MCCInterface&,MessageContext\*). Additionally takes attributes for request and response message to make fine control on message processing possible.

5.40.3.6 bool Arc::DelegationProviderSOAP::UpdateCredentials (MCCInterface & mcc\_interface, MessageContext \* context, const DelegationRestrictions & restrictions = DelegationRestrictions())

Performs UpdateCredentials SOAP operation. This concludes delegation procedure and passes delagated credentials to DelegationConsumerSOAP instance.

The documentation for this class was generated from the following file:


· DelegationInterface.h

## 5.41 ArcSec::DenyOverridesCombiningAlg Class Reference

Implement the "Deny-Overrides" algorithm.

#include <DenyOverridesAlg.h>

Inheritance diagram for ArcSec::DenyOverridesCombiningAlg::



#### **Public Member Functions**

- virtual Result combine (EvaluationCtx \*ctx, std::list< Policy \* > policies)
- virtual const std::string & getalgId (void) const

## 5.41.1 Detailed Description

Implement the "Deny-Overrides" algorithm.

Deny-Overrides, scans the policy set which is given as the parameters of "combine" method, if gets "deny" result from any policy, then stops scanning and gives "deny" as result, otherwise gives "permit".

## **5.41.2** Member Function Documentation

```
5.41.2.1 virtual Result ArcSec::DenyOverridesCombiningAlg::combine (EvaluationCtx * ctx, std::list< Policy * > policies) [virtual]
```

If there is one policy which return negative evaluation result, then omit the other policies and return DECISION DENY

#### **Parameters:**

ctx This object contains request information which will be used to evaluated against policy.policlies This is a container which contains policy objects.

### **Returns:**

The combined result according to the algorithm.

Implements ArcSec::CombiningAlg.

## 5.41.2.2 virtual const std::string& ArcSec::DenyOverridesCombiningAlg::getalgId (void) const [inline, virtual]

Get the identifier

Implements ArcSec::CombiningAlg.

The documentation for this class was generated from the following file:

| 5.41 ArcSec::DenyOverridesCombiningAlg | Class Reference |
|--|-----------------|
|  |                 |


135

• DenyOverridesAlg.h

## 5.42 ArcSec::DurationAttribute Class Reference

#include <DateTimeAttribute.h>

Inheritance diagram for ArcSec::DurationAttribute::



#### **Public Member Functions**

- DurationAttribute (const std::string &v, const std::string &i)
- virtual bool equal (AttributeValue \*other)
- virtual std::string encode ()
- Arc::Period getValue ()
- virtual std::string getType ()
- virtual std::string getId ()

#### **Static Public Member Functions**

• static const std::string & getIdentifier (void)

## **5.42.1 Detailed Description**

Formate: P??Y??M??DT??H??M??S

## **5.42.2** Member Function Documentation

## **5.42.2.1 virtual std::string ArcSec::DurationAttribute::encode ()** [virtual]

encode the value in a string format

Implements ArcSec::AttributeValue.

## **5.42.2.2 virtual bool ArcSec::DurationAttribute::equal (AttributeValue** \* other) [virtual]

Evluate whether "this" equale to the parameter value

Implements ArcSec::AttributeValue.

### **5.42.2.3 virtual std::string ArcSec::DurationAttribute::getId ()** [inline, virtual]

Get the identifier of the <Attribute>

Implements ArcSec::AttributeValue.

# **5.42.2.4 virtual std::string ArcSec::DurationAttribute::getType ()** [inline, virtual]

Get the type of the <Attribute>

Implements ArcSec::AttributeValue.

The documentation for this class was generated from the following file:


• DateTimeAttribute.h

# 5.43 ArcSec::EqualFunction Class Reference

Evaluate whether the two values are equal.

#include <EqualFunction.h>

Inheritance diagram for ArcSec::EqualFunction::



### **Public Member Functions**

- EqualFunction (std::string functionName, std::string argumentType)
- virtual bool evaluate (AttributeValue \*arg0, AttributeValue \*arg1)

### **Static Public Member Functions**

• static std::string getFunctionName (std::string datatype)

# 5.43.1 Detailed Description

Evaluate whether the two values are equal.

### **5.43.2** Member Function Documentation

# **5.43.2.1** virtual bool ArcSec::EqualFunction::evaluate (AttributeValue \* arg0, AttributeValue \* arg1) [virtual]

Evaluate two Attribute Value objects

Implements ArcSec::Function.

# 5.43.2.2 static std::string ArcSec::EqualFunction::getFunctionName (std::string datatype) [static]

help function to get the FunctionName

The documentation for this class was generated from the following file:

• EqualFunction.h

# 5.44 ArcSec::EvalResult Struct Reference

Struct to record the xml node and effect, which will be used by Evaluator to get the information about which rule/policy(in xmlnode) is satisfied.

#include <Result.h>

### **Public Attributes**

Arc::XMLNode nodestd::string effect

# **5.44.1** Detailed Description

Struct to record the xml node and effect, which will be used by Evaluator to get the information about which rule/policy(in xmlnode) is satisfied.

The documentation for this struct was generated from the following file:

• Result.h

# 5.45 ArcSec::EvaluationCtx Class Reference

EvaluationCtx, in charge of storing some context information for evaluation, including Request, current time, etc.

#include < EvaluationCtx.h >

#### **Public Member Functions**

- EvaluationCtx (Request \*request)
- virtual Request \* getRequest () const
- virtual void **setRequestItem** (RequestItem \*reqit)
- virtual RequestItem \* getRequestItem () const
- virtual void split ()
- virtual std::list< RequestTuple \* > getRequestTuples () const
- virtual void **setEvalTuple** (RequestTuple \*tuple)
- virtual RequestTuple \* getEvalTuple () const

### 5.45.1 Detailed Description

EvaluationCtx, in charge of storing some context information for evaluation, including Request, current time, etc.

### 5.45.2 Constructor & Destructor Documentation

## 5.45.2.1 ArcSec::EvaluationCtx::EvaluationCtx (Request \* request)

Construct a new EvaluationCtx based on the given request

### **5.45.3** Member Function Documentation

### **5.45.3.1 virtual void ArcSec::EvaluationCtx::split()** [virtual]

Convert/split one RequestItem (one tuple <SubList, ResList, ActList, CtxList>) into a few <Subject, Resource, Action, Context> tuples. The purpose is for evaluation. The evaluator will evaluate each RequestTuple one by one, not the RequestItem because it includes some independent <Subject, Resource, Action, Context>s and the evaluator should deal with them independently.

The documentation for this class was generated from the following file:


• EvaluationCtx.h

# 5.46 ArcSec::Evaluator Class Reference

Interface for policy evaluation. Execute the policy evaluation, based on the request and policy.

#include <Evaluator.h>

Inheritance diagram for ArcSec::Evaluator::



### **Public Member Functions**

- Evaluator (Arc::XMLNode \*)
- Evaluator (const char \*)
- virtual Response \* evaluate (Request \*request)=0
- virtual Response \* evaluate (const Source &request)=0
- virtual Response \* evaluate (Request \*request, const Source &policy)=0
- virtual Response \* evaluate (const Source & request, const Source & policy)=0
- virtual Response \* evaluate (Request \*request, Policy \*policyobj)=0
- virtual Response \* evaluate (const Source & request, Policy \*policyobj)=0
- virtual AttributeFactory \* getAttrFactory ()=0
- virtual FnFactory \* getFnFactory ()=0
- virtual AlgFactory \* getAlgFactory ()=0
- virtual void addPolicy (const Source &policy, const std::string &id="")=0
- virtual void addPolicy (Policy \*policy, const std::string &id="")=0
- virtual void setCombiningAlg (EvaluatorCombiningAlg alg)=0
- virtual void setCombiningAlg (CombiningAlg \*alg=NULL)=0
- virtual const char \* getName (void) const =0

### **Protected Member Functions**

• virtual Response \* evaluate (EvaluationCtx \*ctx)=0

### **Static Protected Attributes**

• static Arc::Logger logger

## **5.46.1** Detailed Description

Interface for policy evaluation. Execute the policy evaluation, based on the request and policy.

### **5.46.2** Member Function Documentation

# **5.46.2.1 virtual void ArcSec::Evaluator::addPolicy (Policy \*** *policy***, const std::string &** *id* = "") [pure virtual]

Add policy to the evaluator. Policy will be marked with id. The policy object is taken over by this instance and will be destroyed in destructor.

# 5.46.2.2 virtual void ArcSec::Evaluator::addPolicy (const Source & policy, const std::string & id = "") [pure virtual]

Add policy from specified source to the evaluator. Policy will be marked with id.

```
5.46.2.3 virtual Response* ArcSec::Evaluator::evaluate (EvaluationCtx * ctx) [protected, pure virtual]
```

Evaluate the request by using the EvaluationCtx object (which includes the information about request). The ctx is destroyed inside this method (why?!?!?).

```
5.46.2.4 virtual Response* ArcSec::Evaluator::evaluate (const Source & request, Policy * policyobj) [pure virtual]
```

Evaluate the request from specified source against the specified policy. In some implementations all of the existing policie inside the evaluator may be destroyed by this method.

```
5.46.2.5 virtual Response* ArcSec::Evaluator::evaluate (Request * request, Policy * policyobj) [pure virtual]
```

Evaluate the specified request against the specified policy. In some implementations all of the existing policy inside the evaluator may be destroyed by this method.

```
5.46.2.6 virtual Response* ArcSec::Evaluator::evaluate (const Source & request, const Source & policy) [pure virtual]
```

Evaluate the request from specified source against the policy from specified source. In some implementations all of the existing policie inside the evaluator may be destroyed by this method.

```
5.46.2.7 virtual Response* ArcSec::Evaluator::evaluate (Request * request, const Source & policy) [pure virtual]
```

Evaluate the specified request against the policy from specified source. In some implementations all of the existing policies inside the evaluator may be destroyed by this method.

```
5.46.2.8 virtual Response* ArcSec::Evaluator::evaluate (const Source & request) [pure virtual]
```

Evaluates the request by using a specified source

**5.46.2.9 virtual Response\*** ArcSec::Evaluator::evaluate (Request \* request) [pure virtual]

Evaluates the request by using a Request object. Evaluation is done till at least one of policies is satisfied.

**5.46.2.10 virtual AlgFactory\* ArcSec::Evaluator::getAlgFactory ()** [pure virtual]

Get the AlgFactory object

**5.46.2.11** virtual AttributeFactory\* ArcSec::Evaluator::getAttrFactory () [pure virtual]

Get the AttributeFactory object

**5.46.2.12 virtual FnFactory\*** ArcSec::Evaluator::getFnFactory() [pure virtual]

Get the FnFactory object

**5.46.2.13 virtual const char\* ArcSec::Evaluator::getName (void) const** [pure virtual]

Get the name of this evaluator

**5.46.2.14 virtual void ArcSec::Evaluator::setCombiningAlg (CombiningAlg \*** *alg* = NULL) [pure virtual]

Specifies loadable combining algorithms. In case of multiple policies their results will be combined using this algorithm. To switch to simple algorithm specify NULL argument.

**5.46.2.15 virtual void ArcSec::Evaluator::setCombiningAlg (EvaluatorCombiningAlg** *alg***)** [pure virtual]

Specifies one of simple combining algorithms. In case of multiple policies their results will be combined using this algorithm.

The documentation for this class was generated from the following file:

• Evaluator.h

# 5.47 ArcSec::EvaluatorContext Class Reference

Context for evaluator. It includes the factories which will be used to create related objects.

```
#include <Evaluator.h>
```

### **Public Member Functions**

- EvaluatorContext (Evaluator \*evaluator)
- operator AttributeFactory \* ()
- operator FnFactory \* ()
- operator AlgFactory \* ()

# 5.47.1 Detailed Description

Context for evaluator. It includes the factories which will be used to create related objects.

### 5.47.2 Member Function Documentation

### **5.47.2.1** ArcSec::EvaluatorContext::operator AlgFactory \* () [inline]

Returns associated AlgFactory object

### **5.47.2.2** ArcSec::EvaluatorContext::operator AttributeFactory \* () [inline]

Returns associated AttributeFactory object

### **5.47.2.3** ArcSec::EvaluatorContext::operator FnFactory \* () [inline]

Returns associated FnFactory object

The documentation for this class was generated from the following file:

• Evaluator.h

## 5.48 ArcSec::EvaluatorLoader Class Reference

EvaluatorLoader is implemented as a helper class for loading different Evaluator objects, like ArcEvaluator.

#include <EvaluatorLoader.h>

### **Public Member Functions**

- Evaluator \* getEvaluator (const std::string &classname)
- Evaluator \* getEvaluator (const Policy \*policy)
- Evaluator \* getEvaluator (const Request \*request)
- Request \* getRequest (const std::string &classname, const Source &requestsource)
- Request \* getRequest (const Source &requestsource)
- Policy \* getPolicy (const std::string &classname, const Source &policysource)
- Policy \* getPolicy (const Source &policysource)

#### **Static Protected Attributes**

• static Arc::Logger logger

### 5.48.1 Detailed Description

Evaluator Loader is implemented as a helper class for loading different Evaluator objects, like ArcEvaluator.

The object loading is based on the configuration information about evaluator, including information for factory class, request, policy and evaluator itself

### **5.48.2** Member Function Documentation

# 5.48.2.1 Evaluator\* ArcSec::EvaluatorLoader::getEvaluator (const Request \* request)

Get evaluator object suitable for presented request

### 5.48.2.2 Evaluator\* ArcSec::EvaluatorLoader::getEvaluator (const Policy \* policy)

Get evaluator object suitable for presented policy

## 5.48.2.3 Evaluator\* ArcSec::EvaluatorLoader::getEvaluator (const std::string & classname)

Get evaluator object according to the class name

# 5.48.2.4 Policy\* ArcSec::EvaluatorLoader::getPolicy (const Source & policysource)

Get proper policy object according to the policy source

# 5.48.2.5 Policy\* ArcSec::EvaluatorLoader::getPolicy (const std::string & classname, const Source & policysource)

Get policy object according to the class name, based on the policy source

# 5.48.2.6 Request\* ArcSec::EvaluatorLoader::getRequest (const Source & requestsource)

Get request object according to the request source

# 5.48.2.7 Request\* ArcSec::EvaluatorLoader::getRequest (const std::string & classname, const Source & requestsource)

Get request object according to the class name, based on the request source

The documentation for this class was generated from the following file:

• EvaluatorLoader.h

# 5.49 Arc::ExpirationReminder Class Reference

A class intended for internal use within counters.

#include <Counter.h>

### **Public Member Functions**

- bool operator< (const ExpirationReminder &other) const
- Glib::TimeVal getExpiryTime () const
- Counter::IDType getReservationID () const

### **Friends**

· class Counter

# 5.49.1 Detailed Description

A class intended for internal use within counters.

This class is used for "reminder objects" that are used for automatic deallocation of self-expiring reservations.

### **5.49.2** Member Function Documentation

### 5.49.2.1 Glib::TimeVal Arc::ExpirationReminder::getExpiryTime () const

Returns the expiry time.

This method returns the expiry time of the reservation that this ExpirationReminder is associated with.

## **Returns:**

The expiry time.

### 5.49.2.2 Counter::IDType Arc::ExpirationReminder::getReservationID () const

Returns the identification number of the reservation.

This method returns the identification number of the self-expiring reservation that this ExpirationReminder is associated with.

#### **Returns:**

The identification number.

### 5.49.2.3 bool Arc::ExpirationReminder::operator< (const ExpirationReminder & other) const

Less than operator, compares "soonness".

This is the less than operator for the ExpirationReminder class. It compares the priority of such objects with respect to which reservation expires first. It is used when reminder objects are inserted in a priority queue in order to allways place the next reservation to expire at the top.

# **5.49.3** Friends And Related Function Documentation

# **5.49.3.1 friend class Counter** [friend]

The Counter class needs to be a friend.

The documentation for this class was generated from the following file:

• Counter.h

# 5.50 Arc::FileCache Class Reference

#include <FileCache.h>

### **Public Member Functions**

- FileCache (std::string cache\_path, std::string id, uid\_t job\_uid, gid\_t job\_gid)
- FileCache (std::vector< std::string > caches, std::string id, uid\_t job\_uid, gid\_t job\_gid)
- FileCache (const FileCache &cache)
- FileCache ()
- virtual ~FileCache (void)
- bool Start (std::string url, bool &available, bool &is\_locked)
- bool Stop (std::string url)
- bool StopAndDelete (std::string url)
- std::string File (std::string url)
- bool Link (std::string link\_path, std::string url)
- bool Copy (std::string dest\_path, std::string url, bool executable=false)
- bool Clean (unsigned long long int size=1)
- bool Release ()
- bool CheckCreated (std::string url)
- Time GetCreated (std::string url)
- bool CheckValid (std::string url)
- Time GetValid (std::string url)
- bool SetValid (std::string url, Time val)
- operator bool ()
- bool operator== (const FileCache &a)

### 5.50.1 Detailed Description

FileCache provides an interface to all cache operations to be used by external classes. An instance should be created per job, and all files within the job are managed by that instance. When it is decided a file should be downloaded to the cache, Start() should be called, so that the cache file can be prepared and locked. When a transfer has finished successfully, Link() or Copy() should be called to create a hard link to a per-job directory in the cache and then soft link, or copy the file directly to the session directory so it can be accessed from the user's job. Stop() must then be called to release any locks on the cache file.

The cache directory(ies) and the optional directory to link to when the soft-links are made are set in the global configuration file. The names of cache files are formed from a hash of the URL specified as input to the job. To ease the load on the file system, the cache files are split into subdirectories based on the first two characters in the hash. For example the file with hash 76f11edda169848038efbd9fa3df5693 is stored in 76/f11edda169848038efbd9fa3df5693. A cache filename can be found by passing the URL to Find(). For more information on the structure of the cache, see the Grid Manager Administration Guide.

A metadata file with the '.meta' suffix is stored next to each cache file. This contains the URL corresponding to the cache file and the expiry time, if it is available. For example lfc://lfc1.ndgf.org//grid/atlas/test/test/1 20081007151045Z

While cache files are downloaded, they are locked by creating a lock file with the '.lock' suffix next to the cache file. Calling Start() creates this lock and Stop() releases it. All processes calling Start() must wait until they successfully obtain the lock before downloading can begin.

### 5.50.2 Constructor & Destructor Documentation

# 5.50.2.1 Arc::FileCache::FileCache (std::string cache\_path, std::string id, uid\_t job\_uid, gid\_t job\_gid)

Create a new FileCache instance.

#### **Parameters:**

cache\_path The format is "cache\_dir[ link\_path]". path is the path to the cache directory and the optional link\_path is used to create a link in case the cache directory is visible under a different name during actual usage. When linking from the session dir this path is used instead of cache\_path.

id the job id. This is used to create the per-job dir which the job's cache files will be hard linked from job\_uid owner of job. The per-job dir will only be readable by this user job\_gid owner group of job

# 5.50.2.2 Arc::FileCache::FileCache (std::vector< std::string > caches, std::string id, uid\_t job\_uid, gid\_t job\_gid)

Create a new FileCache instance with multiple cache dirs

### **Parameters:**

caches a vector of strings describing caches. The format of each string is "cache\_dir[ link\_path]".
 id the job id. This is used to create the per-job dir which the job's cache files will be hard linked from job\_uid owner of job. The per-job dir will only be readable by this user job\_gid owner group of job

#### 5.50.2.3 Arc::FileCache::FileCache (const FileCache & cache)

Copy constructor

### **5.50.2.4** Arc::FileCache::FileCache() [inline]

Default constructor. Invalid cache.

### **5.50.2.5** virtual Arc::FileCache::~FileCache (void) [virtual]

Destructor

## **5.50.3** Member Function Documentation

### 5.50.3.1 bool Arc::FileCache::CheckCreated (std::string url)

Check if there is an information about creation time. Returns true if the file exists in the cache, since the creation time is the creation time of the cache file.

#### **Parameters:**

url the url corresponding to the cache file for which we want to know if the creation date exists

### 5.50.3.2 bool Arc::FileCache::CheckValid (std::string url)

Check if there is an information about expiry time.

#### **Parameters:**

url the url corresponding to the cache file for which we want to know if the expiration time exists

### **5.50.3.3** bool Arc::FileCache::Clean (unsigned long long int size = 1) [inline]

Remove some amount of oldest information from cache. Returns true on success. Not implemented.

#### **Parameters:**

size amount to be removed (bytes)

### 5.50.3.4 bool Arc::FileCache::Copy (std::string dest path, std::string url, bool executable = false)

Copy the cache file corresponding to url to the dest\_path

### 5.50.3.5 std::string Arc::FileCache::File (std::string url)

Returns the full pathname of the file in the cache which corresponds to the given url.

### 5.50.3.6 Time Arc::FileCache::GetCreated (std::string url)

Get the creation time of a cached file. If the cache file does not exist, 0 is returned.

#### Parameters:

url the url corresponding to the cache file for which we want to know the creation date

### 5.50.3.7 Time Arc::FileCache::GetValid (std::string url)

Get expiry time of a cached file. If the time is not available, a time equivalent to 0 is returned.

### Parameters:

url the url corresponding to the cache file for which we want to know the expiry time

### 5.50.3.8 bool Arc::FileCache::Link (std::string link\_path, std::string url)

Create a hard-link to the per-job dir from the cache dir, and then a soft-link from here to the session directory. This is effectively 'claiming' the file for the job, so even if the original cache file is deleted, eg by some external process, the hard link still exists until it is explicitly released by calling Release().

If cache\_link\_path is set to "." then files will be copied directly to the session directory rather than via the hard link.

### **Parameters:**

link\_path path to the session dir for soft-link or new fileurl url of file to link to or copy

### **5.50.3.9** Arc::FileCache::operator bool (void) [inline]

Returns true if object is useable.

### 5.50.3.10 bool Arc::FileCache::operator== (const FileCache & a)

Return true if all attributes are equal

### 5.50.3.11 bool Arc::FileCache::Release ()

Release claims on input files for the job specified by id. For each cache directory the per-job directory with the hard-links will be deleted.

### 5.50.3.12 bool Arc::FileCache::SetValid (std::string url, Time val)

Set expiry time.

### **Parameters:**

url the url corresponding to the cache file for which we want to set the expiry timeval expiry time

## 5.50.3.13 bool Arc::FileCache::Start (std::string url, bool & available, bool & is\_locked)

Prepare cache for downloading file, and lock the cached file. On success returns true. If there is another process downloading the same url, false is returned and is\_locked is set to true. In this case the client should wait and retry later. If the lock has expired this process will take over the lock and the method will return as if no lock was present, ie available and is\_locked are false.

### **Parameters:**

```
url url that is being downloadedavailable true on exit if the file is already in cacheis_locked true on exit if the file is already locked, ie cannot be used by this process
```

### 5.50.3.14 bool Arc::FileCache::Stop (std::string url)

This method (or stopAndDelete) must be called after file was downloaded or download failed, to release the lock on the cache file. Stop() does not delete the cache file. It returns false if the lock file does not exist, or another pid was found inside the lock file (this means another process took over the lock so this process must go back to Start()), or if it fails to delete the lock file.

#### **Parameters:**

url the url of the file that was downloaded

## 5.50.3.15 bool Arc::FileCache::StopAndDelete (std::string url)

Release the cache file and delete it, because for example a failed download left an incomplete copy, or it has expired. This method also deletes the meta file which contains the url corresponding to the cache file. The logic of the return value is the same as Stop().

## **Parameters:**

url the url corresponding to the cache file that has to be released and deleted

The documentation for this class was generated from the following file:

· FileCache.h

# 5.51 FileCacheHash Class Reference

#include <FileCacheHash.h>

# **Static Public Member Functions**

- static std::string getHash (std::string url)
- static int maxLength ()

# 5.51.1 Detailed Description

FileCacheHash provides methods to make hashes from strings. Currently the md5 hash from the openssl library is used.

## **5.51.2** Member Function Documentation

## **5.51.2.1 static std::string FileCacheHash::getHash (std::string** *url***)** [static]

Return a hash of the given URL, according to the current hash scheme.

## **5.51.2.2 static int FileCacheHash::maxLength ()** [inline, static]

Return the maximum length of a hash string.

The documentation for this class was generated from the following file:

• FileCacheHash.h

# 5.52 Arc::FileInfo Class Reference

FileInfo stores information about files (metadata).

```
#include <FileInfo.h>
```

## **Public Types**

- file\_type\_unknown = 0
- file\_type\_file = 1
- file\_type\_dir = 2
- enum Type { file\_type\_unknown = 0, file\_type\_file = 1, file\_type\_dir = 2 }

### **Public Member Functions**

- FileInfo (const std::string &name="")
- const std::string & GetName () const
- std::string GetLastName () const
- const std::list< URL > & GetURLs () const
- void AddURL (const URL &u)
- bool CheckSize () const
- unsigned long long int GetSize () const
- void **SetSize** (const unsigned long long int s)
- bool CheckCheckSum () const
- const std::string & GetCheckSum () const
- void **SetCheckSum** (const std::string &c)
- bool CheckCreated () const
- Time GetCreated () const
- void **SetCreated** (const Time &t)
- bool CheckValid () const
- Time GetValid () const
- void **SetValid** (const Time &t)
- bool CheckType () const
- Type GetType () const
- void **SetType** (const Type t)
- bool CheckLatency () const
- std::string GetLatency () const
- void **SetLatency** (const std::string l)

### **5.52.1 Detailed Description**

FileInfo stores information about files (metadata).

The documentation for this class was generated from the following file:


• FileInfo.h

# 5.53 ArcSec::FnFactory Class Reference

Interface for function factory class.

#include <FnFactory.h>

Inheritance diagram for ArcSec::FnFactory::



### **Public Member Functions**

• virtual Function \* createFn (const std::string &type)=0

### **Protected Attributes**

• FnMap fnmap

## 5.53.1 Detailed Description

Interface for function factory class.

FnFactory is in charge of creating Function object according to the algorithm type given as argument of method createFn. This class can be inherited for implementing a factory class which can create some specific Function objects.

## 5.53.2 Member Function Documentation

# **5.53.2.1 virtual Function\* ArcSec::FnFactory::createFn (const std::string &** *type***)** [pure virtual]

creat algorithm object based on the type algorithm type

### **Parameters:**

type The type of Function

### **Returns:**

The object of Function

The documentation for this class was generated from the following file:


• FnFactory.h

# 5.54 ArcSec::Function Class Reference

Interface for function, which is in charge of evaluating two AttributeValue.

#include <Function.h>

Inheritance diagram for ArcSec::Function::



### **Public Member Functions**

- Function (std::string, std::string)
- virtual bool evaluate (AttributeValue \*arg0, AttributeValue \*arg1)=0

# **5.54.1** Detailed Description

Interface for function, which is in charge of evaluating two AttributeValue.

### 5.54.2 Member Function Documentation

# **5.54.2.1** virtual bool ArcSec::Function::evaluate (AttributeValue \* arg0, AttributeValue \* arg1) [pure virtual]

Evaluate two Attribute Value objects

Implemented in ArcSec::EqualFunction, and ArcSec::MatchFunction.

The documentation for this class was generated from the following file:

• Function.h

# 5.55 Arc::InfoCache Class Reference

Stores XML document in filesystem split into parts.

#include <InfoCache.h>

### **Public Member Functions**

- bool Query (const char \*xml\_path, const char \*q, Arc::XMLNodeContainer &result)
- bool Query (const std::string &xml\_path, std::string &q, Arc::XMLNodeContainer &result)
- bool **Set** (const char \*xml\_path, Arc::XMLNode &value)
- bool **Set** (const std::string &xml\_path, Arc::XMLNode &value)
- bool Get (const char \*xml\_path, Arc::XMLNodeContainer &result)
- bool **Get** (const std::string &xml\_path, Arc::XMLNodeContainer &result)
- bool **Unset** (const char \*xml\_path)
- bool **Unset** (const std::string &xml path)
- InfoCache (const Arc::Config &cfg, const std::string &service id)

### **Protected Attributes**

• std::string path\_base

## 5.55.1 Detailed Description

Stores XML document in filesystem split into parts.

### 5.55.2 Constructor & Destructor Documentation

### 5.55.2.1 Arc::InfoCache::InfoCache (const Arc::Config & cfg, const std::string & service id)

Creates object according to configuration (see InfoCacheConfig.xsd).

XML configuration is passed in cfg. Argument service\_id is used to distiguish between various documents stored under same path - corresponding files will be stored in subdirectory with service\_id name.

The documentation for this class was generated from the following file:

• InfoCache.h

## 5.56 Arc::InfoFilter Class Reference

Filters information document according to identity of requestor.

#include <InfoFilter.h>

### **Public Member Functions**

- InfoFilter (MessageAuth &id)
- bool Filter (XMLNode doc) const
- bool Filter (XMLNode doc, const InfoFilterPolicies &policies, const Arc::NS &ns) const

# 5.56.1 Detailed Description

Filters information document according to identity of requestor.

Identity is compared to policies stored inside information document and external ones. Parts of document which do not pass policy evaluation are removed.

### 5.56.2 Constructor & Destructor Documentation

### 5.56.2.1 Arc::InfoFilter::InfoFilter (MessageAuth & id)

Creates object and associates identity.

Associated identity is not copied, hence passed argument must not be destroyed while this method is used.

### 5.56.3 Member Function Documentation

# 5.56.3.1 bool Arc::InfoFilter::Filter (XMLNode doc, const InfoFilterPolicies & policies, const Arc::NS & ns) const

Filter information document according to internal and external policies.

In provided document all policies and nodes which have their policies evaluated to negative result are removed. External policies are provided in policies argument. First element of every pair is XPath defining to which XML node policy must be applied. Second element is policy itself. Argument ns defines XML namespaces for XPath evaluation.

### 5.56.3.2 bool Arc::InfoFilter::Filter (XMLNode doc) const

Filter information document according to internal policies.

In provided document all policies and nodes which have their policies evaluated to negative result are removed.

The documentation for this class was generated from the following file:

• InfoFilter.h

# 5.57 Arc::InfoRegister Class Reference

Registration to ISIS interface.

#include <InfoRegister.h>

### **Public Member Functions**

- InfoRegister (XMLNode &node, Service \*service\_)
- operator bool (void)
- bool operator! (void)
- long int getPeriod (void) const
- Service \* getService (void)

### **Friends**

• class InfoRegisterContainer

## 5.57.1 Detailed Description

Registration to ISIS interface.

This class represents service registering to Information Indexing Service. It does not perform registration itself. It only collects configuration information. Configuration is as described in InfoRegisterConfig.xsd for element InfoRegistration.

The documentation for this class was generated from the following file:

# 5.58 Arc::InfoRegisterContainer Class Reference

#include <InfoRegister.h>

## **Public Member Functions**

- void addRegistrars (XMLNode doc)
- void addService (InfoRegister \*reg, const std::list< std::string > &ids, XMLNode cfg=XMLNode())
- void removeService (InfoRegister \*reg)

#### **Static Public Member Functions**

• static InfoRegisterContainer & Instance (void)

# **5.58.1 Detailed Description**

Singleton class for scanning configuration and storing refernces to registration elements.

### **5.58.2** Member Function Documentation

### 5.58.2.1 void Arc::InfoRegisterContainer::addRegistrars (XMLNode doc)

Adds ISISes to list of handled services.

Supplied configuration document is scanned for InfoRegistrar elements and those are turned into InfoRegistrar classes for handling connection to ISIS service each.

# 5.58.2.2 void Arc::InfoRegisterContainer::addService (InfoRegister \* reg, const std::list < std::string > & ids, XMLNode cfg = XMLNode())

Adds service to list of handled.

This method must be called first time after last addRegistrar was called - services will be only associated with ISISes which are already added. Argument ids contains list of ISIS identifiers to which service is associated. If ids is empty then service is associated to all ISISes currently added. If argument cfg is available and no ISISes are configured then addRegistrars is called with cfg used as configuration document.

### 5.58.2.3 void Arc::InfoRegisterContainer::removeService (InfoRegister \* reg)

This method must be called if service being destroyed.

The documentation for this class was generated from the following file:

# 5.59 Arc::InfoRegisters Class Reference

Handling multiple registrations to ISISes.

#include <InfoRegister.h>

### **Public Member Functions**

• InfoRegisters (XMLNode &cfg, Service \*service\_)

# **5.59.1** Detailed Description

Handling multiple registrations to ISISes.

### 5.59.2 Constructor & Destructor Documentation

## 5.59.2.1 Arc::InfoRegisters::InfoRegisters (XMLNode & cfg, Service \* service\_)

Constructor creates InfoRegister objects according to configuration.

Inside cfg elements InfoRegistration are found and for each corresponding InfoRegister object is created. Those objects are destroyed in destructor of this class.

The documentation for this class was generated from the following file:

# 5.60 Arc::InfoRegistrar Class Reference

Registration process associated with particular ISIS.

#include <InfoRegister.h>

### **Public Member Functions**

- operator bool (void)
- bool operator! (void)
- void registration (void)
- bool addService (InfoRegister \*)
- bool removeService (InfoRegister \*)
- const std::string & id (void)

### **Friends**

• class InfoRegisterContainer

# 5.60.1 Detailed Description

Registration process associated with particular ISIS.

Instance of this class starts thread which takes care passing information about associated services to ISIS service defined in configuration. Configuration is as described in InfoRegister.xsd for element InfoRegistrar.

### 5.60.2 Member Function Documentation

### 5.60.2.1 bool Arc::InfoRegistrar::addService (InfoRegister \*)

Adds new service to list of handled services.

Service is described by it's InfoRegister object which must be valid as long as this object is functional.

### 5.60.2.2 void Arc::InfoRegistrar::registration (void)

Performs registartion in a loop.

Never exists unless there is a critical error or requested by destructor.

## 5.60.2.3 bool Arc::InfoRegistrar::removeService (InfoRegister \*)

Removes service from list of handled services.


The documentation for this class was generated from the following file:

# 5.61 Arc::InformationContainer Class Reference

Information System document container and processor.

#include <InformationInterface.h>

Inheritance diagram for Arc::InformationContainer::



# **Public Member Functions**

- InformationContainer (XMLNode doc, bool copy=false)
- XMLNode Acquire (void)
- void Release (void)
- void Assign (XMLNode doc, bool copy=false)

### **Protected Member Functions**

- virtual void Get (const std::list< std::string > &path, XMLNodeContainer &result)
- virtual void Get (XMLNode xpath, XMLNodeContainer &result)

# **Protected Attributes**

XMLNode doc\_

### **5.61.1 Detailed Description**

Information System document container and processor.

This class inherits form InformationInterface and offers container for storing informational XML document.

## 5.61.2 Constructor & Destructor Documentation

5.61.2.1 Arc::InformationContainer::InformationContainer (XMLNode doc, bool copy = false)

Creates an instance with XML document. If is true this method makes a copy of for internal use.

### **5.61.3** Member Function Documentation

## 5.61.3.1 XMLNode Arc::InformationContainer::Acquire (void)

Get a lock on contained XML document. To be used in multi-threaded environment. Do not forget to release it with Release()

### **5.61.3.2 void Arc::InformationContainer::Assign (XMLNode** *doc*, **bool** *copy* = false)

Replaces internal XML document with . If is true this method makes a copy of for internal use.

# 5.61.3.3 virtual void Arc::InformationContainer::Get (const std::list< std::string > & path, XMLNodeContainer & result) [protected, virtual]

This method is called by this object's Process method. Real implementation of this class should return (sub)tree of XML document. This method may be called multiple times per single Process call. Here is a set on XML element names specifying how to reach requested node(s).

Reimplemented from Arc::InformationInterface.

## 5.61.4 Member Data Documentation

### **5.61.4.1 XMLNode Arc::InformationContainer::doc** [protected]

Either link or container of XML document

The documentation for this class was generated from the following file:


• InformationInterface.h

# 5.62 Arc::InformationInterface Class Reference

Information System message processor.

#include <InformationInterface.h>

Inheritance diagram for Arc::InformationInterface::



### **Public Member Functions**

- InformationInterface (bool safe=true)
- SOAPEnvelope \* **Process** (SOAPEnvelope &in)
- SOAPEnvelope \* **Process** (SOAPEnvelope &in, const InfoFilter &filter, const InfoFilterPolicies &policies=InfoFilterPolicies(), const NS &ns=NS())

### **Protected Member Functions**

- virtual void Get (const std::list< std::string > &path, XMLNodeContainer &result)
- virtual void Get (XMLNode xpath, XMLNodeContainer &result)

### **Protected Attributes**

- Glib::Mutex lock\_
- bool to\_lock\_

### **5.62.1 Detailed Description**

Information System message processor.

This class provides callback for 2 operations of WS-ResourceProperties and convenient parsing/generation of corresponding SOAP mesages. In a future it may extend range of supported specifications.

### 5.62.2 Constructor & Destructor Documentation

## **5.62.2.1** Arc::InformationInterface::InformationInterface (bool *safe* = true)

Constructor. If 'safe' is true all calls to Get will be locked.

### **5.62.3** Member Function Documentation

# 5.62.3.1 virtual void Arc::InformationInterface::Get (const std::list< std::string > & path, XMLNodeContainer & result) [protected, virtual]

This method is called by this object's Process method. Real implementation of this class should return (sub)tree of XML document. This method may be called multiple times per single Process call. Here is a set on XML element names specifying how to reach requested node(s).

Reimplemented in Arc::InformationContainer.

### **5.62.4** Member Data Documentation

### **5.62.4.1 Glib::Mutex Arc::InformationInterface::lock** [protected]

Mutex used to protect access to Get methods in multi-threaded env.

The documentation for this class was generated from the following file:

• InformationInterface.h

# 5.63 Arc::InformationRequest Class Reference

Request for information in InfoSystem.

#include <InformationInterface.h>

### **Public Member Functions**

- InformationRequest (void)
- InformationRequest (const std::list< std::string > &path)
- InformationRequest (const std::list< std::list< std::string > > &paths)
- InformationRequest (XMLNode query)
- operator bool (void)
- bool operator! (void)
- SOAPEnvelope \* SOAP (void)

### 5.63.1 Detailed Description

Request for information in InfoSystem.

This is a convenience wrapper creating proper WS-ResourceProperties request targeted InfoSystem interface of service.

## 5.63.2 Constructor & Destructor Documentation

### 5.63.2.1 Arc::InformationRequest::InformationRequest (void)

Dummy constructor

## 5.63.2.2 Arc::InformationRequest::InformationRequest (const std::list< std::string > & path)

Request for attribute specified by elements of path. Currently only first element is used.

# 5.63.2.3 Arc::InformationRequest::InformationRequest (const std::list< std::list< std::string > > & paths)

Request for attribute specified by elements of paths. Currently only first element of every path is used.

### 5.63.2.4 Arc::InformationRequest::InformationRequest (XMLNode query)

Request for attributes specified by XPath query.

### **5.63.3** Member Function Documentation

### 5.63.3.1 SOAPEnvelope\* Arc::InformationRequest::SOAP (void)

Returns generated SOAP message

The documentation for this class was generated from the following file:



169

• InformationInterface.h

# 5.64 Arc::InformationResponse Class Reference

Informational response from InfoSystem.

#include <InformationInterface.h>

### **Public Member Functions**

- InformationResponse (SOAPEnvelope &soap)
- operator bool (void)
- bool operator! (void)
- std::list< XMLNode > Result (void)

# 5.64.1 Detailed Description

Informational response from InfoSystem.

This is a convenience wrapper analyzing WS-ResourceProperties response from InfoSystem interface of service.

## 5.64.2 Constructor & Destructor Documentation

### 5.64.2.1 Arc::InformationResponse::InformationResponse (SOAPEnvelope & soap)

Constructor parses WS-ResourceProperties ressponse. Provided SOAPEnvelope object must be valid as long as this object is in use.

## **5.64.3** Member Function Documentation

### 5.64.3.1 std::list<XMLNode> Arc::InformationResponse::Result (void)

Returns set of attributes which were in SOAP message passed to constructor.

The documentation for this class was generated from the following file:


• InformationInterface.h

# 5.65 Arc::IntraProcessCounter Class Reference

A class for counters used by threads within a single process.

#include <IntraProcessCounter.h>

Inheritance diagram for Arc::IntraProcessCounter::



### **Public Member Functions**

- IntraProcessCounter (int limit, int excess)
- virtual ~IntraProcessCounter ()
- virtual int getLimit ()
- virtual int setLimit (int newLimit)
- virtual int changeLimit (int amount)
- virtual int getExcess ()
- virtual int setExcess (int newExcess)
- virtual int changeExcess (int amount)
- virtual int getValue ()
- virtual CounterTicket reserve (int amount=1, Glib::TimeVal duration=ETERNAL, bool prioritized=false, Glib::TimeVal timeOut=ETERNAL)

## **Protected Member Functions**

- virtual void cancel (IDType reservationID)
- virtual void extend (IDType &reservationID, Glib::TimeVal &expiryTime, Glib::TimeVal duration=ETERNAL)

## 5.65.1 Detailed Description

A class for counters used by threads within a single process.

This is a class for shared among different threads within a single process. See the Counter class for further information about counters and examples of usage.

### **5.65.2** Constructor & Destructor Documentation

### 5.65.2.1 Arc::IntraProcessCounter::IntraProcessCounter (int *limit*, int *excess*)

Creates an IntraProcessCounter with specified limit and excess.

This constructor creates a counter with the specified limit (amount of resources available for reservation) and excess limit (an extra amount of resources that may be used for prioritized reservations).

#### **Parameters:**

limit The limit of the counter.

excess The excess limit of the counter.

### **5.65.2.2 virtual Arc::IntraProcessCounter::**~IntraProcessCounter() [virtual]

Destructor.

This is the destructor of the IntraProcessCounter class. Does not need to do anything.

### **5.65.3** Member Function Documentation

# **5.65.3.1 virtual void Arc::IntraProcessCounter::cancel (IDType** *reservationID*) [protected, virtual]

Cancellation of a reservation.

This method cancels a reservation. It is called by the CounterTicket that corresponds to the reservation.

### **Parameters:**

reservationID The identity number (key) of the reservation to cancel.

## **5.65.3.2 virtual int Arc::IntraProcessCounter::changeExcess (int amount)** [virtual]

Changes the excess limit of the counter.

Changes the excess limit of the counter by adding a certain amount to the current excess limit.

#### **Parameters:**

amount The amount by which to change the excess limit.

### **Returns:**

The new excess limit.

Implements Arc::Counter.

### **5.65.3.3 virtual int Arc::IntraProcessCounter::changeLimit (int amount)** [virtual]

Changes the limit of the counter.

Changes the limit of the counter by adding a certain amount to the current limit.

### **Parameters:**

amount The amount by which to change the limit.

#### **Returns:**

The new limit.

Implements Arc::Counter.

## 5.65.3.4 virtual void Arc::IntraProcessCounter::extend (IDType & reservationID, Glib::TimeVal & expiryTime, Glib::TimeVal duration = ETERNAL) [protected, virtual]

Extension of a reservation.

This method extends a reservation. It is called by the CounterTicket that corresponds to the reservation.

#### **Parameters:**

**reservationID** Used for input as well as output. Contains the identification number of the original reservation on entry and the new identification number of the extended reservation on exit.

*expiryTime* Used for input as well as output. Contains the expiry time of the original reservation on entry and the new expiry time of the extended reservation on exit.

*duration* The time by which to extend the reservation. The new expiration time is computed based on the current time, NOT the previous expiration time.

#### **5.65.3.5** virtual int Arc::IntraProcessCounter::getExcess () [virtual]

Returns the excess limit of the counter.

Returns the excess limit of the counter, i.e. by how much the usual limit may be exceeded by prioritized reservations.

#### **Returns:**

The excess limit.

Implements Arc::Counter.

## **5.65.3.6 virtual int Arc::IntraProcessCounter::getLimit()** [virtual]

Returns the current limit of the counter.

This method returns the current limit of the counter, i.e. how many units can be reserved simultaneously by different threads without claiming high priority.

#### **Returns:**

The current limit of the counter.

Implements Arc::Counter.

#### **5.65.3.7 virtual int Arc::IntraProcessCounter::getValue** () [virtual]

Returns the current value of the counter.

Returns the current value of the counter, i.e. the number of unreserved units. Initially, the value is equal to the limit of the counter. When a reservation is made, the the value is decreased. Normally, the value should never be negative, but this may happen if there are prioritized reservations. It can also happen if the limit is decreased after some reservations have been made, since reservations are never revoked.

#### **Returns:**

The current value of the counter.

Implements Arc::Counter.

# 5.65.3.8 virtual CounterTicket Arc::IntraProcessCounter::reserve (int amount = 1, Glib::TimeVal duration = ETERNAL, bool prioritized = false, Glib::TimeVal timeOut = ETERNAL) [virtual]

Makes a reservation from the counter.

This method makes a reservation from the counter. If the current value of the counter is too low to allow for the reservation, the method blocks until the reservation is possible or times out.

#### **Parameters:**

amount The amount to reserve, default value is 1.

duration The duration of a self expiring reservation, default is that it lasts forever.

prioritized Whether this reservation is prioritized and thus allowed to use the excess limit.

*timeOut* The maximum time to block if the value of the counter is too low, default is to allow "eternal" blocking.

#### **Returns:**

A CounterTicket that can be queried about the status of the reservation as well as for cancellations and extensions.

Implements Arc::Counter.

#### **5.65.3.9 virtual int Arc::IntraProcessCounter::setExcess (int** *newExcess***)** [virtual]

Sets the excess limit of the counter.

This method sets a new excess limit for the counter.

#### **Parameters:**

newExcess The new excess limit, an absolute number.

#### **Returns:**

The new excess limit.

Implements Arc::Counter.

### **5.65.3.10 virtual int Arc::IntraProcessCounter::setLimit (int** *newLimit***)** [virtual]

Sets the limit of the counter.

This method sets a new limit for the counter.

### **Parameters:**

newLimit The new limit, an absolute number.

#### **Returns:**

The new limit.

Implements Arc::Counter.

The documentation for this class was generated from the following file:


• IntraProcessCounter.h

## 5.66 Arc::Loader Class Reference

Plugins loader.

#include <Loader.h>

Inheritance diagram for Arc::Loader::



#### **Public Member Functions**

- Loader (Config &cfg)
- ~Loader ()

#### **Static Public Attributes**

• static Logger logger

## **Protected Attributes**

• PluginsFactory \* factory\_

## 5.66.1 Detailed Description

Plugins loader.

This class processes XML configration and loads specified plugins. Accepted configuration is defined by XML schema mcc.xsd. "Plugins" elements are parsed by this class and corresponding libraries are loaded.

#### 5.66.2 Constructor & Destructor Documentation

5.66.2.1 Arc::Loader::Loader (Config & cfg)

Constructor that takes whole XML configuration and performs common configuration part

5.66.2.2 Arc::Loader::~Loader ()

Destructor destroys all components created by constructor

### 5.66.3 Member Data Documentation

**5.66.3.1** PluginsFactory\* Arc::Loader::factory\_ [protected]

Link to Factory responsible for loading and creation of Plugin and derived objects

The documentation for this class was generated from the following file:


• Loader.h

## 5.67 Arc::LogDestination Class Reference

A base class for log destinations.

#include <Logger.h>

Inheritance diagram for Arc::LogDestination::



#### **Public Member Functions**

• virtual void log (const LogMessage &message)=0

#### **Protected Member Functions**

- LogDestination ()
- LogDestination (const std::string &locale)

#### **Protected Attributes**

• std::string locale

## 5.67.1 Detailed Description

A base class for log destinations.

This class defines an interface for LogDestinations. LogDestination objects will typically contain synchronization mechanisms and should therefore never be copied.

## 5.67.2 Constructor & Destructor Documentation

#### **5.67.2.1** Arc::LogDestination::LogDestination() [protected]

Default constructor.

This destination will use the default locale.

## **5.67.2.2** Arc::LogDestination::LogDestination (const std::string & locale) [protected]

Constructor with specific locale.

This destination will use the specified locale.

## **5.67.3** Member Function Documentation

## **5.67.3.1 virtual void Arc::LogDestination::log (const LogMessage & message)** [pure virtual]

Logs a LogMessage to this LogDestination.

Implemented in Arc::LogStream.

The documentation for this class was generated from the following file:

• Logger.h

## 5.68 Arc::Logger Class Reference

A logger class.

#include <Logger.h>

#### **Public Member Functions**

- Logger (Logger &parent, const std::string &subdomain)
- Logger (Logger &parent, const std::string &subdomain, LogLevel threshold)
- void addDestination (LogDestination &destination)
- void removeDestinations (void)
- void setThreshold (LogLevel threshold)
- LogLevel getThreshold () const
- void msg (LogMessage message)
- void msg (LogLevel level, const std::string &str)
- template < class T0 > void msg (LogLevel level, const std::string &str, const T0 &t0)
- template < class T0, class T1 > void **msg** (LogLevel level, const std::string & str, const T0 & t0, const T1 & t1)
- template<class T0, class T1, class T2> void **msg** (LogLevel level, const std::string &str, const T0 &t0, const T1 &t1, const T2 &t2)
- template<class T0, class T1, class T2, class T3> void **msg** (LogLevel level, const std::string &str, const T0 &t0, const T1 &t1, const T2 &t2, const T3 &t3)
- template<class T0, class T1, class T2, class T3, class T4> void **msg** (LogLevel level, const std::string &str, const T0 &t0, const T1 &t1, const T2 &t2, const T3 &t3, const T4 &t4)
- template < class T0, class T1, class T2, class T3, class T4, class T5> void **msg** (LogLevel level, const std::string &str, const T0 &t0, const T1 &t1, const T2 &t2, const T3 &t3, const T4 &t4, const T5 &t5)
- template < class T0, class T1, class T2, class T3, class T4, class T5, class T6> void msg (LogLevel level, const std::string &str, const T0 &t0, const T1 &t1, const T2 &t2, const T3 &t3, const T4 &t4, const T5 &t5, const T6 &t6)
- template < class T0, class T1, class T2, class T3, class T4, class T5, class T6, class T7> void msg (LogLevel level, const std::string &str, const T0 &t0, const T1 &t1, const T2 &t2, const T3 &t3, const T4 &t4, const T5 &t5, const T6 &t6, const T7 &t7)

#### **Static Public Member Functions**

• static Logger & getRootLogger ()

#### **5.68.1** Detailed Description

A logger class.

This class defines a Logger to which LogMessages can be sent.

Every Logger (except for the rootLogger) has a parent Logger. The domain of a Logger (a string that indicates the origin of LogMessages) is composed by adding a subdomain to the domain of its parent Logger.

A Logger also has a threshold. Every LogMessage that have a level that is greater than or equal to the threshold is forwarded to any LogDestination connected to this Logger as well as to the parent Logger.

Typical usage of the Logger class is to declare a global Logger object for each library/module/component to be used by all classes and methods there.

#### **5.68.2** Constructor & Destructor Documentation

#### 5.68.2.1 Arc::Logger::Logger (Logger & parent, const std::string & subdomain)

Creates a logger.

Creates a logger. The threshold is inherited from its parent Logger.

#### **Parameters:**

```
parent The parent Logger of the new Logger.subdomain The subdomain of the new logger.
```

## 5.68.2.2 Arc::Logger::Logger (Logger & parent, const std::string & subdomain, LogLevel threshold)

Creates a logger.

Creates a logger.

#### **Parameters:**

```
parent The parent Logger of the new Logger.subdomain The subdomain of the new logger.threshold The threshold of the new logger.
```

#### **5.68.3** Member Function Documentation

#### 5.68.3.1 void Arc::Logger::addDestination (LogDestination & destination)

Adds a LogDestination.

Adds a LogDestination to which to forward LogMessages sent to this logger (if they pass the threshold). Since LogDestinatoins should not be copied, the new LogDestination is passed by reference and a pointer to it is kept for later use. It is therefore important that the LogDestination passed to this Logger exists at least as long as the Logger iteslf.

## **5.68.3.2 static Logger & Arc::Logger::getRootLogger()** [static]

The root Logger.

This is the root Logger. It is an ancestor of any other Logger and allways exists.

## 5.68.3.3 LogLevel Arc::Logger::getThreshold () const

Returns the threshold.

Returns the threshold.

#### **Returns:**

The threshold of this Logger.

#### 5.68.3.4 void Arc::Logger::msg (LogLevel level, const std::string & str) [inline]

Logs a message text.

Logs a message text string at the specified LogLevel. This is a convenience method to save some typing. It simply creates a LogMessage and sends it to the other msg() method.

#### **Parameters:**

```
level The level of the message.str The message text.
```

#### 5.68.3.5 void Arc::Logger::msg (LogMessage message)

Sends a LogMessage.

Sends a LogMessage.

#### **Parameters:**

The LogMessage to send.

#### 5.68.3.6 void Arc::Logger::removeDestinations (void)

Removes all LogDestinations.

## 5.68.3.7 void Arc::Logger::setThreshold (LogLevel threshold)

Sets the threshold.

This method sets the threshold of the Logger. Any message sent to this Logger that has a level below this threshold will be discarded.

#### **Parameters:**

The threshold

The documentation for this class was generated from the following file:

· Logger.h

## 5.69 Arc::LogMessage Class Reference

A class for log messages.

#include <Logger.h>

#### **Public Member Functions**

- LogMessage (LogLevel level, const IString &message)
- LogMessage (LogLevel level, const IString &message, const std::string &identifier)
- LogLevel getLevel () const

#### **Protected Member Functions**

• void setIdentifier (std::string identifier)

#### **Friends**

- class Logger
- std::ostream & operator<< (std::ostream &os, const LogMessage &message)

## 5.69.1 Detailed Description

A class for log messages.

This class is used to represent log messages internally. It contains the time the message was created, its level, from which domain it was sent, an identifier and the message text itself.

#### 5.69.2 Constructor & Destructor Documentation

#### 5.69.2.1 Arc::LogMessage::LogMessage (LogLevel level, const IString & message)

Creates a LogMessage with the specified level and message text.

This constructor creates a LogMessage with the specified level and message text. The time is set automatically, the domain is set by the Logger to which the LogMessage is sent and the identifier is composed from the process ID and the address of the Thread object corresponding to the calling thread.

#### **Parameters:**

*level* The level of the LogMessage.

message The message text.

## 5.69.2.2 Arc::LogMessage::LogMessage (LogLevel level, const IString & message, const std::string & identifier)

Creates a LogMessage with the specified attributes.

This constructor creates a LogMessage with the specified level, message text and identifier. The time is set automatically and the domain is set by the Logger to which the LogMessage is sent.

#### **Parameters:**

level The level of the LogMessage.message The message text.ident The identifier of the LogMessage.

## **5.69.3** Member Function Documentation

## 5.69.3.1 LogLevel Arc::LogMessage::getLevel () const

Returns the level of the LogMessage.

Returns the level of the LogMessage.

#### **Returns:**

The level of the LogMessage.

#### **5.69.3.2 void Arc::LogMessage::setIdentifier (std::string** *identifier*) [protected]

Sets the identifier of the LogMessage.

The purpose of this method is to allow subclasses (in case there are any) to set the identifier of a Log-Message.

#### **Parameters:**

The identifier.

## 5.69.4 Friends And Related Function Documentation

## **5.69.4.1 friend class Logger** [friend]

The Logger class is a friend.

The Logger class must have some privileges (e.g. ability to call the setDomain() method), therefore it is a friend.

#### 5.69.4.2 std::ostream & operator << (std::ostream & os, const LogMessage & message) [friend]

Printing of LogMessages to ostreams.

Output operator so that LogMessages can be printed conveniently by LogDestinations.

The documentation for this class was generated from the following file:


• Logger.h

## 5.70 Arc::LogStream Class Reference

A class for logging to ostreams.

#include <Logger.h>

Inheritance diagram for Arc::LogStream::



#### **Public Member Functions**

- LogStream (std::ostream &destination)
- LogStream (std::ostream &destination, const std::string &locale)
- virtual void log (const LogMessage &message)

## 5.70.1 Detailed Description

A class for logging to ostreams.

This class is used for logging to ostreams (cout, cerr, files). It provides synchronization in order to prevent different LogMessages to appear mixed with each other in the stream. In order not to break the synchronization, LogStreams should never be copied. Therefore the copy constructor and assignment operator are private. Furthermore, it is important to keep a LogStream object as long as the Logger to which it has been registered.

#### 5.70.2 Constructor & Destructor Documentation

#### 5.70.2.1 Arc::LogStream::LogStream (std::ostream & destination)

Creates a LogStream connected to an ostream.

Creates a LogStream connected to the specified ostream. In order not to break synchronization, it is important not to connect more than one LogStream object to a certain stream.

#### **Parameters:**

destination The ostream to which to erite LogMessages.

#### 5.70.2.2 Arc::LogStream::LogStream (std::ostream & destination, const std::string & locale)

Creates a LogStream connected to an ostream.

Creates a LogStream connected to the specified ostream. The output will be localised to the specified locale.

## **5.70.3** Member Function Documentation

## 5.70.3.1 virtual void Arc::LogStream::log (const LogMessage & message) [virtual]

Writes a LogMessage to the stream.

This method writes a LogMessage to the ostream that is connected to this LogStream object. It is synchronized so that not more than one LogMessage can be written at a time.

#### **Parameters:**

message The LogMessage to write.

Implements Arc::LogDestination.

The documentation for this class was generated from the following file:


• Logger.h

## 5.71 ArcSec::MatchFunction Class Reference

Evaluate whether arg1 (value in regular expression) matched arg0 (lable in regular expression).

#include <MatchFunction.h>

Inheritance diagram for ArcSec::MatchFunction::



#### **Public Member Functions**

- MatchFunction (std::string functionName, std::string argumentType)
- virtual bool evaluate (AttributeValue \*arg0, AttributeValue \*arg1)

#### **Static Public Member Functions**

• static std::string getFunctionName (std::string datatype)

## 5.71.1 Detailed Description

Evaluate whether arg1 (value in regular expression) matched arg0 (lable in regular expression).

### 5.71.2 Member Function Documentation

## **5.71.2.1** virtual bool ArcSec::MatchFunction::evaluate (AttributeValue \* arg0, AttributeValue \* arg1) [virtual]

Evaluate two Attribute Value objects

Implements ArcSec::Function.

## 5.71.2.2 static std::string ArcSec::MatchFunction::getFunctionName (std::string datatype) [static]

help function to get the FunctionName

The documentation for this class was generated from the following file:


• MatchFunction.h

## 5.72 Arc::MCC Class Reference

Message Chain Component - base class for every MCC plugin.

#include <MCC.h>

Inheritance diagram for Arc::MCC::



#### **Public Member Functions**

- MCC (Arc::Config \*)
- virtual void Next (Arc::MCCInterface \*next, const std::string &label="")
- virtual void AddSecHandler (Arc::Config \*cfg, ArcSec::SecHandler \*sechandler, const std::string &label="")
- virtual void Unlink ()
- virtual Arc::MCC\_Status process (Arc::Message &, Arc::Message &)

## **Protected Member Functions**

- Arc::MCCInterface \* Next (const std::string &label="")
- bool ProcessSecHandlers (Arc::Message &message, const std::string &label="")

## **Protected Attributes**

- std::map< std::string, Arc::MCCInterface \* > next\_
- std::map< std::string, std::list< ArcSec::SecHandler \* > > sechandlers\_

#### **Static Protected Attributes**

• static Arc::Logger logger

## **5.72.1** Detailed Description

Message Chain Component - base class for every MCC plugin.

This is partially virtual class which defines interface and common functionality for every MCC plugin needed for managing of component in a chain.

#### 5.72.2 Constructor & Destructor Documentation

#### 5.72.2.1 Arc::MCC::MCC (Arc::Config \*) [inline]

Example contructor - MCC takes at least it's configuration subtree

#### **5.72.3** Member Function Documentation

```
5.72.3.1 virtual void Arc::MCC::AddSecHandler (Arc::Config * cfg, ArcSec::SecHandler * sechandler, const std::string & label = "") [virtual]
```

Add security components/handlers to this MCC. Security handlers are stacked into a few queues with each queue identified by its label. The queue labelled 'incoming' is executed for every 'request' message after the message is processed by the MCC on the service side and before processing on the client side. The queue labelled 'outgoing' is run for response message before it is processed by MCC algorithms on the service side and after processing on the client side. Those labels are just a matter of agreement and some MCCs may implement different queues executed at various message processing steps.

```
5.72.3.2 virtual void Arc::MCC::Next (Arc::MCCInterface * next, const std::string & label = "")

[virtual]
```

Add reference to next MCC in chain. This method is called by Loader for every potentially labeled link to next component which implements MCCInterface. If next is NULL corresponding link is removed.

Reimplemented in Arc::Plexer.

```
5.72.3.3 virtual Arc::MCC_Status Arc::MCC::process (Arc::Message &, Arc::Message &)
[inline, virtual]
```

Dummy Message processing method. Just a placeholder.

Implements Arc::MCCInterface.

Reimplemented in Arc::Plexer.

## 5.72.3.4 bool Arc::MCC::ProcessSecHandlers (Arc::Message & message, const std::string & label = "") [protected]

Executes security handlers of specified queue. Returns true if the message is authorized for further processing or if there are no security handlers which implement authorization functionality. This is a convenience method and has to be called by the implemention of the MCC.

#### 5.72.3.5 virtual void Arc::MCC::Unlink () [virtual]

Removing all links. Useful for destroying chains.

### 5.72.4 Member Data Documentation

#### **5.72.4.1** Arc::Logger Arc::MCC::logger [static, protected]

A logger for MCCs.

A logger intended to be the parent of loggers in the different MCCs.

Reimplemented in Arc::Plexer.

```
5.72.4.2 std::map<std::string, Arc::MCCInterface *> Arc::MCC::next_ [protected]
```

Set of labeled "next" components. Each implemented MCC must call process() method of corresponding MCCInterface from this set in own process() method.

```
5.72.4.3 std::map<std::string, std::list<ArcSec::SecHandler *> > Arc::MCC::sechandlers_
[protected]
```

Set of labeled authentication and authorization handlers. MCC calls sequence of handlers at specific point depending on associated identifier. In most aces those are "in" and "out" for incoming and outgoing messages correspondingly.

The documentation for this class was generated from the following file:

• MCC.h

## 5.73 Arc::MCC\_Status Class Reference

A class for communication of MCC processing results.

```
#include <MCC_Status.h>
```

#### **Public Member Functions**

- MCC\_Status (StatusKind kind=STATUS\_UNDEFINED, const std::string &origin="???", const std::string &explanation="No explanation.")
- bool isOk () const
- StatusKind getKind () const
- const std::string & getOrigin () const
- const std::string & getExplanation () const
- operator std::string () const
- operator bool (void) const
- bool operator! (void) const

## 5.73.1 Detailed Description

A class for communication of MCC processing results.

This class is used to communicate result status between MCCs. It contains a status kind, a string specifying the origin (MCC) of the status object and an explanation.

## 5.73.2 Constructor & Destructor Documentation

5.73.2.1 Arc::MCC\_Status::MCC\_Status (StatusKind kind = STATUS\_UNDEFINED, const std::string & origin = "???", const std::string & explanation = "No explanation.")

The constructor.

Creates a MCC\_Status object.

#### **Parameters:**

```
kind The StatusKind (default: STATUS_UNDEFINED)
origin The origin MCC (default: "????")
explanation An explanation (default: "No explanation.")
```

#### 5.73.3 Member Function Documentation

#### 5.73.3.1 const std::string& Arc::MCC\_Status::getExplanation () const

Returns an explanation.

This method returns an explanation of this object.

#### **Returns:**

An explanation of this object.

#### 5.73.3.2 StatusKind Arc::MCC\_Status::getKind () const

Returns the status kind.

Returns the status kind of this object.

#### **Returns:**

The status kind of this object.

## 5.73.3.3 const std::string& Arc::MCC\_Status::getOrigin () const

Returns the origin.

This method returns a string specifying the origin MCC of this object.

#### **Returns:**

A string specifying the origin MCC of this object.

## 5.73.3.4 bool Arc::MCC\_Status::isOk () const

Is the status kind ok?

This method returns true iff the status kind of this object is STATUS\_OK

#### **Returns:**

true iff kind==STATUS\_OK

#### 5.73.3.5 Arc::MCC\_Status::operator bool (void) const [inline]

Is the status kind ok?

This method returns true iff the status kind of this object is STATUS\_OK

### **Returns:**

true iff kind==STATUS\_OK

#### 5.73.3.6 Arc::MCC\_Status::operator std::string () const

Conversion to string.

This operator converts a MCC\_Status object to a string.

## **5.73.3.7 bool** Arc::MCC\_Status::operator! (void) const [inline]

not operator

Returns true if the status kind is not OK

#### **Returns:**

true if kind!=STATUS\_OK

The documentation for this class was generated from the following file:


• MCC\_Status.h

## 5.74 Arc::MCCInterface Class Reference

Interface for communication between MCC, Service and Plexer objects.

#include <MCC.h>

Inheritance diagram for Arc::MCCInterface::



#### **Public Member Functions**

• virtual Arc::MCC\_Status process (Arc::Message &request, Arc::Message &response)=0

#### 5.74.1 Detailed Description

Interface for communication between MCC, Service and Plexer objects.

The Interface consists of the method process() which is called by the previous MCC in the chain. For memory management policies please read the description of the Message class.

#### 5.74.2 Member Function Documentation

## 5.74.2.1 virtual Arc::MCC\_Status Arc::MCCInterface::process (Arc::Message & request, Arc::Message & response) [pure virtual]

Method for processing of requests and responses. This method is called by preceding MCC in chain when a request needs to be processed. This method must call similar method of next MCC in chain unless any failure happens. Result returned by call to next MCC should be processed and passed back to previous MCC. In case of failure this method is expected to generate valid error response and return it back to previous MCC without calling the next one.

#### Parameters:

request The request that needs to be processed.

response A Message object that will contain the response of the request when the method returns.

## **Returns:**

An object representing the status of the call.

Implemented in Arc::MCC, and Arc::Plexer.

The documentation for this class was generated from the following file:


• MCC.h

## 5.75 Arc::MCCLoader Class Reference

Creator of Message Component Chains (MCC).

#include <MCCLoader.h>

Inheritance diagram for Arc::MCCLoader::



## **Public Types**

- typedef std::map< std::string, MCC \* > mcc\_container\_t
- typedef std::map< std::string, Service \* > service\_container\_t
- typedef std::map< std::string, ArcSec::SecHandler \* > sechandler\_container\_t
- typedef std::map< std::string, Plexer \* > plexer\_container\_t

#### **Public Member Functions**

- MCCLoader (Config &cfg)
- ~MCCLoader ()
- MCC \* operator[] (const std::string &id)

#### **Friends**

class ChainContext

#### 5.75.1 Detailed Description

Creator of Message Component Chains (MCC).

This class processes XML configration and creates message chains. Accepted configuration is defined by XML schema mcc.xsd. Supported components are of types MCC, Service and Plexer. MCC and Service are loaded from dynamic libraries. For Plexer only internal implementation is supported. This object is also a container for loaded componets. All components and chains are destroyed if this object is destroyed. Chains are created in 2 steps. First all components are loaded and corresponding objects are created. Constructors are supplied with corresponding configuration subtrees. During next step components are linked together by calling their Next() methods. Each call creates labeled link to next component in a chain. 2 step method has an advantage over single step because it allows loops in chains and makes loading procedure more simple. But that also means during short period of time components are only partly configured. Components in such state must produce proper error response if Message arrives. Note: Current implementation requires all components and links to be labeled. All labels must be unique. Future implementation will be able to assign labels automatically.

## 5.75.2 Constructor & Destructor Documentation

## 5.75.2.1 Arc::MCCLoader::MCCLoader (Config & cfg)

Constructor that takes whole XML configuration and creates component chains

## 5.75.2.2 Arc::MCCLoader::~MCCLoader ()

Destructor destroys all components created by constructor

## **5.75.3** Member Function Documentation

#### 5.75.3.1

MCC\* Arc::MCCLoader::operator[] (const std::string & id)

Access entry MCCs in chains. Those are components exposed for external access using 'entry' attribute The documentation for this class was generated from the following file:


• MCCLoader.h

## 5.76 Arc::MD5Sum Class Reference

Implementation of MD5 checksum.

#include <CheckSum.h>

Inheritance diagram for Arc::MD5Sum::



#### **Public Member Functions**

- virtual void start (void)
- virtual void add (void \*buf, unsigned long long int len)
- virtual void **end** (void)
- virtual void **result** (unsigned char \*&res, unsigned int &len) const
- virtual int **print** (char \*buf, int len) const
- virtual void **scan** (const char \*buf)
- virtual operator bool (void) const
- virtual bool operator! (void) const

## **5.76.1** Detailed Description

Implementation of MD5 checksum.

The documentation for this class was generated from the following file:

· CheckSum.h

## 5.77 Arc::Message Class Reference

Object being passed through chain of MCCs.

#include <Message.h>

#### **Public Member Functions**

- Message (void)
- Message (Message &msg)
- Message (long msg\_ptr\_addr)
- ∼Message (void)
- Message & operator= (Message &msg)
- MessagePayload \* Payload (void)
- MessagePayload \* Payload (MessagePayload \*payload)
- MessageAttributes \* Attributes (void)
- void **Attributes** (MessageAttributes \*attr)
- MessageAuth \* Auth (void)
- void **Auth** (MessageAuth \*auth)
- MessageContext \* Context (void)
- MessageAuthContext \* AuthContext (void)
- void Context (MessageContext \*ctx)
- void AuthContext (MessageAuthContext \*auth\_ctx)

## 5.77.1 Detailed Description

Object being passed through chain of MCCs.

An instance of this class refers to objects with main content (MessagePayload), authentication/authorization information (MessageAuth) and common purpose attributes (MessageAttributes). Message class does not manage pointers to objects and their content. It only serves for grouping those objects. Message objects are supposed to be processed by MCCs and Services implementing MCCInterface method process(). All objects constituting content of Message object are subject to following policies:

- 1. All objects created inside call to process() method using new command must be explicitly destroyed within same call using delete command with following exceptions. a) Objects which are assigned to 'response' Message. b) Objects whose management is completely acquired by objects assigned to 'response' Message.
- 2. All objects not created inside call to process() method are not explicitly destroyed within that call with following exception. a) Objects which are part of 'response' Method returned from call to next's process() method. Unless those objects are passed further to calling process(), of course.
- 3. It is not allowed to make 'response' point to same objects as 'request' does on entry to process() method. That is needed to avoid double destruction of same object. (Note: if in a future such need arises it may be solved by storing additional flags in Message object).
- 4. It is allowed to change content of pointers of 'request' Message. Calling process() method must not rely on that object to stay intact.
- 5. Called process() method should either fill 'response' Message with pointers to valid objects or to keep them intact. This makes it possible for calling process() to preload 'response' with valid error message.

#### 5.77.2 Constructor & Destructor Documentation

#### **5.77.2.1** Arc::Message::Message (void) [inline]

Dummy constructor

#### 5.77.2.2 Arc::Message::Message (Message & msg) [inline]

Copy constructor. Ensures shallow copy.

#### 5.77.2.3 Arc::Message::Message (long msg\_ptr\_addr)

Copy constructor. Used by language bindigs

#### **5.77.2.4** Arc::Message::~Message (void) [inline]

Destructor does not affect refered objects except those created internally

#### **5.77.3** Member Function Documentation

#### **5.77.3.1** MessageAttributes\* Arc::Message::Attributes (void) [inline]

Returns a pointer to the current attributes object or creates it if no attributes object has been assigned.

#### **5.77.3.2** MessageAuth\* Arc::Message::Auth (void) [inline]

Returns a pointer to the current authentication/authorization object or creates it if no object has been assigned.

## **5.77.3.3 void Arc::Message::AuthContext** (**MessageAuthContext** \* *auth\_ctx*) [inline]

Assigns auth\* context object

#### **5.77.3.4** MessageAuthContext\* Arc::Message::AuthContext (void) [inline]

Returns a pointer to the current auth\* context object or creates it if no object has been assigned.

## **5.77.3.5 void Arc::Message::Context** (**MessageContext** \* *ctx*) [inline]

Assigns message context object

#### **5.77.3.6** MessageContext\* Arc::Message::Context (void) [inline]

Returns a pointer to the current context object or creates it if no object has been assigned. Last case should happen only if first MCC in a chain is connectionless like one implementing UDP protocol.

5.77.3.7 Message & Arc::Message::operator= (Message & msg) [inline]

Assignment. Ensures shallow copy.

**5.77.3.8** MessagePayload\* Arc::Message::Payload (MessagePayload \* payload) [inline]

Replaces payload with new one. Returns the old one.

**5.77.3.9** MessagePayload\* Arc::Message::Payload (void) [inline]

Returns pointer to current payload or NULL if no payload assigned.

The documentation for this class was generated from the following file:

## 5.78 Arc::MessageAttributes Class Reference

A class for storage of attribute values.

#include <MessageAttributes.h>

#### **Public Member Functions**

- MessageAttributes ()
- void set (const std::string &key, const std::string &value)
- void add (const std::string &key, const std::string &value)
- void removeAll (const std::string &key)
- void remove (const std::string &key, const std::string &value)
- int count (const std::string &key) const
- const std::string & get (const std::string &key) const
- AttributeIterator getAll (const std::string &key) const
- AttributeIterator getAll (void) const

#### **Protected Attributes**

• AttrMap attributes\_

## 5.78.1 Detailed Description

A class for storage of attribute values.

This class is used to store attributes of messages. All attribute keys and their corresponding values are stored as strings. Any key or value that is not a string must thus be represented as a string during storage. Furthermore, an attribute is usually a key-value pair with a unique key, but there may also be multiple such pairs with equal keys.

The key of an attribute is composed by the name of the Message Chain Component (MCC) which produce it and the name of the attribute itself with a colon (:) in between, i.e. MCC\_Name:Attribute\_Name. For example, the key of the "Content-Length" attribute of the HTTP MCC is thus "HTTP:Content-Length".

There are also "global attributes", which may be produced by different MCCs depending on the configuration. The keys of such attributes are NOT prefixed by the name of the producing MCC. Before any new global attribute is introduced, it must be agreed upon by the core development team and added below. The global attributes decided so far are:

• Request-URI Identifies the service to which the message shall be sent. This attribute is produced by e.g. the HTTP MCC and used by the plexer for routing the message to the appropriate service.

#### 5.78.2 Constructor & Destructor Documentation

#### **5.78.2.1** Arc::MessageAttributes::MessageAttributes()

The default constructor.

This is the default constructor of the MessageAttributes class. It constructs an empty object that initially contains no attributes.

#### **5.78.3** Member Function Documentation

#### 5.78.3.1 void Arc::MessageAttributes::add (const std::string & key, const std::string & value)

Adds a value to an attribute.

This method adds a new value to an attribute. Any previous value will be preserved, i.e. the attribute may become multiple valued.

#### **Parameters:**

key The key of the attribute.

value The (new) value of the attribute.

#### 5.78.3.2 int Arc::MessageAttributes::count (const std::string & key) const

Returns the number of values of an attribute.

Returns the number of values of an attribute that matches a certain key.

#### **Parameters:**

key The key of the attribute for which to count values.

#### **Returns:**

The number of values that corresponds to the key.

## 5.78.3.3 const std::string& Arc::MessageAttributes::get (const std::string & key) const

Returns the value of a single-valued attribute.

This method returns the value of a single-valued attribute. If the attribute is not single valued (i.e. there is no such attribute or it is a multiple-valued attribute) an empty string is returned.

#### **Parameters:**

key The key of the attribute for which to return the value.

#### **Returns:**

The value of the attribute.

#### 5.78.3.4 AttributeIterator Arc::MessageAttributes::getAll (void) const

Access all value and attributes.

## 5.78.3.5 AttributeIterator Arc::MessageAttributes::getAll (const std::string & key) const

Access the value(s) of an attribute.

This method returns an AttributeIterator that can be used to access the values of an attribute.

#### **Parameters:**

key The key of the attribute for which to return the values.

#### **Returns:**

An AttributeIterator for access of the values of the attribute.

#### 5.78.3.6 void Arc::MessageAttributes::remove (const std::string & key, const std::string & value)

Removes one value of an attribute.

This method removes a certain value from the attribute that matches a certain key.

#### **Parameters:**

key The key of the attribute from which the value shall be removed.value The value to remove.

#### 5.78.3.7 void Arc::MessageAttributes::removeAll (const std::string & key)

Removes all attributes with a certain key.

This method removes all attributes that match a certain key.

#### **Parameters:**

key The key of the attributes to remove.

#### 5.78.3.8 void Arc::MessageAttributes::set (const std::string & key, const std::string & value)

Sets a unique value of an attribute.

This method removes any previous value of an attribute and sets the new value as the only value.

## **Parameters:**

key The key of the attribute.value The (new) value of the attribute.

#### 5.78.4 Member Data Documentation

#### **5.78.4.1** AttrMap Arc::MessageAttributes::attributes\_ [protected]

Internal storage of attributes.

An AttrMap (multimap) in which all attributes (key-value pairs) are stored.

The documentation for this class was generated from the following file:


· MessageAttributes.h

## 5.79 Arc::MessageAuth Class Reference

Contains authencity information, authorization tokens and decisions.

#include <MessageAuth.h>

Inheritance diagram for Arc::MessageAuth::



#### **Public Member Functions**

- void set (const std::string &key, SecAttr \*value)
- void remove (const std::string &key)
- SecAttr \* get (const std::string &key)
- SecAttr \* operator[] (const std::string &key)
- bool Export (SecAttrFormat format, XMLNode &val) const
- MessageAuth \* Filter (const std::list< std::string > selected\_keys, const std::list< std::string > rejected\_keys) const

#### 5.79.1 Detailed Description

Contains authencity information, authorization tokens and decisions.

This class only supports string keys and SecAttr values.

#### **5.79.2** Member Function Documentation

#### 5.79.2.1 bool Arc::MessageAuth::Export (SecAttrFormat format, XMLNode & val) const

Returns properly catenated attributes in specified format.

Content of XML node at is replaced with generated information if XML tree is empty. If tree at is not empty then Export() tries to merge generated information to already existing like everything would be generated inside same Export() method. If does not represent valid node then new XML tree is created.

## 5.79.2.2 MessageAuth\* Arc::MessageAuth::Filter (const std::list< std::string > selected\_keys, const std::list< std::string > rejected\_keys) const

Creates new instance of MessageAuth with attributes filtered.

In new instance all attributes with keys listed in are removed. If is not empty only corresponding attributes are transfered to new instance. Created instance does not own refered attributes. Hence parent instance must not be deleted as long as this one is in use.

#### 5.79.2.3 SecAttr\* Arc::MessageAuth::get (const std::string & key)

Retrieves reference to security attribute stored under specified key.

## 5.79.2.4 ]

SecAttr\* Arc::MessageAuth::operator[] (const std::string & key) [inline] Same as MessageAuth::get.

## 5.79.2.5 void Arc::MessageAuth::remove (const std::string & key)

Deletes security attribute stored under specified key.

## 5.79.2.6 void Arc::MessageAuth::set (const std::string & key, SecAttr \* value)

Adds/overwrites security attribute stored under specified key.

The documentation for this class was generated from the following file:


• MessageAuth.h

## 5.80 Arc::MessageAuthContext Class Reference

Handler for content of message auth\* context.

#include <Message.h>

Inheritance diagram for Arc::MessageAuthContext::



## **5.80.1** Detailed Description

Handler for content of message auth\* context.

This class is a container for authorization and authentication information. It gets associated with Message object usually by first MCC in a chain and is kept as long as connection persists.

The documentation for this class was generated from the following file:

## 5.81 Arc::MessageContext Class Reference

Handler for content of message context.

#include <Message.h>

#### **Public Member Functions**

- void Add (const std::string &name, MessageContextElement \*element)
- MessageContextElement \* operator[] (const std::string &id)

## 5.81.1 Detailed Description

Handler for content of message context.

This class is a container for objects derived from MessageContextElement. It gets associated with Message object usually by first MCC in a chain and is kept as long as connection persists.

#### **5.81.2** Member Function Documentation

## 5.81.2.1 void Arc::MessageContext::Add (const std::string & name, MessageContextElement \* element)

Provided element is taken over by this class. It is remembered by it and destroyed when this class is destroyed.

The documentation for this class was generated from the following file:

## 5.82 Arc::MessageContextElement Class Reference

Top class for elements contained in message context.

#include <Message.h>

## **5.82.1 Detailed Description**

Top class for elements contained in message context.

Objects of classes inherited with this one may be stored in MessageContext container.


The documentation for this class was generated from the following file:

# 5.83 Arc::MessagePayload Class Reference

Base class for content of message passed through chain.

#include <Message.h>

Inheritance diagram for Arc::MessagePayload::



# **5.83.1** Detailed Description

Base class for content of message passed through chain.

It's not intended to be used directly. Instead functional classes must be derived from it.

The documentation for this class was generated from the following file:


· Message.h

# 5.84 Arc::ModuleManager Class Reference

Manager of shared libraries.

#include <ModuleManager.h>

Inheritance diagram for Arc::ModuleManager::



### **Public Member Functions**

- ModuleManager (const Arc::Config \*cfg)
- Glib::Module \* load (const std::string &name, bool probe=false)
- Glib::Module \* reload (Glib::Module \*module)
- void **unload** (Glib::Module \*module)
- void **unload** (const std::string &name)
- std::string findLocation (const std::string &name)
- void setCfg (Arc::Config \*cfg)

# 5.84.1 Detailed Description

Manager of shared libraries.

This class loads shared libraries/modules. There supposed to be created one instance of it per executable. In such circumstances it would cache handles to loaded modules and not load them multiple times.

### **5.84.2** Constructor & Destructor Documentation

#### 5.84.2.1 Arc::ModuleManager::ModuleManager (const Arc::Config \* cfg)

Constructor. It is supposed to process correponding configuration subtree and tune module loading parameters accordingly. Currently it only sets modulr directory to current one.

### **5.84.3** Member Function Documentation

### 5.84.3.1 std::string Arc::ModuleManager::findLocation (const std::string & name)

Finds shared library corresponding to module 'name' and returns path to it

# **5.84.3.2** Glib::Module\* Arc::ModuleManager::load (const std::string & name, bool probe = false)

Finds module 'name' in cache or loads corresponding shared library

# 5.84.3.3 Glib::Module\* Arc::ModuleManager::reload (Glib::Module \* module)

Reload module previously loaded in probe mode. New module is loaded with all symbols resolved and old module handler is unloaded. In case of error old module is not unloaded.

# 5.84.3.4 void Arc::ModuleManager::setCfg (Arc::Config \* cfg)

Input the configuration subtree, and trigger the module loading (do almost the same as the Constructor); It is function desgined for ClassLoader to adopt the singleton pattern

The documentation for this class was generated from the following file:

• ModuleManager.h

# 5.85 Arc::MultiSecAttr Class Reference

Container of multiple SecAttr attributes.

#include <SecAttr.h>

Inheritance diagram for Arc::MultiSecAttr::



## **Public Member Functions**

- virtual operator bool () const
- virtual bool Export (SecAttrFormat format, XMLNode &val) const
- virtual bool **Import** (SecAttrFormat format, const XMLNode &val)

# **Protected Member Functions**

- virtual bool equal (const SecAttr &b) const
- virtual bool Add (SecAttrFormat format, XMLNode &val)

### **Protected Attributes**

• std::list< SecAttr \* > attrs\_

## 5.85.1 Detailed Description

Container of multiple SecAttr attributes.

This class combines multiple attributes. It's export/import methods catenate results of underlying objects. Primary meaning of this class is to serve as base for classes implementing multi level hierarchical tree-like descriptions of user identity. It may also be used for collecting information of same source or kind. Like all information extracted from X509 certificate.

#### **5.85.2** Member Function Documentation

# **5.85.2.1** virtual bool Arc::MultiSecAttr::Export (SecAttrFormat format, XMLNode & val) const [virtual]

Convert internal structure into specified format. Returns false if format is not supported/suitable for this attribute. XML node referenced by is turned into top level element of specified format.

Reimplemented from Arc::SecAttr.

# **5.85.2.2 virtual Arc::MultiSecAttr::operator bool () const** [virtual]

This function should return false if the value is to be considered null, e.g. if it hasn't been set or initialized. In other cases it should return true.

Reimplemented from Arc::SecAttr.

The documentation for this class was generated from the following file:

• SecAttr.h

# 5.86 Arc::MySQLDatabase Class Reference

#include <MysqlWrapper.h>

Inheritance diagram for Arc::MySQLDatabase::



### **Public Member Functions**

- MySQLDatabase (std::string &server, int port)
- MySQLDatabase (const MySQLDatabase &other)
- virtual bool connect (std::string &dbname, std::string &user, std::string &password)
- virtual bool isconnected () const
- virtual void close ()
- virtual bool enable\_ssl (const std::string keyfile="", const std::string certfile="", const std::string cafile="", const std::string capath="")
- virtual bool shutdown ()

### **Friends**

· class MySQLQuery

# 5.86.1 Detailed Description

Implement the database accessing interface in DBInterface.h by using mysql client library for accessing mysql database

### **5.86.2** Member Function Documentation

# **5.86.2.1 virtual void Arc::MySQLDatabase::close** () [virtual]

Close the connection with database server

Implements Arc::Database.

# 5.86.2.2 virtual bool Arc::MySQLDatabase::connect (std::string & dbname, std::string & user, std::string & password) [virtual]

Do connection with database server

#### Parameters:

dbname The database name which will be used.

user The username which will be used to access database.

password The password which will be used to access database.

Implements Arc::Database.

```
5.86.2.3 virtual bool Arc::MySQLDatabase::enable_ssl (const std::string keyfile = "", const std::string capth = "") [virtual]
```

Enable ssl communication for the connection

#### **Parameters:**

```
keyfile The location of key file.certfile The location of certificate file.cafile The location of ca file.capath The location of ca directory
```

Implements Arc::Database.

# **5.86.2.4 virtual bool Arc::MySQLDatabase::isconnected () const** [inline, virtual]

Get the connection status

Implements Arc::Database.

## **5.86.2.5** virtual bool Arc::MySQLDatabase::shutdown () [virtual]

Ask database server to shutdown

Implements Arc::Database.

The documentation for this class was generated from the following file:


• MysqlWrapper.h

# 5.87 Arc::PayloadRaw Class Reference

Raw byte multi-buffer.

#include <PayloadRaw.h>

Inheritance diagram for Arc::PayloadRaw::



### **Public Member Functions**

- PayloadRaw (void)
- virtual ~PayloadRaw (void)
- virtual char operator[] (int pos) const
- virtual char \* Content (int pos=-1)
- virtual int Size (void) const
- virtual char \* Insert (int pos=0, int size=0)
- virtual char \* Insert (const char \*s, int pos=0, int size=0)
- virtual char \* Buffer (unsigned int num=0)
- virtual int BufferSize (unsigned int num=0) const
- virtual int BufferPos (unsigned int num=0) const
- virtual bool Truncate (unsigned int size)

#### **Protected Attributes**

- int offset
- int size
- std::vector< PayloadRawBuf > **buf\_**

# 5.87.1 Detailed Description

Raw byte multi-buffer.

This is implementation of PayloadRawInterface. Buffers are memory blocks logically placed one after another.

## 5.87.2 Constructor & Destructor Documentation

### **5.87.2.1** Arc::PayloadRaw::PayloadRaw (void) [inline]

Constructor. Created object contains no buffers.

#### **5.87.2.2 virtual Arc::PayloadRaw::**~PayloadRaw (void) [virtual]

Destructor. Frees allocated buffers.

#### **5.87.3** Member Function Documentation

# **5.87.3.1 virtual char\* Arc::PayloadRaw::Buffer (unsigned int** *num* = 0) [virtual]

Returns pointer to num'th buffer

Implements Arc::PayloadRawInterface.

#### **5.87.3.2 virtual int Arc::PayloadRaw::BufferPos (unsigned int** *num* = 0) **const** [virtual]

Returns position of num'th buffer

Implements Arc::PayloadRawInterface.

#### **5.87.3.3 virtual int Arc::PayloadRaw::BufferSize (unsigned int** *num* = 0) **const** [virtual]

Returns length of num'th buffer

Implements Arc::PayloadRawInterface.

## **5.87.3.4 virtual char\*** Arc::PayloadRaw::Content (int pos = -1) [virtual]

Get pointer to buffer content at global position 'pos'. By default to beginning of main buffer whatever that means.

Implements Arc::PayloadRawInterface.

# **5.87.3.5 virtual char\* Arc::PayloadRaw::Insert (const char** \* *s*, **int** *pos* = 0, **int** *size* = 0) [virtual]

Create new buffer at global position 'pos' of size 'size'. Created buffer is filled with content of memory at 's'. If 'size' is 0 content at 's' is expected to be null-terminated.

Implements Arc::PayloadRawInterface.

### **5.87.3.6 virtual char\* Arc::PayloadRaw::Insert (int** *pos* = 0, **int** *size* = 0) [virtual]

Create new buffer at global position 'pos' of size 'size'.

Implements Arc::PayloadRawInterface.

#### 5.87.3.7

virtual char Arc::PayloadRaw::operator[] (int pos) const [virtual]

Returns content of byte at specified position. Specified position 'pos' is treated as global one and goes through all buffers placed one after another.

Implements Arc::PayloadRawInterface.

# **5.87.3.8 virtual int Arc::PayloadRaw::Size (void) const** [virtual]

Returns logical size of whole structure.

Implements Arc::PayloadRawInterface.

# **5.87.3.9 virtual bool Arc::PayloadRaw::Truncate (unsigned int** *size***)** [virtual]

Change size of stored information. If size exceeds end of allocated buffer, buffers are not re-allocated, only logical size is extended. Buffers with location behind new size are deallocated.

Implements Arc::PayloadRawInterface.

The documentation for this class was generated from the following file:


· PayloadRaw.h

# 5.88 Arc::PayloadRawInterface Class Reference

Random Access Payload for Message objects.

#include <PayloadRaw.h>

Inheritance diagram for Arc::PayloadRawInterface::



#### **Public Member Functions**

- virtual char operator[] (int pos) const =0
- virtual char \* Content (int pos=-1)=0
- virtual int Size (void) const =0
- virtual char \* Insert (int pos=0, int size=0)=0
- virtual char \* Insert (const char \*s, int pos=0, int size=0)=0
- virtual char \* Buffer (unsigned int num)=0
- virtual int BufferSize (unsigned int num) const =0
- virtual int BufferPos (unsigned int num) const =0
- virtual bool Truncate (unsigned int size)=0

# 5.88.1 Detailed Description

Random Access Payload for Message objects.

This class is a virtual interface for managing Message payload with arbitrarily accessible content. Inheriting classes are supposed to implement memory-resident or memory-mapped content made of optionally multiple chunks/buffers. Every buffer has own size and offset. This class is purely virtual.

#### **5.88.2** Member Function Documentation

### **5.88.2.1 virtual char\*** Arc::PayloadRawInterface::Buffer (unsigned int *num*) [pure virtual]

Returns pointer to num'th buffer

Implemented in Arc::PayloadRaw.

# **5.88.2.2 virtual int Arc::PayloadRawInterface::BufferPos (unsigned int** *num***) const** [pure virtual]

Returns position of num'th buffer

Implemented in Arc::PayloadRaw.

# **5.88.2.3 virtual int Arc::PayloadRawInterface::BufferSize (unsigned int** *num***) const** [pure virtual]

Returns length of num'th buffer

Implemented in Arc::PayloadRaw.

#### **5.88.2.4 virtual char\* Arc::PayloadRawInterface::Content (int** *pos* = -1) [pure virtual]

Get pointer to buffer content at global position 'pos'. By default to beginning of main buffer whatever that means.

Implemented in Arc::PayloadRaw.

# **5.88.2.5** virtual char\* Arc::PayloadRawInterface::Insert (const char \* s, int pos = 0, int size = 0) [pure virtual]

Create new buffer at global position 'pos' of size 'size'. Created buffer is filled with content of memory at 's'. If 'size' is 0 content at 's' is expected to be null-terminated.

Implemented in Arc::PayloadRaw.

# **5.88.2.6 virtual char\* Arc::PayloadRawInterface::Insert (int** *pos* = 0, **int** *size* = 0) [pure virtual]

Create new buffer at global position 'pos' of size 'size'.

Implemented in Arc::PayloadRaw.

#### 5.88.2.7

virtual char Arc::PayloadRawInterface::operator[] (int pos) const [pure virtual]

Returns content of byte at specified position. Specified position 'pos' is treated as global one and goes through all buffers placed one after another.

Implemented in Arc::PayloadRaw.

#### **5.88.2.8 virtual int Arc::PayloadRawInterface::Size (void) const** [pure virtual]

Returns logical size of whole structure.

Implemented in Arc::PayloadRaw.

# **5.88.2.9 virtual bool Arc::PayloadRawInterface::Truncate (unsigned int size)** [pure virtual]

Change size of stored information. If size exceeds end of allocated buffer, buffers are not re-allocated, only logical size is extended. Buffers with location behind new size are deallocated.

Implemented in Arc::PayloadRaw.

The documentation for this class was generated from the following file:


· PayloadRaw.h

# 5.89 Arc::PayloadSOAP Class Reference

Payload of Message with SOAP content.

#include <PayloadSOAP.h>

Inheritance diagram for Arc::PayloadSOAP::



#### **Public Member Functions**

- PayloadSOAP (const Arc::NS &ns, bool fault=false)
- PayloadSOAP (const Arc::SOAPEnvelope &soap)
- PayloadSOAP (const Arc::MessagePayload &source)

## **5.89.1 Detailed Description**

Payload of Message with SOAP content.

This class combines MessagePayload with SOAPEnvelope to make it possible to pass SOAP messages through MCC chain.

#### 5.89.2 Constructor & Destructor Documentation

# 5.89.2.1 Arc::PayloadSOAP::PayloadSOAP (const Arc::NS & ns, bool fault = false)

Constructor - creates new Message payload

### 5.89.2.2 Arc::PayloadSOAP::PayloadSOAP (const Arc::SOAPEnvelope & soap)

Constructor - creates Message payload from SOAP document. Provided SOAP document is copied to new object.

#### 5.89.2.3 Arc::PayloadSOAP::PayloadSOAP (const Arc::MessagePayload & source)

Constructor - creates SOAP message from payload. PayloadRawInterface and derived classes are supported.

The documentation for this class was generated from the following file:


· PayloadSOAP.h

# 5.90 Arc::PayloadStream Class Reference

POSIX handle as Payload.

#include <PayloadStream.h>

Inheritance diagram for Arc::PayloadStream::



### **Public Member Functions**

- PayloadStream (int h=-1)
- virtual ~PayloadStream (void)
- virtual bool Get (char \*buf, int &size)
- virtual bool Get (std::string &buf)
- virtual std::string Get (void)
- virtual bool Put (const char \*buf, int size)
- virtual bool Put (const std::string &buf)
- virtual bool Put (const char \*buf)
- virtual operator bool (void)
- virtual bool operator! (void)
- virtual int Timeout (void) const
- virtual void Timeout (int to)
- virtual int GetHandle (void)
- virtual int Pos (void) const

### **Protected Attributes**

- int timeout\_
- int handle\_
- bool seekable\_

# 5.90.1 Detailed Description

POSIX handle as Payload.

Thsi is an implementation of PayloadStreamInterface for generic POSIX handle.

### 5.90.2 Constructor & Destructor Documentation

# **5.90.2.1** Arc::PayloadStream::PayloadStream (int h = -1)

Constructor. Attaches to already open handle. Handle is not managed by this class and must be closed by external code.

#### **5.90.2.2 virtual Arc::PayloadStream::~PayloadStream (void)** [inline, virtual]

Destructor.

### 5.90.3 Member Function Documentation

### 5.90.3.1 virtual std::string Arc::PayloadStream::Get (void) [inline, virtual]

Read as many as possible (sane amount) of bytes.

Implements Arc::PayloadStreamInterface.

#### **5.90.3.2 virtual bool Arc::PayloadStream::Get (std::string & buf)** [virtual]

Read as many as possible (sane amount) of bytes into buf.

Implements Arc::PayloadStreamInterface.

### **5.90.3.3 virtual bool Arc::PayloadStream::Get (char** \* *buf*, int & *size*) [virtual]

Extracts information from stream up to 'size' bytes. 'size' contains number of read bytes on exit. Returns true in case of success.

Implements Arc::PayloadStreamInterface.

### **5.90.3.4 virtual int Arc::PayloadStream::GetHandle (void)** [inline, virtual]

Returns POSIX handle of the stream. This method is deprecated and will be removed soon. Currently it is only used by Transport Layer Security MCC.

# **5.90.3.5 virtual Arc::PayloadStream::operator bool (void)** [inline, virtual]

Returns true if stream is valid.

Implements Arc::PayloadStreamInterface.

#### 5.90.3.6 virtual bool Arc::PayloadStream::operator! (void) [inline, virtual]

Returns true if stream is invalid.

Implements Arc::PayloadStreamInterface.

# **5.90.3.7 virtual int Arc::PayloadStream::Pos (void) const** [inline, virtual]

Returns current position in stream if supported.

Implements Arc::PayloadStreamInterface.

#### **5.90.3.8 virtual bool Arc::PayloadStream::Put (const char \*** *buf***)** [inline, virtual]

Push null terminated information from 'buf' into stream. Returns true on success.

Implements Arc::PayloadStreamInterface.

## **5.90.3.9 virtual bool Arc::PayloadStream::Put (const std::string & buf)** [inline, virtual]

Push information from 'buf' into stream. Returns true on success.

Implements Arc::PayloadStreamInterface.

### **5.90.3.10 virtual bool Arc::PayloadStream::Put (const char** \* *buf*, int *size*) [virtual]

Push 'size' bytes from 'buf' into stream. Returns true on success.

Implements Arc::PayloadStreamInterface.

### **5.90.3.11 virtual void Arc::PayloadStream::Timeout (int** *to***)** [inline, virtual]

Set current timeout for Get() and Put() operations.

Implements Arc::PayloadStreamInterface.

### **5.90.3.12 virtual int Arc::PayloadStream::Timeout (void) const** [inline, virtual]

Query current timeout for Get() and Put() operations.

Implements Arc::PayloadStreamInterface.

# 5.90.4 Member Data Documentation

### **5.90.4.1** int Arc::PayloadStream::handle\_ [protected]

Timeout for read/write operations

### **5.90.4.2 bool Arc::PayloadStream::seekable** [protected]

Handle for operations

The documentation for this class was generated from the following file:


• PayloadStream.h

# 5.91 Arc::PayloadStreamInterface Class Reference

Stream-like Payload for Message object.

#include <PayloadStream.h>

Inheritance diagram for Arc::PayloadStreamInterface::



### **Public Member Functions**

- virtual bool Get (char \*buf, int &size)=0
- virtual bool Get (std::string &buf)=0
- virtual std::string Get (void)=0
- virtual bool Put (const char \*buf, int size)=0
- virtual bool Put (const std::string &buf)=0
- virtual bool Put (const char \*buf)=0
- virtual operator bool (void)=0
- virtual bool operator! (void)=0
- virtual int Timeout (void) const =0
- virtual void Timeout (int to)=0
- virtual int Pos (void) const =0

### 5.91.1 Detailed Description

Stream-like Payload for Message object.

This class is a virtual interface for managing stream-like source and destination. It's supposed to be passed through MCC chain as payload of Message. It must be treated by MCCs and Services as dynamic payload. This class is purely virtual.

## 5.91.2 Member Function Documentation

## **5.91.2.1 virtual std::string Arc::PayloadStreamInterface::Get (void)** [pure virtual]

Read as many as possible (sane amount) of bytes.

Implemented in Arc::PayloadStream.

### 5.91.2.2 virtual bool Arc::PayloadStreamInterface::Get (std::string & buf) [pure virtual]

Read as many as possible (sane amount) of bytes into buf.

Implemented in Arc::PayloadStream.

#### **5.91.2.3 virtual bool Arc::PayloadStreamInterface::Get (char** \* *buf*, int & *size*) [pure virtual]

Extracts information from stream up to 'size' bytes. 'size' contains number of read bytes on exit. Returns true in case of success.

Implemented in Arc::PayloadStream.

#### **5.91.2.4 virtual Arc::PayloadStreamInterface::operator bool (void)** [pure virtual]

Returns true if stream is valid.

Implemented in Arc::PayloadStream.

# **5.91.2.5 virtual bool Arc::PayloadStreamInterface::operator! (void)** [pure virtual]

Returns true if stream is invalid.

Implemented in Arc::PayloadStream.

#### **5.91.2.6 virtual int Arc::PayloadStreamInterface::Pos (void) const** [pure virtual]

Returns current position in stream if supported.

Implemented in Arc::PayloadStream.

#### **5.91.2.7 virtual bool Arc::PayloadStreamInterface::Put (const char** \* *buf*) [pure virtual]

Push null terminated information from 'buf' into stream. Returns true on success.

Implemented in Arc::PayloadStream.

# **5.91.2.8 virtual bool Arc::PayloadStreamInterface::Put (const std::string &** *buf***)** [pure virtual]

Push information from 'buf' into stream. Returns true on success.

Implemented in Arc::PayloadStream.

# **5.91.2.9 virtual bool Arc::PayloadStreamInterface::Put (const char** \* *buf*, **int** *size*) [pure virtual]

Push 'size' bytes from 'buf' into stream. Returns true on success.

Implemented in Arc::PayloadStream.

# **5.91.2.10 virtual void Arc::PayloadStreamInterface::Timeout (int** *to***)** [pure virtual]

Set current timeout for Get() and Put() operations.

Implemented in Arc::PayloadStream.

# **5.91.2.11 virtual int Arc::PayloadStreamInterface::Timeout (void) const** [pure virtual]

Query current timeout for Get() and Put() operations.

Implemented in Arc::PayloadStream.

The documentation for this class was generated from the following file:


• PayloadStream.h

# 5.92 Arc::PayloadWSRF Class Reference

This class combines MessagePayload with WSRF.

#include <PayloadWSRF.h>

Inheritance diagram for Arc::PayloadWSRF::



### **Public Member Functions**

- PayloadWSRF (const SOAPEnvelope &soap)
- PayloadWSRF (WSRF &wsrp)
- PayloadWSRF (const MessagePayload &source)
- operator WSRF & (void)
- operator bool (void)

#### **Protected Attributes**

- WSRF & wsrf
- bool owner\_

# 5.92.1 Detailed Description

This class combines MessagePayload with WSRF.

It's intention is to make it possible to pass WSRF messages through MCC chain as one more Payload type.

### 5.92.2 Constructor & Destructor Documentation

# 5.92.2.1 Arc::PayloadWSRF::PayloadWSRF (const SOAPEnvelope & soap)

Constructor - creates Message payload from SOAP message. Returns invalid WSRF if SOAP does not represent WS-ResourceProperties

### 5.92.2.2 Arc::PayloadWSRF::PayloadWSRF (WSRF & wsrp)

Constructor - creates Message payload with acquired WSRF message. WSRF message will be destroyed by destructor of this object.

# 5.92.2.3 Arc::PayloadWSRF::PayloadWSRF (const MessagePayload & source)

Constructor - creates WSRF message from payload. All classes derived from SOAPEnvelope are supported.

The documentation for this class was generated from the following file:


• PayloadWSRF.h

# 5.93 ArcSec::PDP Class Reference

Base class for Policy Decision Point plugins.

#include <PDP.h>

Inheritance diagram for ArcSec::PDP::



### **Public Member Functions**

- PDP (Arc::Config \*cfg)
- virtual bool **isPermitted** (Arc::Message \*msg)=0
- void **SetId** (std::string &id)
- std::string GetId ()

### **Protected Attributes**

• std::string id\_

# **Static Protected Attributes**

• static Arc::Logger logger

# **5.93.1** Detailed Description

Base class for Policy Decision Point plugins.

This virtual class defines method isPermitted() which processes security related information/attributes in Message and makes security decision - permit (true) or deny (false). Configuration of PDP is consumed during creation of instance through XML subtree fed to constructor.


The documentation for this class was generated from the following file:

• PDP.h

# 5.94 ArcSec::PeriodAttribute Class Reference

#include <DateTimeAttribute.h>

Inheritance diagram for ArcSec::PeriodAttribute::



#### **Public Member Functions**

- PeriodAttribute (const std::string &v, const std::string &i)
- virtual bool equal (AttributeValue \*other)
- virtual std::string encode ()
- ArcPeriod getValue ()
- virtual std::string getType ()
- virtual std::string getId ()

#### **Static Public Member Functions**

• static const std::string & getIdentifier (void)

# 5.94.1 Detailed Description

Formate: datetime"/"duration datetime"/"datetime duration"/"datetime

# **5.94.2** Member Function Documentation

# **5.94.2.1 virtual std::string ArcSec::PeriodAttribute::encode** () [virtual]

encode the value in a string format

Implements ArcSec::AttributeValue.

# **5.94.2.2 virtual bool ArcSec::PeriodAttribute::equal (AttributeValue** \* *other*) [virtual]

Evluate whether "this" equale to the parameter value

Implements ArcSec::AttributeValue.

### **5.94.2.3 virtual std::string ArcSec::PeriodAttribute::getId** () [inline, virtual]

Get the identifier of the <Attribute>

Implements ArcSec::AttributeValue.

# **5.94.2.4 virtual std::string ArcSec::PeriodAttribute::getType ()** [inline, virtual]

Get the type of the <Attribute>

Implements ArcSec::AttributeValue.

The documentation for this class was generated from the following file:


• DateTimeAttribute.h

# 5.95 ArcSec::PermitOverridesCombiningAlg Class Reference

Implement the "Permit-Overrides" algorithm.

#include <PermitOverridesAlg.h>

Inheritance diagram for ArcSec::PermitOverridesCombiningAlg::



#### **Public Member Functions**

- virtual Result combine (EvaluationCtx \*ctx, std::list< Policy \* > policies)
- virtual const std::string & getalgId (void) const

# 5.95.1 Detailed Description

Implement the "Permit-Overrides" algorithm.

Permit-Overrides, scans the policy set which is given as the parameters of "combine" method, if gets "permit" result from any policy, then stops scanning and gives "permit" as result, otherwise gives "deny".

# **5.95.2** Member Function Documentation

**5.95.2.1** virtual Result ArcSec::PermitOverridesCombiningAlg::combine (EvaluationCtx \* ctx, std::list< Policy \* > policies) [virtual]

If there is one policy which return positive evaluation result, then omit the other policies and return DECISION\_PERMIT

#### **Parameters:**

ctx This object contains request information which will be used to evaluated against policy.policlies This is a container which contains policy objects.

# **Returns:**

The combined result according to the algorithm.

Implements ArcSec::CombiningAlg.

# 5.95.2.2 virtual const std::string& ArcSec::PermitOverridesCombiningAlg::getalgId (void) const [inline, virtual]

Get the identifier

Implements ArcSec::CombiningAlg.

The documentation for this class was generated from the following file:


• PermitOverridesAlg.h

# 5.96 Arc::Plexer Class Reference

The Plexer class, used for routing messages to services.

#include <Plexer.h>

Inheritance diagram for Arc::Plexer::



# **Public Member Functions**

- Plexer (Config \*cfg)
- virtual ~Plexer ()
- virtual void Next (MCCInterface \*next, const std::string &label)
- virtual MCC\_Status process (Message &request, Message &response)

### **Static Public Attributes**

• static Arc::Logger logger

# 5.96.1 Detailed Description

The Plexer class, used for routing messages to services.

This is the Plexer class. Its purpose is to route incoming messages to appropriate Services and MCC chains.

# 5.96.2 Constructor & Destructor Documentation

# 5.96.2.1 Arc::Plexer::Plexer (Config \* cfg)

The constructor.

This is the constructor. Since all member variables are instances of "well-behaving" STL classes, nothing needs to be done.

### **5.96.2.2 virtual Arc::Plexer::~Plexer ()** [virtual]

The destructor.

This is the destructor. Since all member variables are instances of "well-behaving" STL classes, nothing needs to be done.

### **5.96.3** Member Function Documentation

# **5.96.3.1 virtual void Arc::Plexer::Next (MCCInterface** \* *next*, **const std::string &** *label*) [virtual]

Add reference to next MCC in chain.

This method is called by Loader for every potentially labeled link to next component which implements MCCInterface. If next is set NULL corresponding link is removed.

Reimplemented from Arc::MCC.

# **5.96.3.2 virtual MCC\_Status Arc::Plexer::process (Message & request, Message & response)**[virtual]

Route request messages to appropriate services.

Routes the request message to the appropriate service. Routing is based on the path part of value of the ENDPOINT attribute. Routed message is assigned following attributes: PLEXER:PATTERN - matched pattern, PLEXER:EXTENSION - last unmatched part of ENDPOINT path.

Reimplemented from Arc::MCC.

# 5.96.4 Member Data Documentation

### **5.96.4.1** Arc::Logger Arc::Plexer::logger [static]

A logger for MCCs.

A logger intended to be the parent of loggers in the different MCCs.

Reimplemented from Arc::MCC.

The documentation for this class was generated from the following file:

• Plexer.h

# 5.97 Arc::PlexerEntry Class Reference

A pair of label (regex) and pointer to service.

#include <Plexer.h>

# **Friends**

· class Plexer

# **5.97.1** Detailed Description

A pair of label (regex) and pointer to service.

A helper class that stores a label (regex) and a pointer to a service.

The documentation for this class was generated from the following file:


• Plexer.h

# 5.98 Arc::Plugin Class Reference

Base class for loadable ARC components.

#include <Plugin.h>

Inheritance diagram for Arc::Plugin::



# **5.98.1** Detailed Description

Base class for loadable ARC components.

All classes representing loadable ARC components must be either descendants of this class or be wrapped by its offspring.

The documentation for this class was generated from the following file:

# 5.99 Arc::PluginArgument Class Reference

Base class for passing arguments to loadable ARC components.

#include <Plugin.h>

# 5.99.1 Detailed Description

Base class for passing arguments to loadable ARC components.

During its creation constructor function of ARC loadable component expects instance of class inherited from this one or wrapped in it. Then dynamic type casting is used for obtaining class of expected kind.

The documentation for this class was generated from the following file:

# 5.100 Arc::PluginDescriptor Struct Reference

Description of ARC lodable component.

#include <Plugin.h>

# **Public Attributes**

- const char \* name
- const char \* kind
- uint32\_t version
- get\_plugin\_instance instance

# **5.100.1** Detailed Description

Description of ARC lodable component.


The documentation for this struct was generated from the following file:

# 5.101 Arc::PluginsFactory Class Reference

Generic ARC plugins loader.

#include <Plugin.h>

Inheritance diagram for Arc::PluginsFactory::



### **Public Member Functions**

- PluginsFactory (const Config &cfg)
- Plugin \* get\_instance (const std::string &kind, PluginArgument \*arg)
- Plugin \* get\_instance (const std::string &kind, int version, PluginArgument \*arg)
- Plugin \* get\_instance (const std::string &kind, int min\_version, int max\_version, PluginArgument \*arg)
- Plugin \* get\_instance (const std::string &kind, const std::string &name, PluginArgument \*arg)
- Plugin \* get\_instance (const std::string &kind, const std::string &name, int version, PluginArgument \*arg)
- Plugin \* get\_instance (const std::string &kind, const std::string &name, int min\_version, int max\_version, PluginArgument \*arg)
- bool load (const std::string &name)
- bool load (const std::string &name, const std::string &kind)
- bool **load** (const std::string &name, const std::list< std::string > &kinds)
- template<class P> P \* GetInstance (const std::string &kind, PluginArgument \*arg)
- template<class P> P \* **GetInstance** (const std::string &kind, const std::string &name, Plugin-Argument \*arg)

# 5.101.1 Detailed Description

Generic ARC plugins loader.

The instance of this class provides functionality of loading pluggable ARC components stored in shared libraries. For more information please check HED documentation.

# 5.101.2 Constructor & Destructor Documentation

### 5.101.2.1 Arc::PluginsFactory::PluginsFactory (const Config & cfg)

Constructor - accepts configuration (not yet used) meant to tune loading of modules.

### **5.101.3** Member Function Documentation

# 5.101.3.1 Plugin\* Arc::PluginsFactory::get\_instance (const std::string & kind, PluginArgument \* arg)

These methods load shared library named lib'name', locate plugin constructor functions of specified 'kind' and 'name' (if specified) and call it. Supplied argument affects way plugin instance is created in plugin-specific way. If name of plugin is not specified then all plugins of specified kind are tried with supplied argument till valid instance is created. All loaded plugins are also registered in internal list of this instance of PluginsFactory class. Returns created instance.

### 5.101.3.2 bool Arc::PluginsFactory::load (const std::string & name)

These methods load shared library named lib'name' and check if it contains ARC plugins of specified 'kind'. If there are no specified plugins or if library does not contain any plugins it is unloaded. All loaded plugins are also registered in internal list of this instance of PluginsFactory class. Returns true if library was loaded.


The documentation for this class was generated from the following file:

# 5.102 ArcSec::Policy Class Reference

Interface for containing and processing different types of policy.

#include <Policy.h>

Inheritance diagram for ArcSec::Policy::



### **Public Member Functions**

- Policy ()
- Policy (const Arc::XMLNode)
- Policy (const Arc::XMLNode, EvaluatorContext \*)
- virtual operator bool (void) const =0
- virtual MatchResult match (EvaluationCtx \*)=0
- virtual Result eval (EvaluationCtx \*)=0
- virtual void addPolicy (Policy \*pl)
- virtual void setEvaluatorContext (EvaluatorContext \*)
- virtual void make\_policy ()
- virtual std::string getEffect () const =0
- virtual EvalResult & getEvalResult ()=0
- virtual void setEvalResult (EvalResult &res)=0
- virtual const char \* getEvalName () const =0
- virtual const char \* getName () const =0

### **Protected Attributes**

• std::list< Policy \* > subelements

## **Static Protected Attributes**

• static Arc::Logger logger

# 5.102.1 Detailed Description

Interface for containing and processing different types of policy.

Basically, each policy object is a container which includes a few elements e.g., ArcPolicySet objects includes a few ArcPolicy objects; ArcPolicy object includes a few ArcRule objects. There is logical relationship between ArcRules or ArcPolicies, which is called combining algorithm. According to algorithm, evaluation results from the elements are combined, and then the combined evaluation result is returned to the up-level.

#### 5.102.2 Constructor & Destructor Documentation

**5.102.2.1** ArcSec::Policy::Policy() [inline]

Template constructor - creates empty policy.

**5.102.2.2** ArcSec::Policy::Policy (const Arc::XMLNode) [inline]

Template constructor - creates policy based on XML document.

If XML document is empty then empty policy is created. If it is not empty then it must be valid policy document - otherwise created object should be invalid.

5.102.2.3 ArcSec::Policy::Policy (const Arc::XMLNode, EvaluatorContext \*) [inline]

Template constructor - creates policy based on XML document.

If XML document is empty then empty policy is created. If it is not empty then it must be valid policy document - otherwise created object should be invalid. This constructor is based on the policy node and i the EvaluatorContext which includes the factory objects for combining algorithm and function

### **5.102.3** Member Function Documentation

**5.102.3.1 virtual void ArcSec::Policy::addPolicy (Policy \* pl)** [inline, virtual]

Add a policy element to into "this" object

**5.102.3.2 virtual Result ArcSec::Policy::eval (EvaluationCtx**\*) [pure virtual]

Evaluate policy For the <Rule> of Arc, only get the "Effect" from rules; For the <Policy> of Arc, combine the evaluation result from <Rule>; For the <Rule> of XACML, evaluate the <Condition> node by using information from request, and use the "Effect" attribute of <Rule>; For the <Policy> of XACML, combine the evaluation result from <Rule>

**5.102.3.3 virtual std::string ArcSec::Policy::getEffect () const** [pure virtual]

Get the "Effect" attribute

**5.102.3.4 virtual const char\* ArcSec::Policy::getEvalName () const** [pure virtual]

Get the name of Evaluator which can evaluate this policy

**5.102.3.5 virtual EvalResult & ArcSec::Policy::getEvalResult ()** [pure virtual]

Get eveluation result

**5.102.3.6 virtual const char\* ArcSec::Policy::getName() const** [pure virtual]

Get the name of this policy

**5.102.3.7 virtual void ArcSec::Policy::make\_policy** () [inline, virtual]

Parse XMLNode, and construct the low-level Rule object

5.102.3.8 virtual MatchResult ArcSec::Policy::match (EvaluationCtx \*) [pure virtual]

Evaluate whether the two targets to be evaluated match to each other.

**5.102.3.9 virtual ArcSec::Policy::operator bool (void) const** [pure virtual]

Returns true is object is valid.

**5.102.3.10 virtual void ArcSec::Policy::setEvalResult (EvalResult & res)** [pure virtual]

Set eveluation result

**5.102.3.11 virtual void ArcSec::Policy::setEvaluatorContext (EvaluatorContext \*)** [inline, virtual]

Set Evaluator Context for the usage in creating low-level policy object

The documentation for this class was generated from the following file:

• Policy.h

# 5.103 ArcSec::PolicyParser Class Reference

A interface which will isolate the policy object from actual policy storage (files, urls, database).

```
#include <PolicyParser.h>
```

#### **Public Member Functions**

virtual Policy \* parsePolicy (const Source &source, std::string policyclassname, EvaluatorContext \*ctx)

# 5.103.1 Detailed Description

A interface which will isolate the policy object from actual policy storage (files, urls, database).

Parse the policy from policy source (e.g. files, urls, database, etc.).

#### **5.103.2** Member Function Documentation

**5.103.2.1** virtual Policy\* ArcSec::PolicyParser::parsePolicy (const Source & source, std::string policyclassname, EvaluatorContext \* ctx) [virtual]

Parse policy

#### **Parameters:**

```
source location of the policy
policyclassname name of the policy for ClassLoader
ctx EvaluatorContext which includes the **Factory
```

The documentation for this class was generated from the following file:

· PolicyParser.h

# 5.104 ArcSec::PolicyStore Class Reference

Storage place for policy objects.

#include <PolicyStore.h>

#### **Public Member Functions**

- PolicyStore (const std::string &alg, const std::string &policyclassname, EvaluatorContext \*ctx)
- virtual std::list< PolicyElement > **findPolicy** (EvaluationCtx \*context)
- virtual void addPolicy (const Source &policy, EvaluatorContext \*ctx, const std::string &id)
- virtual void addPolicy (Policy \*policyobj, EvaluatorContext \*ctx, const std::string &id)
- virtual void removePolicies ()
- virtual void releasePolicies ()

#### Classes

· class PolicyElement

# 5.104.1 Detailed Description

Storage place for policy objects.

#### 5.104.2 Constructor & Destructor Documentation

5.104.2.1 ArcSec::PolicyStore::PolicyStore (const std::string & alg, const std::string & policyclassname, EvaluatorContext \* ctx)

Creates policy store with specified combing algorithm (alg - not used yet), policy name (policyclassname) and context (ctx)

The documentation for this class was generated from the following file:

• PolicyStore.h

# 5.105 Arc::RegularExpression Class Reference

A regular expression class.

#include <ArcRegex.h>

#### **Public Member Functions**

- RegularExpression ()
- RegularExpression (std::string pattern)
- RegularExpression (const RegularExpression &regex)
- ∼RegularExpression ()
- const RegularExpression & operator= (const RegularExpression & regex)
- bool isOk ()
- bool hasPattern (std::string str)
- bool match (const std::string &str) const
- bool match (const std::string &str, std::list< std::string > &unmatched, std::list< std::string > &matched) const
- std::string getPattern () const

# 5.105.1 Detailed Description

A regular expression class.

This class is a wrapper around the functions provided in regex.h.

# 5.105.2 Constructor & Destructor Documentation

**5.105.2.1** Arc::RegularExpression::RegularExpression() [inline]

default constructor

5.105.2.2 Arc::RegularExpression::RegularExpression (std::string pattern)

Creates a reges from a pattern string.

5.105.2.3 Arc::RegularExpression::RegularExpression (const RegularExpression & regex)

Copy constructor.

5.105.2.4 Arc::RegularExpression::~RegularExpression ()

Destructor.

### **5.105.3** Member Function Documentation

5.105.3.1 std::string Arc::RegularExpression::getPattern () const

Returns patter.

#### 5.105.3.2 bool Arc::RegularExpression::hasPattern (std::string str)

Returns true if this regex has the pattern provided.

#### 5.105.3.3 bool Arc::RegularExpression::isOk ()

Returns true if the pattern of this regex is ok.

# 5.105.3.4 bool Arc::RegularExpression::match (const std::string & str, std::list< std::string > & unmatched, std::list< std::string > & matched) const

Returns true if this regex matches the string provided. Unmatched parts of the string are stored in 'unmatched'. Matched parts of the string are stored in 'matched'.

#### 5.105.3.5 bool Arc::RegularExpression::match (const std::string & str) const

Returns true if this regex matches whole string provided.

# 5.105.3.6 const RegularExpression& Arc::RegularExpression::operator= (const RegularExpression & regex)

Assignment operator.

The documentation for this class was generated from the following file:


· ArcRegex.h

# 5.106 ArcSec::Request Class Reference

Base class/Interface for request, includes a container for RequestItems and some operations.

#include <Request.h>

Inheritance diagram for ArcSec::Request::



#### **Public Member Functions**

- virtual ReqItemList getRequestItems () const =0
- virtual void setRequestItems (ReqItemList sl)=0
- virtual void addRequestItem (Attrs &sub, Attrs &res, Attrs &act, Attrs &ctx)=0
- virtual void setAttributeFactory (AttributeFactory \*attributefactory)=0
- virtual void make\_request ()=0
- virtual const char \* getEvalName () const =0
- virtual const char \* getName () const =0
- Request ()
- Request (const Source &)

#### **Protected Attributes**

• ReqItemList rlist

# 5.106.1 Detailed Description

Base class/Interface for request, includes a container for RequestItems and some operations.

A Request object can has a few <subjects, actions, objects> tuples, i.e. RequestItem The Request class and any customized class which inherit from it, should be loadable, which means these classes can be dynamically loaded according to the configuration informtation, see the example configuration below: <Service name="pdp.service" id="pdp\_service"> <pdp:PDPConfig> <......> <pdp:Request name="arc.request" /> <.....> </pdp:PDPConfig> </Service>

There can be different types of subclass which inherit Request, such like XACMLRequest, ArcRequest, GACLRequest

#### 5.106.2 Constructor & Destructor Documentation

**5.106.2.1** ArcSec::Request::Request() [inline]

Default constructor

**5.106.2.2** ArcSec::Request::Request (const Source &) [inline]

Constructor: Parse request information from a xml stucture in memory

#### **5.106.3** Member Function Documentation

5.106.3.1 virtual void ArcSec::Request::addRequestItem (Attrs & sub, Attrs & res, Attrs & act, Attrs & ctx) [pure virtual]

Add request tuple from non-XMLNode

**5.106.3.2 virtual const char\* ArcSec::Request::getEvalName () const** [pure virtual]

Get the name of corresponding evaulator

**5.106.3.3 virtual const char\* ArcSec::Request::getName () const** [pure virtual]

Get the name of this request

**5.106.3.4 virtual ReqItemList ArcSec::Request::getRequestItems () const** [pure virtual]

Get all the RequestItem inside RequestItem container

**5.106.3.5 virtual void ArcSec::Request::make\_request()** [pure virtual]

Create the objects included in Request according to the node attached to the Request object

**5.106.3.6 virtual void ArcSec::Request::setAttributeFactory (AttributeFactory \* attributefactory)**[pure virtual]

Set the attribute factory for the usage of Request

**5.106.3.7 virtual void ArcSec::Request::setRequestItems (ReqItemList s1)** [pure virtual]

Set the content of the container

The documentation for this class was generated from the following file:

• Request.h

# 5.107 ArcSec::RequestAttribute Class Reference

Wrapper which includes Attribute Value object which is generated according to date type of one spefic node in Request.xml.

#include <RequestAttribute.h>

#### **Public Member Functions**

- RequestAttribute (Arc::XMLNode &node, AttributeFactory \*attrfactory)
- Arc::XMLNode getNode ()
- std::string **getAttributeId** () const
- void **setAttributeId** (const std::string attributeId)
- std::string **getDataType** () const
- void **setDataType** (const std::string dataType)
- std::string **getIssuer** () const
- void **setIssuer** (const std::string issuer)
- virtual AttributeValue \* getAttributeValue () const
- virtual AttributeFactory \* getAttributeFactory () const
- RequestAttribute & duplicate (RequestAttribute &)

# 5.107.1 Detailed Description

Wrapper which includes Attribute Value object which is generated according to date type of one spefic node in Request.xml.

### 5.107.2 Constructor & Destructor Documentation

5.107.2.1 ArcSec::RequestAttribute::RequestAttribute (Arc::XMLNode & node, AttributeFactory \* attrfactory)

Constructor - create attribute value object according to the "Type" in the node <Attribute attributeid="urn:arc:subject:voms-attribute" type="string">urn:mace:shibboleth:examples</Attribute>

# **5.107.3** Member Function Documentation

#### 5.107.3.1 RequestAttribute & ArcSec::RequestAttribute::duplicate (RequestAttribute &)

Duplicate the parameter into "this"

The documentation for this class was generated from the following file:

· RequestAttribute.h

# 5.108 ArcSec::RequestItem Class Reference

Interface for request item container, < subjects, actions, objects, ctxs> tuple.

#include <RequestItem.h>

#### **Public Member Functions**

- RequestItem (Arc::XMLNode &, AttributeFactory \*)
- virtual SubList **getSubjects** () const =0
- virtual void **setSubjects** (const SubList &sl)=0
- virtual ResList **getResources** () const =0
- virtual void **setResources** (const ResList &rl)=0
- virtual ActList **getActions** () const =0
- virtual void **setActions** (const ActList &al)=0
- virtual CtxList **getContexts** () const =0
- virtual void **setContexts** (const CtxList &ctx)=0

#### **Protected Attributes**

- SubList subjects
- · ResList actions
- ActList resources
- CtxList contexts

# 5.108.1 Detailed Description

Interface for request item container, < subjects, actions, objects, ctxs> tuple.

# 5.108.2 Constructor & Destructor Documentation

**5.108.2.1** ArcSec::RequestItem::RequestItem (Arc::XMLNode &, AttributeFactory \*) [inline]

Constructor

#### **Parameters:**

node The XMLNode structure of the request itemattributefactory The AttributeFactory which will be used to generate RequestAttribute

The documentation for this class was generated from the following file:

· RequestItem.h

# 5.109 ArcSec::RequestTuple Class Reference

RequestTuple, container which includes the.

#include <EvaluationCtx.h>

# **Public Member Functions**

- RequestTuple & duplicate (const RequestTuple &)
- Arc::XMLNode & getNode ()
- void erase ()

# **Public Attributes**

- Subject sub
- Resource res
- Action act
- Context ctx

# 5.109.1 Detailed Description

RequestTuple, container which includes the.

The documentation for this class was generated from the following file:

• EvaluationCtx.h

# 5.110 ArcSec::Response Class Reference

Container for the evaluation results.

#include <Response.h>

# **Public Member Functions**

- void setRequestSize (int size)
- int getRequestSize ()
- virtual ResponseList & getResponseItems ()
- virtual void **setResponseItems** (const ResponseList &rl)
- virtual void addResponseItem (ResponseItem \*respitem)

# **Protected Attributes**

• ResponseList rlist

# 5.110.1 Detailed Description

Container for the evaluation results.

The documentation for this class was generated from the following file:

· Response.h

# 5.111 ArcSec::ResponseItem Struct Reference

Evaluation result concerning one RequestTuple.

#include <Response.h>

# **Public Attributes**

- RequestTuple \* reqtp
- Result res
- Arc::XMLNode reqxml
- Policies pls
- std::list< Arc::XMLNode > plsxml

# 5.111.1 Detailed Description

Evaluation result concerning one RequestTuple.

Include the RequestTuple, related XMLNode, the set of policy objects which give positive evaluation result, and the related XMLNode

The documentation for this struct was generated from the following file:

· Response.h

# 5.112 Arc::Run Class Reference

#include <Run.h>

# **Public Member Functions**

- Run (const std::string &cmdline)
- Run (const std::list< std::string > &argv)
- ∼Run (void)
- operator bool (void)
- bool operator! (void)
- bool Start (void)
- bool Wait (int timeout)
- bool Wait (void)
- int Result (void)
- bool Running (void)
- int ReadStdout (int timeout, char \*buf, int size)
- int ReadStderr (int timeout, char \*buf, int size)
- int WriteStdin (int timeout, const char \*buf, int size)
- void AssignStdout (std::string &str)
- void AssignStderr (std::string &str)
- void AssignStdin (std::string &str)
- void KeepStdout (bool keep=true)
- void KeepStderr (bool keep=true)
- void KeepStdin (bool keep=true)
- void CloseStdout (void)
- void CloseStderr (void)
- void CloseStdin (void)
- void **AssignInitializer** (void(\*initializer\_func)(void \*), void \*initializer\_arg)
- void **AssignKicker** (void(\*kicker\_func)(void \*), void \*kicker\_arg)
- void AssignWorkingDirectory (std::string &wd)
- void Kill (int timeout)

#### **Protected Member Functions**

- bool stdout handler (Glib::IOCondition cond)
- bool stderr\_handler (Glib::IOCondition cond)
- $\bullet \ bool \ \textbf{stdin\_handler} \ (Glib::IOCondition \ cond)\\$
- void **child\_handler** (Glib::Pid pid, int result)

#### **Protected Attributes**

- std::string working\_directory
- int stdout\_
- int stderr
- int stdin\_
- std::string \* stdout\_str\_
- std::string \* stderr\_str\_
- std::string \* stdin\_str\_

- bool stdout\_keep\_
- · bool stderr\_keep\_
- bool stdin\_keep\_
- sigc::connection stdout\_conn\_
- sigc::connection stderr\_conn\_
- sigc::connection stdin\_conn\_
- sigc::connection child\_conn\_
- Arc::Pid \* **pid\_**
- Glib::ArrayHandle< std::string > argv\_
- void(\* initializer\_func\_ )(void \*)
- void \* initializer\_arg\_
- void(\* kicker\_func\_ )(void \*)
- void \* kicker\_arg\_
- bool started\_
- bool running\_
- int result\_
- Glib::Mutex lock\_
- Glib::Cond cond

#### **Friends**

· class RunPump

# 5.112.1 Detailed Description

This class runs external executable. It is possible to read/write it's standard handles or to redirect then to std::string elements.

# 5.112.2 Constructor & Destructor Documentation

#### 5.112.2.1 Arc::Run::Run (const std::string & cmdline)

Constructor preapres object to run cmdline

#### 5.112.2.2 Arc::Run::Run (const std::list< std::string > & argv)

Constructor preapres object to run executable and arguments specified in argv

#### 5.112.2.3 Arc::Run::∼Run (void)

Destructor kill running executable and releases associated resources

# **5.112.3** Member Function Documentation

# 5.112.3.1 void Arc::Run::AssignStderr (std::string & str)

Associate stderr handle of executable with string. This method must be called before Start(). str object must be valid as long as this object exists.

#### 5.112.3.2 void Arc::Run::AssignStdin (std::string & str)

Associate stdin handle of executable with string. This method must be called before Start(). str object must be valid as long as this object exists.

#### 5.112.3.3 void Arc::Run::AssignStdout (std::string & str)

Associate stdout handle of executable with string. This method must be called before Start(). str object must be valid as long as this object exists.

#### **5.112.3.4 void Arc::Run::AssignWorkingDirectory (std::string & wd)** [inline]

Assign working directrry of the running process

#### 5.112.3.5 void Arc::Run::CloseStderr (void)

Closes pipe associated with stderr handle

#### 5.112.3.6 void Arc::Run::CloseStdin (void)

Closes pipe associated with stdin handle

#### 5.112.3.7 void Arc::Run::CloseStdout (void)

Closes pipe associated with stdout handle

#### **5.112.3.8 void** Arc::Run::KeepStderr (bool *keep* = true)

Keep stderr same as parent's if keep = true

#### **5.112.3.9 void** Arc::Run::KeepStdin (bool *keep* = true)

Keep stdin same as parent's if keep = true

#### 5.112.3.10 void Arc::Run::KeepStdout (bool keep = true)

Keep stdout same as parent's if keep = true

#### 5.112.3.11 void Arc::Run::Kill (int timeout)

Kill running executable. First soft kill signal (SIGTERM) is sent to executable. If after timeout seconds executable is still running it's killed completely. Curently this method does not work for Windows OS

# **5.112.3.12** Arc::Run::operator bool (void) [inline]

Returns true if object is valid

#### **5.112.3.13** bool Arc::Run::operator! (void) [inline]

Returns true if object is invalid

#### 5.112.3.14 int Arc::Run::ReadStderr (int timeout, char \* buf, int size)

Read from stderr handle of running executable. This method may be used while stderr is directed to string. But result is unpredictable.

#### 5.112.3.15 int Arc::Run::ReadStdout (int timeout, char \* buf, int size)

Read from stdout handle of running executable. This method may be used while stdout is directed to string. But result is unpredictable.

#### **5.112.3.16** int Arc::Run::Result (void) [inline]

Returns exit code of execution.

#### 5.112.3.17 bool Arc::Run::Running (void)

Return true if execution is going on.

#### 5.112.3.18 bool Arc::Run::Start (void)

Starts running executable. This method may be called only once.

#### 5.112.3.19 bool Arc::Run::Wait (void)

Wait till execution finished

# 5.112.3.20 bool Arc::Run::Wait (int timeout)

Wait till execution finished or till timeout seconds expires. Returns true if execution is complete.

# 5.112.3.21 int Arc::Run::WriteStdin (int timeout, const char \* buf, int size)

Write to stdin handle of running executable. This method may be used while stdin is directed to string. But result is unpredictable.

The documentation for this class was generated from the following file:

• Run.h

# **5.113** RuntimeEnvironment Class Reference

#include <runtimeenvironment.h>

# **Public Member Functions**

- RuntimeEnvironment (const std::string &re)
- ~RuntimeEnvironment ()
- std::string str () const
- std::string Name () const
- std::string Version () const
- bool operator== (const RuntimeEnvironment &other) const
- bool operator!= (const RuntimeEnvironment &other) const
- bool operator> (const RuntimeEnvironment &other) const
- bool operator< (const RuntimeEnvironment &other) const
- bool operator>= (const RuntimeEnvironment &other) const
- bool operator<= (const RuntimeEnvironment &other) const

# 5.113.1 Detailed Description

RuntimeEnvironment class. It represents a runtime environment, and provides functionality for getting information about them.

#### 5.113.2 Constructor & Destructor Documentation

# 5.113.2.1 RuntimeEnvironment::RuntimeEnvironment (const std::string & re)

Constructs a new runtime environemt. String should in general be of the type: STRING-VERSION. Where version consists of numbers with . between them.

#### **5.113.2.2** RuntimeEnvironment::~RuntimeEnvironment()

Destructor. Not that much to say.

#### **5.113.3** Member Function Documentation

#### 5.113.3.1 std::string RuntimeEnvironment::Name () const

Returns the name of the runtime environment.

#### 5.113.3.2 bool RuntimeEnvironment::operator!= (const RuntimeEnvironment & other) const

Inequility operator. Return the opsite of ==

#### 5.113.3.3 bool RuntimeEnvironment::operator< (const RuntimeEnvironment & other) const

Less than operator. Returns false if the other is equal, otherwise it returns the opposite of >

5.113.3.4 bool RuntimeEnvironment::operator<= (const RuntimeEnvironment & other) const

Less than or equal operator. Returns the oppsite of >

5.113.3.5 bool RuntimeEnvironment::operator== (const RuntimeEnvironment & other) const

Equliaty operator. Returns true if the runtime environments have the string representation.

5.113.3.6 bool RuntimeEnvironment::operator> (const RuntimeEnvironment & other) const

Greater than operator. Returns true if the compared runtime environment is greater than the current.

5.113.3.7 bool RuntimeEnvironment::operator>= (const RuntimeEnvironment & other) const

Greater or equal operator. Returns the opposite of <

#### 5.113.3.8 std::string RuntimeEnvironment::str () const

Returns a string representation of the runtime environment. This is usually the same as given in the constructor.

#### 5.113.3.9 std::string RuntimeEnvironment::Version () const

Returns the version of the runtime environment.


The documentation for this class was generated from the following file:

• runtimeenvironment.h

# 5.114 RuntimeEnvironmentError Class Reference

#include <runtimeenvironment.h>

Inheritance diagram for RuntimeEnvironmentError::



#### **Public Member Functions**

• RuntimeEnvironmentError (std::string message)

# **5.114.1** Detailed Description

RuntimeEnvironment exceptions. Gets thrown when an error occurs regarding a runtime environment.

#### 5.114.2 Constructor & Destructor Documentation

# **5.114.2.1** RuntimeEnvironmentError::RuntimeEnvironmentError (std::string message) [inline]

Standard exception class constructor.

The documentation for this class was generated from the following file:

• runtimeenvironment.h

# 5.115 Arc::SAMLToken Class Reference

Class for manipulating SAML Token Profile.

#include <SAMLToken.h>

# **Public Types**

- SAML1
- · SAML2
- enum SAMLVersion { SAML1, SAML2 }

#### **Public Member Functions**

- SAMLToken (SOAPEnvelope &soap)
- SAMLToken (SOAPEnvelope &soap, const std::string &certfile, const std::string &keyfile, SAM-LVersion saml\_version=SAML2)
- ∼SAMLToken (void)
- operator bool (void)
- bool Authenticate (const std::string &cafile, const std::string &capath)
- bool Authenticate (void)

# 5.115.1 Detailed Description

Class for manipulating SAML Token Profile.

This class is for generating/consuming SAML Token profile. See WS-Security SAML Token Profile v1.1 (www.oasis-open.org/committees/wss) Currently this class is used by samltoken handler (will appears in src/hed/pdc/samltokensh/) It is not a must to directly called this class. If we need to use SAML Token functionality, we only need to configure the samltoken handler into service and client. Currently, only a minor part of the specification has been implemented.

About how to identify and reference security token for signing message, currently, only the "SAML Assertion Referenced from KeyInfo" (part 3.4.2 of WS-Security SAML Token Profile v1.1 specification) is supported, which means the implementation can only process SAML assertion "referenced from KeyInfo", and also can only generate SAML Token with SAML assertion "referenced from KeyInfo". More complete support need to implement.

About subject confirmation method, the implementation can process "hold-of-key" (part 3.5.1 of WS-Security SAML Token Profile v1.1 specification) subject subject confirmation method.

About SAML vertion, the implementation can process SAML assertion with SAML version 1.1 and 2.0; can only generate SAML assertion with SAML vertion 2.0.

In the SAML Token profile, for the hold-of-key subject confirmation method, there are three interaction parts: the attesting entity, the relying party and the issuing authority. In the hold-of-key subject confirmation method, it is the attesting entity's subject identity which will be inserted into the SAML assertion.

Firstly the attesting entity authenticates to issuing authority by using some authentication scheme such as WSS x509 Token profile (Alterbatively the usename/password authentication scheme or other different authentication scheme can also be used, unless the issuing authority can retrive the key from a trusted certificate server after firmly establishing the subject's identity under the username/password scheme). So then issuing authority is able to make a definitive statement (sign a SAML assertion) about an act of authentication that has already taken place.

The attesting entity gets the SAML assertion and then signs the soap message together with the assertion by using its private key (the relevant certificate has been authenticated by issuing authority, and its relevant public key has been put into SubjectConfirmation element under saml assertion by issuing authority. Only the actual owner of the saml assertion can do this, as only the subject possesses the private key paired with the public key in the assertion. This establishes an irrefutable connection between the author of the SOAP message and the assertion describing an authentication event.)

The relying party is supposed to trust the issuing authority. When it receives a message from the asserting entity, it will check the saml assertion based on its predetermined trust relationship with the SAML issuing authority, and check the signature of the soap message based on the public key in the saml assertion without directly trust relationship with attesting entity (subject owner).

#### **5.115.2** Member Enumeration Documentation

#### 5.115.2.1 enum Arc::SAMLToken::SAMLVersion

Since the specification SAMLVersion is for distinguishing two types of saml version. It is used as the parameter of constructor.

#### **5.115.3** Constructor & Destructor Documentation

#### 5.115.3.1 Arc::SAMLToken::SAMLToken (SOAPEnvelope & soap)

Constructor. Parse SAML Token information from SOAP header. SAML Token related information is extracted from SOAP header and stored in class variables. And then it the SAMLToken object will be used for authentication.

#### **Parameters:**

soap The SOAP message which contains the SAMLToken in the soap header

# 5.115.3.2 Arc::SAMLToken::SAMLToken (SOAPEnvelope & soap, const std::string & certfile, const std::string & keyfile, SAMLVersion saml\_version = SAML2)

Constructor. Add SAML Token information into the SOAP header. Generated token contains elements SAML token and signature, and is meant to be used for authentication on the consuming side. This constructor is for a specific SAML Token profile usage, in which the attesting entity signs the SAML assertion for itself (self-sign). This usage implicitly requires that the relying party trust the attesting entity. More general (requires issuing authority) usage will be provided by other constructor. And the under-developing SAML service will be used as the issuing authority.

#### **Parameters:**

soap The SOAP message to which the SAML Token will be inserted.certfile The certificate file.keyfile The key file which will be used to create signature.samlversion The SAML version, only SAML2 is supported currently.

#### 5.115.3.3 Arc::SAMLToken::~SAMLToken (void)

Deconstructor. Nothing to be done except finalizing the xmlsec library.

#### **5.115.4** Member Function Documentation

#### 5.115.4.1 bool Arc::SAMLToken::Authenticate (void)

Check signature by using the cert information in soap message

# 5.115.4.2 bool Arc::SAMLToken::Authenticate (const std::string & cafile, const std::string & capath)

Check signature by using the trusted certificates It is used by relying parting after calling SAMLTo-ken(SOAPEnvelope& soap) This method will check the SAML assertion based on the trusted certificated specified as parameter cafile or capath; and also check the signature to soap message (the signature is generated by attesting entity by signing soap body together witl SAML assertion) by using the public key inside SAML assertion.

#### **Parameters:**

cafile ca filecapath ca directory

#### 5.115.4.3 Arc::SAMLToken::operator bool (void)

Returns true of constructor succeeded

The documentation for this class was generated from the following file:


• SAMLToken.h

# 5.116 Arc::SecAttr Class Reference

This is an abstract interface to a security attribute.

#include <SecAttr.h>

Inheritance diagram for Arc::SecAttr::



#### **Public Member Functions**

- SecAttr ()
- bool operator== (const SecAttr &b) const
- bool operator!= (const SecAttr &b) const
- virtual operator bool () const
- virtual bool Export (SecAttrFormat format, std::string &val) const
- virtual bool Export (SecAttrFormat format, XMLNode &val) const
- virtual bool Import (SecAttrFormat format, const std::string &val)
- virtual bool **Import** (SecAttrFormat format, const XMLNode &val)

### **Static Public Attributes**

- static SecAttrFormat UNDEFINED
- static SecAttrFormat ARCAuth
- static SecAttrFormat XACML
- static SecAttrFormat SAML
- static SecAttrFormat GACL

#### **Protected Member Functions**

• virtual bool equal (const SecAttr &b) const

# 5.116.1 Detailed Description

This is an abstract interface to a security attribute.

This class is meant to be inherited to implement security attributes. Depending on what data it needs to store inheriting classes may need to implement constructor and destructor. They must however override the equality and the boolean operators. The equality is meant to compare security attributes. The prototype implies that all attributes are comparable to all others. This behaviour should be modified as needed by using dynamic\_cast operations. The boolean cast operation is meant to embody "nullness" if that is applicable to the particular type.

#### 5.116.2 Constructor & Destructor Documentation

#### **5.116.2.1** Arc::SecAttr::SecAttr() [inline]

representation for GACL policy

#### **5.116.3** Member Function Documentation

# 5.116.3.1 virtual bool Arc::SecAttr::Export (SecAttrFormat format, XMLNode & val) const [virtual]

Convert internal structure into specified format. Returns false if format is not supported/suitable for this attribute. XML node referenced by is turned into top level element of specified format.

Reimplemented in Arc::MultiSecAttr.

# **5.116.3.2** virtual bool Arc::SecAttr::Export (SecAttrFormat format, std::string & val) const [virtual]

Convert internal structure into specified format. Returns false if format is not supported/suitable for this attribute.

# 5.116.3.3 virtual bool Arc::SecAttr::Import (SecAttrFormat format, const std::string & val) [virtual]

Fills internal structure from external object of specified format. Retrns false if failed to do. The usage pattern for this method is not defined and it is provided only to make class symmetric. Hence it's implementation is not required yet.

#### **5.116.3.4 virtual Arc::SecAttr::operator bool () const** [virtual]

This function should return false if the value is to be considered null, e.g. if it hasn't been set or initialized. In other cases it should return true.

Reimplemented in Arc::MultiSecAttr.

#### 5.116.3.5 bool Arc::SecAttr::operator!= (const SecAttr & b) const [inline]

This is a convenience function to allow the usage of "not equal" conditions and need not be overridden.

### 5.116.3.6 bool Arc::SecAttr::operator== (const SecAttr & b) const [inline]

This function should (in inheriting classes) return true if this and b are considered to represent same content. Identifying and restricting the type of b should be done using dynamic\_cast operations. Currently it is not defined how comparison methods to be used. Hence their implementation is not required.

# **5.116.4** Member Data Documentation

# **5.116.4.1 SecAttrFormat Arc::SecAttr::ARCAuth** [static]

own serialization/deserialization format

# **5.116.4.2 SecAttrFormat Arc::SecAttr::GACL** [static]

suitable for inclusion into SAML structures

# **5.116.4.3 SecAttrFormat Arc::SecAttr::SAML** [static]

represenation for XACML policy

# **5.116.4.4 SecAttrFormat Arc::SecAttr::XACML** [static]

representation for ARC authorization policy

The documentation for this class was generated from the following file:

• SecAttr.h

# 5.117 Arc::SecAttrFormat Class Reference

Export/import format.

#include <SecAttr.h>

# **Public Member Functions**

- SecAttrFormat (const SecAttrFormat &format)
- **SecAttrFormat** (const char \*format="")
- SecAttrFormat operator= (SecAttrFormat format)
- SecAttrFormat operator= (const char \*format)
- bool **operator**== (SecAttrFormat format)
- bool **operator==** (const char \*format)
- bool **operator!=** (SecAttrFormat format)
- bool **operator!=** (const char \*format)

# 5.117.1 Detailed Description

Export/import format.

Format is identified by textual identity string. Class description includes basic formats only. That list may be extended.

The documentation for this class was generated from the following file:


• SecAttr.h

# 5.118 Arc::SecAttrValue Class Reference

This is an abstract interface to a security attribute.

#include <SecAttrValue.h>

Inheritance diagram for Arc::SecAttrValue::



#### **Public Member Functions**

- bool operator== (SecAttrValue &b)
- bool operator!= (SecAttrValue &b)
- virtual operator bool ()

#### **Protected Member Functions**

• virtual bool equal (SecAttrValue &b)

# 5.118.1 Detailed Description

This is an abstract interface to a security attribute.

This class is meant to be inherited to implement security attributes. Depending on what data it needs to store inheriting classes may need to implement constructor and destructor. They must however override the equality and the boolean operators. The equality is meant to compare security attributes. The prototype implies that all attributes are comparable to all others. This behaviour should be modified as needed by using dynamic\_cast operations. The boolean cast operation is meant to embody "nullness" if that is applicable to the particular type.

#### **5.118.2** Member Function Documentation

#### **5.118.2.1 virtual Arc::SecAttrValue::operator bool** () [virtual]

This function should return false if the value is to be considered null, e g if it hasn't been set or initialized. In other cases it should return true.

Reimplemented in Arc::CIStringValue.

#### 5.118.2.2 bool Arc::SecAttrValue::operator!= (SecAttrValue & b)

This is a convenience function to allow the usage of "not equal" conditions and need not be overridden.

# 5.118.2.3 bool Arc::SecAttrValue::operator== (SecAttrValue & b)

This function should (in inheriting classes) return true if this and b are considered to be the same. Identifying and restricting the type of b should be done using dynamic\_cast operations.

The documentation for this class was generated from the following file:


• SecAttrValue.h

# 5.119 ArcSec::SecHandler Class Reference

Base class for simple security handling plugins.

#include <SecHandler.h>

Inheritance diagram for ArcSec::SecHandler::



#### **Public Member Functions**

- SecHandler (Arc::Config \*)
- virtual bool **Handle** (Arc::Message \*msg)=0

#### **Static Protected Attributes**

• static Arc::Logger logger

# 5.119.1 Detailed Description

Base class for simple security handling plugins.

This virtual class defines method Handle() which processes security related information/attributes in Message and optionally makes security decision. Instances of such classes are normally arranged in chains abd are called on incoming and outgoing messages in various MCC and Service plugins. Return value of Handle() defines either processing should continie (true) or stop with error (false). Configuration of SecHandler is consumed during creation of instance through XML subtree fed to constructor.

The documentation for this class was generated from the following file:

· SecHandler.h

# 5.120 ArcSec::Security Class Reference

Common stuff used by security related slasses.

#include <Security.h>

# **Friends**

- class SecHandler
- class PDP

# **5.120.1** Detailed Description

Common stuff used by security related slasses.

This class is just a place where to put common stuff that is used by security related slasses. So far it only contains a logger.

The documentation for this class was generated from the following file:


• Security.h

# 5.121 Arc::Service Class Reference

Service - last component in a Message Chain.

#include <Service.h>

Inheritance diagram for Arc::Service::



#### **Public Member Functions**

- Service (Arc::Config \*)
- virtual void AddSecHandler (Arc::Config \*cfg, ArcSec::SecHandler \*sechandler, const std::string &label="")
- virtual bool RegistrationCollector (Arc::XMLNode &doc)
- virtual std::string getID ()

#### **Protected Member Functions**

• bool ProcessSecHandlers (Arc::Message &message, const std::string &label="")

#### **Protected Attributes**

• std::map< std::string, std::list< ArcSec::SecHandler \* > > sechandlers\_

#### **Static Protected Attributes**

• static Logger logger

# **5.121.1** Detailed Description

Service - last component in a Message Chain.

This class which defines interface and common functionality for every Service plugin. Interface is made of method process() which is called by Plexer or MCC class. There is one Service object created for every service description processed by Loader class objects. Classes derived from Service class must implement process() method of MCCInterface. It is up to developer how internal state of service is stored and communicated to other services and external utilities. Service is free to expect any type of payload passed to it and generate any payload as well. Useful types depend on MCCs in chain which leads to that service. For example if service is expected to by linked to SOAP MCC it must accept and generate messages with PayloadSOAP payload. Method process() of class derived from Service class may be called concurently in multiple threads. Developers must take that into account and write thread-safe implementation. Simple

example of service is provided in /src/tests/echo/echo.cpp of source tree. The way to write client couterpart of corresponding service is undefined yet. For example see /src/tests/echo/test.cpp .

#### 5.121.2 Constructor & Destructor Documentation

#### **5.121.2.1** Arc::Service::Service (Arc::Config \*) [inline]

Example contructor - Server takes at least it's configuration subtree

#### **5.121.3** Member Function Documentation

# 5.121.3.1 virtual void Arc::Service::AddSecHandler (Arc::Config \* cfg, ArcSec::SecHandler \* sechandler, const std::string & label = "") [virtual]

Add security components/handlers to this MCC. For more information please see description of MCC::AddSecHandler

#### **5.121.3.2 virtual std::string Arc::Service::getID ()** [inline, virtual]

Service may implement own service identitifer gathering method. This method return identifier of service which is used for registering it Information Services.

# **5.121.3.3 bool** Arc::Service::ProcessSecHandlers (Arc::Message & message, const std::string & label = "") [protected]

Executes security handlers of specified queue. For more information please see description of MCC::ProcessSecHandlers

#### **5.121.3.4 virtual bool Arc::Service::RegistrationCollector (Arc::XMLNode & doc)** [virtual]

Service specific registartion collector, used for generate service registartions. In implemented service this method should generate GLUE2 document with part of service description which service wishes to advertise to Information Services.

#### 5.121.4 Member Data Documentation

#### **5.121.4.1 Logger Arc::Service::logger** [static, protected]

Logger object used to print messages generated by this class.

# **5.121.4.2 std::map<std::list<ArcSec::SecHandler\*>> Arc::Service::sechandlers\_**[protected]

Set of labeled authentication and authorization handlers. MCC calls sequence of handlers at specific point depending on associated identifier. in most aces those are "in" and "out" for incoming and outgoing messages correspondingly.

The documentation for this class was generated from the following file:

• Service.h

# 5.122 Arc::SimpleCondition Class Reference

Simple triggered condition.

#include <Thread.h>

# **Public Member Functions**

- void lock (void)
- void unlock (void)
- void signal (void)
- void signal\_nonblock (void)
- void broadcast (void)
- void wait (void)
- void wait\_nonblock (void)
- bool wait (int t)
- void reset (void)

# **5.122.1** Detailed Description

Simple triggered condition.

Provides condition and semaphor objects in one element.

# **5.122.2** Member Function Documentation

# **5.122.2.1** void Arc::SimpleCondition::broadcast (void) [inline]

Signal about condition to all waiting threads

```
5.122.2.2 void Arc::SimpleCondition::lock (void) [inline]
```

Acquire semaphor

**5.122.2.3 void Arc::SimpleCondition::reset** (**void**) [inline]

Reset object to initial state

**5.122.2.4 void Arc::SimpleCondition::signal** (**void**) [inline]

Signal about condition

#### **5.122.2.5 void Arc::SimpleCondition::signal\_nonblock (void)** [inline]

Signal about condition without using semaphor

# **5.122.2.6** void Arc::SimpleCondition::unlock (void) [inline]

Release semaphor

# **5.122.2.7 bool Arc::SimpleCondition::wait** (int *t*) [inline]

Wait for condition no longer than t milliseconds

# **5.122.2.8** void Arc::SimpleCondition::wait (void) [inline]

Wait for condition

# **5.122.2.9 void Arc::SimpleCondition::wait\_nonblock (void)** [inline]

Wait for condition without using semaphor

The documentation for this class was generated from the following file:

• Thread.h

# 5.123 Arc::SOAPMessage Class Reference

Message restricted to SOAP payload.

#include <SOAPMessage.h>

#### **Public Member Functions**

- SOAPMessage (void)
- SOAPMessage (long msg\_ptr\_addr)
- SOAPMessage (Arc::Message &msg)
- ~SOAPMessage (void)
- Arc::SOAPEnvelope \* Payload (void)
- void Payload (Arc::SOAPEnvelope \*new\_payload)
- Arc::MessageAttributes \* Attributes (void)
- void **Attributes** (Arc::MessageAttributes \*attributes)
- Arc::MessageAuth \* Auth (void)
- void **Auth** (Arc::MessageAuth \*auth)
- Arc::MessageContext \* Context (void)
- void Context (Arc::MessageContext \*context)

# 5.123.1 Detailed Description

Message restricted to SOAP payload.

This is a special Message intended to be used in language bindings for programming languages which are not flexible enough to support all kinds of Payloads. It is passed through chain of MCCs and works like the Message but can carry only SOAP content.

# 5.123.2 Constructor & Destructor Documentation

**5.123.2.1** Arc::SOAPMessage::SOAPMessage (void) [inline]

Dummy constructor

5.123.2.2 Arc::SOAPMessage::SOAPMessage (long msg\_ptr\_addr)

Copy constructor. Used by language bindigs

5.123.2.3 Arc::SOAPMessage::SOAPMessage (Arc::Message & msg)

Copy constructor. Ensures shallow copy.

#### 5.123.2.4 Arc::SOAPMessage::~SOAPMessage (void)

Destructor does not affect refered objects

# **5.123.3** Member Function Documentation

# **5.123.3.1** Arc::MessageAttributes\* Arc::SOAPMessage::Attributes (void) [inline]

Returns a pointer to the current attributes object or NULL if no attributes object has been assigned.

# 5.123.3.2 void Arc::SOAPMessage::Payload (Arc::SOAPEnvelope \* new\_payload)

Replace payload with a COPY of new one

# 5.123.3.3 Arc::SOAPEnvelope\* Arc::SOAPMessage::Payload (void)

Returns pointer to current payload or NULL if no payload assigned.

The documentation for this class was generated from the following file:


· SOAPMessage.h

# 5.124 ArcSec::Source Class Reference

Acquires and parses XML document from specified source.

#include <Source.h>

Inheritance diagram for ArcSec::Source::



# **Public Member Functions**

- Source (const Source &s)
- Source (Arc::XMLNode &xml)
- Source (std::istream &stream)
- Source (Arc::URL &url)
- Source (const std::string &str)
- Arc::XMLNode Get (void) const
- operator bool (void)
- operator Arc::XMLNode (void)

# 5.124.1 Detailed Description

Acquires and parses XML document from specified source.

This class is to be used to provide easy way to specify different sources for XML Authorization Policies and Requests.

## 5.124.2 Constructor & Destructor Documentation

#### **5.124.2.1** ArcSec::Source::Source (const Source & s) [inline]

Copy constructor.

Use this constructor only for temporary objects. Parsed XML document is still owned by copied source and hence lifetime of create object should not exceed that of copied one.

#### 5.124.2.2 ArcSec::Source::Source (Arc::XMLNode & xml)

Copy XML tree from XML subtree refered by xml.

#### 5.124.2.3 ArcSec::Source::Source (std::istream & stream)

Read XML document from stream and parse it.

#### 5.124.2.4 ArcSec::Source::Source (Arc::URL & url)

Fetch XML document from specified url and parse it.

This constructor is not implemented yet.

# 5.124.2.5 ArcSec::Source::Source (const std::string & str)

Read XML document from string.

# **5.124.3** Member Function Documentation

# **5.124.3.1** Arc::XMLNode ArcSec::Source::Get (void) const [inline]

Get reference to parsed document.

# **5.124.3.2** ArcSec::Source::operator bool (void) [inline]

Returns true if valid document is available.

The documentation for this class was generated from the following file:


· Source.h

# 5.125 ArcSec::SourceFile Class Reference

Convenience class for obtaining XML document from file.

#include <Source.h>

Inheritance diagram for ArcSec::SourceFile::



#### **Public Member Functions**

- SourceFile (const SourceFile &s)
- SourceFile (const char \*name)
- SourceFile (const std::string &name)

# 5.125.1 Detailed Description

Convenience class for obtaining XML document from file.

#### 5.125.2 Constructor & Destructor Documentation

# **5.125.2.1** ArcSec::SourceFile::SourceFile (const SourceFile & s) [inline]

See corresponding constructor of Source class.

#### 5.125.2.2 ArcSec::SourceFile::SourceFile (const char \* name)

Read XML document from file named name and store it.

#### 5.125.2.3 ArcSec::SourceFile::SourceFile (const std::string & name)

Read XML document from file named name and store it.

The documentation for this class was generated from the following file:

• Source.h

# 5.126 ArcSec::SourceURL Class Reference

Convenience class for obtaining XML document from remote URL.

#include <Source.h>

Inheritance diagram for ArcSec::SourceURL::



#### **Public Member Functions**

- SourceURL (const SourceURL &s)
- SourceURL (const char \*url)
- SourceURL (const std::string &url)

# 5.126.1 Detailed Description

Convenience class for obtaining XML document from remote URL.

# 5.126.2 Constructor & Destructor Documentation

# **5.126.2.1** ArcSec::SourceURL::SourceURL (const SourceURL & s) [inline]

See corresponding constructor of Source class.

#### 5.126.2.2 ArcSec::SourceURL::SourceURL (const char \* url)

Read XML document from URL url and store it.

#### 5.126.2.3 ArcSec::SourceURL::SourceURL (const std::string & url)

Read XML document from URL url and store it.

The documentation for this class was generated from the following file:

• Source.h

# 5.127 Arc::Time Class Reference

A class for storing and manipulating times.

#include <DateTime.h>

#### **Public Member Functions**

- Time ()
- Time (const time\_t &)
- Time (const std::string &)
- Time & operator= (const time\_t &)
- Time & operator= (const Time &)
- void SetTime (const time\_t &)
- time\_t GetTime () const
- operator std::string () const
- std::string str (const TimeFormat &=time\_format) const
- bool operator< (const Time &) const
- bool operator> (const Time &) const
- bool operator<= (const Time &) const
- bool operator>= (const Time &) const
- bool operator== (const Time &) const
- bool operator!= (const Time &) const
- Time operator+ (const Period &) const
- Time operator- (const Period &) const
- Period operator- (const Time &) const

#### **Static Public Member Functions**

- static void SetFormat (const TimeFormat &)
- static TimeFormat GetFormat ()

# **5.127.1** Detailed Description

A class for storing and manipulating times.

#### 5.127.2 Constructor & Destructor Documentation

#### **5.127.2.1** Arc::Time::Time()

Default constructor. The time is put equal the current time.

#### 5.127.2.2 Arc::Time::Time (const time\_t &)

Constructor that takes a time\_t variable and stores it.

#### 5.127.2.3 Arc::Time::Time (const std::string &)

Constructor that tries to convert a string into a time\_t.

#### **5.127.3** Member Function Documentation

**5.127.3.1 static TimeFormat Arc::Time::GetFormat ()** [static]

Gets the default format for time strings.

5.127.3.2 time\_t Arc::Time::GetTime() const

gets the time

5.127.3.3 Arc::Time::operator std::string () const

Returns a string representation of the time, using the default format.

5.127.3.4 bool Arc::Time::operator!= (const Time &) const

Comparing two Time objects.

5.127.3.5 Time Arc::Time::operator+ (const Period &) const

Adding Time object with Period object.

5.127.3.6 Period Arc::Time::operator- (const Time &) const

Subtracting Time object from the other Time object.

5.127.3.7 Time Arc::Time::operator- (const Period &) const

Subtracting Period object from Time object.

5.127.3.8 bool Arc::Time::operator< (const Time &) const

Comparing two Time objects.

5.127.3.9 bool Arc::Time::operator<= (const Time &) const

Comparing two Time objects.

5.127.3.10 Time& Arc::Time::operator= (const Time &)

Assignment operator from a Time.

5.127.3.11 Time& Arc::Time::operator= (const time\_t &)

Assignment operator from a time\_t.

5.127.3.12 bool Arc::Time::operator== (const Time &) const

Comparing two Time objects.

5.127.3.13 bool Arc::Time::operator> (const Time &) const

Comparing two Time objects.

5.127.3.14 bool Arc::Time::operator>= (const Time &) const

Comparing two Time objects.

**5.127.3.15** static void Arc::Time::SetFormat (const TimeFormat &) [static]

Sets the default format for time strings.

5.127.3.16 void Arc::Time::SetTime (const time\_t &)

sets the time

5.127.3.17 std::string Arc::Time::str (const TimeFormat & = time\_format) const

Returns a string representation of the time, using the specified format.


The documentation for this class was generated from the following file:

• DateTime.h

# **5.128** ArcSec::TimeAttribute Class Reference

#include <DateTimeAttribute.h>

Inheritance diagram for ArcSec::TimeAttribute::



#### **Public Member Functions**

- TimeAttribute (const std::string &v, const std::string &i)
- virtual bool equal (AttributeValue \*other)
- virtual bool lessthan (AttributeValue \*other)
- virtual std::string encode ()
- Arc::Time getValue ()
- virtual std::string getType ()
- virtual std::string getId ()

#### **Static Public Member Functions**

• static const std::string & getIdentifier (void)

# **5.128.1** Detailed Description

Format: HHMMSSZ HH:MM:SS HH:MM:SS+HH:MM HH:MM:SSZ

# **5.128.2** Member Function Documentation

# **5.128.2.1 virtual std::string ArcSec::TimeAttribute::encode** () [virtual]

encode the value in a string format

Implements ArcSec::AttributeValue.

#### **5.128.2.2 virtual bool ArcSec::TimeAttribute::equal (AttributeValue** \* other) [virtual]

Evluate whether "this" equale to the parameter value

Implements ArcSec::AttributeValue.

#### **5.128.2.3 virtual std::string ArcSec::TimeAttribute::getId ()** [inline, virtual]

Get the identifier of the <Attribute>

Implements ArcSec::AttributeValue.

# **5.128.2.4 virtual std::string ArcSec::TimeAttribute::getType ()** [inline, virtual]

Get the type of the <Attribute>

Implements ArcSec::AttributeValue.

The documentation for this class was generated from the following file:


• DateTimeAttribute.h

# 5.129 Arc::URL Class Reference

Class to hold general URL's.

#include <URL.h>

Inheritance diagram for Arc::URL::



# **Public Types**

- base
- onelevel
- subtree
- enum Scope { base, onelevel, subtree }

#### **Public Member Functions**

- **URL** ()
- URL (const std::string &url)
- virtual ~URL ()
- const std::string & Protocol () const
- void ChangeProtocol (const std::string &newprot)
- const std::string & Username () const
- const std::string & Passwd () const
- const std::string & Host () const
- void ChangeHost (const std::string &newhost)
- int Port () const
- void ChangePort (int newport)
- const std::string & Path () const
- std::string FullPath () const
- void ChangePath (const std::string &newpath)
- const std::map< std::string, std::string > & HTTPOptions () const
- const std::string & HTTPOption (const std::string &option, const std::string &undefined="") const
- const std::list< std::string > & LDAPAttributes () const
- void AddLDAPAttribute (const std::string &attribute)
- Scope LDAPScope () const
- void ChangeLDAPScope (const Scope newscope)
- const std::string & LDAPFilter () const
- void ChangeLDAPFilter (const std::string &newfilter)
- const std::map< std::string, std::string > & Options () const
- const std::string & Option (const std::string &option, const std::string &undefined="") const
- void AddOption (const std::string &option, const std::string &value, bool overwrite=true)
- const std::list< URLLocation > & Locations () const
- const std::map< std::string, std::string > & CommonLocOptions () const

- const std::string & CommonLocOption (const std::string &option, const std::string &undefined="")
- virtual std::string str () const
- virtual std::string fullstr () const
- virtual std::string ConnectionURL () const
- bool operator < (const URL &url) const
- bool operator== (const URL &url) const
- operator bool () const
- bool operator! () const

#### **Static Public Member Functions**

• static std::string OptionString (const std::map< std::string, std::string > &options, char separator)

#### **Static Protected Member Functions**

- static std::string BaseDN2Path (const std::string &)
- static std::string Path2BaseDN (const std::string &)

# **Protected Attributes**

- std::string protocol
- std::string username
- std::string passwd
- std::string host
- int port
- std::string path
- std::map< std::string, std::string > httpoptions
- std::list< std::string > ldapattributes
- Scope Idapscope
- std::string ldapfilter
- std::map< std::string, std::string > urloptions
- std::list< URLLocation > locations
- std::map< std::string, std::string > commonlocoptions

#### **Friends**

• std::ostream & operator<< (std::ostream &out, const URL &u)

# 5.129.1 Detailed Description

Class to hold general URL's.

The URL is split into protocol, hostname, port and path. It also accepts file paths which are converted to file://path. Usual system dependant file paths are supported. File path can't start from # symbol (why?). If string representation of URL starts from '@' then it is treated as path to file containing list of URLs.

#### **5.129.2** Member Enumeration Documentation

#### 5.129.2.1 enum Arc::URL::Scope

Scope for LDAP URLs

# 5.129.3 Constructor & Destructor Documentation

## 5.129.3.1 Arc::URL::URL()

Empty constructor. Necessary when the class is part of another class and the like.

#### 5.129.3.2 Arc::URL::URL (const std::string & url)

Constructs a new URL from a string representation.

#### **5.129.3.3 virtual Arc::URL::**~URL() [virtual]

**URL** Destructor

#### **5.129.4** Member Function Documentation

#### 5.129.4.1 void Arc::URL::AddLDAPAttribute (const std::string & attribute)

Adds an LDAP attribute.

# 5.129.4.2 void Arc::URL::AddOption (const std::string & option, const std::string & value, bool overwrite = true)

Adds a **URL** option.

# 5.129.4.3 static std::string Arc::URL::BaseDN2Path (const std::string &) [static, protected]

a private method that converts an ldap basedn to a path.

#### 5.129.4.4 void Arc::URL::ChangeHost (const std::string & newhost)

Changes the hostname of the URL.

## 5.129.4.5 void Arc::URL::ChangeLDAPFilter (const std::string & newfilter)

Changes the LDAP filter.

#### 5.129.4.6 void Arc::URL::ChangeLDAPScope (const Scope newscope)

Changes the LDAP scope.

#### 5.129.4.7 void Arc::URL::ChangePath (const std::string & newpath)

Changes the path of the URL.

### 5.129.4.8 void Arc::URL::ChangePort (int newport)

Changes the port of the URL.

#### 5.129.4.9 void Arc::URL::ChangeProtocol (const std::string & newprot)

Changes the protocol of the URL.

# 5.129.4.10 const std::string& Arc::URL::CommonLocOption (const std::string & option, const std::string & undefined = "") const

Returns the value of a common location option.

#### **Parameters:**

option The option whose value is returned.

undefined This value is returned if the common location option is not defined.

## 5.129.4.11 const std::map<std::string>& Arc::URL::CommonLocOptions () const

Returns the common location options if any.

#### 5.129.4.12 virtual std::string Arc::URL::ConnectionURL() const [virtual]

Returns a string representation with protocol, host and port only

#### 5.129.4.13 std::string Arc::URL::FullPath () const

Returns the path of the URL with all options attached.

# **5.129.4.14 virtual std::string Arc::URL::fullstr () const** [virtual]

Returns a string representation including options and locations

Reimplemented in Arc::URLLocation.

### 5.129.4.15 const std::string& Arc::URL::Host () const

Returns the hostname of the URL.

# 5.129.4.16 const std::string& Arc::URL::HTTPOption (const std::string & option, const std::string & undefined = "") const

Returns the value of an HTTP option.

#### **Parameters:**

option The option whose value is returned.undefined This value is returned if the HTTP option is not defined.

# 5.129.4.17 const std::map<std::string, std::string>& Arc::URL::HTTPOptions () const

Returns HTTP options if any.

#### 5.129.4.18 const std::list<std::string>& Arc::URL::LDAPAttributes () const

Returns the LDAP attributes if any.

#### 5.129.4.19 const std::string& Arc::URL::LDAPFilter () const

Returns the LDAP filter.

#### 5.129.4.20 Scope Arc::URL::LDAPScope () const

Returns the LDAP scope.

# 5.129.4.21 const std::list<URLLocation>& Arc::URL::Locations () const

Returns the locations if any.

#### 5.129.4.22 Arc::URL::operator bool () const

Check if instance holds valid URL

# 5.129.4.23 bool Arc::URL::operator< (const URL & url) const

Compares one **URL** to another

#### 5.129.4.24 bool Arc::URL::operator== (const URL & url) const

Is one URL equal to another?

# 5.129.4.25 const std::string & Arc::URL::Option (const std::string & option, const std::string & undefined = "") const

Returns the value of a URL option.

#### **Parameters:**

option The option whose value is returned.undefined This value is returned if the URL option is not defined.

#### 5.129.4.26 const std::map<std::string, std::string>& Arc::URL::Options () const

Returns URL options if any.

# 5.129.4.27 static std::string Arc::URL::OptionString (const std::map < std::string, std::string > & options, char separator) [static]

Returns a string representation of the options given in the options map

#### 5.129.4.28 const std::string& Arc::URL::Passwd () const

Returns the password of the URL.

#### 5.129.4.29 const std::string& Arc::URL::Path () const

Returns the path of the URL.

# **5.129.4.30 static std::string Arc::URL::Path2BaseDN (const std::string &)** [static, protected]

a private method that converts an ldap path to a basedn.

#### **5.129.4.31** int Arc::URL::Port () const

Returns the port of the URL.

# 5.129.4.32 const std::string& Arc::URL::Protocol () const

Returns the protocol of the URL.

# **5.129.4.33 virtual std::string Arc::URL::str () const** [virtual]

Returns a string representation of the URL.

Reimplemented in Arc::URLLocation.

#### 5.129.4.34 const std::string& Arc::URL::Username () const

Returns the username of the URL.

#### **5.129.5** Friends And Related Function Documentation

5.129.5.1 std::ostream & out, const URL & u) [friend]

Overloaded operator << to print a URL.

#### 5.129.6 Member Data Documentation

5.129.6.1 std::map<std::string, std::string> Arc::URL::commonlocoptions [protected]

common location options for index server URLs.

**5.129.6.2 std::string Arc::URL::host** [protected]

hostname of the url.

**5.129.6.3 std::map<std::string> Arc::URL::httpoptions** [protected]

HTTP options of the url.

**5.129.6.4 std::list<std::string> Arc::URL::ldapattributes** [protected]

LDAP attributes of the url.

**5.129.6.5** std::string Arc::URL::ldapfilter [protected]

LDAP filter of the url.

**5.129.6.6 Scope Arc::URL::ldapscope** [protected]

LDAP scope of the url.

**5.129.6.7 std::list<URLLocation> Arc::URL::locations** [protected]

locations for index server URLs.

**5.129.6.8 std::string Arc::URL::passwd** [protected]

password of the url.

**5.129.6.9 std::string Arc::URL::path** [protected]

the url path.

**5.129.6.10** int Arc::URL::port [protected]

portnumber of the url.

 $\textbf{5.129.6.11} \quad \textbf{std::string } \textbf{Arc::} \textbf{URL::protocol} \quad [\texttt{protected}]$ 

the url protocol.

**5.129.6.12 std::map<std::string> Arc::URL::urloptions** [protected]

options of the url.

**5.129.6.13** std::string Arc::URL::username [protected]

username of the url.

The documentation for this class was generated from the following file:


• URL.h

# 5.130 Arc::URLLocation Class Reference

Class to hold a resolved URL location.

#include <URL.h>

Inheritance diagram for Arc::URLLocation::



#### **Public Member Functions**

- URLLocation (const std::string &url)
- URLLocation (const std::string &url, const std::string &name)
- URLLocation (const URL &url)
- URLLocation (const URL &url, const std::string &name)
- URLLocation (const std::map< std::string, std::string > &options, const std::string &name)
- virtual ~URLLocation ()
- const std::string & Name () const
- virtual std::string str () const
- virtual std::string fullstr () const

#### **Protected Attributes**

• std::string name

# 5.130.1 Detailed Description

Class to hold a resolved **URL** location.

It is specific to file indexing service registrations.

#### 5.130.2 Constructor & Destructor Documentation

#### 5.130.2.1 Arc::URLLocation::URLLocation (const std::string & url)

Creates a URLLocation from a string representaion.

#### 5.130.2.2 Arc::URLLocation::URLLocation (const std::string & url, const std::string & name)

Creates a URLLocation from a string representaion and a name.

# 5.130.2.3 Arc::URLLocation::URLLocation (const URL & url)

Creates a URLLocation from a URL.

#### 5.130.2.4 Arc::URLLocation::URLLocation (const URL & url, const std::string & name)

Creates a URLLocation from a URL and a name.

# 5.130.2.5 Arc::URLLocation::URLLocation (const std::map< std::string, std::string > & options, const std::string & name)

Creates a URLLocation from options and a name.

#### 5.130.2.6 virtual Arc::URLLocation::~URLLocation() [virtual]

URLLocation destructor.

#### **5.130.3** Member Function Documentation

#### **5.130.3.1 virtual std::string Arc::URLLocation::fullstr() const** [virtual]

Returns a string representation including options and locations

Reimplemented from Arc::URL.

#### 5.130.3.2 const std::string& Arc::URLLocation::Name () const

Returns the URLLocation name.

#### 5.130.3.3 virtual std::string Arc::URLLocation::str() const [virtual]

Returns a string representation of the URLLocation.

Reimplemented from Arc::URL.

## **5.130.4** Member Data Documentation

# **5.130.4.1** std::string Arc::URLLocation::name [protected]

the URLLocation name as registered in the indexing service.

The documentation for this class was generated from the following file:

• URL.h

# 5.131 Arc::UsernameToken Class Reference

Interface for manipulation of WS-Security according to Username Token Profile.

#include <UsernameToken.h>

# **Public Types**

- PasswordText
- · PasswordDigest
- enum PasswordType { PasswordText, PasswordDigest }

#### **Public Member Functions**

- UsernameToken (SOAPEnvelope &soap)
- UsernameToken (SOAPEnvelope &soap, const std::string &username, const std::string &password, const std::string &uid, PasswordType pwdtype)
- UsernameToken (SOAPEnvelope &soap, const std::string &username, const std::string &id, bool mac, int iteration)
- operator bool (void)
- std::string Username (void)
- bool Authenticate (const std::string &password, std::string &derived\_key)
- bool Authenticate (std::istream &password, std::string &derived\_key)

#### **Protected Attributes**

XMLNode header\_

### **5.131.1** Detailed Description

Interface for manipulation of WS-Security according to Username Token Profile.

## **5.131.2** Member Enumeration Documentation

# 5.131.2.1 enum Arc::UsernameToken::PasswordType

SOAP header element

### 5.131.3 Constructor & Destructor Documentation

### 5.131.3.1 Arc::UsernameToken::UsernameToken (SOAPEnvelope & soap)

Link to existing SOAP header and parse Username Token information. Username Token related information is extracted from SOAP header and stored in class variables.

# 5.131.3.2 Arc::UsernameToken::UsernameToken (SOAPEnvelope & soap, const std::string & username, const std::string & password, const std::string & uid, PasswordType pwdtype)

Add Username Token information into the SOAP header. Generated token contains elements Username and Password and is meant to be used for authentication.

#### **Parameters:**

```
soap the SOAP message
username <wsse:Username>...</wsse:Username> - if empty it is entered interactively from stdin
password <wsse:Password Type="...">...</wsse:Password> - if empty it is entered interactively
from stdin
uid <wsse:UsernameToken wsu:ID="...">
pwdtype <wsse:Password Type="...">...</wsse:Password>
```

# 5.131.3.3 Arc::UsernameToken::UsernameToken (SOAPEnvelope & soap, const std::string & username, const std::string & id, bool mac, int iteration)

Add Username Token information into the SOAP header. Generated token contains elements Username and Salt and is meant to be used for deriving Key Derivation.

#### **Parameters:**

```
soap the SOAP message
username <wsse:Username>...</wsse:Username>
mac if derived key is meant to be used for Message Authentication Code
iteration <wsse11:Iteration>...</wsse11:Iteration>
```

# **5.131.4** Member Function Documentation

# 5.131.4.1 bool Arc::UsernameToken::Authenticate (std::istream & password, std::string & derived key)

Checks parsed token against password stored in specified stream. If token is meant to be used for deriving a key then key is returned in derived\_key

# 5.131.4.2 bool Arc::UsernameToken::Authenticate (const std::string & password, std::string & derived\_key)

Checks parsed/generated token against specified password. If token is meant to be used for deriving a key then key is returned in derived\_key. In that case authentication is performed outside of UsernameToken class using obtained derived\_key.

#### 5.131.4.3 Arc::UsernameToken::operator bool (void)

Returns true of constructor succeeded

# 5.131.4.4 std::string Arc::UsernameToken::Username (void)

Returns username associated with this instance

The documentation for this class was generated from the following file:

• UsernameToken.h

# 5.132 Arc::VOMSTrustList Class Reference

#include < VOMSUtil.h>

#### **Public Member Functions**

- VOMSTrustList (const std::vector< std::string > &encoded\_list)
- VOMSTrustList (const std::vector< VOMSTrustChain > &chains, const std::vector< VOMSTrust-Regex > &regexs)
- VOMSTrustChain & AddChain (const VOMSTrustChain &chain)
- VOMSTrustChain & AddChain (void)
- RegularExpression & AddRegex (const VOMSTrustRegex &reg)
- int SizeChains (void) const
- int SizeRegexs (void) const
- const VOMSTrustChain & GetChain (int num) const
- const RegularExpression & GetRegex (int num) const

### **5.132.1** Detailed Description

Stores definitions for making decision if VOMS server is trusted

## 5.132.2 Constructor & Destructor Documentation

# 5.132.2.1 Arc::VOMSTrustList::VOMSTrustList (const std::vector< std::string > & encoded\_list)

Creates chain lists and regexps from plain list. List is made of chunks delimited by elements containing pattern "NEXT CHAIN". Each chunk with more than one element is converted into one instance of VOMSTrustChain. Chunks with single element are converted to VOMSTrustChain if element does not have special symbols. Otherwise it is treated Those symbols are '^','\$' and '\*'. as regular expression. Trusted chains can be congicured in two ways: one way is: <tls:VOMSCertTrustDNChain> <tl><tls:VOMSCertTrust-</td> DN>/O=Grid/O=NorduGrid/CN=host/arthur.hep.lu.se</tls:VOMSCertTrustDN> <tls:VOMSCert-TrustDN>/O=Grid/O=NorduGrid/CN=NorduGrid Certification Authority</tl> <tls:VOMSCertTrustDN>—-NEXT CHAIN—</tls:VOMSCertTrustDN> <tls:VOMSCertTrust-DN>/DC=ch/DC=cern/OU=computers/CN=voms.cern.ch</tls:VOMSCertTrustDN> <tls:VOMSCertTrustDN> TrustDN>/DC=ch/DC=cern/CN=CERN Trusted Certification Authority</tl> </tl></tls:VOMSCertTrustDNChain><tls:VOMSCertTrustDNChain><tls:VOMSCertTrustDNChain> TrustDN>/O=Grid/O=NorduGrid/CN=host/arthur.hep.lu.se</tls:VOMSCertTrustDN> <tls:VOMSCertTrustDN> TrustDN>/O=Grid/O=NorduGrid/CN=NorduGrid Certification Authority</tls:VOMSCertTrust-DN> </tls:VOMSCertTrustDNChain> <tls:VOMSCertTrustDNChain> <tls:VOMSCertTrust-DN>/DC=ch/DC=cern/OU=computers/CN=voms.cern.ch</tls:VOMSCertTrustDN> TrustDN>/DC=ch/DC=cern/CN=CERN Trusted Certification Authority</tl> </tl></tds:VOMSCertTrustDNChain> each chunk is supposed to contain a suit of DN of trusted certificate chain, in which the first DN is the DN of the certificate (cert0) which is used to sign the Attribute Certificate (AC), the second DN is the DN of the issuer certificate(cert1) which is used to sign cert0. So if there are one or more intermediate issuers, then there should be 3 or more than 3 DNs in this chunk (considering cert0 and the root certificate, plus the intermediate certificate).

# 5.132.2.2 Arc::VOMSTrustList::VOMSTrustList (const std::vector < VOMSTrustChain > & chains, const std::vector < VOMSTrustRegex > & regexs)

Creates chain lists and regexps from those specified in arguments. See AddChain() and AddRegex() for more information.

#### **5.132.3** Member Function Documentation

# 5.132.3.1 VOMSTrustChain& Arc::VOMSTrustList::AddChain (void)

Adds empty chain of trusted DNs to list.

# 5.132.3.2 VOMSTrustChain & Arc::VOMSTrustList::AddChain (const VOMSTrustChain & chain)

Adds chain of trusted DNs to list. During verification each signature of AC is checked against all stored chains. DNs of chain of certificate used for signing AC are compared against DNs stored in these chains one by one. If needed DN of issuer of last certificate is checked too. Comparison succeeds if DNs in at least one stored chain are same as those in certificate chain. Comparison stops when all DNs in stored chain are compared. If there are more DNs in stored chain than in certificate chain then comparison fails. Empty stored list matches any certificate chain. Taking into account that certificate chains are verified down to trusted CA anyway, having more than one DN in stored chain seems to be useless. But such feature may be found useful by some very strict sysadmins. ??? IMO,DN list here is not only for authentication, it is also kind of ACL, which means the AC consumer only trusts those DNs which issues AC.

## 5.132.3.3 RegularExpression& Arc::VOMSTrustList::AddRegex (const VOMSTrustRegex & reg)

Adds regular expression to list. During verification each signature of AC is checked against all stored regular expressions. DN of signing certificate must match at least one of stored regular expressions.

The documentation for this class was generated from the following file:

• VOMSUtil.h

# 5.133 Arc::WSAEndpointReference Class Reference

Interface for manipulation of WS-Adressing Endpoint Reference.

#include <WSA.h>

#### **Public Member Functions**

- WSAEndpointReference (XMLNode epr)
- WSAEndpointReference (const std::string &address)
- WSAEndpointReference (void)
- ~WSAEndpointReference (void)
- std::string Address (void) const
- void Address (const std::string &uri)
- WSAEndpointReference & operator= (const std::string &address)
- XMLNode ReferenceParameters (void)
- XMLNode MetaData (void)
- operator XMLNode (void)

#### **Protected Attributes**

• XMLNode epr\_

## **5.133.1** Detailed Description

Interface for manipulation of WS-Adressing Endpoint Reference.

It works on Endpoint Reference stored in XML tree. No information is stored in this object except reference to corresponding XML subtree.

### 5.133.2 Constructor & Destructor Documentation

#### 5.133.2.1 Arc::WSAEndpointReference::WSAEndpointReference (XMLNode epr)

Linking to existing EPR in XML tree

#### 5.133.2.2 Arc::WSAEndpointReference::WSAEndpointReference (const std::string & address)

Creating independent EPR - not implemented

## 5.133.2.3 Arc::WSAEndpointReference::WSAEndpointReference (void)

Dummy constructor - creates invalid instance

#### 5.133.2.4 Arc::WSAEndpointReference::~WSAEndpointReference (void)

Destructor. All empty elements of EPR XML are destroyed here too

# **5.133.3** Member Function Documentation

#### 5.133.3.1 void Arc::WSAEndpointReference::Address (const std::string & uri)

Assigns new Address value. If EPR had no Address element it is created.

### 5.133.3.2 std::string Arc::WSAEndpointReference::Address (void) const

Returns Address (URL) encoded in EPR

# 5.133.3.3 XMLNode Arc::WSAEndpointReference::MetaData (void)

Access to MetaData element of EPR. Obtained XML element should be manipulated directly in application-dependent way. If EPR had no MetaData element it is created.

#### 5.133.3.4 Arc::WSAEndpointReference::operator XMLNode (void)

Returns reference to EPR top XML node

# 5.133.3.5 WSAEndpointReference & Arc::WSAEndpointReference::operator= (const std::string & address)

Same as Address(uri)

#### 5.133.3.6 XMLNode Arc::WSAEndpointReference::ReferenceParameters (void)

Access to ReferenceParameters element of EPR. Obtained XML element should be manipulated directly in application-dependent way. If EPR had no ReferenceParameters element it is created.

The documentation for this class was generated from the following file:

• WSA.h

# 5.134 Arc::WSAHeader Class Reference

Interface for manipulation WS-Addressing information in SOAP header.

#include <WSA.h>

## **Public Member Functions**

- WSAHeader (SOAPEnvelope &soap)
- WSAHeader (const std::string &action)
- std::string To (void) const
- void To (const std::string &uri)
- WSAEndpointReference From (void)
- WSAEndpointReference ReplyTo (void)
- WSAEndpointReference FaultTo (void)
- std::string Action (void) const
- void Action (const std::string &uri)
- std::string MessageID (void) const
- void MessageID (const std::string &uri)
- std::string RelatesTo (void) const
- void RelatesTo (const std::string &uri)
- std::string RelationshipType (void) const
- void RelationshipType (const std::string &uri)
- XMLNode ReferenceParameter (int n)
- XMLNode ReferenceParameter (const std::string &name)
- XMLNode NewReferenceParameter (const std::string &name)
- operator XMLNode (void)

#### **Static Public Member Functions**

• static bool Check (SOAPEnvelope &soap)

## **Protected Attributes**

- XMLNode header
- bool header\_allocated\_

#### **5.134.1** Detailed Description

Interface for manipulation WS-Addressing information in SOAP header.

It works on Endpoint Reference stored in XML tree. No information is stored in this object except reference to corresponding XML subtree.

## 5.134.2 Constructor & Destructor Documentation

#### 5.134.2.1 Arc::WSAHeader::WSAHeader (SOAPEnvelope & soap)

Linking to a header of existing SOAP message

#### 5.134.2.2 Arc::WSAHeader::WSAHeader (const std::string & action)

Creating independent SOAP header - not implemented

#### **5.134.3** Member Function Documentation

#### 5.134.3.1 void Arc::WSAHeader::Action (const std::string & uri)

Set content of Action element of SOAP Header. If such element does not exist it's created.

#### 5.134.3.2 std::string Arc::WSAHeader::Action (void) const

Returns content of Action element of SOAP Header.

#### 5.134.3.3 static bool Arc::WSAHeader::Check (SOAPEnvelope & soap) [static]

Tells if specified SOAP message has WSA header

#### 5.134.3.4 WSAEndpointReference Arc::WSAHeader::FaultTo (void)

Returns FaultTo element of SOAP Header. If such element does not exist it's created. Obtained element may be manipulted.

### 5.134.3.5 WSAEndpointReference Arc::WSAHeader::From (void)

Returns From element of SOAP Header. If such element does not exist it's created. Obtained element may be manipulted.

#### 5.134.3.6 void Arc::WSAHeader::MessageID (const std::string & uri)

Set content of MessageID element of SOAP Header. If such element does not exist it's created.

## 5.134.3.7 std::string Arc::WSAHeader::MessageID (void) const

Returns content of MessageID element of SOAP Header.

#### 5.134.3.8 XMLNode Arc::WSAHeader::NewReferenceParameter (const std::string & name)

Creates new ReferenceParameter element with specified name. Returns reference to created element.

#### 5.134.3.9 Arc::WSAHeader::operator XMLNode (void)

Returns reference to SOAP Header - not implemented

#### 5.134.3.10 XMLNode Arc::WSAHeader::ReferenceParameter (const std::string & name)

Returns first ReferenceParameter element with specified name

#### **5.134.3.11 XMLNode** Arc::WSAHeader::ReferenceParameter (int *n*)

Return n-th ReferenceParameter element

#### 5.134.3.12 void Arc::WSAHeader::RelatesTo (const std::string & uri)

Set content of RelatesTo element of SOAP Header. If such element does not exist it's created.

#### 5.134.3.13 std::string Arc::WSAHeader::RelatesTo (void) const

Returns content of RelatesTo element of SOAP Header.

# 5.134.3.14 void Arc::WSAHeader::RelationshipType (const std::string & uri)

Set content of RelationshipType element of SOAP Header. If such element does not exist it's created.

## 5.134.3.15 std::string Arc::WSAHeader::RelationshipType (void) const

Returns content of RelationshipType element of SOAP Header.

#### 5.134.3.16 WSAEndpointReference Arc::WSAHeader::ReplyTo (void)

Returns ReplyTo element of SOAP Header. If such element does not exist it's created. Obtained element may be manipulted.

#### 5.134.3.17 void Arc::WSAHeader::To (const std::string & uri)

Set content of To element of SOAP Header. If such element does not exist it's created.

#### 5.134.3.18 std::string Arc::WSAHeader::To (void) const

Returns content of To element of SOAP Header.

## **5.134.4** Member Data Documentation

### **5.134.4.1** bool Arc::WSAHeader::header\_allocated\_ [protected]

SOAP header element

The documentation for this class was generated from the following file:


• WSA.h

# 5.135 Arc::WSRF Class Reference

Base class for every WSRF message.

#include <WSRF.h>

Inheritance diagram for Arc::WSRF::



#### **Public Member Functions**

- WSRF (SOAPEnvelope &soap, const std::string &action="")
- WSRF (bool fault=false, const std::string &action="")
- virtual SOAPEnvelope & SOAP (void)
- virtual operator bool (void)
- virtual bool operator! (void)

#### **Protected Member Functions**

• void set\_namespaces (void)

#### **Protected Attributes**

- SOAPEnvelope & soap\_
- bool allocated\_
- bool valid\_

# 5.135.1 Detailed Description

Base class for every WSRF message.

This class is not intended to be used directly. Use it like reference while passing through unknown WSRF message or use classes derived from it.

## 5.135.2 Constructor & Destructor Documentation

#### 5.135.2.1 Arc::WSRF::WSRF (SOAPEnvelope & soap, const std::string & action = "")

Constructor - creates object out of supplied SOAP tree.

#### 5.135.2.2 Arc::WSRF::WSRF (bool fault = false, const std::string & action = "")

Constructor - creates new WSRF object

# **5.135.3** Member Function Documentation

# **5.135.3.1 virtual Arc::WSRF::operator bool (void)** [inline, virtual]

Returns true if instance is valid

# **5.135.3.2 void Arc::WSRF::set\_namespaces (void)** [protected]

set WS Resource namespaces and default prefixes in SOAP message

Reimplemented in Arc::WSRP, and Arc::WSRFBaseFault.

# 5.135.3.3 virtual SOAPEnvelope& Arc::WSRF::SOAP (void) [inline, virtual]

Direct access to underlying SOAP element

#### **5.135.4** Member Data Documentation

# **5.135.4.1** bool Arc::WSRF::allocated\_ [protected]

Associated SOAP message - it's SOAP message after all

# **5.135.4.2** bool Arc::WSRF::valid\_ [protected]

true if soap\_ needs to be deleted in destructor

The documentation for this class was generated from the following file:


• WSRF.h

# 5.136 Arc::WSRFBaseFault Class Reference

Base class for WSRF fault messages.

#include <WSRFBaseFault.h>

Inheritance diagram for Arc::WSRFBaseFault::



#### **Public Member Functions**

- WSRFBaseFault (SOAPEnvelope &soap)
- WSRFBaseFault (const std::string &type)
- std::string **Type** (void)
- Time Timestamp (void)
- void Timestamp (Time)
- WSAEndpointReference Originator (void)
- void ErrorCode (const std::string &dialect, const XMLNode &error)
- XMLNode ErrorCode (void)
- std::string ErrorCodeDialect (void)
- void **Description** (int pos, const std::string &desc, const std::string &lang)
- std::string **Description** (int pos)
- std::string **DescriptionLang** (int pos)
- void FaultCause (int pos, const XMLNode &cause)
- XMLNode FaultCause (int pos)

### **Protected Member Functions**

• void set\_namespaces (void)

# 5.136.1 Detailed Description

Base class for WSRF fault messages.

Use classes inherited from it for specific faults.

## 5.136.2 Constructor & Destructor Documentation

#### 5.136.2.1 Arc::WSRFBaseFault::WSRFBaseFault (SOAPEnvelope & soap)

Constructor - creates object out of supplied SOAP tree.

# 5.136.2.2 Arc::WSRFBaseFault::WSRFBaseFault (const std::string & type)

Constructor - creates new WSRF fault

# **5.136.3** Member Function Documentation

# **5.136.3.1 void Arc::WSRFBaseFault::set\_namespaces (void)** [protected]

set WS-ResourceProperties namespaces and default prefixes in SOAP message Reimplemented from Arc::WSRF.

The documentation for this class was generated from the following file:

• WSRFBaseFault.h

# 5.137 Arc::WSRP Class Reference

Base class for WS-ResourceProperties structures.

#include <WSResourceProperties.h>

Inheritance diagram for Arc::WSRP::



#### **Public Member Functions**

- WSRP (bool fault=false, const std::string &action="")
- WSRP (SOAPEnvelope &soap, const std::string &action="")

#### **Protected Member Functions**

• void set\_namespaces (void)

# 5.137.1 Detailed Description

Base class for WS-ResourceProperties structures.

Inheriting classes implement specific WS-ResourceProperties messages and their properties/elements. Refer to WS-ResourceProperties specifications for things specific to every message.

# 5.137.2 Constructor & Destructor Documentation

5.137.2.1 Arc::WSRP::WSRP (bool fault = false, const std::string & action = "")

Constructor - prepares object for creation of new WSRP request/response/fault

# 5.137.2.2 Arc::WSRP::WSRP (SOAPEnvelope & soap, const std::string & action = "")

Constructor - creates object out of supplied SOAP tree. It does not check if 'soap' represents valid WS-ResourceProperties structure. Actual check for validity of structure has to be done by derived class.

## **5.137.3** Member Function Documentation

# **5.137.3.1 void Arc::WSRP::set\_namespaces (void)** [protected]

set WS-ResourceProperties namespaces and default prefixes in SOAP message

Reimplemented from Arc::WSRF.

The documentation for this class was generated from the following file:


| 316                      | Hosting Environment (Daemon) Class Documentation |
|--------------------------|--|
|                          |  |
| • WSResourceProperties.h |  |
|                          |  |
|                          |  |
|                          |  |
|                          |  |
|                          |  |
|                          |  |
|                          |  |
|                          |  |
|                          |  |
|                          |  |
|                          |  |
|                          |  |
|                          |  |
|                          |  |
|                          |  |
|                          |  |
|                          |  |
|                          |  |
|                          |  |
|                          |  |
|                          |  |
|                          |  |
|                          |  |
|                          |  |
|                          |  |
|                          |  |
|                          |  |
|                          |  |
|                          |  |
|                          |  |
|                          |  |

## 5.138 Arc::WSRPFault Class Reference

Base class for WS-ResourceProperties faults.

#include <WSResourceProperties.h>

Inheritance diagram for Arc::WSRPFault::



## **Public Member Functions**

- WSRPFault (SOAPEnvelope &soap)
- WSRPFault (const std::string &type)

## **5.138.1** Detailed Description

Base class for WS-ResourceProperties faults.

#### 5.138.2 Constructor & Destructor Documentation

## 5.138.2.1 Arc::WSRPFault::WSRPFault (SOAPEnvelope & soap)

Constructor - creates object out of supplied SOAP tree.

## 5.138.2.2 Arc::WSRPFault::WSRPFault (const std::string & type)

Constructor - creates new WSRP fault


The documentation for this class was generated from the following file:

• WSResourceProperties.h

## 5.139 Arc::WSRPResourcePropertyChangeFailure Class Reference

#include <WSResourceProperties.h>

Inheritance diagram for Arc::WSRPResourcePropertyChangeFailure::



#### **Public Member Functions**

- WSRPResourcePropertyChangeFailure (SOAPEnvelope &soap)
- WSRPResourcePropertyChangeFailure (const std::string &type)
- XMLNode CurrentProperties (bool create=false)
- XMLNode RequestedProperties (bool create=false)

## 5.139.1 Detailed Description

Base class for WS-ResourceProperties faults which contain ResourcePropertyChangeFailure

#### 5.139.2 Constructor & Destructor Documentation

## **5.139.2.1** Arc::WSRPResourcePropertyChangeFailure::WSRPResourcePropertyChangeFailure (SOAPEnvelope & soap) [inline]

Constructor - creates object out of supplied SOAP tree.

## 5.139.2.2 Arc::WSRPResourcePropertyChangeFailure::WSRPResourcePropertyChangeFailure (const std::string & type) [inline]

Constructor - creates new WSRP fault

The documentation for this class was generated from the following file:

• WSResourceProperties.h

## 5.140 Arc::X509Token Class Reference

Class for manipulating X.509 Token Profile.

#include <X509Token.h>

## **Public Types**

- Signature
- Encryption
- enum X509TokenType { Signature, Encryption }

#### **Public Member Functions**

- X509Token (SOAPEnvelope &soap)
- X509Token (SOAPEnvelope &soap, const std::string &certfile, const std::string &keyfile, X509TokenType token type=Signature)
- ~X509Token (void)
- operator bool (void)
- bool Authenticate (const std::string &cafile, const std::string &capath)
- bool Authenticate (void)

## 5.140.1 Detailed Description

Class for manipulating X.509 Token Profile.

This class is for generating/consuming X.509 Token profile. Currently it is used by x509token handler (src/hed/pdc/x509tokensh/) It is not necessary to directly called this class. If we need to use X.509 Token functionality, we only need to configure the x509token handler into service and client.

#### 5.140.2 Member Enumeration Documentation

### 5.140.2.1 enum Arc::X509Token::X509TokenType

X509TokeType is for distinguishing two types of operation. It is used as the parameter of constuctor.

#### 5.140.3 Constructor & Destructor Documentation

### 5.140.3.1 Arc::X509Token::X509Token (SOAPEnvelope & soap)

Constructor.Parse X509 Token information from SOAP header. X509 Token related information is extracted from SOAP header and stored in class variables. And then it the X509Token object will be used for authentication if the tokentype is Signature; otherwise if the tokentype is Encryption, the encrypted soap body will be decrypted and replaced by decrypted message.

## 5.140.3.2 Arc::X509Token::X509Token (SOAPEnvelope & soap, const std::string & certfile, const std::string & keyfile, X509TokenType token\_type = Signature)

Constructor. Add X509 Token information into the SOAP header. Generated token contains elements X509 token and signature, and is meant to be used for authentication on the consuming side.

#### **Parameters:**

soap The SOAP message to which the X509 Token will be inserted

*certfile* The certificate file which will be used to encrypt the SOAP body (if parameter tokentype is Encryption), or be used as <wse:BinarySecurityToken/> (if parameter tokentype is Signature).

keyfile The key file which will be used to create signature. Not needed when create encryption.

tokentype Token type: Signature or Encryption.

## 5.140.3.3 Arc::X509Token::~X509Token (void)

Deconstructor. Nothing to be done except finalizing the xmlsec library.

#### **5.140.4** Member Function Documentation

#### 5.140.4.1 bool Arc::X509Token::Authenticate (void)

Check signature by using the cert information in soap message. Only the signature itself is checked, and it is not guranteed that the certificate which is supposed to check the signature is trusted.

## 5.140.4.2 bool Arc::X509Token::Authenticate (const std::string & cafile, const std::string & capath)

Check signature by using the certificare information in X509Token which is parsed by the constructor, and the trusted certificates specified as one of the two parameters. Not only the signature (in the X509Token) itself is checked, but also the certificate which is supposed to check the signature needs to be trusted (which means the certificate is issued by the ca certificate from CA file or CA directory). At least one the two parameters should be set.

#### Parameters:

```
cafile The CA filecapath The CA directory
```

## **Returns:**

true if authentication passes; otherwise false

#### 5.140.4.3 Arc::X509Token::operator bool (void)

Returns true of constructor succeeded

The documentation for this class was generated from the following file:


• X509Token.h

## 5.141 Arc::XMLNode Class Reference

Wrapper for LibXML library Tree interface.

#include <XMLNode.h>

Inheritance diagram for Arc::XMLNode::



### **Public Member Functions**

- XMLNode (void)
- XMLNode (const XMLNode &node)
- XMLNode (const std::string &xml)
- XMLNode (const char \*xml, int len=-1)
- XMLNode (const Arc::NS &ns, const char \*name)
- ~XMLNode (void)
- void New (XMLNode &new\_node) const
- operator bool (void) const
- bool operator! (void) const
- bool operator== (const XMLNode &node)
- bool operator!= (const XMLNode &node)
- bool Same (const XMLNode &node)
- bool operator== (bool val)
- bool operator!= (bool val)
- bool operator== (const std::string &str)
- bool operator!= (const std::string &str)
- XMLNode Child (int n=0) const
- XMLNode operator[] (const char \*name) const
- XMLNode operator[] (const std::string &name) const
- XMLNode operator[] (int n) const
- void operator++ (void)
- void operator— (void)
- int Size (void) const
- XMLNode Get (const std::string &name) const
- std::string Name (void) const
- std::string Prefix (void) const
- std::string FullName (void) const
- std::string Namespace (void) const
- void Name (const char \*name)
- void Name (const std::string &name)
- void GetXML (std::string &out\_xml\_str, bool user\_friendly=false) const
- void GetXML (std::string &out\_xml\_str, const std::string &encoding, bool user\_friendly=false) const
- void GetDoc (std::string &out\_xml\_str, bool user\_friendly=false) const

- operator std::string (void) const
- XMLNode & operator= (const char \*content)
- XMLNode & operator= (const std::string &content)
- void Set (const std::string &content)
- XMLNode & operator= (const XMLNode &node)
- XMLNode Attribute (int n=0) const
- XMLNode Attribute (const char \*name) const
- XMLNode Attribute (const std::string &name) const
- XMLNode NewAttribute (const char \*name)
- XMLNode NewAttribute (const std::string &name)
- int AttributesSize (void) const
- void Namespaces (const NS &namespaces)
- NS Namespaces (void)
- std::string NamespacePrefix (const char \*urn)
- XMLNode NewChild (const char \*name, int n=-1, bool global\_order=false)
- XMLNode NewChild (const std::string &name, int n=-1, bool global\_order=false)
- XMLNode NewChild (const char \*name, const NS &namespaces, int n=-1, bool global\_order=false)
- XMLNode NewChild (const std::string &name, const NS &namespaces, int n=-1, bool global\_order=false)
- XMLNode NewChild (const XMLNode &node, int n=-1, bool global order=false)
- void Replace (const XMLNode &node)
- void Destroy (void)
- XMLNodeList Path (const std::string &path) const
- XMLNodeList XPathLookup (const std::string &xpathExpr, const Arc::NS &nsList) const
- XMLNode GetRoot (void)
- XMLNode Parent (void)
- bool SaveToFile (const std::string &file\_name) const
- bool SaveToStream (std::ostream &out) const
- bool ReadFromFile (const std::string &file\_name)
- bool ReadFromStream (std::istream &in)

### **Protected Member Functions**

• XMLNode (xmlNodePtr node)

### **Protected Attributes**

- xmlNodePtr node
- bool is\_owner\_
- bool is\_temporary\_

#### **Friends**

- class XMLNodeContainer
- bool MatchXMLName (const XMLNode &node1, const XMLNode &node2)
- bool MatchXMLName (const XMLNode &node, const char \*name)
- bool MatchXMLName (const XMLNode &node, const std::string &name)
- bool MatchXMLNamespace (const XMLNode &node1, const XMLNode &node2)
- bool MatchXMLNamespace (const XMLNode &node, const char \*uri)
- bool MatchXMLNamespace (const XMLNode &node, const std::string &uri)

## **5.141.1** Detailed Description

Wrapper for LibXML library Tree interface.

This class wraps XML Node, Document and Property/Attribute structures. Each instance serves as pointer to actual LibXML element and provides convenient (for chosen purpose) methods for manipulating it. This class has no special ties to LibXML library and may be easily rewritten for any XML parser which provides interface similar to LibXML Tree. It implements only small subset of XML capabilities, which is probably enough for performing most of useful actions. This class also filters out (usually) useless textual nodes which are often used to make XML documents human-readable.

#### **5.141.2** Constructor & Destructor Documentation

#### **5.141.2.1** Arc::XMLNode::XMLNode (xmlNodePtr node) [inline, protected]

Private constructor for inherited classes Creates instance and links to existing LibXML structure. Acquired structure is not owned by class instance. If there is need to completely pass control of LibXML document to then instance's is\_owner\_ variable has to be set to true.

#### **5.141.2.2** Arc::XMLNode::XMLNode (void) [inline]

Constructor of invalid node Created instance does not point to XML element. All methods are still allowed for such instance but produce no results.

## **5.141.2.3** Arc::XMLNode::XMLNode (const XMLNode & node) [inline]

Copies existing instance. Underlying XML element is NOT copied. Ownership is NOT inherited.

#### 5.141.2.4 Arc::XMLNode::XMLNode (const std::string & xml)

Creates XML document structure from textual representation of XML document. Created structure is pointed and owned by constructed instance

### 5.141.2.5 Arc::XMLNode::XMLNode (const char \* xml, int len = -1)

Same as previous

#### 5.141.2.6 Arc::XMLNode::XMLNode (const Arc::NS & ns, const char \* name)

Creates empty XML document structure with specified namespaces. Created XML contains only root element named 'name'. Created structure is pointed and owned by constructed instance

#### 5.141.2.7 Arc::XMLNode::~XMLNode (void)

Destructor Also destroys underlying XML document if owned by this instance

### **5.141.3** Member Function Documentation

## **5.141.3.1** XMLNode Arc::XMLNode::Attribute (const std::string & name) const [inline]

Returns XMLNode instance representing first attribute of node with specified by name

#### 5.141.3.2 XMLNode Arc::XMLNode::Attribute (const char \* name) const

Returns XMLNode instance representing first attribute of node with specified by name

#### 5.141.3.3 XMLNode Arc::XMLNode::Attribute (int n = 0) const

Returns list of all attributes of node.

Returns XMLNode instance reresenting n-th attribute of node.

#### 5.141.3.4 int Arc::XMLNode::AttributesSize (void) const

Returns number of attributes of node

#### 5.141.3.5 XMLNode Arc::XMLNode::Child (int n = 0) const

Returns XMLNode instance representing n-th child of XML element. If such does not exist invalid XMLNode instance is returned

## 5.141.3.6 void Arc::XMLNode::Destroy (void)

Destroys underlying XML element. XML element is unlinked from XML tree and destroyed. After this operation XMLNode instance becomes invalid

### 5.141.3.7 std::string Arc::XMLNode::FullName (void) const [inline]

Returns prefix:name of XML node

## **5.141.3.8** XMLNode Arc::XMLNode::Get (const std::string & name) const [inline]

Same as operator[]

## 5.141.3.9 void Arc::XMLNode::GetDoc (std::string & out\_xml\_str, bool user\_friendly = false) const

Fills argument with whole XML document textual representation

#### 5.141.3.10 XMLNode Arc::XMLNode::GetRoot (void)

Get the root node from any child node of the tree

## 5.141.3.11 void Arc::XMLNode::GetXML (std::string & out\_xml\_str, const std::string & encoding, bool user\_friendly = false) const

Fills argument with this instance XML subtree textual representation if the XML subtree is corresponding to the encoding format specified in the argument, e.g. utf-8

## 5.141.3.12 void Arc::XMLNode::GetXML (std::string & out\_xml\_str, bool user\_friendly = false) const

Fills argument with this instance XML subtree textual representation

### 5.141.3.13 void Arc::XMLNode::Name (const std::string & name) [inline]

Assigns new name to XML node

#### 5.141.3.14 void Arc::XMLNode::Name (const char \* name)

Assigns new name to XML node

### 5.141.3.15 std::string Arc::XMLNode::Name (void) const

Returns name of XML node

### 5.141.3.16 std::string Arc::XMLNode::Namespace (void) const

Returns namespace URI of XML node

### 5.141.3.17 std::string Arc::XMLNode::NamespacePrefix (const char \* urn)

Returns prefix of specified namespace. Empty string if no such namespace.

### 5.141.3.18 NS Arc::XMLNode::Namespaces (void)

Returns namespaces known at this node

#### 5.141.3.19 void Arc::XMLNode::Namespaces (const NS & namespaces)

Assigns namespaces of XML document at point specified by this instance. If namespace already exists it gets new prefix. New namespaces are added. It is usefull to apply this method to XML being processed in order to refer to it's elements by known prefix.

## 5.141.3.20 void Arc::XMLNode::New (XMLNode & new\_node) const

Creates a copy of XML (sub)tree. If object does not represent whole document - top level document is created. 'new\_node' becomes a pointer owning new XML document.

5.141.3.21 XMLNode Arc::XMLNode::NewAttribute (const std::string & name) [inline]

Creates new attribute with specified name.

**5.141.3.22 XMLNode** Arc::XMLNode::NewAttribute (const char \* *name*)

Creates new attribute with specified name.

5.141.3.23 XMLNode Arc::XMLNode::NewChild (const XMLNode & node, int n = -1, bool  $global\_order = false$ )

Link a copy of supplied XML node as child. Returns instance referring to new child. XML element is a copy of supplied one but not owned by returned instance

5.141.3.24 XMLNode Arc::XMLNode::NewChild (const std::string & name, const NS & namespaces, int n = -1, bool global\_order = false) [inline]

Same as NewChild(const char\*,const NS&,int,bool)

5.141.3.25 XMLNode Arc::XMLNode::NewChild (const char \* name, const NS & namespaces, int n = -1, bool global\_order = false)

Creates new child XML element at specified position with specified name and namespaces. For more information look at NewChild(const char\*,int,bool)

5.141.3.26 XMLNode Arc::XMLNode::NewChild (const std::string & name, int n = -1, bool  $global\_order = false$ ) [inline]

Same as NewChild(const char\*,int,bool)

5.141.3.27 XMLNode Arc::XMLNode::NewChild (const char \* name, int n = -1, bool global\_order = false)

Creates new child XML element at specified position with specified name. Default is to put it at end of list. If global order is true position applies to whole set of children, otherwise only to children of same name

**5.141.3.28** Arc::XMLNode::operator bool (void) const [inline]

Returns true if instance points to XML element - valid instance

5.141.3.29 Arc::XMLNode::operator std::string (void) const

Returns textual content of node excluding content of children nodes

**5.141.3.30** bool Arc::XMLNode::operator! (void) const [inline]

Returns true if instance does not point to XML element - invalid instance

#### 5.141.3.31 bool Arc::XMLNode::operator!= (const std::string & str) [inline]

This operator is needed to avoid ambiguity

#### **5.141.3.32 bool Arc::XMLNode::operator!= (bool** *val***)** [inline]

This operator is needed to avoid ambiguity

### 5.141.3.33 bool Arc::XMLNode::operator!= (const XMLNode & node) [inline]

Returns false if 'node' represents same XML element

### 5.141.3.34 void Arc::XMLNode::operator++ (void)

Convenience operator to switch to next element of same name. If there is no such node this object becomes invalid.

## 5.141.3.35 void Arc::XMLNode::operator-(void)

Convenience operator to switch to previous element of same name. If there is no such node this object becomes invalid.

#### 5.141.3.36 XMLNode& Arc::XMLNode::operator= (const XMLNode & node)

Make instance refer to another XML node. Ownership is not inherited.

### 5.141.3.37 XMLNode& Arc::XMLNode::operator= (const std::string & content) [inline]

Sets textual content of node. All existing children nodes are discarded.

## 5.141.3.38 XMLNode& Arc::XMLNode::operator= (const char \* content)

Sets textual content of node. All existing children nodes are discarded.

## **5.141.3.39 bool** Arc::XMLNode::operator== (const std::string & str) [inline]

This operator is needed to avoid ambiguity

## **5.141.3.40** bool Arc::XMLNode::operator== (bool val) [inline]

This operator is needed to avoid ambiguity

#### 5.141.3.41 bool Arc::XMLNode::operator== (const XMLNode & node) [inline]

Returns true if 'node' represents same XML element

#### 5.141.3.42

XMLNode Arc::XMLNode::operator[] (int *n*) const

Returns XMLNode instance representing n-th node in sequence of siblings of same name. It's main purpose is to be used to retrieve element in array of children of same name like node["name"][5]

#### 5.141.3.43

XMLNode Arc::XMLNode::operator[] (const std::string & name) const [inline]

Similar to previous method

#### 5.141.3.44

XMLNode Arc::XMLNode::operator[] (const char \* name) const

Returns XMLNode instance representing first child element with specified name. Name may be "namespace\_prefix:name" or simply "name". In last case namespace is ignored. If such node does not exist invalid XMLNode instance is returned

#### 5.141.3.45 XMLNode Arc::XMLNode::Parent (void)

Get the parent node from any child node of the tree

## 5.141.3.46 XMLNodeList Arc::XMLNode::Path (const std::string & path) const

Collects nodes corresponding to specified path. This is a convenience function to cover common use of XPath but without performance hit. Path is made of node\_name[/node\_name[...]] and is relative to current node. node\_names are treated in same way as in operator[]. Returns all nodes which are represented by path.

#### 5.141.3.47 std::string Arc::XMLNode::Prefix (void) const

Returns namespace prefix of XML node

### 5.141.3.48 bool Arc::XMLNode::ReadFromFile (const std::string & file\_name)

Read XML document from file and associate it with this node

### 5.141.3.49 bool Arc::XMLNode::ReadFromStream (std::istream & in)

Read XML document from stream and associate it with this node

#### 5.141.3.50 void Arc::XMLNode::Replace (const XMLNode & node)

Makes a copy of supplied XML node and makes this instance refere to it

#### 5.141.3.51 bool Arc::XMLNode::Same (const XMLNode & node) [inline]

Returns true if 'node' represents same XML element - for bindings

#### 5.141.3.52 bool Arc::XMLNode::SaveToFile (const std::string & file\_name) const

Save string representation of node to file

### 5.141.3.53 bool Arc::XMLNode::SaveToStream (std::ostream & out) const

Save string representation of node to stream

#### 5.141.3.54 void Arc::XMLNode::Set (const std::string & content) [inline]

Same as operator=. Used for bindings.

#### 5.141.3.55 int Arc::XMLNode::Size (void) const

Returns number of children nodes

## 5.141.3.56 XMLNodeList Arc::XMLNode::XPathLookup (const std::string & xpathExpr, const Arc::NS & nsList) const

Uses xPath to look up the whole xml structure, Returns a list of XMLNode points. The xpathExpr should be like "//xx:child1/" which indicates the namespace and node that you would like to find; The nsList is the namespace the result should belong to (e.g. xx="uri:test"). Query is run on whole XML document but only the elements belonging to this XML subtree are returned.

### **5.141.4** Friends And Related Function Documentation

## 5.141.4.1 bool MatchXMLName (const XMLNode & node, const std::string & name) [friend]

Returns true if 'name' matches name of 'node'. If name contains prefix it's checked too

#### **5.141.4.2** bool MatchXMLName (const XMLNode & node, const char \* name) [friend]

Returns true if 'name' matches name of 'node'. If name contains prefix it's checked too

#### 5.141.4.3 bool MatchXMLName (const XMLNode & node1, const XMLNode & node2) [friend]

Returns true if underlying XML elements have same names

## **5.141.4.4 bool MatchXMLNamespace (const XMLNode & node, const std::string & uri)**[friend]

Returns true if 'namespace' matches 'node's namespace.

## **5.141.4.5** bool MatchXMLNamespace (const XMLNode & node, const char \* uri) [friend]

Returns true if 'namespace' matches 'node's namespace.

## **5.141.4.6** bool MatchXMLNamespace (const XMLNode & node1, const XMLNode & node2) [friend]

Returns true if underlying XML elements belong to same namespaces

## **5.141.5** Member Data Documentation

### **5.141.5.1** bool Arc::XMLNode::is\_owner\_ [protected]

If true node is owned by this instance - hence released in destructor. Normally that may be true only for top level node of XML document.

### **5.141.5.2 bool Arc::XMLNode::is\_temporary\_** [protected]

This variable is for future

The documentation for this class was generated from the following file:

• XMLNode.h

## 5.142 Arc::XMLNodeContainer Class Reference

#include <XMLNode.h>

#### **Public Member Functions**

- XMLNodeContainer (void)
- XMLNodeContainer (const XMLNodeContainer &)
- XMLNodeContainer & operator= (const XMLNodeContainer &)
- void Add (const XMLNode &)
- void Add (const std::list< XMLNode > &)
- void AddNew (const XMLNode &)
- void AddNew (const std::list< XMLNode > &)
- int Size (void)
- XMLNode operator[] (int)
- std::list< XMLNode > Nodes (void)

## 5.142.1 Detailed Description

Container for multiple XMLNode elements

## 5.142.2 Constructor & Destructor Documentation

## 5.142.2.1 Arc::XMLNodeContainer::XMLNodeContainer (void)

Default constructor

#### 5.142.2.2 Arc::XMLNodeContainer::XMLNodeContainer (const XMLNodeContainer &)

Copy constructor. Add nodes from argument. Nodes owning XML document are copied using AddNew(). Not owning nodes are linked using Add() method.

### 5.142.3 Member Function Documentation

### 5.142.3.1 void Arc::XMLNodeContainer::Add (const std::list< XMLNode > &)

Link multiple XML subtrees to container.

#### 5.142.3.2 void Arc::XMLNodeContainer::Add (const XMLNode &)

Link XML subtree refered by node to container. XML tree must be available as long as this object is used.

#### 5.142.3.3 void Arc::XMLNodeContainer::AddNew (const std::list< XMLNode > &)

Copy multiple XML subtrees to container.

### 5.142.3.4 void Arc::XMLNodeContainer::AddNew (const XMLNode &)

Copy XML subtree referenced by node to container. After this operation container refers to independent XML document. This document is deleted when container is destroyed.

### 5.142.3.5 std::list<XMLNode> Arc::XMLNodeContainer::Nodes (void)

Returns all stored nodes.

## 5.142.3.6 XMLNodeContainer& Arc::XMLNodeContainer::operator= (const XMLNodeContainer &)

Same as copy constructor with current nodes being deleted first.

### 5.142.3.7

XMLNode Arc::XMLNodeContainer::operator[] (int)

Returns n-th node in a store.

## 5.142.3.8 int Arc::XMLNodeContainer::Size (void)

Return number of refered/stored nodes.

The documentation for this class was generated from the following file:


• XMLNode.h

## **5.143** Arc::XMLSecNode Class Reference

Extends XMLNode class to support XML security operation.

#include <XMLSecNode.h>

Inheritance diagram for Arc::XMLSecNode::



## **Public Types**

- RSA\_SHA1
- DSA\_SHA1
- TRIPLEDES
- AES 128
- AES 256
- DEFAULT
- enum SignatureMethod { RSA\_SHA1, DSA\_SHA1 }
- enum SymEncryptionType { TRIPLEDES, AES\_128, AES\_256, DEFAULT }

### **Public Member Functions**

- XMLSecNode (XMLNode &node)
- void AddSignatureTemplate (const std::string &id\_name, const SignatureMethod sign\_method, const std::string &incl\_namespaces="")
- bool SignNode (const std::string &privkey\_file, const std::string &cert\_file)
- bool VerifyNode (const std::string &id\_name, const std::string &ca\_file, const std::string &ca\_path, bool verify\_trusted=true)
- bool EncryptNode (const std::string &cert\_file, const SymEncryptionType encrpt\_type)
- bool DecryptNode (const std::string &privkey\_file, Arc::XMLNode &decrypted\_node)

## 5.143.1 Detailed Description

Extends XMLNode class to support XML security operation.

All XMLNode methods are exposed by inheriting from XMLNode. XMLSecNode itself does not own node, instead it uses the node from the base class XMLNode.

#### **5.143.2** Constructor & Destructor Documentation

5.143.2.1 Arc::XMLSecNode::XMLSecNode (XMLNode & node)

Create a object based on an XMLNode instance.

## **5.143.3** Member Function Documentation

## 5.143.3.1 void Arc::XMLSecNode::AddSignatureTemplate (const std::string & id\_name, const SignatureMethod sign\_method, const std::string & incl\_namespaces = "")

Add the signature template for later signing.

#### **Parameters:**

id\_name The identifier name under this node which will be used for the <Signature> to refer to.
sign\_method The sign method for signing. Two options now, RSA\_SHA1, DSA\_SHA1

## 5.143.3.2 bool Arc::XMLSecNode::DecryptNode (const std::string & privkey\_file, Arc::XMLNode & decrypted\_node)

Decrypt the <xenc:EncryptedData/> under this node, the decrypted node will be output in the second argument of DecryptNode method. And the <xenc:EncryptedData/> under this node will be removed after decryption.

#### **Parameters:**

privkey\_file The private key file, which is used for decrypting
decrypted\_node Output the decrypted node

## 5.143.3.3 bool Arc::XMLSecNode::EncryptNode (const std::string & cert\_file, const SymEncryptionType encrpt\_type)

Encrypt this node, after encryption, this node will be replaced by the encrypted node

#### **Parameters:**

cert\_file The certificate file, the public key parsed from this certificate is used to encrypted the symmetric key, and then the symmetric key is used to encrypted the node

encrpt\_type The encryption type when encrypting the node, four option in SymEncryptionType

verify\_trusted Verify trusted certificates or not. If set to false, then only the signature will be checked
(by using the public key from KeyInfo).

## 5.143.3.4 bool Arc::XMLSecNode::SignNode (const std::string & privkey\_file, const std::string & cert\_file)

Sign this node (identified by id\_name).

#### **Parameters:**

privkey\_file The private key file. The private key is used for signing

cert\_file The certificate file. The certificate is used as the <KeyInfo> part of the <Signature>; <KeyInfo> will be used for the other end to verify this <Signature>

incl\_namespaces InclusiveNamespaces for Tranform in Signature

## 5.143.3.5 bool Arc::XMLSecNode::VerifyNode (const std::string & id\_name, const std::string & ca\_file, const std::string & ca\_path, bool verify\_trusted = true)

Verify the signature under this node

### **Parameters:**

id\_name The id of this node, which is used for identifying the node

ca\_file The CA file which used as trused certificate when verify the certificate in the <KeyInfo> part
 of <Signature>

ca\_path The CA directory; either ca\_file or ca\_path should be set.

The documentation for this class was generated from the following file:

• XMLSecNode.h

# Index

| ~ARCLibError                  | Arc::URLLocation, 300          |
|-------------------------------|--------------------------------|
| ARCLibError, 37               | $\sim$ WSAEndpointReference    |
| ~AutoPointer                  | Arc::WSAEndpointReference, 300 |
| Arc::AutoPointer, 49          | ~X509Token                     |
| ~Counter                      | Arc::X509Token, 320            |
| Arc::Counter, 69              | $\sim$ XMLNode                 |
| ~DataBuffer                   | Arc::XMLNode, 323              |
| Arc::DataBuffer, 81           | ,                              |
| ~DataMover                    | AcceptsMeta                    |
| Arc::DataMover, 89            | Arc::DataPoint, 95             |
| ~DataPoint                    | Arc::DataPointDirect, 105      |
| Arc::DataPoint, 95            | Arc::DataPointIndex, 112       |
| ~DataSpeed                    | Acquire                        |
| Arc::DataSpeed, 119           | Arc::DelegationConsumer, 125   |
| ~Database                     | Arc::InformationContainer, 164 |
| Arc::Database, 78             | Action                         |
| ~FileCache                    | Arc::WSAHeader, 309            |
| Arc::FileCache, 150           | Add                            |
| ~IntraProcessCounter          | Arc::MessageContext, 207       |
| Arc::IntraProcessCounter, 172 | Arc::XMLNodeContainer, 331     |
| ~Loader                       | add                            |
| Arc::Loader, 175              | Arc::MessageAttributes, 202    |
| ~MCCLoader                    | AddCADir                       |
| Arc::MCCLoader, 196           | Arc::BaseConfig, 51            |
| ~Message                      | AddCAFile                      |
| Arc::Message, 199             | Arc::BaseConfig, 51            |
| ~PayloadRaw                   | AddCertificate                 |
| Arc::PayloadRaw, 216          | Arc::BaseConfig, 51            |
| ~PayloadStream                | AddChain                       |
| Arc::PayloadStream, 222       | Arc::VOMSTrustList, 305        |
| ~Plexer                       | addDestination                 |
| Arc::Plexer, 235              | Arc::Logger, 180               |
| ~RegularExpression            | AddLDAPAttribute               |
| Arc::RegularExpression, 248   | Arc::URL, 293                  |
| ~Run                          | AddLocation                    |
| Arc::Run, 258                 | Arc::DataPoint, 95             |
| ~RuntimeEnvironment           | Arc::DataPointDirect, 105      |
| RuntimeEnvironment, 261       | Arc::DataPointIndex, 112       |
| ~SAMLToken                    | AddNew                         |
| Arc::SAMLToken, 265           | Arc::XMLNodeContainer, 331     |
| ~SOAPMessage                  | AddOption                      |
| Arc::SOAPMessage, 280         | Addoption Arc::URL, 293        |
| ~URL                          | AddOverlay                     |
| Arc::URL, 293                 | Acc::BaseConfig, 52            |
| ~URLL ocation                 | AddPluginsPath                 |
|                               |                                |

| Arc::BaseConfig, 52             | load_key_from_certstr, 28           |
|---------------------------------|-------------------------------------|
| addPolicy                       | load_key_from_keyfile, 28           |
| ArcSec::Evaluator, 142          | load_trusted_cert_file, 28          |
| ArcSec::Policy, 244             | load_trusted_cert_str, 28           |
| AddPrivateKey                   | load_trusted_certs, 29              |
| Arc::BaseConfig, 52             | LogLevel, 23                        |
| AddProxy                        | MatchXMLName, 25                    |
| Arc::BaseConfig, 52             | MatchXMLNamespace, 25, 26           |
| AddRegex                        | operator $<<$ , 23, 24              |
| Arc::VOMSTrustList, 305         | parseVOMSAC, 26, 27                 |
| addRegistrars                   | PARSING_ERROR, 23                   |
| Arc::InfoRegisterContainer, 161 | passphrase_callback, 27             |
| addRequestItem                  | plugins_table_name, 29              |
| ArcSec::Request, 251            | PROTOCOL_RECOGNIZED_ERROR, 23       |
| Address                         | ReadURLList, 25                     |
| Arc::WSAEndpointReference, 307  | SESSION_CLOSE, 23                   |
| AddSecHandler                   | SetEnv, 25                          |
| Arc::MCC, 188                   | STATUS OK, 23                       |
| Arc::Service, 276               | StatusKind, 23                      |
| addService                      | StrError, 25                        |
| Arc::InfoRegisterContainer, 161 | string, 27                          |
| Arc::InfoRegistrar, 163         | stringto, 24                        |
| AddSignatureTemplate            | TimeFormat, 22                      |
| Arc::XMLSecNode, 334            | TimeStamp, 23, 24                   |
| AddWSSInfo                      | tokenize, 24                        |
| Arc::BaseConfig, 52             | tostring, 24                        |
| AddWSSType                      | trim, 24                            |
| Arc::BaseConfig, 52             | UNKNOWN_SERVICE_ERROR, 23           |
| allocated_                      | UnsetEnv, 25                        |
|                                 | upper, 24                           |
| Arc::WSRF, 312<br>Arc, 11       | uri_unescape, 24                    |
|                                 | =                                   |
| AttrConstIter, 22               | UUID, 24<br>WSAFault, 23            |
| AttrIter, 22                    |                                     |
| AttrMap, 22                     | WSAFaultAssign, 27                  |
| BUSY_ERROR, 23                  | WSAFaultExtract, 27                 |
| ContentFromPayload, 27          | WSAFaultInvalidAddressingHeader, 23 |
| CreateThreadFunction, 25        | WSAFaultUnknown, 23                 |
| createVOMSAC, 26                | WSSType, 22                         |
| CredentialLogger, 29            | Arc::ArcLocation, 38                |
| ETERNAL, 29                     | Arc::ArcLocation                    |
| final_xmlsec, 27                | Get, 38                             |
| GENERIC_ERROR, 23               | GetPlugins, 38                      |
| get_cert_str, 28                | Init, 38                            |
| get_key_from_certfile, 28       | Arc::AttributeIterator, 41          |
| get_key_from_certstr, 28        | Arc::AttributeIterator              |
| get_key_from_keyfile, 28        | AttributeIterator, 41               |
| get_key_from_keystr, 28         | current_, 43                        |
| get_node, 29                    | end_, 43                            |
| get_plugin_instance, 22         | hasMore, 42                         |
| GetEnv, 25                      | key, 42                             |
| GUID, 24                        | MessageAttributes, 43               |
| HISTORIC, 29                    | operator *, 42                      |
| init_xmlsec, 27                 | operator++, 42                      |
| load_key_from_certfile, 28      | operator->, 43                      |
|                                 |                                     |

| A                             | 1 5 60                        |
|-------------------------------|-------------------------------|
| Arc::AutoPointer, 49          | changeExcess, 69              |
| Arc::AutoPointer              | changeLimit, 69               |
| ~AutoPointer, 49              | Counter, 69                   |
| AutoPointer, 49               | CounterTicket, 73             |
| operator *, 49                | ExpirationReminder, 73        |
| operator bool, 49             | extend, 70                    |
| operator $T *, 50$            | getCounterTicket, 70          |
| operator!, 50                 | getCurrentTime, 70            |
| operator->, 50                | getExcess, 71                 |
| Arc::BaseConfig, 51           | getExpirationReminder, 71     |
| Arc::BaseConfig               | getExpiryTime, 71             |
| AddCADir, 51                  | getLimit, 71                  |
| AddCAFile, 51                 | getValue, 72                  |
| AddCertificate, 51            | IDType, 69                    |
| AddOverlay, 52                | reserve, 72                   |
| AddPluginsPath, 52            | setExcess, 72                 |
| AddPrivateKey, 52             | setLimit, 73                  |
| AddProxy, 52                  | Arc::CounterTicket, 74        |
| AddWSSInfo, 52                | Arc::CounterTicket            |
| AddWSSType, 52                | cancel, 74                    |
| GetOverlay, 52                | Counter, 75                   |
| •                             | Counter, 75 CounterTicket, 74 |
| MakeConfig, 52                |                               |
| Arc::CacheParameters, 53      | extend, 75                    |
| Arc::ChainContext, 54         | isValid, 75                   |
| Arc::ChainContext             | Arc::CRC32Sum, 76             |
| operator PluginsFactory *, 54 | Arc::CredentialError, 77      |
| Arc::CheckSum, 55             | Arc::CredentialError          |
| Arc::CheckSumAny, 56          | CredentialError, 77           |
| Arc::CIStringValue, 58        | Arc::Database, 78             |
| Arc::CIStringValue            | $\sim$ Database, 78           |
| CIStringValue, 58             | close, 79                     |
| equal, 59                     | connect, 79                   |
| operator bool, 59             | Database, 78                  |
| Arc::ClientSOAP, 60           | enable_ssl, 79                |
| Arc::ClientSOAP               | isconnected, 79               |
| ClientSOAP, 60                | shutdown, 79                  |
| process, 60                   | Arc::DataBuffer, 80           |
| Arc::Config, 63               | Arc::DataBuffer               |
| Config, 63, 64                | $\sim$ DataBuffer, 81         |
| getFileName, 64               | buffer_size, 81               |
| parse, 64                     | checksum_object, 81           |
| print, 64                     | checksum_valid, 81            |
| save, 64                      | DataBuffer, 81                |
| setFileName, 64               | eof_position, 81              |
| Arc::CountedPointer, 65       | eof read, 82                  |
| Arc::CountedPointer           | eof_write, 82                 |
| operator *, 65                | error, 82                     |
| operator bool, 65             | error_read, 82                |
| operator T *, 65              | error_transfer, 82            |
| operator!, 65                 | error_write, 82               |
| <u>*</u>                      | for_read, 83                  |
| operator->, 66                |                               |
| Arc::Counter, 67              | for_write, 83                 |
| ~Counter, 69                  | is_notwritten, 83             |
| cancel, 69                    | is_read, 84                   |
|                               |                               |

| is_written, 84                      | HaveLocations, 97            |
|-------------------------------------|------------------------------|
| operator bool, 84                   | IsIndex, 98                  |
| operator[], 84                      | ListFiles, 98                |
| set, 85                             | Local, 98                    |
| speed, 86                           | LocationValid, 98            |
| wait_any, 85                        | NextLocation, 98             |
| wait_eof, 85                        | operator bool, 98            |
| wait_eof_read, 85                   | operator!, 98                |
| wait_eof_write, 85                  | Passive, 98                  |
| wait_read, 85                       | PostRegister, 99             |
| wait_used, 85                       | PreRegister, 99              |
| wait_write, 85                      | PreUnregister, 99            |
| Arc::DataCallback, 87               | ProvidesMeta, 99             |
| Arc::DataHandle, 88                 | Range, 100                   |
| Arc::DataMover, 89                  | ReadOutOfOrder, 100          |
| Arc::DataMover                      | Registered, 100              |
| ∼DataMover, 89                      | Remove, 100                  |
| checks, 90                          | RemoveLocation, 100          |
| DataMover, 89                       | RemoveLocations, 100         |
| force_to_meta, 90                   | Resolve, 100                 |
| passive, 90                         | SetAdditionalChecks, 101     |
| retry, 90                           | SetCheckSum, 101             |
| secure, 90                          | SetCreated, 101              |
| set_default_max_inactivity_time, 90 | SetMeta, 101                 |
| set_default_min_average_speed, 90   | SetSecure, 101               |
| set_default_min_speed, 91           | SetSize, 101                 |
| Transfer, 91                        | SetTries, 101                |
| verbose, 91, 92                     | SetValid, 102                |
| Arc::DataPoint, 93                  | StartReading, 102            |
| Arc::DataPoint                      | StartWriting, 102            |
| ∼DataPoint, 95                      | StopReading, 102             |
| AcceptsMeta, 95                     | StopWriting, 102             |
| AddLocation, 95                     | str, 103                     |
| AssignCredentials, 95               | Unregister, 103              |
| BufNum, 95                          | WriteOutOfOrder, 103         |
| BufSize, 96                         | Arc::DataPointDirect, 104    |
| Cache, 96                           | Arc::DataPointDirect         |
| Check, 96                           | AcceptsMeta, 105             |
| CheckCheckSum, 96                   | AddLocation, 105             |
| CheckCreated, 96                    | BufNum, 105                  |
| CheckSize, 96                       | BufSize, 105                 |
| CheckValid, 96                      | Cache, 106                   |
| CompareMeta, 96                     | CurrentLocation, 106         |
| CurrentLocation, 96                 | CurrentLocationMetadata, 106 |
| CurrentLocationMetadata, 97         | GetAdditionalChecks, 106     |
| DataPoint, 95                       | GetSecure, 106               |
| GetAdditionalChecks, 97             | HaveLocations, 106           |
| GetCheckSum, 97                     | IsIndex, 106                 |
| GetCreated, 97                      | Local, 106                   |
| GetSecure, 97                       | Location Valid, 107          |
| GetSize, 97                         | NextLocation, 107            |
| GetTries, 97                        | Passive, 107                 |
| GetURL, 97                          | PostRegister, 107            |
| GetValid, 97                        | PreRegister, 107             |
|                                     | , ***                        |

| PreUnregister, 108               | reset, 119                        |
|----------------------------------|-----------------------------------|
| ProvidesMeta, 108                | set_base, 119                     |
| Range, 108                       | set_max_data, 120                 |
| ReadOutOfOrder, 108              | set_max_inactivity_time, 120      |
| Registered, 108                  | set_min_average_speed, 120        |
| RemoveLocation, 108              | set_min_speed, 120                |
| RemoveLocations, 108             | set_progress_indicator, 120       |
| Resolve, 109                     | transfer, 120                     |
| SetAdditionalChecks, 109         | transfered_size, 121              |
| SetSecure, 109                   | verbose, 121                      |
| Unregister, 109                  | Arc::DelegationConsumer, 124      |
| WriteOutOfOrder, 109             | Arc::DelegationConsumer           |
| Arc::DataPointIndex, 111         | Acquire, 125                      |
| Arc::DataPointIndex              | Backup, 125                       |
| AcceptsMeta, 112                 | DelegationConsumer, 124           |
| AddLocation, 112                 | Generate, 125                     |
| BufNum, 112                      | ID, 125                           |
| BufSize, 112                     | LogError, 125                     |
| Cache, 112                       | Request, 125                      |
| Check, 112                       | Restore, 125                      |
| CurrentLocation, 113             | Arc::DelegationConsumerSOAP, 126  |
| CurrentLocationMetadata, 113     | Arc::DelegationConsumerSOAP       |
| GetAdditionalChecks, 113         | DelegateCredentialsInit, 126      |
| GetSecure, 113                   | DelegatedToken, 126               |
| HaveLocations, 113               | DelegationConsumerSOAP, 126       |
| IsIndex, 113                     | UpdateCredentials, 127            |
| Local, 113                       | Arc::DelegationContainerSOAP, 128 |
| locations, 117                   | Arc::DelegationContainerSOAP      |
| LocationValid, 113               | context_lock_, 129                |
| NextLocation, 114                | DelegateCredentialsInit, 128      |
| Passive, 114                     | DelegatedToken, 128               |
| ProvidesMeta, 114                | max_duration_, 129                |
| Range, 114                       | max_size_, 129                    |
| ReadOutOfOrder, 114              | max_usage_, 129                   |
| Registered, 114                  | restricted_, 129                  |
| Remove, 114                      | UpdateCredentials, 128            |
| RemoveLocation, 115              | Arc::DelegationProvider, 130      |
| RemoveLocations, 115             | Arc::DelegationProvider           |
| SetAdditionalChecks, 115         | Delegate, 130                     |
| SetSecure, 115                   | DelegationProvider, 130           |
| SetTries, 115                    | Arc::DelegationProviderSOAP, 132  |
| StartReading, 115                | Arc::DelegationProviderSOAP       |
| StartWriting, 116                | DelegateCredentialsInit, 133      |
| StopReading, 116                 | DelegatedToken, 133               |
| StopWriting, 116                 | DelegationProviderSOAP, 132       |
| WriteOutOfOrder, 116             | ID, 133                           |
| Arc::DataSpeed, 118              | UpdateCredentials, 133            |
| Arc::DataSpeed                   | Arc::ExpirationReminder, 147      |
| ~DataSpeed, 119                  | Arc::ExpirationReminder           |
| DataSpeed, 118                   | Counter, 148                      |
| hold, 119                        | getExpiryTime, 147                |
| max_inactivity_time_failure, 119 | getReservationID, 147             |
| min_average_speed_failure, 119   | operator<, 147                    |
| min_speed_failure, 119           | Arc::FileCache, 149               |
| mm_specu_tanuic, 117             | me necache, 147                   |

| A FU C 1  | T. C                            |
|---|---------------------------------|
| Arc::FileCache  | InformationRequest, 168         |
| ~FileCache, 150                                       | SOAP, 168                       |
| CheckCreated, 150                                     | Arc::InformationResponse, 170   |
| CheckValid, 150                                       | Arc::InformationResponse        |
| Clean, 151  | InformationResponse, 170        |
| Copy, 151   | Result, 170                     |
| File, 151   | Arc::IntraProcessCounter, 171   |
| FileCache, 150  | Arc::IntraProcessCounter        |
| GetCreated, 151                                       | $\sim$ IntraProcessCounter, 172 |
| GetValid, 151   | cancel, 172                     |
| Link, 151   | changeExcess, 172               |
| operator bool, 151                                    | changeLimit, 172                |
| operator==, 152                                       | extend, 172                     |
| Release, 152  | getExcess, 173                  |
| SetValid, 152   | getLimit, 173                   |
| Start, 152  | getValue, 173                   |
| Stop, 152   | IntraProcessCounter, 171        |
| StopAndDelete, 152                                    | reserve, 173                    |
| Arc::FileInfo, 155                                    | setExcess, 174                  |
| Arc::InfoCache, 158                                   | setLimit, 174                   |
| Arc::InfoCache  | Arc::Loader, 175                |
| InfoCache, 158  | ~Loader, 175                    |
| Arc::InfoFilter, 159                                  | factory_, 175                   |
| Arc::InfoFilter                                       | Loader, 175                     |
| Filter, 159   | Arc::LogDestination, 177        |
| InfoFilter, 159                                       | Arc::LogDestination, 177        |
|   |                                 |
| Arc::InfoRegister, 160                                | log, 178                        |
| Arc::InfoRegisterContainer, 161                       | LogDestination, 177             |
| Arc::InfoRegisterContainer                            | Arc::Logger, 179                |
| addRegistrars, 161                                    | addDestination, 180             |
| addService, 161                                       | getRootLogger, 180              |
| removeService, 161                                    | getThreshold, 180               |
| Arc::InfoRegisters, 162                               | Logger, 180                     |
| Arc::InfoRegisters                                    | msg, 180, 181                   |
| InfoRegisters, 162                                    | removeDestinations, 181         |
| Arc::InfoRegistrar, 163                               | setThreshold, 181               |
| Arc::InfoRegistrar                                    | Arc::LogMessage, 182            |
| addService, 163                                       | Arc::LogMessage                 |
| registration, 163                                     | getLevel, 183                   |
| removeService, 163                                    | Logger, 183                     |
| Arc::InformationContainer, 164                        | LogMessage, 182                 |
| Arc::InformationContainer                             | operator << , 183               |
| Acquire, 164  | setIdentifier, 183              |
| Assign, 164   | Arc::LogStream, 184             |
| doc_, 165   | Arc::LogStream                  |
| Get, 165  | log, 185                        |
| InformationContainer, 164                             | LogStream, 184                  |
| Arc::InformationInterface, 166                        | Arc::MCC, 187                   |
| Arc::InformationInterface                             | AddSecHandler, 188              |
| Get, 167  | logger, 188                     |
| InformationInterface, 166                             | MCC, 188                        |
| lock_, 167  | Next, 188                       |
| Arc::InformationRequest, 168                          | next_, 189                      |
| Arc::InformationRequest, 108  Arc::InformationRequest |                                 |
| Arcmiormationixequest                                 | process, 188                    |

| ProcessSecHandlers, 188                       | Arc::ModuleManager                                     |
|---|--|
| sechandlers_, 189                             | findLocation, 210                                      |
| Unlink, 188                                   | load, 210  |
| Arc::MCC_Status, 190                          | ModuleManager, 210                                     |
| getExplanation, 190                           | reload, 210  |
| getKind, 190                                  | setCfg, 211  |
| getOrigin, 191                                | Arc::MultiSecAttr, 212                                 |
| isOk, 191                                     | Arc::MultiSecAttr                                      |
| MCC_Status, 190                               | Export, 212  |
| operator bool, 191                            | operator bool, 212                                     |
| operator std::string, 191                     | Arc::MySQLDatabase, 214                                |
| operator!, 191                                | Arc::MySQLDatabase                                     |
| Arc::MCCInterface, 193                        | close, 214   |
| process, 193                                  | connect, 214   |
| Arc::MCCLoader, 195                           | enable_ssl, 215  |
| ~MCCLoader, 196                               | isconnected, 215                                       |
| MCCLoader, 196                                | shutdown, 215  |
| operator[], 196                               | Arc::PayloadRaw, 216                                   |
| Arc::MD5Sum, 197                              | Arc::PayloadRaw  |
| Arc::Message, 198                             | ~PayloadRaw, 216                                       |
| ~Message, 199                                 | Buffer, 217  |
| Attributes, 199                               | BufferPos, 217   |
| Auth, 199                                     | BufferSize, 217  |
| AuthContext, 199                              | Content, 217   |
| Context, 199                                  | Insert, 217  |
| Message, 199                                  | operator[], 217  |
| operator=, 199                                | PayloadRaw, 216  |
| Payload, 200                                  | Size, 217  |
| Arc::MessageAttributes, 201                   | Truncate, 218  |
| Arc::MessageAttributes Arc::MessageAttributes | Arc::PayloadRawInterface, 219                          |
| add, 202                                      | Arc::PayloadRawInterface, 219 Arc::PayloadRawInterface |
| attributes_, 203                              | Buffer, 219  |
| count, 202                                    | BufferPos, 219   |
| get, 202                                      |  |
| E .   | BufferSize, 219  |
| getAll, 202                                   | Content, 220   |
| MessageAttributes, 201                        | Insert, 220  |
| remove, 203                                   | operator[], 220  |
| removeAll, 203                                | Size, 220  |
| set, 203                                      | Truncate, 220  |
| Arc::MessageAuth, 204                         | Arc::PayloadSOAP, 221                                  |
| Arc::MessageAuth                              | Arc::PayloadSOAP                                       |
| Export, 204                                   | PayloadSOAP, 221                                       |
| Filter, 204                                   | Arc::PayloadStream, 222                                |
| get, 204                                      | Arc::PayloadStream                                     |
| operator[], 204                               | ~PayloadStream, 222                                    |
| remove, 205                                   | Get, 223   |
| set, 205                                      | GetHandle, 223   |
| Arc::MessageAuthContext, 206                  | handle_, 224   |
| Arc::MessageContext, 207                      | operator bool, 223                                     |
| Arc::MessageContext                           | operator!, 223   |
| Add, 207                                      | PayloadStream, 222                                     |
| Arc::MessageContextElement, 208               | Pos, 223   |
| Arc::MessagePayload, 209                      | Put, 223, 224  |
| Arc::ModuleManager, 210                       | seekable_, 224   |
|   |  |

| Timeout, 224                     | Run, 258                   |
|----------------------------------|----------------------------|
| Arc::PayloadStreamInterface, 225 | Running, 260               |
| Arc::PayloadStreamInterface      | Start, 260                 |
| Get, 225                         | Wait, 260                  |
| operator bool, 226               | WriteStdin, 260            |
| operator!, 226                   | Arc::SAMLToken, 264        |
| Pos, 226                         | ~SAMLToken, 265            |
| Put, 226                         | Authenticate, 266          |
| Timeout, 226                     | operator bool, 266         |
| Arc::PayloadWSRF, 228            | SAMLToken, 265             |
| Arc::PayloadWSRF                 | SAMLVersion, 265           |
| PayloadWSRF, 228                 | Arc::SecAttr, 267          |
| Arc::Plexer, 235                 | Arc::SecAttr               |
| ∼Plexer, 235                     | ARCAuth, 269               |
| logger, 236                      | Export, 268                |
| Next, 236                        | GACL, 269                  |
| Plexer, 235                      | Import, 268                |
| process, 236                     | operator bool, 268         |
| Arc::PlexerEntry, 237            | operator!=, 268            |
| Arc::Plugin, 238                 | operator==, 268            |
| Arc::PluginArgument, 239         | SAML, 269                  |
| Arc::PluginDescriptor, 240       | SecAttr, 268               |
| Arc::PluginsFactory, 241         | XACML, 269                 |
| Arc::PluginsFactory              | Arc::SecAttrFormat, 270    |
| get_instance, 242                | Arc::SecAttrValue, 271     |
| load, 242                        | Arc::SecAttrValue          |
| PluginsFactory, 241              | operator bool, 271         |
| Arc::RegularExpression, 248      | operator!=, 271            |
| Arc::RegularExpression           | operator==, 271            |
| ~RegularExpression, 248          | Arc::Service, 275          |
| getPattern, 248                  | AddSecHandler, 276         |
| hasPattern, 248                  | getID, 276                 |
| isOk, 249                        | logger, 276                |
| match, 249                       | ProcessSecHandlers, 276    |
| operator=, 249                   | RegistrationCollector, 276 |
| RegularExpression, 248           | sechandlers_, 276          |
| Arc::Run, 257                    | Service, 276               |
| ~Run, 258                        | Arc::SimpleCondition, 278  |
| AssignStderr, 258                | Arc::SimpleCondition       |
| AssignStdin, 258                 | broadcast, 278             |
| AssignStdout, 259                | lock, 278                  |
| AssignWorkingDirectory, 259      | reset, 278                 |
| CloseStderr, 259                 | signal, 278                |
| CloseStdin, 259                  | signal_nonblock, 278       |
| CloseStdout, 259                 | unlock, 278                |
| KeepStderr, 259                  | wait, 279                  |
| KeepStdin, 259 KeepStdin, 259    | wait_nonblock, 279         |
| KeepStdout, 259 KeepStdout, 259  | Arc::SOAPMessage, 280      |
| Kill, 259                        | ~SOAPMessage, 280          |
|                                  | _                          |
| operator   259                   | Attributes, 281            |
| operator!, 259                   | Payload, 281               |
| ReadStderr, 260                  | SOAPMessage, 280           |
| ReadStdout, 260                  | Arc::Time, 286             |
| Result, 260                      | GetFormat, 287             |

| GetTime, 287              | Path, 296                      |
|---------------------------|--------------------------------|
| operator std::string, 287 | path, 297                      |
| operator!=, 287           | Path2BaseDN, 296               |
| operator+, 287            | Port, 296                      |
| operator-, 287            | port, 297                      |
| operator<, 287            | Protocol, 296                  |
| operator<=, 287           | protocol, 297                  |
| operator=, 287            | Scope, 293                     |
| operator==, 287           | str, 296                       |
| operator>, 288            | URL, 293                       |
| operator>=, 288           | urloptions, 298                |
| SetFormat, 288            | Username, 296                  |
| SetTime, 288              | username, 298                  |
| str, 288                  | Arc::URLLocation, 299          |
| Time, 286                 | $\sim$ URLLocation, 300        |
| Arc::URL, 291             | fullstr, 300                   |
| ∼URL, 293                 | Name, 300                      |
| AddLDAPAttribute, 293     | name, 300                      |
| AddOption, 293            | str, 300                       |
| BaseDN2Path, 293          | URLLocation, 299, 300          |
| ChangeHost, 293           | Arc::UsernameToken, 301        |
| ChangeLDAPFilter, 293     | Arc::UsernameToken             |
| ChangeLDAPScope, 293      | Authenticate, 302              |
| ChangePath, 293           | operator bool, 302             |
| ChangePort, 294           | PasswordType, 301              |
| ChangeProtocol, 294       | Username, 302                  |
| CommonLocOption, 294      | UsernameToken, 301, 302        |
| CommonLocOptions, 294     | Arc::VOMSTrustList, 304        |
| commonlocoptions, 297     | Arc::VOMSTrustList             |
| ConnectionURL, 294        | AddChain, 305                  |
| FullPath, 294             | AddRegex, 305                  |
| fullstr, 294              | VOMSTrustList, 304             |
| Host, 294                 | Arc::WSAEndpointReference, 306 |
| host, 297                 | Arc::WSAEndpointReference      |
| HTTPOption, 294           | ~WSAEndpointReference, 306     |
| HTTPOptions, 295          | Address, 307                   |
| httpoptions, 297          | MetaData, 307                  |
| LDAPAttributes, 295       | operator XMLNode, 307          |
| Idapattributes, 297       | operator=, 307                 |
| LDAPFilter, 295           | ReferenceParameters, 307       |
| ldapfilter, 297           | WSAEndpointReference, 306      |
| LDAPScope, 295            | Arc::WSAHeader, 308            |
| ldapscope, 297            | Action, 309                    |
| Locations, 295            | Check, 309                     |
| locations, 297            | FaultTo, 309                   |
| operator bool, 295        | From, 309                      |
| operator<, 295            | header_allocated_, 310         |
| operator < < , 297        | MessageID, 309                 |
| operator==, 295           | NewReferenceParameter, 309     |
| Option, 295               | operator XMLNode, 309          |
| Options, 296              | ReferenceParameter, 309        |
| OptionString, 296         | RelatesTo, 310                 |
| Passwd, 296               |                                |
|                           | RelationshipType, 310          |
| passwd, 297               | ReplyTo, 310                   |

| To, 310  WSAHeader, 308  Are::WSRF, 311  allocated 312   |                     |                                       |
|--|---------------------|---------------------------------------|
| Are:::WSRF, 311     allocated 312     operator bool, 312     set_namespaces, 312     valid 312     WSRF, 311     Are::WSRFBaseFault, 313     Are::WSRFBaseFault, 313     Are::WSRPBaseFault, 317     WSRPFault, 317     WSRPFault, 317     WSRPFault, 317     WSRPFault, 317     WSRPFault, 317     WSRPFosourcePropertyChangeFailure, 318     Are::WSRPResourcePropertyChangeFailure, 318     Are::WSRPResourcePropertyChangeFailure, 318     Are::WSRPResourcePropertyChangeFailure, 318     Are::XS09Token, 320     Authenticate, 320     operator bool, 320     XS09Token, 319     XS09Token, 319     XS09Token, 319     Are::XMLNode, 321     ~XMLNode, 321     ~XMLNode, 321     ~XMLNode, 324     Attribute, 324     Get, 324     Get Boc, 324     Get Boc, 324     GetRoor, 325     Namespace, 325     Namespace, 325     NamespacePrefix, 325     Namespace, 325     NewAltribute, 325, 326     NewChild, 326     operator std::string, 326     operator std::strin      |                     | * ·                                   |
| allocated312   | WSAHeader, 308      | operator=, 327                        |
| operator bool, 312 set_namespaces, 312 valid_, 312 valid_, 312 WSRF, 311 Are::WSRFBaseFault, 313 Are::WSRFBaseFault, 313 Are::WSRFBaseFault, 313 Are::WSRPBaseFault, 313 Are::WSRPBaseFault, 313 Are::WSRPBaseFault, 313 Are::WSRPBaseFault, 313 Are::WSRPBaseFault, 313 Are::WSRPBaseFault, 317 Are::WSRPResourcePropertyChangeFailure, 318 Are::Mil.NodeContainer, 331 Arc::MIl.NodeContainer, 331 Arc::MIl. | Arc::WSRF, 311      | operator==, 327                       |
| set_namespaces, 312  | allocated_, 312     | operator[], 327, 328                  |
| SOAP, 312  | operator bool, 312  | Parent, 328                           |
| SOAP, 312  | set_namespaces, 312 | Path, 328                             |
| valid  | <u>*</u>            |                                       |
| WSRF, 311 Arc::WSRFBaseFault, 313 Arc::WSRPBaseFault set_namespaces, 314 WSRFBaseFault, 313 Arc::WSRP, 315 set_namespaces, 315 WSRP, 315 Arc::WSRPFault, 317 Arc::WSRPResourcePropertyChangeFailure, 318 Arc::WSRPResourcePropertyChangeFailure WSRPResourcePropertyChangeFailure Add, 311 Arc::XMLNodeContainer, 331 Arc::XMLNodeContainer Add, 331 Arc::XMLNodeContainer Arc::XMLNodeContainer Arc::XMLNodeContainer Add, 331 Arc::XMLNodeContainer Add, 331 Arc::XMLNodeContainer Arc::XMLNodeContainer Arc::XMLNodeContainer Arc::XMLNodeContainer Arc::XMLNodeContainer |                     |                                       |
| Arc::WSRFBaseFault, 313 Arc::WSRFBaseFault, 313 Arc::WSRPBaseFault, 313 Arc::WSRP, 315 Set_namespaces, 315 WSRP, 315 Arc::WSRPFault, 317 WSRPFault, 317 WSRPFault, 317 Arc::WSRPResourcePropertyChangeFailure, 318 Arc::WSRPResourcePropertyChangeFailure, 318 Arc::WSRPResourcePropertyChangeFailure, 318 Arc::WSRPResourcePropertyChangeFailure, 318 Arc::XS09Token, 319 ~X509Token, 319 X509Token, 319 XMLNode, 332 Arc::XMLSecNode AddSignatureTemplate, 334 DecryptNode, 334 EncryptNode, 334 EncryptNode, 334 EncryptNode, 334 EncryptNode, 334 XMLSecNode AddSignatureTemplate, 334 DecryptNode, 334 EncryptNode, 334 XMLSecNode, 333 Arc::XMLSecNode AddSignatureTemplate, 334 DecryptNode, 334 EncryptNode, 334 EncryptNode, 334 EncryptNode, 334 XMLSecNode, 333 Arc::XMLSecNode AddSignatureTemplate, 334 DecryptNode, 334 EncryptNode, 334 Encryp |                     | · · · · · · · · · · · · · · · · · · · |
| Arc::WSRFBaseFault, 313 Arc::WSRP, 315 set_namespaces, 315 WSRP, 315 Arc::WSRPFault, 317 WSRPFault, 317 Arc::WSRPResourcePropertyChangeFailure, 318 Arc::WSRPResourcePropertyChangeFailure WSRPResourcePropertyChangeFailure Add. 331 AddNew, 331 Nodes, 332  poperator=, 332 operator=, 3 |                     | •                                     |
| set_namespaces, 314 WSRFBaseFault, 313 Arc::WSRP, 315 set_namespaces, 315 WSRP, 315 Arc::WSRPFault, 317 Arc::WSRPFault, 317 Arc::WSRPResourcePropertyChangeFailure, 318 Arc::WSRPResourcePropertyChangeFailure WSRPResourcePropertyChangeFailure WSRPResourcePropertyChangeFailure, 318 Arc::XS09Token, 319 ~X509Token, 319 Arc::XMLNode, 320 Authenticate, 320 operator bool, 320 XS09Token, 319 XS09Token, 319 XS09Token, 319 XS09Token, 319 XS09Token, 319 XS09Token, 319 Arc::XMLNode, 321 ~XMLNode, 321 Art::MLSecNode, 332 Autribute, 324 AttributesSize, 324 Child, 324 Destroy, 324 FullName, 324 Get, 324 GetRot, 325 is_owner_, 330 is_temporary_, 330 MatchXMLNamespace, 329, 330 Name, 325 Namespaces, 325 Namespaces, 325 Namespaces, 325 Namespaces, 325 Namespaces, 325 Namespaces, 325 NewAttribute, 325, 326 operator bool, 326 operator std::string, 326 operator, 327  SaveToStream, 329 Saze 329 Size, 329 Arc::XMLNodeContainer, 331 Arc::XMLNodeContainer, 321 Arc::XMLNodeContainer, 321 Arc::XMLNodeContainer, 321 Arc::XMLSecNode, 334 Arc::XMLSecNode, 334 Arc::XMLSecNode, 334 A |                     | <u> -</u>                             |
| WSRFBaseFault, 313 Are::WSRP, 315 set_namespaces, 315 WSRP, 315 Are::WSRPFault, 317 Are::WSRPResourcePropertyChangeFailure, 318 Are::WSRPResourcePropertyChangeFailure, 318 Are::XS09Token, 319 ~X509Token, 319 Are::XMLNode, 320 operator bool, 320 X509Token, 319 Are::XMLNode, 321 ~XMLNode, 321 ~XMLNode, 321 ~XMLNode, 321 ~XMLNode, 321 Are::XMLSecNode, 333 Are::XMLSecNode, 333 Are::XMLSecNode, 334 Cett, 324 Get, 325 Namespace, 325 New, 325 Namespace, 325 New, 325 NewAttribute, 325, 326 Operator bool, 326 operator std::string, 32 |                     |                                       |
| Arc::WSRP, 315 set_namespaces, 315 WSRP, 315 Arc::WSRPFault, 317 WSRPFault, 317 Arc::WSRPResourcePropertyChangeFailure, 318 Arc::WSRPResourcePropertyChangeFailure, 318 Arc::XS09Token, 319 ~X509Token, 320 Authenticate, 320 operator bool, 320 XS09Token, 319 X509TokenType, 319 Arc::XMLNode, 321 ~XMLNode, 321 ~XMLNode, 321 Attribute, 324 Attribute, 324 Attribute, 324 Child, 324 Destroy, 324 FullName, 324 GetDoc, 324 GetNot, 324 GetNot, 324 GetNot, 324 GetXML, 324, 325 is_owner_, 330 is_temporary_, 330 MatchXMLNamespace, 329, 330 MatchXMLNamespace, 325 Namespace, 325 Namespace, 325 Namespaces, 325 Namespaces, 325 New, 325 New, 325 New, 325 NewAttribute, 326 operator tool, 326 operator std::string, 326 operator; 326 operator; 326 operator; 326, 327   | •                   |                                       |
| set_namespaces, 315 WSRP, 315 Are:::WSRPFault, 317 WSRPFault, 317 Are:::WSRPResourcePropertyChangeFailure, 318 Are:::WSRPResourcePropertyChangeFailure, 318 Are::XS09Token, 319  |                     |                                       |
| WSRP, 315 Arc::WSRPFault, 317 WSRPFault, 317 Arc::WSRPResourcePropertyChangeFailure, 318 Arc::WSRPResourcePropertyChangeFailure WSRPResourcePropertyChangeFailure, 318 Arc::WSRPResourcePropertyChangeFailure, 318 Arc::WSRPResourcePropertyChangeFailure, 318 Arc::WSRPResourcePropertyChangeFailure, 318 Arc::WSRPResourcePropertyChangeFailure, 318 Arc::XMLNodeContainer, 331 Arc::XMLNodeContainer Add, 331 AddNew, 331 Nodes, 332 operator=, 332 operator=, 332 operator=, 332 operator=, 332 operator=, 332 Arc::XMLSecNode, 333 Arc::XMLSecNode, 333 Arc::XMLSecNode, 333 Arc::XMLSecNode AddSignatureTemplate, 334 DecryptNode, 334 EncryptNode, 334 EncryptNode, 334 SignNode, 334 VerifyNode, 334 VerifyNode, 334 VerifyNode, 334 SignNode, 334 VerifyNode, 334 CERT_TYPE_GSI_3_IMITED_PROXY, 34 CERT_TYPE_GSI_3_IMITED_PROXY, 34 CERT_TYPE_GSI_3_IMITED_PROXY, 34 CERT_TYPE_GSI_3_IMITED_PROXY, 34 CERT_TYPE_RFC_ANYLANGUAGE PROXY, 34 CERT_TYPE_RFC_ANYLANGUAGE PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY, 34 CERT_TYPE_  |                     |                                       |
| Arc::WSRPFault, 317 WSRPFault, 317 Arc::WSRPResourcePropertyChangeFailure, 318 Arc::WSRPResourcePropertyChangeFailure, 318 Arc::X509Token, 319 Arc::X509Token, 319 Arc::XMLNodeContainer Add, 331 AddNew, 331 Arc::XMLNodeContainer Add, 331 AddNew, 331 AddNew, 331 Arc::XMLNodeContainer Add, 331 AddNew, 331 AddNew, 331 Arc::XMLNodeContainer Add, 331 AddNew, 331 Arc::XMLSocNode AddSignatureTemplate, 334 DecryptNode, 334 EncryptNode, 334 EncryptNode, 334 Arc::XMLNodeContainer Add, 331 AddNew, 331 Arc::XMLSocNode AddSignatureTemplate, 334 DecryptNode, 334 Arc::XecEnded  | <u>*</u>            |                                       |
| WSRPFault, 317 Arc::WSRPResourcePropertyChangeFailure, 318 Arc::WSRPResourcePropertyChangeFailure, 318 Arc::X509Token, 319   |                     |                                       |
| Arc::WSRPResourcePropertyChangeFailure, 318 Arc::WSRPResourcePropertyChangeFailure WSRPResourcePropertyChangeFailure, 318 Arc::XS09Token, 319  | •                   | <u> •</u>                             |
| Arc::WSRPResourcePropertyChangeFailure WSRPResourcePropertyChangeFailure, 318 Arc::X509Token, 319  |                     |                                       |
| WSRPResourcePropertyChangeFailure, 318       AddNew, 331         Arc::X509Token, 319       Nodes, 332         ∞x509Token, 320       operator bool, 320         x509Token, 319       X509Token, 319         Arc::XMLNode, 321       Arc::XMLSecNode, 333         Arc::XMLNode, 323       Arc::XMLSecNode, 334         Attribute, 324       DecryptNode, 334         AttributesSize, 324       DecryptNode, 334         Child, 324       SignNode, 334         Destroy, 324       VerifyNode, 334         FullName, 324       Arc::XecAuth         GetDoc, 324       Arc::SecAutr, 269         GetRoot, 324       Arc::SecAutr, 269         GetXML, 324, 325       CERT_TYPE_GSI_2_LIMITED_PROXY, 34         is_owner_, 330       CERT_TYPE_GSI_3_IMPERSONATION         Names, 325       PROXY, 33         Namespaces, 325       CERT_TYPE_GSI_3_LIMITED_PROXY, 34         CERT_TYPE_GSI_3_LIMITED_PROXY, 34         CERT_TYPE_GSI_3_LIMITED_PROXY, 34         CERT_TYPE_GSI_3_LIMITED_PROXY, 34         CERT_TYPE_GSI_3_RESTRICTED         PROXY, 34         CERT_TYPE_GSI_3_RESTRICTED       PROXY, 34         CERT_TYPE_RFC_IMPERSONATION       PROXY, 34         CERT_TYPE_RFC_IMPERSONATION       PROXY, 34 <th< td=""><td></td><td></td></th<>   |                     |                                       |
| Arc::X509Token, 319  |                     | *                                     |
| ~X509Token, 320         operator=, 332           Authenticate, 320         operator[], 332           operator bool, 320         Size, 332           X509Token, 319         XMLNodeContainer, 331           X509TokenType, 319         Arc::XMLSecNode, 333           Arc::XMLNode, 321         Arc::XMLSecNode           ~XMLNode, 323         AddSignatureTemplate, 334           Attribute, 324         DecryptNode, 334           AttributesSize, 324         EncryptNode, 334           Child, 324         SignNode, 334           Destroy, 324         VerifyNode, 334           FullName, 324         ARCAuth           Get, 324         Arc::SecAttr, 269           GetRoot, 324         Arc::SecAttr, 269           GetXML, 324, 325         CERT_TYPE_CA, 33           is_owner_, 330         CERT_TYPE_GSI_2_LIMITED_PROXY, 34           MatchXMLName, 329         CERT_TYPE_GSI_2_LIMITED_PROXY, 34           MatchXMLNamespace, 329, 330         CERT_TYPE_GSI_3_IMPERSONATION           Namespace, 325         PROXY, 34           New, 325         CERT_TYPE_GSI_3_LIMITED_PROXY, 34           CERT_TYPE_GSI_3_INDEPENDENT         PROXY, 34           CERT_TYPE_GSI_3_RESTRICTED         PROXY, 34           CERT_TYPE_RFC_IMPERSONATION         PROXY, 34     <  | - · · · · ·         |                                       |
| Authenticate, 320 operator bool, 320 X509Token, 319 X509Token, 319 Arc::XMLNode, 321  ~XMLNode, 321 Arc::XMLSecNode, 333 Attribute, 324 AttributesSize, 324 Child, 324 Destroy, 324 GetRoot, 324 GetRoot, 324 GetRoot, 324 GetRoot, 324 GetRoot, 324 MatchXMLName, 329 MatchXMLNamespace, 329, 330 Name, 325 Namespace, 325 Namespaces, 325 New Attribute, 325, 326 NewChild, 326 operator bool, 326 operator!=, 326 operator!=, 326 operator!=, 326 operator!=, 326 operator!=, 326  Arc::XMLSecNode, 333 Arc::XMLSecNode, 334 LencryptNode, 334 VerifyNode, 334 VerifyNode, 334 VerifyNode, 334 VerifyNode, 334 VerifyNode, 334 VerifyNode, 334 CERT_TYPE_CA, 33 CERT_TYPE_CA, 33 CERT_TYPE_CA, 33 CERT_TYPE_CA, 33 CERT_TYPE_GSI_2_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_IMPERSONATION PROXY, 33 CERT_TYPE_GSI_3_IMPERSONATION PROXY, 34 CERT_TYPE_GSI_3_RESTRICTED PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY   |                     |                                       |
| operator bool, 320 X509Token, 319 X509Token, 319 Are::XMLNode, 321  Are::XMLNode, 323 Attribute, 324 Attribute, 324 AttributesSize, 324 Child, 324 Destroy, 324 FullName, 324 Get, 324 Get Root, 324 Get Root, 324 GetXML, 324, 325 is_owner_, 330 is_temporary_, 330 MatchXMLName, 329 MatchXMLNamespace, 329, 330 Namespace, 325 Namespace, 325 Namespace, 325 Namespace, 325 New, 325 New, 325 NewAttribute, 326 operator tsd::string, 326 operator!=, 326, 327  XMLNodeContainer, 331 Arc::XMLSecNode, 333 Arc::XMLSecNode, 334 DecryptNode, 334 EncryptNode, 334 EncryptNode, 334 SignNode, 334 ArCAuth Arc::SecAttr, 269 ArcCredential, 30 CERT_TYPE_CA, 33 CERT_TYPE_CA, 33 CERT_TYPE_CA, 33 CERT_TYPE_GSI_2_LIMITED_PROXY, 34 CERT_TYPE_GSI_2_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_IMPERSONATION PROXY, 33 CERT_TYPE_GSI_3_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_RESTRICTED PROXY, 34 CERT_TYPE_GSI_3_RESTRICTED PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY, 34  |                     | <u> </u>                              |
| X509Token, 319 X509TokenType, 319 Arc::XMLNode, 321 Arc::XMLNode, 323 Attribute, 324 Attribute, 324 AttributesSize, 324 Child, 324 Destroy, 324 FullName, 324 Get, 324 Get 324 GetRoot, 324 GetRoot, 324 GetxML, 324, 325 is_owner_, 330 is_temporary_, 330 MatchXMLName, 329 MatchXMLName, 329 MatchXMLNamespace, 329, 330 Namespace, 325 Namespace, 325 Namespaces, 325 Namespaces, 325 New, 325 New, 325 New 4ttribute, 325, 326 Operator bool, 326 Operator std::string, 326 Operator!=, 326, 327  AddSignatureTemplate, 333 Arc::XMLSecNode AddSignatureTemplate, 334 DecryptNode, 334 EncryptNode, 334 EncryptNode, 334 VerifyNode, 333 Arc::XMLSecNode AddSignatureTemplate, 334 DecryptNode, 334 EncryptNode, 334 VerifyNode, 34 VerifyNode,  | •                   | •                                     |
| X509TokenType, 319 Arc::XMLNode, 321  ~XMLNode, 323 Attribute, 324 AttributesSize, 324 Child, 324 Destroy, 324 FullName, 324 GetDoc, 324 GetRoot, 324 GetXML, 324, 325 is_owner_, 330 MatchXMLName, 329 MatchXMLName, 329 MatchXMLNamespace, 325, 326 Namespace, 325 Namespaces, 325 Namespaces, 325 Namespaces, 325 New, 325 New, 325 New, 325 New, 326 Operator std::string, 326 Operator!=, 326, 327  Arc::XMLSecNode, 333 Arc::XMLSecNode AddSignatureTemplate, 334 DecryptNode, 334 EncryptNode, 334 VerifyNode, 334 XMLsecNode, 333 ARCAuth Arc::SecAttr, 269 ArcCredential, 30 CERT_TYPE_CA, 33 CERT_TYPE_CA, 33 CERT_TYPE_GSI_2_LIMITED_PROXY, 34 CERT_TYPE_GSI_2_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_IMPERSONATION PROXY, 33 CERT_TYPE_GSI_3_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_LIMITED_PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY, 34  | <u>*</u>            |                                       |
| Arc::XMLNode, 321  ~XMLNode, 323 Attribute, 324 Attribute, 324 AttributesSize, 324 Child, 324 Destroy, 324 PellName, 324 Get, 324 Get 324 GetXML, 324, 325 is_owner_, 330 MatchXMLName, 329 MatchXMLNamespace, 329, 330 Name, 325 Namespace, 325 Namespace, 325 New Attribute, 325, 326 New Child, 326 operator!, 326 operator!, 326 operator!, 326 Attribute, 323 AddSignatureTemplate, 334 DecryptNode, 334 EncryptNode, 334 VerifyNode, 334 VerifyNode, 334 XMLSecNode, 333 ARCAuth Arc::SecAttr, 269 ArcCredential, 30 CERT_TYPE_CA, 33 CERT_TYPE_CA, 33 CERT_TYPE_EBC, 33 CERT_TYPE_BCS, 33 CERT_TYPE_GSI_2_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_IMPERSONATION PROXY, 33 CERT_TYPE_GSI_3_IMPERSONATION PROXY, 34 CERT_TYPE_GSI_3_RESTRICTED PROXY, 34 CERT_TYPE_GSI_3_RESTRICTED PROXY, 34 CERT_TYPE_RFC_ANYLANGUAGE PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY   |                     | XMLNodeContainer, 331                 |
| AddSignatureTemplate, 334 Attribute, 324 Attribute, 324 AttributesSize, 324 Child, 324 Destroy, 324 FullName, 324 Get, 324 GetDoc, 324 GetDoc, 324 GetML, 324, 325 is_owner_, 330 is_temporary_, 330 MatchXMLName, 329 MatchXMLNamespace, 329, 330 Name, 325 Namespace, 325 Namespace, 325 Namespaces, 325 New, 325 New, 325 NewAttribute, 325, 326 NewChild, 326 operator std::string, 326 operator!_, 326 operator!_, 326 AddSignatureTemplate, 334 DecryptNode, 334 EncryptNode, 334 VerifyNode, 334 XMLSecNode, 333 ARCAuth Arc::SecAttr, 269 ArcCredential, 30 CERT_TYPE_CA, 33 CERT_TYPE_CA, 33 CERT_TYPE_GSI_2_LIMITED_PROXY, 34 CERT_TYPE_GSI_2_PROXY, 34 CERT_TYPE_GSI_3_IMPERSONATION PROXY, 34 CERT_TYPE_GSI_3_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_RESTRICTED PROXY, 34 CERT_TYPE_GSI_3_RESTRICTED PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY, 34 CERT_TYPE_   | X509TokenType, 319  | Arc::XMLSecNode, 333                  |
| Attribute, 324 AttributesSize, 324 Child, 324 Destroy, 324 PullName, 324 Get, 324 GetDoc, 324 GetRoot, 324 GetXML, 324, 325 is_owner_, 330 MatchXMLName, 329 MatchXMLNamespace, 325 Namespace, 325 Namespace, 325 Namespace, 325 Namespace, 325 New, 325 New, 325 New, 325 New, 325 New, 325 NewChild, 326 Operator std::string, 326 Operator!, 326 Operator!, 326 Operator!, 326 Operator!, 326 Operator std::string, 326 Operator!, 324 EncryptNode, 334 EncryptNode, 334 VerifyNode, 334 Namespace, 334 NATCHANAME, 334 NAMLSecNode, 333 ARCAuth Arc::SecAttr, 269 ArcCredential, 30 CERT_TYPE_CA, 33 CERT_TYPE_GSI_2_LIMITED_PROXY, 34 CERT_TYPE_GSI_2_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_IMPERSONATION PROXY, 33 CERT_TYPE_GSI_3_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_RESTRICTED PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY, 3   | Arc::XMLNode, 321   | Arc::XMLSecNode                       |
| AttributesSize, 324 Child, 324 Destroy, 324 FullName, 324 Get, 324 Get Root, 324 GetXML, 324, 325 is_owner_, 330 MatchXMLName, 329 MatchXMLNamespace, 329, 330 Namespace, 325 NamespacePrefix, 325 Namespace, 325 New Attribute, 325, 326 New Child, 326 operator!, 326 operator!, 326 operator!, 326 Oestroy, 324 Arcutefixing Aze SignNode, 334 CERT_SecAttr, 269 ArcCredential, 30 CERT_TYPE_CA, 33 CERT_TYPE_CA, 33 CERT_TYPE_GESI_2_LIMITED_PROXY, 34 CERT_TYPE_GSI_2_PROXY, 34 CERT_TYPE_GSI_3_IMPERSONATION PROXY, 33 CERT_TYPE_GSI_3_INDEPENDENT PROXY, 34 CERT_TYPE_GSI_3_RESTRICTED PROXY, 34 CERT_TYPE_RFC_ANYLANGUAGE PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY, 34 CERT_TYP   | ~XMLNode, 323       | AddSignatureTemplate, 334             |
| Child, 324 Destroy, 324 PullName, 324 Get, 324 Get, 324 Get Boc, 324 GetRoot, 324 GetXML, 324, 325 is_owner_, 330 is_temporary_, 330 MatchXMLName, 329 MatchXMLNamespace, 329, 330 Namespace, 325 Namespace, 325 Namespace, 325 Namespaces, 325 New, 325 New, 325 NewAttribute, 325, 326 NewChild, 326 operator !, 326 operator!, 326 operator!, 326  Destroy, 324  ARCAuth Arc::SecAttr, 269 ArcCredential, 30 CERT_TYPE_CA, 33 CERT_TYPE_GSI_2_LIMITED_PROXY, 34 CERT_TYPE_GSI_2_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_IMPERSONATION PROXY, 33 CERT_TYPE_GSI_3_IMPERSONATION PROXY, 34 CERT_TYPE_GSI_3_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_RESTRICTED PROXY, 34 CERT_TYPE_GSI_3_RESTRICTED PROXY, 34 CERT_TYPE_RFC_ANYLANGUAGE PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY, 34 CERT_TYPE_RFC_INDEPENDENT   | Attribute, 324      | DecryptNode, 334                      |
| Destroy, 324 FullName, 324 Substituting Substitution Substituting Subs | AttributesSize, 324 | EncryptNode, 334                      |
| FullName, 324 Get, 324 Get, 324 GetDoc, 324 GetRoot, 324 GetXML, 324, 325 is_owner_, 330 is_temporary_, 330 MatchXMLName, 329 MatchXMLNamespace, 329, 330 Namespace, 325 Namespace, 325 Namespace, 325 Namespaces, 325 New, 325 New, 325 New, 325 New, 325 New Attribute, 325, 326 NewChild, 326 operator bool, 326 operator!, 326 operator!=, 326, 327  XMLSecNode, 333 ARCAuth Arc::SecAttr, 269 ArcCredential, 30 CERT_TYPE_CA, 33 CERT_TYPE_GSI_2_LIMITED_PROXY, 34 CERT_TYPE_GSI_2_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_IMPERSONATION PROXY, 33 CERT_TYPE_GSI_3_INDEPENDENT PROXY, 34 CERT_TYPE_GSI_3_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_RESTRICTED PROXY, 34 CERT_TYPE_RFC_ANYLANGUAGE PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY, 34 CERT_TYPE_RFC_INDEPENDENT   | Child, 324          | SignNode, 334                         |
| Get, 324 GetDoc, 324 GetRoot, 324 GetXML, 324, 325 is_owner_, 330 is_temporary_, 330 MatchXMLName, 329 MatchXMLNamespace, 329, 330 Namespace, 325 NamespacePrefix, 325 Namespaces, 325 New, 325 New, 325 New, 325 NewAttribute, 325, 326 NewChild, 326 operator bool, 326 operator!_, 326 GERT_TYPE_CA, 33 CERT_TYPE_EBC, 33 CERT_TYPE_GSI_2_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_IMPERSONATION PROXY, 33 CERT_TYPE_GSI_3_INDEPENDENT PROXY, 34 CERT_TYPE_GSI_3_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_RESTRICTED PROXY, 34 CERT_TYPE_RFC_ANYLANGUAGE PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY, 34 CERT_TYPE_RFC_INDEPENDENT  | Destroy, 324        | VerifyNode, 334                       |
| Get, 324 GetDoc, 324 GetRoot, 324 GetXML, 324, 325 is_owner_, 330 is_temporary_, 330 MatchXMLName, 329 MatchXMLNamespace, 329, 330 Namespace, 325 NamespacePrefix, 325 Namespaces, 325 New, 325 New, 325 New, 325 NewAttribute, 325, 326 NewChild, 326 operator bool, 326 operator!_, 326 GERT_TYPE_CA, 33 CERT_TYPE_EBC, 33 CERT_TYPE_GSI_2_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_IMPERSONATION PROXY, 33 CERT_TYPE_GSI_3_INDEPENDENT PROXY, 34 CERT_TYPE_GSI_3_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_RESTRICTED PROXY, 34 CERT_TYPE_RFC_ANYLANGUAGE PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY, 34 CERT_TYPE_RFC_INDEPENDENT  | FullName, 324       | XMLSecNode, 333                       |
| GetDoc, 324 GetRoot, 324 GetXML, 324, 325 is_owner_, 330 is_temporary_, 330 MatchXMLName, 329 MatchXMLNamespace, 329, 330 Namespace, 325 NamespacePrefix, 325 Namespaces, 325 NewAttribute, 325, 326 NewChild, 326 operator !, 326 operator!=, 326, 327  GetXML, 324 Arc::SecAttr, 269 ArcCredential, 30 CERT_TYPE_CA, 33 CERT_TYPE_CSI_2_LIMITED_PROXY, 34 CERT_TYPE_GSI_2_LIMITED_PROXY, 34 CERT_TYPE_GSI_2_PROXY, 34 CERT_TYPE_GSI_3_IMPERSONATION PROXY, 33 CERT_TYPE_GSI_3_INDEPENDENT PROXY, 34 CERT_TYPE_GSI_3_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_RESTRICTED PROXY, 34 CERT_TYPE_RFC_ANYLANGUAGE PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY, 34 CERT_TYPE_RFC_INDEPENDENT   |                     | ARCAuth                               |
| GetRoot, 324 GetXML, 324, 325 is_owner_, 330 is_temporary_, 330 MatchXMLName, 329 MatchXMLNamespace, 329, 330 Namespace, 325 NamespacePrefix, 325 Namespaces, 325 New, 325 New, 325 NewAttribute, 325, 326 NewChild, 326 operator!, 326 operator!=, 326, 327  ArcCredential, 30 CERT_TYPE_CA, 33 CERT_TYPE_BEC, 33 CERT_TYPE_GSI_2_LIMITED_PROXY, 34 CERT_TYPE_GSI_2_PROXY, 34 CERT_TYPE_GSI_3_IMPERSONATION PROXY, 33 CERT_TYPE_GSI_3_INDEPENDENT PROXY, 34 CERT_TYPE_GSI_3_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_RESTRICTED PROXY, 34 CERT_TYPE_RFC_ANYLANGUAGE PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY, 34 CERT_TYPE_RFC_INDEPENDENT  |                     | Arc::SecAttr, 269                     |
| GetXML, 324, 325 is_owner_, 330 is_temporary_, 330 MatchXMLName, 329 MatchXMLNamespace, 329, 330 Namespace, 325 NamespacePrefix, 325 Namespaces, 325 Namespaces, 325 New, 325 New, 325 NewAttribute, 325, 326 NewChild, 326 operator bool, 326 operator!=, 326, 327  CERT_TYPE_GSI_2_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_IMPERSONATION PROXY, 33 CERT_TYPE_GSI_3_INDEPENDENT PROXY, 34 CERT_TYPE_GSI_3_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_RESTRICTED PROXY, 34 CERT_TYPE_RFC_ANYLANGUAGE PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY, 34 CERT_TYPE_RFC_INDEPENDENT  |                     |                                       |
| is_owner_, 330 is_temporary_, 330 CERT_TYPE_EEC, 33 CERT_TYPE_GSI_2_LIMITED_PROXY, 34 MatchXMLName, 329 MatchXMLNamespace, 329, 330 Namespace, 325 Namespace, 325 NamespacePrefix, 325 Namespaces, 325 Namespaces, 325 New, 325 New, 325 NewAttribute, 325, 326 NewChild, 326 operator bool, 326 operator!, 326 operator!, 326 operator!=, 326, 327  CERT_TYPE_EEC, 33 CERT_TYPE_GSI_2_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_RESTRICTED PROXY, 34 CERT_TYPE_RFC_ANYLANGUAGE PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY, 34 CERT_TYPE_RFC_IMPERSONATION CERT_TYPE_RFC_INDEPENDENT  |                     |                                       |
| is_temporary_, 330  MatchXMLName, 329  MatchXMLNamespace, 329, 330  Namespace, 325  NamespacePrefix, 325  New, 325  New, 325  New Attribute, 325, 326  NewChild, 326  operator bool, 326  operator!, 326  operator!=, 326, 327  CERT_TYPE_GSI_2_PROXY, 34  CERT_TYPE_GSI_3_IMPERSONATION PROXY, 33  CERT_TYPE_GSI_3_INDEPENDENT PROXY, 34  CERT_TYPE_GSI_3_LIMITED_PROXY, 34  CERT_TYPE_GSI_3_RESTRICTED PROXY, 34  CERT_TYPE_RFC_ANYLANGUAGE PROXY, 34  CERT_TYPE_RFC_IMPERSONATION PROXY, 34  CERT_TYPE_RFC_IMPERSONATION PROXY, 34  CERT_TYPE_RFC_IMPERSONATION CERT_TYPE_RFC_INDEPENDENT   |                     |                                       |
| MatchXMLName, 329 MatchXMLNamespace, 329, 330 MatchXMLNamespace, 329, 330 Name, 325 Namespace, 325 NamespacePrefix, 325 Namespaces, 325 New, 325 New, 325 NewAttribute, 325, 326 NewChild, 326 operator bool, 326 operator!, 326 operator!=, 326, 327  CERT_TYPE_GSI_3_IMPERSONATION PROXY, 34 CERT_TYPE_GSI_3_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_RESTRICTED PROXY, 34 CERT_TYPE_RFC_ANYLANGUAGE PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY, 34 CERT_TYPE_RFC_IMPERSONATION CERT_TYPE_RFC_IMPERSONATION CERT_TYPE_RFC_INDEPENDENT  |                     |                                       |
| MatchXMLNamespace, 329, 330  Name, 325  Namespace, 325  NamespacePrefix, 325  Namespaces, 325  Namespaces, 325  Namespaces, 325  Namespaces, 325  Namespaces, 325  New, 325  New, 325  NewAttribute, 325, 326  NewChild, 326  operator bool, 326  operator std::string, 326  operator!, 326  operator!=, 326, 327  CERT_TYPE_GSI_3_IMPERSONATION PROXY, 34  CERT_TYPE_GSI_3_LIMITED_PROXY, 34  CERT_TYPE_GSI_3_RESTRICTED PROXY, 34  CERT_TYPE_RFC_ANYLANGUAGE PROXY, 34  CERT_TYPE_RFC_IMPERSONATION PROXY, 34  CERT_TYPE_RFC_IMPERSONATION CERT_TYPE_RFC_IMPERSONATION PROXY, 34  CERT_TYPE_RFC_INDEPENDENT  |                     |                                       |
| Name, 325 Namespace, 325 NamespacePrefix, 325 Namespaces, 325 Namespaces, 325 Namespaces, 325 Namespaces, 325 New, 325 New, 325 NewAttribute, 325, 326 NewChild, 326 Operator bool, 326 Operator std::string, 326 Operator!, 326 Operator!=, 326, 327  PROXY, 33 CERT_TYPE_GSI_3_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_RESTRICTED PROXY, 34 CERT_TYPE_RFC_ANYLANGUAGE PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY, 34 CERT_TYPE_RFC_IMPERSONATION CERT_TYPE_RFC_IMPERSONATION CERT_TYPE_RFC_IMPERSONATION PROXY, 34 CERT_TYPE_RFC_IMPERSONATION CERT_TYPE_RFC_IMPERSONATION  |                     |                                       |
| Namespace, 325 NamespacePrefix, 325 Namespaces, 325 Namespaces, 325 New, 325 New, 325 NewAttribute, 325, 326 NewChild, 326 operator bool, 326 operator std::string, 326 operator!, 326 operator!=, 326, 327  CERT_TYPE_GSI_3_LIMITED_PROXY, 34 CERT_TYPE_GSI_3_RESTRICTED PROXY, 34 CERT_TYPE_RFC_ANYLANGUAGE PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY, 34 CERT_TYPE_RFC_IMPERSONATION CERT_TYPE_RFC_IMPERSONATION CERT_TYPE_RFC_INDEPENDENT  | <u> </u>            |                                       |
| NamespacePrefix, 325 Namespaces, 325 New, 325 New, 325 NewAttribute, 325, 326 NewChild, 326 Operator bool, 326 Operator std::string, 326 Operator!, 326 Operator!=, 326, 327  PROXY, 34 CERT_TYPE_GSI_3_RESTRICTED PROXY, 34 CERT_TYPE_RFC_ANYLANGUAGE PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY, 34 CERT_TYPE_RFC_IMPERSONATION CERT_TYPE_RFC_IMPERSONATION CERT_TYPE_RFC_IMPERSONATION CERT_TYPE_RFC_IMPERSONATION CERT_TYPE_RFC_IMPERSONATION CERT_TYPE_RFC_IMPERSONATION   |                     |                                       |
| Namespaces, 325  New, 325  NewAttribute, 325, 326  NewChild, 326  operator bool, 326  operator!, 326  operator!=, 326, 327  CERT_TYPE_GSI_3_RESTRICTED PROXY, 34  CERT_TYPE_RFC_ANYLANGUAGE PROXY, 34  CERT_TYPE_RFC_IMPERSONATION PROXY, 34  CERT_TYPE_RFC_IMPERSONATION CERT_TYPE_RFC_IMPERSONATION PROXY, 34  CERT_TYPE_RFC_INDEPENDENT   | 1                   |                                       |
| New, 325 NewAttribute, 325, 326 NewChild, 326 Operator bool, 326 Operator std::string, 326 Operator!, 326 Operator!=, 326, 327  CERT_TYPE_GSI_3_RESTRICTED PROXY, 34 CERT_TYPE_RFC_ANYLANGUAGE PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY, 34 CERT_TYPE_RFC_IMPERSONATION CERT_TYPE_RFC_IMPERSONATION   | ÷                   |                                       |
| NewAttribute, 325, 326  NewChild, 326  operator bool, 326  operator std::string, 326  operator!, 326  operator!=, 326, 327  PROXY, 34  CERT_TYPE_RFC_ANYLANGUAGE PROXY, 34  CERT_TYPE_RFC_IMPERSONATION PROXY, 34  CERT_TYPE_RFC_IMPERSONATION   | ÷                   |                                       |
| NewChild, 326 operator bool, 326 operator std::string, 326 operator!, 326 operator!=, 326, 327  CERT_TYPE_RFC_ANYLANGUAGE PROXY, 34 CERT_TYPE_RFC_IMPERSONATION PROXY, 34 CERT_TYPE_RFC_INDEPENDENT  |                     |                                       |
| operator bool, 326 operator std::string, 326 operator!, 326 operator!=, 326, 327  PROXY, 34  CERT_TYPE_RFC_IMPERSONATION PROXY, 34  CERT_TYPE_RFC_INDEPENDENT  |                     |                                       |
| operator std::string, 326 operator!, 326 operator!=, 326, 327  CERT_TYPE_RFC_IMPERSONATION PROXY, 34 CERT_TYPE_RFC_INDEPENDENT   |                     |                                       |
| operator!, 326 PROXY, 34 Operator!=, 326, 327 CERT_TYPE_RFC_INDEPENDENT  | <u>*</u>            |                                       |
| operator!=, 326, 327 CERT_TYPE_RFC_INDEPENDENT   |                     |                                       |
| •  | <u>*</u>            |                                       |
| operator++, 32/ PROXY, 34  | <u>*</u>            |                                       |
|  | operator++, 32/     | PKUX Y, 54                            |

| CERT TYPE REC LIMITED PROVING          | F 1 3 C 140                              |
|--|--|
| CERT_TYPE_RFC_LIMITED_PROXY, 34        | EvaluationCtx, 140                       |
| CERT_TYPE_RFC_RESTRICTED_PROXY,        | split, 140                               |
| 34                                     | ArcSec::Evaluator, 141                   |
| ArcCredential                          | ArcSec::Evaluator                        |
| certType, 33                           | addPolicy, 142                           |
| ARCLibError, 37                        | evaluate, 142                            |
| ARCLibError, 37                        | getAlgFactory, 143                       |
| ARCLibError                            | getAttrFactory, 143                      |
| ~ARCLibError, 37                       | getFnFactory, 143                        |
| ARCLibError, 37                        | getName, 143                             |
| what, 37                               | setCombiningAlg, 143                     |
| ArcSec::AlgFactory, 35                 | ArcSec::EvaluatorContext, 144            |
| ArcSec::AlgFactory                     | ArcSec::EvaluatorContext                 |
| createAlg, 36                          | operator AlgFactory *, 144               |
| ArcSec::Attr, 39                       | operator AttributeFactory *, 144         |
| ArcSec::AttributeFactory, 40           | operator FnFactory *, 144                |
| ArcSec::AttributeProxy, 44             | ArcSec::EvaluatorLoader, 145             |
| ArcSec::AttributeProxy                 | ArcSec::EvaluatorLoader                  |
| getAttribute, 44                       | getEvaluator, 145                        |
| ArcSec::AttributeValue, 45             | getPolicy, 145                           |
| ArcSec::AttributeValue                 | getRequest, 145, 146                     |
| encode, 45                             | ArcSec::FnFactory, 156                   |
| equal, 45                              | ArcSec::FnFactory                        |
| getId, 45                              | createFn, 156                            |
| getType, 45                            | ArcSec::Function, 157                    |
| ArcSec::Attrs, 47                      | ArcSec::Function                         |
| ArcSec::AuthzRequestSection, 48        | evaluate, 157                            |
| ArcSec::CombiningAlg, 61               | ArcSec::MatchFunction, 186               |
| ArcSec::CombiningAlg                   | ArcSec::MatchFunction                    |
| combine, 61                            | evaluate, 186                            |
| getalgId, 61                           | getFunctionName, 186                     |
| ArcSec::DateTimeAttribute, 122         | ArcSec::PDP, 230                         |
| ArcSec::DateTimeAttribute              | ArcSec::PeriodAttribute, 231             |
| encode, 122                            | ArcSec::PeriodAttribute                  |
| equal, 122                             | encode, 231                              |
| getId, 122                             | equal, 231                               |
| _                                      | <u>*</u>                                 |
| getType, 123                           | getId, 231                               |
| ArcSec::DenyOverridesCombiningAlg, 134 | getType, 231                             |
| ArcSec::DenyOverridesCombiningAlg      | ArcSec::PermitOverridesCombiningAlg, 233 |
| combine, 134                           | ArcSec::PermitOverridesCombiningAlg      |
| getalgId, 134                          | combine, 233                             |
| ArcSec::DurationAttribute, 136         | getalgId, 233                            |
| ArcSec::DurationAttribute              | ArcSec::Policy, 243                      |
| encode, 136                            | ArcSec::Policy                           |
| equal, 136                             | addPolicy, 244                           |
| getId, 136                             | eval, 244                                |
| getType, 136                           | getEffect, 244                           |
| ArcSec::EqualFunction, 138             | getEvalName, 244                         |
| ArcSec::EqualFunction                  | getEvalResult, 244                       |
| evaluate, 138                          | getName, 244                             |
| getFunctionName, 138                   | make_policy, 244                         |
| ArcSec::EvalResult, 139                | match, 245                               |
| ArcSec::EvaluationCtx, 140             | operator bool, 245                       |
| ArcSec::EvaluationCtx                  | Policy, 244                              |
|  |  |

| setEvalResult, 245             | Arc::Run, 258                 |
|--------------------------------|-------------------------------|
| setEvaluatorContext, 245       | AssignStdout                  |
| ArcSec::PolicyParser, 246      | Arc::Run, 259                 |
| ArcSec::PolicyParser           | AssignWorkingDirectory        |
| parsePolicy, 246               | Arc::Run, 259                 |
| ArcSec::PolicyStore, 247       | AttrConstIter                 |
| ArcSec::PolicyStore            | Arc, 22                       |
| PolicyStore, 247               | Attribute                     |
| ArcSec::Request, 250           | Arc::XMLNode, 324             |
| ArcSec::Request                | AttributeIterator             |
| addRequestItem, 251            | Arc::AttributeIterator, 41    |
| getEvalName, 251               | Attributes                    |
| getName, 251                   | Arc::Message, 199             |
| getRequestItems, 251           | Arc::SOAPMessage, 281         |
| make_request, 251              | attributes                    |
| Request, 250                   | Arc::MessageAttributes, 203   |
| setAttributeFactory, 251       | AttributesSize                |
| setRequestItems, 251           | Arc::XMLNode, 324             |
| ArcSec::RequestAttribute, 252  | AttrIter                      |
| ArcSec::RequestAttribute       | Arc, 22                       |
| duplicate, 252                 | AttrMap                       |
| RequestAttribute, 252          | Arc, 22                       |
| ArcSec::RequestItem, 253       | Auth                          |
| ArcSec::RequestItem            |                               |
| RequestItem, 253               | Arc::Message, 199             |
| •                              | AuthContext                   |
| ArcSec::RequestTuple, 254      | Arc::Message, 199             |
| ArcSec::Response, 255          | Authenticate                  |
| ArcSec::ResponseItem, 256      | Arc::SAMLToken, 266           |
| ArcSec::SecHandler, 273        | Arc::UsernameToken, 302       |
| ArcSec::Security, 274          | Arc::X509Token, 320           |
| ArcSec::Source, 282            | AutoPointer                   |
| ArcSec::Source                 | Arc::AutoPointer, 49          |
| Get, 283                       | D. d                          |
| operator bool, 283             | Backup                        |
| Source, 282, 283               | Arc::DelegationConsumer, 125  |
| ArcSec::SourceFile, 284        | BaseDN2Path                   |
| ArcSec::SourceFile             | Arc::URL, 293                 |
| SourceFile, 284                | broadcast                     |
| ArcSec::SourceURL, 285         | Arc::SimpleCondition, 278     |
| ArcSec::SourceURL              | Buffer                        |
| SourceURL, 285                 | Arc::PayloadRaw, 217          |
| ArcSec::TimeAttribute, 289     | Arc::PayloadRawInterface, 219 |
| ArcSec::TimeAttribute          | buffer_size                   |
| encode, 289                    | Arc::DataBuffer, 81           |
| equal, 289                     | BufferPos                     |
| getId, 289                     | Arc::PayloadRaw, 217          |
| getType, 289                   | Arc::PayloadRawInterface, 219 |
| Assign                         | BufferSize                    |
| Arc::InformationContainer, 164 | Arc::PayloadRaw, 217          |
| AssignCredentials              | Arc::PayloadRawInterface, 219 |
| Arc::DataPoint, 95             | BufNum                        |
| AssignStderr                   | Arc::DataPoint, 95            |
| Arc::Run, 258                  | Arc::DataPointDirect, 105     |
| AssignStdin                    | Arc::DataPointIndex, 112      |

| BufSize   | Arc::Counter, 69                          |
|---|---|
| Arc::DataPoint, 96                                | Arc::IntraProcessCounter, 172             |
| Arc::DataPointDirect, 105                         | ChangePath                                |
| Arc::DataPointIndex, 112                          | Arc::URL, 293                             |
| BUSY_ERROR  | ChangePort                                |
| Arc, 23   | Arc::URL, 294                             |
|   | ChangeProtocol                            |
| Cache   | Arc::URL, 294                             |
| Arc::DataPoint, 96                                | Check                                     |
| Arc::DataPointDirect, 106                         | Arc::DataPoint, 96                        |
| Arc::DataPointIndex, 112                          | Arc::DataPointIndex, 112                  |
| cancel  | Arc::WSAHeader, 309                       |
| Arc::Counter, 69                                  | CheckCheckSum                             |
| Arc::CounterTicket, 74                            | Arc::DataPoint, 96                        |
| Arc::IntraProcessCounter, 172                     | CheckCreated                              |
| CERT_TYPE_CA                                      | Arc::DataPoint, 96                        |
| ArcCredential, 33                                 | Arc::FileCache, 150                       |
| CERT_TYPE_EEC                                     | checks                                    |
| ArcCredential, 33                                 | Arc::DataMover, 90                        |
| CERT_TYPE_GSI_2_LIMITED_PROXY                     | CheckSize                                 |
| ArcCredential, 34                                 | Arc::DataPoint, 96                        |
| CERT_TYPE_GSI_2_PROXY                             | checksum_object                           |
| ArcCredential, 34                                 | Arc::DataBuffer, 81                       |
| CERT_TYPE_GSI_3_IMPERSONATION                     | checksum_valid                            |
| PROXY   | Arc::DataBuffer, 81                       |
| ArcCredential, 33                                 | CheckValid                                |
| CERT_TYPE_GSI_3_INDEPENDENT_PROXY                 | Arc::DataPoint, 96                        |
| ArcCredential, 34                                 | Arc::FileCache, 150                       |
| CERT_TYPE_GSI_3_LIMITED_PROXY                     | Child                                     |
| ArcCredential, 34                                 | Arc::XMLNode, 324                         |
| CERT_TYPE_GSI_3_RESTRICTED_PROXY                  | CIStringValue                             |
| ArcCredential, 34                                 | Arc::CIStringValue, 58                    |
| CERT_TYPE_RFC_ANYLANGUAGE_PROXY                   | Clean                                     |
| ArcCredential, 34                                 | Arc::FileCache, 151                       |
| CERT_TYPE_RFC_IMPERSONATION_PROXY                 | ClientSOAP                                |
| ArcCredential, 34 CERT_TYPE_RFC_INDEPENDENT_PROXY | Arc::ClientSOAP, 60                       |
| ArcCredential, 34                                 | close                                     |
| CERT_TYPE_RFC_LIMITED_PROXY                       | Arc::Database, 79 Arc::MySQLDatabase, 214 |
| ArcCredential, 34                                 | CloseStderr                               |
| CERT_TYPE_RFC_RESTRICTED_PROXY                    | Arc::Run, 259                             |
| ArcCredential, 34                                 | CloseStdin                                |
| certType  | Arc::Run, 259                             |
| ArcCredential, 33                                 | CloseStdout                               |
| changeExcess                                      | Arc::Run, 259                             |
| Arc::Counter, 69                                  | combine                                   |
| Arc::IntraProcessCounter, 172                     | ArcSec::CombiningAlg, 61                  |
| ChangeHost  | ArcSec::DenyOverridesCombiningAlg, 134    |
| Arc::URL, 293                                     | ArcSec::PermitOverridesCombiningAlg, 233  |
| ChangeLDAPFilter                                  | CommonLocOption                           |
| Arc::URL, 293                                     | Arc::URL, 294                             |
| ChangeLDAPScope                                   | CommonLocOptions                          |
| Arc::URL, 293                                     | Arc::URL, 294                             |
| changeLimit                                       | commonlocoptions                          |
| <u>~</u>  | ±   |

| 4 JUDY 205                                       |                                   |
|--|-----------------------------------|
| Arc::URL, 297                                    | Arc::Database, 78                 |
| CompareMeta                                      | DataBuffer                        |
| Arc::DataPoint, 96                               | Arc::DataBuffer, 81               |
| Config   | DataMover                         |
| Arc::Config, 63, 64                              | Arc::DataMover, 89                |
| connect  | DataPoint                         |
| Arc::Database, 79                                | Arc::DataPoint, 95                |
| Arc::MySQLDatabase, 214                          | DataSpeed                         |
| ConnectionURL                                    | Arc::DataSpeed, 118               |
| Arc::URL, 294                                    | DecryptNode                       |
| Content  | Arc::XMLSecNode, 334              |
| Arc::PayloadRaw, 217                             | Delegate                          |
| Arc::PayloadRawInterface, 220                    | Arc::DelegationProvider, 130      |
| ContentFromPayload                               | DelegateCredentialsInit           |
| Arc, 27  | Arc::DelegationConsumerSOAP, 126  |
| Context  | Arc::DelegationContainerSOAP, 128 |
| Arc::Message, 199                                | Arc::DelegationProviderSOAP, 133  |
| context_lock_                                    | DelegatedToken                    |
| Arc::DelegationContainerSOAP, 129                | Arc::DelegationConsumerSOAP, 126  |
| Copy   | Arc::DelegationContainerSOAP, 128 |
| Arc::FileCache, 151                              | Arc::DelegationProviderSOAP, 133  |
| count  | DelegationConsumer                |
| Arc::MessageAttributes, 202                      | Arc::DelegationConsumer, 124      |
| Counter  | DelegationConsumerSOAP            |
| Arc::Counter, 69                                 | Arc::DelegationConsumerSOAP, 126  |
| Arc::CounterTicket, 75                           | DelegationProvider                |
| Arc::ExpirationReminder, 148                     | Arc::DelegationProvider, 130      |
| CounterTicket                                    | DelegationProviderSOAP            |
| Arc::Counter, 73                                 | Arc::DelegationProviderSOAP, 132  |
| Arc::CounterTicket, 74                           | Destroy                           |
| createAlg  | Arc::XMLNode, 324                 |
| ArcSec::AlgFactory, 36                           | doc_                              |
| createFn   | Arc::InformationContainer, 165    |
| ArcSec::FnFactory, 156                           | duplicate                         |
| CreateThreadFunction                             | ArcSec::RequestAttribute, 252     |
| Arc, 25  | 1                                 |
| createVOMSAC                                     | enable_ssl                        |
| Arc, 26  | Arc::Database, 79                 |
| CredentialError                                  | Arc::MySQLDatabase, 215           |
| Arc::CredentialError, 77                         | encode                            |
| CredentialLogger                                 | ArcSec::AttributeValue, 45        |
| Arc, 29  | ArcSec::DateTimeAttribute, 122    |
| current  | ArcSec::DurationAttribute, 136    |
| Arc::AttributeIterator, 43                       | ArcSec::PeriodAttribute, 231      |
| CurrentLocation                                  | ArcSec::TimeAttribute, 289        |
| Arc::DataPoint, 96                               | EncryptNode                       |
| Arc::DataPointDirect, 106                        | Arc::XMLSecNode, 334              |
|  | end                               |
| Arc::DataPointIndex, 113 CurrentLocationMetadata | Arc::AttributeIterator, 43        |
|  | eof_position                      |
| Arc::DataPoint, 97                               | Arc::DataBuffer, 81               |
| Arc::DataPointDirect, 106                        | eof read                          |
| Arc::DataPointIndex, 113                         | <del>-</del>                      |
| Databasa   | Arc::DataBuffer, 82               |
| Database   | eof_write                         |

| Arc::DataBuffer, 82                     | Arc, 27                               |
|---|---------------------------------------|
| equal                                   | findLocation                          |
| Arc::CIStringValue, 59                  | Arc::ModuleManager, 210               |
| ArcSec::AttributeValue, 45              | for_read                              |
| ArcSec::DateTimeAttribute, 122          | Arc::DataBuffer, 83                   |
| ArcSec::DurationAttribute, 136          | for_write                             |
| ArcSec::PeriodAttribute, 231            | Arc::DataBuffer, 83                   |
| ArcSec::TimeAttribute, 289              | force_to_meta                         |
| error                                   | Arc::DataMover, 90                    |
| Arc::DataBuffer, 82                     | From                                  |
| error_read                              | Arc::WSAHeader, 309                   |
| Arc::DataBuffer, 82                     | FullName                              |
| error_transfer                          | Arc::XMLNode, 324                     |
| Arc::DataBuffer, 82                     | FullPath                              |
| error_write                             | Arc::URL, 294                         |
| Arc::DataBuffer, 82                     | fullstr                               |
| ETERNAL                                 | Arc::URL, 294                         |
| Arc, 29                                 | Arc::URLLocation, 300                 |
| eval                                    |                                       |
| ArcSec::Policy, 244                     | GACL                                  |
| evaluate                                | Arc::SecAttr, 269                     |
| ArcSec::EqualFunction, 138              | Generate                              |
| ArcSec::Evaluator, 142                  | Arc::DelegationConsumer, 125          |
| ArcSec::Function, 157                   | GENERIC_ERROR                         |
| ArcSec::MatchFunction, 186              | Arc, 23                               |
| EvaluationCtx                           | Get                                   |
| ArcSec::EvaluationCtx, 140              | Arc::ArcLocation, 38                  |
| ExpirationReminder                      | Arc::InformationContainer, 165        |
| Arc::Counter, 73                        | Arc::InformationInterface, 167        |
| Export                                  | Arc::PayloadStream, 223               |
| Arc::MessageAuth, 204                   | Arc::PayloadStreamInterface, 225      |
| Arc::MultiSecAttr, 212                  | Arc::XMLNode, 324                     |
| Arc::SecAttr, 268                       | ArcSec::Source, 283                   |
| extend                                  | get                                   |
|   | Arc::MessageAttributes, 202           |
| Arc::Counter, 70 Arc::CounterTicket, 75 | Arc::MessageAuth, 204                 |
| ,                                       | get_cert_str                          |
| Arc::IntraProcessCounter, 172           | Arc, 28                               |
| factory_                                |                                       |
| Arc::Loader, 175                        | get_instance Arc::PluginsFactory, 242 |
| *                                       | •                                     |
| FaultTo                                 | get_key_from_certfile                 |
| Arc::WSAHeader, 309                     | Arc, 28                               |
| File                                    | get_key_from_certstr                  |
| Arc::FileCache, 151                     | Arc, 28                               |
| FileCache                               | get_key_from_keyfile                  |
| Arc::FileCache, 150                     | Arc, 28                               |
| FileCacheHash, 154                      | get_key_from_keystr                   |
| FileCacheHash                           | Arc, 28                               |
| getHash, 154                            | get_node                              |
| maxLength, 154                          | Arc, 29                               |
| Filter                                  | get_plugin_instance                   |
| Arc::InfoFilter, 159                    | Arc, 22                               |
| Arc::MessageAuth, 204                   | GetAdditionalChecks                   |
| final_xmlsec                            | Arc::DataPoint, 97                    |
|   |                                       |

| Arc::DataPointDirect, 106                | ArcSec::MatchFunction, 186        |
|--|-----------------------------------|
| Arc::DataPointIndex, 113                 | GetHandle                         |
| getAlgFactory                            | Arc::PayloadStream, 223           |
| ArcSec::Evaluator, 143                   | getHash                           |
| getalgId                                 | FileCacheHash, 154                |
| ArcSec::CombiningAlg, 61                 | getID                             |
| ArcSec::DenyOverridesCombiningAlg, 134   | Arc::Service, 276                 |
| ArcSec::PermitOverridesCombiningAlg, 233 | getId                             |
| getAll                                   | ArcSec::AttributeValue, 45        |
| Arc::MessageAttributes, 202              | ArcSec::DateTimeAttribute, 122    |
| getAttrFactory                           | ArcSec::DurationAttribute, 136    |
| ArcSec::Evaluator, 143                   | ArcSec::PeriodAttribute, 231      |
| getAttribute                             | ArcSec::TimeAttribute, 289        |
| ArcSec::AttributeProxy, 44               | getKind                           |
| GetCheckSum                              | Arc::MCC_Status, 190              |
| Arc::DataPoint, 97                       | getLevel                          |
| getCounterTicket                         | Arc::LogMessage, 183              |
| Arc::Counter, 70                         | getLimit                          |
| GetCreated                               | Arc::Counter, 71                  |
| Arc::DataPoint, 97                       | Arc::IntraProcessCounter, 173     |
| Arc::FileCache, 151                      | getName                           |
| getCurrentTime                           | ArcSec::Evaluator, 143            |
| Arc::Counter, 70                         | ArcSec::Policy, 244               |
| GetDoc                                   | ArcSec::Request, 251              |
| Arc::XMLNode, 324                        | getOrigin                         |
| getEffect                                | Arc::MCC_Status, 191              |
| ArcSec::Policy, 244                      | GetOverlay                        |
| GetEnv                                   | Arc::BaseConfig, 52               |
| Arc, 25                                  | getPattern                        |
| getEvalName                              | Arc::RegularExpression, 248       |
| ArcSec::Policy, 244                      | GetPlugins                        |
| ArcSec::Request, 251                     | Arc::ArcLocation, 38              |
| getEvalResult                            | getPolicy                         |
| ArcSec::Policy, 244                      | ArcSec::EvaluatorLoader, 145      |
| getEvaluator                             | getRequest                        |
| ArcSec::EvaluatorLoader, 145             | ArcSec::EvaluatorLoader, 145, 146 |
| getExcess                                | getRequestItems                   |
| Arc::Counter, 71                         | ArcSec::Request, 251              |
| Arc::IntraProcessCounter, 173            | getReservationID                  |
| getExpirationReminder                    | Arc::ExpirationReminder, 147      |
| Arc::Counter, 71                         | GetRoot                           |
| getExpiryTime                            | Arc::XMLNode, 324                 |
| Arc::Counter, 71                         | getRootLogger                     |
| Arc::ExpirationReminder, 147             | Arc::Logger, 180                  |
| getExplanation                           | GetSecure                         |
| Arc::MCC_Status, 190                     | Arc::DataPoint, 97                |
| getFileName                              | Arc::DataPointDirect, 106         |
| Arc::Config, 64                          | Arc::DataPointIndex, 113          |
| getFnFactory                             | GetSize                           |
| ArcSec::Evaluator, 143                   | Arc::DataPoint, 97                |
| GetFormat                                | getThreshold                      |
| Arc::Time, 287                           | Arc::Logger, 180                  |
| getFunctionName                          | GetTime                           |
| ArcSec::EqualFunction, 138               | Arc::Time, 287                    |
|  |                                   |

| GetTries                         | Arc::SecAttr, 268              |
|----------------------------------|--------------------------------|
| Arc::DataPoint, 97               | InfoCache                      |
| getType                          | Arc::InfoCache, 158            |
| ArcSec::AttributeValue, 45       | InfoFilter                     |
| ArcSec::DateTimeAttribute, 123   | Arc::InfoFilter, 159           |
| ArcSec::DurationAttribute, 136   | InfoRegisters                  |
| ArcSec::PeriodAttribute, 231     | Arc::InfoRegisters, 162        |
| ArcSec::TimeAttribute, 289       | InformationContainer           |
| GetURL                           | Arc::InformationContainer, 164 |
| Arc::DataPoint, 97               | InformationInterface           |
| GetValid                         | Arc::InformationInterface, 166 |
| Arc::DataPoint, 97               | InformationRequest             |
| Arc::FileCache, 151              | Arc::InformationRequest, 168   |
| getValue                         | InformationResponse            |
| Arc::Counter, 72                 | Arc::InformationResponse, 170  |
| Arc::IntraProcessCounter, 173    | Init                           |
| GetXML                           | Arc::ArcLocation, 38           |
| Arc::XMLNode, 324, 325           | init_xmlsec                    |
| GUID                             | Arc, 27                        |
| Arc, 24                          | Insert                         |
| 1110, 21                         | Arc::PayloadRaw, 217           |
| handle_                          | Arc::PayloadRawInterface, 220  |
| Arc::PayloadStream, 224          | IntraProcessCounter            |
| hasMore                          | Arc::IntraProcessCounter, 171  |
| Arc::AttributeIterator, 42       | is_notwritten                  |
| hasPattern                       | Arc::DataBuffer, 83            |
| Arc::RegularExpression, 248      | is_owner_                      |
| HaveLocations                    |                                |
| Arc::DataPoint, 97               | Arc::XMLNode, 330              |
| Arc::DataPointDirect, 106        | is_read                        |
| Arc::DataPointIndex, 113         | Arc::DataBuffer, 84            |
|                                  | is_temporary_                  |
| header_allocated_                | Arc::XMLNode, 330              |
| Arc::WSAHeader, 310              | is_written                     |
| HISTORIC                         | Arc::DataBuffer, 84            |
| Arc, 29                          | isconnected                    |
| hold                             | Arc::Database, 79              |
| Arc::DataSpeed, 119              | Arc::MySQLDatabase, 215        |
| Host                             | IsIndex                        |
| Arc::URL, 294                    | Arc::DataPoint, 98             |
| host                             | Arc::DataPointDirect, 106      |
| Arc::URL, 297                    | Arc::DataPointIndex, 113       |
| HTTPOption                       | isOk                           |
| Arc::URL, 294                    | Arc::MCC_Status, 191           |
| HTTPOptions                      | Arc::RegularExpression, 249    |
| Arc::URL, 295                    | isValid                        |
| httpoptions                      | Arc::CounterTicket, 75         |
| Arc::URL, 297                    |                                |
|                                  | KeepStderr                     |
| ID                               | Arc::Run, 259                  |
| Arc::DelegationConsumer, 125     | KeepStdin                      |
| Arc::DelegationProviderSOAP, 133 | Arc::Run, 259                  |
| IDType                           | KeepStdout                     |
| Arc::Counter, 69                 | Arc::Run, 259                  |
| Import                           | key                            |
| <del>-</del>                     | -                              |

| Arc::AttributeIterator, 42     | log                               |
|--------------------------------|-----------------------------------|
| Kill                           | Arc::LogDestination, 178          |
| Arc::Run, 259                  | Arc::LogStream, 185               |
|                                | LogDestination                    |
| LDAPAttributes                 | Arc::LogDestination, 177          |
| Arc::URL, 295                  | LogError                          |
| Idapattributes                 | Arc::DelegationConsumer, 125      |
| Arc::URL, 297                  | Logger                            |
| LDAPFilter                     | Arc::Logger, 180                  |
| Arc::URL, 295                  | Arc::LogMessage, 183              |
| ldapfilter                     | logger                            |
| Arc::URL, 297                  | Arc::MCC, 188                     |
| LDAPScope                      | Arc::Plexer, 236                  |
| Arc::URL, 295                  | Arc::Service, 276                 |
| ldapscope                      | LogLevel                          |
| Arc::URL, 297                  | Arc, 23                           |
| Link                           | LogMessage                        |
| Arc::FileCache, 151            | Arc::LogMessage, 182              |
| ListFiles                      | LogStream                         |
| Arc::DataPoint, 98             | Arc::LogStream, 184               |
| load                           |                                   |
| Arc::ModuleManager, 210        | make_policy                       |
| Arc::PluginsFactory, 242       | ArcSec::Policy, 244               |
| load_key_from_certfile         | make_request                      |
| Arc, 28                        | ArcSec::Request, 251              |
| load_key_from_certstr          | MakeConfig                        |
| Arc, 28                        | Arc::BaseConfig, 52               |
| load_key_from_keyfile          | match                             |
| Arc, 28                        | Arc::RegularExpression, 249       |
| load_trusted_cert_file         | ArcSec::Policy, 245               |
| Arc, 28                        | MatchXMLName                      |
| load_trusted_cert_str          | Arc, 25                           |
| Arc, 28                        | Arc::XMLNode, 329                 |
| load_trusted_certs             | MatchXMLNamespace                 |
| Arc, 29                        | Arc, 25, 26                       |
| Loader                         | Arc::XMLNode, 329, 330            |
| Arc::Loader, 175               | max_duration_                     |
| Local                          | Arc::DelegationContainerSOAP, 129 |
| Arc::DataPoint, 98             | max_inactivity_time_failure       |
| Arc::DataPointDirect, 106      | Arc::DataSpeed, 119               |
| Arc::DataPointIndex, 113       | max_size_                         |
| Locations                      | Arc::DelegationContainerSOAP, 129 |
| Arc::URL, 295                  | max_usage_                        |
| locations                      | Arc::DelegationContainerSOAP, 129 |
| Arc::DataPointIndex, 117       | maxLength                         |
| Arc::URL, 297                  | FileCacheHash, 154                |
| LocationValid                  | MCC                               |
| Arc::DataPoint, 98             | Arc::MCC, 188                     |
| Arc::DataPointDirect, 107      | MCC_Status                        |
| Arc::DataPointIndex, 113       | Arc::MCC_Status, 190              |
| lock                           | MCCLoader                         |
| Arc::SimpleCondition, 278      | Arc::MCCLoader, 196               |
| lock_                          | Message                           |
| Arc::InformationInterface, 167 | Arc::Message, 199                 |
|                                |                                   |

| MessageAttributes              | operator AttributeFactory *      |
|--------------------------------|----------------------------------|
| Arc::AttributeIterator, 43     | ArcSec::EvaluatorContext, 144    |
| Arc::MessageAttributes, 201    | operator bool                    |
| MessageID                      | Arc::AutoPointer, 49             |
| Arc::WSAHeader, 309            | Arc::CIStringValue, 59           |
| MetaData                       | Arc::CountedPointer, 65          |
| Arc::WSAEndpointReference, 307 | Arc::DataBuffer, 84              |
| min_average_speed_failure      | Arc::DataPoint, 98               |
| Arc::DataSpeed, 119            | Arc::FileCache, 151              |
| min_speed_failure              | Arc::MCC_Status, 191             |
| Arc::DataSpeed, 119            | Arc::MultiSecAttr, 212           |
| ModuleManager                  | Arc::PayloadStream, 223          |
| Arc::ModuleManager, 210        | Arc::PayloadStreamInterface, 226 |
| msg                            | Arc::Run, 259                    |
| Arc::Logger, 180, 181          | Arc::SAMLToken, 266              |
|                                | Arc::SecAttr, 268                |
| Name                           | Arc::SecAttrValue, 271           |
| Arc::URLLocation, 300          | Arc::URL, 295                    |
| Arc::XMLNode, 325              | Arc::UsernameToken, 302          |
| RuntimeEnvironment, 261        | Arc::WSRF, 312                   |
| name                           | Arc::X509Token, 320              |
| Arc::URLLocation, 300          | Arc::XMLNode, 326                |
| Namespace                      | ArcSec::Policy, 245              |
| Arc::XMLNode, 325              | ArcSec::Source, 283              |
| NamespacePrefix                | operator FnFactory *             |
| Arc::XMLNode, 325              | ArcSec::EvaluatorContext, 144    |
| Namespaces                     | operator PluginsFactory *        |
| Arc::XMLNode, 325              | Arc::ChainContext, 54            |
| New                            | operator std::string             |
| Arc::XMLNode, 325              | Arc::MCC_Status, 191             |
| NewAttribute                   | Arc::Time, 287                   |
| Arc::XMLNode, 325, 326         | Arc::XMLNode, 326                |
| NewChild                       | operator T *                     |
| Arc::XMLNode, 326              | Arc::AutoPointer, 50             |
| NewReferenceParameter          | Arc::CountedPointer, 65          |
| Arc::WSAHeader, 309            | operator XMLNode                 |
| Next                           | Arc::WSAEndpointReference, 307   |
| Arc::MCC, 188                  | Arc::WSAHeader, 309              |
| Arc::Plexer, 236               | operator!                        |
| next                           | Arc::AutoPointer, 50             |
| Arc::MCC, 189                  | Arc::CountedPointer, 65          |
| NextLocation                   | Arc::DataPoint, 98               |
| Arc::DataPoint, 98             | Arc::MCC_Status, 191             |
| Arc::DataPointDirect, 107      | Arc::PayloadStream, 223          |
|                                | Arc::PayloadStreamInterface, 226 |
| Arc::DataPointIndex, 114       | Arc::Run, 259                    |
| Nodes                          |                                  |
| Arc::XMLNodeContainer, 332     | Arc::XMLNode, 326                |
| omenator :                     | operator!=                       |
| operator *                     | Arc::SecAttr, 268                |
| Arc::AttributeIterator, 42     | Arc::SecAttrValue, 271           |
| Arc::AutoPointer, 49           | Arc::Time, 287                   |
| Arc::CountedPointer, 65        | Arc::XMLNode, 326, 327           |
| operator AlgFactory *          | RuntimeEnvironment, 261          |
| ArcSec::EvaluatorContext, 144  | operator+                        |
|                                |                                  |

| Arc::Time, 287                 | Arc::URL, 295             |
|--------------------------------|---------------------------|
| operator++                     | Options Options           |
| Arc::AttributeIterator, 42     | Arc::URL, 296             |
| Arc::XMLNode, 327              | OptionString              |
| operator-                      | Arc::URL, 296             |
| Arc::Time, 287                 | AIC OKL, 270              |
| operator—                      | Parent                    |
| =                              | Arc::XMLNode, 328         |
| Arc::XMLNode, 327              | parse                     |
| operator->                     | Arc::Config, 64           |
| Arc::AttributeIterator, 43     | parsePolicy               |
| Arc::AutoPointer, 50           | ArcSec::PolicyParser, 246 |
| Arc::CountedPointer, 66        | •                         |
| operator<                      | parseVOMSAC               |
| Arc::ExpirationReminder, 147   | Arc, 26, 27               |
| Arc::Time, 287                 | PARSING_ERROR             |
| Arc::URL, 295                  | Arc, 23                   |
| RuntimeEnvironment, 261        | Passive                   |
| operator<<                     | Arc::DataPoint, 98        |
| Arc, 23, 24                    | Arc::DataPointDirect, 107 |
| Arc::LogMessage, 183           | Arc::DataPointIndex, 114  |
| Arc::URL, 297                  | passive                   |
| operator<=                     | Arc::DataMover, 90        |
| Arc::Time, 287                 | passphrase_callback       |
| RuntimeEnvironment, 261        | Arc, 27                   |
| operator=                      | Passwd                    |
| Arc::Message, 199              | Arc::URL, 296             |
| Arc::RegularExpression, 249    | passwd                    |
| Arc::Time, 287                 | Arc::URL, 297             |
| Arc::WSAEndpointReference, 307 | PasswordType              |
| Arc::XMLNode, 327              | Arc::UsernameToken, 301   |
| Arc::XMLNodeContainer, 332     | Path                      |
| operator==                     | Arc::URL, 296             |
| Arc::FileCache, 152            | Arc::XMLNode, 328         |
| Arc::SecAttr, 268              | path                      |
| Arc::SecAttrValue, 271         | Arc::URL, 297             |
| Arc::Time, 287                 | Path2BaseDN               |
| Arc::URL, 295                  | Arc::URL, 296             |
| Arc::XMLNode, 327              | Payload                   |
|                                | Arc::Message, 200         |
| RuntimeEnvironment, 262        | Arc::SOAPMessage, 281     |
| operator>                      |                           |
| Arc::Time, 288                 | PayloadRaw                |
| RuntimeEnvironment, 262        | Arc::PayloadRaw, 216      |
| operator>=                     | PayloadSOAP               |
| Arc::Time, 288                 | Arc::PayloadSOAP, 221     |
| RuntimeEnvironment, 262        | PayloadStream             |
| operator[]                     | Arc::PayloadStream, 222   |
| Arc::DataBuffer, 84            | PayloadWSRF               |
| Arc::MCCLoader, 196            | Arc::PayloadWSRF, 228     |
| Arc::MessageAuth, 204          | Plexer                    |
| Arc::PayloadRaw, 217           | Arc::Plexer, 235          |
| Arc::PayloadRawInterface, 220  | plugins_table_name        |
| Arc::XMLNode, 327, 328         | Arc, 29                   |
| Arc::XMLNodeContainer, 332     | PluginsFactory            |
| Option                         | Arc::PluginsFactory, 241  |

| D. I.                                 | P. 10 .070 1                    |
|---------------------------------------|---------------------------------|
| Policy                                | ReadOutOfOrder                  |
| ArcSec::Policy, 244                   | Arc::DataPoint, 100             |
| PolicyStore                           | Arc::DataPointDirect, 108       |
| ArcSec::PolicyStore, 247              | Arc::DataPointIndex, 114        |
| Port                                  | ReadStderr                      |
| Arc::URL, 296                         | Arc::Run, 260                   |
| port                                  | ReadStdout                      |
| Arc::URL, 297                         | Arc::Run, 260                   |
| Pos                                   | ReadURLList                     |
| Arc::PayloadStream, 223               | Arc, 25                         |
| Arc::PayloadStreamInterface, 226      | ReferenceParameter              |
| PostRegister                          | Arc::WSAHeader, 309             |
| Arc::DataPoint, 99                    | ReferenceParameters             |
| Arc::DataPointDirect, 107             | Arc::WSAEndpointReference, 307  |
| Prefix                                | Registered                      |
| Arc::XMLNode, 328                     | Arc::DataPoint, 100             |
| PreRegister                           | Arc::DataPointDirect, 108       |
| Arc::DataPoint, 99                    | Arc::DataPointIndex, 114        |
| Arc::DataPointDirect, 107             | registration                    |
| PreUnregister                         | Arc::InfoRegistrar, 163         |
| Arc::DataPoint, 99                    | RegistrationCollector           |
| Arc::DataPointDirect, 108             | Arc::Service, 276               |
| print                                 | RegularExpression               |
| Arc::Config, 64                       | Arc::RegularExpression, 248     |
| process                               | RelatesTo                       |
| Arc::ClientSOAP, 60                   | Arc::WSAHeader, 310             |
| Arc::MCC, 188                         | RelationshipType                |
| Arc::MCCInterface, 193                | Arc::WSAHeader, 310             |
| Arc::Plexer, 236                      | Release                         |
|                                       | Arc::FileCache, 152             |
| ProcessSecHandlers                    | reload                          |
| Arc::MCC, 188                         |                                 |
| Arc::Service, 276                     | Arc::ModuleManager, 210         |
| Protocol                              | Remove                          |
| Arc::URL, 296                         | Arc::DataPoint, 100             |
| protocol                              | Arc::DataPointIndex, 114        |
| Arc::URL, 297                         | remove                          |
| PROTOCOL_RECOGNIZED_ERROR             | Arc::MessageAttributes, 203     |
| Arc, 23                               | Arc::MessageAuth, 205           |
| ProvidesMeta                          | removeAll                       |
| Arc::DataPoint, 99                    | Arc::MessageAttributes, 203     |
| Arc::DataPointDirect, 108             | removeDestinations              |
| Arc::DataPointIndex, 114              | Arc::Logger, 181                |
| Put                                   | RemoveLocation                  |
| Arc::PayloadStream, 223, 224          | Arc::DataPoint, 100             |
| Arc::PayloadStreamInterface, 226      | Arc::DataPointDirect, 108       |
|                                       | Arc::DataPointIndex, 115        |
| Range                                 | RemoveLocations                 |
| Arc::DataPoint, 100                   | Arc::DataPoint, 100             |
| Arc::DataPointDirect, 108             | Arc::DataPointDirect, 108       |
| Arc::DataPointIndex, 114              | Arc::DataPointIndex, 115        |
| ReadFromFile                          | removeService                   |
| Arc::XMLNode, 328                     | Arc::InfoRegisterContainer, 161 |
| ReadFromStream                        | Arc::InfoRegistrar, 163         |
| Arc::XMLNode, 328                     | Replace                         |
| ··· · · · · · · · · · · · · · · · · · | 1                               |

| Arc::XMLNode, 328                 | Arc::SecAttr, 269               |
|-----------------------------------|---------------------------------|
| ReplyTo                           | SAMLToken                       |
| Arc::WSAHeader, 310               | Arc::SAMLToken, 265             |
| Request                           | SAMLVersion                     |
| Arc::DelegationConsumer, 125      | Arc::SAMLToken, 265             |
| ArcSec::Request, 250              | save                            |
| RequestAttribute                  | Arc::Config, 64                 |
| ArcSec::RequestAttribute, 252     | SaveToFile                      |
| RequestItem                       | Arc::XMLNode, 329               |
| ArcSec::RequestItem, 253          | SaveToStream                    |
| reserve                           | Arc::XMLNode, 329               |
| Arc::Counter, 72                  | Scope                           |
| Arc::IntraProcessCounter, 173     | Arc::URL, 293                   |
| reset                             | SecAttr                         |
| Arc::DataSpeed, 119               | Arc::SecAttr, 268               |
| Arc::SimpleCondition, 278         | sechandlers_                    |
| Resolve                           | Arc::MCC, 189                   |
| Arc::DataPoint, 100               | Arc::Service, 276               |
| Arc::DataPointDirect, 109         | secure                          |
| Restore                           | Arc::DataMover, 90              |
| Arc::DelegationConsumer, 125      | seekable                        |
| restricted                        | Arc::PayloadStream, 224         |
| Arc::DelegationContainerSOAP, 129 | Service Service                 |
| Result                            | Arc::Service, 276               |
| Arc::InformationResponse, 170     | SESSION_CLOSE                   |
| Arc::Run, 260                     | Arc, 23                         |
|                                   | Set                             |
| Arc::DataMover, 90                | Arc::XMLNode, 329               |
| Run                               | set                             |
|                                   | Arc::DataBuffer, 85             |
| Arc::Run, 258                     | Arc::MessageAttributes, 203     |
| Running Arc::Run, 260             | Arc::MessageAuthoutes, 205      |
|                                   | set base                        |
| RuntimeEnvironment, 261           | Arc::DataSpeed, 119             |
| RuntimeEnvironment, 261           | set_default_max_inactivity_time |
| RuntimeEnvironment                | Arc::DataMover, 90              |
| ~RuntimeEnvironment, 261          | •                               |
| Name, 261                         | set_default_min_average_speed   |
| operator!=, 261                   | Arc::DataMover, 90              |
| operator<, 261                    | set_default_min_speed           |
| operator<=, 261                   | Arc::DataMover, 91              |
| operator==, 262                   | set_max_data                    |
| operator>, 262                    | Arc::DataSpeed, 120             |
| operator>=, 262                   | set_max_inactivity_time         |
| RuntimeEnvironment, 261           | Arc::DataSpeed, 120             |
| str, 262                          | set_min_average_speed           |
| Version, 262                      | Arc::DataSpeed, 120             |
| RuntimeEnvironmentError, 263      | set_min_speed                   |
| RuntimeEnvironmentError, 263      | Arc::DataSpeed, 120             |
| RuntimeEnvironmentError           | set_namespaces                  |
| RuntimeEnvironmentError, 263      | Arc::WSRF, 312                  |
|                                   |                                 |
| United at                         | Arc::WSRFBaseFault, 314         |
| Same                              | Arc::WSRP, 315                  |
| Arc::XMLNode, 328 SAML            |                                 |

| 9                             | 1 N GOV D 1 1 015             |
|-------------------------------|-------------------------------|
| SetAdditionalChecks           | Arc::MySQLDatabase, 215       |
| Arc::DataPoint, 101           | signal                        |
| Arc::DataPointDirect, 109     | Arc::SimpleCondition, 278     |
| Arc::DataPointIndex, 115      | signal_nonblock               |
| setAttributeFactory           | Arc::SimpleCondition, 278     |
| ArcSec::Request, 251          | SignNode                      |
| setCfg                        | Arc::XMLSecNode, 334          |
| Arc::ModuleManager, 211       | Size                          |
| SetCheckSum                   | Arc::PayloadRaw, 217          |
| Arc::DataPoint, 101           | Arc::PayloadRawInterface, 220 |
| setCombiningAlg               | Arc::XMLNode, 329             |
| ArcSec::Evaluator, 143        | Arc::XMLNodeContainer, 332    |
| SetCreated                    | SOAP                          |
|                               |                               |
| Arc::DataPoint, 101           | Arc::InformationRequest, 168  |
| SetEnv                        | Arc::WSRF, 312                |
| Arc, 25                       | SOAPMessage                   |
| setEvalResult                 | Arc::SOAPMessage, 280         |
| ArcSec::Policy, 245           | Source                        |
| setEvaluatorContext           | ArcSec::Source, 282, 283      |
| ArcSec::Policy, 245           | SourceFile                    |
| setExcess                     | ArcSec::SourceFile, 284       |
| Arc::Counter, 72              | SourceURL                     |
| Arc::IntraProcessCounter, 174 | ArcSec::SourceURL, 285        |
| setFileName                   | speed                         |
| Arc::Config, 64               | Arc::DataBuffer, 86           |
| SetFormat                     | split                         |
| Arc::Time, 288                | ArcSec::EvaluationCtx, 140    |
|                               |                               |
| setIdentifier                 | Start                         |
| Arc::LogMessage, 183          | Arc::FileCache, 152           |
| setLimit                      | Arc::Run, 260                 |
| Arc::Counter, 73              | StartReading                  |
| Arc::IntraProcessCounter, 174 | Arc::DataPoint, 102           |
| SetMeta                       | Arc::DataPointIndex, 115      |
| Arc::DataPoint, 101           | StartWriting                  |
| setRequestItems               | Arc::DataPoint, 102           |
| ArcSec::Request, 251          | Arc::DataPointIndex, 116      |
| SetSecure                     | STATUS_OK                     |
| Arc::DataPoint, 101           | Arc, 23                       |
| Arc::DataPointDirect, 109     | StatusKind                    |
| Arc::DataPointIndex, 115      | Arc, 23                       |
| SetSize                       | Stop                          |
| Arc::DataPoint, 101           | Arc::FileCache, 152           |
| setThreshold                  | StopAndDelete                 |
|                               | Arc::FileCache, 152           |
| Arc::Logger, 181              | •                             |
| SetTime                       | StopReading                   |
| Arc::Time, 288                | Arc::DataPoint, 102           |
| SetTries                      | Arc::DataPointIndex, 116      |
| Arc::DataPoint, 101           | StopWriting                   |
| Arc::DataPointIndex, 115      | Arc::DataPoint, 102           |
| SetValid                      | Arc::DataPointIndex, 116      |
| Arc::DataPoint, 102           | str                           |
| Arc::FileCache, 152           | Arc::DataPoint, 103           |
| shutdown                      | Arc::Time, 288                |
| Arc::Database, 79             | Arc::URL, 296                 |
| ,                             | ,                             |

| AmouLIDLI continu 200             | Ama 24                       |
|-----------------------------------|------------------------------|
| Arc::URLLocation, 300             | Arc, 24                      |
| RuntimeEnvironment, 262           | URL                          |
| StrError                          | Arc::URL, 293                |
| Arc, 25                           | URLLocation                  |
| string                            | Arc::URLLocation, 299, 300   |
| Arc, 27                           | urloptions                   |
| stringto                          | Arc::URL, 298                |
| Arc, 24                           | Username                     |
|                                   | Arc::URL, 296                |
| Time                              | Arc::UsernameToken, 302      |
| Arc::Time, 286                    | username                     |
| TimeFormat                        | Arc::URL, 298                |
| Arc, 22                           | UsernameToken                |
| Timeout                           | Arc::UsernameToken, 301, 302 |
| Arc::PayloadStream, 224           | UUID                         |
| Arc::PayloadStreamInterface, 226  | Arc, 24                      |
| TimeStamp                         | 7110, 21                     |
| Arc, 23, 24                       | valid                        |
| To To                             | Arc::WSRF, 312               |
| Arc::WSAHeader, 310               | verbose                      |
| tokenize                          | Arc::DataMover, 91, 92       |
|                                   |                              |
| Arc, 24                           | Arc::DataSpeed, 121          |
| tostring                          | VerifyNode                   |
| Arc, 24                           | Arc::XMLSecNode, 334         |
| Transfer                          | Version                      |
| Arc::DataMover, 91                | RuntimeEnvironment, 262      |
| transfer                          | VOMSTrustList                |
| Arc::DataSpeed, 120               | Arc::VOMSTrustList, 304      |
| transfered_size                   |                              |
| Arc::DataSpeed, 121               | Wait                         |
| trim                              | Arc::Run, 260                |
| Arc, 24                           | wait                         |
| Truncate                          | Arc::SimpleCondition, 279    |
| Arc::PayloadRaw, 218              | wait_any                     |
| Arc::PayloadRawInterface, 220     | Arc::DataBuffer, 85          |
| ,                                 | wait_eof                     |
| UNKNOWN_SERVICE_ERROR             | Arc::DataBuffer, 85          |
| Arc, 23                           | wait_eof_read                |
| Unlink                            | Arc::DataBuffer, 85          |
| Arc::MCC, 188                     | wait_eof_write               |
| unlock                            | Arc::DataBuffer, 85          |
| Arc::SimpleCondition, 278         | wait_nonblock                |
| Unregister Unregister             | Arc::SimpleCondition, 279    |
| Arc::DataPoint, 103               | wait read                    |
|                                   | <del>-</del>                 |
| Arc::DataPointDirect, 109         | Arc::DataBuffer, 85          |
| UnsetEnv                          | wait_used                    |
| Arc, 25                           | Arc::DataBuffer, 85          |
| UpdateCredentials                 | wait_write                   |
| Arc::DelegationConsumerSOAP, 127  | Arc::DataBuffer, 85          |
| Arc::DelegationContainerSOAP, 128 | what                         |
| Arc::DelegationProviderSOAP, 133  | ARCLibError, 37              |
| upper                             | WriteOutOfOrder              |
| Arc, 24                           | Arc::DataPoint, 103          |
| uri_unescape                      | Arc::DataPointDirect, 109    |
|                                   |                              |

```
Arc::DataPointIndex, 116
WriteStdin
    Arc::Run, 260
WSA Endpoint Reference\\
    Arc::WSAEndpointReference, 306
WSAFault
    Arc, 23
WSAFaultAssign
    Arc, 27
WSAFaultExtract
    Arc. 27
WSAFaultInvalidAddressingHeader
    Arc, 23
WSAFaultUnknown
    Arc, 23
WSAHeader
    Arc::WSAHeader, 308
WSRF
    Arc::WSRF, 311
WSRFBaseFault
    Arc::WSRFBaseFault, 313
WSRP
    Arc::WSRP, 315
WSRPFault
    Arc::WSRPFault, 317
WSRPR esource Property Change Failure\\
    Arc::WSRPResourcePropertyChangeFailure,
WSSType
    Arc, 22
X509Token
    Arc::X509Token, 319
X509TokenType
    Arc::X509Token, 319
XACML
    Arc::SecAttr, 269
XMLNode
    Arc::XMLNode, 323
XMLNodeContainer
    Arc::XMLNodeContainer, 331
XMLSecNode
    Arc::XMLSecNode, 333
XPathLookup
    Arc::XMLNode, 329
```