Hosting Environment (Daemon) Reference Manual

Generated by Doxygen 1.4.7

Fri Oct 15 16:07:17 2010

Contents

1	Host	ting Environment (Daemon) Namespace Index	1
	1.1	Hosting Environment (Daemon) Namespace List	1
2	Host	ting Environment (Daemon) Hierarchical Index	3
	2.1	Hosting Environment (Daemon) Class Hierarchy	3
3	Host	ting Environment (Daemon) Data Structure Index	7
	3.1	Hosting Environment (Daemon) Data Structures	7
4	Host	ting Environment (Daemon) File Index	13
	4.1	Hosting Environment (Daemon) File List	13
5	Host	ting Environment (Daemon) Namespace Documentation	17
	5.1	Arc Namespace Reference	17
	5.2	ArcCredential Namespace Reference	41
6	Host	ting Environment (Daemon) Data Structure Documentation	43
	6.1	Arc::Adler32Sum Class Reference	43
	6.2	ArcSec::AlgFactory Class Reference	44
	6.3	Arc::ApplicationEnvironment Class Reference	45
	6.4	Arc::ArcLocation Class Reference	46
	6.5	ArcSec::Attr Struct Reference	47
	6.6	ArcSec::AttributeFactory Class Reference	48
		The second control of the second seco	
	6.7	Arc::AttributeIterator Class Reference	49
	6.7 6.8		49 52
		Arc::AttributeIterator Class Reference	
	6.8 6.9	Arc::AttributeIterator Class Reference	52
	6.8 6.9 6.10	Arc::AttributeIterator Class Reference	52 53
	6.8 6.9 6.10 6.11	ArcSec::AttributeIterator Class Reference	52 53 55

ii CONTENTS

6.14	Arc::BrokerLoader Class Reference	61
6.15	Arc::CacheParameters Struct Reference	63
	Arc::ChainContext Class Reference	64
6.17	Arc::CheckSum Class Reference	65
6.18	Arc::CheckSumAny Class Reference	66
6.19	Arc::CIStringValue Class Reference	67
6.20	Arc::ClientHTTP Class Reference	69
6.21	Arc::ClientInterface Class Reference	70
6.22	Arc::ClientSOAP Class Reference	71
6.23	Arc::ClientTCP Class Reference	73
6.24	ArcSec::CombiningAlg Class Reference	74
6.25	Arc::Config Class Reference	76
6.26	Arc::ConfusaCertHandler Class Reference	78
6.27	Arc::ConfusaParserUtils Class Reference	79
6.28	$Arc:: Counted Pointer < T > Class \ Template \ Reference \ . \ . \ . \ . \ . \ . \ . \ . \ . \ $	81
6.29	Arc::Counter Class Reference	83
6.30	Arc::CounterTicket Class Reference	90
6.31	Arc::CRC32Sum Class Reference	92
6.32	Arc::CredentialError Class Reference	93
6.33	Arc::CredentialStore Class Reference	94
6.34	Arc::Database Class Reference	95
6.35	Arc::DataBuffer Class Reference	98
6.36	Arc::DataCallback Class Reference	105
6.37	Arc::DataHandle Class Reference	106
6.38	Arc::DataMover Class Reference	107
6.39	Arc::DataPoint Class Reference	111
6.40	Arc::DataPointDirect Class Reference	124
6.41	Arc::DataPointIndex Class Reference	131
6.42	Arc::DataSpeed Class Reference	139
6.43	Arc::DataStatus Class Reference	143
6.44	ArcSec::DateTimeAttribute Class Reference	145
6.45	Arc::DelegationConsumer Class Reference	147
6.46	Arc::DelegationConsumerSOAP Class Reference	149
6.47	Arc::DelegationContainerSOAP Class Reference	151
6.48	Arc::DelegationProvider Class Reference	153
6.49	Arc::DelegationProviderSOAP Class Reference	155

CONTENTS

6.51 ArcSec::DurationAttribute Class Reference 6.52 ArcSec::EqualFunction Class Reference 6.53 ArcSec::EvalResult Struct Reference 6.54 ArcSec::EvaluationCtx Class Reference 6.55 ArcSec::Evaluator Class Reference 6.56 ArcSec::EvaluatorContext Class Reference 6.57 ArcSec::EvaluatorLoader Class Reference	. 161 . 163 . 164 . 165 . 168 . 169
6.53 ArcSec::EvalResult Struct Reference	. 163 . 164 . 165 . 168 . 169
6.54 ArcSec::EvaluationCtx Class Reference 6.55 ArcSec::Evaluator Class Reference 6.56 ArcSec::EvaluatorContext Class Reference	. 164. 165. 168. 169. 171
6.55 ArcSec::Evaluator Class Reference 6.56 ArcSec::EvaluatorContext Class Reference	. 165. 168. 169. 171
6.56 ArcSec::EvaluatorContext Class Reference	. 168 . 169 . 171
	. 169 . 171
6.57 ArcSec::EvaluatorLoader Class Reference	. 171
6.58 Arc::ExecutionTarget Class Reference	. 174
6.59 Arc::ExpirationReminder Class Reference	
6.60 Arc::FileCache Class Reference	. 176
6.61 FileCacheHash Class Reference	. 182
6.62 Arc::FileInfo Class Reference	. 183
6.63 Arc::FileLock Class Reference	. 184
6.64 ArcSec::FnFactory Class Reference	. 185
6.65 ArcSec::Function Class Reference	. 186
6.66 Arc::InfoCache Class Reference	. 187
6.67 Arc::InfoFilter Class Reference	. 188
6.68 Arc::InfoRegister Class Reference	. 189
6.69 Arc::InfoRegisterContainer Class Reference	. 190
6.70 Arc::InfoRegisters Class Reference	. 191
6.71 Arc::InfoRegistrar Class Reference	. 192
6.72 Arc::InformationContainer Class Reference	. 193
6.73 Arc::InformationInterface Class Reference	. 195
6.74 Arc::InformationRequest Class Reference	. 197
6.75 Arc::InformationResponse Class Reference	. 199
6.76 Arc::IntraProcessCounter Class Reference	. 200
6.77 Arc::Job Class Reference	. 205
6.78 Arc::JobController Class Reference	. 206
6.79 Arc::JobControllerLoader Class Reference	. 208
6.80 Arc::JobState Class Reference	. 210
6.81 Arc::JobSupervisor Class Reference	. 211
6.82 Arc::Loader Class Reference	. 212
6.83 Arc::LogDestination Class Reference	. 213
6.84 Arc::LogFile Class Reference	. 215
6.85 Arc::Logger Class Reference	. 218

iv CONTENTS

6.86 Arc::LogMessage Class Reference
6.87 Arc::LogStream Class Reference
6.88 ArcSec::MatchFunction Class Reference
6.89 Arc::MCC Class Reference
6.90 Arc::MCC_Status Class Reference
6.91 Arc::MCCInterface Class Reference
6.92 Arc::MCCLoader Class Reference
6.93 Arc::MD5Sum Class Reference
6.94 Arc::Message Class Reference
6.95 Arc::MessageAttributes Class Reference
6.96 Arc::MessageAuth Class Reference
6.97 Arc::MessageAuthContext Class Reference
6.98 Arc::MessageContext Class Reference
6.99 Arc::MessageContextElement Class Reference
6.100Arc::MessagePayload Class Reference
6.101 Arc::ModuleDesc Class Reference
6.102Arc::ModuleManager Class Reference
6.103 Arc::MultiSecAttr Class Reference
6.104Arc::MySQLDatabase Class Reference
6.105 Arc::OAuthConsumer Class Reference
6.106Arc::PathIterator Class Reference
6.107 Arc::PayloadRaw Class Reference
6.108 Arc::PayloadRawInterface Class Reference
6.109 Arc::PayloadSOAP Class Reference
6.110Arc::PayloadStream Class Reference
6.111 Arc::PayloadStreamInterface Class Reference
6.112Arc::PayloadWSRF Class Reference
6.113 ArcSec::PDP Class Reference
6.114ArcSec::PeriodAttribute Class Reference
6.115 ArcSec::PermitOverridesCombiningAlg Class Reference
6.116Arc::Plexer Class Reference
6.117 Arc::PlexerEntry Class Reference
6.118 Arc::Plugin Class Reference
6.119Arc::PluginArgument Class Reference
6.120Arc::PluginDesc Class Reference
6.121 Arc::PluginDescriptor Struct Reference

CONTENTS

6.122Arc::PluginsFactory Class Reference
6.123 ArcSec::Policy Class Reference
6.124ArcSec::PolicyParser Class Reference
6.125 ArcSec::PolicyStore Class Reference
6.126Arc::RegisteredService Class Reference
6.127 Arc::RegularExpression Class Reference
6.128ArcSec::Request Class Reference
6.129ArcSec::RequestAttribute Class Reference
6.130ArcSec::RequestItem Class Reference
6.131 ArcSec::Response Class Reference
6.132ArcSec::ResponseItem Class Reference
6.133 Arc::Run Class Reference
6.134Arc::SAMLToken Class Reference
6.135 Arc::SecAttr Class Reference
6.136Arc::SecAttrFormat Class Reference
6.137 Arc::SecAttrValue Class Reference
6.138ArcSec::SecHandler Class Reference
6.139ArcSec::SecHandlerConfig Class Reference
6.140ArcSec::Security Class Reference
6.141 Arc::Service Class Reference
6.142Arc::SimpleCondition Class Reference
6.143 Arc::SOAPMessage Class Reference
6.144Arc::Software Class Reference
6.145 Arc::Software Requirement Class Reference
6.146ArcSec::Source Class Reference
6.147 ArcSec::SourceFile Class Reference
6.148ArcSec::SourceURL Class Reference
6.149 Arc::Submitter Class Reference
6.150Arc::SubmitterLoader Class Reference
6.151 Arc::TargetGenerator Class Reference
6.152Arc::TargetRetriever Class Reference
6.153 Arc::TargetRetrieverLoader Class Reference
6.154Arc::ThreadRegistry Class Reference
6.155 Arc::Time Class Reference
6.156ArcSec::TimeAttribute Class Reference
6.157 Arc::URLLocation Class Reference

Vi

	6.158Arc::UserConfig Class Reference	361
	6.159Arc::UsernameToken Class Reference	389
	6.160Arc::UserSwitch Class Reference	391
	6.161Arc::VOMSTrustList Class Reference	392
	6.162Arc::WSAEndpointReference Class Reference	394
	6.163Arc::WSAHeader Class Reference	396
	6.164Arc::WSRF Class Reference	399
	6.165Arc::WSRFBaseFault Class Reference	401
	6.166Arc::WSRP Class Reference	403
	6.167Arc::WSRPFault Class Reference	405
	6.168Arc::WSRPResourcePropertyChangeFailure Class Reference	406
	6.169Arc::X509Token Class Reference	407
	6.170Arc::XMLNode Class Reference	409
	6.171 Arc::XMLNodeContainer Class Reference	420
	6.172Arc::XMLSecNode Class Reference	422
7	Hosting Environment (Daemon) File Documentation	425
	7.1 LIRI h File Reference	425

Hosting Environment (Daemon) Namespace Index

1.1 Hosting Environment (Daemon) Namespace List

Here is a list of all documented namespaces with brief descriptions:

Arc	(Some	utility	methods	for	using	xml	security	library	
	(http:/	/www.alek	sey.com/xml:	sec/))					17
ArcCr	edential								41

2	Hosting Environment (Daemon) Namespace Index

Hosting Environment (Daemon) Hierarchical Index

2.1 Hosting Environment (Daemon) Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

Arc::ArcLocation
ArcSec::Attr
Arc::AttributeIterator
ArcSec::AttributeProxy
ArcSec::AttributeValue
ArcSec::DateTimeAttribute
ArcSec::DurationAttribute
ArcSec::PeriodAttribute
ArcSec::TimeAttribute
ArcSec::Attrs
ArcSec::AuthzRequestSection
Arc::AutoPointer < T >
Arc::BaseConfig
Arc::CacheParameters
Arc::ChainContext
Arc::CheckSum
Arc::Adler32Sum
Arc::CheckSumAny
Arc::CRC32Sum
Arc::MD5Sum
Arc::ClientInterface
Arc::ClientTCP
Arc::ClientHTTP
Arc::ClientSOAP
ArcSec::CombiningAlg
ArcSec::DenyOverridesCombiningAlg
ArcSec::PermitOverridesCombiningAlg
Arc::ConfusaCertHandler
Arc::ConfusaParserUtils

Arc::CountedPointer $<$ T $>$	81
arc::Counter	83
Arc::IntraProcessCounter	 200
arc::CounterTicket	90
arc::CredentialError	93
arc::CredentialStore	94
arc::Database	95
Arc::MySQLDatabase	 254
arc::DataBuffer	98
arc::DataCallback	105
arc::DataHandle	106
arc::DataMover	107
arc::DataSpeed	139
arc::DataStatus	143
arc::DelegationConsumer	147
Arc::DelegationConsumerSOAP	149
arc::DelegationContainerSOAP	 151
arc::DelegationProvider	 153
Arc::DelegationProviderSOAP	 155
arcSec::EvalResult	 163
arcSec::EvaluationCtx	 164
arcSec::EvaluatorContext	168
arcSec::EvaluatorLoader	169
arc::ExecutionTarget	 171
arc::ExpirationReminder	174
arc::FileCache	176
ileCacheHash	182
arc::FileInfo	183
arc::FileLock	184
arcSec::Function	 186
ArcSec::EqualFunction	161
ArcSec::MatchFunction	 225
arc::InfoCache	 187
arc::InfoFilter	
arc::InfoRegister	
arc::InfoRegisterContainer	190
arc::InfoRegisters	191
arc::InfoRegistrar	192
arc::InformationInterface	195
Arc::InformationContainer	 193
arc::InformationRequest	 197
arc::InformationResponse	 199
arc::Job	205
arc::JobState	 210
arc::JobSupervisor	211
arc::Loader	212
Arc::BrokerLoader	61
Arc::JobControllerLoader	208
Arc::MCCLoader	235
Arc::SubmitterLoader	344
Arc::TargetRetrieverLoader	351
arc::LogDestination	 213

Arc::LogFile
Arc::LogStream
Arc::Logger
Arc::LogMessage
Arc::MCC_Status
Arc::Message
Arc::MessageAttributes
Arc::MessageAuth
Arc::MessageAuthContext
Arc::MessageContext
Arc::MessageContextElement
Arc::MessagePayload
Arc::PayloadRawInterface
Arc::PayloadRaw
Arc::PayloadSOAP
Arc::PayloadStreamInterface
Arc::PayloadStream
Arc::PayloadWSRF
Arc::ModuleDesc
Arc::ModuleManager
C
;
Arc::OAuthConsumer
Arc::PathIterator
Arc::PlexerEntry
Arc::Plugin
Arc::DataPoint
Arc::DataPointDirect
Arc::DataPointIndex
Arc::JobController
Arc::MCCInterface
Arc::MCC
Arc::Plexer
Arc::Service
Arc::RegisteredService
Arc::Submitter
Arc::TargetRetriever
ArcSec::AlgFactory
ArcSec::AttributeFactory
ArcSec::Evaluator
ArcSec::FnFactory
ArcSec::PDP
ArcSec::Policy
ArcSec::Request
ArcSec::SecHandler
Arc::PluginDesc
Arc::RegularExpression
ArcSec::RequestAttribute
ATCACC REGUESHIEIII /97

	298
· · · · · · · · · · · · · · · · · · ·	299
	300
	304
	307
Arc::MultiSecAttr	253
	310
Arc::SecAttrValue	311
Arc::CIStringValue	67
ArcSec::Security	315
	319
	321
Arc::Software	323
Arc::ApplicationEnvironment	45
Arc::SoftwareRequirement	331
ArcSec::Source	339
ArcSec::SourceFile	341
ArcSec::SourceURL	342
Arc::TargetGenerator	346
Arc::ThreadRegistry	353
	354
	359
	361
	389
	391
	392
r	394 396
	<i>3</i> 96
	401
	405
Then we fill resource troperty changer under the	406
110000000000000000000000000000000000000	403
	407
	409
8	76
	422
The been been been been been been been be	314
Arc::XMLNodeContainer	420

Hosting Environment (Daemon) Data Structure Index

3.1 Hosting Environment (Daemon) Data Structures

Here are the data structures with brief descriptions:

Arc::Counter (A class defining a common interface for counters)	83
Arc::CounterTicket (A class for "tickets" that correspond to counter reservations)	90
Arc::CRC32Sum (Implementation of CRC32 checksum)	92
Arc::CredentialError	93
Arc::CredentialStore	94
Arc::Database (Interface for calling database client library)	95
Arc::DataBuffer (Represents set of buffers)	98
Arc::DataCallback	105
Arc::DataHandle (This class is a wrapper around the DataPoint (p. 111) class)	106
Arc::DataMover	107
Arc::DataPoint (This base class is an abstraction of URL)	111
Arc::DataPointDirect (This is a kind of generalized file handle)	124
Arc::DataPointIndex (Complements DataPoint (p. 111) with attributes common for Index-	
ing Service (p. 316) URLs)	131
Arc::DataSpeed (Keeps track of average and instantaneous transfer speed)	139
Arc::DataStatus	143
ArcSec::DateTimeAttribute	145
Arc::DelegationConsumer	147
Arc::DelegationConsumerSOAP	149
Arc::DelegationContainerSOAP	151
Arc::DelegationProvider	153
Arc::DelegationProviderSOAP	155
ArcSec::DenyOverridesCombiningAlg (Implement the ''Deny-Overrides'' algorithm)	157
ArcSec::DurationAttribute	159
ArcSec::EqualFunction (Evaluate whether the two values are equal)	161
ArcSec::EvalResult (Struct to record the xml node and effect, which will be used by Evalu-	
ator (p. 165) to get the information about which rule/policy(in xmlnode) is satisfied	
)	163
ArcSec::EvaluationCtx (EvaluationCtx (p. 164), in charge of storing some context informa-	
tion for)	164
ArcSec::Evaluator (Interface for policy evaluation. Execute the policy evaluation, based on	
the request and policy)	165
ArcSec::EvaluatorContext (Context for evaluator. It includes the factories which will be	
used to create related objects)	168
ArcSec::EvaluatorLoader (EvaluatorLoader (p. 169) is implemented as a helper class for	
loading different Evaluator (p. 165) objects, like ArcEvaluator)	169
Arc::ExecutionTarget (ExecutionTarget (p. 171))	171
Arc::FileCache	176
FileCacheHash	182
Arc::FileInfo (FileInfo (p. 183) stores information about files (metadata))	183
Arc::FileLock (A general file locking class)	184
ArcSec::FnFactory (Interface for function factory class)	185
ArcSec::Function (Interface for function, which is in charge of evaluating two Attribute-	100
Value (p. 53))	186
Arc::InfoCache (Stores XML document in filesystem split into parts)	187
Arc::InfoFilter (Filters information document according to identity of requestor)	188
Arc::InfoRegister (Registration to ISIS interface)	189
Arc::InfoRegisterContainer	190
Arc::InfoRegisters (Handling multiple registrations to ISISes)	190
Arc::InfoRegistrar (Registration process associated with particular ISIS)	191
Arc::InformationContainer (Information System document container and processor)	192
Arc::InformationInterface (Information System document container and processor)	193
Arc::InformationRequest (Request for information in InfoSystem)	
ATC IIIIOI III AUOII NEQUEST (NEQUEST IOF IIIOFIII AUOII III IIII OSYSTEIII)	19/

Arc::InformationResponse (Informational response from InfoSystem)	199
Arc::IntraProcessCounter (A class for counters used by threads within a single process) .	200
Arc::Job (Job (p. 205))	205
Arc::JobController (Must be specialized for each supported middleware flavour)	206
Arc::JobControllerLoader	208
Arc::JobState	210
Arc::JobSupervisor (% JobSupervisor (p. 211) class)	211
Arc::Loader (Plugins loader)	212
Arc::LogDestination (A base class for log destinations)	
Arc::LogFile (A class for logging to files)	
Arc::Logger (A logger class)	
Arc::LogMessage (A class for log messages)	
Arc::LogStream (A class for logging to ostreams)	
ArcSec::MatchFunction (Evaluate whether arg1 (value in regular expression) matched	
arg0 (lable in regular expression))	225
Arc::MCC (Message (p. 238) Chain Component - base class for every MCC (p. 227) plugin)	227
Arc::MCC_Status (A class for communication of MCC (p. 227) processing results)	230
Arc::MCCInterface (Interface for communication between MCC (p. 227), Service (p. 316)	230
and Plexer (p. 277) objects)	233
Arc::MCCLoader (Creator of Message (p. 238) Component Chains (MCC (p. 227))	235
Arc::MD5Sum (Implementation of MD5 checksum)	237
Arc::Message (Object being passed through chain of MCCs)	238
Arc::Message (Object being passed through chain of MrCcs)	241
Arc::MessageAuth (Contains authencity information, authorization tokens and decisions)	241
Arc::MessageAuthContext (Handler for content of message auth* context)	
Arc::MessageContext (Handler for content of message context)	247
Arc::MessageContextElement (Top class for elements contained in message context)	248
Arc::MessagePayload (Base class for content of message passed through chain)	249
Arc::ModuleDesc (Description of loadable module)	
Arc::ModuleManager (Manager of shared libraries)	
Arc::MultiSecAttr (Container of multiple SecAttr (p. 307) attributes)	
Arc::MySQLDatabase	
Arc::OAuthConsumer	
Arc::PathIterator (Class to iterate through elements of path)	
Arc::PayloadRaw (Raw byte multi-buffer)	
Arc::PayloadRawInterface (Random Access Payload for Message (p. 238) objects)	
Arc::PayloadSOAP (Payload of Message (p. 238) with SOAP content)	
Arc::PayloadStream (POSIX handle as Payload)	265
Arc::PayloadStreamInterface (Stream-like Payload for Message (p. 238) object)	268
Arc::PayloadWSRF (This class combines MessagePayload (p. 249) with WSRF (p. 399))	271
ArcSec::PDP (Base class for Policy (p. 286) Decision Point plugins)	272
ArcSec::PeriodAttribute	273
ArcSec::PermitOverridesCombiningAlg (Implement the "Permit-Overrides" algorithm) .	275
Arc::Plexer (The Plexer (p. 277) class, used for routing messages to services)	277
Arc::PlexerEntry (A pair of label (regex) and pointer to MCC (p. 227))	279
Arc::Plugin (Base class for loadable ARC components)	280
Arc::PluginArgument (Base class for passing arguments to loadable ARC components)	281
Arc::PluginDesc (Description of plugin)	282
Arc::PluginDescriptor (Description of ARC lodable component)	283
Arc::PluginsFactory (Generic ARC plugins loader)	284
ArcSec::Policy (Interface for containing and processing different types of policy)	286
ArcSec::PolicyParser (A interface which will isolate the policy object from actual policy	_55
storage (files, urls, database))	289
ArcSec::PolicyStore (Storage place for policy objects)	290
Artebeent one, but to the part for point, objects /	270

Arc::RegisteredService (RegisteredService (p. 291) - extension of Service (p. 316) perform-	
ing self-registration)	291
Arc::RegularExpression (A regular expression class)	292
ArcSec::Request (Base class/Interface for request, includes a container for RequestItems	
and some operations)	294
ArcSec::RequestAttribute (Wrapper which includes AttributeValue (p. 53) object which is	
generated according to date type of one spefic node in Request.xml)	296
ArcSec::RequestItem (Interface for request item container, <subjects, actions,="" objects,<="" th=""><th></th></subjects,>	
ctxs> tuple)	297
ArcSec::Response (Container for the evaluation results)	
ArcSec::ResponseItem (Evaluation result concerning one RequestTuple)	
Arc::Run	
Arc::SAMLToken (Class for manipulating SAML Token Profile)	
Arc::SecAttr (This is an abstract interface to a security attribute)	
Arc::SecAttrFormat (Export/import format)	
Arc::SecAttrValue (This is an abstract interface to a security attribute)	
ArcSec::SecHandler (Base class for simple security handling plugins)	
ArcSec::SecHandlerConfig	
ArcSec::Security (Common stuff used by security related slasses)	
Arc::Service (Service (p. 316) - last component in a Message (p. 238) Chain)	
Arc::SimpleCondition (Simple triggered condition)	
Arc::SOAPMessage (Message (p. 238) restricted to SOAP payload)	
Arc::Software (Used to represent software (names and version) and comparison)	323
Arc::Software (Class used to express and resolve version requirements on soft-	323
ware)	331
ArcSec::Source (Acquires and parses XML document from specified source)	339
ArcSec::SourceFile (Convenience class for obtaining XML document from file)	341
Aresectional transfer of the convenience class for obtaining Avite document from the justice.	271
ArcSecv-SourceIIDI (Convenience class for obtaining VMI document from remote IIDI)	3/12
Arc:SourceURL (Convenience class for obtaining XML document from remote URL) Arc:Submitter (Rese class for the Submitters)	342
Arc::Submitter (Base class for the Submitters)	343
Arc::Submitter (Base class for the Submitters)	343 344
Arc::Submitter (Base class for the Submitters)	343 344 346
Arc::Submitter (Base class for the Submitters)	343 344 346 349
Arc::Submitter (Base class for the Submitters)	343 344 346 349 351
Arc::Submitter (Base class for the Submitters)	343 344 346 349 351 353
Arc::Submitter (Base class for the Submitters)	343 344 346 349 351 353 354
Arc::Submitter (Base class for the Submitters)	343 344 346 349 351 353 354 357
Arc::Submitter (Base class for the Submitters) Arc::SubmitterLoader Arc::TargetGenerator (Target generation class) Arc::TargetRetriever (TargetRetriever base class) Arc::TargetRetrieverLoader Arc::ThreadRegistry Arc::Time (A class for storing and manipulating times) ArcSec::TimeAttribute Arc::URLLocation (Class to hold a resolved URL location)	343 344 346 349 351 353 354 357 359
Arc::Submitter (Base class for the Submitters) Arc::SubmitterLoader Arc::TargetGenerator (Target generation class) Arc::TargetRetriever (TargetRetriever base class) Arc::TargetRetrieverLoader Arc::ThreadRegistry Arc::Time (A class for storing and manipulating times) ArcSec::TimeAttribute Arc::URLLocation (Class to hold a resolved URL location) Arc::UserConfig (User configuration class)	343 344 346 349 351 353 354 357
Arc::Submitter (Base class for the Submitters) Arc::SubmitterLoader Arc::TargetGenerator (Target generation class) Arc::TargetRetriever (TargetRetriever base class) Arc::TargetRetrieverLoader Arc::ThreadRegistry Arc::Time (A class for storing and manipulating times) ArcSec::TimeAttribute Arc::URLLocation (Class to hold a resolved URL location) Arc::UserConfig (User configuration class) Arc::UsernameToken (Interface for manipulation of WS-Security according to Username	343 344 346 349 351 353 354 357 361
Arc::Submitter (Base class for the Submitters) Arc::SubmitterLoader Arc::TargetGenerator (Target generation class) Arc::TargetRetriever (TargetRetriever base class) Arc::TargetRetrieverLoader Arc::ThreadRegistry Arc::Time (A class for storing and manipulating times) ArcSec::TimeAttribute Arc::URLLocation (Class to hold a resolved URL location) Arc::UserConfig (User configuration class) Arc::UsernameToken (Interface for manipulation of WS-Security according to Username Token Profile)	343 344 349 351 353 354 357 359 361
Arc::Submitter (Base class for the Submitters) Arc::SubmitterLoader Arc::TargetGenerator (Target generation class) Arc::TargetRetriever (TargetRetriever base class) Arc::TargetRetrieverLoader Arc::ThreadRegistry Arc::Time (A class for storing and manipulating times) ArcSec::TimeAttribute Arc::URLLocation (Class to hold a resolved URL location) Arc::UserConfig (User configuration class) Arc::UsernameToken (Interface for manipulation of WS-Security according to Username Token Profile) Arc::UserSwitch	343 344 346 349 351 353 354 357 359 361 389 391
Arc::Submitter (Base class for the Submitters) Arc::SubmitterLoader Arc::TargetGenerator (Target generation class) Arc::TargetRetriever (TargetRetriever base class) Arc::TargetRetrieverLoader Arc::ThreadRegistry Arc::Time (A class for storing and manipulating times) ArcSec::TimeAttribute Arc::URLLocation (Class to hold a resolved URL location) Arc::UserConfig (User configuration class) Arc::UsernameToken (Interface for manipulation of WS-Security according to Username Token Profile) Arc::UserSwitch Arc::VOMSTrustList	343 344 349 351 353 354 357 359 361
Arc::Submitter (Base class for the Submitters) Arc::SubmitterLoader Arc::TargetGenerator (Target generation class) Arc::TargetRetriever (TargetRetriever base class) Arc::TargetRetrieverLoader Arc::ThreadRegistry Arc::Time (A class for storing and manipulating times) Arc::TimeAttribute Arc::URLLocation (Class to hold a resolved URL location) Arc::UserConfig (User configuration class) Arc::UsernameToken (Interface for manipulation of WS-Security according to Username Token Profile) Arc::UserSwitch Arc::VOMSTrustList Arc::WSAEndpointReference (Interface for manipulation of WS-Adressing Endpoint Ref-	343 344 346 349 351 353 354 357 359 361 389 391
Arc::Submitter (Base class for the Submitters) Arc::SubmitterLoader Arc::TargetGenerator (Target generation class) Arc::TargetRetriever (TargetRetriever base class) Arc::TargetRetrieverLoader Arc::ThreadRegistry Arc::Time (A class for storing and manipulating times) ArcSec::TimeAttribute Arc::URLLocation (Class to hold a resolved URL location) Arc::UserConfig (User configuration class) Arc::UsernameToken (Interface for manipulation of WS-Security according to Username Token Profile) Arc::UserSwitch Arc::VOMSTrustList Arc::WSAEndpointReference (Interface for manipulation of WS-Adressing Endpoint Reference)	343 344 346 349 351 353 354 357 359 361 389 391
Arc::Submitter (Base class for the Submitters) Arc::SubmitterLoader Arc::TargetGenerator (Target generation class) Arc::TargetRetriever (TargetRetriever base class) Arc::TargetRetrieverLoader Arc::ThreadRegistry Arc::Time (A class for storing and manipulating times) ArcSec::TimeAttribute Arc::URLLocation (Class to hold a resolved URL location) Arc::UserConfig (User configuration class) Arc::UsernameToken (Interface for manipulation of WS-Security according to Username Token Profile) Arc::UserSwitch Arc::VOMSTrustList Arc::WSAEndpointReference (Interface for manipulation of WS-Adressing Endpoint Reference) Arc::WSAHeader (Interface for manipulation WS-Addressing information in SOAP	343 344 346 349 351 353 354 357 359 361 389 391 392
Arc::Submitter (Base class for the Submitters) Arc::SubmitterLoader Arc::TargetGenerator (Target generation class) Arc::TargetRetriever (TargetRetriever base class) Arc::TargetRetrieverLoader Arc::ThreadRegistry Arc::Time (A class for storing and manipulating times) ArcSec::TimeAttribute Arc::URLLocation (Class to hold a resolved URL location) Arc::UserConfig (User configuration class) Arc::UsernameToken (Interface for manipulation of WS-Security according to Username Token Profile) Arc::UserSwitch Arc::VOMSTrustList Arc::WSAEndpointReference (Interface for manipulation of WS-Adressing Endpoint Reference) Arc::WSAHeader (Interface for manipulation WS-Addressing information in SOAP header)	343 344 346 349 351 353 354 357 359 361 389 391 392
Arc::Submitter (Base class for the Submitters) Arc::SubmitterLoader Arc::TargetGenerator (Target generation class) Arc::TargetRetriever (TargetRetriever base class) Arc::TargetRetrieverLoader Arc::ThreadRegistry Arc::Time (A class for storing and manipulating times) ArcSec::TimeAttribute Arc::URLLocation (Class to hold a resolved URL location) Arc::UserConfig (User configuration class) Arc::UsernameToken (Interface for manipulation of WS-Security according to Username Token Profile) Arc::UserSwitch Arc::VOMSTrustList Arc::WSAEndpointReference (Interface for manipulation of WS-Adressing Endpoint Reference) Arc::WSAHeader (Interface for manipulation WS-Addressing information in SOAP header) Arc::WSRF (Base class for every WSRF (p. 399) message)	343 344 346 349 351 353 354 357 359 361 389 391 392 394
Arc::Submitter (Base class for the Submitters) Arc::SubmitterLoader Arc::TargetGenerator (Target generation class) Arc::TargetRetriever (TargetRetriever base class) Arc::TargetRetrieverLoader Arc::ThreadRegistry Arc::Time (A class for storing and manipulating times) ArcSec::TimeAttribute Arc::URLLocation (Class to hold a resolved URL location) Arc::UserConfig (User configuration class) Arc::UsernameToken (Interface for manipulation of WS-Security according to Username Token Profile) Arc::UserSwitch Arc::VOMSTrustList Arc::WSAEndpointReference (Interface for manipulation of WS-Adressing Endpoint Reference) Arc::WSAHeader (Interface for manipulation WS-Addressing information in SOAP header) Arc::WSRF (Base class for every WSRF (p. 399) message) Arc::WSRFBaseFault (Base class for WSRF (p. 399) fault messages)	343 344 346 349 351 353 354 357 361 389 391 392 394 401
Arc::Submitter (Base class for the Submitters) Arc::SubmitterLoader Arc::TargetGenerator (Target generation class) Arc::TargetRetriever (TargetRetriever base class) Arc::TargetRetrieverLoader Arc::ThreadRegistry Arc::Time (A class for storing and manipulating times) ArcSec::TimeAttribute Arc::URLLocation (Class to hold a resolved URL location) Arc::UserConfig (User configuration class) Arc::UsernameToken (Interface for manipulation of WS-Security according to Username Token Profile) Arc::UserSwitch Arc::VOMSTrustList Arc::WSAEndpointReference (Interface for manipulation of WS-Adressing Endpoint Reference) Arc::WSAHeader (Interface for manipulation WS-Addressing information in SOAP header) Arc::WSRF (Base class for every WSRF (p. 399) message) Arc::WSRFBaseFault (Base class for WSRF (p. 399) fault messages) Arc::WSRP (Base class for WS-ResourceProperties structures)	343 344 346 349 351 353 354 357 359 361 392 394 394 401 403
Arc::Submitter (Base class for the Submitters) Arc::SubmitterLoader Arc::TargetGenerator (Target generation class) Arc::TargetRetriever (TargetRetriever base class) Arc::TargetRetrieverLoader Arc::ThreadRegistry Arc::Time (A class for storing and manipulating times) ArcSec::TimeAttribute Arc::URLLocation (Class to hold a resolved URL location) Arc::UserConfig (User configuration class) Arc::UsernameToken (Interface for manipulation of WS-Security according to Username Token Profile) Arc::UserSwitch Arc::VOMSTrustList Arc::WSAEndpointReference (Interface for manipulation of WS-Adressing Endpoint Reference) Arc::WSAHeader (Interface for manipulation WS-Addressing information in SOAP header) Arc::WSRF (Base class for every WSRF (p. 399) message) Arc::WSRF (Base class for WS-ResourceProperties structures) Arc::WSRP (Base class for WS-ResourceProperties faults)	343 344 346 349 351 353 354 357 359 361 392 394 401 403 405
Arc::Submitter (Base class for the Submitters) Arc::SubmitterLoader Arc::TargetGenerator (Target generation class) Arc::TargetRetriever (TargetRetriever base class) Arc::TargetRetrieverLoader Arc::Time (A class for storing and manipulating times) Arc:Sec::Time (A class for storing and manipulating times) Arc::URLLocation (Class to hold a resolved URL location) Arc::UserConfig (User configuration class) Arc::UsernameToken (Interface for manipulation of WS-Security according to Username Token Profile) Arc::UserSwitch Arc::VSAEndpointReference (Interface for manipulation of WS-Adressing Endpoint Reference) Arc::WSAHeader (Interface for manipulation WS-Addressing information in SOAP header) Arc::WSRF (Base class for every WSRF (p. 399) message) Arc::WSRFBaseFault (Base class for WS-ResourceProperties structures) Arc::WSRPFault (Base class for WS-ResourceProperties faults) Arc::WSRPResourcePropertyChangeFailure	343 344 346 349 351 353 354 357 359 361 392 394 401 403 405 406
Arc::Submitter (Base class for the Submitters) Arc::SubmitterLoader Arc::TargetGenerator (Target generation class) Arc::TargetRetriever (TargetRetriever base class) Arc::TargetRetrieverLoader Arc::Time (A class for storing and manipulating times) Arc:Sec::Time (A class for storing and manipulating times) Arc::URLLocation (Class to hold a resolved URL location) Arc::UserConfig (User configuration class) Arc::UsernameToken (Interface for manipulation of WS-Security according to Username Token Profile) Arc::UserSwitch Arc::VOMSTrustList Arc::WSAEndpointReference (Interface for manipulation of WS-Adressing Endpoint Reference) Arc::WSAHeader (Interface for manipulation WS-Addressing information in SOAP header) Arc::WSRF (Base class for every WSRF (p. 399) message) Arc::WSRFBaseFault (Base class for WSRF (p. 399) fault messages) Arc::WSRP (Base class for WS-ResourceProperties structures) Arc::WSRPFault (Base class for WS-ResourceProperties faults) Arc::WSRPResourcePropertyChangeFailure Arc::X509Token (Class for manipulating X.509 Token Profile)	343 344 346 349 351 353 354 357 359 361 392 394 403 405 406 407
Arc::Submitter (Base class for the Submitters) Arc::SubmitterLoader Arc::TargetGenerator (Target generation class) Arc::TargetRetriever (TargetRetriever base class) Arc::TargetRetrieverLoader Arc::Time (A class for storing and manipulating times) Arc:Sec::Time (A class for storing and manipulating times) Arc::URLLocation (Class to hold a resolved URL location) Arc::UserConfig (User configuration class) Arc::UsernameToken (Interface for manipulation of WS-Security according to Username Token Profile) Arc::UserSwitch Arc::VSAEndpointReference (Interface for manipulation of WS-Adressing Endpoint Reference) Arc::WSAHeader (Interface for manipulation WS-Addressing information in SOAP header) Arc::WSRF (Base class for every WSRF (p. 399) message) Arc::WSRFBaseFault (Base class for WS-ResourceProperties structures) Arc::WSRPFault (Base class for WS-ResourceProperties faults) Arc::WSRPResourcePropertyChangeFailure	343 344 346 349 351 353 354 357 359 361 392 394 401 403 405 406 407 409

Hosting Environment (Daemon) Data Structures	
Arc::XMLSecNode (Extends XMLNode (p. 409) class to support XML security operation)	4

12	Hosting Environment (Daemon) Data Structure Index

Hosting Environment (Daemon) File Index

4.1 Hosting Environment (Daemon) File List

Here is a list of all documented files with brief descriptions:

AlgFactory.h	??
AnyURIAttribute.h	??
ArcConfig.h	??
ARCJSDLParser.h	??
ArcLocation.h	??
ArcRegex.h	??
AttributeFactory.h	??
AttributeProxy.h	??
AttributeValue.h	??
Base64.h	??
SooleanAttribute.h	??
Broker.h	??
ByteArray.h	??
CertUtil.h	??
CheckSum.h	??
CIStringValue.h	??
ClassLoader.h	??
ClientInterface.h	??
ClientSAML2SSO.h	??
ClientX509Delegation.h	??
CombiningAlg.h	??
ConfusaCertHandler.h	??
ConfusaParserUtils.h	??
Counter.h	??
Credential.h	??
CredentialStore.h	??
OataBuffer.h	??
DataCallback.h	??
OataHandle.h	??
OataMover.h	??
OataPoint.h	??

D. 4. D. 2. 4D2 4 L	??
DataPointDirect.h	
DataPointIndex.h	
DataSpeed.h	??
DataStatus.h	??
DateTime.h	
DateTimeAttribute.h	
DBInterface.h	
DBranch.h	
DelegationInterface.h	
DenyOverridesAlg.h	??
EqualFunction.h	??
EvaluationCtx.h	
Evaluator.h	
EvaluatorLoader.h	
ExecutionTarget.h	
FileCache.h	
FileCacheHash.h	??
FileInfo.h	??
FileLock.h	??
FileUtils.h	
FinderLoader.h	
FnFactory.h	
Function.h	
GenericAttribute.h	
GlobusErrorUtils.h	??
GlobusWorkarounds.h	??
GSSCredential.h	
GUID.h	
HakaClient.h	
InfoCache.h	
InfoFilter.h	
InfoRegister.h	
InformationInterface.h	??
IniConfig.h	??
InRangeFunction.h	
IntraProcessCounter.h	
IString.h	
JDLParser.h	
Jobh	
JobController.h	
JobDescription.h	
JobDescriptionParser.h	??
JobState.h	??
JobSupervisor.h	??
listfunc.h	
Loader.h	
Logger.h	
MatchFunction.h	
MCC.h	
MCC_Status.h	??
MCCLoader.h	??
Message.h	
MessageAttributes.h	
MessageAuth.h	

ModuleManager.h	??
MysqlWrapper.h	
OAuthConsumer.h	??
OpenIdpClient.h	??
OpenSSL.h	??
OptionParser.h	??
OrderedAlg.h	??
PayloadRaw.h	??
PayloadSOAP.h	??
PayloadStream.h	
PayloadWSRF.h	
PDP.h	
PermitOverridesAlg.h	
Plexer.h	
Plugin.h	
e e e e e e e e e e e e e e e e e e e	
Policy.h	
PolicyParser.h	
PolicyStore.h	
Profile.h	
Proxycertinfo.h	
RegisteredService.h	
Request.h	
RequestAttribute.h	
RequestItem.h	
Response.h	??
Result.h	??
RSLParser.h	??
Run.h	??
SAML2LoginClient.h	??
saml_util.h	??
SAMLToken.h	??
SecAttr.h	??
SecAttrValue.h	??
SecHandler.h	??
Security.h	??
Service.h	??
SOAPEnvelope.h	??
SOAPMessage.h	22
Software.h	??
Source.h	??
	??
StringConv.h	??
S .	??
Submitter.h	??
TargetGenerator.h	
TargetRetriever.h	??
loader/TestMCC.h	??
message/TestMCC.h	??
TestService.h	??
Thread.h	??
URL.h (Class to hold general URL's)	425
URLMap.h	??
User.h	??
UserConfig.h	??
UsernameToken.h	??

Utils.h	??
VOMSAttribute.h	??
VOMSUtil.h	??
vin32.h	??
WSA.h	??
WSResourceProperties.h	??
WSRF.h	??
WSRFBaseFault.h	??
K500NameAttribute.h	??
K509Token.h	??
KmlContainer.h	??
KmlDatabase.h	??
KMLNode.h	??
XMLSecNode.h	??
KmlSecUtils.h	??
KRSLParser.h	??

Hosting Environment (Daemon) Namespace Documentation

5.1 Arc Namespace Reference

Some utility methods for using xml security library (http://www.aleksey.com/xmlsec/).

Data Structures

- · class ARCJSDLParser
- class Broker
- · class BrokerLoader
- class BrokerPluginArgument
- class ClientInterface

Utility base class for MCC (p. 227).

class ClientTCP

Class for setting up a MCC (p. 227) chain for TCP communication.

- struct HTTPClientInfo
- class ClientHTTP

Class for setting up a MCC (p. 227) chain for HTTP communication.

- class ClientSOAP
- class SecHandlerConfig
- class DNListHandlerConfig
- · class ARCPolicyHandlerConfig
- class ClientHTTPwithSAML2SSO
- class ClientSOAPwithSAML2SSO
- class ClientX509Delegation
- class ConfusaCertHandler
- class ConfusaParserUtils
- · class HakaClient
- · class OpenIdpClient
- class OAuthConsumer

- class SAML2LoginClient
- class SAML2SSOHTTPClient
- class ApplicationEnvironment

ApplicationEnvironment (p. 45).

• class ExecutionTarget

ExecutionTarget (p. 171).

- · class JDLParser
- · class Job

Job (p. 205).

· class JobController

Must be specialized for each supported middleware flavour.

- class JobControllerLoader
- class JobControllerPluginArgument
- · class Range
- class ScalableTime
- class ScalableTime< int >
- class JobIdentificationType
- class ExecutableType
- class NotificationType
- class ApplicationType
- class ResourceSlotType
- · class DiskSpaceRequirementType
- class ResourceTargetType
- class ResourcesType
- class DataSourceType
- class DataTargetType
- · class DataType
- class FileType
- class DirectoryType
- class DataStagingType
- class JobMetaType
- class JobDescription
- class JobDescriptionParser
- · class JobState
- class JobSupervisor

% JobSupervisor (p. 211) class

- class RSLValue
- class RSLLiteral
- · class RSLVariable
- class RSLConcat
- class RSLList
- class RSLSequence
- class RSL
- class RSLBoolean
- class RSLCondition

- class RSLParser
- class Software

Used to represent software (names and version) and comparison.

• class SoftwareRequirement

Class used to express and resolve version requirements on software.

class Submitter

Base class for the Submitters.

- class SubmitterLoader
- class SubmitterPluginArgument
- class TargetGenerator

Target generation class

class TargetRetriever

TargetRetriever base class

- class TargetRetrieverLoader
- class TargetRetrieverPluginArgument
- class XRSLParser
- class Config

Configuration element - represents (sub)tree of ARC configuration.

- class BaseConfig
- class ArcLocation

Determines ARC installation location.

• class RegularExpression

A regular expression class.

- class Base64
- class MemoryAllocationException
- class ByteArray
- class Counter

A class defining a common interface for counters.

• class CounterTicket

A class for "tickets" that correspond to counter reservations.

• class ExpirationReminder

A class intended for internal use within counters.

- · class Period
- class Time

A class for storing and manipulating times.

· class Database

Interface for calling database client library.

- · class Query
- · class DItem
- · class DBranch
- class DItemString
- · class FileLock

A general file locking class.

- class IniConfig
- class IntraProcessCounter

A class for counters used by threads within a single process.

- · class PrintFBase
- · class PrintF
- · class IString
- struct LoggerFormat
- · class LogMessage

A class for log messages.

• class LogDestination

A base class for log destinations.

· class LogStream

A class for logging to ostreams.

class LogFile

A class for logging to files.

· class Logger

A logger class.

- class MySQLDatabase
- · class MySQLQuery
- class OptionParser
- class Profile
- class Run
- class SimpleCondition

Simple triggered condition.

- class SimpleCounter
- · class ThreadRegistry
- class ThreadInitializer
- · class URL
- class URLLocation

Class to hold a resolved URL location.

· class PathIterator

Class to iterate through elements of path.

- class User
- class UserSwitch

- class initializeCredentialsType
- class UserConfig

User configuration class

• class AutoPointer

Wrapper for pointer with automatic destruction.

class CountedPointer

Wrapper for pointer with automatic destruction and mutiple references.

- · class NS
- · class XMLNode

Wrapper for LibXML library Tree interface.

- class XMLNodeContainer
- class CredentialError
- class Credential
- class VOMSTrustList
- class CredentialStore
- · class CheckSum

Defines interface for variuos checksum manipulations.

class CRC32Sum

Implementation of CRC32 checksum.

· class MD5Sum

Implementation of MD5 checksum.

class Adler32Sum

Implementation of Adler32 checksum.

· class CheckSumAny

Wraper for CheckSum (p. 65) class.

• class DataBuffer

Represents set of buffers.

- class DataCallback
- class DataHandle

This class is a wrapper around the DataPoint (p. 111) class.

- · class DataMover
- · class DataPoint

This base class is an abstraction of URL.

- · class DataPointLoader
- class DataPointPluginArgument
- class DataPointDirect

This is a kind of generalized file handle.

· class DataPointIndex

Complements DataPoint (p. 111) with attributes common for Indexing Service (p. 316) URLs.

· class DataSpeed

Keeps track of average and instantaneous transfer speed.

- class DataStatus
- struct CacheParameters
- class FileCache
- · class FileInfo

FileInfo (p. 183) stores information about files (metadata).

- class URLMap
- class XmlContainer
- class XmlDatabase
- class DelegationConsumer
- · class DelegationProvider
- class DelegationConsumerSOAP
- class DelegationProviderSOAP
- · class DelegationContainerSOAP
- · class GlobusResult
- · class GSSCredential
- class InfoCache

Stores XML document in filesystem split into parts.

- class InfoCacheInterface
- class InfoFilter

Filters information document according to identity of requestor.

· class InfoRegister

Registration to ISIS interface.

· class InfoRegisters

 $Hand ling\ multiple\ registrations\ to\ ISISes.$

- struct Register_Info_Type
- struct ISIS_description
- class InfoRegistrar

Registration process associated with particular ISIS.

- class InfoRegisterContainer
- class InformationInterface

Information System message processor.

• class InformationContainer

Information System document container and processor.

· class InformationRequest

Request for information in InfoSystem.

• class InformationResponse

Informational response from InfoSystem.

• class RegisteredService

RegisteredService (p. 291) - extension of Service (p. 316) performing self-registration.

- class FinderLoader
- · class Loader

Plugins loader.

• class LoadableModuleDesciption

· class ModuleManager

Manager of shared libraries.

· class Plugin

Base class for loadable ARC components.

• class PluginArgument

Base class for passing arguments to loadable ARC components.

• struct PluginDescriptor

Description of ARC lodable component.

class PluginDesc

Description of plugin.

· class ModuleDesc

Description of loadable module.

• class PluginsFactory

Generic ARC plugins loader.

• class MCCInterface

Interface for communication between MCC (p. 227), Service (p. 316) and Plexer (p. 277) objects.

• class MCC

Message (p. 238) Chain Component - base class for every MCC (p. 227) plugin.

- class MCCConfig
- class MCCPluginArgument
- class MCC_Status

A class for communication of MCC (p. 227) processing results.

class MCCLoader

Creator of Message (p. 238) Component Chains (MCC (p. 227)).

• class ChainContext

Interface to chain specific functionality.

· class MessagePayload

Base class for content of message passed through chain.

• class MessageContextElement

Top class for elements contained in message context.

• class MessageContext

Handler for content of message context.

• class MessageAuthContext

Handler for content of message auth* context.

· class Message

Object being passed through chain of MCCs.

• class AttributeIterator

A const iterator class for accessing multiple values of an attribute.

• class MessageAttributes

A class for storage of attribute values.

· class MessageAuth

Contains authencity information, authorization tokens and decisions.

· class PayloadRawInterface

Random Access Payload for Message (p. 238) objects.

• struct PayloadRawBuf

· class PayloadRaw

Raw byte multi-buffer.

· class PayloadSOAP

Payload of Message (p. 238) with SOAP content.

• class PayloadStreamInterface

Stream-like Payload for Message (p. 238) object.

class PayloadStream

POSIX handle as Payload.

class PlexerEntry

A pair of label (regex) and pointer to MCC (p. 227).

• class Plexer

The Plexer (p. 277) class, used for routing messages to services.

class CIStringValue

This class implements case insensitive strings as security attributes.

• class SecAttrValue

This is an abstract interface to a security attribute.

class SecAttrFormat

Export/import format.

· class SecAttr

This is an abstract interface to a security attribute.

class MultiSecAttr

Container of multiple SecAttr (p. 307) attributes.

· class Service

Service (p. 316) - last component in a Message (p. 238) Chain.

- class ServicePluginArgument
- class SOAPMessage

Message (p. 238) restricted to SOAP payload.

- · class ClassLoader
- class ClassLoaderPluginArgument
- class WSAEndpointReference

Interface for manipulation of WS-Adressing Endpoint Reference.

· class WSAHeader

Interface for manipulation WS-Addressing information in SOAP header.

· class SAMLToken

Class for manipulating SAML Token Profile.

• class UsernameToken

Interface for manipulation of WS-Security according to Username Token Profile.

• class X509Token

Class for manipulating X.509 Token Profile.

class PayloadWSRF

This class combines MessagePayload (p. 249) with WSRF (p. 399).

class WSRP

Base class for WS-ResourceProperties structures.

• class WSRPFault

Base class for WS-ResourceProperties faults.

- class WSRPInvalidResourcePropertyQNameFault
- class WSRPResourcePropertyChangeFailure
- class WSRPUnableToPutResourcePropertyDocumentFault
- class WSRPInvalidModificationFault
- $\bullet \ class \ WSRPU nable To Modify Resource Property Fault$
- class WSRPSetResourcePropertyRequestFailedFault
- $\bullet\ class\ WSRPInsertResource Properties RequestFailed Fault$

- class WSRPUpdateResourcePropertiesRequestFailedFault
- class WSRPDeleteResourcePropertiesRequestFailedFault
- class WSRPGetResourcePropertyDocumentRequest
- class WSRPGetResourcePropertyDocumentResponse
- class WSRPGetResourcePropertyRequest
- class WSRPGetResourcePropertyResponse
- class WSRPGetMultipleResourcePropertiesRequest
- class WSRPGetMultipleResourcePropertiesResponse
- class WSRPPutResourcePropertyDocumentRequest
- class WSRPPutResourcePropertyDocumentResponse
- class WSRPModifyResourceProperties
- class WSRPInsertResourceProperties
- class WSRPUpdateResourceProperties
- class WSRPDeleteResourceProperties
- class WSRPSetResourcePropertiesRequest
- $\bullet \ class \ WSRPS et Resource Properties Response$
- $\bullet \ class \ WSRPInsertResource Properties Request$
- $\bullet \ class \ WSRPInsertResource Properties Response$
- class WSRPUpdateResourcePropertiesRequest
- class WSRPUpdateResourcePropertiesResponse
- $\bullet \ class \ WSRPD eleteResource Properties Request$
- $\bullet \ class \ WSRPD eleteResource Properties Response$
- $\bullet \ class \ WSRPQueryResource Properties Request$
- class WSRPQueryResourcePropertiesResponse
- · class WSRF

Base class for every WSRF (p. 399) message.

• class WSRFBaseFault

Base class for WSRF (p. 399) fault messages.

- class WSRFResourceUnknownFault
- class WSRFResourceUnavailableFault
- · class XMLSecNode

Extends XMLNode (p. 409) class to support XML security operation.

Typedefs

- typedef Plugin *(*) get_plugin_instance (PluginArgument *arg)
- typedef std::multimap< std::string, std::string > AttrMap
- typedef AttrMap::const_iterator AttrConstIter
- typedef AttrMap::iterator AttrIter

Enumerations

- enum TimeFormat
- · enum LogLevel
- enum StatusKind { ,

STATUS_OK = 1, GENERIC_ERROR = 2, PARSING_ERROR = 4, PROTOCOL_-RECOGNIZED_ERROR = 8,

UNKNOWN SERVICE ERROR = 16, BUSY ERROR = 32, SESSION CLOSE = 64 }

• enum WSAFault { , WSAFaultUnknown, WSAFaultInvalidAddressingHeader }

Functions

- std::ostream & operator << (std::ostream &, const Period &)
- std::ostream & operator<< (std::ostream &, const Time &)
- std::string TimeStamp (const TimeFormat &=Time::GetFormat())
- std::string TimeStamp (Time, const TimeFormat &=Time::GetFormat())
- int FileOpen (const std::string &path, int flags, mode_t mode=0600)
- int FileOpen (const std::string &path, int flags, uid_t uid, gid_t gid, mode_t mode=0600)
- bool FileCopy (const std::string &source_path, const std::string &destination_path)
- bool FileCopy (const std::string &source_path, int destination_handle)
- bool FileCopy (int source_handle, const std::string &destination_path)
- bool FileCopy (int source handle, int destination handle)
- Glib::Dir * DirOpen (const std::string &path)
- Glib::Dir * DirOpen (const std::string &path, uid_t uid, gid_t gid)
- bool FileStat (const std::string &path, struct stat *st, bool follow_symlinks)
- bool FileStat (const std::string &path, struct stat *st, uid_t uid, gid_t gid, bool follow_symlinks)
- bool DirCreate (const std::string &path, mode_t mode, bool with_parents=false)
- bool DirCreate (const std::string &path, uid_t uid, gid_t gid, mode_t mode, bool with_parents=false)
- bool DirDelete (const std::string &path)
- bool DirDelete (const std::string &path, uid_t uid, gid_t gid)
- void GUID (std::string &guid)
- std::string UUID (void)
- std::ostream & operator<< (std::ostream &os, LogLevel level)
- LogLevel string_to_level (const std::string &str)
- bool istring_to_level (const std::string &llStr, LogLevel &ll)
- bool string_to_level (const std::string &str, LogLevel &ll)
- std::string level_to_string (const LogLevel &level)
- LogLevel old_level_to_level (unsigned int old_level)
- template<typename T> T stringto (const std::string &s)
- template<typename T> bool stringto (const std::string &s, T &t)
- template<typename T> std::string tostring (T t, const int width=0, const int precision=0)
- std::string lower (const std::string &s)
- std::string upper (const std::string &s)
- void tokenize (const std::string &str, std::vector< std::string > &tokens, const std::string &delimiters=" ")
- std::string trim (const std::string &str, const char *sep=NULL)
- std::string strip (const std::string &str)
- std::string uri_unescape (const std::string &str)
- std::string convert_to_rdn (const std::string &dn)
- bool CreateThreadFunction (void(*func)(void *), void *arg, SimpleCounter *count=NULL)
- std::list< URL > ReadURLList (const URL &urllist)
- std::string GetEnv (const std::string &var)
- std::string GetEnv (const std::string &var, bool &found)
- bool SetEnv (const std::string &var, const std::string &value, bool overwrite=true)
- void UnsetEnv (const std::string &var)
- std::string StrError (int errnum=errno)
- bool MatchXMLName (const XMLNode &node1, const XMLNode &node2)
- bool MatchXMLName (const XMLNode &node, const char *name)
- bool MatchXMLName (const XMLNode &node, const std::string &name)

- bool MatchXMLNamespace (const XMLNode &node1, const XMLNode &node2)
- bool MatchXMLNamespace (const XMLNode &node, const char *uri)
- bool MatchXMLNamespace (const XMLNode &node, const std::string &uri)
- bool createVOMSAC (std::string &codedac, Credential &issuer_cred, Credential &holder_cred, std::vector< std::string > &fqan, std::vector< std::string > &targets, std::vector< std::string > &attributes, std::string &voname, std::string &uri, int lifetime)
- bool addVOMSAC (ArcCredential::AC **&aclist, std::string &acorder, std::string &decodedac)
- bool parseVOMSAC (X509 *holder, const std::string &ca_cert_dir, const std::string &ca_cert_file, const VOMSTrustList &vomscert_trust_dn, std::vector < std::string > &output, bool verify=true)
- bool parseVOMSAC (const Credential &holder_cred, const std::string &ca_cert_dir, const std::string &ca_cert_file, const VOMSTrustList &vomscert_trust_dn, std::vector< std::string > &output, bool verify=true)
- char * VOMSDecode (const char *data, int size, int *j)
- const std::string get property (const Arc::Credential &u, const std::string property)
- bool OpenSSLInit (void)
- void HandleOpenSSLError (void)
- void HandleOpenSSLError (int code)
- std::string string (StatusKind kind)
- const char * ContentFromPayload (const MessagePayload &payload)
- void WSAFaultAssign (SOAPEnvelope &mesage, WSAFault fid)
- WSAFault WSAFaultExtract (SOAPEnvelope &message)
- int passphrase_callback (char *buf, int size, int rwflag, void *)
- bool init xmlsec (void)
- bool final_xmlsec (void)
- std::string get_cert_str (const char *certfile)
- xmlSecKey * get_key_from_keystr (const std::string &value)
- xmlSecKey * get_key_from_keyfile (const char *keyfile)
- std::string get_key_from_certfile (const char *certfile)
- $\bullet \ xmlSecKey* get_key_from_certstr \ (const \ std::string \ \&value)\\$
- xmlSecKeysMngrPtr load_key_from_keyfile (xmlSecKeysMngrPtr *keys_manager, const char *keyfile)
- xmlSecKeysMngrPtr load_key_from_certfile (xmlSecKeysMngrPtr *keys_manager, const char *certfile)
- xmlSecKeysMngrPtr load_key_from_certstr (xmlSecKeysMngrPtr *keys_manager, const std::string &certstr)
- xmlSecKeysMngrPtr load_trusted_cert_file (xmlSecKeysMngrPtr *keys_manager, const char *cert_file)
- $\bullet \ xmlSecKeysMngrPtr \ load_trusted_cert_str \ (xmlSecKeysMngrPtr \ *keys_manager, \ const \ std::string \&cert_str)$
- xmlSecKeysMngrPtr load_trusted_certs (xmlSecKeysMngrPtr *keys_manager, const char *cafile, const char *capath)
- XMLNode get_node (XMLNode &parent, const char *name)

Variables

- const Glib::TimeVal ETERNAL
- const Glib::TimeVal HISTORIC
- const size_t thread_stacksize = (16 * 1024 * 1024)
- Logger CredentialLogger
- const char * plugins table name

5.1.1 Detailed Description

Some utility methods for using xml security library (http://www.aleksey.com/xmlsec/).

ARCJSDLParser The ARCJSDLParser class, derived from the JobDescription-Parser class, is primarily a job description parser for the consolidated job description language (ARCJSDL), derived from JSDL, described in the following document http://svn.nordugrid.org/trac/nordugrid/browser/arc1/trunk/doc/tech_doc/client/job_description.odt. However it is also capable of parsing regular JSDL (GFD 136), the POSIX-JSDL extension (GFD 136) and the JSDL HPC Profile Application Extension (GFD 111 and GFD 114). When parsing ARCJSDL takes precedence over other non-ARCJSDL, so if a non-ARCJSDL element specifies the same attribute as ARCJSDL, the ARCJSDL element will be saved. The output generated by the ARCJSDLParser::UnParse method will follow that of the ARCJSDL document, see reference above.

5.1.2 Typedef Documentation

5.1.2.1 typedef Plugin*(*) Arc::get_plugin_instance(PluginArgument *arg)

Constructor function of ARC lodable component.

This function is called with plugin-specific argument and should produce and return valid instance of plugin. If plugin can't be produced by any reason (for example because passed argument is not applicable) then NULL is returned. No exceptions should be raised.

5.1.2.2 typedef std::multimap<std::string,std::string> Arc::AttrMap

A typefed of a multimap for storage of message attributes.

This typedef is used as a shorthand for a multimap that uses strings for keys as well as values. It is used within the MesssageAttributes class for internal storage of message attributes, but is not visible externally.

5.1.2.3 typedef AttrMap::const iterator Arc::AttrConstIter

A typedef of a const_iterator for AttrMap.

This typedef is used as a shorthand for a const_iterator for AttrMap. It is used extensively within the **MessageAttributes** (p.241) class as well as the AttributesIterator class, but is not visible externally.

5.1.2.4 typedef AttrMap::iterator Arc::AttrIter

A typedef of an (non-const) iterator for AttrMap.

This typedef is used as a shorthand for a (non-const) iterator for AttrMap. It is used in one method within the **MessageAttributes** (p.241) class, but is not visible externally.

5.1.3 Enumeration Type Documentation

5.1.3.1 enum Arc::TimeFormat

An enumeration that contains the possible textual timeformats.

5.1.3.2 enum Arc::LogLevel

Logging levels.

Logging levels for tagging and filtering log messages. FATAL level designates very severe error events that will presumably lead the application to abort. ERROR level designates error events that might still allow the application to continue running. WARNING level designates potentially harmful situations. INFO level designates informational messages that highlight the progress of the application at coarse-grained level. VERBOSE level designates fine-grained informational events that will give additional information about the application. DEBUG level designates finer-grained informational events which should only be used for debugging purposes.

5.1.3.3 enum Arc::StatusKind

Status kinds (types).

This enum defines a set of possible status kinds.

Enumerator:

STATUS OK Default status - undefined error.

GENERIC_ERROR No error.

PARSING_ERROR Error does not fit any class.

PROTOCOL_RECOGNIZED_ERROR Error detected while parsing request/response.

UNKNOWN_SERVICE_ERROR Message (p.238) does not fit into expected
 protocol.

BUSY_ERROR There is no destination configured for this message.

SESSION_CLOSE Message (p.238) can't be processed now.

5.1.3.4 enum Arc::WSAFault

WS-Addressing possible faults.

Enumerator:

WSAFaultUnknown This is not a fault

WSAFaultInvalidAddressingHeader This is not a WS-Addressing fault

5.1.4 Function Documentation

5.1.4.1 std::ostream& Arc::operator<< (std::ostream &, const Period &)

Prints a Period-object to the given ostream - typically cout.

5.1.4.2 std::ostream& Arc::operator<< (std::ostream &, const Time &)

Prints a Time-object to the given ostream - typically cout.

5.1.4.3 std::string Arc::TimeStamp (const TimeFormat & = Time::GetFormat())

Returns a time-stamp of the current time in some format.

5.1.4.4 std::string Arc::TimeStamp (Time, const TimeFormat & = Time::GetFormat())

Returns a time-stamp of some specified time in some format.

5.1.4.5 int Arc::FileOpen (const std::string & path, int flags, mode_t mode = 0600)

Open a file and return a file handle.

5.1.4.6 int Arc::FileOpen (const std::string & path, int flags, uid_t uid, gid_t gid, mode_t mode = 0600)

Open a file using the specified uid and gid and return a file handle.

5.1.4.7 bool Arc::FileCopy (const std::string & source_path, const std::string & destination_path)

Copy file source_path to file destination_path.

5.1.4.8 bool Arc::FileCopy (const std::string & source_path, int destination_handle)

Copy file source_path to file handle destination_handle.

5.1.4.9 bool Arc::FileCopy (int source_handle, const std::string & destination_path)

Copy from file handle source_handle to file handle destination_path.

5.1.4.10 bool Arc::FileCopy (int source_handle, int destination_handle)

Copy from file handle source_handle to file handle destination_handle.

5.1.4.11 Glib::Dir* Arc::DirOpen (const std::string & path)

Open a directory and return a pointer to a Dir object which can be iterated over.

5.1.4.12 Glib::Dir* Arc::DirOpen (const std::string & path, uid_t uid, gid_t gid)

Open a directory using the specified uid and gid and return a pointer to a Dir object which can be iterated over.

5.1.4.13 bool Arc::FileStat (const std::string & path, struct stat * st, bool follow_symlinks)

Stat a file and put info into the st struct.

5.1.4.14 bool Arc::FileStat (const std::string & path, struct stat * st, uid_t uid, gid_t gid, bool follow_symlinks)

Stat a file using the specified uid and gid and put info into the st struct.

5.1.4.15 bool Arc::DirCreate (const std::string & path, mode_t mode, bool with_parents = false)

Create a new directory.

5.1.4.16 bool Arc::DirCreate (const std::string & path, uid_t uid, gid_t gid, mode_t mode, bool with_parents = false)

Create a new directory using the specified uid and gid.

5.1.4.17 bool Arc::DirDelete (const std::string & path)

Delete a directory.

5.1.4.18 bool Arc::DirDelete (const std::string & path, uid_t uid, gid_t gid)

Delete a directory using the specified uid and gid.

5.1.4.19 void Arc::GUID (std::string & guid)

Generates a unique identifier using information such as IP address, current time etc.

5.1.4.20 std::string Arc::UUID (void)

Generates a unique identifier using the system uuid libraries.

5.1.4.21 std::ostream & Arc::operator << (std::ostream & os, LogLevel level)

Printing of LogLevel values to ostreams.

Output operator so that LogLevel values can be printed in a nicer way.

5.1.4.22 LogLevel Arc::string_to_level (const std::string & str)

Convert string to a LogLevel.

5.1.4.23 bool Arc::istring_to_level (const std::string & llStr, LogLevel & ll)

Case-insensitive parsing of a string to a LogLevel with error response.

The method will try to parse (case-insensitive) the argument string to a corresponding LogLevel. If the method suceeds, true will be returned and the argument 11 will be set to the parsed LogLevel. If the parsing fails false will be returned. The parsing succeeds if 11Str match (case-insensitively) one of the names of the LogLevel members.

Parameters:

```
llStr a string which should be parsed to a Arc::LogLevel (p.30).
```

ll a Arc::LogLevel (p.30) reference which will be set to the matching
Arc::LogLevel (p.30) upon successful parsing.

Returns:

true in case of successful parsing, otherwise false.

See also:

LogLevel (p. 30)

5.1.4.24 bool Arc::string_to_level (const std::string & str, LogLevel & ll)

Same as istring_to_level except it is case-sensitive.

5.1.4.25 std::string Arc::level_to_string (const LogLevel & level)

Convert LogLevel to a string.

5.1.4.26 LogLevel Arc::old_level_to_level (unsigned int *old_level*)

Convert an old-style log level (int from 0 to 5) to a LogLevel.

5.1.4.27 template<typename T> T Arc::stringto (const std::string & s)

This method converts a string to any type.

5.1.4.28 template<typename T> bool Arc::stringto (const std::string & s, T & t)

This method converts a string to any type but lets calling function process errors.

5.1.4.29 template<typename T> std::string Arc::tostring (T t, const int width = 0, const int precision = 0)

This method converts any type to a string of the width given.

5.1.4.30 std::string Arc::lower (const std::string & s)

This method converts to lower case of the string.

5.1.4.31 std::string Arc::upper (const std::string & s)

This method converts to upper case of the string.

5.1.4.32 void Arc::tokenize (const std::string & str, std::vector< std::string > & tokens, const std::string & delimiters = " ")

This method tokenizes string.

5.1.4.33 std::string Arc::trim (const std::string & str, const char * sep = NULL)

This method removes given separators from the beginning and the end of the string.

5.1.4.34 std::string Arc::strip (const std::string & str)

This method removes blank lines from the passed text string. Lines with only space on them are considered blank.

5.1.4.35 std::string Arc::uri_unescape (const std::string & str)

This method unescape the URI encoded string.

5.1.4.36 std::string Arc::convert_to_rdn (const std::string & dn)

Convert dn to rdn: /O=Grid/OU=Knowarc/CN=abc --> CN=abc,OU=Knowarc,O=Grid.

5.1.4.37 bool Arc::CreateThreadFunction (void(*)(void *) func, void * arg, SimpleCounter * count = NULL)

Helper function to create simple thread.

It takes care of all pecularities of Glib::Thread API. As result it runs function 'func' with argument 'arg' in a separate thread. If count parameter not NULL then corresponding object will be incremented before function returns and then decremented then thread finished. Returns true on success.

5.1.4.38 std::list<URL> Arc::ReadURLList (const URL & urllist)

Reads a list of URLs from a file.

5.1.4.39 std::string Arc::GetEnv (const std::string & var)

Portable function for getting environment variables.

5.1.4.40 std::string Arc::GetEnv (const std::string & var, bool & found)

Portable function for getting environment variables.

5.1.4.41 bool Arc::SetEnv (const std::string & var, const std::string & value, bool overwrite = true)

Portable function for setting environment variables.

5.1.4.42 void Arc::UnsetEnv (const std::string & var)

Portable function for unsetting environment variables.

5.1.4.43 std::string Arc::StrError (int errnum = errno)

Portable function for obtaining description of last system error.

5.1.4.44 bool Arc::MatchXMLName (const XMLNode & node1, const XMLNode & node2)

Returns true if underlying XML elements have same names

5.1.4.45 bool Arc::MatchXMLName (const XMLNode & node, const char * name)

Returns true if 'name' matches name of 'node'. If name contains prefix it's checked too

5.1.4.46 bool Arc::MatchXMLName (const XMLNode & node, const std::string & name)

Returns true if 'name' matches name of 'node'. If name contains prefix it's checked too

5.1.4.47 bool Arc::MatchXMLNamespace (const XMLNode & node1, const XMLNode & node2)

Returns true if underlying XML elements belong to same namespaces

5.1.4.48 bool Arc::MatchXMLNamespace (const XMLNode & node, const char * uri)

Returns true if 'namespace' matches 'node's namespace.

5.1.4.49 bool Arc::MatchXMLNamespace (const XMLNode & node, const std::string & uri)

Returns true if 'namespace' matches 'node's namespace.

5.1.4.50 bool Arc::createVOMSAC (std::string & codedac, Credential & issuer_cred, Credential & holder_cred, std::vector< std::string > & fqan, std::vector< std::string > & targets, std::vector< std::string > & attributes, std::string & voname, std::string & uri, int lifetime)

Create AC(Attribute Certificate) with voms specific format.

Parameters:

codedac The coded AC as output of this method

issuer_cred The issuer credential which is used to sign the AC
holder_cred The holder credential, the holder certificate is the one which
carries AC The rest arguments are the same as the above method

5.1.4.51 bool Arc::addVOMSAC (ArcCredential::AC **& aclist, std::string & acorder, std::string & decodedac)

Add decoded AC string into a list of AC objects

Parameters:

aclist The list of AC objects (output)
acorder The order of AC objects (output)
decodedac The AC string that is decoded from the string returned from voms
 server (input)

5.1.4.52 bool Arc::parseVOMSAC (X509 * holder, const std::string & ca_cert_dir, const std::string & ca_cert_file, const VOMSTrustList & vomscert_trust_dn, std::vector < std::string > & output, bool verify = true)

Parse the certificate, and output the attributes.

Parameters:

holder The proxy certificate which includes the voms specific formated AC.

 ${\it ca_cert_dir}$ The trusted certificates which are used to verify the certificate which is used to sign the AC

 ${\it ca_cert_file}$ The same as ca_cert_dir except it is a file instead of a directory. Only one of them need to be set

vomsdir The directory which include *.lsc file for each vo.
 For instance, a vo called "knowarc.eu" should have file
 \$prefix/vomsdir/knowarc/voms.knowarc.eu.lsc which contains on the
 first line the DN of the VOMS server, and on the second line the
 corresponding CA DN: /O=Grid/O=NorduGrid/OU=KnowARC/CN=voms.knowarc.eu
 /O=Grid/O=NorduGrid/CN=NorduGrid Certification Authority See more in:
 https://twiki.cern.ch/twiki/bin/view/LCG/VomsFAQforServiceManagers

output The parsed attributes (Role and Generic Attribute) . Each attribute
 is stored in element of a vector as a string. It is up to the consumer
 to understand the meaning of the attribute. There are two types of
 attributes stored in VOMS AC: AC_IETFATTR, AC_FULL_ATTRIBUTES. The AC_ IETFATTR will be like /Role=Employee/Group=Tester/Capability=NULL The AC_ FULL_ATTRIBUTES will be like knowarc:Degree=PhD (qualifier::name=value)
 In order to make the output attribute values be identical, the voms
 server information is added as prefix of the original attributes
 in AC. for AC_FULL_ATTRIBUTES, the voname + hostname is added:
 /voname=knowarc.eu/hostname=arthur.hep.lu.se:15001//knowarc.eu/coredev:attribute1=1
 for AC_IETFATTR, the 'VO' (voname) is added: /VO=knowarc.eu/Group=coredev/Role=NULL/Capability=NULL

some other redundant attributes is provided: voname=knowarc.eu/hostname=arthur.hep.lu.se:15001

Parameters:

verify true: Verify the voms certificate is trusted based on the ca_cert_ dir/ca_cert_file which specifies the CA certificates, and the vomscert_ trust_dn which specifies the trusted DN chain from voms server certificate
 to CA certificate.

false: Not verify, which means the issuer of AC (voms server certificate is supposed to be trusted by default). In this case the parameters 'ca_cert_dir', 'ca_cert_file' and 'vomscert_trust_dn' will not effect, and should be set as empty. This case is specifically used by 'arcproxy -info' to list all of the attributes in AC, and not to need to verify if the AC's issuer is trusted.

5.1.4.53 bool Arc::parseVOMSAC (const Credential & holder_cred, const std::string & ca_cert_dir, const std::string & ca_cert_file, const VOMSTrustList & vomscert_trust_dn, std::vector < std::string > & output, bool verify = true)

Parse the certificate. The same as the above one

5.1.4.54 char* Arc::VOMSDecode (const char * data, int size, int * j)

Decode the data which is encoded by voms server. Since voms code uses some specific coding method (not base64 encoding), we simply copy the method from voms code to here

5.1.4.55 const std::string Arc::get_property (const Arc::Credential & u, const std::string property)

Extract the needed field from the certificate

5.1.4.56 bool Arc::OpenSSLInit (void)

This function initializes OpenSSL library.

It may be called multiple times and makes sure everything is done properly and OpenSSL may be used in multi-threaded environment. Because this function makes use of $\bf ArcLocation$ (p. 46) it is advisable to call it after $\bf ArcLocation$::Init() (p. 46).

5.1.4.57 void Arc::HandleOpenSSLError (void)

Prints chain of accumulaed OpenSSL errors if any available.

5.1.4.58 void Arc::HandleOpenSSLError (int code)

Prints chain of accumulaed OpenSSL errors if any available.

5.1.4.59 std::string Arc::string (StatusKind kind)

Conversion to string.

Conversion from StatusKind to string.

Parameters:

kind The StatusKind to convert.

5.1.4.60 const char* Arc::ContentFromPayload (const MessagePayload & payload)

Returns pointer to main memory chunk of **Message** (p.238) payload.

If no buffer is present or if payload is not of **PayloadRawInterface** (p.262) type NULL is returned.

5.1.4.61 void Arc::WSAFaultAssign (SOAPEnvelope & mesage, WSAFault fid)

Makes WS-Addressing fault.

It fills SOAP Fault message with WS-Addressing fault related information.

5.1.4.62 WSAFault Arc::WSAFaultExtract (SOAPEnvelope & message)

Gets WS-addressing fault.

Analyzes SOAP Fault message and returns WS-Addressing fault it represents.

5.1.4.63 int Arc::passphrase_callback (char * buf, int size, int rwflag, void *)

callback method for inputing passphrase of key file

5.1.4.64 bool Arc::init_xmlsec (void)

Initialize the xml security library, it should be called before the xml security functionality is used.

5.1.4.65 bool Arc::final_xmlsec (void)

Finalize the xml security library

5.1.4.66 std::string Arc::get_cert_str (const char * certfile)

Get certificate in string format from certificate file

5.1.4.67 xmlSecKey* Arc::get_key_from_keystr (const std::string & value)

Get key in xmlSecKey structure from key in string format

5.1.4.68 xmlSecKey* Arc::get_key_from_keyfile (const char * keyfile)

Get key in xmlSecKey structure from key file

5.1.4.69 std::string Arc::get_key_from_certfile (const char * certfile)

Get public key in string format from certificate file

5.1.4.70 xmlSecKey* Arc::get_key_from_certstr (const std::string & value)

Get public key in xmlSecKey structure from certificate string (the string under "---BEGIN CERTIFICATE---" and "---END CERTIFICATE---")

5.1.4.71 xmlSecKeysMngrPtr Arc::load_key_from_keyfile (xmlSecKeysMngrPtr * keys_manager, const char * keyfile)

Load private or public key from a key file into key manager

5.1.4.72 xmlSecKeysMngrPtr Arc::load_key_from_certfile (xmlSecKeysMngrPtr * keys_manager, const char * certfile)

Load public key from a certificate file into key manager

5.1.4.73 xmlSecKeysMngrPtr Arc::load_key_from_certstr (xmlSecKeysMngrPtr * keys_manager, const std::string & certstr)

Load public key from a certificate string into key manager

5.1.4.74 xmlSecKeysMngrPtr Arc::load_trusted_cert_file (xmlSecKeysMngrPtr * keys_manager, const char * cert_file)

Load trusted certificate from certificate file into key manager

5.1.4.75 xmlSecKeysMngrPtr Arc::load_trusted_cert_str (xmlSecKeysMngrPtr * keys_manager, const std::string & cert_str)

Load trusted certificate from cetrtificate string into key manager

5.1.4.76 xmlSecKeysMngrPtr Arc::load_trusted_certs (xmlSecKeysMngrPtr * keys_manager, const char * cafile, const char * capath)

Load trusted cetificates from a file or directory into key manager

5.1.4.77 XMLNode Arc::get_node (XMLNode & parent, const char * name)

Generate a new child **XMLNode** (p. 409) with specified name

5.1.5 Variable Documentation

5.1.5.1 const Glib::TimeVal Arc::ETERNAL

A time very far in the future.

5.1.5.2 const Glib::TimeVal Arc::HISTORIC

A time very far in the past.

5.1.5.3 const size_t Arc::thread_stacksize = (16 * 1024 * 1024)

Defines size of stack assigned to every new thread.

So far it takes care of automatic initialization of threading environment and creation of simple detached threads. Always use it instead of glibmm/thread.h and keep among first includes. It safe to use it multiple times and to include it both from source files and other include files.

5.1.5.4 Logger Arc::CredentialLogger

Logger (p. 218) to be used by all modules of credentials library

5.1.5.5 const char* Arc::plugins_table_name

Name of symbol refering to table of plugins.

This C null terminated string specifies name of symbol which shared library should export to give an access to an array of PluginDescriptor (p.283) elements. The array is terminated by element with all components set to NULL.

5.2 ArcCredential Namespace Reference

Data Structures

- struct cert_verify_context
- struct PROXYPOLICY_st
- struct PROXYCERTINFO st
- struct **ACDIGEST**
- struct ACIS
- struct ACFORM
- struct ACACI
- struct **ACHOLDER**
- struct ACVAL
- struct ACIETFATTR
- struct ACTARGET
- struct **ACTARGETS**
- struct ACATTR
- struct ACINFO
- struct ACC
- struct ACSEQ
- struct **ACCERTS**
- struct **ACATTRIBUTE**
- struct **ACATTHOLDER**
- struct **ACFULLATTRIBUTES**

Enumerations

• enum certType {

CERT_TYPE_EEC, CERT_TYPE_CA, CERT_TYPE_GSI_3_IMPERSONATION_PROXY, CERT_TYPE_GSI_3_INDEPENDENT_PROXY,

CERT_TYPE_GSI_3_LIMITED_PROXY, CERT_TYPE_GSI_3_RESTRICTED_PROXY, CERT_TYPE_GSI_2_LIMITED_PROXY,

CERT_TYPE_RFC_IMPERSONATION_PROXY, CERT_TYPE_RFC_INDEPENDENT_-PROXY, CERT_TYPE_RFC_LIMITED_PROXY, CERT_TYPE_RFC_RESTRICTED_-PROXY,

CERT_TYPE_RFC_ANYLANGUAGE_PROXY }

5.2.1 Detailed Description

The code is derived from globus gsi, voms, and openssl-0.9.8e. The existing code for maintaining proxy certificates in OpenSSL only covers standard proxies and does not cover old Globus proxies, so here the Globus code is introduced.

5.2.2 Enumeration Type Documentation

5.2.2.1 enum ArcCredential::certType

Enumerator:

 $\ensuremath{\textit{CERT_TYPE_EEC}}$ A end entity certificate

- CERT_TYPE_CA A CA certificate

- CERT_TYPE_GSI_3_LIMITED_PROXY A X.509 Proxy Certificate Profile (pre-RFC)
 compliant limited proxy
- CERT_TYPE_GSI_3_RESTRICTED_PROXY A X.509 Proxy Certificate Profile
 (pre-RFC) compliant restricted proxy
- CERT_TYPE_GSI_2_PROXY A legacy Globus impersonation proxy
- CERT_TYPE_GSI_2_LIMITED_PROXY A legacy Globus limited impersonation proxy
- CERT_TYPE_RFC_IMPERSONATION_PROXY A X.509 Proxy Certificate Profile RFC
 compliant impersonation proxy; RFC inheritAll proxy
- CERT_TYPE_RFC_INDEPENDENT_PROXY A X.509 Proxy Certificate Profile RFC
 compliant independent proxy; RFC independent proxy
- CERT_TYPE_RFC_LIMITED_PROXY A X.509 Proxy Certificate Profile RFC
 compliant limited proxy
- CERT_TYPE_RFC_RESTRICTED_PROXY A X.509 Proxy Certificate Profile RFC
 compliant restricted proxy
- CERT_TYPE_RFC_ANYLANGUAGE_PROXY RFC anyLanguage proxy

Chapter 6


Hosting Environment (Daemon) Data Structure Documentation

6.1 Arc::Adler32Sum Class Reference

Implementation of Adler32 checksum.

#include <CheckSum.h>

Inheritance diagram for Arc::Adler32Sum::



6.1.1 Detailed Description

Implementation of Adler32 checksum.

The documentation for this class was generated from the following file:


• CheckSum.h

6.2 ArcSec::AlgFactory Class Reference

Interface for algorithm factory class.

#include <AlgFactory.h>

Inheritance diagram for ArcSec::AlgFactory::



Public Member Functions

virtual CombiningAlg * createAlg (const std::string &type)=0

6.2.1 Detailed Description

Interface for algorithm factory class.

AlgFactory (p.44) is in charge of creating **CombiningAlg** (p.74) according to the algorithm type given as argument of method createAlg. This class can be inherited for implementing a factory class which can create some specific combining algorithm objects.

6.2.2 Member Function Documentation

6.2.2.1 virtual CombiningAlg* ArcSec::AlgFactory::createAlg (const std::string & type) [pure virtual]

creat algorithm object based on the type algorithm type

Parameters:

type The type of combining algorithm

Returns:

The object of **CombiningAlg** (p.74)

The documentation for this class was generated from the following file:


· AlgFactory.h

6.3 Arc::ApplicationEnvironment Class Reference

ApplicationEnvironment (p. 45).

#include <ExecutionTarget.h>

Inheritance diagram for Arc::ApplicationEnvironment::



6.3.1 Detailed Description

ApplicationEnvironment (p. 45).

The ApplicationEnvironment is closely related to the definition given in GLUE2. By extending the **Software** (p.323) class the two GLUE2 attributes AppName and App-Version are mapped to two private members. However these can be obtained through the inheriated member methods getName and getVersion.

GLUE2 description: A description of installed application software or software environment characteristics available within one or more Execution Environments.

The documentation for this class was generated from the following file:

• ExecutionTarget.h

6.4 Arc::ArcLocation Class Reference

Determines ARC installation location.

#include <ArcLocation.h>

Static Public Member Functions

- static void Init (std::string path)
- static const std::string & Get ()
- static std::list< std::string > GetPlugins ()

6.4.1 Detailed Description

Determines ARC installation location.

6.4.2 Member Function Documentation

6.4.2.1 static const std::string& Arc::ArcLocation::Get () [static]

Returns ARC installation location.

6.4.2.2 static std::list<std::string> Arc::ArcLocation::GetPlugins () [static]

Returns ARC plugins directory location.

Main source is value of variable ARC_PLUGIN_PATH, otherwise path is derived from installation location.

6.4.2.3 static void Arc::ArcLocation::Init (std::string *path***)** [static]

Initializes location information.

Main source is value of variable ARC_LOCATION, otherwise path to executable provided in is used. If nothing works then warning message is sent to logger and initial installation prefix is used.

The documentation for this class was generated from the following file:

• ArcLocation.h

6.5 ArcSec::Attr Struct Reference

Attr (p.47) contains a tuple of attribute type and value. #include <Request.h>

6.5.1 Detailed Description


Attr (p. 47) contains a tuple of attribute type and value. The documentation for this struct was generated from the following file:

• Request.h

6.6 ArcSec::AttributeFactory Class Reference

#include <AttributeFactory.h>

Inheritance diagram for ArcSec::AttributeFactory::



6.6.1 Detailed Description

Base attribute factory class

The documentation for this class was generated from the following file:

• AttributeFactory.h

6.7 Arc::AttributeIterator Class Reference

A const iterator class for accessing multiple values of an attribute. #include <MessageAttributes.h>

Public Member Functions

- AttributeIterator ()
- const std::string & operator * () const
- const std::string * operator \rightarrow () const
- const std::string & key (void) const
- const AttributeIterator & operator++ ()
- AttributeIterator operator++ (int)
- bool hasMore () const

Protected Member Functions

• AttributeIterator (AttrConstIter begin, AttrConstIter end)

Protected Attributes

- · AttrConstIter current_
- AttrConstIter end_

Friends

· class MessageAttributes

6.7.1 Detailed Description

A const iterator class for accessing multiple values of an attribute.

This is an iterator class that is used when accessing multiple values of an attribute. The getAll() method of the **MessageAttributes** (p.241) class returns an **AttributeIterator** (p.49) object that can be used to access the values of the attribute.

```
Typical usage is:
    MessageAttributes attributes;
...
for (AttributeIterator iterator=attributes.getAll("Foo:Bar");
    iterator.hasMore(); ++iterator)
    std::cout << *iterator << std::endl;</pre>
```

6.7.2 Constructor & Destructor Documentation

6.7.2.1 Arc::AttributeIterator::AttributeIterator ()

Default constructor.

The default constructor. Does nothing since all attributes are instances of well-behaving STL classes.

6.7.2.2 Arc::AttributeIterator::AttributeIterator (AttrConstIter begin, AttrConstIter end) [protected]

Protected constructor used by the **MessageAttributes** (p. 241) class.

This constructor is used to create an iterator for iteration over all values of an attribute. It is not supposed to be visible externally, but is only used from within the getAll() method of **MessageAttributes** (p.241) class.

Parameters:

begin A const_iterator pointing to the first matching key-value pair in the
 internal multimap of the MessageAttributes (p.241) class.

end A const_iterator pointing to the first key-value pair in the internal
 multimap of the MessageAttributes (p.241) class where the key is larger
 than the key searched for.

6.7.3 Member Function Documentation

6.7.3.1 bool Arc::AttributeIterator::hasMore () const

Predicate method for iteration termination.

This method determines whether there are more values for the iterator to refer to.

Returns:

Returns true if there are more values, otherwise false.

6.7.3.2 const std::string& Arc::AttributeIterator::key (void) const

The key of attribute.

This method returns reference to key of attribute to which iterator refers.

$\textbf{6.7.3.3} \quad \textbf{const std::string\& Arc::AttributeIterator::operator} * () \ \textbf{const}$

The dereference operator.

This operator is used to access the current value referred to by the iterator.

Returns:

A (constant reference to a) string representation of the current value.

6.7.3.4 AttributeIterator Arc::AttributeIterator::operator++ (int)

The postfix advance operator.

Advances the iterator to the next value. Works intuitively.

Returns:

An iterator referring to the value referred to by this iterator before the advance.

6.7.3.5 const AttributeIterator& Arc::AttributeIterator::operator++ ()

The prefix advance operator.

Advances the iterator to the next value. Works intuitively.

Returns:

A const reference to this iterator.

6.7.3.6 const std::string* Arc::AttributeIterator::operator \rightarrow () const

The arrow operator.

Used to call methods for value objects (strings) conveniently.

6.7.4 Friends And Related Function Documentation

6.7.4.1 friend class MessageAttributes [friend]

The MessageAttributes (p. 241) class is a friend.

The constructor that creates an **AttributeIterator** (p. 49) that is connected to the internal multimap of the **MessageAttributes** (p. 241) class should not be exposed to the outside, but it still needs to be accessible from the getAll() method of the **MessageAttributes** (p. 241) class. Therefore, that class is a friend.

6.7.5 Field Documentation

6.7.5.1 AttrConstIter Arc::AttributeIterator::current_ [protected]

A const_iterator pointing to the current key-value pair.

This iterator is the internal representation of the current value. It points to the corresponding key-value pair in the internal multimap of the **Message-Attributes** (p. 241) class.

6.7.5.2 AttrConstIter Arc::AttributeIterator::end_ [protected]

A const_iterator pointing beyond the last key-value pair.

A const_iterator pointing to the first key-value pair in the internal multimap of the **MessageAttributes** (p.241) class where the key is larger than the key searched for.

The documentation for this class was generated from the following file:

• MessageAttributes.h

6.8 ArcSec::AttributeProxy Class Reference

Interface for creating the **AttributeValue** (p.53) object, it will be used by **AttributeFactory** (p.48).

#include <AttributeProxy.h>

Public Member Functions

• virtual AttributeValue * getAttribute (const Arc::XMLNode &node)=0

6.8.1 Detailed Description

Interface for creating the **AttributeValue** (p.53) object, it will be used by **AttributeFactory** (p.48).

The **AttributeProxy** (p.52) object will be insert into AttributeFactoty; and the getAttribute(node) method will be called inside AttributeFacroty.createvalue(node), in order to create a specific **AttributeValue** (p.53)

6.8.2 Member Function Documentation

6.8.2.1 virtual AttributeValue* ArcSec::AttributeProxy::getAttribute (const Arc::XMLNode & node) [pure virtual]

Create a **AttributeValue** (p.53) object according to the information inside the XMLNode as parameter.

The documentation for this class was generated from the following file:


• AttributeProxy.h

6.9 ArcSec::AttributeValue Class Reference

Interface for containing different type of <Attribute> node for both policy and request.

#include <AttributeValue.h>

Inheritance diagram for ArcSec::AttributeValue::



Public Member Functions

- virtual bool equal (AttributeValue *value, bool check_id=true)=0
- virtual std::string encode ()=0
- virtual std::string getType ()=0
- virtual std::string getId ()=0

6.9.1 Detailed Description

Interface for containing different type of <a tribute> node for both policy and request.

 contains different "Type" definition; Each type of needs different approach to compare the value. Any specific class which is for processing specific "Type" should inherit this class. The "Type" supported so far is: StringAttribute, DateAttribute, TimeAttribute (p. 357), DurationAttribute (p. 159), PeriodAttribute (p. 273), AnyURIAttribute, X500NameAttribute

6.9.2 Member Function Documentation

6.9.2.1 virtual std::string ArcSec::AttributeValue::encode () [pure virtual]

encode the value in a string format

Implemented in ArcSec::DateTimeAttribute (p. 145), ArcSec::TimeAttribute (p. 357), ArcSec::DurationAttribute (p. 159), and ArcSec::PeriodAttribute (p. 273).

6.9.2.2 virtual bool ArcSec::AttributeValue::equal (AttributeValue * *value***, bool** *check_id* **=** true) [pure virtual]

Evaluate whether "this" is equal to the parameter value

Implemented in ArcSec::DateTimeAttribute (p. 145), ArcSec::TimeAttribute (p. 357), ArcSec::DurationAttribute (p. 159), and ArcSec::PeriodAttribute (p. 273).

6.9.2.3 virtual std::string ArcSec::AttributeValue::getId () [pure virtual]

Get the AttributeId of the <Attribute>

Implemented in ArcSec::DateTimeAttribute (p. 145), ArcSec::TimeAttribute (p. 357), ArcSec::DurationAttribute (p. 159), and ArcSec::PeriodAttribute (p. 273).

6.9.2.4 virtual std::string ArcSec::AttributeValue::getType () [pure virtual]

Get the DataType of the <Attribute>

Implemented in ArcSec::DateTimeAttribute (p. 145), ArcSec::TimeAttribute (p. 357), ArcSec::DurationAttribute (p. 159), and ArcSec::PeriodAttribute (p. 273).

The documentation for this class was generated from the following file:

• AttributeValue.h

6.10 ArcSec::Attrs Class Reference

Attrs (p. 55) is a container for one or more Attr (p. 47).

#include <Request.h>

6.10.1 Detailed Description

Attrs (p. 55) is a container for one or more Attr (p. 47).

Attrs (p. 55) includes includes methonds for inserting, getting items, and counting size as well The documentation for this class was generated from the following file:

• Request.h

6.11 ArcSec::AuthzRequestSection Struct Reference

#include <PDP.h>

6.11.1 Detailed Description

These structure are based on the request schema for PDP (p. 272), so far it can apply to the ArcPDP's request schema, see src/hed/pdc/Request.xsd and src/hed/pdc/Request.xml. It could also apply to the XACMLPDP's request schema, since the difference is minor.

Another approach is, the service composes/marshalls the xml structure directly, then the service should use difference code to compose for ArcPDP's request schema and XACMLPDP's schema, which is not so good.

The documentation for this struct was generated from the following file:

• PDP.h

6.12 Arc::AutoPointer< T > Class Template Reference

Wrapper for pointer with automatic destruction.

#include <Utils.h>

Public Member Functions

- AutoPointer (void)
- AutoPointer (T *o)
- ∼AutoPointer (void)
- T & operator * (void) const
- $T * operator \rightarrow (void) const$
- · operator bool (void) const
- bool operator! (void) const
- operator T * (void) const

6.12.1 Detailed Description

template<typename T> class Arc::AutoPointer< T>

Wrapper for pointer with automatic destruction.

If ordinary pointer is wrapped in instance of this class it will be automatically destroyed when instance is destroyed. This is useful for maintaing pointers in scope of one function. Only pointers returned by new() are supported.

6.12.2 Constructor & Destructor Documentation

6.12.2.1 template<typename T> Arc::AutoPointer< T>::AutoPointer (void) [inline]

NULL pointer constructor.

6.12.2.2 template<**typename** T> Arc::AutoPointer< T>::AutoPointer (T * 0) [inline]

Constructor which wraps pointer.

6.12.2.3 template<typename T> Arc::AutoPointer< T>::~AutoPointer (void) [inline]

Destructor destroys wrapped object using delete().

6.12.3 Member Function Documentation

6.12.3.1 template<typename T> T& Arc::AutoPointer< T>::operator * (void) const [inline]

For refering wrapped object.

- **6.12.3.2** template<typename T> Arc::AutoPointer< T>::operator bool (void) const [inline]

 Returns false if pointer is NULL and true otherwise.
- $\textbf{6.12.3.3} \quad \textbf{template} < \textbf{typename } T > \textbf{Arc::AutoPointer} < T > \textbf{::operator } T * (\textbf{void}) \textbf{ const} \quad \texttt{[inline]}$ Cast to original pointer.
- $\textbf{6.12.3.5} \quad \textbf{template} < \textbf{typename} \ T > T * Arc:: AutoPointer < T > :: operator \rightarrow (void) \ const \quad \texttt{[inline]}$ For referring wrapped object.

The documentation for this class was generated from the following file:

• Utils.h

6.13 Arc::BaseConfig Class Reference

#include <ArcConfig.h>

Public Member Functions

- void AddPluginsPath (const std::string &path)
- void AddPrivateKey (const std::string &path)
- void AddCertificate (const std::string &path)
- void AddProxy (const std::string &path)
- void AddCAFile (const std::string &path)
- void AddCADir (const std::string &path)
- void AddOverlay (XMLNode cfg)
- void GetOverlay (std::string fname)
- virtual XMLNode MakeConfig (XMLNode cfg) const

6.13.1 Detailed Description

Configuration for client interface. It contains information which can't be expressed in class constructor arguments. Most probably common things like software installation location, identity of user, etc.

6.13.2 Member Function Documentation

6.13.2.1 void Arc::BaseConfig::AddCADir (const std::string & path)

Add CA directory

6.13.2.2 void Arc::BaseConfig::AddCAFile (const std::string & path)

Add CA file

6.13.2.3 void Arc::BaseConfig::AddCertificate (const std::string & path)

Add certificate

6.13.2.4 void Arc::BaseConfig::AddOverlay (XMLNode cfg)

Add configuration overlay

6.13.2.5 void Arc::BaseConfig::AddPluginsPath (const std::string & path)

Adds non-standard location of plugins

6.13.2.6 void Arc::BaseConfig::AddPrivateKey (const std::string & path)

Add private key

6.13.2.7 void Arc::BaseConfig::AddProxy (const std::string & path)

Add credentials proxy

6.13.2.8 void Arc::BaseConfig::GetOverlay (std::string fname)

Read overlay from file

6.13.2.9 virtual XMLNode Arc::BaseConfig::MakeConfig (XMLNode *cfg*) **const** [virtual]

Adds configuration part corresponding to stored information into common configuration tree supplied in 'cfg' argument. Returns reference to XML node representing configuration of Module-Manager (p. 251)


The documentation for this class was generated from the following file:

· ArcConfig.h

6.14 Arc::BrokerLoader Class Reference

#include <Broker.h>

Inheritance diagram for Arc::BrokerLoader::



Public Member Functions

- BrokerLoader ()
- ∼BrokerLoader ()
- Broker * load (const std::string &name, const UserConfig &usercfg)
- const std::list< Broker * > & GetBrokers () const

6.14.1 Detailed Description

Class responsible for loading Broker plugins The Broker objects returned by a BrokerLoader (p. 61) must not be used after the BrokerLoader (p. 61) goes out of scope.

6.14.2 Constructor & Destructor Documentation

6.14.2.1 Arc::BrokerLoader::BrokerLoader()

Constructor Creates a new BrokerLoader (p. 61).

6.14.2.2 Arc::BrokerLoader::~BrokerLoader ()

Destructor Calling the destructor destroys all Brokers loaded by the BrokerLoader (p. 61) instance.

6.14.3 Member Function Documentation

6.14.3.1 const std::list<Broker*>& Arc::BrokerLoader::GetBrokers () const [inline]

Retrieve the list of loaded Brokers.

Returns:

A reference to the list of Brokers.

6.14.3.2 Broker* Arc::BrokerLoader::load (const std::string & name, const UserConfig & usercfg)

Load a new Broker

Parameters:

name The name of the Broker to load.usercfg The UserConfig (p. 361) object for the new Broker.

Returns:

A pointer to the new Broker (NULL on error).

The documentation for this class was generated from the following file:

• Broker.h

6.15 Arc::CacheParameters Struct Reference

#include <FileCache.h>

6.15.1 Detailed Description

Contains data on the parameters of a cache.

The documentation for this struct was generated from the following file:

• FileCache.h

6.16 Arc::ChainContext Class Reference

Interface to chain specific functionality.

#include <MCCLoader.h>

Public Member Functions

• operator PluginsFactory * ()

6.16.1 Detailed Description

Interface to chain specific functionality.

Object of this class is associated with every MCCLoader (p. 235) object. It is accessible for MCC (p. 227) and Service (p. 316) components and provides an interface to manipulate chains stored in Loader (p. 212). This makes it possible to modify chains dynamically - like deploying new services on demand.

6.16.2 Member Function Documentation

6.16.2.1 Arc::ChainContext::operator PluginsFactory * () [inline]

Returns associated PluginsFactory (p. 284) object

The documentation for this class was generated from the following file:


· MCCLoader.h

6.17 Arc::CheckSum Class Reference

Defines interface for variuos checksum manipulations.

#include <CheckSum.h>

Inheritance diagram for Arc::CheckSum::



6.17.1 Detailed Description

Defines interface for variuos checksum manipulations.

This class is used during data transfers through DataBuffer (p. 98) class

The documentation for this class was generated from the following file:


· CheckSum.h

6.18 Arc::CheckSumAny Class Reference

Wraper for CheckSum (p. 65) class.

#include <CheckSum.h>

Inheritance diagram for Arc::CheckSumAny::



6.18.1 Detailed Description

Wraper for CheckSum (p. 65) class.

To be used for manipulation of any supported checksum type in a transparent way.

The documentation for this class was generated from the following file:


· CheckSum.h

6.19 Arc::CIStringValue Class Reference

This class implements case insensitive strings as security attributes.

#include <CIStringValue.h>

Inheritance diagram for Arc::CIStringValue::



Public Member Functions

- CIStringValue ()
- CIStringValue (const char *ss)
- CIStringValue (const std::string &ss)
- virtual operator bool ()

Protected Member Functions

• virtual bool equal (SecAttrValue &b)

6.19.1 Detailed Description

This class implements case insensitive strings as security attributes.

This is an example of how to inherit SecAttrValue (p. 311). The class is meant to implement security attributes that are case insensitive strings.

6.19.2 Constructor & Destructor Documentation

6.19.2.1 Arc::CIStringValue::CIStringValue()

Default constructor

6.19.2.2 Arc::CIStringValue::CIStringValue (const char * ss)

This is a constructor that takes a string litteral.

6.19.2.3 Arc::CIStringValue::CIStringValue (const std::string & ss)

This is a constructor that takes a string object.

6.19.3 Member Function Documentation

6.19.3.1 virtual bool Arc::CIStringValue::equal (SecAttrValue & b) [protected, virtual]

This function returns true if two strings are the same apart from letter case Reimplemented from Arc::SecAttrValue (p. 311).

6.19.3.2 virtual Arc::CIStringValue::operator bool () [virtual]

This function returns false if the string is empty or uninitialized

Reimplemented from Arc::SecAttrValue (p. 311).

The documentation for this class was generated from the following file:


• CIStringValue.h

6.20 Arc::ClientHTTP Class Reference

Class for setting up a MCC (p. 227) chain for HTTP communication.

#include <ClientInterface.h>

Inheritance diagram for Arc::ClientHTTP::



6.20.1 Detailed Description

Class for setting up a MCC (p. 227) chain for HTTP communication.

The ClientHTTP (p. 69) class inherits from the ClientTCP (p. 73) class and adds an HTTP MCC (p. 227) to the chain.

The documentation for this class was generated from the following file:


· ClientInterface.h

6.21 Arc::ClientInterface Class Reference

Utility base class for MCC (p. 227).

#include <ClientInterface.h>

Inheritance diagram for Arc::ClientInterface::



6.21.1 Detailed Description

Utility base class for MCC (p. 227).

The ClientInterface (p. 70) class is a utility base class used for configuring a client side Message (p. 238) Chain Component (MCC (p. 227)) chain and loading it into memory. It has several specializations of increasing complexity of the MCC (p. 227) chains.


The documentation for this class was generated from the following file:

• ClientInterface.h

6.22 Arc::ClientSOAP Class Reference

#include <ClientInterface.h>

Inheritance diagram for Arc::ClientSOAP::



Public Member Functions

- ClientSOAP ()
- MCC_Status process (PayloadSOAP *request, PayloadSOAP **response)
- MCC_Status process (const std::string &action, PayloadSOAP *request, PayloadSOAP *response)
- MCC * GetEntry ()
- void AddSecHandler (XMLNode handlercfg, const std::string &libanme="", const std::string &libpath="")
- virtual bool Load ()

6.22.1 Detailed Description

Class with easy interface for sending/receiving SOAP messages over HTTP(S/G). It takes care of configuring MCC (p. 227) chain and making an entry point.

6.22.2 Constructor & Destructor Documentation

6.22.2.1 Arc::ClientSOAP::ClientSOAP() [inline]

Constructor creates MCC (p. 227) chain and connects to server.

6.22.3 Member Function Documentation

6.22.3.1 void Arc::ClientSOAP::AddSecHandler (XMLNode *handlercfg*, const std::string & *libanme* = "", const std::string & *libpath* = "")

Adds security handler to configuration of SOAP MCC (p. 227)

Reimplemented from Arc::ClientHTTP (p. 69).

6.22.3.2 MCC* Arc::ClientSOAP::GetEntry () [inline]

Returns entry point to SOAP MCC (p. 227) in configured chain. To initialize entry point Load() (p. 72) method must be called.

Reimplemented from Arc::ClientHTTP (p. 69).

6.22.3.3 virtual bool Arc::ClientSOAP::Load () [virtual]

Instantiates pluggable elements according to generated configuration

Reimplemented from Arc::ClientHTTP (p. 69).

6.22.3.4 MCC_Status Arc::ClientSOAP::process (const std::string & action, PayloadSOAP * request, PayloadSOAP ** response)

Send SOAP request with specified SOAP action and receive response.

6.22.3.5 MCC_Status Arc::ClientSOAP::process (PayloadSOAP * request, PayloadSOAP ** response)

Send SOAP request and receive response.

The documentation for this class was generated from the following file:


· ClientInterface.h

6.23 Arc::ClientTCP Class Reference

Class for setting up a MCC (p. 227) chain for TCP communication.

#include <ClientInterface.h>

Inheritance diagram for Arc::ClientTCP::



6.23.1 Detailed Description

Class for setting up a MCC (p. 227) chain for TCP communication.

The ClientTCP (p. 73) class is a specialization of the ClientInterface (p. 70) which sets up a client MCC (p. 227) chain for TCP communication, and optionally with a security layer on top which can be either TLS, GSI or SSL3.

The documentation for this class was generated from the following file:


• ClientInterface.h

6.24 ArcSec::CombiningAlg Class Reference

Interface for combining algrithm.

#include <CombiningAlg.h>

Inheritance diagram for ArcSec::CombiningAlg::



Public Member Functions

- virtual Result combine (EvaluationCtx *ctx, std::list< Policy * > policies)=0
- virtual const std::string & getalgId (void) const =0

6.24.1 Detailed Description

Interface for combining algrithm.

This class is used to implement a specific combining algorithm for combining policies.

6.24.2 Member Function Documentation

6.24.2.1 virtual Result ArcSec::CombiningAlg::combine (EvaluationCtx * *ctx*, **std::list**< **Policy** * > *policies*) [pure virtual]

Evaluate request against policy, and if there are more than one policies, combine the evaluation results according to the combing algorithm implemented inside in the method combine(ctx, policies) itself.

Parameters:

ctx The information about request is included

policies The "match" and "eval" method inside each policy will be called, and then those results from each policy will be combined according to the combining algorithm inside Combing-Alg class.

Implemented in ArcSec::DenyOverridesCombiningAlg (p. 157), and ArcSec::PermitOverrides-CombiningAlg (p. 275).

6.24.2.2 virtual const std::string& ArcSec::CombiningAlg::getalgId (void) const [pure virtual]

Get the identifier of the combining algorithm class

Returns:

The identity of the algorithm

 $\label{lem:lemented} \begin{tabular}{ll} Implemented in $ArcSec::DenyOverrides CombiningAlg (p. 157), and $ArcSec::PermitOverrides CombiningAlg (p. 275). \end{tabular}$

The documentation for this class was generated from the following file:


• CombiningAlg.h

6.25 Arc::Config Class Reference

Configuration element - represents (sub)tree of ARC configuration.

#include <ArcConfig.h>

Inheritance diagram for Arc::Config::



Public Member Functions

- Config ()
- Config (const char *filename)
- Config (const std::string &xml_str)
- Config (XMLNode xml)
- Config (long cfg_ptr_addr)
- Config (const Config &cfg)
- void print (void)
- void parse (const char *filename)
- const std::string & getFileName (void) const
- void setFileName (const std::string &filename)
- void save (const char *filename)

6.25.1 Detailed Description

Configuration element - represents (sub)tree of ARC configuration.

This class is intended to be used to pass configuration details to various parts of HED and external modules. Currently it's just a wrapper over XML tree. But than may change in a future, although interface should be preserved. Currently it is capable of loading XML configuration document from file. In future it will be capable of loading more user-readable format and process it into tree-like structure convenient for machine processing (XML-like). So far there are no schema and/or namespaces assigned.

6.25.2 Constructor & Destructor Documentation

6.25.2.1 Arc::Config::Config() [inline]

Creates empty XML tree

6.25.2.2 Arc::Config::Config (const char * filename)

Loads configuration document from file 'filename'

6.25.2.3 Arc::Config::Config (const std::string & xml_str) [inline]

Parse configuration document from memory

6.25.2.4 Arc::Config::Config (XMLNode xml) [inline]

Acquire existing XML (sub)tree. Content is not copied. Make sure XML tree is not destroyed while in use by this object.

6.25.2.5 Arc::Config::Config (long cfg_ptr_addr)

Copy constructor used by language bindings

6.25.2.6 Arc::Config::Config (const Config & cfg)

Copy constructor used by language bindings

6.25.3 Member Function Documentation

6.25.3.1 const std::string& Arc::Config::getFileName (void) const [inline]

Gives back file name of config file or empty string if it was generared from the XMLNode (p.409) subtree

6.25.3.2 void Arc::Config::parse (const char * filename)

Parse configuration document from file 'filename'

6.25.3.3 void Arc::Config::print (void)

Print structure of document. For debuging purposes. Printed content is not an XML document.

6.25.3.4 void Arc::Config::save (const char * filename)

Save to file

6.25.3.5 void Arc::Config::setFileName (const std::string & filename) [inline]

Set the file name of config file

The documentation for this class was generated from the following file:

ArcConfig.h

6.26 Arc::ConfusaCertHandler Class Reference

#include <ConfusaCertHandler.h>

Public Member Functions

- ConfusaCertHandler (int keysize, const std::string dn)
- std::string getCertRequestB64 ()
- bool createCertRequest (std::string password="", std::string storedir="./")

6.26.1 Detailed Description

Wrapper around Credential handling the Confusa specifics.

6.26.2 Constructor & Destructor Documentation

6.26.2.1 Arc::ConfusaCertHandler::ConfusaCertHandler (int keysize, const std::string dn)

Create a new ConfusaCertHandler (p. 78) for DN dn and given keysize Basically Confusa cert handler wraps around Credential

6.26.3 Member Function Documentation

6.26.3.1 bool Arc::ConfusaCertHandler::createCertRequest (std::string *password* = "", std::string *storedir* = " . / ")

Create a new end entity certificate, with a private key encrypted with password password. Private key and certificate will be stored in directory storedir.

6.26.3.2 std::string Arc::ConfusaCertHandler::getCertRequestB64 ()

Get the certificate request managed by this confusa cert handler in base 64 encoding

The documentation for this class was generated from the following file:

· ConfusaCertHandler.h

6.27 Arc::ConfusaParserUtils Class Reference

#include <ConfusaParserUtils.h>

Static Public Member Functions

- static std::string urlencode (const std::string url)
- static std::string urlencode_params (const std::string url)
- static xmlDocPtr get_doc (const std::string xml_file)
- static void destroy_doc (xmlDocPtr doc)
- static std::string extract_body_information (const std::string html_string)
- static std::string handle_redirect_step (Arc::MCCConfig cfg, const std::string remote_url, std::string *cookies=NULL, std::multimap< std::string, std::string > *httpAttributes=NULL)
- static std::string evaluate_path (xmlDocPtr doc, const std::string xpathExpr, std::list< std::string > *contentList=NULL)

6.27.1 Detailed Description

Methods often needed in evaluation web pages from the Confusa WebSSO workflow

6.27.2 Member Function Documentation

6.27.2.1 static void Arc::ConfusaParserUtils::destroy_doc (xmlDocPtr *doc***)** [static]

Destroy a libxml2 doc representation

6.27.2.2 static std::string Arc::ConfusaParserUtils::evaluate_path (xmlDocPtr doc, const std::string xpathExpr, std::list< std::string > * contentList = NULL) [static]

Evaluate the given xPathExpr on the document ptr. Return a string with the FIRST result if content-List is NULL. Return a string with the first result and all results, including the first one, in contentList if contentList is not null.

6.27.2.3 static std::string Arc::ConfusaParserUtils::extract_body_information (const std::string html_string) [static]

Get the part only within <body> and </body> in a HTML string For parsing, usually only this part is interesting.

6.27.2.4 static xmlDocPtr Arc::ConfusaParserUtils::get_doc (const std::string xml_file) [static]

Construct a lixml2 doc representation from the xml file

6.27.2.5 static std::string Arc::ConfusaParserUtils::handle_redirect_step (Arc::MCCConfig cfg, const std::string remote_url, std::string * cookies = NULL, std::multimap < std::string, std::string > * httpAttributes = NULL) [static]

Handle a single redirect step from the SAML2 WebSSO profile. Store the received cookie in *cookie and pass the given httpAttributes to the site during redirect.

6.27.2.6 static std::string Arc::ConfusaParserUtils::urlencode (const std::string *url*) [static] **urlencode the passed string**

6.27.2.7 static std::string Arc::ConfusaParserUtils::urlencode_params (const std::string *url*) [static]

Urlencode the passed string with respect to the parameters. The difference to urlencode is that the parameters will keep their seperators, i.e. the ? and & separating parameters will be preserved.

The documentation for this class was generated from the following file:

· ConfusaParserUtils.h

6.28 Arc::CountedPointer< T > Class Template Reference

Wrapper for pointer with automatic destruction and mutiple references.

#include <Utils.h>

Public Member Functions

- T & operator * (void) const
- $T * operator \rightarrow (void) const$
- operator bool (void) const
- bool operator! (void) const
- operator T * (void) const

Data Structures

· class Base

6.28.1 Detailed Description

template<typename T> class Arc::CountedPointer< T>

Wrapper for pointer with automatic destruction and mutiple references.

If ordinary pointer is wrapped in instance of this class it will be automatically destroyed when all instances refering to it are destroyed. This is useful for maintaing pointers refered from multiple structures with automatic destruction of original object when last reference is destroyed. It is similar to Java approach with a difference that descruction time is strictly defined. Only pointers returned by new() are supported. This class is not thread-safe

6.28.2 Member Function Documentation

6.28.2.1 template<typename T> T& Arc::CountedPointer< T>::operator * (void) const [inline]

For refering wrapped object.

 $\textbf{6.28.2.2} \quad template < typename \ T > Arc:: Counted Pointer < T > :: operator \ bool \ (void) \ const \\ \texttt{[inline]}$

Returns false if pointer is NULL and true otherwise.

6.28.2.3 template<typename T> Arc::CountedPointer< T>::operator T*(void) const [inline]

Cast to original pointer.

 $\textbf{6.28.2.4} \quad template < typename \ T > bool \ Arc:: Counted Pointer < T > ::operator! \ (void) \ const \\ \textit{[inline]}$

Returns true if pointer is NULL and false otherwise.

 $\textbf{6.28.2.5} \quad template < typename \ T > T*\ Arc:: Counted Pointer < T > :: operator \rightarrow (void)\ const$ $[\verb|inline||$

For refering wrapped object.

The documentation for this class was generated from the following file:


• Utils.h

6.29 Arc::Counter Class Reference

A class defining a common interface for counters.

#include <Counter.h>

Inheritance diagram for Arc::Counter::



Public Member Functions

- virtual ∼Counter ()
- virtual int getLimit ()=0
- virtual int setLimit (int newLimit)=0
- virtual int changeLimit (int amount)=0
- virtual int getExcess ()=0
- virtual int setExcess (int newExcess)=0
- virtual int changeExcess (int amount)=0
- virtual int getValue ()=0
- virtual CounterTicket reserve (int amount=1, Glib::TimeVal duration=ETERNAL, bool prioritized=false, Glib::TimeVal timeOut=ETERNAL)=0

Protected Types

• typedef unsigned long long int IDType

Protected Member Functions

- Counter ()
- virtual void cancel (IDType reservationID)=0
- \bullet virtual void extend (IDType &reservationID, Glib::TimeVal &expiryTime, Glib::TimeVal duration=ETERNAL)=0
- Glib::TimeVal getCurrentTime ()
- Glib::TimeVal getExpiryTime (Glib::TimeVal duration)
- $\hbox{$\bullet$ CounterTicket getCounterTicket (Counter::IDType reservationID, Glib::TimeVal expiry-time, Counter* (Counter*) }$
- ExpirationReminder getExpirationReminder (Glib::TimeVal expTime, Counter::IDType res-ID)

Friends

- · class CounterTicket
- class ExpirationReminder

6.29.1 Detailed Description

A class defining a common interface for counters.

This class defines a common interface for counters as well as some common functionality.

The purpose of a counter is to provide housekeeping some resource such as e.g. disk space, memory or network bandwidth. The counter itself will not be aware of what kind of resource it limits the use of. Neither will it be aware of what unit is being used to measure that resource. Counters are thus very similar to semaphores. Furthermore, counters are designed to handle concurrent operations from multiple threads/processes in a consistent manner.

Every counter has a limit, an excess limit and a value. The limit is a number that specify how many units are available for reservation. The value is the number of units that are currently available for reservation, i.e. has not allready been reserved. The excess limit specify how many extra units can be reserved for high priority needs even if there are no normal units available for reservation. The excess limit is similar to the credit limit of e.g. a VISA card.

The users of the resource must thus first call the counter in order to make a reservation of an appropriate amount of the resource, then allocate and use the resource and finally call the counter again to cancel the reservation.

Typical usage is:

```
// Declare a counter. Replace XYZ by some appropriate kind of
// counter and provide required parameters. Unit is MB.
XYZCounter memory(...);
...
// Make a reservation of memory for 2000000 doubles.
CounterTicket tick = memory.reserve(2*sizeof(double));
// Use the memory.
double* A=new double[2000000];
doSomething(A);
delete[] A;
// Cancel the reservation.
tick.cancel();
```

There are also alternative ways to make reservations, including self-expiring reservations, prioritized reservations and reservations that fail if they cannot be made fast enough.

For self expiring reservations, a duration is provided in the reserve call:

```
tick = memory.reserve(2*sizeof(double), Glib::TimeVal(1,0));
```

A self-expiring reservation can be cancelled explicitly before it expires, but if it is not cancelled it will expire automatically when the duration has passed. The default value for the duration is ETERNAL, which means that the reservation will not be cancelled automatically.

Prioritized reservations may use the excess limit and succeed immediately even if there are no normal units available for reservation. The value of the counter will in this case become negative. A prioritized reservation looks like this:

```
tick = memory.reserve(2*sizeof(double), Glib::TimeVal(1,0), true);
```

Finally, a time out option can be provided for a reservation. If some task should be performed within two seconds or not at all, the reservation can look like this:

6.29.2 Member Typedef Documentation

6.29.2.1 typedef unsigned long long int Arc::Counter::IDType [protected]

A typedef of identification numbers for reservation.

This is a type that is used as identification numbers (keys) for referencing of reservations. It is used internally in counters for book keeping of reservations as well as in the CounterTicket (p. 90) class in order to be able to cancel and extend reservations.

6.29.3 Constructor & Destructor Documentation

6.29.3.1 Arc::Counter::Counter() [protected]

Default constructor.

This is the default constructor. Since Counter (p. 83) is an abstract class, it should only be used by subclasses. Therefore it is protected. Furthermore, since the Counter (p. 83) class has no attributes, nothing needs to be initialized and thus this constructor is empty.

6.29.3.2 virtual Arc::Counter::~Counter() [virtual]

The destructor.

This is the destructor of the Counter (p. 83) class. Since the Counter (p. 83) class has no attributes, nothing needs to be cleaned up and thus the destructor is empty.

6.29.4 Member Function Documentation

6.29.4.1 virtual void Arc::Counter::cancel (IDType *reservationID*) [protected, pure virtual]

Cancellation of a reservation.

This method cancels a reservation. It is called by the CounterTicket (p. 90) that corresponds to the reservation.

Parameters:

reservationID The identity number (key) of the reservation to cancel.

6.29.4.2 virtual int Arc::Counter::changeExcess (int *amount***)** [pure virtual]

Changes the excess limit of the counter.

Changes the excess limit of the counter by adding a certain amount to the current excess limit.

Parameters:

amount The amount by which to change the excess limit.

Returns:

The new excess limit.

Implemented in Arc::IntraProcessCounter (p. 201).

6.29.4.3 virtual int Arc::Counter::changeLimit (int amount) [pure virtual]

Changes the limit of the counter.

Changes the limit of the counter by adding a certain amount to the current limit.

Parameters:

amount The amount by which to change the limit.

Returns:

The new limit.

Implemented in Arc::IntraProcessCounter (p. 201).

6.29.4.4 virtual void Arc::Counter::extend (IDType & reservationID, Glib::TimeVal & expiryTime, Glib::TimeVal duration = ETERNAL) [protected, pure virtual]

Extension of a reservation.

This method extends a reservation. It is called by the CounterTicket (p. 90) that corresponds to the reservation.

Parameters:

reservationID Used for input as well as output. Contains the identification number of the original reservation on entry and the new identification number of the extended reservation on exit.

expiryTime Used for input as well as output. Contains the expiry time of the original reservation on entry and the new expiry time of the extended reservation on exit.

duration The time by which to extend the reservation. The new expiration time is computed based on the current time, NOT the previous expiration time.

6.29.4.5 CounterTicket Arc::Counter::getCounterTicket (Counter::IDType reservationID, Glib::TimeVal expiryTime, Counter * counter) [protected]

A "relay method" for a constructor of the CounterTicket (p. 90) class.

This method acts as a relay for one of the constructors of the CounterTicket (p. 90) class. That constructor is private, but needs to be accessible from the subclasses of Counter (p. 83) (bot not from anywhere else). In order not to have to declare every possible subclass of Counter (p. 83) as a friend of CounterTicket (p. 90), only the base class Counter (p. 83) is a friend and its subclasses access the constructor through this method. (If C++ had supported "package access", as Java does, this trick would not have been necessary.)

Parameters:

reservationID The identity number of the reservation corresponding to the CounterTicket (p. 90).

expiryTime the expiry time of the reservation corresponding to the CounterTicket (p. 90). *counter* The Counter (p. 83) from which the reservation has been made.

Returns:

The counter ticket that has been created.

6.29.4.6 Glib::TimeVal Arc::Counter::getCurrentTime() [protected]

Get the current time.

Returns the current time. An "adapter method" for the assign_current_time() method in the Glib::TimeVal class. return The current time.

6.29.4.7 virtual int Arc::Counter::getExcess () [pure virtual]

Returns the excess limit of the counter.

Returns the excess limit of the counter, i.e. by how much the usual limit may be exceeded by prioritized reservations.

Returns:

The excess limit.

Implemented in Arc::IntraProcessCounter (p. 202).

6.29.4.8 ExpirationReminder Arc::Counter::getExpirationReminder (Glib::TimeVal expTime, Counter::IDType resID) [protected]

A "relay method" for the constructor of ExpirationReminder (p. 174).

This method acts as a relay for one of the constructors of the ExpirationReminder (p. 174) class. That constructor is private, but needs to be accessible from the subclasses of Counter (p. 83) (bot not from anywhere else). In order not to have to declare every possible subclass of Counter (p. 83) as a friend of ExpirationReminder (p. 174), only the base class Counter (p. 83) is a friend and its subclasses access the constructor through this method. (If C++ had supported "package access", as Java does, this trick would not have been necessary.)

Parameters:

expTime the expiry time of the reservation corresponding to the ExpirationReminder (p. 174). *resID* The identity number of the reservation corresponding to the ExpirationReminder (p. 174).

Returns:

The ExpirationReminder (p. 174) that has been created.

6.29.4.9 Glib::TimeVal Arc::Counter::getExpiryTime (Glib::TimeVal *duration*) [protected]

Computes an expiry time.

This method computes an expiry time by adding a duration to the current time.

Parameters:

duration The duration.

Returns:

The expiry time.

6.29.4.10 virtual int Arc::Counter::getLimit() [pure virtual]

Returns the current limit of the counter.

This method returns the current limit of the counter, i.e. how many units can be reserved simultaneously by different threads without claiming high priority.

Returns:

The current limit of the counter.

Implemented in Arc::IntraProcessCounter (p. 202).

6.29.4.11 virtual int Arc::Counter::getValue () [pure virtual]

Returns the current value of the counter.

Returns the current value of the counter, i.e. the number of unreserved units. Initially, the value is equal to the limit of the counter. When a reservation is made, the the value is decreased. Normally, the value should never be negative, but this may happen if there are prioritized reservations. It can also happen if the limit is decreased after some reservations have been made, since reservations are never revoked.

Returns:

The current value of the counter.

Implemented in Arc::IntraProcessCounter (p. 202).

6.29.4.12 virtual CounterTicket Arc::Counter::reserve (int amount = 1, Glib::TimeVal duration = ETERNAL, bool prioritized = false, Glib::TimeVal timeOut = ETERNAL) [pure virtual]

Makes a reservation from the counter.

This method makes a reservation from the counter. If the current value of the counter is too low to allow for the reservation, the method blocks until the reservation is possible or times out.

Parameters:

amount The amount to reserve, default value is 1.

duration The duration of a self expiring reservation, default is that it lasts forever.

prioritized Whether this reservation is prioritized and thus allowed to use the excess limit.

timeOut The maximum time to block if the value of the counter is too low, default is to allow "eternal" blocking.

Returns:

A CounterTicket (p. 90) that can be queried about the status of the reservation as well as for cancellations and extensions.

Implemented in Arc::IntraProcessCounter (p. 203).

6.29.4.13 virtual int Arc::Counter::setExcess (int *newExcess***)** [pure virtual]

Sets the excess limit of the counter.

This method sets a new excess limit for the counter.

Parameters:

newExcess The new excess limit, an absolute number.

Returns:

The new excess limit.

Implemented in Arc::IntraProcessCounter (p. 203).

6.29.4.14 virtual int Arc::Counter::setLimit (int newLimit) [pure virtual]

Sets the limit of the counter.

This method sets a new limit for the counter.

Parameters:

newLimit The new limit, an absolute number.

Returns:

The new limit.

Implemented in Arc::IntraProcessCounter (p. 203).

6.29.5 Friends And Related Function Documentation

6.29.5.1 friend class CounterTicket [friend]

The CounterTicket (p. 90) class needs to be a friend.

6.29.5.2 friend class ExpirationReminder [friend]

The ExpirationReminder (p. 174) class needs to be a friend.

The documentation for this class was generated from the following file:

• Counter.h

6.30 Arc::CounterTicket Class Reference

A class for "tickets" that correspond to counter reservations.

```
#include <Counter.h>
```

Public Member Functions

- CounterTicket ()
- bool isValid ()
- void extend (Glib::TimeVal duration)
- void cancel ()

Friends

· class Counter

6.30.1 Detailed Description

A class for "tickets" that correspond to counter reservations.

This is a class for reservation tickets. When a reservation is made from a Counter (p. 83), a ReservationTicket is returned. This ticket can then be queried about the validity of a reservation. It can also be used for cancelation and extension of reservations.

Typical usage is:

```
// Declare a counter. Replace XYZ by some appropriate kind of
// counter and provide required parameters. Unit is MB.
XYZCounter memory(...);
...
// Make a reservation of memory for 2000000 doubles.
CounterTicket tick = memory.reserve(2*sizeof(double));
// Use the memory.
double* A=new double[2000000];
doSomething(A);
delete[] A;
// Cancel the reservation.
tick.cancel();
```

6.30.2 Constructor & Destructor Documentation

6.30.2.1 Arc::CounterTicket::CounterTicket()

The default constructor.

This is the default constructor. It creates a CounterTicket (p. 90) that is not valid. The ticket object that is created can later be assigned a ticket that is returned by the reserve() method of a Counter (p. 83).

6.30.3 Member Function Documentation

6.30.3.1 void Arc::CounterTicket::cancel ()

Cancels a resrvation.

This method is called to cancel a reservation. It may be called also for self-expiring reservations, which will then be cancelled before they were originally planned to expire.

6.30.3.2 void Arc::CounterTicket::extend (Glib::TimeVal duration)

Extends a reservation.

Extends a self-expiring reservation. In order to succeed the extension should be made before the previous reservation expires.

Parameters:

duration The time by which to extend the reservation. The new expiration time is computed based on the current time, NOT the previous expiration time.

6.30.3.3 bool Arc::CounterTicket::isValid ()

Returns the validity of a CounterTicket (p. 90).

This method checks whether a CounterTicket (p. 90) is valid. The ticket was probably returned earlier by the reserve() method of a Counter (p. 83) but the corresponding reservation may have expired.

Returns:

The validity of the ticket.

6.30.4 Friends And Related Function Documentation

6.30.4.1 friend class Counter [friend]

The Counter (p. 83) class needs to be a friend.

The documentation for this class was generated from the following file:


· Counter.h

6.31 Arc::CRC32Sum Class Reference

Implementation of CRC32 checksum.

#include <CheckSum.h>

Inheritance diagram for Arc::CRC32Sum::



6.31.1 Detailed Description

Implementation of CRC32 checksum.

The documentation for this class was generated from the following file:

• CheckSum.h

6.32 Arc::CredentialError Class Reference

#include <Credential.h>

Public Member Functions

• CredentialError (const std::string &what="")

6.32.1 Detailed Description

This is an exception class that is used to handle runtime errors discovered in the Credential class.

6.32.2 Constructor & Destructor Documentation

6.32.2.1 Arc::CredentialError::CredentialError (const std::string & what = "")

This is the constructor of the CredentialError (p. 93) class.

Parameters:

what An explanation of the error.

The documentation for this class was generated from the following file:

• Credential.h

6.33 Arc::CredentialStore Class Reference

#include <CredentialStore.h>

6.33.1 Detailed Description

This class provides functionality for storing delegated crdentials and retrieving them from some store services. This is very preliminary implementation and currently support only one type of credentials - X.509 proxies, and only one type of store service - MyProxy. Later it will be extended to support at least following services: ARC delegation service, VOMS service, local file system.

The documentation for this class was generated from the following file:


· CredentialStore.h

6.34 Arc::Database Class Reference

Interface for calling database client library.

#include <DBInterface.h>

Inheritance diagram for Arc::Database::



Public Member Functions

- Database ()
- Database (std::string &server, int port)
- Database (const Database &other)
- virtual ∼Database ()
- virtual bool connect (std::string &dbname, std::string &user, std::string &password)=0
- virtual bool isconnected () const =0
- virtual void close ()=0
- virtual bool enable_ssl (const std::string keyfile="", const std::string certfile="", const std::string capile="")=0
- virtual bool shutdown ()=0

6.34.1 Detailed Description

Interface for calling database client library.

For different types of database client library, different classes should be implemented by implementing this interface.

6.34.2 Constructor & Destructor Documentation

6.34.2.1 Arc::Database::Database() [inline]

Default constructor

6.34.2.2 Arc::Database::Database (std::string & server, int port) [inline]

Constructor which uses the server's name(or IP address) and port as parametes

6.34.2.3 Arc::Database::Database (const Database & other) [inline]

Copy constructor

```
6.34.2.4 virtual Arc::Database::~Database() [inline, virtual]
```

Deconstructor

6.34.3 Member Function Documentation

```
6.34.3.1 virtual void Arc::Database::close () [pure virtual]
```

Close the connection with database server

Implemented in Arc::MySQLDatabase (p. 254).

6.34.3.2 virtual bool Arc::Database::connect (std::string & dbname, std::string & user, std::string & password) [pure virtual]

Do connection with database server

Parameters:

```
dbname The database name which will be used.

user The username which will be used to access database.

password The password which will be used to access database.
```

Implemented in Arc::MySQLDatabase (p. 254).

```
6.34.3.3 virtual bool Arc::Database::enable_ssl (const std::string keyfile = "", const std::string cafile = "", const std::string capath = "") [pure virtual]
```

Enable ssl communication for the connection

Parameters:

```
keyfile The location of key file.

certfile The location of certificate file.

cafile The location of ca file.

capath The location of ca directory
```

Implemented in Arc::MySQLDatabase (p. 255).

```
6.34.3.4 virtual bool Arc::Database::isconnected () const [pure virtual]
```

Get the connection status

Implemented in Arc::MySQLDatabase (p. 255).

6.34.3.5 virtual bool Arc::Database::shutdown () [pure virtual]

Ask database server to shutdown

Implemented in Arc::MySQLDatabase (p. 255).

The documentation for this class was generated from the following file:

6 34	A rc.	·Dataha	se Class	Referer	1CE

97

• DBInterface.h

6.35 Arc::DataBuffer Class Reference

Represents set of buffers.

#include <DataBuffer.h>

Public Member Functions

- operator bool () const
- DataBuffer (unsigned int size=65536, int blocks=3)
- DataBuffer (CheckSum *cksum, unsigned int size=65536, int blocks=3)
- ∼DataBuffer ()
- bool set (CheckSum *cksum=NULL, unsigned int size=65536, int blocks=3)
- int add (CheckSum *cksum)
- char * operator[] (int n)
- bool for_read (int &handle, unsigned int &length, bool wait)
- bool for_read ()
- bool is_read (int handle, unsigned int length, unsigned long long int offset)
- bool is_read (char *buf, unsigned int length, unsigned long long int offset)
- bool for_write (int &handle, unsigned int &length, unsigned long long int &offset, bool wait)
- bool for_write ()
- bool is_written (int handle)
- bool is written (char *buf)
- bool is_notwritten (int handle)
- bool is_notwritten (char *buf)
- void eof_read (bool v)
- void eof_write (bool v)
- void error_read (bool v)
- void error_write (bool v)
- bool eof_read ()
- bool eof_write ()
- bool error_read ()
- bool error_write ()
- bool error_transfer ()
- bool error ()
- bool wait_any ()
- bool wait_used ()
- bool checksum_valid () const
- const CheckSum * checksum_object () const
- bool wait_eof_read ()
- bool wait_read ()
- bool wait_eof_write ()
- bool wait_write ()
- bool wait_eof ()
- unsigned long long int eof_position () const
- unsigned int buffer_size () const

Data Fields

• DataSpeed speed

Data Structures

- struct buf_desc
- · class checksum desc

6.35.1 Detailed Description

Represents set of buffers.

This class is used used during data transfer using DataPoint (p. 111) classes.

6.35.2 Constructor & Destructor Documentation

6.35.2.1 Arc::DataBuffer::DataBuffer (unsigned int size = 65536, int blocks = 3)

Contructor

Parameters:

```
size size of every buffer in bytes. blocks number of buffers.
```

6.35.2.2 Arc::DataBuffer::DataBuffer (CheckSum * cksum, unsigned int size = 65536, int blocks = 3)

Contructor

Parameters:

```
size size of every buffer in bytes.
```

blocks number of buffers.

cksum object which will compute checksum. Should not be destroyed till DataBuffer (p. 98) itself.

6.35.2.3 Arc::DataBuffer::~DataBuffer ()

Destructor.

6.35.3 Member Function Documentation

6.35.3.1 int Arc::DataBuffer::add (CheckSum * cksum)

Add a checksum object which will compute checksum of buffer.

Parameters:

cksum object which will compute checksum. Should not be destroyed till DataBuffer (p. 98) itself.

Returns:

integer position in the list of checksum objects.

6.35.3.2 unsigned int Arc::DataBuffer::buffer_size () const

Returns size of buffer in object. If not initialized then this number represents size of default buffer.

6.35.3.3 const CheckSum* Arc::DataBuffer::checksum_object () const

Returns CheckSum (p. 65) object specified in constructor, returns NULL if index is not in list.

Parameters:

index of the checksum in question.

6.35.3.4 bool Arc::DataBuffer::checksum_valid () const

Returns true if checksum was successfully computed, returns false if index is not in list.

Parameters:

index of the checksum in question.

6.35.3.5 unsigned long long int Arc::DataBuffer::eof_position() const [inline]

Returns offset following last piece of data transferred.

6.35.3.6 bool Arc::DataBuffer::eof_read ()

Returns true if object was informed about end of transfer on 'read' side.

6.35.3.7 void Arc::DataBuffer::eof_read (bool v)

Informs object if there will be no more request for 'read' buffers. v true if no more requests.

6.35.3.8 bool Arc::DataBuffer::eof_write()

Returns true if object was informed about end of transfer on 'write' side.

6.35.3.9 void Arc::DataBuffer::eof_write (bool v)

Informs object if there will be no more request for 'write' buffers. v true if no more requests.

6.35.3.10 bool Arc::DataBuffer::error ()

Returns true if object was informed about error or internal error occured.

6.35.3.11 bool Arc::DataBuffer::error read ()

Returns true if object was informed about error on 'read' side.

6.35.3.12 void Arc::DataBuffer::error_read (bool v)

Informs object if error accured on 'read' side.

Parameters:

v true if error.

6.35.3.13 bool Arc::DataBuffer::error_transfer()

Returns true if eror occured inside object.

6.35.3.14 bool Arc::DataBuffer::error_write()

Returns true if object was informed about error on 'write' side.

6.35.3.15 void Arc::DataBuffer::error_write (bool v)

Informs object if error accured on 'write' side.

Parameters:

v true if error.

6.35.3.16 bool Arc::DataBuffer::for_read ()

Check if there are buffers which can be taken by for_read() (p. 101). This function checks only for buffers and does not take eof and error conditions into account.

6.35.3.17 bool Arc::DataBuffer::for_read (int & handle, unsigned int & length, bool wait)

Request buffer for READING INTO it.

Parameters:

handle returns buffer's number.

length returns size of buffer

wait if true and there are no free buffers, method will wait for one.

Returns:

true on success

6.35.3.18 bool Arc::DataBuffer::for_write()

Check if there are buffers which can be taken by for_write() (p. 101). This function checks only for buffers and does not take eof and error conditions into account.

6.35.3.19 bool Arc::DataBuffer::for_write (int & handle, unsigned int & length, unsigned long long int & offset, bool wait)

Request buffer for WRITING FROM it.

Parameters:

```
handle returns buffer's number.

length returns size of buffer

wait if true and there are no free buffers, method will wait for one.
```

6.35.3.20 bool Arc::DataBuffer::is_notwritten (char * buf)

Informs object that data was NOT written from buffer (and releases buffer).

Parameters:

```
buf - address of buffer
```

6.35.3.21 bool Arc::DataBuffer::is_notwritten (int handle)

Informs object that data was NOT written from buffer (and releases buffer).

Parameters:

handle buffer's number.

6.35.3.22 bool Arc::DataBuffer::is_read (char * buf, unsigned int length, unsigned long long int offset)

Informs object that data was read into buffer.

Parameters:

```
buf - address of bufferlength amount of data.offset offset in stream, file, etc.
```

6.35.3.23 bool Arc::DataBuffer::is_read (int *handle*, unsigned int *length*, unsigned long long int *offset*)

Informs object that data was read into buffer.

Parameters:

```
handle buffer's number.length amount of data.offset offset in stream, file, etc.
```

6.35.3.24 bool Arc::DataBuffer::is_written (char * buf)

Informs object that data was written from buffer.

Parameters:

buf - address of buffer

6.35.3.25 bool Arc::DataBuffer::is_written (int handle)

Informs object that data was written from buffer.

Parameters:

handle buffer's number.

6.35.3.26 Arc::DataBuffer::operator bool (void) const [inline]

Check if DataBuffer (p. 98) object is initialized.

6.35.3.27 char* Arc::DataBuffer::operator[] (int n)

Direct access to buffer by number.

6.35.3.28 bool Arc::DataBuffer::set (CheckSum * cksum = NULL, unsigned int size = 65536, int blocks = 3)

Reinitialize buffers with different parameters.

Parameters:

size size of every buffer in bytes.

blocks number of buffers.

cksum object which will compute checksum. Should not be destroyed till DataBuffer (p. 98) itself.

6.35.3.29 bool Arc::DataBuffer::wait_any ()

Wait (max 60 sec.) till any action happens in object. Returns true if action is eof on any side.

6.35.3.30 bool Arc::DataBuffer::wait_eof()

Wait till end of transfer happens on any side.

6.35.3.31 bool Arc::DataBuffer::wait_eof_read()

Wait till end of transfer happens on 'read' side.

6.35.3.32 bool Arc::DataBuffer::wait_eof_write ()

Wait till end of transfer happens on 'write' side.

6.35.3.33 bool Arc::DataBuffer::wait_read ()

Wait till end of transfer or error happens on 'read' side.

6.35.3.34 bool Arc::DataBuffer::wait_used ()

Wait till there are no more used buffers left in object.

6.35.3.35 bool Arc::DataBuffer::wait_write()

Wait till end of transfer or error happens on 'write' side.

6.35.4 Field Documentation

6.35.4.1 DataSpeed Arc::DataBuffer::speed

This object controls transfer speed.

The documentation for this class was generated from the following file:

• DataBuffer.h

6.36 Arc::DataCallback Class Reference

#include <DataCallback.h>

6.36.1 Detailed Description

This class is used by DataHandle (p. 106) to report missing space on local filesystem. One of 'cb' functions here will be called if operation initiated by DataHandle::start_reading runs out of disk space.

The documentation for this class was generated from the following file:

• DataCallback.h

6.37 Arc::DataHandle Class Reference

This class is a wrapper around the DataPoint (p. 111) class.

#include <DataHandle.h>

6.37.1 Detailed Description

This class is a wrapper around the DataPoint (p. 111) class.

It simplifies the construction, use and destruction of DataPoint (p. 111) objects.

The documentation for this class was generated from the following file:

• DataHandle.h

6.38 Arc::DataMover Class Reference

#include <DataMover.h>

Public Member Functions

- DataMover ()
- ∼DataMover ()
- DataStatus Transfer (DataPoint &source, DataPoint &destination, FileCache &cache, const URLMap &map, callback cb=NULL, void *arg=NULL, const char *prefix=NULL)
- DataStatus Transfer (DataPoint &source, DataPoint &destination, FileCache &cache, const URLMap &map, unsigned long long int min_speed, time_t min_speed_time, unsigned long long int min_average_speed, time_t max_inactivity_time, callback cb=NULL, void *arg=NULL, const char *prefix=NULL)
- bool verbose ()
- void verbose (bool)
- void verbose (const std::string &prefix)
- bool retry ()
- void retry (bool)
- void secure (bool)
- · void passive (bool)
- void force_to_meta (bool)
- bool checks ()
- void checks (bool v)
- void set_default_min_speed (unsigned long long int min_speed, time_t min_speed_time)
- void set_default_min_average_speed (unsigned long long int min_average_speed)
- void set_default_max_inactivity_time (time_t max_inactivity_time)

6.38.1 Detailed Description

A purpose of this class is to provide an interface that moves data between two locations specified by URLs. It's main action is represented by methods DataMover::Transfer (p. 109). Instance represents only attributes used during transfer.

6.38.2 Constructor & Destructor Documentation

6.38.2.1 Arc::DataMover::DataMover()

Constructor.

6.38.2.2 Arc::DataMover::~DataMover ()

Destructor.

6.38.3 Member Function Documentation

6.38.3.1 void Arc::DataMover::checks (bool v)

Set if to make check for existance of remote file (and probably other checks too) before initiating 'reading' and 'writing' operations.

Parameters:

v true if allowed (default is true).

6.38.3.2 bool Arc::DataMover::checks ()

Check if check for existance of remote file is done before initiating 'reading' and 'writing' operations.

6.38.3.3 void Arc::DataMover::force_to_meta (bool)

Set if file should be transferred and registered even if such LFN is already registered and source is not one of registered locations.

6.38.3.4 void Arc::DataMover::passive (bool)

Set if passive transfer should be used for FTP-like transfers.

6.38.3.5 void Arc::DataMover::retry (bool)

Set if transfer will be retried in case of failure.

6.38.3.6 bool Arc::DataMover::retry ()

Check if transfer will be retried in case of failure.

6.38.3.7 void Arc::DataMover::secure (bool)

Set if high level of security (encryption) will be used duirng transfer if available.

Set maximal allowed time for waiting for any data. For more information see description of Data-Speed $(p.\,139)$ class.

6.38.3.9 void Arc::DataMover::set_default_min_average_speed (unsigned long long int min_average_speed) [inline]

Set minimal allowed average transfer speed (default is 0 averaged over whole time of transfer. For more information see description of DataSpeed (p. 139) class.

6.38.3.10 void Arc::DataMover::set_default_min_speed (unsigned long long int min_speed, time_t min_speed_time) [inline]

Set minimal allowed transfer speed (default is 0) to 'min_speed'. If speed drops below for time longer than 'min_speed_time' error is raised. For more information see description of DataSpeed (p. 139) class.

6.38.3.11 DataStatus Arc::DataMover::Transfer (DataPoint & source, DataPoint & destination, FileCache & cache, const URLMap & map, unsigned long long int min_speed, time_t min_speed_time, unsigned long long int min_average_speed, time_t max_inactivity_time, callback cb = NULL, void * arg = NULL, const char * prefix = NULL)

Initiates transfer from 'source' to 'destination'.

Parameters:

min_speed minimal allowed current speed.

min_speed_time time for which speed should be less than 'min_speed' before transfer fails.

min_average_speed minimal allowed average speed.

max_inactivity_time time for which should be no activity before transfer fails.

6.38.3.12 DataStatus Arc::DataMover::Transfer (DataPoint & source, DataPoint & destination, FileCache & cache, const URLMap & map, callback cb = NULL, void * arg = NULL, const char * prefix = NULL)

Initiates transfer from 'source' to 'destination'.

Parameters:

source Source URL.

destination destination URL.

cache controls caching of downloaded files (if destination url is "file://"). If caching is not needed default constructor FileCache() can be used.

map URL mapping/convertion table (for 'source' URL).

cb if not NULL, transfer is done in separate thread and 'cb' is called after transfer completes/fails.

arg passed to 'cb'.

prefix if 'verbose' is activated this information will be printed before each line representing current transfer status.

6.38.3.13 void Arc::DataMover::verbose (const std::string & prefix)

Activate printing information about transfer status.

Parameters:

prefix use this string if 'prefix' in DataMover::Transfer (p. 109) is NULL.

6.38.3.14 void Arc::DataMover::verbose (bool)

Activate printing information about transfer status.

6.38.3.15 bool Arc::DataMover::verbose ()

Check if printing information about transfer status is activated.

The documentation for this class was generated from the following file:


· DataMover.h

6.39 Arc::DataPoint Class Reference

This base class is an abstraction of URL.

#include <DataPoint.h>

Inheritance diagram for Arc::DataPoint::



Public Types

- ACCESS LATENCY ZERO
- ACCESS_LATENCY_SMALL
- ACCESS_LATENCY_LARGE
- enum DataPointAccessLatency { ACCESS_LATENCY_ZERO, ACCESS_LATENCY_SMALL, ACCESS_LATENCY_LARGE }

Public Member Functions

- DataPoint (const URL &url, const UserConfig &usercfg)
- virtual ∼DataPoint ()
- virtual const URL & GetURL () const
- virtual const UserConfig & GetUserConfig () const
- virtual std::string str () const
- virtual operator bool () const
- virtual bool operator! () const
- virtual DataStatus StartReading (DataBuffer &buffer)=0
- virtual DataStatus StartWriting (DataBuffer &buffer, DataCallback *space_cb=NULL)=0
- virtual DataStatus StopReading ()=0
- virtual DataStatus StopWriting ()=0
- virtual DataStatus Check ()=0
- virtual DataStatus Remove ()=0
- virtual DataStatus ListFiles (std::list< FileInfo > &files, bool long_list=false, bool resolve=false, bool metadata=false)=0
- virtual void ReadOutOfOrder (bool v)=0
- virtual bool WriteOutOfOrder ()=0
- virtual void SetAdditionalChecks (bool v)=0
- virtual bool GetAdditionalChecks () const =0
- virtual void SetSecure (bool v)=0
- virtual bool GetSecure () const =0
- virtual void Passive (bool v)=0
- virtual DataStatus GetFailureReason (void) const
- virtual void Range (unsigned long long int start=0, unsigned long long int end=0)=0

- virtual DataStatus Resolve (bool source)=0
- virtual bool Registered () const =0
- virtual DataStatus PreRegister (bool replication, bool force=false)=0
- virtual DataStatus PostRegister (bool replication)=0
- virtual DataStatus PreUnregister (bool replication)=0
- virtual DataStatus Unregister (bool all)=0
- virtual bool CheckSize () const
- virtual void SetSize (const unsigned long long int val)
- virtual unsigned long long int GetSize () const
- virtual bool CheckCheckSum () const
- virtual void SetCheckSum (const std::string &val)
- virtual const std::string & GetCheckSum () const
- virtual const std::string DefaultCheckSum () const
- virtual bool CheckCreated () const
- virtual void SetCreated (const Time &val)
- virtual const Time & GetCreated () const
- virtual bool CheckValid () const
- virtual void SetValid (const Time &val)
- virtual const Time & GetValid () const
- virtual void SetAccessLatency (const DataPointAccessLatency &latency)
- virtual DataPointAccessLatency GetAccessLatency () const
- virtual long long int BufSize () const =0
- virtual int BufNum () const =0
- · virtual bool Cache () const
- virtual bool Local () const =0
- virtual int GetTries () const
- virtual void SetTries (const int n)
- virtual void NextTry (void)
- virtual bool IsIndex () const =0
- virtual bool AcceptsMeta ()=0
- virtual bool ProvidesMeta ()=0
- virtual void SetMeta (const DataPoint &p)
- virtual bool CompareMeta (const DataPoint &p) const
- virtual const URL & CurrentLocation () const =0
- virtual const std::string & CurrentLocationMetadata () const =0
- virtual DataStatus CompareLocationMetadata () const =0
- virtual bool NextLocation ()=0
- virtual bool LocationValid () const =0
- virtual bool LastLocation ()=0
- virtual bool HaveLocations () const =0
- virtual DataStatus AddLocation (const URL &url, const std::string &meta)=0
- virtual DataStatus RemoveLocation ()=0
- virtual DataStatus RemoveLocations (const DataPoint &p)=0
- virtual int AddCheckSumObject (CheckSum *cksum)=0
- virtual void SortLocations (const std::string &pattern, const URLMap &url_map)=0

Protected Attributes

• std::list< std::string > valid url options

6.39.1 Detailed Description

This base class is an abstraction of URL.

Specializations should be provided for different kind of direct access URLs (file://, ftp://, gsiftp://, http://, https://, https://, or indexing service URLs (rls://, lfc://, ...). **DataPoint** (p.111) provides means to resolve an indexing service URL into multiple URLs and to loop through them.

6.39.2 Member Enumeration Documentation

6.39.2.1 enum Arc::DataPoint::DataPointAccessLatency

Describes the latency to access this URL.

For now this value is one of a small set specified by the enumeration. In the future with more sophisticated protocols or information it could be replaced by a more fine-grained list of possibilities such as an int value.

Enumerator:

ACCESS_LATENCY_ZERO URL can be accessed instantly.

ACCESS_LATENCY_SMALL URL has low (but non-zero) access latency, for example staged from disk.

ACCESS_LATENCY_LARGE URL has a large access latency, for example staged from tape.

6.39.3 Constructor & Destructor Documentation

6.39.3.1 Arc::DataPoint::DataPoint (const URL & url, const UserConfig & usercfg)

Constructor requires URL to be provided.

References to url and usercfg arguments are stored internally and hence corresponding objects must stay available during whole lifetime of this instance.

6.39.3.2 virtual Arc::DataPoint::~DataPoint() [virtual]

Destructor.

6.39.4 Member Function Documentation

6.39.4.1 virtual bool Arc::DataPoint::AcceptsMeta () [pure virtual]

If endpoint can have any use from meta information.

Implemented in Arc::DataPointDirect (p. 125), and Arc::DataPointIndex (p. 132).

6.39.4.2 virtual int Arc::DataPoint::AddCheckSumObject (CheckSum * *cksum*) [pure virtual]

Add a checksum object which will compute checksum during transmission.

cksum object which will compute checksum. Should not be destroyed till DataPointer itself.

Returns:

integer position in the list of checksum objects.

Implemented in Arc::DataPointDirect (p. 125), and Arc::DataPointIndex (p. 132).

6.39.4.3 virtual DataStatus Arc::DataPoint::AddLocation (const URL & url, const std::string & meta) [pure virtual]

Add URL to list.

Parameters:

url Location URL to add.

meta Location meta information.

Implemented in Arc::DataPointDirect (p. 125), and Arc::DataPointIndex (p. 132).

6.39.4.4 virtual int Arc::DataPoint::BufNum () const [pure virtual]

Get suggested number of buffers for transfers.

Implemented in Arc::DataPointDirect (p. 125), and Arc::DataPointIndex (p. 132).

6.39.4.5 virtual long long int Arc::DataPoint::BufSize () const [pure virtual]

Get suggested buffer size for transfers.

Implemented in Arc::DataPointDirect (p. 126), and Arc::DataPointIndex (p. 133).

6.39.4.6 virtual bool Arc::DataPoint::Cache () const [virtual]

Returns true if file is cacheable.

6.39.4.7 virtual DataStatus Arc::DataPoint::Check () [pure virtual]

Query the DataPoint (p. 111) to check if object is accessible.

If possible this method will also try to provide meta information about the object.

Implemented in Arc::DataPointIndex (p. 133).

6.39.4.8 virtual bool Arc::DataPoint::CheckCheckSum () const [virtual]

Check if meta-information 'checksum' is available.

6.39.4.9 virtual bool Arc::DataPoint::CheckCreated () const [virtual]

Check if meta-information 'creation/modification time' is available.

6.39.4.10 virtual bool Arc::DataPoint::CheckSize () const [virtual]

Check if meta-information 'size' is available.

6.39.4.11 virtual bool Arc::DataPoint::CheckValid () const [virtual]

Check if meta-information 'validity time' is available.

6.39.4.12 virtual DataStatus Arc::DataPoint::CompareLocationMetadata () const [pure virtual]

Compare metadata of DataPoint (p. 111) and current location.

Returns inconsistency error or error encountered during operation, or success

Implemented in Arc::DataPointDirect (p. 126), and Arc::DataPointIndex (p. 133).

6.39.4.13 virtual bool Arc::DataPoint::CompareMeta (const DataPoint & p) const [virtual]

Compare meta information from another object.

Undefined values are not used for comparison.

Parameters:

p object to which to compare.

6.39.4.14 virtual const URL& Arc::DataPoint::CurrentLocation () const [pure virtual]

Returns current (resolved) URL.

Implemented in Arc::DataPointDirect (p. 126), and Arc::DataPointIndex (p. 133).

6.39.4.15 virtual const std::string& Arc::DataPoint::CurrentLocationMetadata () const [pure virtual]

Returns meta information used to create current URL.

Usage differs between different indexing services.

Implemented in Arc::DataPointDirect (p. 126), and Arc::DataPointIndex (p. 133).

6.39.4.16 virtual const std::string Arc::DataPoint::DefaultCheckSum () const [virtual]

Default checksum type.

6.39.4.17 virtual DataPointAccessLatency Arc::DataPoint::GetAccessLatency () const [virtual]

Get value of meta-information 'access latency'.

Reimplemented in Arc::DataPointIndex (p. 133).

6.39.4.18 virtual bool Arc::DataPoint::GetAdditionalChecks () const [pure virtual]

Check if additional checks before will be performed.

Implemented in Arc::DataPointDirect (p. 126), and Arc::DataPointIndex (p. 133).

6.39.4.19 virtual const std::string& Arc::DataPoint::GetCheckSum () const [virtual]

Get value of meta-information 'checksum'.

6.39.4.20 virtual const Time& Arc::DataPoint::GetCreated () const [virtual]

Get value of meta-information 'creation/modification time'.

6.39.4.21 virtual DataStatus Arc::DataPoint::GetFailureReason (void) const [virtual]

Returns reason of transfer failure, as reported by callbacks. This could be different from the failure returned by the methods themselves.

6.39.4.22 virtual bool Arc::DataPoint::GetSecure () **const** [pure virtual]

Check if heavy security during data transfer is allowed.

Implemented in Arc::DataPointDirect (p. 126), and Arc::DataPointIndex (p. 133).

6.39.4.23 virtual unsigned long long int Arc::DataPoint::GetSize () const [virtual]

Get value of meta-information 'size'.

6.39.4.24 virtual int Arc::DataPoint::GetTries () const [virtual]

Returns number of retries left.

6.39.4.25 virtual const URL& Arc::DataPoint::GetURL() const [virtual]

Returns the URL that was passed to the constructor.

6.39.4.26 virtual const UserConfig& Arc::DataPoint::GetUserConfig() const [virtual]

Returns the UserConfig (p. 361) that was passed to the constructor.

6.39.4.27 virtual const Time& Arc::DataPoint::GetValid () const [virtual]

Get value of meta-information 'validity time'.

6.39.4.28 virtual bool Arc::DataPoint::HaveLocations () const [pure virtual]

Returns true if number of resolved URLs is not 0.

Implemented in Arc::DataPointDirect (p. 126), and Arc::DataPointIndex (p. 134).

6.39.4.29 virtual bool Arc::DataPoint::IsIndex () const [pure virtual]

Check if URL is an Indexing Service (p. 316).

Implemented in Arc::DataPointDirect (p. 126), and Arc::DataPointIndex (p. 134).

6.39.4.30 virtual bool Arc::DataPoint::LastLocation () [pure virtual]

Returns true if the current location is the last.

Implemented in Arc::DataPointDirect (p. 127), and Arc::DataPointIndex (p. 134).

6.39.4.31 virtual DataStatus Arc::DataPoint::ListFiles (std::list< FileInfo > & files, bool long_list = false, bool resolve = false, bool metadata = false) [pure virtual]

List file(s).

If the DataPoint (p. 111) represents a directory its contents will be listed.

Parameters:

files will contain list of file names and optionally their attributes.

long_list if true, list additional properties of each file.

resolve if true, resolve physical locations (relevant for indexing services only).

metadata if true, find all available metadata.

6.39.4.32 virtual bool Arc::DataPoint::Local () const [pure virtual]

Returns true if file is local, e.g. file:// urls.

Implemented in Arc::DataPointDirect (p. 127), and Arc::DataPointIndex (p. 134).

6.39.4.33 virtual bool Arc::DataPoint::LocationValid () const [pure virtual]

Returns false if out of retries.

Implemented in Arc::DataPointDirect (p. 127), and Arc::DataPointIndex (p. 134).

6.39.4.34 virtual bool Arc::DataPoint::NextLocation () [pure virtual]

Switch to next location in list of URLs.

At last location switch to first if number of allowed retries is not exceeded. Returns false if no retries left.

Implemented in Arc::DataPointDirect (p. 127), and Arc::DataPointIndex (p. 134).

6.39.4.35 virtual void Arc::DataPoint::NextTry (void) [virtual]

Decrease number of retries left.

6.39.4.36 virtual Arc::DataPoint::operator bool () const [virtual]

Is DataPoint (p. 111) valid?

6.39.4.37 virtual bool Arc::DataPoint::operator! () const [virtual]

Is DataPoint (p. 111) valid?

6.39.4.38 virtual void Arc::DataPoint::Passive (bool v) [pure virtual]

Request passive transfers for FTP-like protocols.

Parameters:

true to request.

Implemented in Arc::DataPointDirect (p. 127), and Arc::DataPointIndex (p. 134).

6.39.4.39 virtual DataStatus Arc::DataPoint::PostRegister (bool replication) [pure virtual]

Index Service (p. 316) postregistration.

Used for same purpose as PreRegister. Should be called after actual transfer of file successfully finished.

Parameters:

replication if true, the file is being replicated between two locations registered in Indexing Service (p. 316) under same name.

Implemented in Arc::DataPointDirect (p. 127).

6.39.4.40 virtual DataStatus Arc::DataPoint::PreRegister (bool *replication***, bool** *force* = false) [pure virtual]

Index service preregistration.

This function registers the physical location of a file into an indexing service. It should be called *before* the actual transfer to that location happens.

Parameters:

replication if true, the file is being replicated between two locations registered in the indexing service under same name.

force if true, perform registration of a new file even if it already exists. Should be used to fix failures in Indexing Service (p. 316).

Implemented in Arc::DataPointDirect (p. 128).

6.39.4.41 virtual DataStatus Arc::DataPoint::PreUnregister (bool replication) [pure virtual]

Index Service (p. 316) preunregistration.

Should be called if file transfer failed. It removes changes made by PreRegister.

Parameters:

replication if true, the file is being replicated between two locations registered in Indexing Service (p. 316) under same name.

Implemented in Arc::DataPointDirect (p. 128).

6.39.4.42 virtual bool Arc::DataPoint::ProvidesMeta () [pure virtual]

If endpoint can provide at least some meta information directly.

Implemented in Arc::DataPointDirect (p. 128), and Arc::DataPointIndex (p. 135).

6.39.4.43 virtual void Arc::DataPoint::Range (unsigned long long int *start* = 0, unsigned long long int *end* = 0) [pure virtual]

Set range of bytes to retrieve.

Default values correspond to whole file.

Implemented in Arc::DataPointDirect (p. 128), and Arc::DataPointIndex (p. 135).

6.39.4.44 virtual void Arc::DataPoint::ReadOutOfOrder (bool v) [pure virtual]

Parameters:

v true if allowed (default is false).

Implemented in Arc::DataPointDirect (p. 128), and Arc::DataPointIndex (p. 135).

6.39.4.45 virtual bool Arc::DataPoint::Registered () const [pure virtual]

Check if file is registered in Indexing Service (p. 316).

Proper value is obtainable only after Resolve.

Implemented in Arc::DataPointDirect (p. 129), and Arc::DataPointIndex (p. 135).

6.39.4.46 virtual DataStatus Arc::DataPoint::Remove () [pure virtual]

Remove/delete object at URL.

Implemented in Arc::DataPointIndex (p. 135).

6.39.4.47 virtual DataStatus Arc::DataPoint::RemoveLocation () [pure virtual]

Remove current URL from list.

Implemented in Arc::DataPointDirect (p. 129), and Arc::DataPointIndex (p. 135).

6.39.4.48 virtual DataStatus Arc::DataPoint::RemoveLocations (const DataPoint & p) [pure virtual]

Remove locations present in another DataPoint (p. 111) object.

Implemented in Arc::DataPointDirect (p. 129), and Arc::DataPointIndex (p. 135).

6.39.4.49 virtual DataStatus Arc::DataPoint::Resolve (bool *source***)** [pure virtual]

Resolves index service URL into list of ordinary URLs.

Also obtains meta information about the file.

Parameters:

source true if DataPoint (p. 111) object represents source of information.

Implemented in Arc::DataPointDirect (p. 129).

6.39.4.50 virtual void Arc::DataPoint::SetAccessLatency (const DataPointAccessLatency & *latency*) [virtual]

Set value of meta-information 'access latency'.

6.39.4.51 virtual void Arc::DataPoint::SetAdditionalChecks (bool v) [pure virtual]

Allow/disallow additional checks.

Check for existance of remote file (and probably other checks too) before initiating reading and writing operations.

Parameters:

v true if allowed (default is true).

Implemented in Arc::DataPointDirect (p. 129), and Arc::DataPointIndex (p. 135).

6.39.4.52 virtual void Arc::DataPoint::SetCheckSum (const std::string & val) [virtual]

Set value of meta-information 'checksum'.

Reimplemented in Arc::DataPointIndex (p. 136).

6.39.4.53 virtual void Arc::DataPoint::SetCreated (const Time & val) [virtual]

Set value of meta-information 'creation/modification time'.

6.39.4.54 virtual void Arc::DataPoint::SetMeta (const DataPoint & p) [virtual]

Copy meta information from another object.

Already defined values are not overwritten.

p object from which information is taken.

Reimplemented in Arc::DataPointIndex (p. 136).

6.39.4.55 virtual void Arc::DataPoint::SetSecure (bool v) [pure virtual]

Allow/disallow heavy security during data transfer.

Parameters:

v true if allowed (default depends on protocol).

Implemented in Arc::DataPointDirect (p. 129), and Arc::DataPointIndex (p. 136).

6.39.4.56 virtual void Arc::DataPoint::SetSize (const unsigned long long int *val***)** [virtual]

Set value of meta-information 'size'.

Reimplemented in Arc::DataPointIndex (p. 136).

6.39.4.57 virtual void Arc::DataPoint::SetTries (const int n) [virtual]

Set number of retries.

Reimplemented in Arc::DataPointIndex (p. 136).

6.39.4.58 virtual void Arc::DataPoint::SetValid (const Time & val) [virtual]

Set value of meta-information 'validity time'.

6.39.4.59 virtual void Arc::DataPoint::SortLocations (const std::string & pattern, const URLMap & url_map) [pure virtual]

Sort locations according to the specified pattern.

Parameters:

pattern a set of strings, separated by |, to match against.

Implemented in Arc::DataPointDirect (p. 130), and Arc::DataPointIndex (p. 136).

6.39.4.60 virtual DataStatus Arc::DataPoint::StartReading (DataBuffer & *buffer*) [pure virtual]

Start reading data from URL.

Separate thread to transfer data will be created. No other operation can be performed while reading is in progress.

buffer operation will use this buffer to put information into. Should not be destroyed before stop_reading was called and returned.

Implemented in Arc::DataPointIndex (p. 137).

6.39.4.61 virtual DataStatus Arc::DataPoint::StartWriting (DataBuffer & buffer, DataCallback * space_cb = NULL) [pure virtual]

Start writing data to URL.

Separate thread to transfer data will be created. No other operation can be performed while writing is in progress.

Parameters:

buffer operation will use this buffer to get information from. Should not be destroyed before stop_writing was called and returned.

space_cb callback which is called if there is not enough space to store data. May not implemented for all protocols.

Implemented in Arc::DataPointIndex (p. 137).

6.39.4.62 virtual DataStatus Arc::DataPoint::StopReading () [pure virtual]

Stop reading.

Must be called after corresponding start_reading method, either after all data is transferred or to cancel transfer. Use buffer object to find out when data is transferred. Must return failure if any happened during transfer.

Implemented in Arc::DataPointIndex (p. 137).

6.39.4.63 virtual DataStatus Arc::DataPoint::StopWriting() [pure virtual]

Stop writing.

Must be called after corresponding start_writing method, either after all data is transferred or to cancel transfer. Use buffer object to find out when data is transferred. Must return failure if any happened during transfer.

Implemented in Arc::DataPointIndex (p. 137).

6.39.4.64 virtual std::string Arc::DataPoint::str() const [virtual]

Returns a string representation of the DataPoint (p. 111).

6.39.4.65 virtual DataStatus Arc::DataPoint::Unregister (bool *all***)** [pure virtual]

Index Service (p. 316) unregistration.

Remove information about file registered in Indexing Service (p. 316).

all if true, information about file itself is (LFN) is removed. Otherwise only particular physical instance is unregistered.

Implemented in Arc::DataPointDirect (p. 130).

6.39.4.66 virtual bool Arc::DataPoint::WriteOutOfOrder() [pure virtual]

Returns true if URL can accept scattered data for *writing* operation.

Implemented in Arc::DataPointDirect (p. 130), and Arc::DataPointIndex (p. 138).

6.39.5 Field Documentation

6.39.5.1 std::list<std::string> Arc::DataPoint::valid_url_options [protected]

Subclasses should add their own specific options to this list

The documentation for this class was generated from the following file:


· DataPoint.h

6.40 Arc::DataPointDirect Class Reference

This is a kind of generalized file handle.

#include <DataPointDirect.h>

Inheritance diagram for Arc::DataPointDirect::



Public Member Functions

- virtual bool IsIndex () const
- virtual long long int BufSize () const
- virtual int BufNum () const
- virtual bool Local () const
- virtual void ReadOutOfOrder (bool v)
- virtual bool WriteOutOfOrder ()
- virtual void SetAdditionalChecks (bool v)
- virtual bool GetAdditionalChecks () const
- virtual void SetSecure (bool v)
- virtual bool GetSecure () const
- virtual void Passive (bool v)
- virtual void Range (unsigned long long int start=0, unsigned long long int end=0)
- virtual int AddCheckSumObject (CheckSum *cksum)
- virtual DataStatus Resolve (bool source)
- · virtual bool Registered () const
- virtual DataStatus PreRegister (bool replication, bool force=false)
- virtual DataStatus PostRegister (bool replication)
- virtual DataStatus PreUnregister (bool replication)
- virtual DataStatus Unregister (bool all)
- virtual bool AcceptsMeta ()
- virtual bool ProvidesMeta ()
- virtual const URL & CurrentLocation () const
- virtual const std::string & CurrentLocationMetadata () const
- virtual DataStatus CompareLocationMetadata () const
- virtual bool NextLocation ()
- virtual bool LocationValid () const
- virtual bool HaveLocations () const
- virtual bool LastLocation ()
- virtual DataStatus AddLocation (const URL &url, const std::string &meta)
- virtual DataStatus RemoveLocation ()
- virtual DataStatus RemoveLocations (const DataPoint &p)
- virtual void SortLocations (const std::string &, const URLMap &)

6.40.1 Detailed Description

This is a kind of generalized file handle.

Differently from file handle it does not support operations read() and write(). Instead it initiates operation and uses object of class DataBuffer (p. 98) to pass actual data. It also provides other operations like querying parameters of remote object. It is used by higher-level classes DataMove and DataMovePar to provide data transfer service for application.

6.40.2 Member Function Documentation

```
6.40.2.1 virtual bool Arc::DataPointDirect::AcceptsMeta () [virtual]
```

If endpoint can have any use from meta information.

Implements Arc::DataPoint (p. 113).

```
6.40.2.2 virtual int Arc::DataPointDirect::AddCheckSumObject (CheckSum * cksum) [virtual]
```

Add a checksum object which will compute checksum during transmission.

Parameters:

cksum object which will compute checksum. Should not be destroyed till DataPointer itself.

Returns:

integer position in the list of checksum objects.

```
Implements Arc::DataPoint (p. 113).
```

6.40.2.3 virtual DataStatus Arc::DataPointDirect::AddLocation (const URL & url, const std::string & meta) [virtual]

Add URL to list.

Parameters:

```
url Location URL to add.
```

meta Location meta information.

Implements Arc::DataPoint (p. 114).

6.40.2.4 virtual int Arc::DataPointDirect::BufNum () const [virtual]

Get suggested number of buffers for transfers.

Implements Arc::DataPoint (p. 114).

6.40.2.5 virtual long long int Arc::DataPointDirect::BufSize () const [virtual]

Get suggested buffer size for transfers.

Implements Arc::DataPoint (p. 114).

6.40.2.6 virtual DataStatus Arc::DataPointDirect::CompareLocationMetadata () const

Compare metadata of DataPoint (p. 111) and current location.

Returns inconsistency error or error encountered during operation, or success

Implements Arc::DataPoint (p. 115).

6.40.2.7 virtual const URL& Arc::DataPointDirect::CurrentLocation () const [virtual]

Returns current (resolved) URL.

Implements Arc::DataPoint (p. 115).

6.40.2.8 virtual const std::string& Arc::DataPointDirect::CurrentLocationMetadata () const [virtual]

Returns meta information used to create current URL.

Usage differs between different indexing services.

Implements Arc::DataPoint (p. 115).

6.40.2.9 virtual bool Arc::DataPointDirect::GetAdditionalChecks () const [virtual]

Check if additional checks before will be performed.

Implements Arc::DataPoint (p. 116).

6.40.2.10 virtual bool Arc::DataPointDirect::GetSecure () const [virtual]

Check if heavy security during data transfer is allowed.

Implements Arc::DataPoint (p. 116).

6.40.2.11 virtual bool Arc::DataPointDirect::HaveLocations () const [virtual]

Returns true if number of resolved URLs is not 0.

Implements Arc::DataPoint (p. 117).

6.40.2.12 virtual bool Arc::DataPointDirect::IsIndex () const [virtual]

Check if URL is an Indexing Service (p. 316).

Implements Arc::DataPoint (p. 117).

6.40.2.13 virtual bool Arc::DataPointDirect::LastLocation () [virtual]

Returns true if the current location is the last.

Implements Arc::DataPoint (p. 117).

6.40.2.14 virtual bool Arc::DataPointDirect::Local () const [virtual]

Returns true if file is local, e.g. file:// urls.

Implements Arc::DataPoint (p. 117).

6.40.2.15 virtual bool Arc::DataPointDirect::LocationValid () const [virtual]

Returns false if out of retries.

Implements Arc::DataPoint (p. 117).

6.40.2.16 virtual bool Arc::DataPointDirect::NextLocation () [virtual]

Switch to next location in list of URLs.

At last location switch to first if number of allowed retries is not exceeded. Returns false if no retries left.

Implements Arc::DataPoint (p. 117).

6.40.2.17 virtual void Arc::DataPointDirect::Passive (bool v) [virtual]

Request passive transfers for FTP-like protocols.

Parameters:

true to request.

Implements Arc::DataPoint (p. 118).

6.40.2.18 virtual DataStatus Arc::DataPointDirect::PostRegister (bool replication) [virtual]

Index Service (p. 316) postregistration.

Used for same purpose as PreRegister. Should be called after actual transfer of file successfully finished.

Parameters:

replication if true, the file is being replicated between two locations registered in Indexing Service (p. 316) under same name.

Implements Arc::DataPoint (p. 118).

6.40.2.19 virtual DataStatus Arc::DataPointDirect::PreRegister (bool *replication***, bool** *force* = false) [virtual]

Index service preregistration.

This function registers the physical location of a file into an indexing service. It should be called *before* the actual transfer to that location happens.

Parameters:

replication if true, the file is being replicated between two locations registered in the indexing service under same name.

force if true, perform registration of a new file even if it already exists. Should be used to fix failures in Indexing Service (p. 316).

Implements Arc::DataPoint (p. 118).

6.40.2.20 virtual DataStatus Arc::DataPointDirect::PreUnregister (bool replication) [virtual]

Index Service (p. 316) preunregistration.

Should be called if file transfer failed. It removes changes made by PreRegister.

Parameters:

replication if true, the file is being replicated between two locations registered in Indexing Service (p. 316) under same name.

Implements Arc::DataPoint (p. 119).

6.40.2.21 virtual bool Arc::DataPointDirect::ProvidesMeta () [virtual]

If endpoint can provide at least some meta information directly.

Implements Arc::DataPoint (p. 119).

6.40.2.22 virtual void Arc::DataPointDirect::Range (unsigned long long int *start* = 0, unsigned long long int *end* = 0) [virtual]

Set range of bytes to retrieve.

Default values correspond to whole file.

Implements Arc::DataPoint (p. 119).

6.40.2.23 virtual void Arc::DataPointDirect::ReadOutOfOrder (bool v) [virtual]

Parameters:

v true if allowed (default is false).

Implements Arc::DataPoint (p. 119).

6.40.2.24 virtual bool Arc::DataPointDirect::Registered () const [virtual]

Check if file is registered in Indexing Service (p. 316).

Proper value is obtainable only after Resolve.

Implements Arc::DataPoint (p. 119).

6.40.2.25 virtual DataStatus Arc::DataPointDirect::RemoveLocation () [virtual]

Remove current URL from list.

Implements Arc::DataPoint (p. 119).

6.40.2.26 virtual DataStatus Arc::DataPointDirect::RemoveLocations (const DataPoint & p) [virtual]

Remove locations present in another DataPoint (p. 111) object.

Implements Arc::DataPoint (p. 120).

6.40.2.27 virtual DataStatus Arc::DataPointDirect::Resolve (bool source) [virtual]

Resolves index service URL into list of ordinary URLs.

Also obtains meta information about the file.

Parameters:

source true if DataPoint (p. 111) object represents source of information.

Implements Arc::DataPoint (p. 120).

6.40.2.28 virtual void Arc::DataPointDirect::SetAdditionalChecks (bool v) [virtual]

Allow/disallow additional checks.

Check for existance of remote file (and probably other checks too) before initiating reading and writing operations.

Parameters:

v true if allowed (default is true).

Implements Arc::DataPoint (p. 120).

6.40.2.29 virtual void Arc::DataPointDirect::SetSecure (bool v) [virtual]

Allow/disallow heavy security during data transfer.

Parameters:

v true if allowed (default depends on protocol).

Implements Arc::DataPoint (p. 121).

6.40.2.30 virtual void Arc::DataPointDirect::SortLocations (const std::string &, const URLMap &) [inline, virtual]

Sort locations according to the specified pattern.

Parameters:

pattern a set of strings, separated by |, to match against.

Implements Arc::DataPoint (p. 121).

6.40.2.31 virtual DataStatus Arc::DataPointDirect::Unregister (bool all) [virtual]

Index Service (p. 316) unregistration.

Remove information about file registered in Indexing Service (p. 316).

Parameters:

all if true, information about file itself is (LFN) is removed. Otherwise only particular physical instance is unregistered.

Implements Arc::DataPoint (p. 122).

6.40.2.32 virtual bool Arc::DataPointDirect::WriteOutOfOrder () [virtual]

Returns true if URL can accept scattered data for *writing* operation.

Implements Arc::DataPoint (p. 123).

The documentation for this class was generated from the following file:


• DataPointDirect.h

6.41 Arc::DataPointIndex Class Reference

Complements DataPoint (p. 111) with attributes common for Indexing Service (p. 316) URLs.

#include <DataPointIndex.h>

Inheritance diagram for Arc::DataPointIndex::



Public Member Functions

- virtual const URL & CurrentLocation () const
- virtual const std::string & CurrentLocationMetadata () const
- virtual DataStatus CompareLocationMetadata () const
- virtual bool NextLocation ()
- virtual bool LocationValid () const
- virtual bool HaveLocations () const
- virtual bool LastLocation ()
- virtual DataStatus RemoveLocation ()
- virtual DataStatus RemoveLocations (const DataPoint &p)
- virtual DataStatus AddLocation (const URL &url, const std::string &meta)
- virtual void SortLocations (const std::string &pattern, const URLMap &url_map)
- virtual bool IsIndex () const
- virtual bool AcceptsMeta ()
- virtual bool ProvidesMeta ()
- virtual void SetMeta (const DataPoint &p)
- virtual void SetCheckSum (const std::string &val)
- virtual void SetSize (const unsigned long long int val)
- virtual bool Registered () const
- virtual void SetTries (const int n)
- virtual long long int BufSize () const
- virtual int BufNum () const
- virtual bool Local () const
- virtual DataStatus StartReading (DataBuffer &buffer)
- virtual DataStatus StartWriting (DataBuffer &buffer, DataCallback *space_cb=NULL)
- virtual DataStatus StopReading ()
- virtual DataStatus StopWriting ()
- virtual DataStatus Check ()
- virtual DataStatus Remove ()
- virtual void ReadOutOfOrder (bool v)
- virtual bool WriteOutOfOrder ()
- virtual void SetAdditionalChecks (bool v)
- virtual bool GetAdditionalChecks () const

- virtual void SetSecure (bool v)
- virtual bool GetSecure () const
- virtual DataPointAccessLatency GetAccessLatency () const
- virtual void Passive (bool v)
- virtual void Range (unsigned long long int start=0, unsigned long long int end=0)
- virtual int AddCheckSumObject (CheckSum *cksum)

6.41.1 Detailed Description

Complements DataPoint (p. 111) with attributes common for Indexing Service (p. 316) URLs.

It should never be used directly. Instead inherit from it to provide a class for specific a Indexing Service (p. 316).

6.41.2 Member Function Documentation

```
6.41.2.1 virtual bool Arc::DataPointIndex::AcceptsMeta () [virtual]
```

If endpoint can have any use from meta information.

Implements Arc::DataPoint (p. 113).

6.41.2.2 virtual int Arc::DataPointIndex::AddCheckSumObject (CheckSum * cksum) [virtual]

Add a checksum object which will compute checksum during transmission.

Parameters:

cksum object which will compute checksum. Should not be destroyed till DataPointer itself.

Returns:

integer position in the list of checksum objects.

Implements Arc::DataPoint (p. 113).

6.41.2.3 virtual DataStatus Arc::DataPointIndex::AddLocation (const URL & url, const std::string & meta) [virtual]

Add URL to list.

Parameters:

```
url Location URL to add.meta Location meta information.
```

Implements Arc::DataPoint (p. 114).

6.41.2.4 virtual int Arc::DataPointIndex::BufNum () const [virtual]

Get suggested number of buffers for transfers.

Implements Arc::DataPoint (p. 114).

6.41.2.5 virtual long long int Arc::DataPointIndex::BufSize () const [virtual]

Get suggested buffer size for transfers.

Implements Arc::DataPoint (p. 114).

6.41.2.6 virtual DataStatus Arc::DataPointIndex::Check () [virtual]

Query the DataPoint (p. 111) to check if object is accessible.

If possible this method will also try to provide meta information about the object.

Implements Arc::DataPoint (p. 114).

6.41.2.7 virtual DataStatus Arc::DataPointIndex::CompareLocationMetadata () **const** [virtual]

Compare metadata of DataPoint (p. 111) and current location.

Returns inconsistency error or error encountered during operation, or success

Implements Arc::DataPoint (p. 115).

6.41.2.8 virtual const URL& Arc::DataPointIndex::CurrentLocation () const [virtual]

Returns current (resolved) URL.

Implements Arc::DataPoint (p. 115).

 $\textbf{6.41.2.9} \quad \textbf{virtual const std::string\& Arc::DataPointIndex::CurrentLocationMetadata () const} \\ \text{[virtual]}$

Returns meta information used to create current URL.

Usage differs between different indexing services.

Implements Arc::DataPoint (p. 115).

6.41.2.10 virtual DataPointAccessLatency Arc::DataPointIndex::GetAccessLatency () const [virtual]

Get value of meta-information 'access latency'.

Reimplemented from Arc::DataPoint (p. 115).

6.41.2.11 virtual bool Arc::DataPointIndex::GetAdditionalChecks () const [virtual]

Check if additional checks before will be performed.

Implements Arc::DataPoint (p. 116).

6.41.2.12 virtual bool Arc::DataPointIndex::GetSecure () const [virtual]

Check if heavy security during data transfer is allowed.

```
Implements Arc::DataPoint (p. 116).
6.41.2.13 virtual bool Arc::DataPointIndex::HaveLocations () const [virtual]
Returns true if number of resolved URLs is not 0.
Implements Arc::DataPoint (p. 117).
6.41.2.14 virtual bool Arc::DataPointIndex::IsIndex () const [virtual]
Check if URL is an Indexing Service (p. 316).
Implements Arc::DataPoint (p. 117).
6.41.2.15 virtual bool Arc::DataPointIndex::LastLocation () [virtual]
Returns true if the current location is the last.
Implements Arc::DataPoint (p. 117).
6.41.2.16 virtual bool Arc::DataPointIndex::Local () const [virtual]
Returns true if file is local, e.g. file:// urls.
Implements Arc::DataPoint (p. 117).
6.41.2.17 virtual bool Arc::DataPointIndex::LocationValid () const [virtual]
Returns false if out of retries.
Implements Arc::DataPoint (p. 117).
6.41.2.18 virtual bool Arc::DataPointIndex::NextLocation () [virtual]
Switch to next location in list of URLs.
At last location switch to first if number of allowed retries is not exceeded. Returns false if no retries
Implements Arc::DataPoint (p. 117).
6.41.2.19 virtual void Arc::DataPointIndex::Passive (bool v) [virtual]
Request passive transfers for FTP-like protocols.
Parameters:
    true to request.
```

Implements Arc::DataPoint (p. 118).

6.41.2.20 virtual bool Arc::DataPointIndex::ProvidesMeta() [virtual]

If endpoint can provide at least some meta information directly.

Implements Arc::DataPoint (p. 119).

6.41.2.21 virtual void Arc::DataPointIndex::Range (unsigned long long int *start* = 0, unsigned long long int *end* = 0) [virtual]

Set range of bytes to retrieve.

Default values correspond to whole file.

Implements Arc::DataPoint (p. 119).

6.41.2.22 virtual void Arc::DataPointIndex::ReadOutOfOrder (bool v) [virtual]

Parameters:

v true if allowed (default is false).

Implements Arc::DataPoint (p. 119).

6.41.2.23 virtual bool Arc::DataPointIndex::Registered () const [virtual]

Check if file is registered in Indexing Service (p. 316).

Proper value is obtainable only after Resolve.

Implements Arc::DataPoint (p. 119).

6.41.2.24 virtual DataStatus Arc::DataPointIndex::Remove () [virtual]

Remove/delete object at URL.

Implements Arc::DataPoint (p. 119).

6.41.2.25 virtual DataStatus Arc::DataPointIndex::RemoveLocation () [virtual]

Remove current URL from list.

Implements Arc::DataPoint (p. 119).

6.41.2.26 virtual DataStatus Arc::DataPointIndex::RemoveLocations (const DataPoint & p) [virtual]

Remove locations present in another DataPoint (p. 111) object.

Implements Arc::DataPoint (p. 120).

6.41.2.27 virtual void Arc::DataPointIndex::SetAdditionalChecks (bool v) [virtual]

Allow/disallow additional checks.

Check for existance of remote file (and probably other checks too) before initiating reading and writing operations.

Parameters:

```
v true if allowed (default is true).
```

Implements Arc::DataPoint (p. 120).

6.41.2.28 virtual void Arc::DataPointIndex::SetCheckSum (const std::string & val) [virtual]

Set value of meta-information 'checksum'.

Reimplemented from Arc::DataPoint (p. 120).

6.41.2.29 virtual void Arc::DataPointIndex::SetMeta (const DataPoint & p) [virtual]

Copy meta information from another object.

Already defined values are not overwritten.

Parameters:

p object from which information is taken.

Reimplemented from Arc::DataPoint (p. 120).

6.41.2.30 virtual void Arc::DataPointIndex::SetSecure (bool v) [virtual]

Allow/disallow heavy security during data transfer.

Parameters:

v true if allowed (default depends on protocol).

Implements Arc::DataPoint (p. 121).

6.41.2.31 virtual void Arc::DataPointIndex::SetSize (const unsigned long long int *val***)** [virtual]

Set value of meta-information 'size'.

Reimplemented from Arc::DataPoint (p. 121).

6.41.2.32 virtual void Arc::DataPointIndex::SetTries (const int *n***)** [virtual]

Set number of retries.

Reimplemented from Arc::DataPoint (p. 121).

6.41.2.33 virtual void Arc::DataPointIndex::SortLocations (const std::string & pattern, const URLMap & url_map) [virtual]

Sort locations according to the specified pattern.

Parameters:

pattern a set of strings, separated by |, to match against.

Implements Arc::DataPoint (p. 121).

6.41.2.34 virtual DataStatus Arc::DataPointIndex::StartReading (DataBuffer & buffer)

Start reading data from URL.

Separate thread to transfer data will be created. No other operation can be performed while reading is in progress.

Parameters:

buffer operation will use this buffer to put information into. Should not be destroyed before stop_reading was called and returned.

Implements Arc::DataPoint (p. 121).

```
6.41.2.35 virtual DataStatus Arc::DataPointIndex::StartWriting (DataBuffer & buffer, DataCallback * space_cb = NULL) [virtual]
```

Start writing data to URL.

Separate thread to transfer data will be created. No other operation can be performed while writing is in progress.

Parameters:

buffer operation will use this buffer to get information from. Should not be destroyed before stop_writing was called and returned.

space_cb callback which is called if there is not enough space to store data. May not implemented for all protocols.

Implements Arc::DataPoint (p. 122).

```
6.41.2.36 virtual DataStatus Arc::DataPointIndex::StopReading () [virtual]
```

Stop reading.

Must be called after corresponding start_reading method, either after all data is transferred or to cancel transfer. Use buffer object to find out when data is transferred. Must return failure if any happened during transfer.

Implements Arc::DataPoint (p. 122).

```
6.41.2.37 virtual DataStatus Arc::DataPointIndex::StopWriting() [virtual]
```

Stop writing.

Must be called after corresponding start_writing method, either after all data is transferred or to cancel transfer. Use buffer object to find out when data is transferred. Must return failure if any happened during transfer.

Implements Arc::DataPoint (p. 122).

6.41.2.38 virtual bool Arc::DataPointIndex::WriteOutOfOrder () [virtual]

Returns true if URL can accept scattered data for *writing* operation.

Implements Arc::DataPoint (p. 123).

The documentation for this class was generated from the following file:

• DataPointIndex.h

6.42 Arc::DataSpeed Class Reference

Keeps track of average and instantaneous transfer speed.

#include <DataSpeed.h>

Public Member Functions

- DataSpeed (time t base=DATASPEED AVERAGING PERIOD)
- DataSpeed (unsigned long long int min_speed, time_t min_speed_time, unsigned long long int min_average_speed, time_t max_inactivity_time, time_t base=DATASPEED_AVERAGING_-PERIOD)
- ∼DataSpeed (void)
- · void verbose (bool val)
- void verbose (const std::string &prefix)
- bool verbose (void)
- void set_min_speed (unsigned long long int min_speed, time_t min_speed_time)
- void set_min_average_speed (unsigned long long int min_average_speed)
- void set_max_inactivity_time (time_t max_inactivity_time)
- time_t get_max_inactivity_time ()
- void set_base (time_t base_=DATASPEED_AVERAGING_PERIOD)
- void set_max_data (unsigned long long int max=0)
- void set_progress_indicator (show_progress_t func=NULL)
- void reset (void)
- bool transfer (unsigned long long int n=0)
- void hold (bool disable)
- bool min_speed_failure ()
- bool min_average_speed_failure ()
- bool max_inactivity_time_failure ()
- unsigned long long int transferred_size (void)

6.42.1 Detailed Description

Keeps track of average and instantaneous transfer speed.

Also detects data transfer inactivity and other transfer timeouts.

6.42.2 Constructor & Destructor Documentation

6.42.2.1 Arc::DataSpeed::DataSpeed (time_t *base* = DATASPEED_AVERAGING_PERIOD)

Constructor

Parameters:

base time period used to average values (default 1 minute).

6.42.2.2 Arc::DataSpeed::DataSpeed (unsigned long long int min_speed, time_t min_speed_time, unsigned long long int min_average_speed, time_t max_inactivity_time, time_t base = DATASPEED_AVERAGING_PERIOD)

Constructor

Parameters:

base time period used to average values (default 1 minute).

min_speed minimal allowed speed (Butes per second). If speed drops and holds below threshold for min_speed_time_ seconds error is triggered.

min_speed_time

min_average_speed_ minimal average speed (Bytes per second) to trigger error. Averaged over whole current transfer time.

max_inactivity_time - if no data is passing for specified amount of time (seconds), error is triggered.

6.42.2.3 Arc::DataSpeed::~DataSpeed (void)

Destructor.

6.42.3 Member Function Documentation

6.42.3.1 time_t Arc::DataSpeed::get_max_inactivity_time() [inline]

Get inactivity timeout.

6.42.3.2 void Arc::DataSpeed::hold (bool disable)

Turn off speed control.

Parameters:

disable true to turn off.

6.42.3.3 bool Arc::DataSpeed::max_inactivity_time_failure() [inline]

Check if maximal inactivity time error was triggered.

6.42.3.4 bool Arc::DataSpeed::min_average_speed_failure() [inline]

Check if minimal average speed error was triggered.

6.42.3.5 bool Arc::DataSpeed::min_speed_failure() [inline]

Check if minimal speed error was triggered.

6.42.3.6 void Arc::DataSpeed::reset (void)

Reset all counters and triggers.

6.42.3.7 void Arc::DataSpeed::set_base (**time_t** *base_* = DATASPEED_AVERAGING_PERIOD)

Set averaging time period.

Parameters:

base time period used to average values (default 1 minute).

6.42.3.8 void Arc::DataSpeed::set_max_data (unsigned long long int *max* = 0)

Set amount of data to be transferred. Used in verbose messages.

Parameters:

max amount of data in bytes.

6.42.3.9 void Arc::DataSpeed::set_max_inactivity_time (time_t max_inactivity_time)

Set inactivity tiemout.

Parameters:

max_inactivity_time - if no data is passing for specified amount of time (seconds), error is triggered.

6.42.3.10 void Arc::DataSpeed::set_min_average_speed (unsigned long long int min_average_speed)

Set minmal avaerage speed.

Parameters:

min_average_speed_ minimal average speed (Bytes per second) to trigger error. Averaged over whole current transfer time.

6.42.3.11 void Arc::DataSpeed::set_min_speed (unsigned long long int min_speed, time_t min_speed_time)

Set minimal allowed speed.

Parameters:

min_speed minimal allowed speed (Butes per second). If speed drops and holds below threshold for min_speed_time_ seconds error is triggered.

min_speed_time

6.42.3.12 void Arc::DataSpeed::set_progress_indicator (show_progress_t func = NULL)

Specify which external function will print verbose messages. If not specified internal one is used.

Parameters:

pointer to function which prints information.

6.42.3.13 bool Arc::DataSpeed::transfer (unsigned long long int n = 0)

Inform object, about amount of data has been transferred. All errors are triggered by this method. To make them work application must call this method periodically even with zero value.

Parameters:

n amount of data transferred (bytes).

6.42.3.14 unsigned long long int Arc::DataSpeed::transferred_size (void) [inline]

Returns amount of data this object knows about.

6.42.3.15 bool Arc::DataSpeed::verbose (void)

Check if speed information is going to be printed.

6.42.3.16 void Arc::DataSpeed::verbose (const std::string & prefix)

Print information about current speed and amout of data.

Parameters:

'prefix' add this string at the beginning of every string.

6.42.3.17 void Arc::DataSpeed::verbose (bool val)

Activate printing information about current time speeds, amount of transferred data.

The documentation for this class was generated from the following file:

• DataSpeed.h

6.43 Arc::DataStatus Class Reference

#include <DataStatus.h>

Public Types

- Success = 0
- ReadAcquireError = 1
- WriteAcquireError = 2
- ReadResolveError = 3
- WriteResolveError = 4
- ReadStartError = 5
- WriteStartError = 6
- ReadError = 7
- WriteError = 8
- TransferError = 9
- ReadStopError = 10
- WriteStopError = 11
- PreRegisterError = 12
- PostRegisterError = 13
- UnregisterError = 14
- **CacheError** = **15**
- CredentialsExpiredError = 16
- DeleteError = 17
- NoLocationError = 18
- LocationAlreadyExistsError = 19
- NotSupportedForDirectDataPointsError = 20
- UnimplementedError = 21
- IsReadingError = 22
- IsWritingError = 23
- CheckError = 24
- **ListError** = 25
- NotInitializedError = 26
- **SystemError** = **27**
- StageError = 28
- InconsistentMetadataError = 29
- UnknownError = 30
- enum DataStatusType {

Success = 0, ReadAcquireError = 1, WriteAcquireError = 2, ReadResolveError = 3,

WriteResolveError = 4, ReadStartError = 5, WriteStartError = 6, ReadError = 7,

WriteError = 8, TransferError = 9, ReadStopError = 10, WriteStopError = 11,

PreRegisterError = 12, PostRegisterError = 13, UnregisterError = 14, CacheError = 15,

CredentialsExpiredError = 16, DeleteError = 17, NoLocationError = 18, LocationAlready-ExistsError = 19,

NotSupportedForDirectDataPointsError = 20, UnimplementedError = 21, IsReadingError = 22, IsWritingError = 23,

CheckError = 24, ListError = 25, NotInitializedError = 26, SystemError = 27,

StageError = 28, InconsistentMetadataError = 29, UnknownError = 30}

6.43.1 Detailed Description

A class to be used for return types of all major data handling methods. It describes the outcome of the method.

6.43.2 Member Enumeration Documentation

6.43.2.1 enum Arc::DataStatus::DataStatusType

Enumerator:

Success Operation completed successfully.

ReadAcquireError Source is bad URL or can't be used due to some reason.

WriteAcquireError Destination is bad URL or can't be used due to some reason.

ReadResolveError Resolving of index service URL for source failed.

WriteResolveError Resolving of index service URL for destination failed.

ReadStartError Can't read from source.

WriteStartError Can't write to destination.

ReadError Failed while reading from source.

WriteError Failed while writing to destination.

TransferError Failed while transfering data (mostly timeout).

ReadStopError Failed while finishing reading from source.

WriteStopError Failed while finishing writing to destination.

PreRegisterError First stage of registration of index service URL failed.

PostRegisterError Last stage of registration of index service URL failed.

UnregisterError Unregistration of index service URL failed.

CacheError Error in caching procedure.

Credentials Expired Error due to provided credentials are expired.

DeleteError Error deleting location or URL.

NoLocationError No valid location available.

LocationAlreadyExistsError No valid location available.

NotSupportedForDirectDataPointsError Operation has no sense for this kind of URL.

UnimplementedError Feature is unimplemented.

IsReadingError DataPoint (p. 111) is already reading.

IsWritingError DataPoint (p. 111) is already writing.

CheckError Access check failed.

ListError File listing failed.

NotInitializedError Object initialization failed.

SystemError Error in OS.

StageError Staging error.

InconsistentMetadataError Inconsistent metadata.

UnknownError Undefined.


The documentation for this class was generated from the following file:

• DataStatus.h

6.44 ArcSec::DateTimeAttribute Class Reference

#include <DateTimeAttribute.h>

Inheritance diagram for ArcSec::DateTimeAttribute::



Public Member Functions

- virtual bool equal (AttributeValue *other, bool check_id=true)
- virtual std::string encode ()
- virtual std::string getType ()
- virtual std::string getId ()

6.44.1 Detailed Description

Format: YYYYMMDDHHMMSSZ Day Month DD HH:MM:SS YYYY YYYY-MM-DD HH:MM:SS YYYY-MM-DDTHH:MM:SS+HH:MM YYYY-MM-DDTHH:MM:SSZ

6.44.2 Member Function Documentation

6.44.2.1 virtual std::string ArcSec::DateTimeAttribute::encode () [virtual]

encode the value in a string format

Implements ArcSec::AttributeValue (p. 53).

6.44.2.2 virtual bool ArcSec::DateTimeAttribute::equal (AttributeValue * *other*, **bool** *check_id* = true) [virtual]

Evaluate whether "this" is equal to the parameter value

Implements ArcSec::AttributeValue (p. 53).

6.44.2.3 virtual std::string ArcSec::DateTimeAttribute::getId () [inline, virtual]

Get the AttributeId of the <Attribute>

Implements ArcSec::AttributeValue (p. 54).

6.44.2.4 virtual std::string ArcSec::DateTimeAttribute::getType () [inline, virtual]

Get the DataType of the <Attribute>

Implements ArcSec::AttributeValue (p. 54).


The documentation for this class was generated from the following file:

• DateTimeAttribute.h

6.45 Arc::DelegationConsumer Class Reference

#include <DelegationInterface.h>

Inheritance diagram for Arc::DelegationConsumer::



Public Member Functions

- DelegationConsumer (void)
- DelegationConsumer (const std::string &content)
- const std::string & ID (void)
- bool Backup (std::string &content)
- bool Restore (const std::string &content)
- bool Request (std::string &content)
- bool Acquire (std::string &content)
- bool Acquire (std::string &content, std::string &identity)

Protected Member Functions

- bool Generate (void)
- void LogError (void)

6.45.1 Detailed Description

A consumer of delegated X509 credentials. During delegation procedure this class acquires delegated credentials aka proxy - certificate, private key and chain of previous certificates. Delegation procedure consists of calling Request() (p. 148) method for generating certificate request followed by call to Acquire() (p. 148) method for making complete credentials from certificate chain.

6.45.2 Constructor & Destructor Documentation

6.45.2.1 Arc::DelegationConsumer::DelegationConsumer (void)

Creates object with new private key

6.45.2.2 Arc::DelegationConsumer::DelegationConsumer (const std::string & content)

Creates object with provided private key

6.45.3 Member Function Documentation

6.45.3.1 bool Arc::DelegationConsumer::Acquire (std::string & content, std::string & identity)

Includes the functionality in Acquire(content); pluse extracting the credential identity

6.45.3.2 bool Arc::DelegationConsumer::Acquire (std::string & content)

Ads private key into certificates chain in 'content' On exit content contains complete delegated credentials.

6.45.3.3 bool Arc::DelegationConsumer::Backup (std::string & content)

Stores content of this object into a string

6.45.3.4 bool Arc::DelegationConsumer::Generate (void) [protected]

Private key

6.45.3.5 const std::string& Arc::DelegationConsumer::ID (void)

Return identifier of this object - not implemented

6.45.3.6 void Arc::DelegationConsumer::LogError (void) [protected]

Creates private key

6.45.3.7 bool Arc::DelegationConsumer::Request (std::string & content)

Make X509 certificate request from internal private key

6.45.3.8 bool Arc::DelegationConsumer::Restore (const std::string & content)

Restores content of object from string


The documentation for this class was generated from the following file:

• DelegationInterface.h

6.46 Arc::DelegationConsumerSOAP Class Reference

#include <DelegationInterface.h>

Inheritance diagram for Arc::DelegationConsumerSOAP::



Public Member Functions

- DelegationConsumerSOAP (void)
- DelegationConsumerSOAP (const std::string &content)
- bool DelegateCredentialsInit (const std::string &id, const SOAPEnvelope &in, SOAPEnvelope &out)
- bool UpdateCredentials (std::string &credentials, const SOAPEnvelope &in, SOAPEnvelope &out)
- bool UpdateCredentials (std::string &credentials, std::string &identity, const SOAPEnvelope &in, SOAPEnvelope &out)
- bool DelegatedToken (std::string &credentials, XMLNode token)

6.46.1 Detailed Description

This class extends DelegationConsumer (p.147) to support SOAP message exchange. Implements WS interface http://www.nordugrid.org/schemas/delegation described in delegation.wsdl.

6.46.2 Constructor & Destructor Documentation

6.46.2.1 Arc::DelegationConsumerSOAP::DelegationConsumerSOAP (void)

Creates object with new private key

6.46.2.2 Arc::DelegationConsumerSOAP::DelegationConsumerSOAP (const std::string & content)

Creates object with specified private key

6.46.3 Member Function Documentation

6.46.3.1 bool Arc::DelegationConsumerSOAP::DelegateCredentialsInit (const std::string & id, const SOAPEnvelope & in, SOAPEnvelope & out)

Process SOAP message which starts delagation. Generated message in 'out' is meant to be sent back to DelagationProviderSOAP. Argument 'id' contains identifier of procedure and is used only to produce SOAP message.

6.46.3.2 bool Arc::DelegationConsumerSOAP::DelegatedToken (std::string & credentials, XMLNode token)

Similar to UpdateCredentials but takes only DelegatedToken XML element

6.46.3.3 bool Arc::DelegationConsumerSOAP::UpdateCredentials (std::string & credentials, std::string & identity, const SOAPEnvelope & in, SOAPEnvelope & out)

Includes the functionality in above UpdateCredentials method; plus extracting the credential identity

6.46.3.4 bool Arc::DelegationConsumerSOAP::UpdateCredentials (std::string & credentials, const SOAPEnvelope & in, SOAPEnvelope & out)

Accepts delegated credentials. Process 'in' SOAP message and stores full proxy credentials in 'credentials'. 'out' message is generated for sending to DelagationProviderSOAP.

The documentation for this class was generated from the following file:

• DelegationInterface.h

6.47 Arc::DelegationContainerSOAP Class Reference

#include <DelegationInterface.h>

Public Member Functions

- bool DelegateCredentialsInit (const SOAPEnvelope &in, SOAPEnvelope &out)
- bool UpdateCredentials (std::string &credentials, const SOAPEnvelope &in, SOAPEnvelope &out)
- bool DelegatedToken (std::string &credentials, XMLNode token)

Protected Attributes

- int max size
- int max_duration_
- int max_usage_
- · bool context_lock_
- bool restricted

6.47.1 Detailed Description

Manages multiple delegated credentials. Delegation consumers are created automatically with DelegateCredentialsInit method up to max_size_ and assigned unique identifier. It's methods are similar to those of **DelegationConsumerSOAP** (p.149) with identifier included in SOAP message used to route execution to one of managed **DelegationConsumerSOAP** (p.149) instances.

6.47.2 Member Function Documentation

6.47.2.1 bool Arc::DelegationContainerSOAP::DelegateCredentialsInit (const SOAPEnvelope & in, SOAPEnvelope & out)

See DelegationConsumerSOAP::DelegateCredentialsInit (p. 149)

6.47.2.2 bool Arc::DelegationContainerSOAP::DelegatedToken (std::string & credentials, XMLNode token)

See DelegationConsumerSOAP::DelegatedToken (p. 150)

6.47.2.3 bool Arc::DelegationContainerSOAP::UpdateCredentials (std::string & credentials, const SOAPEnvelope & in, SOAPEnvelope & out)

See DelegationConsumerSOAP::UpdateCredentials (p.150)

6.47.3 Field Documentation

6.47.3.1 bool Arc::DelegationContainerSOAP::context_lock_ [protected]

If true delegation consumer is deleted when connection context is destroyed

6.47.3.2 int Arc::DelegationContainerSOAP::max_duration_ [protected]

Lifetime of unused delegation consumer

6.47.3.3 int Arc::DelegationContainerSOAP::max_size_ [protected]

Max. number of delegation consumers

6.47.3.4 int Arc::DelegationContainerSOAP::max_usage_ [protected]

Max. times same delegation consumer may accept credentials

6.47.3.5 bool Arc::DelegationContainerSOAP::restricted_ [protected]

If true all delegation phases must be performed by same identity


The documentation for this class was generated from the following file:

• DelegationInterface.h

6.48 Arc::DelegationProvider Class Reference

#include <DelegationInterface.h>

Inheritance diagram for Arc::DelegationProvider::



Public Member Functions

- DelegationProvider (const std::string &credentials)
- DelegationProvider (const std::string &cert_file, const std::string &key_file, std::istream *inpwd=NULL)
- std::string Delegate (const std::string &request, const DelegationRestrictions &restrictions=DelegationRestrictions())

6.48.1 Detailed Description

A provider of delegated credentials. During delegation procedure this class generates new credential to be used in proxy/delegated credential.

6.48.2 Constructor & Destructor Documentation

6.48.2.1 Arc::DelegationProvider::DelegationProvider (const std::string & credentials)

Creates instance from provided credentials. Credentials are used to sign delegated credentials. Arguments should contain PEM-encoded certificate, private key and optionally certificates chain.

6.48.2.2 Arc::DelegationProvider::DelegationProvider (const std::string & cert_file, const std::string & key_file, std::istream * inpwd = NULL)

Creates instance from provided credentials. Credentials are used to sign delegated credentials. Arguments should contain filesystem path to PEM-encoded certificate and private key. Optionally cert_file may contain certificates chain.

6.48.3 Member Function Documentation

6.48.3.1 std::string Arc::DelegationProvider::Delegate (const std::string & request, const DelegationRestrictions & restrictions = DelegationRestrictions())

Perform delegation. Takes X509 certificate request and creates proxy credentials excluding private key. Result is then to be fed into **Delegation-Consumer::Acquire** (p.148)


The documentation for this class was generated from the following file:

154	Hosting Environment (Daemon) Data Structure Documentation
• DelegationInterface.h	
Delegacioninectiace.	

6.49 Arc::DelegationProviderSOAP Class Reference

#include <DelegationInterface.h>

Inheritance diagram for Arc::DelegationProviderSOAP::



Public Member Functions

- DelegationProviderSOAP (const std::string &credentials)
- DelegationProviderSOAP (const std::string &cert_file, const std::string &key_file, std::istream *inpwd=NULL)
- bool DelegateCredentialsInit (MCCInterface &mcc interface, MessageContext *context)
- bool DelegateCredentialsInit (MCCInterface &mcc_interface, MessageAttributes *attributes_in, MessageAttributes *attributes_out, MessageContext *context)
- bool UpdateCredentials (MCCInterface &mcc_interface, MessageContext *context, const DelegationRestrictions &restrictions=DelegationRestrictions())
- bool UpdateCredentials (MCCInterface &mcc_interface, MessageAttributes *attributes_in, MessageAttributes *attributes_out, MessageContext *context, const DelegationRestrictions &restrictions=DelegationRestrictions())
- bool DelegatedToken (XMLNode parent)
- const std::string & ID (void)

6.49.1 Detailed Description

Extension of DelegationProvider (p.153) with SOAP exchange interface. This class is also a temporary container for intermediate information used during delegation procedure.

6.49.2 Constructor & Destructor Documentation

6.49.2.1 Arc::DelegationProviderSOAP::DelegationProviderSOAP (const std::string & credentials)

Creates instance from provided credentials. Credentials are used to sign delegated credentials.

6.49.2.2 Arc::DelegationProviderSOAP::DelegationProviderSOAP (const std::string & cert_file, const std::string & key_file, std::istream * inpwd = NULL)

Creates instance from provided credentials. Credentials are used to sign delegated credentials. Arguments should contain filesystem path to PEM-encoded certificate and private key. Optionally cert_file may contain certificates chain.

6.49.3 Member Function Documentation

6.49.3.1 bool Arc::DelegationProviderSOAP::DelegateCredentialsInit (MCCInterface & mcc_interface, MessageAttributes * attributes_in, MessageAttributes * attributes_out, MessageContext * context)

Extended version of DelegateCredentialsInit(MCCInterface&,Message-Context*) (p.156). Additionally takes attributes for request and response message to make fine control on message processing possible.

6.49.3.2 bool Arc::DelegationProviderSOAP::DelegateCredentialsInit (MCCInterface & mcc interface, MessageContext * context)

Performs DelegateCredentialsInit SOAP operation. As result request for delegated credentials is received by this instance and stored internally. Call to Update-Credentials should follow.

6.49.3.3 bool Arc::DelegationProviderSOAP::DelegatedToken (XMLNode parent)

Generates DelegatedToken element. Element is created as child of provided XML element and contains structure described in delegation.wsdl.

6.49.3.4 const std::string& Arc::DelegationProviderSOAP::ID (void) [inline]

Returns the identifier by service accepting delegated credentials. This identifier may then be used to refer to credentials stored at service.

6.49.3.5 bool Arc::DelegationProviderSOAP::UpdateCredentials (MCCInterface & mcc_interface, MessageAttributes * attributes_in, MessageAttributes * attributes_out, MessageContext * context, const DelegationRestrictions & restrictions = DelegationRestrictions())

Extended version of UpdateCredentials(MCCInterface%, MessageContext*). Additionally takes attributes for request and response message to make fine control on message processing possible.

6.49.3.6 bool Arc::DelegationProviderSOAP::UpdateCredentials (MCCInterface & mcc_interface, MessageContext * context, const DelegationRestrictions & restrictions = DelegationRestrictions())

Performs UpdateCredentials SOAP operation. This concludes delegation procedure and passes delagated credentials to **DelegationConsumerSOAP** (p.149) instance.

The documentation for this class was generated from the following file:


• DelegationInterface.h

6.50 ArcSec::DenyOverridesCombiningAlg Class Reference

Implement the "Deny-Overrides" algorithm.

#include <DenyOverridesAlg.h>

Inheritance diagram for ArcSec::DenyOverridesCombiningAlg::



Public Member Functions

- virtual Result combine (EvaluationCtx *ctx, std::list< Policy * > policies)
- virtual const std::string & getalgId (void) const

6.50.1 Detailed Description

Implement the "Deny-Overrides" algorithm.

Deny-Overrides, scans the policy set which is given as the parameters of "combine" method, if gets "deny" result from any policy, then stops scanning and gives "deny" as result, otherwise gives "permit".

6.50.2 Member Function Documentation

6.50.2.1 virtual Result ArcSec::DenyOverridesCombiningAlg::combine (EvaluationCtx * ctx, std::list< Policy * > policies) [virtual]

If there is one policy which return negative evaluation result, then omit the other policies and return ${\tt DECISION_DENY}$

Parameters:

ctx This object contains request information which will be used to evaluated against policy.

policlies This is a container which contains policy objects.

Returns:

The combined result according to the algorithm.

Implements ArcSec::CombiningAlg (p. 74).

6.50.2.2 virtual const std::string& ArcSec::DenyOverridesCombiningAlg::getalgId (void) const [inline, virtual]

Get the identifier

Implements ArcSec::CombiningAlg (p. 74).


The documentation for this class was generated from the following file:

• DenyOverridesAlg.h

6.51 ArcSec::DurationAttribute Class Reference

#include <DateTimeAttribute.h>

Inheritance diagram for ArcSec::DurationAttribute::



Public Member Functions

- virtual bool equal (AttributeValue *other, bool check_id=true)
- virtual std::string encode ()
- virtual std::string getType ()
- virtual std::string getId ()

6.51.1 Detailed Description

Formate: P??Y??M??DT??H??M??S

6.51.2 Member Function Documentation

6.51.2.1 virtual std::string ArcSec::DurationAttribute::encode () [virtual]

encode the value in a string format

Implements ArcSec::AttributeValue (p. 53).

6.51.2.2 virtual bool ArcSec::DurationAttribute::equal (AttributeValue * *other*, **bool** *check_id* = true) [virtual]

Evaluate whether "this" is equal to the parameter value

Implements ArcSec::AttributeValue (p. 53).

6.51.2.3 virtual std::string ArcSec::DurationAttribute::getId () [inline, virtual]

Get the AttributeId of the <Attribute>

Implements ArcSec::AttributeValue (p. 54).

6.51.2.4 virtual std::string ArcSec::DurationAttribute::getType () [inline, virtual]

Get the DataType of the <Attribute>

Implements ArcSec::AttributeValue (p. 54).

The documentation for this class was generated from the following file:


160	Hosting Environment (Daemon) Data Structure Documentation
• DateTimeAttribute.h	

6.52 ArcSec::EqualFunction Class Reference

Evaluate whether the two values are equal.

#include <EqualFunction.h>

Inheritance diagram for ArcSec::EqualFunction::



Public Member Functions

- virtual AttributeValue * evaluate (AttributeValue *arg0, AttributeValue *arg1, bool check_id=true)
- virtual std::list< AttributeValue * > evaluate (std::list< AttributeValue * > args, bool check_-id=true)

Static Public Member Functions

• static std::string getFunctionName (std::string datatype)

6.52.1 Detailed Description

Evaluate whether the two values are equal.

6.52.2 Member Function Documentation

6.52.2.1 virtual std::list<AttributeValue*> ArcSec::EqualFunction::evaluate (std::list< AttributeValue * > args, bool check_id = true) [virtual]

Evaluate a list of AttributeValue (p. 53) objects, and return a list of Attribute objects Implements ArcSec::Function (p. 186).

6.52.2.2 virtual AttributeValue* ArcSec::EqualFunction::evaluate (AttributeValue * arg0, AttributeValue * arg1, bool check_id = true) [virtual]

Evaluate two AttributeValue (p. 53) objects, and return one AttributeValue (p. 53) object Implements ArcSec::Function (p. 186).

6.52.2.3 static std::string ArcSec::EqualFunction::getFunctionName (std::string *datatype*) [static]

help function to get the FunctionName

The documentation for this class was generated from the following file:

• EqualFunction.h

6.53 ArcSec::EvalResult Struct Reference

Struct to record the xml node and effect, which will be used by Evaluator $(p.\,165)$ to get the information about which rule/policy(in xmlnode) is satisfied.

#include <Result.h>

6.53.1 Detailed Description

Struct to record the xml node and effect, which will be used by Evaluator $(p.\,165)$ to get the information about which rule/policy(in xmlnode) is satisfied.

The documentation for this struct was generated from the following file:

• Result.h

6.54 ArcSec::EvaluationCtx Class Reference

EvaluationCtx (p. 164), in charge of storing some context information for.

#include <EvaluationCtx.h>

Public Member Functions

• EvaluationCtx (Request *request)

6.54.1 Detailed Description

EvaluationCtx (p. 164), in charge of storing some context information for.

6.54.2 Constructor & Destructor Documentation

6.54.2.1 ArcSec::EvaluationCtx::EvaluationCtx (Request * request) [inline]

Construct a new EvaluationCtx (p. 164) based on the given request

The documentation for this class was generated from the following file:


• EvaluationCtx.h

6.55 ArcSec::Evaluator Class Reference

Interface for policy evaluation. Execute the policy evaluation, based on the request and policy.

#include <Evaluator.h>

Inheritance diagram for ArcSec::Evaluator::



Public Member Functions

- virtual Response * evaluate (Request *request)=0
- virtual Response * evaluate (const Source & request)=0
- virtual Response * evaluate (Request *request, const Source &policy)=0
- virtual Response * evaluate (const Source &request, const Source &policy)=0
- virtual Response * evaluate (Request *request, Policy *policyobj)=0
- virtual Response * evaluate (const Source & request, Policy *policyobj)=0
- virtual AttributeFactory * getAttrFactory ()=0
- virtual FnFactory * getFnFactory ()=0
- virtual AlgFactory * getAlgFactory ()=0
- virtual void addPolicy (const Source &policy, const std::string &id="")=0
- virtual void addPolicy (Policy *policy, const std::string &id='''')=0
- virtual void setCombiningAlg (EvaluatorCombiningAlg alg)=0
- virtual void setCombiningAlg (CombiningAlg *alg=NULL)=0
- virtual const char * getName (void) const =0

Protected Member Functions

• virtual Response * evaluate (EvaluationCtx *ctx)=0

6.55.1 Detailed Description

Interface for policy evaluation. Execute the policy evaluation, based on the request and policy.

6.55.2 Member Function Documentation

6.55.2.1 virtual void ArcSec::Evaluator::addPolicy (Policy * *policy*, **const std::string &** *id* = "") [pure virtual]

Add policy to the evaluator. Policy (p. 286) will be marked with id. The policy object is taken over by this instance and will be destroyed in destructor.

6.55.2.2 virtual void ArcSec::Evaluator::addPolicy (const Source & policy, const std::string & id = "") [pure virtual]

Add policy from specified source to the evaluator. Policy (p. 286) will be marked with id.

6.55.2.3 virtual Response* ArcSec::Evaluator::evaluate (EvaluationCtx * *ctx***)** [protected, pure virtual]

Evaluate the request by using the EvaluationCtx (p. 164) object (which includes the information about request). The ctx is destroyed inside this method (why?!?!?).

6.55.2.4 virtual Response* ArcSec::Evaluator::evaluate (const Source & request, Policy * policyobj) [pure virtual]

Evaluate the request from specified source against the specified policy. In some implementations all of the existing policie inside the evaluator may be destroyed by this method.

6.55.2.5 virtual Response* ArcSec::Evaluator::evaluate (Request * *request***, Policy *** *policyobj***)** [pure virtual]

Evaluate the specified request against the specified policy. In some implementations all of the existing policy inside the evaluator may be destroyed by this method.

6.55.2.6 virtual Response* ArcSec::Evaluator::evaluate (const Source & request, const Source & policy) [pure virtual]

Evaluate the request from specified source against the policy from specified source. In some implementations all of the existing policie inside the evaluator may be destroyed by this method.

6.55.2.7 virtual Response* ArcSec::Evaluator::evaluate (Request * *request***, const Source &** *policy***)** [pure virtual]

Evaluate the specified request against the policy from specified source. In some implementations all of the existing policies inside the evaluator may be destroyed by this method.

6.55.2.8 virtual Response* ArcSec::Evaluator::evaluate (const Source & *request***)** [pure virtual]

Evaluates the request by using a specified source

6.55.2.9 virtual Response* **ArcSec::Evaluator::evaluate (Request** * *request*) [pure virtual]

Evaluates the request by using a Request (p. 294) object. Evaluation is done till at least one of policies is satisfied.

6.55.2.10 virtual AlgFactory* ArcSec::Evaluator::getAlgFactory () [pure virtual]

Get the AlgFactory (p. 44) object

6.55.2.11 virtual AttributeFactory* ArcSec::Evaluator::getAttrFactory() [pure virtual]

Get the AttributeFactory (p. 48) object

6.55.2.12 virtual FnFactory* ArcSec::Evaluator::getFnFactory () [pure virtual]

Get the FnFactory (p. 185) object

6.55.2.13 virtual const char* ArcSec::Evaluator::getName (void) const [pure virtual]

Get the name of this evaluator

6.55.2.14 virtual void ArcSec::Evaluator::setCombiningAlg (CombiningAlg * *alg* = NULL) [pure virtual]

Specifies loadable combining algorithms. In case of multiple policies their results will be combined using this algorithm. To switch to simple algorithm specify NULL argument.

6.55.2.15 virtual void ArcSec::Evaluator::setCombiningAlg (EvaluatorCombiningAlg *alg***)** [pure virtual]

Specifies one of simple combining algorithms. In case of multiple policies their results will be combined using this algorithm.

The documentation for this class was generated from the following file:

• Evaluator.h

6.56 ArcSec::EvaluatorContext Class Reference

Context for evaluator. It includes the factories which will be used to create related objects.

#include <Evaluator.h>

Public Member Functions

- operator AttributeFactory * ()
- operator FnFactory * ()
- operator AlgFactory * ()

6.56.1 Detailed Description

Context for evaluator. It includes the factories which will be used to create related objects.

6.56.2 Member Function Documentation

6.56.2.1 ArcSec::EvaluatorContext::operator AlgFactory * () [inline]

Returns associated AlgFactory (p. 44) object

6.56.2.2 ArcSec::EvaluatorContext::operator AttributeFactory * () [inline]

Returns associated AttributeFactory (p. 48) object

6.56.2.3 ArcSec::EvaluatorContext::operator FnFactory * () [inline]

Returns associated FnFactory (p. 185) object

The documentation for this class was generated from the following file:

• Evaluator.h

6.57 ArcSec::EvaluatorLoader Class Reference

Evaluator Loader (p. 169) is implemented as a helper class for loading different Evaluator (p. 165) objects, like ArcEvaluator.

#include <EvaluatorLoader.h>

Public Member Functions

- Evaluator * getEvaluator (const std::string &classname)
- Evaluator * getEvaluator (const Policy *policy)
- Evaluator * getEvaluator (const Request *request)
- Request * getRequest (const std::string &classname, const Source &requestsource)
- Request * getRequest (const Source & requestsource)
- Policy * getPolicy (const std::string &classname, const Source &policysource)
- Policy * getPolicy (const Source &policysource)

6.57.1 Detailed Description

EvaluatorLoader (p. 169) is implemented as a helper class for loading different Evaluator (p. 165) objects, like ArcEvaluator.

The object loading is based on the configuration information about evaluator, including information for factory class, request, policy and evaluator itself

6.57.2 Member Function Documentation

6.57.2.1 Evaluator* ArcSec::EvaluatorLoader::getEvaluator (const Request * request)

Get evaluator object suitable for presented request

6.57.2.2 Evaluator* ArcSec::EvaluatorLoader::getEvaluator (const Policy * policy)

Get evaluator object suitable for presented policy

6.57.2.3 Evaluator* ArcSec::EvaluatorLoader::getEvaluator (const std::string & classname)

Get evaluator object according to the class name

6.57.2.4 Policy* ArcSec::EvaluatorLoader::getPolicy (const Source & policysource)

Get proper policy object according to the policy source

6.57.2.5 Policy* ArcSec::EvaluatorLoader::getPolicy (const std::string & classname, const Source & policysource)

Get policy object according to the class name, based on the policy source

6.57.2.6 Request* ArcSec::EvaluatorLoader::getRequest (const Source & requestsource)

Get request object according to the request source

6.57.2.7 Request* ArcSec::EvaluatorLoader::getRequest (const std::string & classname, const Source & requestsource)

Get request object according to the class name, based on the request source The documentation for this class was generated from the following file:

• EvaluatorLoader.h

6.58 Arc::ExecutionTarget Class Reference

ExecutionTarget (p. 171).

#include <ExecutionTarget.h>

Public Member Functions

- ExecutionTarget ()
- ExecutionTarget (const ExecutionTarget &target)
- ExecutionTarget (const long int addrptr)
- ExecutionTarget & operator= (const ExecutionTarget & target)
- Submitter * GetSubmitter (const UserConfig &ucfg) const
- void Update (const JobDescription &jobdesc)
- void Print (bool longlist) const

Data Fields

- std::string ComputingShareName
- int64_t MaxMainMemory
- int64_t MaxVirtualMemory
- int64_t MaxDiskSpace
- Software OperatingSystem
- std::list< ApplicationEnvironment > ApplicationEnvironments

6.58.1 Detailed Description

ExecutionTarget (p. 171).

This class describe a target which accept computing jobs. All of the members contained in this class, with a few exceptions, are directly linked to attributes defined in the GLUE Specification v. 2.0 (GFD-R-P.147).

6.58.2 Constructor & Destructor Documentation

6.58.2.1 Arc::ExecutionTarget::ExecutionTarget()

Create an ExecutionTarget (p. 171).

Default constructor to create an ExecutionTarget (p. 171). Takes no arguments.

6.58.2.2 Arc::ExecutionTarget::ExecutionTarget (const ExecutionTarget & target)

Create an ExecutionTarget (p. 171).

Copy constructor.

Parameters:

target ExecutionTarget (p. 171) to copy.

6.58.2.3 Arc::ExecutionTarget::ExecutionTarget (const long int addrptr)

Create an ExecutionTarget (p. 171).

Copy constructor? Needed from Python?

Parameters:

addrptr

6.58.3 Member Function Documentation

6.58.3.1 Submitter* Arc::ExecutionTarget::GetSubmitter (const UserConfig & ucfg) const

Get Submitter (p. 343) to the computing resource represented by the ExecutionTarget (p. 171).

Method which returns a specialized Submitter (p. 343) which can be used for submitting jobs to the computing resource represented by the ExecutionTarget (p. 171). In order to return the correct specialized Submitter (p. 343) the GridFlavour variable must be correctly set.

Parameters:

ucfg UserConfig (p. 361) object with paths to user credentials etc.

6.58.3.2 ExecutionTarget& Arc::ExecutionTarget::operator= (const ExecutionTarget & target)

Create an ExecutionTarget (p. 171).

Assignment operator

Parameters:

target is ExecutionTarget (p. 171) to copy.

6.58.3.3 void Arc::ExecutionTarget::Print (bool longlist) const

Print the ExecutionTarget (p. 171) information to std::cout.

Method to print the ExecutionTarget (p. 171) attributes to std::cout

Parameters:

longlist is true for long list printing.

6.58.3.4 void Arc::ExecutionTarget::Update (const JobDescription & jobdesc)

Update ExecutionTarget (p. 171) after successful job submission.

Method to update the ExecutionTarget (p. 171) after a job successfully has been submitted to the computing resource it represents. E.g. if a job is sent to the computing resource and is expected to enter the queue, then the WaitingJobs attribute is incremented with 1.

Parameters:

jobdesc contains all information about the job submitted.

6.58.4 Field Documentation

6.58.4.1 std::list<ApplicationEnvironment> Arc::ExecutionTarget::ApplicationEnvironments

ApplicationEnvironments.

The ApplicationEnvironments member is a list of ApplicationEnvironment's, defined in section 6.7 GLUE2.

6.58.4.2 std::string Arc::ExecutionTarget::ComputingShareName

ComputingShareName String 0..1.

Human-readable name. This variable represents the ComputingShare.Name attribute of GLUE2.

6.58.4.3 int64_t Arc::ExecutionTarget::MaxDiskSpace

MaxDiskSpace UInt64 0..1 GB.

The maximum disk space that a job is allowed use in the working; if the limit is hit, then the LRMS MAY kill the job. A negative value specifies that this member is undefined.

6.58.4.4 int64_t Arc::ExecutionTarget::MaxMainMemory

MaxMainMemory UInt64 0..1 MB.

The maximum physical RAM that a job is allowed to use; if the limit is hit, then the LRMS MAY kill the job. A negative value specifies that this member is undefined.

6.58.4.5 int64_t Arc::ExecutionTarget::MaxVirtualMemory

MaxVirtualMemory UInt64 0..1 MB.

The maximum total memory size (RAM plus swap) that a job is allowed to use; if the limit is hit, then the LRMS MAY kill the job. A negative value specifies that this member is undefined.

6.58.4.6 Software Arc::ExecutionTarget::OperatingSystem

OperatingSystem.

The OperatingSystem member is not present in GLUE2 but contains the three GLUE2 attributes OSFamily, OSName and OSVersion.

- OSFamily OSFamily_t 1 * The general family to which the Execution Environment operating * system belongs.
- OSName OSName_t 0..1 * The specific name of the operating sytem
- OSVersion String 0..1 * The version of the operating system, as defined by the vendor.

The documentation for this class was generated from the following file:

• ExecutionTarget.h

6.59 Arc::ExpirationReminder Class Reference

A class intended for internal use within counters.

#include <Counter.h>

Public Member Functions

- bool operator< (const ExpirationReminder &other) const
- Glib::TimeVal getExpiryTime () const
- Counter::IDType getReservationID () const

Friends

· class Counter

6.59.1 Detailed Description

A class intended for internal use within counters.

This class is used for "reminder objects" that are used for automatic deallocation of self-expiring reservations.

6.59.2 Member Function Documentation

6.59.2.1 Glib::TimeVal Arc::ExpirationReminder::getExpiryTime () const

Returns the expiry time.

This method returns the expiry time of the reservation that this ExpirationReminder (p. 174) is associated with.

Returns:

The expiry time.

6.59.2.2 Counter::IDType Arc::ExpirationReminder::getReservationID () const

Returns the identification number of the reservation.

This method returns the identification number of the self-expiring reservation that this Expiration-Reminder (p. 174) is associated with.

Returns:

The identification number.

6.59.2.3 bool Arc::ExpirationReminder::operator< (const ExpirationReminder & other) const

Less than operator, compares "soonness".

This is the less than operator for the ExpirationReminder (p. 174) class. It compares the priority of such objects with respect to which reservation expires first. It is used when reminder objects are inserted in a priority queue in order to allways place the next reservation to expire at the top.

6.59.3 Friends And Related Function Documentation

6.59.3.1 friend class Counter [friend]

The Counter (p. 83) class needs to be a friend.

The documentation for this class was generated from the following file:

• Counter.h

6.60 Arc::FileCache Class Reference

#include <FileCache.h>

Public Member Functions

- FileCache (std::string cache_path, std::string id, uid_t job_uid, gid_t job_gid)
- FileCache (std::vector< std::string > caches, std::string id, uid_t job_uid, gid_t job_gid)
- FileCache (std::vector< std::string > caches, std::vector< std::string > remote_caches, std::vector< std::string > draining_caches, std::string id, uid_t job_uid, gid_t job_gid, int cache max=100, int cache min=100)
- FileCache ()
- bool Start (std::string url, bool &available, bool &is_locked, bool use_remote=true)
- bool Stop (std::string url)
- bool StopAndDelete (std::string url)
- std::string File (std::string url)
- bool Link (std::string link_path, std::string url)
- bool Copy (std::string dest_path, std::string url, bool executable=false)
- bool Release ()
- bool AddDN (std::string url, std::string DN, Time expiry_time)
- bool CheckDN (std::string url, std::string DN)
- bool CheckCreated (std::string url)
- Time GetCreated (std::string url)
- bool CheckValid (std::string url)
- Time GetValid (std::string url)
- bool SetValid (std::string url, Time val)
- operator bool ()
- bool operator== (const FileCache &a)

6.60.1 Detailed Description

FileCache (p. 176) provides an interface to all cache operations to be used by external classes. An instance should be created per job, and all files within the job are managed by that instance. When it is decided a file should be downloaded to the cache, Start() (p. 180) should be called, so that the cache file can be prepared and locked. When a transfer has finished successfully, Link() (p. 179) or Copy() (p. 179) should be called to create a hard link to a per-job directory in the cache and then soft link, or copy the file directly to the session directory so it can be accessed from the user's job. Stop() (p. 180) must then be called to release any locks on the cache file.

The cache directory(ies) and the optional directory to link to when the soft-links are made are set in the global configuration file. The names of cache files are formed from a hash of the URL specified as input to the job. To ease the load on the file system, the cache files are split into subdirectories based on the first two characters in the hash. For example the file with hash 76f11edda169848038efbd9fa3df5693 is stored in 76/f11edda169848038efbd9fa3df5693. A cache filename can be found by passing the URL to Find(). For more information on the structure of the cache, see the Grid Manager Administration Guide.

A metadata file with the '.meta' suffix is stored next to each cache file. This contains the URL corresponding to the cache file and the expiry time, if it is available. For example lfc://lfc1.ndgf.org//grid/atlas/test/test1 20081007151045Z

While cache files are downloaded, they are locked by creating a lock file with the '.lock' suffix next to the cache file. Calling Start() (p. 180) creates this lock and Stop() (p. 180) releases it. All processes calling Start() (p. 180) must wait until they successfully obtain the lock before downloading can begin.

6.60.2 Constructor & Destructor Documentation

6.60.2.1 Arc::FileCache::FileCache (std::string cache_path, std::string id, uid_t job_uid, gid_t job_gid)

Create a new FileCache (p. 176) instance.

Parameters:

cache_path The format is "cache_dir[link_path]". path is the path to the cache directory and the optional link_path is used to create a link in case the cache directory is visible under a different name during actual usage. When linking from the session dir this path is used instead of cache_path.

id the job id. This is used to create the per-job dir which the job's cache files will be hard linked from

job_uid owner of job. The per-job dir will only be readable by this user job_gid owner group of job

6.60.2.2 Arc::FileCache::FileCache (std::vector< std::string > caches, std::string id, uid_t job_uid, gid_t job_gid)

Create a new FileCache (p. 176) instance with multiple cache dirs

Parameters:

caches a vector of strings describing caches. The format of each string is "cache_dir[link_path]".

id the job id. This is used to create the per-job dir which the job's cache files will be hard linked from

job_uid owner of job. The per-job dir will only be readable by this user job_gid owner group of job

6.60.2.3 Arc::FileCache::FileCache (std::vector< std::string > caches, std::vector< std::string > remote_caches, std::vector< std::string > draining_caches, std::string id, uid_t job_uid, gid_t job_gid, int cache_max = 100, int cache_min = 100)

Create a new FileCache (p. 176) instance with multiple cache dirs, remote caches and draining cache directories.

Parameters:

caches a vector of strings describing caches. The format of each string is "cache_dir[link_path]".

remote_caches Same format as caches. These are the paths to caches which are under the control of other Grid Managers and are read-only for this process.

draining_caches Same format as caches. These are the paths to caches which are to be drained.id the job id. This is used to create the per-job dir which the job's cache files will be hard linked from

job_uid owner of job. The per-job dir will only be readable by this userjob_gid owner group of jobcache_max maximum used space by cache, as percentage of the file systemcache_min minimum used space by cache, as percentage of the file system

6.60.2.4 Arc::FileCache::FileCache() [inline]

Default constructor. Invalid cache.

6.60.3 Member Function Documentation

6.60.3.1 bool Arc::FileCache::AddDN (std::string url, std::string DN, Time expiry_time)

Add the given DN to the list of cached DNs with the given expiry time

Parameters:

url the url corresponding to the cache file to which we want to add a cached DNDN the DN of the userexpiry_time the expiry time of this DN in the DN cache

6.60.3.2 bool Arc::FileCache::CheckCreated (std::string url)

Check if there is an information about creation time. Returns true if the file exists in the cache, since the creation time is the creation time of the cache file.

Parameters:

url the url corresponding to the cache file for which we want to know if the creation date exists

6.60.3.3 bool Arc::FileCache::CheckDN (std::string url, std::string DN)

Check if the given DN is cached for authorisation.

Parameters:

url the url corresponding to the cache file for which we want to check the cached DN DN the DN of the user

6.60.3.4 bool Arc::FileCache::CheckValid (std::string url)

Check if there is an information about expiry time.

Parameters:

url the url corresponding to the cache file for which we want to know if the expiration time exists

6.60.3.5 bool Arc::FileCache::Copy (std::string dest_path, std::string url, bool executable = false)

Copy the cache file corresponding to url to the dest_path

6.60.3.6 std::string Arc::FileCache::File (std::string url)

Returns the full pathname of the file in the cache which corresponds to the given url.

6.60.3.7 Time Arc::FileCache::GetCreated (std::string url)

Get the creation time of a cached file. If the cache file does not exist, 0 is returned.

Parameters:

url the url corresponding to the cache file for which we want to know the creation date

6.60.3.8 Time Arc::FileCache::GetValid (std::string url)

Get expiry time of a cached file. If the time is not available, a time equivalent to 0 is returned.

Parameters:

url the url corresponding to the cache file for which we want to know the expiry time

6.60.3.9 bool Arc::FileCache::Link (std::string link_path, std::string url)

Create a hard-link to the per-job dir from the cache dir, and then a soft-link from here to the session directory. This is effectively 'claiming' the file for the job, so even if the original cache file is deleted, eg by some external process, the hard link still exists until it is explicitly released by calling Release() (p. 180).

If cache_link_path is set to "." then files will be copied directly to the session directory rather than via the hard link.

Parameters:

link_path path to the session dir for soft-link or new file
url url of file to link to or copy

6.60.3.10 Arc::FileCache::operator bool (void) [inline]

Returns true if object is useable.

6.60.3.11 bool Arc::FileCache::operator== (const FileCache & a)

Return true if all attributes are equal

6.60.3.12 bool Arc::FileCache::Release ()

Release claims on input files for the job specified by id. For each cache directory the per-job directory with the hard-links will be deleted.

6.60.3.13 bool Arc::FileCache::SetValid (std::string url, Time val)

Set expiry time.

Parameters:

url the url corresponding to the cache file for which we want to set the expiry timeval expiry time

6.60.3.14 bool Arc::FileCache::Start (std::string url, bool & available, bool & is_locked, bool use_remote = true)

Prepare cache for downloading file, and lock the cached file. On success returns true. If there is another process downloading the same url, false is returned and is_locked is set to true. In this case the client should wait and retry later. If the lock has expired this process will take over the lock and the method will return as if no lock was present, ie available and is locked are false.

Parameters:

url url that is being downloaded
 available true on exit if the file is already in cache
 is_locked true on exit if the file is already locked, ie cannot be used by this process
 remote_caches Same format as caches. These are the paths to caches which are under the control of other Grid Managers and are read-only for this process.

6.60.3.15 bool Arc::FileCache::Stop (std::string url)

This method (or stopAndDelete) must be called after file was downloaded or download failed, to release the lock on the cache file. Stop() (p. 180) does not delete the cache file. It returns false if the lock file does not exist, or another pid was found inside the lock file (this means another process took over the lock so this process must go back to Start() (p. 180)), or if it fails to delete the lock file.

Parameters:

url the url of the file that was downloaded

6.60.3.16 bool Arc::FileCache::StopAndDelete (std::string url)

Release the cache file and delete it, because for example a failed download left an incomplete copy, or it has expired. This method also deletes the meta file which contains the url corresponding to the cache file. The logic of the return value is the same as Stop() (p. 180).

Parameters:

url the url corresponding to the cache file that has to be released and deleted

The documentation for this class was generated from the following file:

• FileCache.h

6.61 FileCacheHash Class Reference

#include <FileCacheHash.h>

Static Public Member Functions

- static std::string getHash (std::string url)
- static int maxLength ()

6.61.1 Detailed Description

FileCacheHash (p. 182) provides methods to make hashes from strings. Currently the md5 hash from the openssl library is used.

6.61.2 Member Function Documentation

6.61.2.1 static std::string FileCacheHash::getHash (std::string *url***)** [static]

Return a hash of the given URL, according to the current hash scheme.

6.61.2.2 static int FileCacheHash::maxLength() [inline, static]

Return the maximum length of a hash string.

The documentation for this class was generated from the following file:

• FileCacheHash.h

6.62 Arc::FileInfo Class Reference

FileInfo (p. 183) stores information about files (metadata).

#include <FileInfo.h>

6.62.1 Detailed Description

FileInfo (p. 183) stores information about files (metadata).

The documentation for this class was generated from the following file:

• FileInfo.h

6.63 Arc::FileLock Class Reference

A general file locking class.

#include <FileLock.h>

Public Member Functions

- FileLock (const std::string &filename)
- ∼FileLock ()
- operator bool ()
- bool operator! ()

6.63.1 Detailed Description

A general file locking class.

6.63.2 Constructor & Destructor Documentation

6.63.2.1 Arc::FileLock::FileLock (const std::string & filename)

Create a new FileLock (p. 184). Blocks until the lock is obtained.

6.63.2.2 Arc::FileLock::~FileLock()

Remove the lock.

6.63.3 Member Function Documentation

6.63.3.1 Arc::FileLock::operator bool ()

true if the lock is held and valid

6.63.3.2 bool Arc::FileLock::operator! ()

true if the lock is not valid

The documentation for this class was generated from the following file:


• FileLock.h

6.64 ArcSec::FnFactory Class Reference

Interface for function factory class.

#include <FnFactory.h>

Inheritance diagram for ArcSec::FnFactory::



Public Member Functions

• virtual Function * createFn (const std::string &type)=0

6.64.1 Detailed Description

Interface for function factory class.

FnFactory (p. 185) is in charge of creating Function (p. 186) object according to the algorithm type given as argument of method createFn. This class can be inherited for implementing a factory class which can create some specific Function (p. 186) objects.

6.64.2 Member Function Documentation

6.64.2.1 virtual Function* ArcSec::FnFactory::createFn (const std::string & type) [pure virtual]

creat algorithm object based on the type algorithm type

Parameters:

type The type of Function (p. 186)

Returns:

The object of Function (p. 186)

The documentation for this class was generated from the following file:


• FnFactory.h

6.65 ArcSec::Function Class Reference

Interface for function, which is in charge of evaluating two AttributeValue (p. 53).

#include <Function.h>

Inheritance diagram for ArcSec::Function::



Public Member Functions

- virtual AttributeValue * evaluate (AttributeValue *arg0, AttributeValue *arg1, bool check_id=true)=0
- virtual std::list< AttributeValue * > evaluate (std::list< AttributeValue * > args, bool check_-id=true)=0

6.65.1 Detailed Description

Interface for function, which is in charge of evaluating two AttributeValue (p. 53).

6.65.2 Member Function Documentation

6.65.2.1 virtual std::list<AttributeValue*> ArcSec::Function::evaluate (std::list< AttributeValue *> args, bool check_id = true) [pure virtual]

Evaluate a list of AttributeValue (p. 53) objects, and return a list of Attribute objects Implemented in ArcSec::EqualFunction (p. 161), and ArcSec::MatchFunction (p. 225).

6.65.2.2 virtual AttributeValue* ArcSec::Function::evaluate (AttributeValue * arg0, AttributeValue * arg1, bool check_id = true) [pure virtual]

Evaluate two AttributeValue (p. 53) objects, and return one AttributeValue (p. 53) object Implemented in ArcSec::EqualFunction (p. 161), and ArcSec::MatchFunction (p. 225). The documentation for this class was generated from the following file:

• Function.h

6.66 Arc::InfoCache Class Reference

Stores XML document in filesystem split into parts.

#include <InfoCache.h>

Public Member Functions

• InfoCache (const Config &cfg, const std::string &service_id)

6.66.1 Detailed Description

Stores XML document in filesystem split into parts.

6.66.2 Constructor & Destructor Documentation

6.66.2.1 Arc::InfoCache::InfoCache (const Config & cfg, const std::string & service_id)

Creates object according to configuration (see InfoCacheConfig.xsd).

XML configuration is passed in cfg. Argument service_id is used to distiguish between various documents stored under same path - corresponding files will be stored in subdirectory with service_id name.

The documentation for this class was generated from the following file:

• InfoCache.h

6.67 Arc::InfoFilter Class Reference

Filters information document according to identity of requestor.

#include <InfoFilter.h>

Public Member Functions

- InfoFilter (MessageAuth &id)
- bool Filter (XMLNode doc) const
- bool Filter (XMLNode doc, const InfoFilterPolicies &policies, const NS &ns) const

6.67.1 Detailed Description

Filters information document according to identity of requestor.

Identity is compared to policies stored inside information document and external ones. Parts of document which do not pass policy evaluation are removed.

6.67.2 Constructor & Destructor Documentation

6.67.2.1 Arc::InfoFilter::InfoFilter (MessageAuth & id)

Creates object and associates identity.

Associated identity is not copied, hence passed argument must not be destroyed while this method is used.

6.67.3 Member Function Documentation

6.67.3.1 bool Arc::InfoFilter::Filter (XMLNode doc, const InfoFilterPolicies & policies, const NS & ns) const

Filter information document according to internal and external policies.

In provided document all policies and nodes which have their policies evaluated to negative result are removed. External policies are provided in policies argument. First element of every pair is XPath defining to which XML node policy must be applied. Second element is policy itself. Argument ns defines XML namespaces for XPath evaluation.

6.67.3.2 bool Arc::InfoFilter::Filter (XMLNode doc) const

Filter information document according to internal policies.

In provided document all policies and nodes which have their policies evaluated to negative result are removed.

The documentation for this class was generated from the following file:

• InfoFilter.h

6.68 Arc::InfoRegister Class Reference

Registration to ISIS interface.

#include <InfoRegister.h>

6.68.1 Detailed Description

Registration to ISIS interface.

This class represents service registering to Information Indexing Service (p. 316). It does not perform registration itself. It only collects configuration information. Configuration is as described in Info-RegisterConfig.xsd for element InfoRegistration.

The documentation for this class was generated from the following file:

• InfoRegister.h

6.69 Arc::InfoRegisterContainer Class Reference

#include <InfoRegister.h>

Public Member Functions

- InfoRegistrar * addRegistrar (XMLNode doc)
- void addService (InfoRegister *reg, const std::list< std::string > &ids, XMLNode cfg=XMLNode())
- void removeService (InfoRegister *reg)

6.69.1 Detailed Description

Singleton class for scanning configuration and storing refernces to registration elements.

6.69.2 Member Function Documentation

6.69.2.1 InfoRegistrar* Arc::InfoRegisterContainer::addRegistrar (XMLNode doc)

Adds ISISes to list of handled services.

Supplied configuration document is scanned for InfoRegistrar (p. 192) elements and those are turned into InfoRegistrar (p. 192) classes for handling connection to ISIS service each.

6.69.2.2 void Arc::InfoRegisterContainer::addService (InfoRegister * reg, const std::list< std::string > & ids, XMLNode cfg = XMLNode())

Adds service to list of handled.

This method must be called first time after last addRegistrar was called - services will be only associated with ISISes which are already added. Argument ids contains list of ISIS identifiers to which service is associated. If ids is empty then service is associated to all ISISes currently added. If argument cfg is available and no ISISes are configured then addRegistrars is called with cfg used as configuration document.

6.69.2.3 void Arc::InfoRegisterContainer::removeService (InfoRegister * reg)

This method must be called if service being destroyed.

The documentation for this class was generated from the following file:

· InfoRegister.h

6.70 Arc::InfoRegisters Class Reference

Handling multiple registrations to ISISes.

#include <InfoRegister.h>

Public Member Functions

• InfoRegisters (XMLNode &cfg, Service *service_)

6.70.1 Detailed Description

Handling multiple registrations to ISISes.

6.70.2 Constructor & Destructor Documentation

6.70.2.1 Arc::InfoRegisters::InfoRegisters (XMLNode & cfg, Service * service_)

Constructor creates InfoRegister (p. 189) objects according to configuration.

Inside cfg elements InfoRegistration are found and for each corresponding InfoRegister (p. 189) object is created. Those objects are destroyed in destructor of this class.

The documentation for this class was generated from the following file:

· InfoRegister.h

6.71 Arc::InfoRegistrar Class Reference

Registration process associated with particular ISIS.

#include <InfoRegister.h>

Public Member Functions

- void registration (void)
- bool addService (InfoRegister *, XMLNode &)
- bool removeService (InfoRegister *)

6.71.1 Detailed Description

Registration process associated with particular ISIS.

Instance of this class starts thread which takes care passing information about associated services to ISIS service defined in configuration. Configuration is as described in InfoRegister.xsd for element InfoRegistrar (p. 192).

6.71.2 Member Function Documentation

6.71.2.1 bool Arc::InfoRegistrar::addService (InfoRegister *, XMLNode &)

Adds new service to list of handled services.

Service (p. 316) is described by it's InfoRegister (p. 189) object which must be valid as long as this object is functional.

6.71.2.2 void Arc::InfoRegistrar::registration (void)

Performs registartion in a loop.

Never exits unless there is a critical error or requested by destructor.

6.71.2.3 bool Arc::InfoRegistrar::removeService (InfoRegister *)

Removes service from list of handled services.

The documentation for this class was generated from the following file:


• InfoRegister.h

6.72 Arc::InformationContainer Class Reference

Information System document container and processor.

#include <InformationInterface.h>

Inheritance diagram for Arc::InformationContainer::



Public Member Functions

- InformationContainer (XMLNode doc, bool copy=false)
- XMLNode Acquire (void)
- void Assign (XMLNode doc, bool copy=false)

Protected Member Functions

• virtual void Get (const std::list< std::string > &path, XMLNodeContainer &result)

Protected Attributes

• XMLNode doc_

6.72.1 Detailed Description

Information System document container and processor.

This class inherits form InformationInterface $(p.\,195)$ and offers container for storing informational XML document.

6.72.2 Constructor & Destructor Documentation

6.72.2.1 Arc::InformationContainer::InformationContainer (XMLNode doc, bool copy = false)

Creates an instance with XML document . If is true this method makes a copy of for internal use.

6.72.3 Member Function Documentation

6.72.3.1 XMLNode Arc::InformationContainer::Acquire (void)

Get a lock on contained XML document. To be used in multi-threaded environment. Do not forget to release it with Release()

6.72.3.2 void Arc::InformationContainer::Assign (XMLNode *doc*, **bool** *copy* = false)

Replaces internal XML document with . If is true this method makes a copy of for internal use.

6.72.3.3 virtual void Arc::InformationContainer::Get (const std::list< std::string > & path, XMLNodeContainer & result) [protected, virtual]

This method is called by this object's Process method. Real implementation of this class should return (sub)tree of XML document. This method may be called multiple times per single Process call. Here is a set on XML element names specifying how to reach requested node(s).

Reimplemented from Arc::InformationInterface (p. 195).

6.72.4 Field Documentation

6.72.4.1 XMLNode Arc::InformationContainer::doc [protected]

Either link or container of XML document

The documentation for this class was generated from the following file:


• InformationInterface.h

6.73 Arc::InformationInterface Class Reference

Information System message processor.

#include <InformationInterface.h>

Inheritance diagram for Arc::InformationInterface::



Public Member Functions

• InformationInterface (bool safe=true)

Protected Member Functions

• virtual void Get (const std::list< std::string > &path, XMLNodeContainer &result)

Protected Attributes

• Glib::Mutex lock_

6.73.1 Detailed Description

Information System message processor.

This class provides callback for 2 operations of WS-ResourceProperties and convenient parsing/generation of corresponding SOAP mesages. In a future it may extend range of supported specifications.

6.73.2 Constructor & Destructor Documentation

6.73.2.1 Arc::InformationInterface::InformationInterface (bool *safe* = true)

Constructor. If 'safe' is true all calls to Get will be locked.

6.73.3 Member Function Documentation

6.73.3.1 virtual void Arc::InformationInterface::Get (const std::list< std::string > & path, XMLNodeContainer & result) [protected, virtual]

This method is called by this object's Process method. Real implementation of this class should return (sub)tree of XML document. This method may be called multiple times per single Process call. Here is a set on XML element names specifying how to reach requested node(s).

Reimplemented in Arc::InformationContainer (p. 194).

6.73.4 Field Documentation

6.73.4.1 Glib::Mutex Arc::InformationInterface::lock_ [protected]

Mutex used to protect access to Get methods in multi-threaded env.

The documentation for this class was generated from the following file:

• InformationInterface.h

6.74 Arc::InformationRequest Class Reference

Request for information in InfoSystem.

#include <InformationInterface.h>

Public Member Functions

- InformationRequest (void)
- InformationRequest (const std::list< std::string > &path)
- InformationRequest (const std::list< std::list< std::string > > &paths)
- InformationRequest (XMLNode query)
- SOAPEnvelope * SOAP (void)

6.74.1 Detailed Description

Request for information in InfoSystem.

This is a convenience wrapper creating proper WS-ResourceProperties request targeted InfoSystem interface of service.

6.74.2 Constructor & Destructor Documentation

6.74.2.1 Arc::InformationRequest::InformationRequest (void)

Dummy constructor

6.74.2.2 Arc::InformationRequest::InformationRequest (const std::list< std::string > & path)

Request for attribute specified by elements of path. Currently only first element is used.

6.74.2.3 Arc::InformationRequest::InformationRequest (const std::list< std::list< std::string > > & paths)

Request for attribute specified by elements of paths. Currently only first element of every path is used.

6.74.2.4 Arc::InformationRequest::InformationRequest (XMLNode query)

Request for attributes specified by XPath query.

6.74.3 Member Function Documentation

6.74.3.1 SOAPEnvelope* Arc::InformationRequest::SOAP (void)

Returns generated SOAP message

The documentation for this class was generated from the following file:

198	Hosting Environment (Daemon) Data Structure Documentation
• InformationInterface.h	

6.75 Arc::InformationResponse Class Reference

Informational response from InfoSystem.

#include <InformationInterface.h>

Public Member Functions

- InformationResponse (SOAPEnvelope &soap)
- std::list< XMLNode > Result (void)

6.75.1 Detailed Description

Informational response from InfoSystem.

This is a convenience wrapper analyzing WS-ResourceProperties response from InfoSystem interface of service.

6.75.2 Constructor & Destructor Documentation

6.75.2.1 Arc::InformationResponse::InformationResponse (SOAPEnvelope & soap)

Constructor parses WS-ResourceProperties ressponse. Provided SOAPEnvelope object must be valid as long as this object is in use.

6.75.3 Member Function Documentation

6.75.3.1 std::list<XMLNode> Arc::InformationResponse::Result (void)

Returns set of attributes which were in SOAP message passed to constructor.

The documentation for this class was generated from the following file:


• InformationInterface.h

6.76 Arc::IntraProcessCounter Class Reference

A class for counters used by threads within a single process.

#include <IntraProcessCounter.h>

Inheritance diagram for Arc::IntraProcessCounter::



Public Member Functions

- IntraProcessCounter (int limit, int excess)
- virtual ~IntraProcessCounter ()
- virtual int getLimit ()
- virtual int setLimit (int newLimit)
- virtual int changeLimit (int amount)
- virtual int getExcess ()
- virtual int setExcess (int newExcess)
- virtual int changeExcess (int amount)
- virtual int getValue ()
- virtual CounterTicket reserve (int amount=1, Glib::TimeVal duration=ETERNAL, bool prioritized=false, Glib::TimeVal timeOut=ETERNAL)

Protected Member Functions

- virtual void cancel (IDType reservationID)
- virtual void extend (IDType &reservationID, Glib::TimeVal &expiryTime, Glib::TimeVal duration=ETERNAL)

6.76.1 Detailed Description

A class for counters used by threads within a single process.

This is a class for shared among different threads within a single process. See the Counter (p. 83) class for further information about counters and examples of usage.

6.76.2 Constructor & Destructor Documentation

6.76.2.1 Arc::IntraProcessCounter::IntraProcessCounter (int *limit*, int *excess*)

Creates an IntraProcessCounter (p. 200) with specified limit and excess.

This constructor creates a counter with the specified limit (amount of resources available for reservation) and excess limit (an extra amount of resources that may be used for prioritized reservations).

Parameters:

limit The limit of the counter.

excess The excess limit of the counter.

6.76.2.2 virtual Arc::IntraProcessCounter::~IntraProcessCounter() [virtual]

Destructor.

This is the destructor of the IntraProcessCounter (p. 200) class. Does not need to do anything.

6.76.3 Member Function Documentation

6.76.3.1 virtual void Arc::IntraProcessCounter::cancel (IDType *reservationID*) [protected, virtual]

Cancellation of a reservation.

This method cancels a reservation. It is called by the CounterTicket (p. 90) that corresponds to the reservation.

Parameters:

reservationID The identity number (key) of the reservation to cancel.

6.76.3.2 virtual int Arc::IntraProcessCounter::changeExcess (int *amount***)** [virtual]

Changes the excess limit of the counter.

Changes the excess limit of the counter by adding a certain amount to the current excess limit.

Parameters:

amount The amount by which to change the excess limit.

Returns:

The new excess limit.

Implements Arc::Counter (p. 85).

6.76.3.3 virtual int Arc::IntraProcessCounter::changeLimit (int amount) [virtual]

Changes the limit of the counter.

Changes the limit of the counter by adding a certain amount to the current limit.

Parameters:

amount The amount by which to change the limit.

Returns:

The new limit.

Implements Arc::Counter (p. 86).

6.76.3.4 virtual void Arc::IntraProcessCounter::extend (IDType & reservationID, Glib::TimeVal & expiryTime, Glib::TimeVal duration = ETERNAL) [protected, virtual]

Extension of a reservation.

This method extends a reservation. It is called by the CounterTicket (p. 90) that corresponds to the reservation.

Parameters:

reservationID Used for input as well as output. Contains the identification number of the original reservation on entry and the new identification number of the extended reservation on exit.

expiryTime Used for input as well as output. Contains the expiry time of the original reservation on entry and the new expiry time of the extended reservation on exit.

duration The time by which to extend the reservation. The new expiration time is computed based on the current time, NOT the previous expiration time.

6.76.3.5 virtual int Arc::IntraProcessCounter::getExcess() [virtual]

Returns the excess limit of the counter.

Returns the excess limit of the counter, i.e. by how much the usual limit may be exceeded by prioritized reservations.

Returns:

The excess limit.

Implements Arc::Counter (p. 87).

6.76.3.6 virtual int Arc::IntraProcessCounter::getLimit() [virtual]

Returns the current limit of the counter.

This method returns the current limit of the counter, i.e. how many units can be reserved simultaneously by different threads without claiming high priority.

Returns:

The current limit of the counter.

Implements Arc::Counter (p. 88).

6.76.3.7 virtual int Arc::IntraProcessCounter::getValue () [virtual]

Returns the current value of the counter.

Returns the current value of the counter, i.e. the number of unreserved units. Initially, the value is equal to the limit of the counter. When a reservation is made, the the value is decreased. Normally, the value should never be negative, but this may happen if there are prioritized reservations. It can also happen if the limit is decreased after some reservations have been made, since reservations are never revoked.

Returns:

The current value of the counter.

Implements Arc::Counter (p. 88).

6.76.3.8 virtual CounterTicket Arc::IntraProcessCounter::reserve (int amount = 1, Glib::TimeVal duration = ETERNAL, bool prioritized = false, Glib::TimeVal timeOut = ETERNAL)

[virtual]

Makes a reservation from the counter.

This method makes a reservation from the counter. If the current value of the counter is too low to allow for the reservation, the method blocks until the reservation is possible or times out.

Parameters:

amount The amount to reserve, default value is 1.

duration The duration of a self expiring reservation, default is that it lasts forever.

prioritized Whether this reservation is prioritized and thus allowed to use the excess limit.

timeOut The maximum time to block if the value of the counter is too low, default is to allow "eternal" blocking.

Returns:

A CounterTicket (p. 90) that can be queried about the status of the reservation as well as for cancellations and extensions.

Implements Arc::Counter (p. 88).

6.76.3.9 virtual int Arc::IntraProcessCounter::setExcess (int *newExcess***)** [virtual]

Sets the excess limit of the counter.

This method sets a new excess limit for the counter.

Parameters:

newExcess The new excess limit, an absolute number.

Returns:

The new excess limit.

Implements Arc::Counter (p. 89).

6.76.3.10 virtual int Arc::IntraProcessCounter::setLimit (int *newLimit***)** [virtual]

Sets the limit of the counter.

This method sets a new limit for the counter.

Parameters:

newLimit The new limit, an absolute number.

Returns:

The new limit.

Implements Arc::Counter (p. 89).

The documentation for this class was generated from the following file:

• IntraProcessCounter.h

6.77 Arc::Job Class Reference

Job (p. 205).

#include <Job.h>

Public Member Functions

- Job ()
- void Print (bool longlist) const

6.77.1 Detailed Description

Job (p. 205).

This class describe a Grid job. Most of the members contained in this class are directly linked to the ComputingActivity defined in the GLUE Specification v. 2.0 (GFD-R-P.147).

6.77.2 Constructor & Destructor Documentation

6.77.2.1 Arc::Job::Job ()

Create a Job (p. 205) object.

Default constructor. Takes no arguments.

6.77.3 Member Function Documentation

6.77.3.1 void Arc::Job::Print (bool longlist) const

Print the Job (p. 205) information to std::cout.

Method to print the Job (p. 205) attributes to std::cout

Parameters:

longlist is boolean for long listing (more details).

The documentation for this class was generated from the following file:


• Job.h

6.78 Arc::JobController Class Reference

Must be specialized for each supported middleware flavour.

#include <JobController.h>

Inheritance diagram for Arc::JobController::



Public Member Functions

- void FillJobStore (const std::list< URL > &jobids)
- bool PrintJobStatus (const std::list< std::string > &status, const bool longlist)
- bool Migrate (TargetGenerator &targetGen, Broker *broker, const UserConfig &usercfg, const bool forcemigration, std::list< URL > &migratedJobIDs)

6.78.1 Detailed Description

Must be specialized for each supported middleware flavour.

The JobController (p. 206) is the base class for middleware specialized derived classes. The JobController (p. 206) base class is also the implementer of all public functionality that should be offered by the middleware specific specializations. In other words all virtual functions of the JobController (p. 206) are private. The initialization of a (specialized) JobController (p. 206) object takes two steps. First the JobController (p. 206) specialization for the required grid flavour must be loaded by the JobController Loader (p. 208), which sees to that the JobController (p. 206) receives information about its Grid flavour and the local joblist file containing information about all active jobs (flavour independent). The next step is the filling of the JobController (p. 206) job pool (JobStore) which is the pool of jobs that the JobController (p. 206) can manage.

6.78.2 Member Function Documentation

6.78.2.1 void Arc::JobController::FillJobStore (const std::list< URL > & jobids)

Fill jobstore.

Method to fill the jobstore with jobs that should be managed.

Parameters:

jobids List of jobids to be loaded to the jobstore. If empty all jobs of the specialized grid flavour present in the joblist file (given through the usercfg to the constructor) will be loaded to the jobstore.

6.78.2.2 bool Arc::JobController::Migrate (TargetGenerator & targetGen, Broker * broker, const UserConfig & usercfg, const bool forcemigration, std::list< URL > & migratedJobIDs)

Migrate job from cluster A to Cluster B.

Method to migrate the jobs contained in the jobstore.

Parameters:

targetGen TargetGenerator (p. 346) with targets to migrate the job to.

broker Broker to be used when selecting target.

forcemigration boolean which specifies whether a migrated job should persist if the new cluster does not succeed sending a kill/terminate request for the job.

6.78.2.3 bool Arc::JobController::PrintJobStatus (const std::list< std::string > & status, const bool longlist)

Print job status to stdout.

The job status is printed to stdout when calling this method. More specifically the Job::Print (p. 205) method is called on each of the Job (p. 205) objects stored in this object, and the boolean argument *longlist* is passed directly to the method indicating whether verbose job status should be printed. The *status* argument is a list of strings each representing a job state (JobState (p. 210)) which is used to indicate that only jobs with a job state in the list should be considered. If the list *status* is empty all jobs will be considered.

This method is not supposed to be overloaded by extending classes.

Parameters:

status a list of strings representing states to be considered.

longlist a boolean indicating whether verbose job information should be printed.

Returns:

This method always returns true.

See also:

GetJobInformation Job::Print (p. 205) JobState (p. 210)


The documentation for this class was generated from the following file:

JobController.h

6.79 Arc::JobControllerLoader Class Reference

#include <JobController.h>

Inheritance diagram for Arc::JobControllerLoader::



Public Member Functions

- JobControllerLoader ()
- ∼JobControllerLoader ()
- JobController * load (const std::string &name, const UserConfig &usercfg)
- const std::list< JobController * > & GetJobControllers () const

6.79.1 Detailed Description

Class responsible for loading JobController (p. 206) plugins The JobController (p. 206) objects returned by a JobControllerLoader (p. 208) must not be used after the JobControllerLoader (p. 208) goes out of scope.

6.79.2 Constructor & Destructor Documentation

6.79.2.1 Arc::JobControllerLoader::JobControllerLoader()

Constructor Creates a new JobControllerLoader (p. 208).

6.79.2.2 Arc::JobControllerLoader::~JobControllerLoader()

Destructor Calling the destructor destroys all JobControllers loaded by the JobControllerLoader (p. 208) instance.

6.79.3 Member Function Documentation

6.79.3.1 const std::list<JobController*>& Arc::JobControllerLoader::GetJobControllers () const [inline]

Retrieve the list of loaded JobControllers.

Returns:

A reference to the list of JobControllers.

6.79.3.2 JobController* Arc::JobControllerLoader::load (const std::string & name, const UserConfig & usercfg)

Load a new JobController (p. 206)

Parameters:

```
name The name of the JobController (p. 206) to load.usercfg The UserConfig (p. 361) object for the new JobController (p. 206).
```

Returns:

A pointer to the new JobController (p. 206) (NULL on error).

The documentation for this class was generated from the following file:

• JobController.h

6.80 Arc::JobState Class Reference

#include <JobState.h>

6.80.1 Detailed Description

ARC general state model. The class comprise the general state model of the ARC-lib, and are herein used to compare job states from the different middlewares supported by the plugin structure of the ARC-lib. Which is why every ACC plugin should contain a class derived from this class. The derived class should consist of a constructor and a mapping function (a JobStateMap) which maps a std::string to a JobState (p. 210):StateType. An example of a constructor in a plugin could be: JobStatePlugin::JobStatePluging(const std::string& state): JobState(state, &pluginStateMap) {} where &pluginStateMap is a reference to the JobStateMap defined by the derived class.

The documentation for this class was generated from the following file:

• JobState.h

6.81 Arc::JobSupervisor Class Reference

% JobSupervisor (p. 211) class

#include <JobSupervisor.h>

Public Member Functions

- JobSupervisor (const UserConfig &usercfg, const std::list< std::string > &jobs)
- const std::list< JobController * > & GetJobControllers ()

6.81.1 Detailed Description

% JobSupervisor (p. 211) class

The JobSupervisor (p. 211) class is tool for loading JobController (p. 206) plugins for managing Grid jobs.

6.81.2 Constructor & Destructor Documentation

6.81.2.1 Arc::JobSupervisor::JobSupervisor (const UserConfig & usercfg, const std::list< std::string > & jobs)

Create a JobSupervisor (p. 211) object.

Default constructor to create a JobSupervisor $(p.\,211)$. Automatically loads JobController $(p.\,206)$ plugins based upon the input jobids.

Parameters:

usercfg Reference to UserConfig (p. 361) object with information about user credentials and joblistfile.

jobs List of jobs(jobid or job name) to be managed.

6.81.3 Member Function Documentation

6.81.3.1 const std::list<JobController*>& Arc::JobSupervisor::GetJobControllers() [inline]

Get list of JobControllers.

Method to get the list of JobControllers loaded by constructor.

The documentation for this class was generated from the following file:


· JobSupervisor.h

6.82 Arc::Loader Class Reference

Plugins loader.

#include <Loader.h>

Inheritance diagram for Arc::Loader::



Public Member Functions

- Loader (XMLNode cfg)
- ∼Loader ()

Protected Attributes

• PluginsFactory * factory_

6.82.1 Detailed Description

Plugins loader.

This class processes XML configration and loads specified plugins. Accepted configuration is defined by XML schema mcc.xsd. "Plugins" elements are parsed by this class and corresponding libraries are loaded.

6.82.2 Constructor & Destructor Documentation

6.82.2.1 Arc::Loader::Loader (XMLNode cfg)

Constructor that takes whole XML configuration and performs common configuration part

6.82.2.2 Arc::Loader::~Loader ()

Destructor destroys all components created by constructor

6.82.3 Field Documentation

6.82.3.1 PluginsFactory* **Arc::Loader::factory**_ [protected]

Link to Factory responsible for loading and creation of Plugin (p. 280) and derived objects The documentation for this class was generated from the following file:


• Loader.h

6.83 Arc::LogDestination Class Reference

A base class for log destinations.

#include <Logger.h>

Inheritance diagram for Arc::LogDestination::



Public Member Functions

• virtual void log (const LogMessage &message)=0

Protected Member Functions

- LogDestination ()
- LogDestination (const std::string &locale)

6.83.1 Detailed Description

A base class for log destinations.

This class defines an interface for LogDestinations. LogDestination (p. 213) objects will typically contain synchronization mechanisms and should therefore never be copied.

6.83.2 Constructor & Destructor Documentation

6.83.2.1 Arc::LogDestination::LogDestination() [protected]

Default constructor.

This destination will use the default locale.

6.83.2.2 Arc::LogDestination::LogDestination (const std::string & locale) [protected]

Constructor with specific locale.

This destination will use the specified locale.

6.83.3 Member Function Documentation

6.83.3.1 virtual void Arc::LogDestination::log (const LogMessage & message) [pure virtual]

Logs a LogMessage (p. 221) to this LogDestination (p. 213).

Implemented in Arc::LogStream (p. 224), and Arc::LogFile (p. 216). The documentation for this class was generated from the following file:


• Logger.h

6.84 Arc::LogFile Class Reference

A class for logging to files.

#include <Logger.h>

Inheritance diagram for Arc::LogFile::



Public Member Functions

- LogFile (const std::string &path)
- LogFile (const std::string &path, const std::string &locale)
- void setMaxSize (int newsize)
- void setBackups (int newbackup)
- void setReopen (bool newreopen)
- operator bool (void)
- bool operator! (void)
- virtual void log (const LogMessage &message)

6.84.1 Detailed Description

A class for logging to files.

This class is used for logging to files. It provides synchronization in order to prevent different Log-Messages to appear mixed with each other in the stream. It is possible to limit size of created file. Whenever specified size is exceeded fiel is deleted and new one is created. Old files may be moved into backup files instead of being deleted. Those files have names same as initial file with additional number suffix - similar to those found in /var/log of many Unix-like systems.

6.84.2 Constructor & Destructor Documentation

6.84.2.1 Arc::LogFile::LogFile (const std::string & path)

Creates a LogFile (p. 215) connected to a file.

Creates a LogFile (p. 215) connected to the file located at specified path. In order not to break synchronization, it is important not to connect more than one LogFile (p. 215) object to a certain file. If file does not exist it will be created.

Parameters:

path The path to file to which to write LogMessages.

6.84.2.2 Arc::LogFile::LogFile (const std::string & path, const std::string & locale)

Creates a LogFile (p. 215) connected to a file.

Creates a LogFile (p.215) connected to the file located at specified path. The output will be localised to the specified locale.

6.84.3 Member Function Documentation

6.84.3.1 virtual void Arc::LogFile::log (const LogMessage & message) [virtual]

Writes a LogMessage (p. 221) to the file.

This method writes a LogMessage (p. 221) to the file that is connected to this LogFile (p. 215) object. If after writing size of file exceeds one set by setMaxSize() (p. 216) file is moved to backup and new one is created.

Parameters:

message The LogMessage (p. 221) to write.

Implements Arc::LogDestination (p. 213).

6.84.3.2 Arc::LogFile::operator bool (void)

Returns true if this instance is valid.

6.84.3.3 bool Arc::LogFile::operator! (void)

Returns true if this instance is invalid.

6.84.3.4 void Arc::LogFile::setBackups (int newbackup)

Set number of backups to store.

Set number of backups to store. When file size exceeds one specified with setMaxSize() (p. 216) file is closed and moved to one named path.1. If path.1 exists it is moved to path.2 and so on. Number of path.# files is one set in newbackup.

Parameters:

newbackup Number of backup files.

6.84.3.5 void Arc::LogFile::setMaxSize (int newsize)

Set maximal allowed size of file.

Set maximal allowed size of file. This value is not obeyed exactly. Spesified size may be exceeded by amount of one LogMessage (p. 221). To disable limit specify -1.

Parameters:

newsize Max size of log file.

6.84.3.6 void Arc::LogFile::setReopen (bool newreopen)

Set file reopen on every write.

Set file reopen on every write. If set to true file is opened before writing every log record and closed afterward.

Parameters:

newreopen If file to be reopened for every log record.

The documentation for this class was generated from the following file:

• Logger.h

6.85 Arc::Logger Class Reference

A logger class.

#include <Logger.h>

Public Member Functions

- Logger (Logger &parent, const std::string &subdomain)
- Logger (Logger &parent, const std::string &subdomain, LogLevel threshold)
- ∼Logger ()
- void addDestination (LogDestination &destination)
- void removeDestinations (void)
- void setThreshold (LogLevel threshold)
- LogLevel getThreshold () const
- void msg (LogMessage message)
- void msg (LogLevel level, const std::string &str)

Static Public Member Functions

• static Logger & getRootLogger ()

6.85.1 Detailed Description

A logger class.

This class defines a Logger (p. 218) to which LogMessages can be sent.

Every Logger (p. 218) (except for the rootLogger) has a parent Logger (p. 218). The domain of a Logger (p. 218) (a string that indicates the origin of LogMessages) is composed by adding a subdomain to the domain of its parent Logger (p. 218).

A Logger (p. 218) also has a threshold. Every LogMessage (p. 221) that have a level that is greater than or equal to the threshold is forwarded to any LogDestination (p. 213) connected to this Logger (p. 218) as well as to the parent Logger (p. 218).

Typical usage of the Logger (p. 218) class is to declare a global Logger (p. 218) object for each library/module/component to be used by all classes and methods there.

6.85.2 Constructor & Destructor Documentation

6.85.2.1 Arc::Logger::Logger (Logger & parent, const std::string & subdomain)

Creates a logger.

Creates a logger. The threshold is inherited from its parent Logger (p. 218).

Parameters:

parent The parent Logger (p. 218) of the new Logger (p. 218). subdomain The subdomain of the new logger.

6.85.2.2 Arc::Logger::Logger (Logger & parent, const std::string & subdomain, LogLevel threshold)

Creates a logger.

Creates a logger.

Parameters:

```
parent The parent Logger (p. 218) of the new Logger (p. 218). subdomain The subdomain of the new logger. threshold The threshold of the new logger.
```

6.85.2.3 Arc::Logger::~Logger()

Destroys a logger.

Destructor

6.85.3 Member Function Documentation

6.85.3.1 void Arc::Logger::addDestination (LogDestination & destination)

Adds a LogDestination (p. 213).

Adds a LogDestination (p. 213) to which to forward LogMessages sent to this logger (if they pass the threshold). Since LogDestinatoins should not be copied, the new LogDestination (p. 213) is passed by reference and a pointer to it is kept for later use. It is therefore important that the LogDestination (p. 213) passed to this Logger (p. 218) exists at least as long as the Logger (p. 218) iteslf.

```
6.85.3.2 static Logger & Arc::Logger::getRootLogger() [static]
```

The root Logger (p. 218).

This is the root Logger (p. 218). It is an ancestor of any other Logger (p. 218) and allways exists.

6.85.3.3 LogLevel Arc::Logger::getThreshold () const

Returns the threshold.

Returns the threshold.

Returns:

The threshold of this Logger (p. 218).

6.85.3.4 void Arc::Logger::msg (**LogLevel** *level*, **const std::string** & *str*) [inline]

Logs a message text.

Logs a message text string at the specified LogLevel. This is a convenience method to save some typing. It simply creates a LogMessage (p. 221) and sends it to the other msg() (p. 220) method.

Parameters:

```
level The level of the message.str The message text.
```

6.85.3.5 void Arc::Logger::msg (LogMessage message)

```
Sends a LogMessage (p. 221).
Sends a LogMessage (p. 221).
```

Parameters:

The LogMessage (p. 221) to send.

6.85.3.6 void Arc::Logger::removeDestinations (void)

Removes all LogDestinations.

6.85.3.7 void Arc::Logger::setThreshold (LogLevel threshold)

Sets the threshold.

This method sets the threshold of the Logger (p. 218). Any message sent to this Logger (p. 218) that has a level below this threshold will be discarded.

Parameters:

The threshold

The documentation for this class was generated from the following file:

• Logger.h

6.86 Arc::LogMessage Class Reference

A class for log messages.

#include <Logger.h>

Public Member Functions

- LogMessage (LogLevel level, const IString &message)
- LogMessage (LogLevel level, const IString &message, const std::string &identifier)
- LogLevel getLevel () const

Protected Member Functions

• void setIdentifier (std::string identifier)

Friends

- class Logger
- std::ostream & operator<< (std::ostream &os, const LogMessage &message)

6.86.1 Detailed Description

A class for log messages.

This class is used to represent log messages internally. It contains the time the message was created, its level, from which domain it was sent, an identifier and the message text itself.

6.86.2 Constructor & Destructor Documentation

6.86.2.1 Arc::LogMessage::LogMessage (LogLevel level, const IString & message)

Creates a LogMessage (p. 221) with the specified level and message text.

This constructor creates a LogMessage $(p.\,221)$ with the specified level and message text. The time is set automatically, the domain is set by the Logger $(p.\,218)$ to which the LogMessage $(p.\,221)$ is sent and the identifier is composed from the process ID and the address of the Thread object corresponding to the calling thread.

Parameters:

```
level The level of the LogMessage (p. 221). message The message text.
```

6.86.2.2 Arc::LogMessage::LogMessage (LogLevel level, const IString & message, const std::string & identifier)

Creates a LogMessage (p. 221) with the specified attributes.

This constructor creates a LogMessage (p. 221) with the specified level, message text and identifier. The time is set automatically and the domain is set by the Logger (p. 218) to which the LogMessage (p. 221) is sent.

Parameters:

```
level The level of the LogMessage (p. 221).message The message text.ident The identifier of the LogMessage (p. 221).
```

6.86.3 Member Function Documentation

6.86.3.1 LogLevel Arc::LogMessage::getLevel () const

Returns the level of the LogMessage (p. 221).

Returns the level of the LogMessage (p. 221).

Returns:

The level of the LogMessage (p. 221).

6.86.3.2 void Arc::LogMessage::setIdentifier (std::string *identifier*) [protected]

Sets the identifier of the LogMessage (p. 221).

The purpose of this method is to allow subclasses (in case there are any) to set the identifier of a LogMessage (p. 221).

Parameters:

The identifier.

6.86.4 Friends And Related Function Documentation

6.86.4.1 friend class Logger [friend]

The Logger (p. 218) class is a friend.

The Logger (p. 218) class must have some privileges (e.g. ability to call the setDomain() method), therefore it is a friend.

6.86.4.2 std::ostream & operator << (std::ostream & os, const LogMessage & message) [friend]

Printing of LogMessages to ostreams.

Output operator so that LogMessages can be printed conveniently by LogDestinations.

The documentation for this class was generated from the following file:


· Logger.h

6.87 Arc::LogStream Class Reference

A class for logging to ostreams.

#include <Logger.h>

Inheritance diagram for Arc::LogStream::



Public Member Functions

- LogStream (std::ostream &destination)
- LogStream (std::ostream &destination, const std::string &locale)
- virtual void log (const LogMessage &message)

6.87.1 Detailed Description

A class for logging to ostreams.

This class is used for logging to ostreams (cout, cerr, files). It provides synchronization in order to prevent different LogMessages to appear mixed with each other in the stream. In order not to break the synchronization, LogStreams should never be copied. Therefore the copy constructor and assignment operator are private. Furthermore, it is important to keep a LogStream (p. 223) object as long as the Logger (p. 218) to which it has been registered.

6.87.2 Constructor & Destructor Documentation

6.87.2.1 Arc::LogStream::LogStream (std::ostream & destination)

Creates a LogStream (p. 223) connected to an ostream.

Creates a LogStream (p. 223) connected to the specified ostream. In order not to break synchronization, it is important not to connect more than one LogStream (p. 223) object to a certain stream.

Parameters:

destination The ostream to which to erite LogMessages.

6.87.2.2 Arc::LogStream::LogStream (std::ostream & destination, const std::string & locale)

Creates a LogStream (p. 223) connected to an ostream.

Creates a LogStream (p. 223) connected to the specified ostream. The output will be localised to the specified locale.

6.87.3 Member Function Documentation

6.87.3.1 virtual void Arc::LogStream::log (const LogMessage & message) [virtual]

Writes a LogMessage (p. 221) to the stream.

This method writes a LogMessage (p. 221) to the ostream that is connected to this LogStream (p. 223) object. It is synchronized so that not more than one LogMessage (p. 221) can be written at a time.

Parameters:

message The LogMessage (p. 221) to write.

Implements Arc::LogDestination (p. 213).

The documentation for this class was generated from the following file:


· Logger.h

6.88 ArcSec::MatchFunction Class Reference

Evaluate whether arg1 (value in regular expression) matched arg0 (lable in regular expression).

#include <MatchFunction.h>

Inheritance diagram for ArcSec::MatchFunction::



Public Member Functions

- virtual AttributeValue * evaluate (AttributeValue *arg0, AttributeValue *arg1, bool check_id=true)
- virtual std::list< AttributeValue * > evaluate (std::list< AttributeValue * > args, bool check_-id=true)

Static Public Member Functions

• static std::string getFunctionName (std::string datatype)

6.88.1 Detailed Description

Evaluate whether arg1 (value in regular expression) matched arg0 (lable in regular expression).

6.88.2 Member Function Documentation

6.88.2.1 virtual std::list<AttributeValue*> ArcSec::MatchFunction::evaluate (std::list< AttributeValue * > args, bool check_id = true) [virtual]

Evaluate a list of AttributeValue (p. 53) objects, and return a list of Attribute objects Implements ArcSec::Function (p. 186).

6.88.2.2 virtual AttributeValue* ArcSec::MatchFunction::evaluate (AttributeValue * arg0, AttributeValue * arg1, bool check_id = true) [virtual]

Evaluate two AttributeValue (p. 53) objects, and return one AttributeValue (p. 53) object Implements ArcSec::Function (p. 186).

6.88.2.3 static std::string ArcSec::MatchFunction::getFunctionName (std::string *datatype*) [static]

help function to get the FunctionName

The documentation for this class was generated from the following file:


• MatchFunction.h

6.89 Arc::MCC Class Reference

Message (p. 238) Chain Component - base class for every MCC (p. 227) plugin.

#include <MCC.h>

Inheritance diagram for Arc::MCC::



Public Member Functions

- MCC (Config *)
- virtual void Next (MCCInterface *next, const std::string &label="")
- virtual void AddSecHandler (Config *cfg, ArcSec::SecHandler *sechandler, const std::string &label="")
- virtual void Unlink ()
- virtual MCC Status process (Message &, Message &)

Protected Member Functions

• bool ProcessSecHandlers (Message &message, const std::string &label="") const

Protected Attributes

- std::map< std::string, MCCInterface * > next_
- std::map< std::string, std::list< ArcSec::SecHandler * > > sechandlers_

Static Protected Attributes

• static Logger logger

6.89.1 Detailed Description

Message (p. 238) Chain Component - base class for every MCC (p. 227) plugin.

This is partially virtual class which defines interface and common functionality for every MCC (p. 227) plugin needed for managing of component in a chain.

6.89.2 Constructor & Destructor Documentation

6.89.2.1 Arc::MCC::MCC (Config *) [inline]

Example contructor - MCC (p. 227) takes at least it's configuration subtree

6.89.3 Member Function Documentation

6.89.3.1 virtual void Arc::MCC::AddSecHandler (Config * cfg, ArcSec::SecHandler * sechandler, const std::string & label = "") [virtual]

Add security components/handlers to this MCC (p. 227). Security handlers are stacked into a few queues with each queue identified by its label. The queue labelled 'incoming' is executed for every 'request' message after the message is processed by the MCC (p. 227) on the service side and before processing on the client side. The queue labelled 'outgoing' is run for response message before it is processed by MCC (p. 227) algorithms on the service side and after processing on the client side. Those labels are just a matter of agreement and some MCCs may implement different queues executed at various message processing steps.

6.89.3.2 virtual void Arc::MCC::Next (MCCInterface * *next*, const std::string & *label* = "") [virtual]

Add reference to next MCC (p. 227) in chain. This method is called by Loader (p. 212) for every potentially labeled link to next component which implements MCCInterface (p. 233). If next is NULL corresponding link is removed.

Reimplemented in Arc::Plexer (p. 278).

6.89.3.3 virtual MCC_Status Arc::MCC::process (Message &, Message &) [inline, virtual]

Dummy Message (p. 238) processing method. Just a placeholder.

Implements Arc::MCCInterface (p. 233).

Reimplemented in Arc::Plexer (p. 278).

6.89.3.4 bool Arc::MCC::ProcessSecHandlers (Message & message, const std::string & label = "") const [protected]

Executes security handlers of specified queue. Returns true if the message is authorized for further processing or if there are no security handlers which implement authorization functionality. This is a convenience method and has to be called by the implemention of the MCC (p. 227).

6.89.3.5 virtual void Arc::MCC::Unlink () [virtual]

Removing all links. Useful for destroying chains.

6.89.4 Field Documentation

6.89.4.1 Logger Arc::MCC::logger [static, protected]

A logger for MCCs.

A logger intended to be the parent of loggers in the different MCCs.

Reimplemented in Arc::Plexer (p. 278).

6.89.4.2 std::map<std::string, MCCInterface *> **Arc::MCC::next_** [protected]

Set of labeled "next" components. Each implemented MCC (p. 227) must call process() (p. 228) method of corresponding MCCInterface (p. 233) from this set in own process() (p. 228) method.

6.89.4.3 std::map<**std::string**, **std::list**<**ArcSec::SecHandler** *> > **Arc::MCC::sechandlers_** [protected]

Set of labeled authentication and authorization handlers. MCC (p. 227) calls sequence of handlers at specific point depending on associated identifier. In most aces those are "in" and "out" for incoming and outgoing messages correspondingly.

The documentation for this class was generated from the following file:

• MCC.h

6.90 Arc::MCC_Status Class Reference

A class for communication of MCC (p. 227) processing results.

```
#include <MCC_Status.h>
```

Public Member Functions

- MCC_Status (StatusKind kind=STATUS_UNDEFINED, const std::string &origin="???", const std::string &explanation="No explanation.")
- · bool isOk () const
- StatusKind getKind () const
- const std::string & getOrigin () const
- const std::string & getExplanation () const
- operator std::string () const
- · operator bool (void) const
- bool operator! (void) const

6.90.1 Detailed Description

A class for communication of MCC (p. 227) processing results.

This class is used to communicate result status between MCCs. It contains a status kind, a string specifying the origin (MCC (p. 227)) of the status object and an explanation.

6.90.2 Constructor & Destructor Documentation

6.90.2.1 Arc::MCC_Status::MCC_Status (StatusKind kind = STATUS_UNDEFINED, const std::string & origin = "???", const std::string & explanation = "No explanation.")

The constructor.

Creates a MCC_Status (p. 230) object.

Parameters:

```
kind The StatusKind (default: STATUS_UNDEFINED)

origin The origin MCC (p. 227) (default: "???")

explanation An explanation (default: "No explanation.")
```

6.90.3 Member Function Documentation

6.90.3.1 const std::string& Arc::MCC_Status::getExplanation () const

Returns an explanation.

This method returns an explanation of this object.

Returns:

An explanation of this object.

6.90.3.2 StatusKind Arc::MCC_Status::getKind () const

Returns the status kind.

Returns the status kind of this object.

Returns:

The status kind of this object.

6.90.3.3 const std::string& Arc::MCC_Status::getOrigin () const

Returns the origin.

This method returns a string specifying the origin MCC (p. 227) of this object.

Returns:

A string specifying the origin MCC (p. 227) of this object.

6.90.3.4 bool Arc::MCC_Status::isOk () const

Is the status kind ok?

This method returns true if the status kind of this object is STATUS_OK

Returns:

true if kind==STATUS_OK

6.90.3.5 Arc::MCC_Status::operator bool (void) const [inline]

Is the status kind ok?

This method returns true if the status kind of this object is STATUS_OK

Returns:

true if kind==STATUS_OK

6.90.3.6 Arc::MCC_Status::operator std::string () const

Conversion to string.

This operator converts a MCC_Status (p. 230) object to a string.

6.90.3.7 bool Arc::MCC_Status::operator! (void) const [inline]

not operator

Returns true if the status kind is not OK

Returns:

true if kind!=STATUS_OK

The documentation for this class was generated from the following file:


• MCC_Status.h

6.91 Arc::MCCInterface Class Reference

Interface for communication between MCC (p. 227), Service (p. 316) and Plexer (p. 277) objects.

#include <MCC.h>

Inheritance diagram for Arc::MCCInterface::



Public Member Functions

• virtual MCC_Status process (Message &request, Message &response)=0

6.91.1 Detailed Description

Interface for communication between MCC (p. 227), Service (p. 316) and Plexer (p. 277) objects.

The Interface consists of the method process() (p. 233) which is called by the previous MCC (p. 227) in the chain. For memory management policies please read the description of the Message (p. 238) class.

6.91.2 Member Function Documentation

6.91.2.1 virtual MCC_Status Arc::MCCInterface::process (Message & request, Message & response) [pure virtual]

Method for processing of requests and responses. This method is called by preceeding MCC (p. 227) in chain when a request needs to be processed. This method must call similar method of next MCC (p. 227) in chain unless any failure happens. Result returned by call to next MCC (p. 227) should be processed and passed back to previous MCC (p. 227). In case of failure this method is expected to generate valid error response and return it back to previous MCC (p. 227) without calling the next one.

Parameters:

request The request that needs to be processed.

 ${\it response} \ \ A \ Message \ (p.\ 238) \ object \ that \ will \ contain \ the \ response \ of \ the \ request \ when \ the \ method \ returns.$

Returns:

An object representing the status of the call.

Implemented in Arc::MCC (p. 228), and Arc::Plexer (p. 278).

The documentation for this class was generated from the following file:


• MCC.h

6.92 Arc::MCCLoader Class Reference

Creator of Message (p. 238) Component Chains (MCC (p. 227)).

#include <MCCLoader.h>

Inheritance diagram for Arc::MCCLoader::



Public Member Functions

- MCCLoader (Config &cfg)
- ∼MCCLoader ()
- MCC * operator[] (const std::string &id)

6.92.1 Detailed Description

Creator of Message (p. 238) Component Chains (MCC (p. 227)).

This class processes XML configration and creates message chains. Accepted configuration is defined by XML schema mcc.xsd. Supported components are of types MCC (p. 227), Service (p. 316) and Plexer (p. 277). MCC (p. 227) and Service (p. 316) are loaded from dynamic libraries. For Plexer (p. 277) only internal implementation is supported. This object is also a container for loaded components. All components and chains are destroyed if this object is destroyed. Chains are created in 2 steps. First all components are loaded and corresponding objects are created. Constructors are supplied with corresponding configuration subtrees. During next step components are linked together by calling their Next() methods. Each call creates labeled link to next component in a chain. 2 step method has an advantage over single step because it allows loops in chains and makes loading procedure more simple. But that also means during short period of time components are only partly configured. Components in such state must produce proper error response if Message (p. 238) arrives. Note: Current implementation requires all components and links to be labeled. All labels must be unique. Future implementation will be able to assign labels automatically.

6.92.2 Constructor & Destructor Documentation

6.92.2.1 Arc::MCCLoader::MCCLoader (Config & cfg)

Constructor that takes whole XML configuration and creates component chains

6.92.2.2 Arc::MCCLoader::~MCCLoader ()

Destructor destroys all components created by constructor

6.92.3 Member Function Documentation

6.92.3.1 MCC* Arc::MCCLoader::operator[] (const std::string & id)

Access entry MCCs in chains. Those are components exposed for external access using 'entry' attribute

The documentation for this class was generated from the following file:

• MCCLoader.h

6.93 Arc::MD5Sum Class Reference

Implementation of MD5 checksum.

#include <CheckSum.h>

Inheritance diagram for Arc::MD5Sum::



6.93.1 Detailed Description

Implementation of MD5 checksum.

The documentation for this class was generated from the following file:

• CheckSum.h

6.94 Arc::Message Class Reference

Object being passed through chain of MCCs.

#include <Message.h>

Public Member Functions

- Message (void)
- Message (Message &msg)
- Message (long msg_ptr_addr)
- ∼Message (void)
- Message & operator= (Message &msg)
- MessagePavload * Pavload (void)
- MessagePayload * Payload (MessagePayload *payload)
- MessageAttributes * Attributes (void)
- MessageAuth * Auth (void)
- MessageContext * Context (void)
- MessageAuthContext * AuthContext (void)
- void Context (MessageContext *ctx)
- void AuthContext (MessageAuthContext *auth_ctx)

6.94.1 Detailed Description

Object being passed through chain of MCCs.

An instance of this class refers to objects with main content (MessagePayload (p. 249)), authentication/authorization information (MessageAuth (p. 244)) and common purpose attributes (MessageAttributes (p. 241)). Message (p. 238) class does not manage pointers to objects and their content. It only serves for grouping those objects. Message (p. 238) objects are supposed to be processed by MCCs and Services implementing MCCInterface (p. 233) method process(). All objects constituting content of Message (p. 238) object are subject to following policies:

- 1. All objects created inside call to process() method using new command must be explicitly destroyed within same call using delete command with following exceptions. a) Objects which are assigned to 'response' Message (p. 238). b) Objects whose management is completely acquired by objects assigned to 'response' Message (p. 238).
- 2. All objects not created inside call to process() method are not explicitly destroyed within that call with following exception. a) Objects which are part of 'response' Method returned from call to next's process() method. Unless those objects are passed further to calling process(), of course.
- 3. It is not allowed to make 'response' point to same objects as 'request' does on entry to process() method. That is needed to avoid double destruction of same object. (Note: if in a future such need arises it may be solved by storing additional flags in Message (p. 238) object).
- 4. It is allowed to change content of pointers of 'request' Message (p. 238). Calling process() method must not rely on that object to stay intact.
- 5. Called process() method should either fill 'response' Message (p. 238) with pointers to valid objects or to keep them intact. This makes it possible for calling process() to preload 'response' with valid error message.

6.94.2 Constructor & Destructor Documentation

6.94.2.1 Arc::Message::Message (void) [inline]

Dummy constructor

6.94.2.2 Arc::Message::Message (Message & msg) [inline]

Copy constructor. Ensures shallow copy.

6.94.2.3 Arc::Message::Message (long msg_ptr_addr)

Copy constructor. Used by language bindigs

6.94.2.4 Arc::Message::~Message (void) [inline]

Destructor does not affect refered objects except those created internally

6.94.3 Member Function Documentation

6.94.3.1 MessageAttributes* Arc::Message::Attributes (void) [inline]

Returns a pointer to the current attributes object or creates it if no attributes object has been assigned.

6.94.3.2 MessageAuth* Arc::Message::Auth (void) [inline]

Returns a pointer to the current authentication/authorization object or creates it if no object has been assigned.

6.94.3.3 void Arc::Message::AuthContext (**MessageAuthContext** * *auth_ctx*) [inline]

Assigns auth* context object

6.94.3.4 MessageAuthContext* Arc::Message::AuthContext (void) [inline]

Returns a pointer to the current auth* context object or creates it if no object has been assigned.

6.94.3.5 void Arc::Message::Context (**MessageContext** * *ctx*) [inline]

Assigns message context object

6.94.3.6 MessageContext* Arc::Message::Context (void) [inline]

Returns a pointer to the current context object or creates it if no object has been assigned. Last case should happen only if first MCC (p. 227) in a chain is connectionless like one implementing UDP protocol.

6.94.3.7 Message & Arc::Message::operator= (Message & msg) [inline]

Assignment. Ensures shallow copy.

6.94.3.8 MessagePayload* Arc::Message::Payload (MessagePayload * payload) [inline]

Replaces payload with new one. Returns the old one.

6.94.3.9 MessagePayload* Arc::Message::Payload (void) [inline]

Returns pointer to current payload or NULL if no payload assigned.

The documentation for this class was generated from the following file:

• Message.h

6.95 Arc::MessageAttributes Class Reference

A class for storage of attribute values.

#include <MessageAttributes.h>

Public Member Functions

- MessageAttributes ()
- void set (const std::string &key, const std::string &value)
- void add (const std::string &key, const std::string &value)
- void removeAll (const std::string &key)
- void remove (const std::string &key, const std::string &value)
- int count (const std::string &key) const
- const std::string & get (const std::string &key) const
- AttributeIterator getAll (const std::string &key) const
- AttributeIterator getAll (void) const

Protected Attributes

AttrMap attributes_

6.95.1 Detailed Description

A class for storage of attribute values.

This class is used to store attributes of messages. All attribute keys and their corresponding values are stored as strings. Any key or value that is not a string must thus be represented as a string during storage. Furthermore, an attribute is usually a key-value pair with a unique key, but there may also be multiple such pairs with equal keys.

The key of an attribute is composed by the name of the Message (p. 238) Chain Component (MCC (p. 227)) which produce it and the name of the attribute itself with a colon (:) in between, i.e. MCC_Name:Attribute_Name. For example, the key of the "Content-Length" attribute of the HTTP MCC (p. 227) is thus "HTTP:Content-Length".

There are also "global attributes", which may be produced by different MCCs depending on the configuration. The keys of such attributes are NOT prefixed by the name of the producing MCC (p. 227). Before any new global attribute is introduced, it must be agreed upon by the core development team and added below. The global attributes decided so far are:

• Request-URI Identifies the service to which the message shall be sent. This attribute is produced by e.g. the HTTP MCC (p. 227) and used by the plexer for routing the message to the appropriate service.

6.95.2 Constructor & Destructor Documentation

6.95.2.1 Arc::MessageAttributes::MessageAttributes ()

The default constructor.

This is the default constructor of the MessageAttributes (p. 241) class. It constructs an empty object that initially contains no attributes.

6.95.3 Member Function Documentation

6.95.3.1 void Arc::MessageAttributes::add (const std::string & key, const std::string & value)

Adds a value to an attribute.

This method adds a new value to an attribute. Any previous value will be preserved, i.e. the attribute may become multiple valued.

Parameters:

key The key of the attribute.

value The (new) value of the attribute.

6.95.3.2 int Arc::MessageAttributes::count (const std::string & key) const

Returns the number of values of an attribute.

Returns the number of values of an attribute that matches a certain key.

Parameters:

key The key of the attribute for which to count values.

Returns:

The number of values that corresponds to the key.

6.95.3.3 const std::string& Arc::MessageAttributes::get (const std::string & key) const

Returns the value of a single-valued attribute.

This method returns the value of a single-valued attribute. If the attribute is not single valued (i.e. there is no such attribute or it is a multiple-valued attribute) an empty string is returned.

Parameters:

key The key of the attribute for which to return the value.

Returns:

The value of the attribute.

6.95.3.4 AttributeIterator Arc::MessageAttributes::getAll (void) const

Access all value and attributes.

6.95.3.5 AttributeIterator Arc::MessageAttributes::getAll (const std::string & key) const

Access the value(s) of an attribute.

This method returns an AttributeIterator (p. 49) that can be used to access the values of an attribute.

Parameters:

key The key of the attribute for which to return the values.

Returns:

An AttributeIterator (p. 49) for access of the values of the attribute.

6.95.3.6 void Arc::MessageAttributes::remove (const std::string & key, const std::string & value)

Removes one value of an attribute.

This method removes a certain value from the attribute that matches a certain key.

Parameters:

key The key of the attribute from which the value shall be removed. value The value to remove.

6.95.3.7 void Arc::MessageAttributes::removeAll (const std::string & key)

Removes all attributes with a certain key.

This method removes all attributes that match a certain key.

Parameters:

key The key of the attributes to remove.

6.95.3.8 void Arc::MessageAttributes::set (const std::string & key, const std::string & value)

Sets a unique value of an attribute.

This method removes any previous value of an attribute and sets the new value as the only value.

Parameters:

key The key of the attribute.value The (new) value of the attribute.

6.95.4 Field Documentation

6.95.4.1 AttrMap Arc::MessageAttributes::attributes_ [protected]

Internal storage of attributes.

An AttrMap (multimap) in which all attributes (key-value pairs) are stored.

The documentation for this class was generated from the following file:


· MessageAttributes.h

6.96 Arc::MessageAuth Class Reference

Contains authencity information, authorization tokens and decisions.

#include <MessageAuth.h>

Inheritance diagram for Arc::MessageAuth::



Public Member Functions

- void set (const std::string &key, SecAttr *value)
- void remove (const std::string &key)
- SecAttr * get (const std::string &key)
- SecAttr * operator[] (const std::string &key)
- bool Export (SecAttrFormat format, XMLNode &val) const
- MessageAuth * Filter (const std::list< std::string > &selected_keys, const std::list< std::string > &rejected_keys)

6.96.1 Detailed Description

Contains authencity information, authorization tokens and decisions.

This class only supports string keys and SecAttr (p. 307) values.

6.96.2 Member Function Documentation

6.96.2.1 bool Arc::MessageAuth::Export (SecAttrFormat format, XMLNode & val) const

Returns properly catenated attributes in specified format.

Content of XML node at is replaced with generated information if XML tree is empty. If tree at is not empty then Export() (p. 244) tries to merge generated information to already existing like everything would be generated inside same Export() (p. 244) method. If does not represent valid node then new XML tree is created.

6.96.2.2 MessageAuth* Arc::MessageAuth::Filter (const std::list< std::string > & selected_keys, const std::list< std::string > & rejected_keys)

Creates new instance of MessageAuth (p. 244) with attributes filtered.

In new instance all attributes with keys listed in are removed. If is not empty only corresponding attributes are transferred to new instance. Created instance does not own refered attributes. Hence parent instance must not be deleted as long as this one is in use.

6.96.2.3 SecAttr* Arc::MessageAuth::get (const std::string & key)

Retrieves reference to security attribute stored under specified key.

6.96.2.4 SecAttr* Arc::MessageAuth::operator[] (const std::string & key) [inline]

Same as MessageAuth::get (p. 245).

6.96.2.5 void Arc::MessageAuth::remove (const std::string & key)

Deletes security attribute stored under specified key.

6.96.2.6 void Arc::MessageAuth::set (const std::string & key, SecAttr * value)

Adds/overwrites security attribute stored under specified key.

The documentation for this class was generated from the following file:

· MessageAuth.h

6.97 Arc::MessageAuthContext Class Reference

Handler for content of message auth* context.

#include <Message.h>

Inheritance diagram for Arc::MessageAuthContext::



6.97.1 Detailed Description

Handler for content of message auth* context.

This class is a container for authorization and authentication information. It gets associated with Message (p. 238) object usually by first MCC (p. 227) in a chain and is kept as long as connection persists.

The documentation for this class was generated from the following file:

• Message.h

6.98 Arc::MessageContext Class Reference

Handler for content of message context.

#include <Message.h>

Public Member Functions

• void Add (const std::string &name, MessageContextElement *element)

6.98.1 Detailed Description

Handler for content of message context.

This class is a container for objects derived from MessageContextElement (p. 248). It gets associated with Message (p. 238) object usually by first MCC (p. 227) in a chain and is kept as long as connection persists.

6.98.2 Member Function Documentation

6.98.2.1 void Arc::MessageContext::Add (const std::string & name, MessageContextElement * element)

Provided element is taken over by this class. It is remembered by it and destroyed when this class is destroyed.

The documentation for this class was generated from the following file:

Message.h

6.99 Arc::MessageContextElement Class Reference

Top class for elements contained in message context.

#include <Message.h>

6.99.1 Detailed Description

Top class for elements contained in message context.

Objects of classes inherited with this one may be stored in MessageContext (p. 247) container.

The documentation for this class was generated from the following file:


• Message.h

6.100 Arc::MessagePayload Class Reference

Base class for content of message passed through chain.

#include <Message.h>

Inheritance diagram for Arc::MessagePayload::



6.100.1 Detailed Description

Base class for content of message passed through chain.

It's not intended to be used directly. Instead functional classes must be derived from it.

The documentation for this class was generated from the following file:

• Message.h

6.101 Arc::ModuleDesc Class Reference

Description of loadable module.

#include <Plugin.h>

6.101.1 Detailed Description

Description of loadable module.

This class is used for reports

The documentation for this class was generated from the following file:


• Plugin.h

6.102 Arc::ModuleManager Class Reference

Manager of shared libraries.

#include <ModuleManager.h>

Inheritance diagram for Arc::ModuleManager::



Public Member Functions

- ModuleManager (XMLNode cfg)
- Glib::Module * load (const std::string &name, bool probe=false)
- std::string find (const std::string &name)
- Glib::Module * reload (Glib::Module *module)
- void unload (Glib::Module *module)
- void unload (const std::string &name)
- std::string findLocation (const std::string &name)
- bool makePersistent (Glib::Module *module)
- bool makePersistent (const std::string &name)
- void setCfg (XMLNode cfg)

6.102.1 Detailed Description

Manager of shared libraries.

This class loads shared libraries/modules. There supposed to be created one instance of it per executable. In such circumstances it would cache handles to loaded modules and not load them multiple times.

6.102.2 Constructor & Destructor Documentation

6.102.2.1 Arc::ModuleManager::ModuleManager (XMLNode cfg)

Constructor. It is supposed to process correponding configuration subtree and tune module loading parameters accordingly.

6.102.3 Member Function Documentation

6.102.3.1 std::string Arc::ModuleManager::find (const std::string & name)

Finds loadable module by 'name' looking in same places as load() (p. 252) does, but does not load it.

6.102.3.2 std::string Arc::ModuleManager::findLocation (const std::string & name)

Finds shared library corresponding to module 'name' and returns path to it

6.102.3.3 Glib::Module* Arc::ModuleManager::load (const std::string & name, bool probe = false)

Finds module 'name' in cache or loads corresponding loadable module

6.102.3.4 bool Arc::ModuleManager::makePersistent (const std::string & name)

Make sure this module is never unloaded. Even if unload() (p. 252) is called.

6.102.3.5 bool Arc::ModuleManager::makePersistent (Glib::Module * module)

Make sure this module is never unloaded. Even if unload() (p. 252) is called.

6.102.3.6 Glib::Module* Arc::ModuleManager::reload (Glib::Module * module)

Reload module previously loaded in probe mode. New module is loaded with all symbols resolved and old module handler is unloaded. In case of error old module is not unloaded.

6.102.3.7 void Arc::ModuleManager::setCfg (XMLNode cfg)

Input the configuration subtree, and trigger the module loading (do almost the same as the Constructor); It is function desgined for ClassLoader to adopt the singleton pattern

6.102.3.8 void Arc::ModuleManager::unload (const std::string & name)

Unload module by its name

6.102.3.9 void Arc::ModuleManager::unload (Glib::Module * module)

Unload module by its identifier

The documentation for this class was generated from the following file:


· ModuleManager.h

6.103 Arc::MultiSecAttr Class Reference

Container of multiple SecAttr (p. 307) attributes.

#include <SecAttr.h>

Inheritance diagram for Arc::MultiSecAttr::



Public Member Functions

- virtual operator bool () const
- · virtual bool Export (SecAttrFormat format, XMLNode &val) const

6.103.1 Detailed Description

Container of multiple SecAttr (p. 307) attributes.

This class combines multiple attributes. It's export/import methods catenate results of underlying objects. Primary meaning of this class is to serve as base for classes implementing multi level hierarchical tree-like descriptions of user identity. It may also be used for collecting information of same source or kind. Like all information extracted from X509 certificate.

6.103.2 Member Function Documentation

6.103.2.1 virtual bool Arc::MultiSecAttr::Export (SecAttrFormat *format***, XMLNode &** *val***) const** [virtual]

Convert internal structure into specified format. Returns false if format is not supported/suitable for this attribute. XML node referenced by is turned into top level element of specified format.

Reimplemented from Arc::SecAttr (p. 308).

6.103.2.2 virtual Arc::MultiSecAttr::operator bool () const [virtual]

This function should return false if the value is to be considered null, e.g. if it hasn't been set or initialized. In other cases it should return true.

Reimplemented from Arc::SecAttr (p. 308).


The documentation for this class was generated from the following file:

· SecAttr.h

6.104 Arc::MySQLDatabase Class Reference

#include <MysqlWrapper.h>

Inheritance diagram for Arc::MySQLDatabase::



Public Member Functions

- virtual bool connect (std::string &dbname, std::string &user, std::string &password)
- · virtual bool isconnected () const
- virtual void close ()
- virtual bool enable_ssl (const std::string keyfile="", const std::string certfile="", const std::string capath="")
- virtual bool shutdown ()

6.104.1 Detailed Description

Implement the database accessing interface in DBInterface.h (p. ??) by using mysql client library for accessing mysql database

6.104.2 Member Function Documentation

6.104.2.1 virtual void Arc::MySQLDatabase::close () [virtual]

Close the connection with database server

Implements Arc::Database (p. 96).

6.104.2.2 virtual bool Arc::MySQLDatabase::connect (std::string & dbname, std::string & user, std::string & password) [virtual]

Do connection with database server

Parameters:

dbname The database name which will be used.

user The username which will be used to access database.

password The password which will be used to access database.

Implements Arc::Database (p. 96).

```
6.104.2.3 virtual bool Arc::MySQLDatabase::enable_ssl (const std::string keyfile = "", const std::string capth = "") const std::string capth = "") [virtual]
```

Enable ssl communication for the connection

```
Parameters:
```

```
keyfile The location of key file.

certfile The location of certificate file.

cafile The location of ca file.

capath The location of ca directory
```

Implements Arc::Database (p. 96).

6.104.2.4 virtual bool Arc::MySQLDatabase::isconnected () const [inline, virtual]

Get the connection status

Implements Arc::Database (p. 96).

6.104.2.5 virtual bool Arc::MySQLDatabase::shutdown () [virtual]

Ask database server to shutdown

Implements Arc::Database (p. 96).

The documentation for this class was generated from the following file:

• MysqlWrapper.h

6.105 Arc::OAuthConsumer Class Reference

#include <OAuthConsumer.h>

Public Member Functions

- OAuthConsumer (const MCCConfig cfg, const URL url, std::list< std::string > idp_stack)
- MCC_Status parseDN (std::string *dn)
- MCC_Status approveCSR (const std::string approve_page)
- MCC_Status pushCSR (const std::string b64_pub_key, const std::string pub_key_hash, std::string *approve_page)
- MCC_Status storeCert (const std::string cert_path, const std::string auth_token, const std::string b64_dn)

Protected Member Functions

MCC_Status processLogin (const std::string username="", const std::string password="")

6.105.1 Detailed Description

The OAuth functionality depends on the availability of the liboauth C-bindings library

6.105.2 Constructor & Destructor Documentation

6.105.2.1 Arc::OAuthConsumer::OAuthConsumer (const MCCConfig cfg, const URL url, std::list< std::string > idp_stack)

Construct an OAuth consumer with url as service provider. idp_name is currently ignored, since the idp to which the SAML2 redirect will take place is presently a hardcoded value on the SAML2 SP side. This is expected to change in the future.

6.105.3 Member Function Documentation

6.105.3.1 MCC_Status Arc::OAuthConsumer::approveCSR (const std::string approve_page)

Unsupported placeholder function until Confusa supports OAuth.

6.105.3.2 MCC_Status Arc::OAuthConsumer::parseDN (std::string * dn)

Unsupported placeholder function until Confusa supports OAuth.

6.105.3.3 MCC_Status Arc::OAuthConsumer::processLogin (const std::string username = "", const std::string password = "") [protected]

Main function performing all the OAuth login steps. Username and password will be ignored.

6.105.3.4 MCC_Status Arc::OAuthConsumer::pushCSR (const std::string b64_pub_key, const std::string pub_key_hash, std::string *approve_page)

Unsupported placeholder function until Confusa supports OAuth.

6.105.3.5 MCC_Status Arc::OAuthConsumer::storeCert (const std::string cert_path, const std::string auth_token, const std::string b64_dn)

Unsupported placeholder function until Confusa supports OAuth.

The documentation for this class was generated from the following file:

• OAuthConsumer.h

6.106 Arc::PathIterator Class Reference

Class to iterate through elements of path.

#include <URL.h>

Public Member Functions

- PathIterator (const std::string &path, bool end=false)
- PathIterator & operator++ ()
- PathIterator & operator-()
- operator bool () const
- std::string operator * () const
- std::string Rest () const

6.106.1 Detailed Description

Class to iterate through elements of path.

6.106.2 Constructor & Destructor Documentation

6.106.2.1 Arc::PathIterator::PathIterator (const std::string & path, bool end = false)

Constructor accepts path and stores it internally. If end is set to false iterator is pointing at first element in path. Otherwise selected element is one before last.

6.106.3 Member Function Documentation

6.106.3.1 std::string Arc::PathIterator::operator * () const

Returns part of initial path from first till and including current

6.106.3.2 Arc::PathIterator::operator bool () const

Return false when iterator moved outside path elements

6.106.3.3 PathIterator& Arc::PathIterator::operator++ ()

Advances iterator to point at next path element

6.106.3.4 PathIterator& Arc::PathIterator::operator-()

Moves iterator to element before current

 $\textbf{6.106.3.5} \quad \textbf{std::string Arc::PathIterator::Rest () const}$

Returns part of initial path from one after current till end

The documentation for this class was generated from the following file:


• URL.h

6.107 Arc::PayloadRaw Class Reference

Raw byte multi-buffer.

#include <PayloadRaw.h>

Inheritance diagram for Arc::PayloadRaw::



Public Member Functions

- PayloadRaw (void)
- virtual \sim PayloadRaw (void)
- virtual Size_t Size (void) const
- virtual char * Buffer (unsigned int num=0)
- virtual Size_t BufferSize (unsigned int num=0) const
- virtual Size_t BufferPos (unsigned int num=0) const

6.107.1 Detailed Description

Raw byte multi-buffer.

This is implementation of PayloadRawInterface $(p.\,262)$. Buffers are memory blocks logically placed one after another.

6.107.2 Constructor & Destructor Documentation

6.107.2.1 Arc::PayloadRaw::PayloadRaw (void) [inline]

Constructor. Created object contains no buffers.

6.107.2.2 virtual Arc::PayloadRaw::~PayloadRaw (void) [virtual]

Destructor. Frees allocated buffers.

6.107.3 Member Function Documentation

6.107.3.1 virtual char* Arc::PayloadRaw::Buffer (unsigned int *num* = 0) [virtual]

Returns pointer to num'th buffer

Implements Arc::PayloadRawInterface (p. 262).

6.107.3.2 virtual Size_t Arc::PayloadRaw::BufferPos (unsigned int num = 0) const [virtual]

Returns position of num'th buffer

Implements Arc::PayloadRawInterface (p. 262).

6.107.3.3 virtual Size_t Arc::PayloadRaw::BufferSize (unsigned int num = 0) const [virtual]

Returns length of num'th buffer

Implements Arc::PayloadRawInterface (p. 263).

6.107.3.4 virtual Size_t Arc::PayloadRaw::Size (void) const [virtual]

Returns logical size of whole structure.

Implements Arc::PayloadRawInterface (p. 263).

The documentation for this class was generated from the following file:


• PayloadRaw.h

6.108 Arc::PayloadRawInterface Class Reference

Random Access Payload for Message (p. 238) objects.

#include <PayloadRaw.h>

Inheritance diagram for Arc::PayloadRawInterface::



Public Member Functions

- virtual char operator[] (Size_t pos) const =0
- virtual char * Content (Size_t pos=-1)=0
- virtual Size t Size (void) const =0
- virtual char * Insert (Size_t pos=0, Size_t size=0)=0
- virtual char * Insert (const char *s, Size_t pos=0, Size_t size=-1)=0
- virtual char * Buffer (unsigned int num)=0
- virtual Size_t BufferSize (unsigned int num) const =0
- virtual Size_t BufferPos (unsigned int num) const =0
- virtual bool Truncate (Size_t size)=0

6.108.1 Detailed Description

Random Access Payload for Message (p. 238) objects.

This class is a virtual interface for managing Message (p. 238) payload with arbitrarily accessible content. Inheriting classes are supposed to implement memory-resident or memory-mapped content made of optionally multiple chunks/buffers. Every buffer has own size and offset. This class is purely virtual.

6.108.2 Member Function Documentation

6.108.2.1 virtual char* Arc::PayloadRawInterface::Buffer (unsigned int num) [pure virtual]

Returns pointer to num'th buffer

Implemented in Arc::PayloadRaw (p. 260).

6.108.2.2 virtual Size_t Arc::PayloadRawInterface::BufferPos (unsigned int *num***) const** [pure virtual]

Returns position of num'th buffer

Implemented in Arc::PayloadRaw (p. 261).

6.108.2.3 virtual Size_t Arc::PayloadRawInterface::BufferSize (unsigned int *num***) const** [pure virtual]

Returns length of num'th buffer

Implemented in Arc::PayloadRaw (p. 261).

6.108.2.4 virtual char* Arc::PayloadRawInterface::Content (Size_t *pos* = -1) [pure virtual]

Get pointer to buffer content at global position 'pos'. By default to beginning of main buffer whatever that means.

6.108.2.5 virtual char* Arc::PayloadRawInterface::Insert (const char * s, Size_t pos = 0, Size_t size = -1) [pure virtual]

Create new buffer at global position 'pos' of size 'size'. Created buffer is filled with content of memory at 's'. If 'size' is negative content at 's' is expected to be null-terminated.

6.108.2.6 virtual char* Arc::PayloadRawInterface::Insert (Size_t pos = 0, Size_t size = 0) [pure virtual]

Create new buffer at global position 'pos' of size 'size'.

6.108.2.7 virtual char Arc::PayloadRawInterface::operator[] (Size_t pos) const [pure virtual]

Returns content of byte at specified position. Specified position 'pos' is treated as global one and goes through all buffers placed one after another.

6.108.2.8 virtual Size_t Arc::PayloadRawInterface::Size (void) const [pure virtual]

Returns logical size of whole structure.

Implemented in Arc::PayloadRaw (p. 261).

6.108.2.9 virtual bool Arc::PayloadRawInterface::Truncate (Size_t size) [pure virtual]

Change size of stored information. If size exceeds end of allocated buffer, buffers are not re-allocated, only logical size is extended. Buffers with location behind new size are deallocated.

The documentation for this class was generated from the following file:


· PayloadRaw.h

6.109 Arc::PayloadSOAP Class Reference

Payload of Message (p. 238) with SOAP content.

#include <PayloadSOAP.h>

Inheritance diagram for Arc::PayloadSOAP::



Public Member Functions

- PayloadSOAP (const NS &ns, bool fault=false)
- PayloadSOAP (const SOAPEnvelope &soap)
- PayloadSOAP (const MessagePayload &source)

6.109.1 Detailed Description

Payload of Message (p. 238) with SOAP content.

This class combines MessagePayload (p. 249) with SOAPEnvelope to make it possible to pass SOAP messages through MCC (p. 227) chain.

6.109.2 Constructor & Destructor Documentation

6.109.2.1 Arc::PayloadSOAP::PayloadSOAP (const NS & ns, bool fault = false)

Constructor - creates new Message (p. 238) payload

6.109.2.2 Arc::PayloadSOAP::PayloadSOAP (const SOAPEnvelope & soap)

Constructor - creates Message (p. 238) payload from SOAP document. Provided SOAP document is copied to new object.

6.109.2.3 Arc::PayloadSOAP::PayloadSOAP (const MessagePayload & source)

 $\label{lem:constructor-creates} \textbf{COAP} \ \ \textbf{message from payload.} \ \ \textbf{PayloadRawInterface} \ \ (\textbf{p. 262}) \ \ \textbf{and} \ \ \textbf{derived}$ classes are supported.

The documentation for this class was generated from the following file:


· PayloadSOAP.h

6.110 Arc::PayloadStream Class Reference

POSIX handle as Payload.

#include <PayloadStream.h>

Inheritance diagram for Arc::PayloadStream::



Public Member Functions

- PayloadStream (int h=-1)
- virtual ~PayloadStream (void)
- virtual bool Get (char *buf, int &size)
- virtual bool Get (std::string &buf)
- virtual std::string Get (void)
- virtual bool Put (const std::string &buf)
- virtual bool Put (const char *buf)
- virtual operator bool (void)
- virtual bool operator! (void)
- virtual int Timeout (void) const
- virtual void Timeout (int to)
- virtual Size_t Pos (void) const
- virtual Size_t Size (void) const
- virtual Size_t Limit (void) const

Protected Attributes

- int handle
- · bool seekable_

6.110.1 Detailed Description

POSIX handle as Payload.

This is an implementation of PayloadStreamInterface (p. 268) for generic POSIX handle.

6.110.2 Constructor & Destructor Documentation

6.110.2.1 Arc::PayloadStream::PayloadStream (int h = -1)

Constructor. Attaches to already open handle. Handle is not managed by this class and must be closed by external code.

6.110.2.2 virtual Arc::PayloadStream::~PayloadStream (void) [inline, virtual]

Destructor.

6.110.3 Member Function Documentation

6.110.3.1 virtual std::string Arc::PayloadStream::Get (void) [inline, virtual]

Read as many as possible (sane amount) of bytes.

Implements Arc::PayloadStreamInterface (p. 268).

6.110.3.2 virtual bool Arc::PayloadStream::Get (std::string & buf) [virtual]

Read as many as possible (sane amount) of bytes into buf.

Implements Arc::PayloadStreamInterface (p. 269).

6.110.3.3 virtual bool Arc::PayloadStream::Get (char * *buf*, int & *size*) [virtual]

Extracts information from stream up to 'size' bytes. 'size' contains number of read bytes on exit. Returns true in case of success.

Implements Arc::PayloadStreamInterface (p. 269).

6.110.3.4 virtual Size t Arc::PayloadStream::Limit (void) const [inline, virtual]

Returns position at which stream reading will stop if supported. That may be not same as Size() (p. 267) if instance is meant to provide access to only part of underlying obejct.

Implements Arc::PayloadStreamInterface (p. 269).

6.110.3.5 virtual Arc::PayloadStream::operator bool (void) [inline, virtual]

Returns true if stream is valid.

Implements Arc::PayloadStreamInterface (p. 269).

6.110.3.6 virtual bool Arc::PayloadStream::operator! (void) [inline, virtual]

Returns true if stream is invalid.

Implements Arc::PayloadStreamInterface (p. 269).

6.110.3.7 virtual Size t Arc::PayloadStream::Pos (void) const [inline, virtual]

Returns current position in stream if supported.

Implements Arc::PayloadStreamInterface (p. 269).

6.110.3.8 virtual bool Arc::PayloadStream::Put (const char * *buf***)** [inline, virtual]

Push null terminated information from 'buf' into stream. Returns true on success.

Implements Arc::PayloadStreamInterface (p. 269).

6.110.3.9 virtual bool Arc::PayloadStream::Put (const std::string & buf) [inline, virtual]

Push information from 'buf' into stream. Returns true on success.

Implements Arc::PayloadStreamInterface (p. 269).

6.110.3.10 virtual Size_t Arc::PayloadStream::Size (void) const [inline, virtual]

Returns size of underlying object if supported.

Implements Arc::PayloadStreamInterface (p. 270).

6.110.3.11 virtual void Arc::PayloadStream::Timeout (int to) [inline, virtual]

Set current timeout for Get() (p. 266) and Put() operations.

Implements Arc::PayloadStreamInterface (p. 270).

6.110.3.12 virtual int Arc::PayloadStream::Timeout (void) const [inline, virtual]

Query current timeout for Get() (p. 266) and Put() operations.

Implements Arc::PayloadStreamInterface (p. 270).

6.110.4 Field Documentation

6.110.4.1 int Arc::PayloadStream::handle_ [protected]

Timeout for read/write operations

6.110.4.2 bool Arc::PayloadStream::seekable_ [protected]

Handle for operations

The documentation for this class was generated from the following file:


• PayloadStream.h

6.111 Arc::PayloadStreamInterface Class Reference

Stream-like Payload for Message (p. 238) object.

#include <PayloadStream.h>

Inheritance diagram for Arc::PayloadStreamInterface::



Public Member Functions

- virtual bool Get (char *buf, int &size)=0
- virtual bool Get (std::string &buf)=0
- virtual std::string Get (void)=0
- virtual bool Put (const char *buf, Size_t size)=0
- virtual bool Put (const std::string &buf)=0
- virtual bool Put (const char *buf)=0
- virtual operator bool (void)=0
- virtual bool operator! (void)=0
- virtual int Timeout (void) const =0
- virtual void Timeout (int to)=0
- virtual Size_t Pos (void) const =0
- virtual Size_t Size (void) const =0
- virtual Size_t Limit (void) const =0

6.111.1 Detailed Description

Stream-like Payload for Message (p. 238) object.

This class is a virtual interface for managing stream-like source and destination. It's supposed to be passed through MCC (p. 227) chain as payload of Message (p. 238). It must be treated by MCCs and Services as dynamic payload. This class is purely virtual.

6.111.2 Member Function Documentation

6.111.2.1 virtual std::string Arc::PayloadStreamInterface::Get (void) [pure virtual]

Read as many as possible (sane amount) of bytes.

Implemented in Arc::PayloadStream (p. 266).

6.111.2.2 virtual bool Arc::PayloadStreamInterface::Get (std::string & *buf***)** [pure virtual]

Read as many as possible (sane amount) of bytes into buf.

Implemented in Arc::PayloadStream (p. 266).

6.111.2.3 virtual bool Arc::PayloadStreamInterface::Get (char * *buf*, int & *size*) [pure virtual]

Extracts information from stream up to 'size' bytes. 'size' contains number of read bytes on exit. Returns true in case of success.

Implemented in Arc::PayloadStream (p. 266).

6.111.2.4 virtual Size_t Arc::PayloadStreamInterface::Limit (void) const [pure virtual]

Returns position at which stream reading will stop if supported. That may be not same as Size() (p. 270) if instance is meant to provide access to only part of underlying obejct.

Implemented in Arc::PayloadStream (p. 266).

6.111.2.5 virtual Arc::PayloadStreamInterface::operator bool (void) [pure virtual]

Returns true if stream is valid.

Implemented in Arc::PayloadStream (p. 266).

6.111.2.6 virtual bool Arc::PayloadStreamInterface::operator! (void) [pure virtual]

Returns true if stream is invalid.

Implemented in Arc::PayloadStream (p. 266).

6.111.2.7 virtual Size_t Arc::PayloadStreamInterface::Pos (void) const [pure virtual]

Returns current position in stream if supported.

Implemented in Arc::PayloadStream (p. 266).

6.111.2.8 virtual bool Arc::PayloadStreamInterface::Put (const char * *buf*) [pure virtual]

Push null terminated information from 'buf' into stream. Returns true on success.

Implemented in Arc::PayloadStream (p. 267).

6.111.2.9 virtual bool Arc::PayloadStreamInterface::Put (const std::string & *buf***)** [pure virtual]

Push information from 'buf' into stream. Returns true on success.

Implemented in Arc::PayloadStream (p. 267).

6.111.2.10 virtual bool Arc::PayloadStreamInterface::Put (const char * *buf***, Size_t** *size***)** [pure virtual]

Push 'size' bytes from 'buf' into stream. Returns true on success.

6.111.2.11 virtual Size_t Arc::PayloadStreamInterface::Size (void) const [pure virtual]

Returns size of underlying object if supported.

Implemented in Arc::PayloadStream (p. 267).

6.111.2.12 virtual void Arc::PayloadStreamInterface::Timeout (int to) [pure virtual]

Set current timeout for Get() (p. 268) and Put() (p. 270) operations.

Implemented in Arc::PayloadStream (p. 267).

6.111.2.13 virtual int Arc::PayloadStreamInterface::Timeout (void) const [pure virtual]

Query current timeout for Get() (p. 268) and Put() (p. 270) operations.

Implemented in Arc::PayloadStream (p. 267).

The documentation for this class was generated from the following file:


· PayloadStream.h

6.112 Arc::PayloadWSRF Class Reference

This class combines MessagePayload (p. 249) with WSRF (p. 399).

#include <PayloadWSRF.h>

Inheritance diagram for Arc::PayloadWSRF::



Public Member Functions

- PayloadWSRF (const SOAPEnvelope &soap)
- PayloadWSRF (WSRF &wsrp)
- PayloadWSRF (const MessagePayload &source)

6.112.1 Detailed Description

This class combines MessagePayload (p. 249) with WSRF (p. 399).

It's intention is to make it possible to pass WSRF (p. 399) messages through MCC (p. 227) chain as one more Payload type.

6.112.2 Constructor & Destructor Documentation

6.112.2.1 Arc::PayloadWSRF::PayloadWSRF (const SOAPEnvelope & soap)

 $\textbf{Constructor-creates Message (p. 238) payload from SOAP message. Returns invalid WSRF (p. 399)} \\ \textbf{if SOAP does not represent WS-Resource Properties}$

6.112.2.2 Arc::PayloadWSRF::PayloadWSRF (WSRF & wsrp)

Constructor - creates Message (p. 238) payload with acquired WSRF (p. 399) message. WSRF (p. 399) message will be destroyed by destructor of this object.

6.112.2.3 Arc::PayloadWSRF::PayloadWSRF (const MessagePayload & source)

Constructor-creates WSRF~(p.~399)~message from payload.~All classes derived from SOAPEnvelope are supported.

The documentation for this class was generated from the following file:

• PayloadWSRF.h

6.113 ArcSec::PDP Class Reference

Base class for Policy (p. 286) Decision Point plugins.

#include <PDP.h>

Inheritance diagram for ArcSec::PDP::



6.113.1 Detailed Description

Base class for Policy (p. 286) Decision Point plugins.

This virtual class defines method isPermitted() which processes security related information/attributes in Message and makes security decision - permit (true) or deny (false). Configuration of PDP (p. 272) is consumed during creation of instance through XML subtree fed to constructor.


The documentation for this class was generated from the following file:

• PDP.h

6.114 ArcSec::PeriodAttribute Class Reference

#include <DateTimeAttribute.h>

Inheritance diagram for ArcSec::PeriodAttribute::



Public Member Functions

- virtual bool equal (AttributeValue *other, bool check id=true)
- virtual std::string encode ()
- virtual std::string getType ()
- virtual std::string getId ()

6.114.1 Detailed Description

Formate: datetime"/"duration datetime"/"datetime duration"/"datetime

6.114.2 Member Function Documentation

6.114.2.1 virtual std::string ArcSec::PeriodAttribute::encode () [virtual]

encode the value in a string format

Implements ArcSec::AttributeValue (p. 53).

6.114.2.2 virtual bool ArcSec::PeriodAttribute::equal (AttributeValue * *other*, **bool** *check_id* = true) [virtual]

Evaluate whether "this" is equal to the parameter value

Implements ArcSec::AttributeValue (p. 53).

6.114.2.3 virtual std::string ArcSec::PeriodAttribute::getId () [inline, virtual]

Get the AttributeId of the <Attribute>

Implements ArcSec::AttributeValue (p. 54).

6.114.2.4 virtual std::string ArcSec::PeriodAttribute::getType () [inline, virtual]

Get the DataType of the <Attribute>

Implements ArcSec::AttributeValue (p. 54).

The documentation for this class was generated from the following file:


• DateTimeAttribute.h

6.115 ArcSec::PermitOverridesCombiningAlg Class Reference

Implement the "Permit-Overrides" algorithm.

#include <PermitOverridesAlg.h>

Inheritance diagram for ArcSec::PermitOverridesCombiningAlg::



Public Member Functions

- $\bullet \ virtual \ Result \ combine \ (EvaluationCtx \ *ctx, \ std:: list < Policy \ * > policies) \\$
- virtual const std::string & getalgId (void) const

6.115.1 Detailed Description

Implement the "Permit-Overrides" algorithm.

Permit-Overrides, scans the policy set which is given as the parameters of "combine" method, if gets "permit" result from any policy, then stops scanning and gives "permit" as result, otherwise gives "deny".

6.115.2 Member Function Documentation

6.115.2.1 virtual Result ArcSec::PermitOverridesCombiningAlg::combine (EvaluationCtx * *ctx*, **std::list< Policy** * > *policies*) [virtual]

If there is one policy which return positive evaluation result, then omit the other policies and return ${\tt DECISION_PERMIT}$

Parameters:

ctx This object contains request information which will be used to evaluated against policy.

policlies This is a container which contains policy objects.

Returns:

The combined result according to the algorithm.

Implements ArcSec::CombiningAlg (p. 74).

6.115.2.2 virtual const std::string& ArcSec::PermitOverridesCombiningAlg::getalgId (void) const [inline, virtual]

Get the identifier

Implements ArcSec::CombiningAlg (p. 74).

The documentation for this class was generated from the following file:


• PermitOverridesAlg.h

6.116 Arc::Plexer Class Reference

The Plexer (p. 277) class, used for routing messages to services.

#include <Plexer.h>

Inheritance diagram for Arc::Plexer::



Public Member Functions

- Plexer (Config *cfg)
- virtual ∼Plexer ()
- virtual void Next (MCCInterface *next, const std::string &label)
- virtual MCC_Status process (Message &request, Message &response)

Static Public Attributes

• static Logger logger

6.116.1 Detailed Description

The Plexer (p. 277) class, used for routing messages to services.

This is the Plexer (p. 277) class. Its purpose is to route incoming messages to appropriate Services and MCC (p. 227) chains.

6.116.2 Constructor & Destructor Documentation

6.116.2.1 Arc::Plexer::Plexer (Config * cfg)

The constructor.

This is the constructor. Since all member variables are instances of "well-behaving" STL classes, nothing needs to be done.

6.116.2.2 virtual Arc::Plexer::~Plexer() [virtual]

The destructor.

This is the destructor. Since all member variables are instances of "well-behaving" STL classes, nothing needs to be done.

6.116.3 Member Function Documentation

6.116.3.1 virtual void Arc::Plexer::Next (MCCInterface * *next*, **const std::string &** *label*) [virtual]

Add reference to next MCC (p. 227) in chain.

This method is called by Loader (p. 212) for every potentially labeled link to next component which implements MCCInterface (p. 233). If next is set NULL corresponding link is removed.

Reimplemented from Arc::MCC (p. 228).

6.116.3.2 virtual MCC_Status Arc::Plexer::process (Message & request, Message & response) [virtual]

Route request messages to appropriate services.

Routes the request message to the appropriate service. Routing is based on the path part of value of the ENDPOINT attribute. Routed message is assigned following attributes: PLEXER:PATTERN - matched pattern, PLEXER:EXTENSION - last unmatched part of ENDPOINT path.

Reimplemented from Arc::MCC (p. 228).

6.116.4 Field Documentation

6.116.4.1 Logger Arc::Plexer::logger [static]

A logger for MCCs.

A logger intended to be the parent of loggers in the different MCCs.

Reimplemented from Arc::MCC (p. 229).

The documentation for this class was generated from the following file:

· Plexer.h

6.117 Arc::PlexerEntry Class Reference

A pair of label (regex) and pointer to MCC (p. 227).

#include <Plexer.h>

6.117.1 Detailed Description

A pair of label (regex) and pointer to MCC (p. 227).

A helper class that stores a label (regex) and a pointer to a service.

The documentation for this class was generated from the following file:


• Plexer.h

6.118 Arc::Plugin Class Reference

Base class for loadable ARC components.

#include <Plugin.h>

Inheritance diagram for Arc::Plugin::



6.118.1 Detailed Description

Base class for loadable ARC components.

All classes representing loadable ARC components must be either descendants of this class or be wrapped by its offspring.

The documentation for this class was generated from the following file:

• Plugin.h

6.119 Arc::PluginArgument Class Reference

Base class for passing arguments to loadable ARC components.

#include <Plugin.h>

Public Member Functions

- PluginsFactory * get_factory (void)
- Glib::Module * get_module (void)

6.119.1 Detailed Description

Base class for passing arguments to loadable ARC components.

During its creation constructor function of ARC loadable component expects instance of class inherited from this one or wrapped in it. Then dynamic type casting is used for obtaining class of expected kind.

6.119.2 Member Function Documentation

6.119.2.1 PluginsFactory* Arc::PluginArgument::get_factory (void)

Returns pointer to factory which instantiated plugin.

Because factory usually destroys/unloads plugins in its destructor it should be safe to keep this pointer inside plugin for later use. But one must always check.

6.119.2.2 Glib::Module* Arc::PluginArgument::get_module (void)

Returns pointer to loadable module/library which contains plugin.

Corresponding factory keeps list of modules till itself is destroyed. So it should be safe to keep that pointer. But care must be taken if module contains persistent plugins. Such modules stay in memory after factory is detroyed. So it is advisable to use obtained pointer only in constructor function of plugin.

The documentation for this class was generated from the following file:

6.120 Arc::PluginDesc Class Reference

Description of plugin.

#include <Plugin.h>

6.120.1 Detailed Description

Description of plugin.

This class is used for reports

The documentation for this class was generated from the following file:

6.121 Arc::PluginDescriptor Struct Reference

Description of ARC lodable component.

#include <Plugin.h>

6.121.1 Detailed Description

Description of ARC lodable component.


The documentation for this struct was generated from the following file:

6.122 Arc::PluginsFactory Class Reference

Generic ARC plugins loader.

#include <Plugin.h>

Inheritance diagram for Arc::PluginsFactory::



Public Member Functions

- PluginsFactory (XMLNode cfg)
- void TryLoad (bool v=true)
- bool load (const std::string &name)
- bool scan (const std::string &name, ModuleDesc &desc)
- void report (std::list< ModuleDesc > &descs)

6.122.1 Detailed Description

Generic ARC plugins loader.

The instance of this class provides functionality of loading pluggable ARC components stored in shared libraries. For more information please check HED documentation. This class is thread-safe - its methods are proceed from simultatneous use form multiple threads. Current thread protection implementation is suboptimal and will be revised in future.

6.122.2 Constructor & Destructor Documentation

6.122.2.1 Arc::PluginsFactory::PluginsFactory (XMLNode cfg)

Constructor - accepts configuration (not yet used) meant to tune loading of modules.

6.122.3 Member Function Documentation

6.122.3.1 bool Arc::PluginsFactory::load (const std::string & name)

These methods load module named lib'name' and check if it contains ARC plugin(s) of specified 'kind' and 'name'. If there are no specified plugins or module does not contain any ARC plugins it is unloaded. All loaded plugins are also registered in internal list of this instance of PluginsFactory (p. 284) class. Returns true if any plugin was loaded.

6.122.3.2 void Arc::PluginsFactory::report (std::list< ModuleDesc > & descs)

Provides information about currently loaded modules and plugins.

6.122.3.3 bool Arc::PluginsFactory::scan (const std::string & name, ModuleDesc & desc)

Collect information about plugins stored in module(s) with specified names. Returns true if any of specified modules has plugins.

6.122.3.4 void Arc::PluginsFactory::TryLoad (**bool** *v* = true) [inline]

Specifies if loadable module may be loaded while looking for analyzing its content. If set to false only *.apd files are checked. Modules without corresponding *.apd will be ignored. Default is true;


The documentation for this class was generated from the following file:

6.123 ArcSec::Policy Class Reference

Interface for containing and processing different types of policy.

#include <Policy.h>

Inheritance diagram for ArcSec::Policy::



Public Member Functions

- Policy ()
- Policy (const Arc::XMLNode)
- Policy (const Arc::XMLNode, EvaluatorContext *)
- virtual operator bool (void) const =0
- virtual MatchResult match (EvaluationCtx *)=0
- virtual Result eval (EvaluationCtx *)=0
- virtual void addPolicy (Policy *pl)
- virtual void setEvaluatorContext (EvaluatorContext *)
- virtual void make_policy ()
- virtual std::string getEffect () const =0
- virtual EvalResult & getEvalResult ()=0
- virtual void setEvalResult (EvalResult &res)=0
- virtual const char * getEvalName () const =0
- virtual const char * getName () const =0

6.123.1 Detailed Description

Interface for containing and processing different types of policy.

Basically, each policy object is a container which includes a few elements e.g., ArcPolicySet objects includes a few ArcPolicy objects; ArcPolicy object includes a few ArcRule objects. There is logical relationship between ArcRules or ArcPolicies, which is called combining algorithm. According to algorithm, evaluation results from the elements are combined, and then the combined evaluation result is returned to the up-level.

6.123.2 Constructor & Destructor Documentation

6.123.2.1 ArcSec::Policy::Policy() [inline]

Template constructor - creates empty policy.

6.123.2.2 ArcSec::Policy::Policy (const Arc::XMLNode) [inline]

Template constructor - creates policy based on XML document.

If XML document is empty then empty policy is created. If it is not empty then it must be valid policy document - otherwise created object should be invalid.

6.123.2.3 ArcSec::Policy::Policy (const Arc::XMLNode, EvaluatorContext *) [inline]

Template constructor - creates policy based on XML document.

If XML document is empty then empty policy is created. If it is not empty then it must be valid policy document - otherwise created object should be invalid. This constructor is based on the policy node and i the EvaluatorContext $(p.\,168)$ which includes the factory objects for combining algorithm and function

6.123.3 Member Function Documentation

6.123.3.1 virtual void ArcSec::Policy::addPolicy (Policy * pl) [inline, virtual]

Add a policy element to into "this" object

6.123.3.2 virtual Result ArcSec::Policy::eval (EvaluationCtx*) [pure virtual]

Evaluate policy For the <Rule> of Arc (p. 17), only get the "Effect" from rules; For the <Policy> of Arc (p. 17), combine the evaluation result from <Rule>; For the <Rule> of XACML, evaluate the <Condition> node by using information from request, and use the "Effect" attribute of <Rule>; For the <Policy> of XACML, combine the evaluation result from <Rule>

6.123.3.3 virtual std::string ArcSec::Policy::getEffect () const [pure virtual]

Get the "Effect" attribute

6.123.3.4 virtual const char* ArcSec::Policy::getEvalName () const [pure virtual]

Get the name of Evaluator (p. 165) which can evaluate this policy

6.123.3.5 virtual EvalResult & ArcSec::Policy::getEvalResult () [pure virtual]

Get eveluation result

6.123.3.6 virtual const char* ArcSec::Policy::getName () const [pure virtual]

Get the name of this policy

6.123.3.7 virtual void ArcSec::Policy::make_policy() [inline, virtual]

Parse XMLNode, and construct the low-level Rule object

6.123.3.8 virtual MatchResult ArcSec::Policy::match (EvaluationCtx *) [pure virtual]

Evaluate whether the two targets to be evaluated match to each other.

6.123.3.9 virtual ArcSec::Policy::operator bool (void) const [pure virtual]

Returns true is object is valid.

6.123.3.10 virtual void ArcSec::Policy::setEvalResult (EvalResult & res) [pure virtual]

Set eveluation result

6.123.3.11 virtual void ArcSec::Policy::setEvaluatorContext (EvaluatorContext *) [inline, virtual]

Set Evaluator (p. 165) Context for the usage in creating low-level policy object The documentation for this class was generated from the following file:

· Policy.h

6.124 ArcSec::PolicyParser Class Reference

A interface which will isolate the policy object from actual policy storage (files, urls, database).

#include <PolicyParser.h>

Public Member Functions

• virtual Policy * parsePolicy (const Source &source, std::string policyclassname, Evaluator-Context *ctx)

6.124.1 Detailed Description

A interface which will isolate the policy object from actual policy storage (files, urls, database). Parse the policy from policy source (e.g. files, urls, database, etc.).

6.124.2 Member Function Documentation

6.124.2.1 virtual Policy* ArcSec::PolicyParser::parsePolicy (const Source & source, std::string policyclassname, EvaluatorContext * ctx) [virtual]

Parse policy

Parameters:

```
source location of the policy
policyclassname name of the policy for ClassLoader
ctx EvaluatorContext (p. 168) which includes the **Factory
```

The documentation for this class was generated from the following file:

· PolicyParser.h

6.125 ArcSec::PolicyStore Class Reference

Storage place for policy objects.

#include <PolicyStore.h>

Public Member Functions

• PolicyStore (const std::string &alg, const std::string &policyclassname, EvaluatorContext *ctx)

Data Structures

• class PolicyElement

6.125.1 Detailed Description

Storage place for policy objects.

6.125.2 Constructor & Destructor Documentation

6.125.2.1 ArcSec::PolicyStore::PolicyStore (const std::string & alg, const std::string & policyclassname, EvaluatorContext * ctx)

Creates policy store with specified combing algorithm (alg - not used yet), policy name (policyclass-name) and context (ctx)

The documentation for this class was generated from the following file:


• PolicyStore.h

6.126 Arc::RegisteredService Class Reference

RegisteredService (p. 291) - extension of Service (p. 316) performing self-registration.

#include <RegisteredService.h>

Inheritance diagram for Arc::RegisteredService::



Public Member Functions

• RegisteredService (Config *)

6.126.1 Detailed Description

RegisteredService (p. 291) - extension of Service (p. 316) performing self-registration.

6.126.2 Constructor & Destructor Documentation

6.126.2.1 Arc::RegisteredService::RegisteredService (Config *)

Example contructor - Server takes at least it's configuration subtree

The documentation for this class was generated from the following file:

· RegisteredService.h

6.127 Arc::RegularExpression Class Reference

A regular expression class.

#include <ArcRegex.h>

Public Member Functions

- RegularExpression ()
- RegularExpression (std::string pattern)
- RegularExpression (const RegularExpression ®ex)
- ∼RegularExpression ()
- const RegularExpression & operator= (const RegularExpression & regex)
- bool isOk ()
- bool hasPattern (std::string str)
- bool match (const std::string &str) const
- bool match (const std::string &str, std::list< std::string > &unmatched, std::list< std::string > &matched) const
- std::string getPattern () const

6.127.1 Detailed Description

A regular expression class.

This class is a wrapper around the functions provided in regex.h.

6.127.2 Constructor & Destructor Documentation

6.127.2.1 Arc::RegularExpression::RegularExpression() [inline]

default constructor

6.127.2.2 Arc::RegularExpression::RegularExpression (std::string pattern)

Creates a reges from a pattern string.

6.127.2.3 Arc::RegularExpression::RegularExpression (const RegularExpression & regex)

Copy constructor.

6.127.2.4 Arc::RegularExpression::~RegularExpression ()

Destructor.

6.127.3 Member Function Documentation

 $\textbf{6.127.3.1} \quad \textbf{std::string Arc::RegularExpression::getPattern () const}$

Returns pattern.

6.127.3.2 bool Arc::RegularExpression::hasPattern (std::string str)

Returns true if this regex has the pattern provided.

6.127.3.3 bool Arc::RegularExpression::isOk ()

Returns true if the pattern of this regex is ok.

6.127.3.4 bool Arc::RegularExpression::match (const std::string & str, std::list< std::string > & unmatched, std::list< std::string > & matched) const

Returns true if this regex matches the string provided.

Unmatched parts of the string are stored in 'unmatched'. Matched parts of the string are stored in 'matched'. The first entry in matched is the string that matched the regex, and the following entries are parenthesised elements of the regex

6.127.3.5 bool Arc::RegularExpression::match (const std::string & str) const

Returns true if this regex matches whole string provided.

6.127.3.6 const RegularExpression& Arc::RegularExpression::operator= (const RegularExpression & regex)

Assignment operator.

The documentation for this class was generated from the following file:


· ArcRegex.h

6.128 ArcSec::Request Class Reference

Base class/Interface for request, includes a container for RequestItems and some operations.

#include <Request.h>

Inheritance diagram for ArcSec::Request::



Public Member Functions

- virtual RegItemList getRequestItems () const
- virtual void setRequestItems (ReqItemList)
- virtual void addRequestItem (Attrs &, Attrs &, Attrs &, Attrs &)
- virtual void setAttributeFactory (AttributeFactory *attributefactory)=0
- virtual void make_request ()=0
- virtual const char * getEvalName () const =0
- virtual const char * getName () const =0
- Request ()
- Request (const Source &)

6.128.1 Detailed Description

Base class/Interface for request, includes a container for RequestItems and some operations.

A Request (p. 294) object can has a few <subjects, actions, objects> tuples, i.e. Request-Item (p. 297) The Request (p. 294) class and any customized class which inherit from it, should be loadable, which means these classes can be dynamically loaded according to the configuration information, see the example configuration below: <Service name="pdp.service" id="pdp_service" <pdp:PDPConfig> <.....> <pdp:Request (p. 294) name="arc.request" /> <.....> </pdp:PDPConfig> </service>

There can be different types of subclass which inherit Request (p. 294), such like XACMLRequest, ArcRequest, GACLRequest

6.128.2 Constructor & Destructor Documentation

6.128.2.1 ArcSec::Request::Request() [inline]

Default constructor

6.128.2.2 ArcSec::Request::Request (const Source &) [inline]

Constructor: Parse request information from a xml stucture in memory

6.128.3 Member Function Documentation

6.128.3.1 virtual void ArcSec::Request::addRequestItem (Attrs &, Attrs &, Attrs &) [inline, virtual]

Add request tuple from non-XMLNode

6.128.3.2 virtual const char* ArcSec::Request::getEvalName () const [pure virtual]

Get the name of corresponding evaulator

6.128.3.3 virtual const char* ArcSec::Request::getName () const [pure virtual]

Get the name of this request

6.128.3.4 virtual ReqItemList ArcSec::Request::getRequestItems () const [inline, virtual]

Get all the RequestItem (p. 297) inside RequestItem (p. 297) container

6.128.3.5 virtual void ArcSec::Request::make_request() [pure virtual]

Create the objects included in Request (p. 294) according to the node attached to the Request (p. 294) object

6.128.3.6 virtual void ArcSec::Request::setAttributeFactory (AttributeFactory * *attributefactory***)** [pure virtual]

Set the attribute factory for the usage of Request (p. 294)

6.128.3.7 virtual void ArcSec::Request::setRequestItems (ReqItemList) [inline, virtual]

Set the content of the container

The documentation for this class was generated from the following file:

• Request.h

6.129 ArcSec::RequestAttribute Class Reference

Wrapper which includes AttributeValue (p. 53) object which is generated according to date type of one spefic node in Request.xml.

#include <RequestAttribute.h>

Public Member Functions

- RequestAttribute (Arc::XMLNode &node, AttributeFactory *attrfactory)
- RequestAttribute & duplicate (RequestAttribute &)

6.129.1 Detailed Description

Wrapper which includes AttributeValue (p. 53) object which is generated according to date type of one spefic node in Request.xml.

6.129.2 Constructor & Destructor Documentation

6.129.2.1 ArcSec::RequestAttribute::RequestAttribute (Arc::XMLNode & node, AttributeFactory * attrfactory)

Constructor - create attribute value object according to the "Type" in the node <Attribute attributeid="urn:arc:subject:voms-attribute" type="string">urn:mace:shibboleth:examples</Attribute>

6.129.3 Member Function Documentation

6.129.3.1 RequestAttribute& ArcSec::RequestAttribute::duplicate (RequestAttribute &)

Duplicate the parameter into "this"

The documentation for this class was generated from the following file:

• RequestAttribute.h

6.130 ArcSec::RequestItem Class Reference

Interface for request item container, < subjects, actions, objects, ctxs> tuple.

#include <RequestItem.h>

Public Member Functions

• RequestItem (Arc::XMLNode &, AttributeFactory *)

6.130.1 Detailed Description

Interface for request item container, < subjects, actions, objects, ctxs> tuple.

6.130.2 Constructor & Destructor Documentation

6.130.2.1 ArcSec::RequestItem::RequestItem (Arc::XMLNode &, AttributeFactory *) [inline]

Constructor

Parameters:

node The XMLNode structure of the request item

attributefactory The AttributeFactory (p. 48) which will be used to generate RequestAttribute

(p. 296)

The documentation for this class was generated from the following file:

· RequestItem.h

6.131 ArcSec::Response Class Reference

Container for the evaluation results.

#include <Response.h>

6.131.1 Detailed Description

Container for the evaluation results.

The documentation for this class was generated from the following file:

· Response.h

6.132 ArcSec::ResponseItem Class Reference

Evaluation result concerning one RequestTuple.

#include <Response.h>

6.132.1 Detailed Description

Evaluation result concerning one RequestTuple.

Include the RequestTuple, related XMLNode, the set of policy objects which give positive evaluation result, and the related XMLNode

The documentation for this class was generated from the following file:

· Response.h

6.133 Arc::Run Class Reference

#include <Run.h>

Public Member Functions

- Run (const std::string &cmdline)
- Run (const std::list< std::string > &argv)
- \sim Run (void)
- operator bool (void)
- bool operator! (void)
- bool Start (void)
- bool Wait (int timeout)
- bool Wait (void)
- int Result (void)
- bool Running (void)
- int ReadStdout (int timeout, char *buf, int size)
- int ReadStderr (int timeout, char *buf, int size)
- int WriteStdin (int timeout, const char *buf, int size)
- void AssignStdout (std::string &str)
- void AssignStderr (std::string &str)
- void AssignStdin (std::string &str)
- void KeepStdout (bool keep=true)
- void KeepStderr (bool keep=true)
- void KeepStdin (bool keep=true)
- void CloseStdout (void)
- void CloseStderr (void)
- void CloseStdin (void)
- void AssignWorkingDirectory (std::string &wd)
- void Kill (int timeout)
- void Abandon (void)

6.133.1 Detailed Description

This class runs external executable. It is possible to read/write it's standard handles or to redirect then to std::string elements.

6.133.2 Constructor & Destructor Documentation

6.133.2.1 Arc::Run::Run (const std::string & cmdline)

Constructor preapres object to run cmdline

6.133.2.2 Arc::Run::Run (const std::list< std::string > & argv)

Constructor preapres object to run executable and arguments specified in argv

6.133.2.3 Arc::Run::∼Run (void)

Destructor kills running executable and releases associated resources

6.133.3 Member Function Documentation

6.133.3.1 void Arc::Run::Abandon (void)

Detach this object from running process. After calling this method instance is not associated with external process anymore. As result destructor will not kill process.

6.133.3.2 void Arc::Run::AssignStderr (std::string & str)

Associate stderr handle of executable with string. This method must be called before Start() (p. 302). str object must be valid as long as this object exists.

6.133.3.3 void Arc::Run::AssignStdin (std::string & str)

Associate stdin handle of executable with string. This method must be called before Start() (p. 302). str object must be valid as long as this object exists.

6.133.3.4 void Arc::Run::AssignStdout (std::string & str)

Associate stdout handle of executable with string. This method must be called before Start() (p. 302). str object must be valid as long as this object exists.

6.133.3.5 void Arc::Run::AssignWorkingDirectory (**std::string** & *wd*) [inline]

Assign working directtry of the running process

6.133.3.6 void Arc::Run::CloseStderr (void)

Closes pipe associated with stderr handle

6.133.3.7 void Arc::Run::CloseStdin (void)

Closes pipe associated with stdin handle

6.133.3.8 void Arc::Run::CloseStdout (void)

Closes pipe associated with stdout handle

6.133.3.9 void Arc::Run::KeepStderr (bool *keep* = true)

Keep stderr same as parent's if keep = true

6.133.3.10 void Arc::Run::KeepStdin (bool *keep* = true)

Keep stdin same as parent's if keep = true

6.133.3.11 void Arc::Run::KeepStdout (bool keep = true)

Keep stdout same as parent's if keep = true

6.133.3.12 void Arc::Run::Kill (int timeout)

Kill running executable. First soft kill signal (SIGTERM) is sent to executable. If after timeout seconds executable is still running it's killed completely. Curently this method does not work for Windows OS

6.133.3.13 Arc::Run::operator bool (void) [inline]

Returns true if object is valid

6.133.3.14 bool Arc::Run::operator! (void) [inline]

Returns true if object is invalid

6.133.3.15 int Arc::Run::ReadStderr (int timeout, char * buf, int size)

Read from stderr handle of running executable. Parameter timeout specifies upper limit for which method will block in milliseconds. Negative means infinite. This method may be used while stderr is directed to string. But result is unpredictable. Returns number of read bytes.

6.133.3.16 int Arc::Run::ReadStdout (int timeout, char * buf, int size)

Read from stdout handle of running executable. Parameter timeout specifies upper limit for which method will block in milliseconds. Negative means infinite. This method may be used while stdout is directed to string. But result is unpredictable. Returns number of read bytes.

6.133.3.17 int Arc::Run::Result (void) [inline]

Returns exit code of execution.

6.133.3.18 bool Arc::Run::Running (void)

Return true if execution is going on.

6.133.3.19 bool Arc::Run::Start (void)

Starts running executable. This method may be called only once.

6.133.3.20 bool Arc::Run::Wait (void)

Wait till execution finished

6.133.3.21 bool Arc::Run::Wait (int timeout)

Wait till execution finished or till timeout seconds expires. Returns true if execution is complete.

6.133.3.22 int Arc::Run::WriteStdin (int timeout, const char * buf, int size)

Write to stdin handle of running executable. Parameter timeout specifies upper limit for which method will block in milliseconds. Negative means infinite. This method may be used while stdin is directed to string. But result is unpredictable. Returns number of written bytes.

The documentation for this class was generated from the following file:

· Run.h

6.134 Arc::SAMLToken Class Reference

Class for manipulating SAML Token Profile.

#include <SAMLToken.h>

Public Types

• enum SAMLVersion

Public Member Functions

- SAMLToken (SOAPEnvelope &soap)
- SAMLToken (SOAPEnvelope &soap, const std::string &certfile, const std::string &keyfile, SAMLVersion saml_version=SAML2, XMLNode saml_assertion=XMLNode())
- ∼SAMLToken (void)
- operator bool (void)
- bool Authenticate (const std::string &cafile, const std::string &capath)
- bool Authenticate (void)

6.134.1 Detailed Description

Class for manipulating SAML Token Profile.

This class is for generating/consuming SAML Token profile. See WS-Security SAML Token Profile v1.1 (www.oasis-open.org/committees/wss) Currently this class is used by samltoken handler (will appears in src/hed/pdc/samltokensh/) It is not a must to directly called this class. If we need to use SAML Token functionality, we only need to configure the samltoken handler into service and client. Currently, only a minor part of the specification has been implemented.

About how to identify and reference security token for signing message, currently, only the "SAML Assertion Referenced from KeyInfo" (part 3.4.2 of WS-Security SAML Token Profile v1.1 specification) is supported, which means the implementation can only process SAML assertion "referenced from KeyInfo", and also can only generate SAML Token with SAML assertion "referenced from KeyInfo". More complete support need to implement.

About subject confirmation method, the implementation can process "hold-of-key" (part 3.5.1 of WS-Security SAML Token Profile v1.1 specification) subject subject confirmation method.

About SAML vertion, the implementation can process SAML assertion with SAML version 1.1 and 2.0; can only generate SAML assertion with SAML vertion 2.0.

In the SAML Token profile, for the hold-of-key subject confirmation method, there are three interaction parts: the attesting entity, the relying party and the issuing authority. In the hold-of-key subject confirmation method, it is the attesting entity's subject identity which will be inserted into the SAML assertion.

Firstly the attesting entity authenticates to issuing authority by using some authentication scheme such as WSS x509 Token profile (Alterbatively the usename/password authentication scheme or other different authentication scheme can also be used, unless the issuing authority can retrive the key from a trusted certificate server after firmly establishing the subject's identity under the username/password scheme). So then issuing authority is able to make a definitive statement (sign a SAML assertion) about an act of authentication that has already taken place.

The attesting entity gets the SAML assertion and then signs the soap message together with the assertion by using its private key (the relevant certificate has been authenticated by issuing authority, and its relevant public key has been put into SubjectConfirmation element under saml assertion by issuing authority. Only the actual owner of the saml assertion can do this, as only the subject possesses the private key paired with the public key in the assertion. This establishes an irrefutable connection between the author of the SOAP message and the assertion describing an authentication event.)

The relying party is supposed to trust the issuing authority. When it receives a message from the asserting entity, it will check the saml assertion based on its predetermined trust relationship with the SAML issuing authority, and check the signature of the soap message based on the public key in the saml assertion without directly trust relationship with attesting entity (subject owner).

6.134.2 Member Enumeration Documentation

6.134.2.1 enum Arc::SAMLToken::SAMLVersion

Since the specification SAMLVersion is for distinguishing two types of saml version. It is used as the parameter of constructor.

6.134.3 Constructor & Destructor Documentation

6.134.3.1 Arc::SAMLToken::SAMLToken (SOAPEnvelope & soap)

Constructor. Parse SAML Token information from SOAP header. SAML Token related information is extracted from SOAP header and stored in class variables. And then it the SAMLToken (p. 304) object will be used for authentication.

Parameters:

soap The SOAP message which contains the SAMLToken (p. 304) in the soap header

6.134.3.2 Arc::SAMLToken::SAMLToken (SOAPEnvelope & soap, const std::string & certfile, const std::string & keyfile, SAMLVersion saml_version = SAML2, XMLNode saml_assertion = XMLNode())

Constructor. Add SAML Token information into the SOAP header. Generated token contains elements SAML token and signature, and is meant to be used for authentication on the consuming side. This constructor is for a specific SAML Token profile usage, in which the attesting entity signs the SAML assertion for itself (self-sign). This usage implicitly requires that the relying party trust the attesting entity. More general (requires issuing authority) usage will be provided by other constructor. And the under-developing SAML service will be used as the issuing authority.

Parameters:

soap The SOAP message to which the SAML Token will be inserted.

certfile The certificate file.

keyfile The key file which will be used to create signature.

samlversion The SAML version, only SAML2 is supported currently.

samlassertion The SAML assertion got from 3rd party, and used for protecting the SOAP message; If not present, then self-signed assertion will be generated.

6.134.3.3 Arc::SAMLToken::~SAMLToken (void)

Deconstructor. Nothing to be done except finalizing the xmlsec library.

6.134.4 Member Function Documentation

6.134.4.1 bool Arc::SAMLToken::Authenticate (void)

Check signature by using the cert information in soap message

6.134.4.2 bool Arc::SAMLToken::Authenticate (const std::string & cafile, const std::string & capath)

Check signature by using the trusted certificates It is used by relying parting after calling SAMLTo-ken(SOAPEnvelope& soap) (p. 305) This method will check the SAML assertion based on the trusted certificated specified as parameter cafile or capath; and also check the signature to soap message (the signature is generated by attesting entity by signing soap body together witl SAML assertion) by using the public key inside SAML assetion.

Parameters:

cafile ca file capath ca directory

6.134.4.3 Arc::SAMLToken::operator bool (void)

Returns true of constructor succeeded

The documentation for this class was generated from the following file:


• SAMLToken.h

6.135 Arc::SecAttr Class Reference

This is an abstract interface to a security attribute.

#include <SecAttr.h>

Inheritance diagram for Arc::SecAttr::



Public Member Functions

- SecAttr ()
- bool operator== (const SecAttr &b) const
- bool operator!= (const SecAttr &b) const
- virtual operator bool () const
- virtual bool Export (SecAttrFormat format, std::string &val) const
- virtual bool Export (SecAttrFormat format, XMLNode &val) const
- virtual bool Import (SecAttrFormat format, const std::string &val)

Static Public Attributes

- static SecAttrFormat ARCAuth
- static SecAttrFormat XACML
- static SecAttrFormat SAML
- static SecAttrFormat GACL

6.135.1 Detailed Description

This is an abstract interface to a security attribute.

This class is meant to be inherited to implement security attributes. Depending on what data it needs to store inheriting classes may need to implement constructor and destructor. They must however override the equality and the boolean operators. The equality is meant to compare security attributes. The prototype implies that all attributes are comparable to all others. This behaviour should be modified as needed by using dynamic_cast operations. The boolean cast operation is meant to embody "nullness" if that is applicable to the particular type.

6.135.2 Constructor & Destructor Documentation

6.135.2.1 Arc::SecAttr::SecAttr() [inline]

representation for GACL policy

6.135.3 Member Function Documentation

6.135.3.1 virtual bool Arc::SecAttr::Export (SecAttrFormat format, XMLNode & val) const [virtual]

Convert internal structure into specified format. Returns false if format is not supported/suitable for this attribute. XML node referenced by is turned into top level element of specified format.

Reimplemented in Arc::MultiSecAttr (p. 253).

6.135.3.2 virtual bool Arc::SecAttr::Export (SecAttrFormat *format***, std::string &** *val***) const** [virtual]

Convert internal structure into specified format. Returns false if format is not supported/suitable for this attribute.

6.135.3.3 virtual bool Arc::SecAttr::Import (SecAttrFormat format, const std::string & val)

[virtual]

Fills internal structure from external object of specified format. Returns false if failed to do. The usage pattern for this method is not defined and it is provided only to make class symmetric. Hence it's implementation is not required yet.

6.135.3.4 virtual Arc::SecAttr::operator bool () const [virtual]

This function should return false if the value is to be considered null, e.g. if it hasn't been set or initialized. In other cases it should return true.

Reimplemented in Arc::MultiSecAttr (p. 253).

6.135.3.5 bool Arc::SecAttr::operator!= (const SecAttr & b) const [inline]

This is a convenience function to allow the usage of "not equal" conditions and need not be overridden.

6.135.3.6 bool Arc::SecAttr::operator== (const SecAttr & b) const [inline]

This function should (in inheriting classes) return true if this and b are considered to represent same content. Identifying and restricting the type of b should be done using dynamic_cast operations. Currently it is not defined how comparison methods to be used. Hence their implementation is not required.

6.135.4 Field Documentation

6.135.4.1 SecAttrFormat Arc::SecAttr::ARCAuth [static]

own serialization/deserialization format

6.135.4.2 SecAttrFormat Arc::SecAttr::GACL [static]

suitable for inclusion into SAML structures

6.135.4.3 SecAttrFormat Arc::SecAttr::SAML [static]

represenation for XACML policy

6.135.4.4 SecAttrFormat Arc::SecAttr::XACML [static]

representation for ARC authorization policy

The documentation for this class was generated from the following file:

• SecAttr.h

6.136 Arc::SecAttrFormat Class Reference

Export/import format.

#include <SecAttr.h>

6.136.1 Detailed Description

Export/import format.

Format is identified by textual identity string. Class description includes basic formats only. That list may be extended.

The documentation for this class was generated from the following file:


• SecAttr.h

6.137 Arc::SecAttrValue Class Reference

This is an abstract interface to a security attribute.

#include <SecAttrValue.h>

Inheritance diagram for Arc::SecAttrValue::



Public Member Functions

- bool operator== (SecAttrValue &b)
- bool operator!= (SecAttrValue &b)
- virtual operator bool ()

6.137.1 Detailed Description

This is an abstract interface to a security attribute.

This class is meant to be inherited to implement security attributes. Depending on what data it needs to store inheriting classes may need to implement constructor and destructor. They must however override the equality and the boolean operators. The equality is meant to compare security attributes. The prototype implies that all attributes are comparable to all others. This behaviour should be modified as needed by using dynamic_cast operations. The boolean cast operation is meant to embody "nullness" if that is applicable to the particular type.

6.137.2 Member Function Documentation

6.137.2.1 virtual Arc::SecAttrValue::operator bool () [virtual]

This function should return false if the value is to be considered null, e g if it hasn't been set or initialized. In other cases it should return true.

Reimplemented in Arc::CIStringValue (p. 68).

6.137.2.2 bool Arc::SecAttrValue::operator!= (SecAttrValue & b)

This is a convenience function to allow the usage of "not equal" conditions and need not be overridden.

6.137.2.3 bool Arc::SecAttrValue::operator== (SecAttrValue & b)

This function should (in inheriting classes) return true if this and b are considered to be the same. Identifying and restricting the type of b should be done using dynamic_cast operations.

The documentation for this class was generated from the following file:


• SecAttrValue.h

6.138 ArcSec::SecHandler Class Reference

Base class for simple security handling plugins.

#include <SecHandler.h>

Inheritance diagram for ArcSec::SecHandler::



6.138.1 Detailed Description

Base class for simple security handling plugins.

This virtual class defines method Handle() which processes security related information/attributes in Message and optionally makes security decision. Instances of such classes are normally arranged in chains abd are called on incoming and outgoing messages in various MCC and Service plugins. Return value of Handle() defines either processing should continie (true) or stop with error (false). Configuration of SecHandler (p. 313) is consumed during creation of instance through XML subtree fed to constructor.


The documentation for this class was generated from the following file:

• SecHandler.h

6.139 ArcSec::SecHandlerConfig Class Reference

#include <SecHandler.h>

Inheritance diagram for ArcSec::SecHandlerConfig::



6.139.1 Detailed Description

Helper class to create Security (p. 315) Handler configuration

The documentation for this class was generated from the following file:

• SecHandler.h

6.140 ArcSec::Security Class Reference

Common stuff used by security related slasses.

#include <Security.h>

6.140.1 Detailed Description

Common stuff used by security related slasses.

This class is just a place where to put common stuff that is used by security related slasses. So far it only contains a logger.

The documentation for this class was generated from the following file:


• Security.h

6.141 Arc::Service Class Reference

Service (p. 316) - last component in a Message (p. 238) Chain.

#include <Service.h>

Inheritance diagram for Arc::Service::



Public Member Functions

- Service (Config *)
- virtual void AddSecHandler (Config *cfg, ArcSec::SecHandler *sechandler, const std::string &label='''')
- virtual bool RegistrationCollector (XMLNode &doc)
- virtual std::string getID ()

Protected Member Functions

• bool ProcessSecHandlers (Message &message, const std::string &label="") const

Protected Attributes

• std::map< std::string, std::list< ArcSec::SecHandler * > > sechandlers_

Static Protected Attributes

· static Logger logger

6.141.1 Detailed Description

Service (p. 316) - last component in a Message (p. 238) Chain.

This class which defines interface and common functionality for every Service (p. 316) plugin. Interface is made of method process() (p. 233) which is called by Plexer (p. 277) or MCC (p. 227) class. There is one Service (p. 316) object created for every service description processed by Loader (p. 212) class objects. Classes derived from Service (p. 316) class must implement process() (p. 233) method of MCCInterface (p. 233). It is up to developer how internal state of service is stored and communicated to other services and external utilites. Service (p. 316) is free to expect any type of payload passed to it and generate any payload as well. Useful types depend on MCCs in chain which leads

to that service. For example if service is expected to by linked to SOAP MCC (p.227) it must accept and generate messages with PayloadSOAP (p.264) payload. Method process() (p.233) of class derived from Service (p.316) class may be called concurrently in multiple threads. Developers must take that into account and write thread-safe implementation. Simple example of service is provided in /src/tests/echo/echo.cpp of source tree. The way to write client couterpart of corresponding service is undefined yet. For example see /src/tests/echo/test.cpp .

6.141.2 Constructor & Destructor Documentation

6.141.2.1 Arc::Service::Service (Config *)

Example contructor - Server takes at least it's configuration subtree

6.141.3 Member Function Documentation

6.141.3.1 virtual void Arc::Service::AddSecHandler (Config * cfg, ArcSec::SecHandler * sechandler, const std::string & label = "") [virtual]

Add security components/handlers to this MCC (p. 227). For more information please see description of MCC::AddSecHandler (p. 228)

6.141.3.2 virtual std::string Arc::Service::getID () [inline, virtual]

Service (p. 316) may implement own service identitifer gathering method. This method return identifier of service which is used for registering it Information Services.

6.141.3.3 bool Arc::Service::ProcessSecHandlers (Message & message, const std::string & label = "") const [protected]

Executes security handlers of specified queue. For more information please see description of MCC::ProcessSecHandlers (p. 228)

6.141.3.4 virtual bool Arc::Service::RegistrationCollector (XMLNode & doc) [virtual]

Service (p. 316) specific registartion collector, used for generate service registartions. In implemented service this method should generate GLUE2 document with part of service description which service wishes to advertise to Information Services.

6.141.4 Field Documentation

6.141.4.1 Logger Arc::Service::logger [static, protected]

Logger (p. 218) object used to print messages generated by this class.

 $\textbf{6.141.4.2} \quad \textbf{std::map} < \textbf{std::string,std::list} < \textbf{ArcSec::SecHandler*} > \textbf{Arc::Service::sechandlers} \\ [\texttt{protected}]$

Set of labeled authentication and authorization handlers. MCC (p. 227) calls sequence of handlers at specific point depending on associated identifier. in most aces those are "in" and "out" for incoming and outgoing messages correspondingly.

The documentation for this class was generated from the following file:

• Service.h

6.142 Arc::SimpleCondition Class Reference

Simple triggered condition.

#include <Thread.h>

Public Member Functions

- void lock (void)
- void unlock (void)
- void signal (void)
- void signal_nonblock (void)
- void broadcast (void)
- void wait (void)
- void wait_nonblock (void)
- bool wait (int t)
- void reset (void)

6.142.1 Detailed Description

Simple triggered condition.

Provides condition and semaphor objects in one element.

6.142.2 Member Function Documentation

6.142.2.1 void Arc::SimpleCondition::broadcast (void) [inline]

Signal about condition to all waiting threads

6.142.2.2 void Arc::SimpleCondition::lock (void) [inline]

Acquire semaphor

6.142.2.3 void Arc::SimpleCondition::reset (void) [inline]

Reset object to initial state

6.142.2.4 void Arc::SimpleCondition::signal (void) [inline]

Signal about condition

6.142.2.5 void Arc::SimpleCondition::signal_nonblock (void) [inline]

Signal about condition without using semaphor

6.142.2.6 void Arc::SimpleCondition::unlock (void) [inline]

Release semaphor

6.142.2.7 bool Arc::SimpleCondition::wait (int *t*) [inline]

Wait for condition no longer than t milliseconds

6.142.2.8 void Arc::SimpleCondition::wait (void) [inline]

Wait for condition

6.142.2.9 void Arc::SimpleCondition::wait_nonblock (void) [inline]

Wait for condition without using semaphor

The documentation for this class was generated from the following file:

· Thread.h

6.143 Arc::SOAPMessage Class Reference

Message (p. 238) restricted to SOAP payload.

#include <SOAPMessage.h>

Public Member Functions

- SOAPMessage (void)
- SOAPMessage (long msg_ptr_addr)
- SOAPMessage (Message &msg)
- ∼SOAPMessage (void)
- SOAPEnvelope * Payload (void)
- void Payload (SOAPEnvelope *new_payload)
- MessageAttributes * Attributes (void)

6.143.1 Detailed Description

Message (p. 238) restricted to SOAP payload.

This is a special Message (p. 238) intended to be used in language bindings for programming languages which are not flexible enough to support all kinds of Payloads. It is passed through chain of MCCs and works like the Message (p. 238) but can carry only SOAP content.

6.143.2 Constructor & Destructor Documentation

6.143.2.1 Arc::SOAPMessage::SOAPMessage (void) [inline]

Dummy constructor

6.143.2.2 Arc::SOAPMessage::SOAPMessage (long msg_ptr_addr)

Copy constructor. Used by language bindigs

6.143.2.3 Arc::SOAPMessage::SOAPMessage (Message & msg)

Copy constructor. Ensures shallow copy.

6.143.2.4 Arc::SOAPMessage::~SOAPMessage (void)

Destructor does not affect refered objects

6.143.3 Member Function Documentation

6.143.3.1 MessageAttributes* Arc::SOAPMessage::Attributes (void) [inline]

Returns a pointer to the current attributes object or NULL if no attributes object has been assigned.

6.143.3.2 void Arc::SOAPMessage::Payload (SOAPEnvelope * new_payload)

Replace payload with a COPY of new one

6.143.3.3 SOAPEnvelope* Arc::SOAPMessage::Payload (void)

Returns pointer to current payload or NULL if no payload assigned.

The documentation for this class was generated from the following file:


• SOAPMessage.h

6.144 Arc::Software Class Reference

Used to represent software (names and version) and comparison.

#include <Software.h>

Inheritance diagram for Arc::Software::



Public Types

- typedef bool(Software::*) ComparisonOperator (const Software &) const
- NOTEQUAL = 0
- EQUAL = 1
- GREATERTHAN = 2
- LESSTHAN = 3
- GREATERTHANOREQUAL = 4
- LESSTHANOREQUAL = 5
- enum ComparisonOperatorEnum {

NOTEQUAL = 0, EQUAL = 1, GREATERTHAN = 2, LESSTHAN = 3, GREATERTHANOREQUAL = 4, LESSTHANOREQUAL = 5 }

Public Member Functions

- Software ()
- Software (const std::string &name_version)
- Software (const std::string &name, const std::string &version)
- Software (const std::string &family, const std::string &name, const std::string &version)
- bool empty () const
- bool operator== (const Software &sw) const
- bool operator!= (const Software &sw) const
- bool operator> (const Software &sw) const
- bool operator< (const Software &sw) const
- bool operator>= (const Software &sw) const
- bool operator <= (const Software &sw) const
- std::string operator() () const
- operator std::string (void) const
- const std::string & getFamily () const
- const std::string & getName () const
- const std::string & getVersion () const

Static Public Member Functions

- static ComparisonOperator convert (const ComparisonOperatorEnum &co)
- static std::string toString (ComparisonOperator co)

Static Public Attributes

static const std::string VERSIONTOKENS

Friends

• std::ostream & operator<< (std::ostream &out, const Software &sw)

6.144.1 Detailed Description

Used to represent software (names and version) and comparison.

The Software (p. 323) class is used to represent the name of a piece of software internally. Generally software are identified by a name and possibly a version number. Some software can also be categorized by type or family (compilers, operating system, etc.). A software object can be compared to other software objects using the comparison operators contained in this class. The basic usage of this class is to test if some specified software requirement (SoftwareRequirement (p. 331)) are fulfilled, by using the comparability of the class.

Internally the Software (p. 323) object is represented by a family and name identifier, and the software version is tokenized at the characters defined in VERSIONTOKENS, and stored as a list of tokens.

6.144.2 Member Typedef Documentation

6.144.2.1 typedef bool(Software::*) Arc::Software::ComparisonOperator(const Software &) const

Definition of a comparison operator method pointer.

This typedef defines a comparison operator method pointer.

See also:

```
operator==,
operator!=,
operator>,
operator<,
operator>=,
operator<=,
ComparisonOperatorEnum (p. 324).</pre>
```

6.144.3 Member Enumeration Documentation

6.144.3.1 enum Arc::Software::ComparisonOperatorEnum

Comparison operator enum.

The ComparisonOperatorEnum (p. 324) enumeration is a 1-1 correspondance between the defined comparison method operators (Software::ComparisonOperator (p. 324)), and can be used in circumstances where method pointers are not supported.

Enumerator:

```
NOTEQUAL see operator!=
```

EQUAL see operator==

GREATERTHAN see operator>

LESSTHAN see operator<

GREATERTHANOREQUAL see operator>=

LESSTHANOREQUAL see operator<=

6.144.4 Constructor & Destructor Documentation

6.144.4.1 Arc::Software::Software() [inline]

Dummy constructor.

This constructor creates a empty object.

6.144.4.2 Arc::Software::Software (const std::string & name_version)

Create a Software (p. 323) object.

Create a Software (p. 323) object from a single string composed of a name and a version part. The created object will contain a empty family part. The name and version part of the string will be split at the first occurrence of a dash (-) which is followed by a digit (0-9). If the string does not contain such a pattern, the passed string will be taken to be the name and version will be empty.

Parameters:

name_version should be a string composed of the name and version of the software to represent.

6.144.4.3 Arc::Software::Software (const std::string & name, const std::string & version)

Create a Software (p. 323) object.

Create a Software (p. 323) object with the specified name and version. The family part will be left empty.

Parameters:

name the software name to represent.

version the software version to represent.

6.144.4.4 Arc::Software::Software (const std::string & family, const std::string & name, const std::string & version)

Create a Software (p. 323) object.

Create a Software (p. 323) object with the specified family, name and version.

Parameters:

family the software family to represent.

name the software name to represent.

version the software version to represent.

6.144.5 Member Function Documentation

6.144.5.1 static ComparisonOperator Arc::Software::convert (const ComparisonOperatorEnum & co) [static]

Convert a ComparisonOperatorEnum (p. 324) value to a comparison method pointer.

The passed ComparisonOperatorEnum (p. 324) will be converted to a comparison method pointer defined by the Software::ComparisonOperator (p. 324) typedef.

This static method is not defined in language bindings created with Swig, since method pointers are not supported by Swig.

Parameters:

co a ComparisonOperatorEnum (p. 324) value.

Returns:

A method pointer to a comparison method is returned.

6.144.5.2 bool Arc::Software::empty () const [inline]

Indicates whether the object is empty.

Returns:

true if the name of this object is empty, otherwise false.

6.144.5.3 const std::string& Arc::Software::getFamily () const [inline]

Get family.

Returns:

The family the represented software belongs to is returned.

6.144.5.4 const std::string& Arc::Software::getName () const [inline]

Get name.

Returns:

The name of the represented software is returned.

6.144.5.5 const std::string& Arc::Software::getVersion () const [inline]

Get version.

Returns:

The version of the represented software is returned.

6.144.5.6 Arc::Software::operator std::string (void) const [inline]

Cast to string.

This casting operator behaves exactly as ::operator()() does. The cast is used like (std::string) <software-object>.

See also:

operator()().

6.144.5.7 bool Arc::Software::operator!= (const Software & sw) const [inline]

Inequality operator (non-trivial behaviour).

The inequality operator should be used to test if two Software (p. 323) objects are of different versions but share the same name and family. So it should not be used to test if two Software (p. 323) objects differ in either name, version or family. Two Software (p. 323) objects are inequal if they share the same name and family but have different versions and the versions are non-empty.

Parameters:

sw is the RHS Software (p. 323) object.

Returns:

true when the two objects are inequal, otherwise false.

6.144.5.8 std::string Arc::Software::operator() () const

Get string representation.

Returns the string representation of this object, which is 'family'-'name'-'version'.

Returns:

The string representation of this object is returned.

See also

operator std::string() (p. 327).

6.144.5.9 bool Arc::Software::operator < (const Software & sw) const [inline]

Less-than operator.

The behaviour of this less-than operator is equivalent to the greater-than operator (operator>() (p. 328)) with the LHS and RHS swapped.

Parameters:

sw is the RHS object.

Returns:

true if the LHS is less than the RHS, otherwise false.

See also:

```
operator>() (p. 328).
```

6.144.5.10 bool Arc::Software::operator<= (const Software & sw) const [inline]

Less-than or equal operator.

The LHS object is greater than or equal to the RHS object if the LHS equal the RHS (operator==() (p. 328)) or if the LHS is greater than the RHS (operator>() (p. 328)).

Parameters:

```
sw is the RHS object.
```

Returns:

true if the LHS is less than or equal the RHS, otherwise false.

See also:

```
operator==() (p. 328),
operator<() (p. 327).</pre>
```

6.144.5.11 bool Arc::Software::operator== (const Software & sw) const [inline]

Equality operator.

Two Software (p. 323) objects are equal if they are of the same family, and if they have the same name. If BOTH objects specifies a version they must also equal, for the objects to be equal. Otherwise the two objects does not equal. This operator can also be represented by the Software::EQUAL (p. 325) ComparisonOperatorEnum (p. 324) value.

Parameters:

```
sw is the RHS Software (p. 323) object.
```

Returns:

true when the two objects equals, otherwise false.

6.144.5.12 bool Arc::Software::operator> (const Software & sw) const

Greater-than operator.

For the LHS object to be greater than the RHS object they must first share the same family and name and have non-empty versions. Then, the first version token of each object is compared and if they are identical, the two next version tokens will be compared. If not identical, the two tokens will be parsed as integers, and if parsing fails the LHS is not greater than the RHS. If parsing succeeds

and the integers equals, the two next tokens will be compared, otherwise the comparison is resolved by the integer comparison.

If the LHS contains more version tokens than the RHS, and the comparison have not been resolved at the point of equal number of tokens, then if the additional tokens contains a token which cannot be parsed to a integer the LHS is not greater than the RHS. If the parsed integer is not 0 then the LHS is greater than the RHS. If the rest of the additional tokens are 0, the LHS is not greater than the RHS.

If the RHS contains more version tokens than the LHS and comparison have not been resolved at the point of equal number of tokens, or simply if comparison have not been resolved at the point of equal number of tokens, then the LHS is not greater than the RHS.

Parameters:

sw is the RHS object.

Returns:

true if the LHS is greater than the RHS, otherwise false.

6.144.5.13 bool Arc::Software::operator>= (const Software & sw) const [inline]

Greater-than or equal operator.

The LHS object is greater than or equal to the RHS object if the LHS equal the RHS (operator==() (p. 328)) or if the LHS is greater than the RHS (operator>() (p. 328)).

Parameters:

sw is the RHS object.

Returns:

true if the LHS is greated than or equal the RHS, otherwise false.

See also:

```
operator==() (p. 328), operator>() (p. 328).
```

6.144.5.14 static std::string Arc::Software::toString (ComparisonOperator co) [static]

Convert Software::ComparisonOperator (p. 324) to a string.

This method is not available in language bindings created by Swig, since method pointers are not supported by Swig.

Parameters:

```
co is a Software::ComparisonOperator (p. 324).
```

Returns:

The string representation of the passed Software::ComparisonOperator (p. 324) is returned.

6.144.6 Friends And Related Function Documentation

6.144.6.1 std::ostream & operator << (std::ostream & out, const Software & sw) [friend]

Write Software (p. 323) string representation to a std::ostream.

Write the string representation of a Software (p. 323) object to a std::ostream.

Parameters:

out is a std::ostream to write the string representation of the Software (p. 323) object to. sw is the Software (p. 323) object to write to the std::ostream.

Returns:

The passed std::ostream out is returned.

6.144.7 Field Documentation

6.144.7.1 const std::string Arc::Software::VERSIONTOKENS [static]

Tokens used to split version string.

This string constant specifies which tokens will be used to split the version string.

The documentation for this class was generated from the following file:

• Software.h

6.145 Arc::SoftwareRequirement Class Reference

Class used to express and resolve version requirements on software.

#include <Software.h>

Public Member Functions

- SoftwareRequirement (bool requiresAll=false)
- SoftwareRequirement (const Software &sw, Software::ComparisonOperator swCom-Op=&Software::operator==, bool requiresAll=false)
- SoftwareRequirement (const Software &sw, Software::ComparisonOperatorEnum co, bool requiresAll=false)
- SoftwareRequirement & operator= (const SoftwareRequirement &sr)
- SoftwareRequirement (const SoftwareRequirement &sr)
- void add (const Software &sw, Software::ComparisonOperator swCom-Op=&Software::operator==)
- void add (const Software &sw, Software::ComparisonOperatorEnum co)
- bool isRequiringAll () const
- void setRequirement (bool all)
- bool isSatisfied (const Software &sw) const
- bool isSatisfied (const std::list< Software > &swList) const
- bool isSatisfied (const std::list< ApplicationEnvironment > &swList) const
- bool selectSoftware (const Software &sw)
- bool selectSoftware (const std::list< Software > &swList)
- bool selectSoftware (const std::list< ApplicationEnvironment > &swList)
- bool isResolved () const
- bool empty () const
- void clear ()
- const std::list< Software > & getSoftwareList () const
- const std::list< Software::ComparisonOperator > & getComparisonOperatorList () const

6.145.1 Detailed Description

Class used to express and resolve version requirements on software.

A requirement in this class is defined as a pair composed of a Software (p. 323) object and either a Software::ComparisonOperator (p. 324) method pointer or equally a Software::ComparisonOperatorEnum (p. 324) enum value. A SoftwareRequirement (p. 331) object can contain multiple of such requirements, and then it can specified if all these requirements should be satisfied, or if it is enough to satisfy only one of them. The requirements can be satisfied by a single Software (p. 323) object or a list of either Software (p. 323) or ApplicationEnvironment (p. 45) objects, by using the method isSatisfied() (p. 336). This class also contain a number of methods (selectSoftware() (p. 337)) to select Software (p. 323) objects which are satisfying the requirements, and in this way resolving requirements.

6.145.2 Constructor & Destructor Documentation

6.145.2.1 Arc::SoftwareRequirement::SoftwareRequirement (bool requiresAll = false) [inline]

Create a empty SoftwareRequirement (p. 331) object.

The created Software Requirement (p. 331) object will contain no requirements.

Parameters:

requiresAll indicates whether the all requirements have to be satisfied (true) or if only a single one (false), the default is that only a single requirement need to be satisfied.

6.145.2.2 Arc::SoftwareRequirement::SoftwareRequirement (const Software & sw, Software::ComparisonOperator swComOp = &Software::operator==, bool requiresAll = false)

Create a SoftwareRequirement (p. 331) object.

The created SoftwareRequirement (p. 331) object will contain one requirement specified by the Software (p. 323) object sw, and the Software::ComparisonOperator (p. 324) swComOp.

This constructor is not available in language bindings created by Swig, since method pointers are not supported by Swig, see SoftwareRequirement(const Software&, Software::ComparisonOperator-Enum, bool) (p. 332) instead.

Parameters:

```
sw is the Software (p. 323) object of the requirement to add.
```

swComOp is the Software::ComparisonOperator (p. 324) of the requirement to add.

requiresAll indicates whether the all requirements have to be satisfied (true) or if only a single one (false), the default is that only a single requirement need to be satisfied.

6.145.2.3 Arc::SoftwareRequirement::SoftwareRequirement (const Software & sw, Software::ComparisonOperatorEnum co, bool requiresAll = false)

Create a SoftwareRequirement (p. 331) object.

The created SoftwareRequirement (p. 331) object will contain one requirement specified by the Software (p. 323) object sw, and the Software::ComparisonOperatorEnum (p. 324) co.

Parameters:

sw is the Software (p. 323) object of the requirement to add.

co is the Software::ComparisonOperatorEnum (p. 324) of the requirement to add.

requiresAll indicates whether the all requirements have to be satisfied (true) or if only a single one (false), the default is that only a single requirement need to be satisfied.

6.145.2.4 Arc::SoftwareRequirement::SoftwareRequirement (const SoftwareRequirement & sr) [inline]

Copy constructor.

Create a SoftwareRequirement (p. 331) object from another SoftwareRequirement (p. 331) object.

Parameters:

sr is the SoftwareRequirement (p. 331) object to make a copy of.

6.145.3 Member Function Documentation

6.145.3.1 void Arc::SoftwareRequirement::add (const Software & sw, Software::ComparisonOperatorEnum co)

Add a Software (p. 323) object a corresponding comparion operator to this object.

Adds software name and version to list of requirements and associates the comparison operator with it (equality by default).

Parameters:

sw is the Software (p. 323) object to add as part of a requirement.

co is the Software::ComparisonOperatorEnum (p. 324) value to add as part of a requirement, the default enum will be Software::EQUAL (p. 325).

6.145.3.2 void Arc::SoftwareRequirement::add (const Software & sw, Software::ComparisonOperator swComOp = &Software::operator==)

Add a Software (p. 323) object a corresponding comparion operator to this object.

Adds software name and version to list of requirements and associates the comparison operator with it (equality by default).

This method is not available in language bindings created by Swig, since method pointers are not supported by Swig, see add(const Software&, Software::ComparisonOperatorEnum) (p. 333) instead.

Parameters:

sw is the Software (p. 323) object to add as part of a requirement.

swComOp is the Software::ComparisonOperator (p. 324) method pointer to add as part of a requirement, the default operator will be Software::operator==() (p. 328).

6.145.3.3 void Arc::SoftwareRequirement::clear() [inline]

Clear the object.

The requirements in this object will be cleared when invoking this method.

6.145.3.4 bool Arc::SoftwareRequirement::empty() const [inline]

Test if the object is empty.

Returns:

true if this object do no contain any requirements, otherwise false.

6.145.3.5 const std::list<Software::ComparisonOperator>& Arc::SoftwareRequirement::get-ComparisonOperatorList() const [inline]

Get list of comparison operators.

Returns:

The list of internally stored comparison operators is returned.

See also:

```
Software::ComparisonOperator (p. 324), getSoftwareList (p. 334).
```

6.145.3.6 const std::list<Software>& Arc::SoftwareRequirement::getSoftwareList() const [inline]

Get list of Software (p. 323) objects.

Returns:

The list of internally stored Software (p. 323) objects is returned.

See also:

```
Software (p. 323), getComparisonOperatorList (p. 334).
```

6.145.3.7 bool Arc::SoftwareRequirement::isRequiringAll () **const** [inline]

Indicates whether all requirments has to be satisfied.

This method returns true if all requirements has to be satisfied. If only one requirement has to be satisfied, false is returned.

Returns:

true if all requirements has to be satisfied, otherwise false.

See also:

setRequirement (p. 338).

6.145.3.8 bool Arc::SoftwareRequirement::isResolved () const

Indicates whether requirements have been resolved or not.

If specified that only one requirement has to be satisfied, then for this object to be resolved it can only contain one requirement and it has use the equal operator (Software::operator== (p. 328)).

If specified that all requirements has to be satisfied, then for this object to be resolved each requirement must have a Software (p. 323) object with a unique family/name composition, i.e. no other requirements have a Software (p. 323) object with the same family/name composition, and each requirement must use the equal operator (Software::operator== (p. 328)).

If this object has been resolved then true is returned when invoking this method, otherwise false is returned.

Returns:

true if this object have been resolved, otherwise false.

6.145.3.9 bool Arc::SoftwareRequirement::isSatisfied (const std::list< ApplicationEnvironment > & swList) const

Test if requirements are satisfied.

This method behaves in exactly the same way as the isSatisfied(const Software&) const (p. 336) method does.

Parameters:

swList is the list of ApplicationEnvironment (p. 45) objects which should be used to try satisfy the requirements.

Returns:

true if requirements are satisfied, otherwise false.

See also:

```
isSatisfied(const Software&) const (p. 336),
isSatisfied(const std::list<Software>&) const (p. 335),
selectSoftware(const std::list<ApplicationEnvironment>&) (p. 336),
isResolved() const (p. 335).
```

 $\textbf{6.145.3.10} \quad \textbf{bool Arc::SoftwareRequirement::isSatisfied (const std::list< Software > \& \textit{swList})} \\ \quad \textbf{const}$

Test if requirements are satisfied.

Returns true if stored requirements are satisfied by software specified in *swList*, otherwise false is returned.

Note that if all requirements must be satisfied and multiple requirements exist having identical name and family all these requirements should be satisfied by a single Software (p. 323) object.

Parameters:

swList is the list of Software (p. 323) objects which should be used to try satisfy the requirements.

Returns:

true if requirements are satisfied, otherwise false.

See also:

```
isSatisfied(const Software&) const (p. 336),
isSatisfied(const std::list<ApplicationEnvironment>&) const (p. 335),
selectSoftware(const std::list<Software>&) (p. 337),
isResolved() const (p. 335).
```

6.145.3.11 bool Arc::SoftwareRequirement::isSatisfied (const Software & sw) const [inline]

Test if requirements are satisfied.

Returns true if the requirements are satisfied by the specified Software (p. 323) sw, otherwise false is returned.

Parameters:

sw is the Software (p. 323) which should satisfy the requirements.

Returns:

true if requirements are satisfied, otherwise false.

See also:

```
isSatisfied(const std::list<Software>&) const (p. 335), isSatisfied(const std::list<ApplicationEnvironment>&) const (p. 335), selectSoftware(const Software&) (p. 337), isResolved() const (p. 335).
```

6.145.3.12 SoftwareRequirement& Arc::SoftwareRequirement::operator= (const SoftwareRequirement & sr)

Assignment operator.

Set this object equal to that of the passed SoftwareRequirement (p. 331) object sr.

Parameters:

sr is the SoftwareRequirement (p. 331) object to set object equal to.

6.145.3.13 bool Arc::SoftwareRequirement::selectSoftware (const std::list< ApplicationEnvironment > & swList)

Select software.

This method behaves exactly as the selectSoftware(const std::list<Software>&) (p. 337) method does.

Parameters:

swList is a list of ApplicationEnvironment (p. 45) objects used to satisfy requirements.

Returns:

true if requirements are satisfied, otherwise false.

See also:

```
selectSoftware(const Software&) (p. 337),
selectSoftware(const std::list<Software>&) (p. 337),
isSatisfied(const std::list<ApplicationEnvironment>&) const (p. 335),
isResolved() const (p. 335).
```

6.145.3.14 bool Arc::SoftwareRequirement::selectSoftware (const std::list < Software > & swList)

Select software.

If the passed list of Software (p. 323) objects swList do not satisfy the requirements false is returned and this object is not modified. If however the list of Software (p. 323) objects swList do satisfy the requirements true is returned and the Software (p. 323) objects satisfying the requirements will replace these with the equality operator (Software::operator== (p. 328)) used as the comparator for the new requirements.

Note that if all requirements must be satisfied and multiple requirements exist having identical name and family all these requirements should be satisfied by a single Software (p. 323) object and it will replace all these requirements.

Parameters:

swList is a list of Software (p. 323) objects used to satisfy requirements.

Returns:

true if requirements are satisfied, otherwise false.

See also:

```
selectSoftware(const Software&) (p. 337),
selectSoftware(const std::list<ApplicationEnvironment>&) (p. 336),
isSatisfied(const std::list<Software>&) const (p. 335),
isResolved() const (p. 335).
```

6.145.3.15 bool Arc::SoftwareRequirement::selectSoftware (const Software & sw) [inline]

Select software.

If the passed Software (p. 323) sw do not satisfy the requirements false is returned and this object is not modified. If however the Software (p. 323) object sw do satisfy the requirements true is returned and the requirements are set to equal the sw Software (p. 323) object.

Parameters:

sw is the Software (p. 323) object used to satisfy requirements.

Returns:

true if requirements are satisfied, otherwise false.

See also:

```
selectSoftware(const std::list<Software>&) (p. 337),
selectSoftware(const std::list<ApplicationEnvironment>&) (p. 336),
isSatisfied(const Software&) const (p. 336),
isResolved() const (p. 335).
```

6.145.3.16 void Arc::SoftwareRequirement::setRequirement (bool all) [inline]

Set relation between requirements.

Specifies if all requirements stored need to be satisfied or if it is enough to satisfy only one of them.

Parameters:

all is a boolean specifying if all requirements has to be satisfied.

See also:

```
isRequiringAll() (p. 334).
```

The documentation for this class was generated from the following file:


· Software.h

6.146 ArcSec::Source Class Reference

Acquires and parses XML document from specified source.

#include <Source.h>

Inheritance diagram for ArcSec::Source::



Public Member Functions

- Source (const Source &s)
- Source (Arc::XMLNode &xml)
- Source (std::istream &stream)
- Source (Arc::URL &url)
- Source (const std::string &str)
- Arc::XMLNode Get (void) const
- operator bool (void)

6.146.1 Detailed Description

Acquires and parses XML document from specified source.

This class is to be used to provide easy way to specify different sources for XML Authorization Policies and Requests.

6.146.2 Constructor & Destructor Documentation

6.146.2.1 ArcSec::Source::Source (const Source & s) [inline]

Copy constructor.

Use this constructor only for temporary objects. Parsed XML document is still owned by copied source and hence lifetime of create object should not exceed that of copied one.

6.146.2.2 ArcSec::Source::Source (Arc::XMLNode & xml)

Copy XML tree from XML subtree refered by xml.

6.146.2.3 ArcSec::Source::Source (std::istream & stream)

Read XML document from stream and parse it.

6.146.2.4 ArcSec::Source::Source (Arc::URL & url)

Fetch XML document from specified url and parse it.

This constructor is not implemented yet.

6.146.2.5 ArcSec::Source::Source (const std::string & str)

Read XML document from string.

6.146.3 Member Function Documentation

6.146.3.1 Arc::XMLNode ArcSec::Source::Get (void) const [inline]

Get reference to parsed document.

6.146.3.2 ArcSec::Source::operator bool (void) [inline]

Returns true if valid document is available.

The documentation for this class was generated from the following file:


· Source.h

6.147 ArcSec::SourceFile Class Reference

Convenience class for obtaining XML document from file.

#include <Source.h>

Inheritance diagram for ArcSec::SourceFile::



Public Member Functions

- SourceFile (const SourceFile &s)
- SourceFile (const char *name)
- SourceFile (const std::string &name)

6.147.1 Detailed Description

Convenience class for obtaining XML document from file.

6.147.2 Constructor & Destructor Documentation

6.147.2.1 ArcSec::SourceFile::SourceFile (const SourceFile & s) [inline]

See corresponding constructor of Source (p. 339) class.

6.147.2.2 ArcSec::SourceFile::SourceFile (const char * name)

Read XML document from file named name and store it.

6.147.2.3 ArcSec::SourceFile::SourceFile (const std::string & name)

Read XML document from file named name and store it.

The documentation for this class was generated from the following file:

• Source.h

6.148 ArcSec::SourceURL Class Reference

Convenience class for obtaining XML document from remote URL.

#include <Source.h>

Inheritance diagram for ArcSec::SourceURL::



Public Member Functions

- SourceURL (const SourceURL &s)
- SourceURL (const char *url)
- SourceURL (const std::string &url)

6.148.1 Detailed Description

Convenience class for obtaining XML document from remote URL.

6.148.2 Constructor & Destructor Documentation

6.148.2.1 ArcSec::SourceURL::SourceURL (const SourceURL & s) [inline]

See corresponding constructor of Source (p. 339) class.

6.148.2.2 ArcSec::SourceURL::SourceURL (const char * url)

Read XML document from URL url and store it.

6.148.2.3 ArcSec::SourceURL::SourceURL (const std::string & url)

Read XML document from URL url and store it.

The documentation for this class was generated from the following file:


• Source.h

6.149 Arc::Submitter Class Reference

Base class for the Submitters.

#include <Submitter.h>

Inheritance diagram for Arc::Submitter::



Public Member Functions

- virtual URL Submit (const JobDescription &jobdesc, const ExecutionTarget &et) const =0
- virtual URL Migrate (const URL &jobid, const JobDescription &jobdesc, const Execution-Target &et, bool forcemigration) const =0

6.149.1 Detailed Description

Base class for the Submitters.

Submitter (p. 343) is the base class for Grid middleware specialized Submitter (p. 343) objects. The class submits job(s) to the computing resource it represents and uploads (needed by the job) local input files.

6.149.2 Member Function Documentation

6.149.2.1 virtual URL Arc::Submitter::Migrate (const URL & jobid, const JobDescription & jobdesc, const ExecutionTarget & et, bool forcemigration) const [pure virtual]

This virtual method should be overridden by plugins which should be capable of migrating jobs. The active job which should be migrated is pointed to by the URL jobid, and is represented by the JobDescription jobdesc. The forcemigration boolean specifies if the migration should succeed if the active job cannot be terminated. The protected method AddJob can be used to save job information. This method should return the URL of the migrated job. In case migration fails an empty URL should be returned.

6.149.2.2 virtual URL Arc::Submitter::Submit (const JobDescription & jobdesc, const ExecutionTarget & et) const [pure virtual]

This virtual method should be overridden by plugins which should be capable of submitting jobs, defined in the JobDescription jobdesc, to the ExecutionTarget (p. 171) et. The protected convenience method AddJob can be used to save job information. This method should return the URL of the submitted job. In case submission fails an empty URL should be returned.


The documentation for this class was generated from the following file:

• Submitter.h

6.150 Arc::SubmitterLoader Class Reference

#include <Submitter.h>

Inheritance diagram for Arc::SubmitterLoader::



Public Member Functions

- SubmitterLoader ()
- ~SubmitterLoader ()
- Submitter * load (const std::string &name, const UserConfig &usercfg)
- const std::list< Submitter * > & GetSubmitters () const

6.150.1 Detailed Description

Class responsible for loading Submitter (p. 343) plugins The Submitter (p. 343) objects returned by a SubmitterLoader (p. 344) must not be used after the SubmitterLoader (p. 344) goes out of scope.

6.150.2 Constructor & Destructor Documentation

6.150.2.1 Arc::SubmitterLoader::SubmitterLoader ()

Constructor Creates a new SubmitterLoader (p. 344).

6.150.2.2 Arc::SubmitterLoader::~SubmitterLoader ()

Destructor Calling the destructor destroys all Submitters loaded by the SubmitterLoader (p. 344) instance.

6.150.3 Member Function Documentation

 $\textbf{6.150.3.1} \quad \textbf{const std::list} < \textbf{Submitter*} > \& \ \textbf{Arc::SubmitterLoader::GetSubmitters} \ () \ \textbf{const} \\ \text{[inline]}$

Retrieve the list of loaded Submitters.

Returns:

A reference to the list of Submitters.

6.150.3.2 Submitter* Arc::SubmitterLoader::load (const std::string & name, const UserConfig & usercfg)

Load a new Submitter (p. 343)

Parameters:

```
name The name of the Submitter (p. 343) to load.

usercfg The UserConfig (p. 361) object for the new Submitter (p. 343).
```

Returns:

A pointer to the new Submitter (p. 343) (NULL on error).

The documentation for this class was generated from the following file:

• Submitter.h

6.151 Arc::TargetGenerator Class Reference

Target generation class

#include <TargetGenerator.h>

Public Member Functions

- TargetGenerator (const UserConfig &usercfg)
- void GetTargets (int targetType, int detailLevel)
- const std::list< ExecutionTarget > & FoundTargets () const
- std::list< ExecutionTarget > & ModifyFoundTargets ()
- const std::list< XMLNode * > & FoundJobs () const
- bool AddService (const URL &url)
- bool AddIndexServer (const URL &url)
- void AddTarget (const ExecutionTarget &target)
- void AddJob (const XMLNode &job)
- void PrintTargetInfo (bool longlist) const
- SimpleCounter & ServiceCounter (void)

6.151.1 Detailed Description

Target generation class

The TargetGenerator (p. 346) class is the umbrella class for resource discovery and information retrieval (index servers and computing clusters). It can also be used to locate user Grid jobs but does not collect the job details (see the arcsync CLI)). The TargetGenerator (p. 346) loads TargetRetriever (p. 349) plugins (which implements the actual information retrieval) from URL objects found in the UserConfig (p. 361) object passed to its constructor using the custem TargetRetrieverLoader (p. 351). E.g. if an URL pointing to an ARC1 computing resource is found in the UserConfig (p. 361) object the TargetRetrieverARC1 is loaded.

6.151.2 Constructor & Destructor Documentation

6.151.2.1 Arc::TargetGenerator::TargetGenerator (const UserConfig & usercfg)

Create a TargetGenerator (p. 346) object.

Default constructor to create a TargeGenerator. The constructor reads the computing and index service URL objects from the passed UserConfig (p. 361) object using the UserConfig (p. 361):Get-SelectedServices method. From each URL a matching specialized TargetRetriever (p. 349) plugin is loaded using the TargetRetrieverLoader (p. 351).

Parameters:

usercfg Reference to UserConfig (p. 361) object with URL objects to computing and/or index services and paths to user credentials.

6.151.3 Member Function Documentation

6.151.3.1 bool Arc::TargetGenerator::AddIndexServer (const URL & url)

Add a new index server to the foundIndexServers list.

Method to add a new index server to the list of foundIndexServers in a thread secure way. Compares the argument URL against the servers returned by UserConfig::GetRejectedServices (p. 373) and only allows to add the service if not specifically rejected.

Parameters:

url URL pointing to the index server.

6.151.3.2 void Arc::TargetGenerator::AddJob (const XMLNode & job)

Add a new Job (p. 205) to the foundJobs list.

Method to add a new Job (p. 205) (usually discovered by a TargetRetriever (p. 349)) to the list of foundJobs in a thread secure way.

Parameters:

job XMLNode (p. 409) describing the job.

6.151.3.3 bool Arc::TargetGenerator::AddService (const URL & url)

Add a new computing service to the foundServices list.

Method to add a new service to the list of foundServices in a thread secure way. Compares the argument URL against the services returned by UserConfig::GetRejectedServices (p. 373) and only allows to add the service if not specifically rejected.

Parameters:

url URL pointing to the information system of the computing service.

6.151.3.4 void Arc::TargetGenerator::AddTarget (const ExecutionTarget & target)

Add a new ExecutionTarget (p. 171) to the foundTargets list.

Method to add a new ExecutionTarget (p. 171) (usually discovered by a TargetRetriever (p. 349)) to the list of foundTargets in a thread secure way.

Parameters:

target ExecutionTarget (p. 171) to be added.

 $\textbf{6.151.3.5} \quad const \ std:: list < XMLNode* > \& \ Arc:: Target Generator:: Found Jobs \ () \ const$

Return Grid jobs found by GetTargets.

Method to return the list of Grid jobs found by a call to the GetTargets method.

6.151.3.6 const std::list<ExecutionTarget>& Arc::TargetGenerator::FoundTargets () const

Return targets found by GetTargets.

Method to return a const list of ExecutionTarget (p. 171) objects (currently only supported Target type) found by the GetTarget method.

6.151.3.7 void Arc::TargetGenerator::GetTargets (int targetType, int detailLevel)

Find available targets.

Method to prepare a list of chosen Targets with a specified detail level. Current implementation supports finding computing clusters (ExecutionTarget (p. 171)) with full detail level and Grid jobs with limited detail level.

Parameters:

```
targetType 0 = ExecutionTarget (p. 171), 1 = Grid jobs
detailLevel 1 = All details, 2 = Limited details (not implemented)
```

6.151.3.8 std::list<ExecutionTarget>& Arc::TargetGenerator::ModifyFoundTargets ()

Return targets found by GetTargets.

Method to return the list of ExecutionTarget (p. 171) objects (currently only supported Target type) found by the GetTarget method.

6.151.3.9 void Arc::TargetGenerator::PrintTargetInfo (bool longlist) const

Prints target information.

Method to print information of the found targets to std::cout.

Parameters:

longlist false for minimal information, true for detailed information

6.151.3.10 SimpleCounter& Arc::TargetGenerator::ServiceCounter (void)

Returns reference to worker counter.

This method returns reference to counter which keeps amount of started worker threads communicating with services asynchronously. The counter must be incremented for every thread started and decremented when thread exits. Main thread will then wait till counters drops to zero.

The documentation for this class was generated from the following file:


• TargetGenerator.h

6.152 Arc::TargetRetriever Class Reference

TargetRetriever base class

#include <TargetRetriever.h>

Inheritance diagram for Arc::TargetRetriever::



Public Member Functions

• virtual void GetTargets (TargetGenerator &mom, int targetType, int detailLevel)=0

Protected Member Functions

• TargetRetriever (const UserConfig &usercfg, const URL &url, ServiceType st, const std::string &flavour)

6.152.1 Detailed Description

TargetRetriever base class

The TargetRetriever (p. 349) class is a pure virtual base class to be used for grid flavour specializations. It is designed to work in conjunction with the TargetGenerator (p. 346).

6.152.2 Constructor & Destructor Documentation

6.152.2.1 Arc::TargetRetriever::TargetRetriever (const UserConfig & usercfg, const URL & url, ServiceType st, const std::string & flavour) [protected]

TargetRetriever (p. 349) constructor.

Default constructor to create a TargeGenerator. The constructor reads the computing and index service URL objects from the

Parameters:

usercfg

url

st

flavour

6.152.3 Member Function Documentation

6.152.3.1 virtual void Arc::TargetRetriever::GetTargets (TargetGenerator & mom, int targetType, int detailLevel) [pure virtual]

Method for collecting targets.

Pure virtual method for collecting targets. Implementation depends on the Grid middleware in question and is thus left to the specialized class.

Parameters:

```
    mom is the reference to the TargetGenerator (p. 346) which has loaded the TargetRetriever (p. 349)
    targetType is the identification of targets to find (0=ExecutionTargets, 1=Grid Jobs)
    detailLevel is the required level of details (1 = All details, 2 = Limited details)
```


The documentation for this class was generated from the following file:

• TargetRetriever.h

6.153 Arc::TargetRetrieverLoader Class Reference

#include <TargetRetriever.h>

Inheritance diagram for Arc::TargetRetrieverLoader::



Public Member Functions

- TargetRetrieverLoader ()
- ∼TargetRetrieverLoader ()
- TargetRetriever * load (const std::string &name, const UserConfig &usercfg, const URL &url, const ServiceType &st)
- const std::list< TargetRetriever * > & GetTargetRetrievers () const

6.153.1 Detailed Description

Class responsible for loading TargetRetriever (p. 349) plugins The TargetRetriever (p. 349) objects returned by a TargetRetrieverLoader (p. 351) must not be used after the TargetRetrieverLoader (p. 351) goes out of scope.

6.153.2 Constructor & Destructor Documentation

6.153.2.1 Arc::TargetRetrieverLoader::TargetRetrieverLoader ()

Constructor Creates a new TargetRetrieverLoader (p. 351).

6.153.2.2 Arc::TargetRetrieverLoader::~TargetRetrieverLoader()

Destructor Calling the destructor destroys all TargetRetrievers loaded by the TargetRetrieverLoader (p. 351) instance.

6.153.3 Member Function Documentation

6.153.3.1 const std::list<TargetRetriever*>& Arc::TargetRetrieverLoader::GetTargetRetrievers () const [inline]

Retrieve the list of loaded TargetRetrievers.

Returns:

A reference to the list of TargetRetrievers.

6.153.3.2 TargetRetriever* Arc::TargetRetrieverLoader::load (const std::string & name, const UserConfig & usercfg, const URL & url, const ServiceType & st)

Load a new TargetRetriever (p. 349)

Parameters:

```
name The name of the TargetRetriever (p. 349) to load.
usercfg The UserConfig (p. 361) object for the new TargetRetriever (p. 349).
url The URL used to contact the target.
st specifies service type of the target.
```

Returns:

A pointer to the new TargetRetriever (p. 349) (NULL on error).

The documentation for this class was generated from the following file:

• TargetRetriever.h

6.154 Arc::ThreadRegistry Class Reference

#include <Thread.h>

Public Member Functions

- void RegisterThread (void)
- void UnregisterThread (void)
- bool WaitOrCancel (int timeout)
- bool WaitForExit (int timeout=-1)

6.154.1 Detailed Description

This class is a set of conditions, mutexes, etc. conveniently exposed to monitor running child threads and to wait till they exit. There are no protections against race conditions. So use it carefully.

6.154.2 Member Function Documentation

6.154.2.1 void Arc::ThreadRegistry::RegisterThread (void)

Register thread as started/starting into this instance.

6.154.2.2 void Arc::ThreadRegistry::UnregisterThread (void)

Report thread as exited.

6.154.2.3 bool Arc::ThreadRegistry::WaitForExit (int *timeout* = -1)

Wait for registered threads to exit. Leave after timeout miliseconds if failed. Returns true if all registered threads reported their exit.

6.154.2.4 bool Arc::ThreadRegistry::WaitOrCancel (int timeout)

Wait for timeout milliseconds or cancel request. Returns true if cancel request received.

The documentation for this class was generated from the following file:

• Thread.h

6.155 Arc::Time Class Reference

A class for storing and manipulating times.

#include <DateTime.h>

Public Member Functions

- Time ()
- Time (time_t)
- Time (time_t time, uint32_t nanosec)
- Time (const std::string &)
- Time & operator= (time_t)
- Time & operator= (const Time &)
- Time & operator= (const char *)
- Time & operator= (const std::string &)
- void SetTime (time t)
- void SetTime (time_t time, uint32_t nanosec)
- time_t GetTime () const
- operator std::string () const
- std::string str (const TimeFormat &=time_format) const
- bool operator< (const Time &) const
- bool operator> (const Time &) const
- bool operator<= (const Time &) const
- bool operator>= (const Time &) const
- bool operator== (const Time &) const
- bool operator!= (const Time &) const
- Time operator+ (const Period &) const
- Time operator- (const Period &) const
 Period operator- (const Time &) const

Static Public Member Functions

- static void SetFormat (const TimeFormat &)
- static TimeFormat GetFormat ()

6.155.1 Detailed Description

A class for storing and manipulating times.

6.155.2 Constructor & Destructor Documentation

6.155.2.1 Arc::Time::Time()

Default constructor. The time is put equal the current time.

6.155.2.2 Arc::Time::Time (time t)

Constructor that takes a time_t variable and stores it.

6.155.2.3 Arc::Time::Time (time_t time, uint32_t nanosec)

Constructor that takes a fine grained time variables and stores them.

6.155.2.4 Arc::Time::Time (const std::string &)

Constructor that tries to convert a string into a time_t.

6.155.3 Member Function Documentation

6.155.3.1 static TimeFormat Arc::Time::GetFormat () [static]

Gets the default format for time strings.

6.155.3.2 time_t Arc::Time::GetTime () const

gets the time

6.155.3.3 Arc::Time::operator std::string () const

Returns a string representation of the time, using the default format.

6.155.3.4 bool Arc::Time::operator!= (const Time &) const

Comparing two Time (p. 354) objects.

6.155.3.5 Time Arc::Time::operator+ (const Period &) const

Adding Time (p. 354) object with Period object.

6.155.3.6 Period Arc::Time::operator- (const Time &) const

Subtracting Time (p. 354) object from the other Time (p. 354) object.

6.155.3.7 Time Arc::Time::operator- (const Period &) const

Subtracting Period object from Time (p. 354) object.

6.155.3.8 bool Arc::Time::operator< (const Time &) const

Comparing two Time (p. 354) objects.

6.155.3.9 bool Arc::Time::operator<= (const Time &) const

Comparing two Time (p. 354) objects.

```
6.155.3.10 Time& Arc::Time::operator= (const std::string &)
Assignment operator from a string.
6.155.3.11 Time& Arc::Time::operator= (const char *)
Assignment operator from a char pointer.
6.155.3.12 Time& Arc::Time::operator= (const Time &)
Assignment operator from a Time (p. 354).
6.155.3.13 Time& Arc::Time::operator= (time_t)
Assignment operator from a time_t.
6.155.3.14 bool Arc::Time::operator== (const Time &) const
Comparing two Time (p. 354) objects.
6.155.3.15 bool Arc::Time::operator> (const Time &) const
Comparing two Time (p. 354) objects.
6.155.3.16 bool Arc::Time::operator>= (const Time &) const
Comparing two Time (p. 354) objects.
6.155.3.17 static void Arc::Time::SetFormat (const TimeFormat &) [static]
Sets the default format for time strings.
6.155.3.18 void Arc::Time::SetTime (time_t time, uint32_t nanosec)
sets the fine grained time
6.155.3.19 void Arc::Time::SetTime (time_t)
sets the time
6.155.3.20 std::string Arc::Time::str (const TimeFormat & = time_format) const
Returns a string representation of the time, using the specified format.
```


The documentation for this class was generated from the following file:

• DateTime.h

6.156 ArcSec::TimeAttribute Class Reference

#include <DateTimeAttribute.h>

Inheritance diagram for ArcSec::TimeAttribute::



Public Member Functions

- virtual bool equal (AttributeValue *other, bool check id=true)
- virtual std::string encode ()
- virtual std::string getType ()
- virtual std::string getId ()

6.156.1 Detailed Description

Format: HHMMSSZ HH:MM:SS HH:MM:SS+HH:MM HH:MM:SSZ

6.156.2 Member Function Documentation

6.156.2.1 virtual std::string ArcSec::TimeAttribute::encode () [virtual]

encode the value in a string format

Implements ArcSec::AttributeValue (p. 53).

6.156.2.2 virtual bool ArcSec::TimeAttribute::equal (AttributeValue * *other*, **bool** *check_id* = true) [virtual]

Evaluate whether "this" is equal to the parameter value

Implements ArcSec::AttributeValue (p. 53).

6.156.2.3 virtual std::string ArcSec::TimeAttribute::getId () [inline, virtual]

Get the AttributeId of the <Attribute>

Implements ArcSec::AttributeValue (p. 54).

6.156.2.4 virtual std::string ArcSec::TimeAttribute::getType () [inline, virtual]

Get the DataType of the <Attribute>

Implements ArcSec::AttributeValue (p. 54).

The documentation for this class was generated from the following file:

358	Hosting Environment (Daemon) Data Structure Documentation
• DateTimeAttribute.h	
2 444 2 444 444 444 444 444 444 444 444	

6.157 Arc::URLLocation Class Reference

Class to hold a resolved URL location.

#include <URL.h>

Public Member Functions

- URLLocation (const std::string &url)
- URLLocation (const std::string &url, const std::string &name)
- URLLocation (const URL &url)
- URLLocation (const URL &url, const std::string &name)
- URLLocation (const std::map< std::string, std::string > &options, const std::string &name)
- virtual ~URLLocation ()
- const std::string & Name () const
- virtual std::string str () const
- virtual std::string fullstr () const

Protected Attributes

• std::string name

6.157.1 Detailed Description

Class to hold a resolved URL location.

It is specific to file indexing service registrations.

6.157.2 Constructor & Destructor Documentation

6.157.2.1 Arc::URLLocation::URLLocation (const std::string & url)

Creates a URLLocation (p. 359) from a string representaion.

6.157.2.2 Arc::URLLocation::URLLocation (const std::string & url, const std::string & name)

Creates a URLLocation (p. 359) from a string representaion and a name.

6.157.2.3 Arc::URLLocation::URLLocation (const URL & url)

Creates a URLLocation (p. 359) from a URL.

6.157.2.4 Arc::URLLocation::URLLocation (const URL & url, const std::string & name)

Creates a URLLocation (p. 359) from a URL and a name.

6.157.2.5 Arc::URLLocation::URLLocation (const std::map< std::string, std::string > & options, const std::string & name)

Creates a URLLocation (p. 359) from options and a name.

6.157.2.6 virtual Arc::URLLocation::~URLLocation () [virtual]

URLLocation (p. 359) destructor.

6.157.3 Member Function Documentation

6.157.3.1 virtual std::string Arc::URLLocation::fullstr() const [virtual]

Returns a string representation including options and locations

6.157.3.2 const std::string& Arc::URLLocation::Name () const

Returns the URLLocation (p. 359) name.

6.157.3.3 virtual std::string Arc::URLLocation::str () const [virtual]

Returns a string representation of the URLLocation (p. 359).

6.157.4 Field Documentation

6.157.4.1 std::string Arc::URLLocation::name [protected]

the URLLocation (p. 359) name as registered in the indexing service.

The documentation for this class was generated from the following file:

• URL.h

6.158 Arc::UserConfig Class Reference

User configuration class

#include <UserConfig.h>

Public Member Functions

- UserConfig (initializeCredentialsType initializeCredentials=initializeCredentialsType())
- UserConfig (const std::string &conffile, initializeCredentialsType initializeCredentialsType(), bool loadSysConfig=true)
- UserConfig (const std::string &conffile, const std::string &jfile, initializeCredentialsType initializeCredentials=initializeCredentialsType(), bool loadSysConfig=true)
- UserConfig (const long int &ptraddr)
- void InitializeCredentials ()
- bool CredentialsFound () const
- bool LoadConfigurationFile (const std::string &conffile, bool ignoreJobListFile=true)
- bool SaveToFile (const std::string &filename) const
- void ApplyToConfig (BaseConfig &ccfg) const
- operator bool () const
- bool operator! () const
- bool JobListFile (const std::string &path)
- const std::string & JobListFile () const
- bool AddServices (const std::list< std::string > &services, ServiceType st)
- bool AddServices (const std::list< std::string > &selected, const std::list< std::string > &rejected, ServiceType st)
- const URLListMap & GetSelectedServices (ServiceType st) const
- const URLListMap & GetRejectedServices (ServiceType st) const
- void ClearSelectedServices ()
- void ClearSelectedServices (ServiceType st)
- void ClearRejectedServices ()
- void ClearRejectedServices (ServiceType st)
- bool Timeout (int newTimeout)
- int Timeout () const
- bool Verbosity (const std::string &newVerbosity)
- const std::string & Verbosity () const
- bool Broker (const std::string &name)
- bool Broker (const std::string &name, const std::string &argument)
- const std::pair < std::string, std::string > & Broker () const
- bool Bartender (const std::vector< URL > &urls)
- void AddBartender (const URL &url)
- const std::vector < URL > & Bartender () const
- bool VOMSServerPath (const std::string &path)
- const std::string & VOMSServerPath () const
- bool UserName (const std::string &name)
- const std::string & UserName () const
- bool Password (const std::string &newPassword)
- const std::string & Password () const
- bool ProxyPath (const std::string &newProxyPath)
- const std::string & ProxyPath () const

- bool CertificatePath (const std::string &newCertificatePath)
- const std::string & CertificatePath () const
- bool KeyPath (const std::string &newKeyPath)
- const std::string & KeyPath () const
- bool KeyPassword (const std::string &newKeyPassword)
- const std::string & KeyPassword () const
- bool KeySize (int newKeySize)
- int KeySize () const
- bool CACertificatePath (const std::string &newCACertificatePath)
- const std::string & CACertificatePath () const
- bool CACertificatesDirectory (const std::string &newCACertificatesDirectory)
- const std::string & CACertificatesDirectory () const
- bool CertificateLifeTime (const Period &newCertificateLifeTime)
- const Period & CertificateLifeTime () const
- bool SLCS (const URL &newSLCS)
- const URL & SLCS () const
- bool StoreDirectory (const std::string &newStoreDirectory)
- const std::string & StoreDirectory () const
- bool IdPName (const std::string &name)
- const std::string & IdPName () const
- bool OverlayFile (const std::string &path)
- const std::string & OverlayFile () const
- bool UtilsDirPath (const std::string &dir)
- const std::string & UtilsDirPath () const

Static Public Attributes

- static const std::string ARCUSERDIRECTORY
- static const std::string SYSCONFIG
- static const std::string SYSCONFIGARCLOC
- static const std::string DEFAULTCONFIG
- static const std::string EXAMPLECONFIG
- static const int DEFAULT_TIMEOUT = 20
- static const std::string DEFAULT_BROKER

6.158.1 Detailed Description

User configuration class

This class provides a container for a selection of various attributes/parameters which can be configured to needs of the user, and can be read by implementing instances or programs. The class can be used in two ways. One can create a object from a configuration file, or simply set the desired attributes by using the setter method, associated with every setable attribute. The list of attributes which can be configured in this class are:

- certificatepath / CertificatePath(const std::string&) (p. 371)
- keypath / KeyPath(const std::string&) (p. 378)
- proxypath / ProxyPath(const std::string&) (p. 382)

- cacertificatesdirectory / CACertificatesDirectory(const std::string&) (p. 370)
- cacertificatepath / CACertificatePath(const std::string&) (p. 369)
- timeout / Timeout(int) (p. 384)
- joblist / JobListFile(const std::string&) (p. 376)
- defaultservices / AddServices(const std::list<std::string>&, const std::list<std::string>&,
 ServiceType) (p. 366)
- rejectservices / AddServices(const std::list<std::string>&, const std::list<std::string>&, ServiceType) (p. 366)
- verbosity / Verbosity(const std::string&) (p. 386)
- brokername / Broker(const std::string&) (p. 369) or Broker(const std::string&, const std::string&) (p. 368)
- brokerarguments / Broker(const std::string&) (p. 369) or Broker(const std::string&, const std::string&) (p. 368)
- bartender / Bartender(const std::list<URL>&)
- vomsserverpath / VOMSServerPath(const std::string&) (p. 387)
- username / UserName(const std::string&) (p. 385)
- password / Password(const std::string&) (p. 381)
- keypassword / KeyPassword(const std::string&) (p. 377)
- keysize / KeySize(int) (p. 378)
- certificatelifetime / CertificateLifeTime(const Period&) (p. 371)
- slcs / SLCS(const URL&) (p. 383)
- storedirectory / StoreDirectory(const std::string&) (p. 384)
- idpname / IdPName(const std::string&) (p. 374)

where the first term is the name of the attribute used in the configuration file, and the second term is the associated setter method (for more information about a given attribute see the description of the setter method).

The configuration file should have a INI-style format and the IniConfig class will thus be used to parse the file. The above mentioned attributes should be placed in the common section. Another section is also valid in the configuration file, which is the alias section. Here it is possible to define aliases representing one or multiple services. These aliases can be used in the AddServices(const std::list<std::string>&, ServiceType) (p. 366) and AddServices(const std::list<std::string>&, const std::list<std::string>&, ServiceType) (p. 366) methods.

The UserConfig (p.361) class also provides a method InitializeCredentials() (p.375) for locating user credentials by searching in different standard locations. The CredentialsFound() (p.373) method can be used to test if locating the credentials succeeded.

6.158.2 Constructor & Destructor Documentation

6.158.2.1 Arc::UserConfig::UserConfig (initializeCredentialsType initializeCredentialsType())

Create a UserConfig (p. 361) object.

The UserConfig (p. 361) object created by this constructor initializes only default values, and if specified by the *initializeCredentials* boolean credentials will be tried initialized using the Initialize-Credentials() (p. 375) method. The object is only non-valid if initialization of credentials fails which can be checked with the operator bool() method.

Parameters:

initializeCredentials is a optional boolean indicating if the InitializeCredentials() (p. 375) method should be invoked, the default is true.

See also:

```
InitializeCredentials() (p. 375) operator bool()
```

6.158.2.2 Arc::UserConfig::UserConfig (const std::string & conffile, initializeCredentialsType initializeCredentials = initializeCredentialsType (), bool loadSysConfig = true)

Create a UserConfig (p. 361) object.

The UserConfig (p. 361) object created by this constructor will, if specified by the *loadSysConfig* boolean, first try to load the system configuration file by invoking the LoadConfigurationFile() (p. 379) method, and if this fails a WARNING is reported. Then the configuration file passed will be tried loaded using the before mentioned method, and if this fails an ERROR is reported, and the created object will be non-valid. Note that if the passed file path is empty the example configuration will be tried copied to the default configuration file path specified by DEFAULTCONFIG. If the example file cannot be copied one or more WARNING messages will be reported and no configration will be loaded. If loading the configurations file succeeded and if *initializeCredentials* is true then credentials will be initialized using the InitializeCredentials() (p. 375) method, and if no valid credentials are found the created object will be non-valid.

Parameters:

conffile is the path to a INI-configuration file.

initializeCredentials is a boolean indicating if credentials should be initialized, the default is true.

loadSysConfig is a boolean indicating if the system configuration file should be loaded aswell, the default is true.

```
LoadConfigurationFile(const std::string&, bool) (p. 379)
InitializeCredentials() (p. 375)
operator bool()
SYSCONFIG (p. 388)
EXAMPLECONFIG (p. 388)
```

6.158.2.3 Arc::UserConfig::UserConfig (const std::string & conffile, const std::string & jfile, initializeCredentialsType initializeCredentials = initializeCredentialsType(), bool loadSysConfig = true)

Create a UserConfig (p. 361) object.

The UserConfig (p. 361) object created by this constructor does only differ from the UserConfig(const std::string&, bool, bool) constructor in that it is possible to pass the path of the job list file directly to this constructor. If the job list file *joblistfile* is empty, the behaviour of this constructor is exactly the same as the before mentioned, otherwise the job list file will be initilized by invoking the setter method JobListFile(const std::string&) (p. 376). If it fails the created object will be non-valid, otherwise the specified configuration file *conffile* will be loaded with the *ignoreJobListFile* argument set to true.

Parameters:

conffile is the path to a INI-configuration file jfile is the path to a (non-)existing job list file.

 $\begin{tabular}{ll} \it initialize Credentials is a boolean indicating if credentials should be initialized, the default is true. \\ \end{tabular}$

loadSysConfig is a boolean indicating if the system configuration file should be loaded aswell, the default is true.

See also:

```
JobListFile(const std::string&) (p. 376)
LoadConfigurationFile(const std::string&, bool) (p. 379)
InitializeCredentials() (p. 375)
operator bool()
```

6.158.2.4 Arc::UserConfig::UserConfig (const long int & ptraddr)

Language binding constructor.

The passed long int should be a pointer address to a UserConfig (p. 361) object, and this address is then casted into this UserConfig (p. 361) object.

Parameters:

ptraddr is an memory address to a UserConfig (p. 361) object.

6.158.3 Member Function Documentation

```
6.158.3.1 void Arc::UserConfig::AddBartender (const URL & url) [inline]
```

Set bartenders, used to contact Chelonia.

Takes as input a Bartender URL and adds this to the list of bartenders.

Parameters:

url is a URL to be added to the list of bartenders.

```
Bartender(const std::list<URL>&)
Bartender() const (p. 367)
```

6.158.3.2 bool Arc::UserConfig::AddServices (const std::list< std::string > & selected, const std::list< std::string > & rejected, ServiceType st)

Add selected and rejected services.

The only diffence in behaviour of this method compared to the AddServices(const std::list<std::string>&, ServiceType) (p. 366) method is the input parameters and the format these parameters should follow. Instead of having an optional '-' in front of the string selected and rejected services should be specified in the two different arguments.

Two attributes are indirectly associated with this setter method 'defaultservices' and 'rejectservices'. The values specified with the 'defaultservices' attribute will be added to the list of selected services, and like-wise with the 'rejectservices' attribute.

Parameters:

selected is a list of services which will be added to the selected services of this object.

rejected is a list of services which will be added to the rejected services of this object.

st specifies the ServiceType of the services to add.

Returns:

This method return false in case an alias cannot be resolved. In any other case true is returned.

See also:

```
AddServices(const std::list<std::string>&, ServiceType) (p. 366)
GetSelectedServices() (p. 374)
GetRejectedServices() (p. 373)
ClearSelectedServices() (p. 373)
ClearRejectedServices() (p. 372)
LoadConfigurationFile() (p. 379)
```

6.158.3.3 bool Arc::UserConfig::AddServices (const std::list< std::string > & services, ServiceType st)

Add selected and rejected services.

This method adds selected services and adds services to reject from the specified list *services*, which contains string objects. The syntax of a single element in the list must be expressed in the following two formats:

$$[-] < flavour >:< service \ url > |[-] < alias >$$

where the optional '-' indicate that the service should be added to the private list of services to reject. In the first format the <flavour> part indicates the type of ACC plugin to use when contacting the service, which is specified by the URL <service_url>, and in the second format the <alias> part specifies a alias defined in a parsed configuration file, note that the alias must not contain any of the charaters ':', '.', ' ' or '\t'. If a alias cannot be resolved an ERROR will be reported to the logger and the method will return false. If a element in the list services cannot be parsed an ERROR will be reported, and the element is skipped.

Two attributes are indirectly associated with this setter method 'defaultservices' and 'rejectservices'. The values specified with the 'defaultservices' attribute will be added to the list of selected services, and like-wise with the 'rejectservices' attribute.

Parameters:

services is a list of services to either select or reject.

st indicates the type of the specfied services.

Returns:

This method returns false in case an alias cannot be resolved. In any other case true is returned.

See also:

```
AddServices(const std::string&, const std::string&, ServiceType)
GetSelectedServices() (p. 374)
GetRejectedServices() (p. 373)
ClearSelectedServices() (p. 373)
ClearRejectedServices() (p. 372)
LoadConfigurationFile() (p. 379)
```

6.158.3.4 void Arc::UserConfig::ApplyToConfig (BaseConfig & ccfg) const

Apply credentials to BaseConfig (p. 59).

This methods sets the BaseConfig (p. 59) credentials to the credentials contained in this object. It also passes user defined configuration overlay if any.

See also:

```
InitializeCredentials() (p. 375)
CredentialsFound() (p. 373)
BaseConfig (p. 59)
```

Parameters:

ccfg a BaseConfig (p. 59) object which will configured with the credentials of this object.

```
6.158.3.5 const std::vector<URL>& Arc::UserConfig::Bartender() const [inline]
```

Get bartenders.

Returns a list of Bartender URLs

Returns:

The list of bartender URL objects is returned.

```
Bartender(const std::list<URL>&)
AddBartender(const URL&) (p. 365)
```

6.158.3.6 bool Arc::UserConfig::Bartender (const std::vector < URL > & urls) [inline]

Set bartenders, used to contact Chelonia.

Takes as input a vector of Bartender URLs.

The attribute associated with this setter method is 'bartender'.

Parameters:

urls is a list of URL object to be set as bartenders.

Returns:

This method always returns true.

See also:

```
AddBartender(const URL&) (p. 365)
Bartender() const (p. 367)
```

6.158.3.7 const std::pair<std::string, std::string>& Arc::UserConfig::Broker() const [inline]

Get the broker and corresponding arguments.

The returned pair contains the broker name as the first component and the argument as the second.

See also:

```
Broker(const std::string&) (p. 369)
Broker(const std::string&, const std::string&) (p. 368)
DEFAULT_BROKER (p. 387)
```

6.158.3.8 bool Arc::UserConfig::Broker (const std::string & name, const std::string & argument) [inline]

Set broker to use in target matching.

As opposed to the Broker(const std::string&) (p. 369) method this method sets broker name and arguments directly from the passed two arguments.

Two attributes are associated with this setter method 'brokername' and 'brokerarguments'.

Parameters:

```
name is the name of the broker.argument is the arguments of the broker.
```

Returns:

This method always returns true.

```
Broker (p. 369)
Broker(const std::string&) (p. 369)
Broker() const (p. 368)
DEFAULT_BROKER (p. 387)
```

6.158.3.9 bool Arc::UserConfig::Broker (const std::string & name)

Set broker to use in target matching.

The string passed to this method should be in the format:

```
< name > [:< argument >]
```

where the <name> is the name of the broker and cannot contain any ':', and the optional <argument> should contain arguments which should be passed to the broker.

Two attributes are associated with this setter method 'brokername' and 'brokerarguments'.

Parameters:

name the broker name and argument specified in the format given above.

Returns:

This method allways returns true.

See also:

```
Broker (p. 369)
Broker(const std::string&, const std::string&) (p. 368)
Broker() const (p. 368)
DEFAULT_BROKER (p. 387)
```

6.158.3.10 const std::string& Arc::UserConfig::CACertificatePath() const [inline]

Get path to CA-certificate.

Retrieve the path to the file containing CA-certificate. This configuration parameter is deprecated.

Returns:

The path to the CA-certificate is returned.

See also:

```
CACertificatePath(const std::string&) (p. 369)
```

6.158.3.11 bool Arc::UserConfig::CACertificatePath (const std::string & newCACertificatePath)

Set CA-certificate path.

The path to the file containing CA-certificate will be set when calling this method. This configuration parameter is deprecated - use CACertificatesDirectory instead. Only arcslcs uses it.

The attribute associated with this setter method is 'cacertificatepath'.

Parameters:

newCACertificatePath is the path to the CA-certificate.

Returns:

This method always returns true.

See also:

CACertificatePath() const (p. 369)

6.158.3.12 const std::string& Arc::UserConfig::CACertificatesDirectory () const [inline]

Get path to CA-certificate directory.

Retrieve the path to the CA-certificate directory.

Returns:

The path to the CA-certificate directory is returned.

See also:

```
InitializeCredentials() (p. 375)
CredentialsFound() const (p. 373)
CACertificatesDirectory(const std::string&) (p. 370)
```

6.158.3.13 bool Arc::UserConfig::CACertificatesDirectory (const std::string & newCACertificatesDirectory) [inline]

Set path to CA-certificate directory.

The path to the directory containing CA-certificates will be set when calling this method. Note that the InitializeCredentials() (p. 375) method will also try to set this path, by searching in different locations.

The attribute associated with this setter method is 'cacertificatesdirectory'.

Parameters:

newCACertificatesDirectory is the path to the CA-certificate directory.

Returns:

This method always returns true.

See also:

```
InitializeCredentials() (p. 375)
CredentialsFound() const (p. 373)
CACertificatesDirectory() const (p. 370)
```

6.158.3.14 const Period& Arc::UserConfig::CertificateLifeTime() const [inline]

Get certificate life time.

Gets lifetime of user certificate which will be obtained from Short Lived Credentials Service (p. 316).

Returns:

The certificate life time is returned as a Period object.

See also:

CertificateLifeTime(const Period&) (p. 371)

6.158.3.15 bool Arc::UserConfig::CertificateLifeTime (const Period & newCertificateLifeTime)

Set certificate life time.

Sets lifetime of user certificate which will be obtained from Short Lived Credentials Service (p. 316).

The attribute associated with this setter method is 'certificatelifetime'.

Parameters:

newCertificateLifeTime is the life time of a certificate, as a Period object.

Returns:

This method always returns true.

See also:

CertificateLifeTime() const (p. 370)

6.158.3.16 const std::string& Arc::UserConfig::CertificatePath() const [inline]

Get path to certificate.

The path to the cerficate is returned when invoking this method.

Returns:

The certificate path is returned.

See also:

```
InitializeCredentials() (p. 375)
CredentialsFound() const (p. 373)
CertificatePath(const std::string&) (p. 371)
KeyPath() const (p. 377)
```

6.158.3.17 bool Arc::UserConfig::CertificatePath (const std::string & newCertificatePath)

Set path to certificate.

The path to user certificate will be set by this method. The path to the correcsponding key can be set with the KeyPath(const std::string&) (p. 378) method. Note that the InitializeCredentials() (p. 375) method will also try to set this path, by searching in different locations.

The attribute associated with this setter method is 'certificatepath'.

Parameters:

newCertificatePath is the path to the new certificate.

Returns:

This method always returns true.

See also:

InitializeCredentials() (p. 375) CredentialsFound() const (p. 373) CertificatePath() const (p. 371) KeyPath(const std::string&) (p. 378)

6.158.3.18 void Arc::UserConfig::ClearRejectedServices (ServiceType st)

Clear rejected services with specified ServiceType.

Calling this method will cause the internally stored rejected services with the ServiceType st to be cleared.

See also:

```
ClearRejectedServices() (p. 372)
ClearSelectedServices(ServiceType) (p. 372)
AddServices(const std::list<std::string>&, ServiceType) (p. 366)
AddServices(const std::list<std::string>&, const std::list<std::string>&, ServiceType) (p. 366)
GetRejectedServices() (p. 373)
```

6.158.3.19 void Arc::UserConfig::ClearRejectedServices ()

Clear selected services.

Calling this method will cause the internally stored rejected services to be cleared.

See also:

```
ClearRejectedServices(ServiceType) (p. 372)
ClearSelectedServices() (p. 373)
AddServices(const std::list<std::string>&, ServiceType) (p. 366)
AddServices(const std::list<std::string>&, const std::list<std::string>&, ServiceType) (p. 366)
GetRejectedServices() (p. 373)
```

6.158.3.20 void Arc::UserConfig::ClearSelectedServices (ServiceType st)

Clear selected services with specified ServiceType.

Calling this method will cause the internally stored selected services with the ServiceType st to be cleared.

See also:

ClearSelectedServices() (p. 373)

ClearRejectedServices(ServiceType) (p. 372)
AddServices(const std::list<std::string>&, ServiceType) (p. 366)
AddServices(const std::list<std::string>&, const std::list<std::string>&, ServiceType) (p. 366)
GetSelectedServices() (p. 374)

6.158.3.21 void Arc::UserConfig::ClearSelectedServices ()

Clear selected services.

Calling this method will cause the internally stored selected services to be cleared.

See also:

ClearSelectedServices(ServiceType) (p. 372)
ClearRejectedServices() (p. 372)
AddServices(const std::list<std::string>&, ServiceType) (p. 366)
AddServices(const std::list<std::string>&, const std::list<std::string>&, ServiceType) (p. 366)
GetSelectedServices() (p. 374)

6.158.3.22 bool Arc::UserConfig::CredentialsFound () const [inline]

Validate credential location.

Valid credentials consists of a combination of a path to existing CA-certificate directory and either a path to existing proxy or a path to existing user key/certificate pair. If valid credentials are found this method returns true, otherwise false is returned.

Returns:

true if valid credentials are found, otherwise false.

See also:

InitializeCredentials() (p. 375)

6.158.3.23 const URLListMap& Arc::UserConfig::GetRejectedServices (ServiceType st) const

Get rejected services.

Get the rejected services with the ServiceType specified by st.

Parameters:

st specifies which ServiceType should be returned by the method.

Returns:

The rejected services is returned.

```
AddServices(const std::list<std::string>&, ServiceType) (p. 366)
AddServices(const std::list<std::string>&, const std::list<std::string>&, ServiceType) (p. 366)
GetSelectedServices(ServiceType)
ClearRejectedServices() (p. 372)
```

6.158.3.24 const URLListMap& Arc::UserConfig::GetSelectedServices (ServiceType st) const

Get selected services.

Get the selected services with the ServiceType specified by st.

Parameters:

st specifies which ServiceType should be returned by the method.

Returns:

The selected services is returned.

See also:

```
Add Services (const\ std::list < std::string > \&,\ Service Type)\ (p.\ 366) Add Services (const\ std::list < std::string > \&,\ const\ std::list < std::string > \&,\ Service Type)\ (p.\ 366) Get Rejected Services (Service Type)\ const\ (p.\ 373) Clear Selected Services ()\ (p.\ 373)
```

6.158.3.25 const std::string& Arc::UserConfig::IdPName() const [inline]

Get IdP name.

Gets Identity Provider name (Shibboleth) to which user belongs.

Returns:

The IdP name

See also:

IdPName(const std::string&) (p. 374)

6.158.3.26 bool Arc::UserConfig::IdPName (const std::string & name) [inline]

Set IdP name.

Sets Identity Provider name (Shibboleth) to which user belongs. It is used for contacting Short Lived Certificate Service (p. 316).

The attribute associated with this setter method is 'idpname'.

Parameters:

name is the new IdP name.

Returns:

This method always returns true.

6.158.3.27 void Arc::UserConfig::InitializeCredentials ()

Initialize user credentials.

The location of the user credentials will be tried located when calling this method and stored internally when found. The method searches in different locations. First the user proxy or the user key/certificate pair is tried located in the following order:

- Proxy path specified by the environment variable X509_USER_PROXY
- Key/certificate path specified by the environment X509_USER_KEY and X509_USER_CERT
- Proxy path specified in either configuration file passed to the contructor or explicitly set using the setter method ProxyPath(const std::string&) (p. 382)
- Key/certificate path specified in either configuration file passed to the constructor or explicitly set using the setter methods KeyPath(const std::string&) (p. 378) and CertificatePath(const std::string&) (p. 371)
- ProxyPath with file name x509up_u concatenated with the user ID located in the OS temporary directory.

If the proxy or key/certificate pair have been explicitly specified only the specified path(s) will be tried, and if not found a ERROR is reported. If the proxy or key/certificate have not been specified and it is not located in the temporary directory a WARNING will be reported and the host key/certificate pair is tried and then the Globus key/certificate pair and a ERROR will be reported if not found in any of these locations.

Together with the proxy and key/certificate pair, the path to the directory containing CA certificates is also tried located when invoking this method. The directory will be tried located in the following order:

- Path specified by the X509_CERT_DIR environment variable.
- Path explicitly specified either in a parsed configuration file using the cacertficatecirectory or by using the setter method CACertificatesDirectory() (p. 370).
- Path created by concatenating the output of User::Home() with '.globus' and 'certificates' separated by the directory delimeter.
- Path created by concatenating the output of Glib::get_home_dir() with '.globus' and 'certificates' separated by the directory delimeter.
- Path created by concatenating the output of ArcLocation::Get() (p. 46), with 'etc' and 'certificates' separated by the directory delimeter.
- Path created by concatenating the output of ArcLocation::Get() (p. 46), with 'etc', 'grid-security' and 'certificates' separated by the directory delimeter.
- Path created by concatenating the output of ArcLocation::Get() (p. 46), with 'share' and 'certificates' separated by the directory delimeter.
- Path created by concatenating 'etc', 'grid-security' and 'certificates' separated by the directory delimeter.

If the CA certificate directory have explicitly been specified and the directory does not exist a ERROR is reported. If none of the directories above does not exist a ERROR is reported.

See also:

CredentialsFound() (p. 373)

ProxyPath(const std::string&) (p. 382) KeyPath(const std::string&) (p. 378) CertificatePath(const std::string&) (p. 371)

CACertificatesDirectory(const std::string&) (p. 370)

6.158.3.28 const std::string& Arc::UserConfig::JobListFile() const [inline]

Get a reference to the path of the job list file.

The job list file is used to store and fetch information about submitted computing jobs to computing services. This method will return the path to the specified job list file.

Returns:

The path to the job list file is returned.

See also:

JobListFile(const std::string&) (p. 376)

6.158.3.29 bool Arc::UserConfig::JobListFile (const std::string & path)

Set path to job list file.

The method takes a path to a file which will be used as the job list file for storing and reading job information. If the specified path *path* does not exist a empty job list file will be tried created. If creating the job list file in any way fails *false* will be returned and a ERROR message will be reported. Otherwise *true* is returned. If the directory containing the file does not exist, it will be tried created. The method will also return *false* if the file is not a regular file.

The attribute associated with this setter method is 'joblist'.

Parameters:

path the path to the job list file.

Returns:

If the job list file is a regular file or if it can be created true is returned, otherwise false is returned.

See also:

```
JobListFile() const (p. 376)
```

6.158.3.30 const std::string& Arc::UserConfig::KeyPassword () const [inline]

Get password for generated key.

Get password to be used to encode private key of credentials obtained from Short Lived Credentials Service (p. 316).

Returns:

The key password is returned.

See also:

```
KeyPassword(const std::string&) (p. 377)
KeyPath() const (p. 377)
KeySize() const (p. 378)
```

6.158.3.31 bool Arc::UserConfig::KeyPassword (const std::string & newKeyPassword) [inline]

Set password for generated key.

Set password to be used to encode private key of credentials obtained from Short Lived Credentials Service (p. 316).

The attribute associated with this setter method is 'keypassword'.

Parameters:

newKeyPassword is the new password to the key.

Returns:

This method always returns true.

See also:

```
KeyPassword() const (p. 376)
KeyPath(const std::string&) (p. 378)
KeySize(int) (p. 378)
```

6.158.3.32 const std::string& Arc::UserConfig::KeyPath () const [inline]

Get path to key.

The path to the key is returned when invoking this method.

Returns:

The path to the user key is returned.

```
InitializeCredentials() (p. 375)
CredentialsFound() const (p. 373)
KeyPath(const std::string&) (p. 378)
CertificatePath() const (p. 371)
KeyPassword() const (p. 376)
KeySize() const (p. 378)
```

6.158.3.33 bool Arc::UserConfig::KeyPath (const std::string & newKeyPath) [inline]

Set path to key.

The path to user key will be set by this method. The path to the corresponding certificate can be set with the CertificatePath(const std::string&) (p. 371) method. Note that the InitializeCredentials() (p. 375) method will also try to set this path, by searching in different locations.

The attribute associated with this setter method is 'keypath'.

Parameters:

newKeyPath is the path to the new key.

Returns:

This method always returns true.

See also:

InitializeCredentials() (p. 375) CredentialsFound() const (p. 373) KeyPath() const (p. 377) CertificatePath(const std::string&) (p. 371) KeyPassword(const std::string&) (p. 377) KeySize(int) (p. 378)

6.158.3.34 int Arc::UserConfig::KeySize() const [inline]

Get key size.

Get size/strengt of private key of credentials obtained from Short Lived Credentials Service (p. 316).

Returns:

The key size, as an integer, is returned.

See also:

KeySize(int) (p. 378) KeyPath() const (p. 377) KeyPassword() const (p. 376)

6.158.3.35 bool Arc::UserConfig::KeySize (int newKeySize) [inline]

Set key size.

Set size/strengt of private key of credentials obtained from Short Lived Credentials Service (p. 316). The attribute associated with this setter method is 'keysize'.

Parameters:

newKeySize is the size, an an integer, of the key.

Returns:

This method always returns true.

See also:

```
KeySize() const (p. 378)
KeyPath(const std::string&) (p. 378)
KeyPassword(const std::string&) (p. 377)
```

6.158.3.36 bool Arc::UserConfig::LoadConfigurationFile (const std::string & conffile, bool ignoreJobListFile = true)

Load specified configuration file.

The configuration file passed is parsed by this method by using the IniConfig class. If the parsing is unsuccessful a WARNING is reported.

The format of the configuration file should follow that of INI, and every attribute present in the file is only allowed once, if otherwise a WARNING will be reported. The file can contain at most two sections, one named common and the other name alias. If other sections exist a WARNING will be reported. Only the following attributes is allowed in the common section of the configuration file:

- certificatepath (CertificatePath(const std::string&) (p. 371))
- keypath (KeyPath(const std::string&) (p. 378))
- proxypath (ProxyPath(const std::string&) (p. 382))
- cacertificatesdirectory (CACertificatesDirectory(const std::string&) (p. 370))
- cacertificatepath (CACertificatePath(const std::string&) (p. 369))
- timeout (Timeout(int) (p. 384))
- joblist (JobListFile(const std::string&) (p. 376))
- defaultservices (AddServices(const_std::list<std::string>&, const_std::list<std::string>&, ServiceType) (p. 366))
- rejectservices (AddServices(const std::list<std::string>&, const std::list<std::string>&, ServiceType) (p. 366))
- verbosity (Verbosity(const std::string&) (p. 386))
- brokername (Broker(const std::string&) (p. 369) or Broker(const std::string&, const std::string&) (p. 368))
- brokerarguments (Broker(const std::string&) (p. 369) or Broker(const std::string&, const std::string&) (p. 368))
- bartender (Bartender(const std::list<URL>&))
- vomsserverpath (VOMSServerPath(const std::string&) (p. 387))
- username (UserName(const std::string&) (p. 385))
- password (Password(const std::string&) (p. 381))
- keypassword (KeyPassword(const std::string&) (p. 377))

- keysize (KeySize(int) (p. 378))
- certificatelifetime (CertificateLifeTime(const Period&) (p. 371))
- slcs (SLCS(const URL&) (p. 383))
- storedirectory (StoreDirectory(const std::string&) (p. 384))
- idpname (IdPName(const std::string&) (p. 374))

where the method in parentheses is the associated setter method. If other attributes exist in the common section a WARNING will be reported for each of these attributes. In the alias section aliases can be defined, and should represent a selection of services. The alias can then refered to by input to the AddServices(const std::list<std::string>&, ServiceType) (p. 366) and AddServices(const std::list<std::string>&, ServiceType) (p. 366) methods. An alias can not contain any of the characters '.', ':', ' or '\t' and should be defined as follows:

```
< alias_name > = < service_type > : < flavour > : < service_url > | < alias_ref > [...]
```

where <alias_name> is the name of the defined alias, <service_type> is the service type in lower case, <flavour> is the type of middleware plugin to use, <service_url> is the URL which should be used to contact the service and <alias_ref> is another defined alias. The parsed aliases will be stored internally and resolved when needed. If a alias already exist, and another alias with the same name is parsed then this other alias will overwrite the existing alias.

Parameters:

conffile is the path to the configuration file.

ignoreJobListFile is a optional boolean which indicates whether the joblistfile attribute in the configuration file should be ignored. Default is to ignored it (true).

Returns:

If loading the configuration file succeeds true is returned, otherwise false is returned.

See also:

```
SaveToFile() (p. 382)
```

6.158.3.37 Arc::UserConfig::operator bool (void) const [inline]

Check for validity.

The validity of an object created from this class can be checked using this casting operator. An object is valid if the constructor did not encounter any errors.

See also:

```
operator!() (p. 380)
```

6.158.3.38 bool Arc::UserConfig::operator! (void) const [inline]

Check for non-validity.

See operator bool() for a description.

See also:

operator bool()

6.158.3.39 const std::string& Arc::UserConfig::OverlayFile () const [inline]

Get path to configuration overlay file.

Returns:

The overlay file path

See also:

OverlayFile(const std::string&) (p. 381)

6.158.3.40 bool Arc::UserConfig::OverlayFile (const std::string & path) [inline]

Set path to configuration overlay file.

Content of specified file is a backdoor to configuration XML generated from information stored in this class. The content of file is passed to BaseConfig (p. 59) class in ApplyToConfig(BaseConfig&) then merged with internal configuration XML representation. This feature is meant for quick prototyping/testing/tuning of functionality without rewriting code. It is meant for developers and most users won't need it.

The attribute associated with this setter method is 'overlayfile'.

Parameters:

path is the new overlay file path.

Returns:

This method always returns true.

See also:

6.158.3.41 const std::string& Arc::UserConfig::Password () const [inline]

Get password.

Get password which is used for requesting credentials from Short Lived Credentials Service (p. 316).

Returns:

The password is returned.

See also:

Password(const std::string&) (p. 381)

6.158.3.42 bool Arc::UserConfig::Password (const std::string & newPassword) [inline]

Set password.

Set password which is used for requesting credentials from Short Lived Credentials Service (p. 316).

The attribute associated with this setter method is 'password'.

Parameters:

newPassword is the new password to set.

Returns:

This method always returns true.

See also:

Password() const (p. 381)

6.158.3.43 const std::string& Arc::UserConfig::ProxyPath () const [inline]

Get path to user proxy.

Retrieve path to user proxy.

Returns:

Returns the path to the user proxy.

See also:

ProxyPath(const std::string&) (p. 382)

6.158.3.44 bool Arc::UserConfig::ProxyPath (const std::string & newProxyPath) [inline]

Set path to user proxy.

This method will set the path of the user proxy. Note that the InitializeCredentials() (p. 375) method will also try to set this path, by searching in different locations.

The attribute associated with this setter method is 'proxypath'

Parameters:

newProxyPath is the path to a user proxy.

Returns:

This method always returns true.

See also:

InitializeCredentials() (p. 375) CredentialsFound() (p. 373) ProxyPath() const (p. 382)

6.158.3.45 bool Arc::UserConfig::SaveToFile (const std::string & filename) const

Save to INI file.

This method will save the object data as a INI file. The saved file can be loaded with the Load-ConfigurationFile method.

```
Parameters:
```

filename the name of the file which the data will be saved to.

Returns:

false if unable to get handle on file, otherwise true is returned.

See also:

LoadConfigurationFile() (p. 379)

6.158.3.46 const URL& Arc::UserConfig::SLCS () const [inline]

Get the URL to the Short Lived Certificate Service (p. 316) (SLCS).

Returns:

The SLCS is returned.

See also:

SLCS(const URL&) (p. 383)

6.158.3.47 bool Arc::UserConfig::SLCS (const URL & newSLCS) [inline]

Set the URL to the Short Lived Certificate Service (p. 316) (SLCS).

The attribute associated with this setter method is 'slcs'.

Parameters:

newSLCS is the URL to the SLCS

Returns:

This method always returns true.

See also:

SLCS() const (p. 383)

6.158.3.48 const std::string& Arc::UserConfig::StoreDirectory() const [inline]

Get store diretory.

Sets directory which is used to store credentials obtained from Short Lived Credential Servide.

Returns:

The path to the store directory is returned.

See also:

StoreDirectory(const std::string&) (p. 384)

6.158.3.49 bool Arc::UserConfig::StoreDirectory (const std::string & newStoreDirectory) [inline]

Set store directory.

Sets directory which will be used to store credentials obtained from Short Lived Credential Servide.

The attribute associated with this setter method is 'storedirectory'.

Parameters:

newStoreDirectory is the path to the store directory.

Returns:

This method always returns true.

See also:

6.158.3.50 int Arc::UserConfig::Timeout () const [inline]

Get timeout.

Returns the timeout in seconds.

Returns:

timeout in seconds.

See also:

```
Timeout(int) (p. 384)
DEFAULT_TIMEOUT (p. 388)
```

6.158.3.51 bool Arc::UserConfig::Timeout (int newTimeout)

Set timeout.

When communicating with a service the timeout specifies how long, in seconds, the communicating instance should wait for a response. If the response have not been received before this period in time, the connection is typically dropped, and an error will be reported.

This method will set the timeout to the specified integer. If the passed integer is less than or equal to 0 then false is returned and the timeout will not be set, otherwise true is returned and the timeout will be set to the new value.

The attribute associated with this setter method is 'timeout'.

Parameters:

newTimeout the new timeout value in seconds.

Returns:

false in case newTimeout <= 0, otherwise true.

```
See also:
```

```
Timeout() const (p. 384)
DEFAULT_TIMEOUT (p. 388)
```

6.158.3.52 const std::string& Arc::UserConfig::UserName () const [inline]

Get user-name.

Get username which is used for requesting credentials from Short Lived Credentials Service (p. 316).

Returns:

The username is returned.

See also:

UserName(const std::string&) (p. 385)

6.158.3.53 bool Arc::UserConfig::UserName (const std::string & name) [inline]

Set user-name for SLCS.

 $Set \ username \ which \ is \ used \ for \ requesting \ credentials \ from \ Short \ Lived \ Credentials \ Service \ (p. 316).$

The attribute associated with this setter method is 'username'.

Parameters:

name is the name of the user.

Returns:

This method always return true.

See also:

UserName() const (p. 385)

6.158.3.54 const std::string& Arc::UserConfig::UtilsDirPath() const [inline]

Get path to directory storing utility files for DataPoints.

Returns:

The utils dir path

See also:

UtilsDirPath(const std::string&) (p. 386)

6.158.3.55 bool Arc::UserConfig::UtilsDirPath (const std::string & dir)

Set path to directory storing utility files for DataPoints.

Some DataPoints can store information on remote services in local files. This method sets the path to the directory containing these files. For example arc* tools set it to ARCUSERDIRECTORY and A-REX sets it to the control directory. The directory is created if it does not exist.

Parameters:

path is the new utils dir path.

Returns:

This method always returns true.

6.158.3.56 const std::string& Arc::UserConfig::Verbosity () const [inline]

Get the user selected level of verbosity.

The string representation of the verbosity level specified by the user is returned when calling this method. If the user have not specified the verbosity level the empty string will be referenced.

Returns:

the verbosity level, or empty if it has not been set.

See also:

Verbosity(const std::string&) (p. 386)

6.158.3.57 bool Arc::UserConfig::Verbosity (const std::string & newVerbosity)

Set verbosity.

The verbosity will be set when invoking this method. If the string passed cannot be parsed into a corresponding LogLevel, using the function a WARNING is reported and false is returned, otherwise true is returned.

The attribute associated with this setter method is 'verbosity'.

Returns:

true in case the verbosity could be set to a allowed LogLevel, otherwise false.

See also:

Verbosity() const (p. 386)

6.158.3.58 const std::string& Arc::UserConfig::VOMSServerPath() const [inline]

Get path to file containing VOMS configuration.

Get path to file which contians list of VOMS services and associated configuration parameters.

Returns:

The path to VOMS configuration file is returned.

See also:

VOMSServerPath(const std::string&) (p. 387)

6.158.3.59 bool Arc::UserConfig::VOMSServerPath (const std::string & path) [inline]

Set path to file containing VOMS configuration.

Set path to file which contians list of VOMS services and associated configuration parameters needed to contact those services. It is used by arcproxy.

The attribute associated with this setter method is 'vomsserverpath'.

Parameters:

path the path to VOMS configuration file

Returns:

This method always return true.

See also:

VOMSServerPath() const (p. 386)

6.158.4 Field Documentation

6.158.4.1 const std::string Arc::UserConfig::ARCUSERDIRECTORY [static]

Path to ARC user home directory.

The ARCUSERDIRECTORY variable is the path to the ARC home directory of the current user. This path is created using the User::Home() method.

See also:

User::Home()

6.158.4.2 const std::string Arc::UserConfig::DEFAULT_BROKER [static]

Default broker.

The *DEFAULT_BROKER* specifies the name of the broker which should be used in case no broker is explicitly chosen.

See also:

Broker (p. 369)
Broker(const std::string&) (p. 369)
Broker(const std::string&, const std::string&) (p. 368)
Broker() const (p. 368)

6.158.4.3 const int Arc::UserConfig::DEFAULT_TIMEOUT = 20 [static]

Default timeout in seconds.

The *DEFAULT_TIMEOUT* specifies interval which will be used in case no timeout interval have been explicitly specified. For a description about timeout see Timeout(int) (p. 384).

See also:

Timeout(int) (p. 384) Timeout() const (p. 384)

6.158.4.4 const std::string Arc::UserConfig::DEFAULTCONFIG [static]

Path to default configuration file.

The *DEFAULTCONFIG* variable is the path to the default configuration file used in case no configuration file have been specified. The path is created from the ARCUSERDIRECTORY object.

6.158.4.5 const std::string Arc::UserConfig::EXAMPLECONFIG [static]

Path to example configuration.

The EXAMPLECONFIG variable is the path to the example configuration file.

6.158.4.6 const std::string Arc::UserConfig::SYSCONFIG [static]

Path to system configuration.

The SYSCONFIG variable is the path to the system configuration file. This variable is only equal to SYSCONFIGARCLOC if ARC is installed in the root (highly unlikely).

6.158.4.7 const std::string Arc::UserConfig::SYSCONFIGARCLOC [static]

Path to system configuration at ARC location.

The SYSCONFIGARCLOC variable is the path to the system configuration file which reside at the ARC installation location.

The documentation for this class was generated from the following file:

UserConfig.h

6.159 Arc::UsernameToken Class Reference

Interface for manipulation of WS-Security according to Username Token Profile.

#include <UsernameToken.h>

Public Types

• enum PasswordType

Public Member Functions

- UsernameToken (SOAPEnvelope &soap)
- UsernameToken (SOAPEnvelope &soap, const std::string &username, const std::string &password, const std::string &uid, PasswordType pwdtype)
- UsernameToken (SOAPEnvelope &soap, const std::string &username, const std::string &id, bool mac, int iteration)
- operator bool (void)
- std::string Username (void)
- bool Authenticate (const std::string &password, std::string &derived_key)
- bool Authenticate (std::istream &password, std::string &derived_key)

6.159.1 Detailed Description

Interface for manipulation of WS-Security according to Username Token Profile.

6.159.2 Member Enumeration Documentation

6.159.2.1 enum Arc::UsernameToken::PasswordType

SOAP header element

6.159.3 Constructor & Destructor Documentation

6.159.3.1 Arc::UsernameToken::UsernameToken (SOAPEnvelope & soap)

Link to existing SOAP header and parse Username Token information. Username Token related information is extracted from SOAP header and stored in class variables.

6.159.3.2 Arc::UsernameToken::UsernameToken (SOAPEnvelope & soap, const std::string & username, const std::string & password, const std::string & uid, PasswordType pwdtype)

Add Username Token information into the SOAP header. Generated token contains elements Username and Password and is meant to be used for authentication.

Parameters:

soap the SOAP message

```
username <wsse:Username>...</wsse:Username> - if empty it is entered interactively from
    stdin

password <wsse:Password Type="...">...</wsse:Password> - if empty it is entered interac-
    tively from stdin

uid <wsse:UsernameToken (p. 389) wsu:ID="...">
pwdtype <wsse:Password Type="...">...</wsse:Password>
```

6.159.3.3 Arc::UsernameToken::UsernameToken (SOAPEnvelope & soap, const std::string & username, const std::string & id, bool mac, int iteration)

Add Username Token information into the SOAP header. Generated token contains elements Username and Salt and is meant to be used for deriving Key Derivation.

Parameters:

```
soap the SOAP message
username <wsse:Username>...</wsse:Username>
mac if derived key is meant to be used for Message (p. 238) Authentication Code
iteration <wsse11:Iteration>...</wsse11:Iteration>
```

6.159.4 Member Function Documentation

6.159.4.1 bool Arc::UsernameToken::Authenticate (std::istream & password, std::string & derived_key)

Checks parsed token against password stored in specified stream. If token is meant to be used for deriving a key then key is returned in derived_key

6.159.4.2 bool Arc::UsernameToken::Authenticate (const std::string & password, std::string & derived_key)

Checks parsed/generated token against specified password. If token is meant to be used for deriving a key then key is returned in derived_key. In that case authentication is performed outside of UsernameToken (p. 389) class using obtained derived_key.

6.159.4.3 Arc::UsernameToken::operator bool (void)

Returns true of constructor succeeded

6.159.4.4 std::string Arc::UsernameToken::Username (void)

Returns username associated with this instance

The documentation for this class was generated from the following file:

• UsernameToken.h

6.160 Arc::UserSwitch Class Reference

#include <User.h>

6.160.1 Detailed Description

If this class is created user identity is switched to provided uid and gid. Due to internal lock there will be only one valid instance of this class. Any attempt to create another instance will block till first one is destroyed. If uid and gid are set to 0 then user identity is not switched. But lock is applied anyway. The lock has dual purpose. First and most important is to protect communication with underlying operating system which may depend on user identity. For that it is advisable for code which talks to operating system to acquire valid instance of this class. Care must be taken for not to hold that instance too long cause that may block other code in multithreaded envoronment. Other purpose of this lock is to provide workaround for glibc bug in __nptl_setxid. That bug causes lockup of seteuid() function if racing with fork. To avoid this problem the lock mentioned above is used by Run (p. 300) class while spawning new process.

The documentation for this class was generated from the following file:

• User.h

6.161 Arc::VOMSTrustList Class Reference

#include < VOMSUtil.h>

Public Member Functions

- VOMSTrustList (const std::vector< std::string > &encoded list)
- VOMSTrustList (const std::vector< VOMSTrustChain > &chains, const std::vector< VOMSTrustRegex > ®exs)
- VOMSTrustChain & AddChain (const VOMSTrustChain &chain)
- VOMSTrustChain & AddChain (void)
- RegularExpression & AddRegex (const VOMSTrustRegex ®)

6.161.1 Detailed Description

Stores definitions for making decision if VOMS server is trusted

6.161.2 Constructor & Destructor Documentation

6.161.2.1 Arc::VOMSTrustList::VOMSTrustList (const std::vector < std::string > & encoded_list)

Creates chain lists and regexps from plain list. List is made of chunks delimited by elements containing pattern "NEXT CHAIN". Each chunk with more than one element is converted into one instance of VOMSTrustChain. Chunks with single element are converted to VOMSTrust-Chain if element does not have special symbols. Otherwise it is treated as regular expres-Those symbols are ,, ; and ,* . Trusted chains can be congicured in two ways: <tls:VOMSCertTrustDNChain> <tls:VOMSCertTrustDN>/0=Grid/0=Nordu-Grid/CN=host/arthur.hep.lu.se</tls:VOMSCertTrustDN> <tls:VOMSCertTrust-DN>/O=Grid/O=NorduGrid/CN=NorduGrid Certification Authority</tls:VOMSCert-TrustDN> <tl><tls:VOMSCertTrustDN>—-NEXT CHAIN—</tls:VOMSCertTrustDN> <tls:VOMSCertTrustDN>/DC=ch/DC=cern/OU=computers/CN=voms.cern.ch</tls:VOMSCert-<tls:VOMSCertTrustDN>/DC=ch/DC=cern/CN=CERN TrustDN> Trusted Certifica-</tl></tls:VOMSCertTrustDNChain> tion **Authority**</tls:VOMSCertTrustDN> the <tls:VOMSCertTrustDN>/O=Grid/O=Norduway <tls:VOMSCertTrustDNChain> Grid/CN=host/arthur.hep.lu.se</tls:VOMSCertTrustDN> <tls:VOMSCertTrust-DN>/O=Grid/O=NorduGrid/CN=NorduGrid Certification Authority</tls:VOMSCertTrust-<tls:VOMSCert-<tls:VOMSCertTrustDNChain> DN></tl></tls:VOMSCertTrustDNChain> TrustDN>/DC=ch/DC=cern/OU=computers/CN=voms.cern.ch</tls:VOMSCertTrust-<tls:VOMSCertTrustDN>/DC=ch/DC=cern/CN=CERN **Trusted** Authority</tls:VOMSCertTrustDN> </tls:VOMSCertTrustDNChain> each chunk is supposed to contain a suit of DN of trusted certificate chain, in which the first DN is the DN of the certificate (cert0) which is used to sign the Attribute Certificate (AC), the second DN is the DN of the issuer certificate(cert1) which is used to sign cert0. So if there are one or more intermediate issuers, then there should be 3 or more than 3 DNs in this chunk (considering cert0 and the root certificate, plus the intermediate certificate).

6.161.2.2 Arc::VOMSTrustList::VOMSTrustList (const std::vector < VOMSTrustChain > & chains, const std::vector < VOMSTrustRegex > & regexs)

Creates chain lists and regexps from those specified in arguments. See AddChain() (p. 393) and Add-Regex() (p. 393) for more information.

6.161.3 Member Function Documentation

6.161.3.1 VOMSTrustChain& Arc::VOMSTrustList::AddChain (void)

Adds empty chain of trusted DNs to list.

6.161.3.2 VOMSTrustChain & Arc::VOMSTrustList::AddChain (const VOMSTrustChain & chain)

Adds chain of trusted DNs to list. During verification each signature of AC is checked against all stored chains. DNs of chain of certificate used for signing AC are compared against DNs stored in these chains one by one. If needed DN of issuer of last certificate is checked too. Comparison succeeds if DNs in at least one stored chain are same as those in certificate chain. Comparison stops when all DNs in stored chain are compared. If there are more DNs in stored chain than in certificate chain then comparison fails. Empty stored list matches any certificate chain. Taking into account that certificate chains are verified down to trusted CA anyway, having more than one DN in stored chain seems to be useless. But such feature may be found useful by some very strict sysadmins. ??? IMO,DN list here is not only for authentication, it is also kind of ACL, which means the AC consumer only trusts those DNs which issues AC.

6.161.3.3 RegularExpression& Arc::VOMSTrustList::AddRegex (const VOMSTrustRegex & reg)

Adds regular expression to list. During verification each signature of AC is checked against all stored regular expressions. DN of signing certificate must match at least one of stored regular expressions.

The documentation for this class was generated from the following file:

• VOMSUtil.h

6.162 Arc::WSAEndpointReference Class Reference

Interface for manipulation of WS-Adressing Endpoint Reference.

#include <WSA.h>

Public Member Functions

- WSAEndpointReference (XMLNode epr)
- WSAEndpointReference (const WSAEndpointReference &wsa)
- WSAEndpointReference (const std::string &address)
- WSAEndpointReference (void)
- ~WSAEndpointReference (void)
- std::string Address (void) const
- void Address (const std::string &uri)
- WSAEndpointReference & operator= (const std::string &address)
- XMLNode ReferenceParameters (void)
- XMLNode MetaData (void)
- operator XMLNode (void)

6.162.1 Detailed Description

Interface for manipulation of WS-Adressing Endpoint Reference.

It works on Endpoint Reference stored in XML tree. No information is stored in this object except reference to corresponding XML subtree.

6.162.2 Constructor & Destructor Documentation

6.162.2.1 Arc::WSAEndpointReference::WSAEndpointReference (XMLNode epr)

Linking to existing EPR in XML tree

6.162.2.2 Arc::WSAEndpointReference::WSAEndpointReference (const WSAEndpointReference & wsa)

Copy constructor

6.162.2.3 Arc::WSAEndpointReference::WSAEndpointReference (const std::string & address)

Creating independent EPR - not implemented

6.162.2.4 Arc::WSAEndpointReference::WSAEndpointReference (void)

Dummy constructor - creates invalid instance

6.162.2.5 Arc::WSAEndpointReference::~WSAEndpointReference (void)

Destructor. All empty elements of EPR XML are destroyed here too

6.162.3 Member Function Documentation

6.162.3.1 void Arc::WSAEndpointReference::Address (const std::string & uri)

Assigns new Address value. If EPR had no Address element it is created.

6.162.3.2 std::string Arc::WSAEndpointReference::Address (void) const

Returns Address (URL) encoded in EPR

6.162.3.3 XMLNode Arc::WSAEndpointReference::MetaData (void)

Access to MetaData element of EPR. Obtained XML element should be manipulated directly in application-dependent way. If EPR had no MetaData element it is created.

6.162.3.4 Arc::WSAEndpointReference::operator XMLNode (void)

Returns reference to EPR top XML node

6.162.3.5 WSAEndpointReference& Arc::WSAEndpointReference::operator= (const std::string & address)

Same as Address(uri)

6.162.3.6 XMLNode Arc::WSAEndpointReference::ReferenceParameters (void)

Access to ReferenceParameters element of EPR. Obtained XML element should be manipulated directly in application-dependent way. If EPR had no ReferenceParameters element it is created.

The documentation for this class was generated from the following file:

• WSA.h

6.163 Arc::WSAHeader Class Reference

Interface for manipulation WS-Addressing information in SOAP header.

#include <WSA.h>

Public Member Functions

- WSAHeader (SOAPEnvelope &soap)
- WSAHeader (const std::string &action)
- std::string To (void) const
- void To (const std::string &uri)
- WSAEndpointReference From (void)
- WSAEndpointReference ReplyTo (void)
- WSAEndpointReference FaultTo (void)
- std::string Action (void) const
- void Action (const std::string &uri)
- std::string MessageID (void) const
- void MessageID (const std::string &uri)
- std::string RelatesTo (void) const
- void RelatesTo (const std::string &uri)
- std::string RelationshipType (void) const
- void RelationshipType (const std::string &uri)
- XMLNode ReferenceParameter (int n)
- XMLNode ReferenceParameter (const std::string &name)
- XMLNode NewReferenceParameter (const std::string &name)
- operator XMLNode (void)

Static Public Member Functions

static bool Check (SOAPEnvelope &soap)

Protected Attributes

• bool header_allocated_

6.163.1 Detailed Description

Interface for manipulation WS-Addressing information in SOAP header.

It works on Endpoint Reference stored in XML tree. No information is stored in this object except reference to corresponding XML subtree.

6.163.2 Constructor & Destructor Documentation

6.163.2.1 Arc::WSAHeader::WSAHeader (SOAPEnvelope & soap)

Linking to a header of existing SOAP message

6.163.2.2 Arc::WSAHeader::WSAHeader (const std::string & action)

Creating independent SOAP header - not implemented

6.163.3 Member Function Documentation

6.163.3.1 void Arc::WSAHeader::Action (const std::string & uri)

Set content of Action element of SOAP Header. If such element does not exist it's created.

6.163.3.2 std::string Arc::WSAHeader::Action (void) const

Returns content of Action element of SOAP Header.

6.163.3.3 static bool Arc::WSAHeader::Check (SOAPEnvelope & soap) [static]

Tells if specified SOAP message has WSA header

6.163.3.4 WSAEndpointReference Arc::WSAHeader::FaultTo (void)

Returns FaultTo element of SOAP Header. If such element does not exist it's created. Obtained element may be manipulted.

6.163.3.5 WSAEndpointReference Arc::WSAHeader::From (void)

Returns From element of SOAP Header. If such element does not exist it's created. Obtained element may be manipulted.

6.163.3.6 void Arc::WSAHeader::MessageID (const std::string & uri)

Set content of MessageID element of SOAP Header. If such element does not exist it's created.

6.163.3.7 std::string Arc::WSAHeader::MessageID (void) const

Returns content of MessageID element of SOAP Header.

6.163.3.8 XMLNode Arc::WSAHeader::NewReferenceParameter (const std::string & name)

Creates new ReferenceParameter element with specified name. Returns reference to created element.

6.163.3.9 Arc::WSAHeader::operator XMLNode (void)

Returns reference to SOAP Header - not implemented

6.163.3.10 XMLNode Arc::WSAHeader::ReferenceParameter (const std::string & name)

Returns first ReferenceParameter element with specified name

6.163.3.11 XMLNode Arc::WSAHeader::ReferenceParameter (int *n*)

Return n-th ReferenceParameter element

6.163.3.12 void Arc::WSAHeader::RelatesTo (const std::string & uri)

Set content of RelatesTo element of SOAP Header. If such element does not exist it's created.

6.163.3.13 std::string Arc::WSAHeader::RelatesTo (void) const

Returns content of RelatesTo element of SOAP Header.

6.163.3.14 void Arc::WSAHeader::RelationshipType (const std::string & uri)

Set content of Relationship Type element of SOAP Header. If such element does not exist it's created.

6.163.3.15 std::string Arc::WSAHeader::RelationshipType (void) const

Returns content of Relationship Type element of SOAP Header.

6.163.3.16 WSAEndpointReference Arc::WSAHeader::ReplyTo (void)

Returns ReplyTo element of SOAP Header. If such element does not exist it's created. Obtained element may be manipulted.

6.163.3.17 void Arc::WSAHeader::To (const std::string & uri)

Set content of To element of SOAP Header. If such element does not exist it's created.

6.163.3.18 std::string Arc::WSAHeader::To (void) const

Returns content of To element of SOAP Header.

6.163.4 Field Documentation

6.163.4.1 bool Arc::WSAHeader::header_allocated_ [protected]

SOAP header element

The documentation for this class was generated from the following file:


• WSA.h

6.164 Arc::WSRF Class Reference

Base class for every WSRF (p. 399) message.

#include <WSRF.h>

Inheritance diagram for Arc::WSRF::



Public Member Functions

- WSRF (SOAPEnvelope &soap, const std::string &action="")
- WSRF (bool fault=false, const std::string &action="")
- virtual SOAPEnvelope & SOAP (void)
- virtual operator bool (void)

Protected Member Functions

void set_namespaces (void)

Protected Attributes

- bool allocated_
- bool valid_

6.164.1 Detailed Description

Base class for every WSRF (p. 399) message.

This class is not intended to be used directly. Use it like reference while passing through unknown WSRF (p. 399) message or use classes derived from it.

6.164.2 Constructor & Destructor Documentation

6.164.2.1 Arc::WSRF::WSRF (SOAPEnvelope & soap, const std::string & action = "")

Constructor - creates object out of supplied SOAP tree.

6.164.2.2 Arc::WSRF::WSRF (bool fault = false, const std::string & action = "")

Constructor - creates new WSRF (p. 399) object

6.164.3 Member Function Documentation

6.164.3.1 virtual Arc::WSRF::operator bool (void) [inline, virtual]

Returns true if instance is valid

6.164.3.2 void Arc::WSRF::set_namespaces (**void**) [protected]

set WS Resource namespaces and default prefixes in SOAP message

Reimplemented in Arc::WSRP (p. 403), and Arc::WSRFBaseFault (p. 401).

6.164.3.3 virtual SOAPEnvelope& Arc::WSRF::SOAP (void) [inline, virtual]

Direct access to underlying SOAP element

6.164.4 Field Documentation

6.164.4.1 bool Arc::WSRF::allocated_ [protected]

Associated SOAP message - it's SOAP message after all

6.164.4.2 bool Arc::WSRF::valid_ [protected]

true if soap_ needs to be deleted in destructor

The documentation for this class was generated from the following file:


• WSRF.h

6.165 Arc::WSRFBaseFault Class Reference

Base class for WSRF (p. 399) fault messages.

#include <WSRFBaseFault.h>

Inheritance diagram for Arc::WSRFBaseFault::



Public Member Functions

- WSRFBaseFault (SOAPEnvelope &soap)
- WSRFBaseFault (const std::string &type)

Protected Member Functions

void set_namespaces (void)

6.165.1 Detailed Description

Base class for WSRF (p. 399) fault messages.

Use classes inherited from it for specific faults.

6.165.2 Constructor & Destructor Documentation

6.165.2.1 Arc::WSRFBaseFault::WSRFBaseFault (SOAPEnvelope & soap)

Constructor - creates object out of supplied SOAP tree.

6.165.2.2 Arc::WSRFBaseFault::WSRFBaseFault (const std::string & type)

Constructor - creates new WSRF (p. 399) fault

6.165.3 Member Function Documentation

6.165.3.1 void Arc::WSRFBaseFault::set_namespaces (void) [protected]

set WS-ResourceProperties namespaces and default prefixes in SOAP message

Reimplemented from Arc::WSRF (p. 400).

The documentation for this class was generated from the following file:

• WSRFBaseFault.h

6.166 Arc::WSRP Class Reference

Base class for WS-ResourceProperties structures.

#include <WSResourceProperties.h>

Inheritance diagram for Arc::WSRP::



Public Member Functions

- WSRP (bool fault=false, const std::string &action="")
- WSRP (SOAPEnvelope &soap, const std::string &action="")

Protected Member Functions

void set namespaces (void)

6.166.1 Detailed Description

Base class for WS-ResourceProperties structures.

Inheriting classes implement specific WS-ResourceProperties messages and their properties/elements. Refer to WS-ResourceProperties specifications for things specific to every message.

6.166.2 Constructor & Destructor Documentation

6.166.2.1 Arc::WSRP::WSRP (bool fault = false, const std::string & action = "")

Constructor - prepares object for creation of new WSRP (p. 403) request/response/fault

6.166.2.2 Arc::WSRP::WSRP (SOAPEnvelope & soap, const std::string & action = "")

Constructor - creates object out of supplied SOAP tree. It does not check if 'soap' represents valid WS-ResourceProperties structure. Actual check for validity of structure has to be done by derived class.

6.166.3 Member Function Documentation

6.166.3.1 void Arc::WSRP::set_namespaces (void) [protected]

set WS-ResourceProperties namespaces and default prefixes in SOAP message

Reimplemented from Arc::WSRF (p. 400).

The documentation for this class was generated from the following file:


• WSResourceProperties.h

6.167 Arc::WSRPFault Class Reference

Base class for WS-ResourceProperties faults.

#include <WSResourceProperties.h>

Inheritance diagram for Arc::WSRPFault::



Public Member Functions

- WSRPFault (SOAPEnvelope &soap)
- WSRPFault (const std::string &type)

6.167.1 Detailed Description

Base class for WS-ResourceProperties faults.

6.167.2 Constructor & Destructor Documentation

6.167.2.1 Arc::WSRPFault::WSRPFault (SOAPEnvelope & soap)

Constructor - creates object out of supplied SOAP tree.

6.167.2.2 Arc::WSRPFault::WSRPFault (const std::string & type)

Constructor - creates new WSRP (p. 403) fault


The documentation for this class was generated from the following file:

• WSResourceProperties.h

6.168 Arc::WSRPResourcePropertyChangeFailure Class Reference

#include <WSResourceProperties.h>

Inheritance diagram for Arc::WSRPResourcePropertyChangeFailure::



Public Member Functions

- WSRPResourcePropertyChangeFailure (SOAPEnvelope &soap)
- WSRPResourcePropertyChangeFailure (const std::string &type)

6.168.1 Detailed Description

Base class for WS-ResourceProperties faults which contain ResourcePropertyChangeFailure

6.168.2 Constructor & Destructor Documentation

6.168.2.1 Arc::WSRPResourcePropertyChangeFailure::WSRPResourcePropertyChangeFailure (SOAPEnvelope & soap) [inline]

Constructor - creates object out of supplied SOAP tree.

6.168.2.2 Arc::WSRPResourcePropertyChangeFailure::WSRPResourcePropertyChangeFailure (const std::string & type) [inline]

Constructor - creates new WSRP (p. 403) fault

The documentation for this class was generated from the following file:

• WSResourceProperties.h

6.169 Arc::X509Token Class Reference

Class for manipulating X.509 Token Profile.

#include <X509Token.h>

Public Types

• enum X509TokenType

Public Member Functions

- X509Token (SOAPEnvelope &soap, const std::string &keyfile="")
- X509Token (SOAPEnvelope &soap, const std::string &certfile, const std::string &keyfile, X509TokenType token_type=Signature)
- ~X509Token (void)
- operator bool (void)
- bool Authenticate (const std::string &cafile, const std::string &capath)
- bool Authenticate (void)

6.169.1 Detailed Description

Class for manipulating X.509 Token Profile.

This class is for generating/consuming X.509 Token profile. Currently it is used by x509token handler (src/hed/pdc/x509tokensh/) It is not necessary to directly called this class. If we need to use X.509 Token functionality, we only need to configure the x509token handler into service and client.

6.169.2 Member Enumeration Documentation

6.169.2.1 enum Arc::X509Token::X509TokenType

X509TokeType is for distinguishing two types of operation. It is used as the parameter of constuctor.

6.169.3 Constructor & Destructor Documentation

6.169.3.1 Arc::X509Token::X509Token (SOAPEnvelope & soap, const std::string & keyfile = "")

Constructor.Parse X509 Token information from SOAP header. X509 Token related information is extracted from SOAP header and stored in class variables. And then it the X509Token (p. 407) object will be used for authentication if the tokentype is Signature; otherwise if the tokentype is Encryption, the encrypted soap body will be decrypted and replaced by decrypted message. keyfile is only needed when the X509Token (p. 407) is encryption token

6.169.3.2 Arc::X509Token::X509Token (SOAPEnvelope & soap, const std::string & certfile, const std::string & keyfile, X509TokenType token_type = Signature)

Constructor. Add X509 Token information into the SOAP header. Generated token contains elements X509 token and signature, and is meant to be used for authentication on the consuming side.

Parameters:

soap The SOAP message to which the X509 Token will be inserted

certfile The certificate file which will be used to encrypt the SOAP body (if parameter tokentype is Encryption), or be used as <wse:BinarySecurityToken/> (if parameter tokentype is Signature).

keyfile The key file which will be used to create signature. Not needed when create encryption. *tokentype* Token type: Signature or Encryption.

6.169.3.3 Arc::X509Token::~X509Token (void)

Deconstructor. Nothing to be done except finalizing the xmlsec library.

6.169.4 Member Function Documentation

6.169.4.1 bool Arc::X509Token::Authenticate (void)

Check signature by using the cert information in soap message. Only the signature itself is checked, and it is not guranteed that the certificate which is supposed to check the signature is trusted.

6.169.4.2 bool Arc::X509Token::Authenticate (const std::string & cafile, const std::string & capath)

Check signature by using the certificare information in X509Token (p. 407) which is parsed by the constructor, and the trusted certificates specified as one of the two parameters. Not only the signature (in the X509Token (p. 407)) itself is checked, but also the certificate which is supposed to check the signature needs to be trused (which means the certificate is issued by the ca certificate from CA file or CA directory). At least one the the two parameters should be set.

Parameters:

cafile The CA file capath The CA directory

Returns:

true if authentication passes; otherwise false

6.169.4.3 Arc::X509Token::operator bool (void)

Returns true of constructor succeeded

The documentation for this class was generated from the following file:


X509Token.h

6.170 Arc::XMLNode Class Reference

Wrapper for LibXML library Tree interface.

#include <XMLNode.h>

Inheritance diagram for Arc::XMLNode::



Public Member Functions

- XMLNode (void)
- XMLNode (const XMLNode &node)
- XMLNode (const std::string &xml)
- XMLNode (const char *xml, int len=-1)
- XMLNode (long ptr_addr)
- XMLNode (const NS &ns, const char *name)
- ∼XMLNode (void)
- void New (XMLNode &node) const
- void Exchange (XMLNode &node)
- void Move (XMLNode &node)
- void Swap (XMLNode &node)
- operator bool (void) const
- bool operator! (void) const
- bool operator== (const XMLNode &node)
- bool operator!= (const XMLNode &node)
- bool Same (const XMLNode &node)
- bool operator== (bool val)
- bool operator!= (bool val)
- bool operator== (const std::string &str)
- bool operator!= (const std::string &str)
- bool operator== (const char *str)
- bool operator!= (const char *str)
- XMLNode Child (int n=0)
- XMLNode operator[] (const char *name) const
- XMLNode operator[] (const std::string &name) const
- XMLNode operator[] (int n) const
- void operator++ (void)
- void operator– (void)
- int Size (void) const
- XMLNode Get (const std::string &name) const
- std::string Name (void) const
- std::string Prefix (void) const
- std::string FullName (void) const
- std::string Namespace (void) const

- void Name (const char *name)
- void Name (const std::string &name)
- void GetXML (std::string &out_xml_str, bool user_friendly=false) const
- void GetXML (std::string &out_xml_str, const std::string &encoding, bool user_friendly=false) const
- void GetDoc (std::string &out_xml_str, bool user_friendly=false) const
- operator std::string (void) const
- XMLNode & operator= (const char *content)
- XMLNode & operator= (const std::string &content)
- void Set (const std::string &content)
- XMLNode & operator= (const XMLNode &node)
- XMLNode Attribute (int n=0)
- XMLNode Attribute (const char *name)
- XMLNode Attribute (const std::string &name)
- XMLNode NewAttribute (const char *name)
- XMLNode NewAttribute (const std::string &name)
- int AttributesSize (void) const
- void Namespaces (const NS &namespaces, bool keep=false, int recursion=-1)
- NS Namespaces (void)
- std::string NamespacePrefix (const char *urn)
- XMLNode NewChild (const char *name, int n=-1, bool global order=false)
- XMLNode NewChild (const std::string &name, int n=-1, bool global_order=false)
- XMLNode NewChild (const char *name, const NS &namespaces, int n=-1, bool global_-order=false)
- XMLNode NewChild (const std::string &name, const NS &namespaces, int n=-1, bool global_order=false)
- XMLNode NewChild (const XMLNode &node, int n=-1, bool global_order=false)
- void Replace (const XMLNode &node)
- void Destroy (void)
- XMLNodeList Path (const std::string &path)
- XMLNodeList XPathLookup (const std::string &xpathExpr, const NS &nsList)
- XMLNode GetRoot (void)
- XMLNode Parent (void)
- bool SaveToFile (const std::string &file_name) const
- bool SaveToStream (std::ostream &out) const
- bool ReadFromFile (const std::string &file_name)
- bool ReadFromStream (std::istream &in)
- bool Validate (const std::string &schema_file, std::string &err_msg)

Protected Member Functions

• XMLNode (xmlNodePtr node)

Protected Attributes

- · bool is_owner_
- bool is temporary

Friends

- bool MatchXMLName (const XMLNode &node1, const XMLNode &node2)
- bool MatchXMLName (const XMLNode &node, const char *name)
- bool MatchXMLName (const XMLNode &node, const std::string &name)
- bool MatchXMLNamespace (const XMLNode &node1, const XMLNode &node2)
- bool MatchXMLNamespace (const XMLNode &node, const char *uri)
- bool MatchXMLNamespace (const XMLNode &node, const std::string &uri)

6.170.1 Detailed Description

Wrapper for LibXML library Tree interface.

This class wraps XML Node, Document and Property/Attribute structures. Each instance serves as pointer to actual LibXML element and provides convenient (for chosen purpose) methods for manipulating it. This class has no special ties to LibXML library and may be easily rewritten for any XML parser which provides interface similar to LibXML Tree. It implements only small subset of XML capabilities, which is probably enough for performing most of useful actions. This class also filters out (usually) useless textual nodes which are often used to make XML documents human-readable.

6.170.2 Constructor & Destructor Documentation

6.170.2.1 Arc::XMLNode::XMLNode (xmlNodePtr node) [inline, protected]

Private constructor for inherited classes Creates instance and links to existing LibXML structure. Acquired structure is not owned by class instance. If there is need to completely pass control of LibXML document to then instance's is owner variable has to be set to true.

6.170.2.2 Arc::XMLNode::XMLNode (void) [inline]

Constructor of invalid node Created instance does not point to XML element. All methods are still allowed for such instance but produce no results.

6.170.2.3 Arc::XMLNode::XMLNode (const XMLNode & node) [inline]

Copies existing instance. Underlying XML element is NOT copied. Ownership is NOT inherited. Strictly speaking it shuld be no const here - but that conflicts with C++.

6.170.2.4 Arc::XMLNode::XMLNode (const std::string & xml)

Creates XML document structure from textual representation of XML document. Created structure is pointed and owned by constructed instance

6.170.2.5 Arc::XMLNode::XMLNode (const char * xml, int len = -1)

Same as previous

6.170.2.6 Arc::XMLNode::XMLNode (long ptr_addr)

Copy constructor. Used by language bindigs

6.170.2.7 Arc::XMLNode::XMLNode (const NS & ns, const char * name)

Creates empty XML document structure with specified namespaces. Created XML contains only root element named 'name'. Created structure is pointed and owned by constructed instance

6.170.2.8 Arc::XMLNode::~XMLNode (void)

Destructor Also destroys underlying XML document if owned by this instance

6.170.3 Member Function Documentation

6.170.3.1 XMLNode Arc::XMLNode::Attribute (const std::string & name) [inline]

Returns XMLNode (p. 409) instance representing first attribute of node with specified by name

6.170.3.2 XMLNode Arc::XMLNode::Attribute (const char * name)

Returns XMLNode (p. 409) instance representing first attribute of node with specified by name

6.170.3.3 XMLNode Arc::XMLNode::Attribute (int n = 0)

Returns list of all attributes of node.

Returns XMLNode (p. 409) instance reresenting n-th attribute of node.

6.170.3.4 int Arc::XMLNode::AttributesSize (void) const

Returns number of attributes of node

6.170.3.5 XMLNode Arc::XMLNode::Child (int n = 0)

Returns XMLNode (p. 409) instance representing n-th child of XML element. If such does not exist invalid XMLNode (p. 409) instance is returned

6.170.3.6 void Arc::XMLNode::Destroy (void)

Destroys underlying XML element. XML element is unlinked from XML tree and destroyed. After this operation XMLNode (p. 409) instance becomes invalid

6.170.3.7 void Arc::XMLNode::Exchange (XMLNode & node)

Exchanges XML (sub)trees. Following conbinations are possible If either this ir node are refering owned XML tree (top level node) then references are simply excanged. This opearationis fast. If both

this and node are refering to XML (sub)tree of different documents then (sub)trees are exchahed between documents. If both this and node are refering to XML (sub)tree of same document then (sub)trees are moved inside document. The main reason for this method is to provide effective way to insert one XML document inside another. One should take into account that if any of exchanged nodes is top level it must be also owner of document. Otherwise method will fail. If both nodes are top level owners and/or invlaid nodes then this method is identical to Swap() (p. 418).

6.170.3.8 std::string Arc::XMLNode::FullName (void) const [inline]

Returns prefix:name of XML node

6.170.3.9 XMLNode Arc::XMLNode::Get (const std::string & name) const [inline]

Same as operator[]

6.170.3.10 void Arc::XMLNode::GetDoc (std::string & out_xml_str, bool user_friendly = false) const

Fills argument with whole XML document textual representation

6.170.3.11 XMLNode Arc::XMLNode::GetRoot (void)

Get the root node from any child node of the tree

6.170.3.12 void Arc::XMLNode::GetXML (std::string & out_xml_str, const std::string & encoding, bool user_friendly = false) const

Fills argument with this instance XML subtree textual representation if the XML subtree is corresponding to the encoding format specified in the argument, e.g. utf-8

6.170.3.13 void Arc::XMLNode::GetXML (std::string & out_xml_str, bool user_friendly = false) const

Fills argument with this instance XML subtree textual representation

6.170.3.14 void Arc::XMLNode::Move (XMLNode & node)

Moves content of this XML (sub)tree to node This opeartion is similar to New except that XML (sub)tree to refered by this is destroyed. This method is more effective than combination of New() (p. 414) and Destroy() (p. 412) because internally it is optimized not to copy data if not needed. The main purpose of this is to effectively extract part of XML document.

6.170.3.15 void Arc::XMLNode::Name (const std::string & name) [inline]

Assigns new name to XML node

6.170.3.16 void Arc::XMLNode::Name (const char * name)

Assigns new name to XML node

6.170.3.17 std::string Arc::XMLNode::Name (void) const

Returns name of XML node

6.170.3.18 std::string Arc::XMLNode::Namespace (void) const

Returns namespace URI of XML node

6.170.3.19 std::string Arc::XMLNode::NamespacePrefix (const char * urn)

Returns prefix of specified namespace. Empty string if no such namespace.

6.170.3.20 NS Arc::XMLNode::Namespaces (void)

Returns namespaces known at this node

6.170.3.21 void Arc::XMLNode::Namespaces (const NS & namespaces, bool keep = false, int recursion = -1)

Assigns namespaces of XML document at point specified by this instance. If namespace already exists it gets new prefix. New namespaces are added. It is useful to apply this method to XML being processed in order to refer to it's elements by known prefix. If keep is set to false existing namespace definition residing at this instance and below are removed (default beavior). If recursion is set to positive number then depth of prefix replacement is limited by this number (0 limits it to this node only). For unlimted recursion use -1. If recursion is limited then value of keep is ignored and existing namespaces are always kept.

6.170.3.22 void Arc::XMLNode::New (XMLNode & node) const

Creates a copy of XML (sub)tree. If object does not represent whole document - top level document is created. 'new_node' becomes a pointer owning new XML document.

6.170.3.23 XMLNode Arc::XMLNode::NewAttribute (const std::string & name) [inline]

Creates new attribute with specified name.

6.170.3.24 XMLNode Arc::XMLNode::NewAttribute (const char * name)

Creates new attribute with specified name.

6.170.3.25 XMLNode Arc::XMLNode::NewChild (const XMLNode & node, int n = -1, bool $global_order = false$)

Link a copy of supplied XML node as child. Returns instance referring to new child. XML element is a copy of supplied one but not owned by returned instance

6.170.3.26 XMLNode Arc::XMLNode::NewChild (const std::string & name, const NS & namespaces, int n = -1, bool global_order = false) [inline]

Same as NewChild(const char*,const NS&,int,bool) (p. 415)

6.170.3.27 XMLNode Arc::XMLNode::NewChild (const char * name, const NS & namespaces, int n = -1, bool $global_order = false$)

Creates new child XML element at specified position with specified name and namespaces. For more information look at NewChild(const char*,int,bool) (p. 415)

6.170.3.28 XMLNode Arc::XMLNode::NewChild (const std::string & name, int n = -1, bool $global_order = false$) [inline]

Same as NewChild(const char*,int,bool) (p. 415)

6.170.3.29 XMLNode Arc::XMLNode::NewChild (const char * name, int n = -1, bool $global_order$ = false)

Creates new child XML element at specified position with specified name. Default is to put it at end of list. If global order is true position applies to whole set of children, otherwise only to children of same name. Returns created node.

6.170.3.30 Arc::XMLNode::operator bool (void) const [inline]

Returns true if instance points to XML element - valid instance

6.170.3.31 Arc::XMLNode::operator std::string (void) const

Returns textual content of node excluding content of children nodes

6.170.3.32 bool Arc::XMLNode::operator! (void) const [inline]

Returns true if instance does not point to XML element - invalid instance

6.170.3.33 bool Arc::XMLNode::operator!= (const char * str) [inline]

This operator is needed to avoid ambiguity

6.170.3.34 bool Arc::XMLNode::operator!= (const std::string & str) [inline]

This operator is needed to avoid ambiguity

6.170.3.35 bool Arc::XMLNode::operator!= (bool val) [inline]

This operator is needed to avoid ambiguity

6.170.3.36 bool Arc::XMLNode::operator!= (const XMLNode & node) [inline]

Returns false if 'node' represents same XML element

6.170.3.37 void Arc::XMLNode::operator++ (void)

Convenience operator to switch to next element of same name. If there is no such node this object becomes invalid.

6.170.3.38 void Arc::XMLNode::operator- (void)

Convenience operator to switch to previous element of same name. If there is no such node this object becomes invalid.

6.170.3.39 XMLNode& Arc::XMLNode::operator= (const XMLNode & node)

Make instance refer to another XML node. Ownership is not inherited. Due to nature of XMLNode (p. 409) there should be no const here, but that does not fit into C++.

6.170.3.40 XMLNode& Arc::XMLNode::operator= (const std::string & content) [inline]

Sets textual content of node. All existing children nodes are discarded.

6.170.3.41 XMLNode& Arc::XMLNode::operator= (const char * content)

Sets textual content of node. All existing children nodes are discarded.

6.170.3.42 bool Arc::XMLNode::operator== (const char * str) [inline]

This operator is needed to avoid ambiguity

6.170.3.43 bool Arc::XMLNode::operator== (const std::string & str) [inline]

This operator is needed to avoid ambiguity

6.170.3.44 bool Arc::XMLNode::operator== (bool *val***)** [inline]

This operator is needed to avoid ambiguity

6.170.3.45 bool Arc::XMLNode::operator== (const XMLNode & node) [inline]

Returns true if 'node' represents same XML element

6.170.3.46 XMLNode Arc::XMLNode::operator[] (int n) const

Returns XMLNode (p. 409) instance representing n-th node in sequence of siblings of same name. It's main purpose is to be used to retrieve element in array of children of same name like node["name"][5]. This method should not be marked const because obtaining unrestricted XMLNode (p. 409) of child element allows modification of underlying XML tree. But in order to keep const in other places non-const-handling is passed to programmer. Otherwise C++ compiler goes nuts.

6.170.3.47 XMLNode Arc::XMLNode::operator[] (const std::string & name) const [inline]

Similar to previous method

6.170.3.48 XMLNode Arc::XMLNode::operator[] (const char * name) const

Returns XMLNode (p. 409) instance representing first child element with specified name. Name may be "namespace_prefix:name" or simply "name". In last case namespace is ignored. If such node does not exist invalid XMLNode (p. 409) instance is returned. This method should not be marked const because obtaining unrestricted XMLNode (p. 409) of child element allows modification of underlying XML tree. But in order to keep const in other places non-const-handling is passed to programmer. Otherwise C++ compiler goes nuts.

6.170.3.49 XMLNode Arc::XMLNode::Parent (void)

Get the parent node from any child node of the tree

6.170.3.50 XMLNodeList Arc::XMLNode::Path (const std::string & path)

Collects nodes corresponding to specified path. This is a convenience function to cover common use of XPath but without performance hit. Path is made of node_name[/node_name[...]] and is relative to current node. node_names are treated in same way as in operator[]. Returns all nodes which are represented by path.

6.170.3.51 std::string Arc::XMLNode::Prefix (void) const

Returns namespace prefix of XML node

6.170.3.52 bool Arc::XMLNode::ReadFromFile (const std::string & file_name)

Read XML document from file and associate it with this node

6.170.3.53 bool Arc::XMLNode::ReadFromStream (std::istream & in)

Read XML document from stream and associate it with this node

6.170.3.54 void Arc::XMLNode::Replace (const XMLNode & node)

Makes a copy of supplied XML node and makes this instance refere to it

6.170.3.55 bool Arc::XMLNode::Same (const XMLNode & node) [inline]

Returns true if 'node' represents same XML element - for bindings

6.170.3.56 bool Arc::XMLNode::SaveToFile (const std::string & file_name) const

Save string representation of node to file

6.170.3.57 bool Arc::XMLNode::SaveToStream (std::ostream & out) const

Save string representation of node to stream

6.170.3.58 void Arc::XMLNode::Set (const std::string & content) [inline]

Same as operator=. Used for bindings.

6.170.3.59 int Arc::XMLNode::Size (void) const

Returns number of children nodes

6.170.3.60 void Arc::XMLNode::Swap (XMLNode & node)

Swaps XML (sub)trees to this this and node refer. For XML subtrees this method is not anyhow different then using combination XMLNode (p. 409) tmp=*this; *this=node; node=tmp; But in case of either this or node owning XML document ownership is swapped too. And this is a main purpose of Swap() (p. 418) method.

6.170.3.61 bool Arc::XMLNode::Validate (const std::string & schema_file, std::string & err_msg)

XML schema validation against the schema file defined as argument

6.170.3.62 XMLNodeList Arc::XMLNode::XPathLookup (const std::string & xpathExpr, const NS & nsList)

Uses xPath to look up the whole xml structure, Returns a list of XMLNode (p. 409) points. The xpath-Expr should be like "//xx:child1/" which indicates the namespace and node that you would like to find; The nsList is the namespace the result should belong to (e.g. xx="uri:test"). Query is run on whole XML document but only the elements belonging to this XML subtree are returned.

6.170.4 Friends And Related Function Documentation

6.170.4.1 bool MatchXMLName (const XMLNode & node, const std::string & name) [friend]

Returns true if 'name' matches name of 'node'. If name contains prefix it's checked too

6.170.4.2 bool MatchXMLName (const XMLNode & node, const char * name) [friend]

Returns true if 'name' matches name of 'node'. If name contains prefix it's checked too

6.170.4.3 bool MatchXMLName (const XMLNode & node1, const XMLNode & node2) [friend]

Returns true if underlying XML elements have same names

6.170.4.4 bool MatchXMLNamespace (const XMLNode & node, const std::string & uri) [friend]

Returns true if 'namespace' matches 'node's namespace.

6.170.4.5 bool MatchXMLNamespace (const XMLNode & node, const char * uri) [friend]

Returns true if 'namespace' matches 'node's namespace.

6.170.4.6 bool MatchXMLNamespace (const XMLNode & node1, const XMLNode & node2) [friend]

Returns true if underlying XML elements belong to same namespaces

6.170.5 Field Documentation

6.170.5.1 bool Arc::XMLNode::is_owner_ [protected]

If true node is owned by this instance - hence released in destructor. Normally that may be true only for top level node of XML document.

6.170.5.2 bool Arc::XMLNode::is_temporary_ [protected]

This variable is for future

The documentation for this class was generated from the following file:

• XMLNode.h

6.171 Arc::XMLNodeContainer Class Reference

#include <XMLNode.h>

Public Member Functions

- XMLNodeContainer (void)
- XMLNodeContainer (const XMLNodeContainer &)
- XMLNodeContainer & operator= (const XMLNodeContainer &)
- void Add (const XMLNode &)
- void Add (const std::list< XMLNode > &)
- void AddNew (const XMLNode &)
- void AddNew (const std::list< XMLNode > &)
- int Size (void) const
- XMLNode operator[] (int)
- std::list< XMLNode > Nodes (void)

6.171.1 Detailed Description

Container for multiple XMLNode (p. 409) elements

6.171.2 Constructor & Destructor Documentation

6.171.2.1 Arc::XMLNodeContainer::XMLNodeContainer (void)

Default constructor

6.171.2.2 Arc::XMLNodeContainer::XMLNodeContainer (const XMLNodeContainer &)

Copy constructor. Add nodes from argument. Nodes owning XML document are copied using Add-New() (p. 421). Not owning nodes are linked using Add() (p. 420) method.

6.171.3 Member Function Documentation

6.171.3.1 void Arc::XMLNodeContainer::Add (const std::list< XMLNode > &)

Link multiple XML subtrees to container.

6.171.3.2 void Arc::XMLNodeContainer::Add (const XMLNode &)

Link XML subtree refered by node to container. XML tree must be available as long as this object is used.

6.171.3.3 void Arc::XMLNodeContainer::AddNew (const std::list< XMLNode > &)

Copy multiple XML subtrees to container.

6.171.3.4 void Arc::XMLNodeContainer::AddNew (const XMLNode &)

Copy XML subtree referenced by node to container. After this operation container refers to independent XML document. This document is deleted when container is destroyed.

6.171.3.5 std::list<XMLNode> Arc::XMLNodeContainer::Nodes (void)

Returns all stored nodes.

6.171.3.6 XMLNodeContainer& Arc::XMLNodeContainer::operator= (const XMLNodeContainer &)

Same as copy constructor with current nodes being deleted first.

6.171.3.7 XMLNode Arc::XMLNodeContainer::operator[] (int)

Returns n-th node in a store.

6.171.3.8 int Arc::XMLNodeContainer::Size (void) const

Return number of refered/stored nodes.

The documentation for this class was generated from the following file:


• XMLNode.h

6.172 Arc::XMLSecNode Class Reference

Extends XMLNode (p. 409) class to support XML security operation.

#include <XMLSecNode.h>

Inheritance diagram for Arc::XMLSecNode::



Public Member Functions

- XMLSecNode (XMLNode &node)
- void AddSignatureTemplate (const std::string &id_name, const SignatureMethod sign_method, const std::string &incl_namespaces=""")
- bool SignNode (const std::string &privkey file, const std::string &cert file)
- bool VerifyNode (const std::string &id_name, const std::string &ca_file, const std::string &ca_path, bool verify_trusted=true)
- bool EncryptNode (const std::string &cert_file, const SymEncryptionType encrpt_type)
- bool DecryptNode (const std::string &privkey_file, XMLNode &decrypted_node)

6.172.1 Detailed Description

Extends XMLNode (p. 409) class to support XML security operation.

All XMLNode (p. 409) methods are exposed by inheriting from XMLNode (p. 409). XMLSecNode (p. 422) itself does not own node, instead it uses the node from the base class XMLNode (p. 409).

6.172.2 Constructor & Destructor Documentation

6.172.2.1 Arc::XMLSecNode::XMLSecNode (XMLNode & node)

Create a object based on an XMLNode (p. 409) instance.

6.172.3 Member Function Documentation

6.172.3.1 void Arc::XMLSecNode::AddSignatureTemplate (const std::string & id_name, const SignatureMethod sign_method, const std::string & incl_namespaces = "")

Add the signature template for later signing.

Parameters:

id_name The identifier name under this node which will be used for the <Signature> to refer to.

sign_method The sign method for signing. Two options now, RSA_SHA1, DSA_SHA1

6.172.3.2 bool Arc::XMLSecNode::DecryptNode (const std::string & privkey_file, XMLNode & decrypted_node)

Decrypt the <xenc:EncryptedData/> under this node, the decrypted node will be output in the second argument of DecryptNode method. And the <xenc:EncryptedData/> under this node will be removed after decryption.

Parameters:

privkey_file The private key file, which is used for decrypting
decrypted_node Output the decrypted node

6.172.3.3 bool Arc::XMLSecNode::EncryptNode (const std::string & cert_file, const SymEncryptionType encrpt_type)

Encrypt this node, after encryption, this node will be replaced by the encrypted node

Parameters:

cert_file The certificate file, the public key parsed from this certificate is used to encrypted the
symmetric key, and then the symmetric key is used to encrypted the node

encrpt_type The encryption type when encrypting the node, four option in SymEncryptionType verify_trusted Verify trusted certificates or not. If set to false, then only the signature will be checked (by using the public key from KeyInfo).

6.172.3.4 bool Arc::XMLSecNode::SignNode (const std::string & privkey_file, const std::string & cert file)

Sign this node (identified by id_name).

Parameters:

6.172.3.5 bool Arc::XMLSecNode::VerifyNode (const std::string & id_name, const std::string & ca_file, const std::string & ca_path, bool verify_trusted = true)

Verify the signature under this node

Parameters:

id_name The id of this node, which is used for identifying the node

 $\it ca_file~$ The CA file which used as trused certificate when verify the certificate in the <KeyInfo> part of <Signature>

ca_path The CA directory; either ca_file or ca_path should be set.

The documentation for this class was generated from the following file:

· XMLSecNode.h

424	Hosting Environment (Daemon) Data Structure Documentation

Chapter 7

Hosting Environment (Daemon) File Documentation

7.1 URL.h File Reference

Class to hold general URL's.

```
#include <iostream>
#include <list>
#include <map>
#include <string>
```

Namespaces

• namespace Arc

Data Structures

- class Arc::URL
- class Arc::URLLocation

Class to hold a resolved URL location.

• class Arc::PathIterator

Class to iterate through elements of path.

Functions

• std::list< URL > Arc::ReadURLList (const URL &urllist)

7.1.1 Detailed Description

Class to hold general URL's.

The URL is split into protocol, hostname, port and path. This class tries to follow RFC 3986 for spliting URLs at least for protocol + host part. It also accepts local file paths which are converted to file:path. Usual system dependant file paths are supported. Relative paths are converted to absolute ones by prepending them with current working directory path. File path can't start from # symbol (why?). If string representation of URL starts from '@' then it is treated as path to file containing list of URLs. Simple URL is parsed in following way: [protocol:][//[username:passwd@][host][:port]][;urloptions[;...]][/path[?httpoption[&...]][:metadata The 'protocol' and 'host' parts are treated as case-insensitive and to avoid confusion are converted to lowercase in constructor. Note that 'path' is always converted to absolute path in constructor. Meaning of 'absolute' may depend upon URL type. For generic URL and local POSIX file paths that means path starts from / like /path/to/file For Windows paths absolute path may look like C: It is important to note that path still can be empty. For referencing local file using absolute path on POSIX filesystem one may use either file:///path/to/file or file:/path/to/file Relative path will look like file:to/file For local Windows files possible URLs are file:C:\path\to\file file:to URLs representing LDAP resources have different structure of options following 'path' part ldap://host[:port][;urloptions[;...]][/path[?attributes[?scope[?filter]]]] For LDAP URLs paths are converted from /key1=value1/.../keyN=valueN notation to key-N=valueN,..., key1=value1 and hence path does not contain leading /. If LDAP URL initially had path in second notation leading / is treated as separator only and is stripped. URLs of indexing services optionally may have locations specified before 'host' part protocol://[location[;location[;...]]@][host][:port]... The structure of 'location' element is protocol specific.

Index

~AutoPointer	Arc::SubmitterLoader, 344
Arc::AutoPointer, 57	\sim TargetRetrieverLoader
~BrokerLoader	Arc::TargetRetrieverLoader, 351
Arc::BrokerLoader, 61	\sim URLLocation
~Counter	Arc::URLLocation, 360
Arc::Counter, 85	\sim WSAEndpointReference
∼DataBuffer	Arc::WSAEndpointReference, 394
Arc::DataBuffer, 99	~X509Token
~DataMover	Arc::X509Token, 408
Arc::DataMover, 107	\sim XMLNode
~DataPoint	Arc::XMLNode, 412
Arc::DataPoint, 113	
~DataSpeed	Abandon
Arc::DataSpeed, 140	Arc::Run, 301
~Database	AcceptsMeta
Arc::Database, 95	Arc::DataPoint, 113
~FileLock	Arc::DataPointDirect, 125
Arc::FileLock, 184	Arc::DataPointIndex, 132
~IntraProcessCounter	ACCESS_LATENCY_LARGE
Arc::IntraProcessCounter, 201	Arc::DataPoint, 113
~JobControllerLoader	ACCESS_LATENCY_SMALL
Arc::JobControllerLoader, 208	Arc::DataPoint, 113
~Loader	ACCESS_LATENCY_ZERO
Arc::Loader, 212	Arc::DataPoint, 113
~Logger	Acquire
Arc::Logger, 219	Arc::DelegationConsumer, 148
∼MCCLoader	Arc::InformationContainer, 193
Arc::MCCLoader, 235	Action
∼Message	Arc::WSAHeader, 397
Arc::Message, 239	Add
∼PayloadRaw	Arc::MessageContext, 247
Arc::PayloadRaw, 260	Arc::XMLNodeContainer, 420
∼PayloadStream	add
Arc::PayloadStream, 265	Arc::DataBuffer, 99
~Plexer	Arc::MessageAttributes, 242
Arc::Plexer, 277	Arc::SoftwareRequirement, 333
\sim RegularExpression	AddBartender
Arc::RegularExpression, 292	Arc::UserConfig, 365
∼Run	AddCADir
Arc::Run, 300	<pre>Arc::BaseConfig, 59</pre>
\sim SAMLToken	AddCAFile
Arc::SAMLToken, 305	Arc::BaseConfig, 59
\sim SOAPMessage	AddCertificate
Arc::SOAPMessage, 321	Arc::BaseConfig, 59
\sim SubmitterLoader	AddChain

7 MOMOT	7
Arc::VOMSTrustList, 393	Arc, 36
AddCheckSumObject	allocated_
Arc::DataPoint, 113	Arc::WSRF, 400
Arc::DataPointDirect, 125	ApplicationEnvironments
Arc::DataPointIndex, 132	Arc::ExecutionTarget, 173
addDestination	ApplyToConfig
Arc::Logger, 219	Arc::UserConfig, 367
AddDN	approveCSR
Arc::FileCache, 178	Arc::OAuthConsumer, 256
AddIndexServer	Arc, 17
Arc::TargetGenerator, 347	addVOMSAC, 36
AddJob	AttrConstIter, 29
Arc::TargetGenerator, 347	AttrIter, 29
AddLocation	AttrMap, 29
Arc::DataPoint, 114	BUSY_ERROR, 30
Arc::DataPointDirect, 125	ContentFromPayload, 38
Arc::DataPointIndex, 132	convert_to_rdn, 34
AddNew	CreateThreadFunction, 34
Arc::XMLNodeContainer, 420	createVOMSAC, 35
AddOverlay	CredentialLogger, 40
Arc::BaseConfig, 59	DirCreate, 32
AddPluginsPath	DirDelete, 32
Arc::BaseConfig, 59	DirOpen, 31
addPolicy	ETERNAL, 39
ArcSec::Evaluator, 165	FileCopy, 31
ArcSec::Policy, 287	FileOpen, 31
AddPrivateKey	FileStat, 31, 32
Arc::BaseConfig, 59	final_xmlsec, 38
AddProxy	GENERIC_ERROR, 30
Arc::BaseConfig, 59	get_cert_str, 38
AddRegex	get_key_from_certfile, 38
Arc::VOMSTrustList, 393	get_key_from_certstr, 39
addRegistrar	get_key_from_keyfile, 38
Arc::InfoRegisterContainer, 190	get_key_from_keystr, 38
addRequestItem	get_node, 39
ArcSec::Request, 295	get_plugin_instance, 29
Address	get_property, 37
Arc::WSAEndpointReference, 395	GetEnv, 34
AddSecHandler	GUID, 32
Arc::ClientSOAP, 71	HandleOpenSSLError, 37
Arc::MCC, 228	HISTORIC, 39
Arc::Service, 317	init_xmlsec, 38
AddService	istring_to_level, 32
Arc::TargetGenerator, 347	level_to_string, 33
addService	<pre>load_key_from_certfile, 39</pre>
Arc::InfoRegisterContainer, 190	load_key_from_certstr, 39
Arc::InfoRegistrar, 192	load_key_from_keyfile, 39
AddServices	load_trusted_cert_file, 39
Arc::UserConfig, 365, 366	load_trusted_cert_str, 39
AddSignatureTemplate	load_trusted_certs, 39
Arc::XMLSecNode, 422	LogLevel, 30
AddTarget	lower, 33
Arc::TargetGenerator, 347	MatchXMLName, 35
addVOMSAC	MatchXMLNamespace, 35
444 V 0110110	racemminamespace, 55

old_level_to_level, 33	Arc::AutoPointer
OpenSSLInit, 37	\sim AutoPointer, 57
operator<<, 30, 32	AutoPointer, 57
parseVOMSAC, 36, 37	operator *, 57
PARSING_ERROR, 30	operator bool, 57
passphrase_callback, 38	operator T *, 58
plugins_table_name, 40	operator!, 58
PROTOCOL_RECOGNIZED_ERROR, 30	operator->, 58
ReadURLList, 34	Arc::BaseConfig, 59
SESSION_CLOSE, 30	Arc::BaseConfig
SetEnv, 34	AddCADir, 59
STATUS_OK, 30	AddCAFile, 59
StatusKind, 30	AddCertificate, 59
StrError, 35	AddOverlay, 59
string, 37	AddPluginsPath, 59
string_to_level, 32, 33	AddPrivateKey, 59
stringto, 33	AddProxy, 59
strip, 34	GetOverlay, 60
thread_stacksize, 40	MakeConfig, 60
TimeFormat, 30	Arc::BrokerLoader, 61
TimeStamp, 31	Arc::BrokerLoader
tokenize, 34	~BrokerLoader, 61
tostring, 33	BrokerLoader, 61
trim, 34	GetBrokers, 61
UNKNOWN_SERVICE_ERROR, 30	load, 61
UnsetEnv, 35	Arc::CacheParameters, 63
upper, 33	Arc::ChainContext, 64
uri_unescape, 34	Arc::ChainContext
UUID, 32	operator PluginsFactory *, 64
VOMSDecode, 37	Arc::CheckSum, 65
WSAFault, 30	Arc::CheckSumAny, 66
WSAFaultAssign, 38	Arc::CIStringValue, 67
WSAFaultExtract, 38	Arc::CIStringValue
WSAFaultInvalidAddressingHeader, 30	CIStringValue, 67
WSAFaultUnknown, 30	equal, 68
Arc::Adler32Sum, 43	operator bool, 68
	_
Arc::ApplicationEnvironment, 45	Arc::ClientHTTP, 69
Arc::ArcLocation, 46	Arc::ClientInterface, 70
Arc::ArcLocation	Arc::ClientSOAP, 71
Get, 46	Arc::ClientSOAP
GetPlugins, 46	AddSecHandler, 71
Init, 46	ClientSOAP, 71
Arc::AttributeIterator, 49	GetEntry, 71
Arc::AttributeIterator	Load, 72
AttributeIterator, 49, 50	process, 72
current_, 51	Arc::ClientTCP, 73
end_, 51	Arc::Config, 76
hasMore, 50	Config, 76, 77
key, 50	getFileName, 77
MessageAttributes, 51	parse, 77
operator *, 50	print, 77
operator++, 50, 51	save, 77
operator->, 51	setFileName, 77
Arc::AutoPointer, 57	Arc::ConfusaCertHandler, 78

Arc::ConfusaCertHandler	close, 96
ConfusaCertHandler, 78	connect, 96
createCertRequest, 78	Database, 95
getCertRequestB64, 78	enable_ssl, 96
Arc::ConfusaParserUtils, 79	isconnected, 96
Arc::ConfusaParserUtils	shutdown, 96
destroy_doc, 79	Arc::DataBuffer, 98
evaluate_path, 79	Arc::DataBuffer
extract_body_information, 79	∼DataBuffer, 99
get_doc, 79	add, 99
handle_redirect_step, 79	buffer_size, 99
urlencode, 80	checksum_object, 100
urlencode_params, 80	checksum_valid, 100
Arc::CountedPointer, 81	DataBuffer, 99
Arc::CountedPointer	eof_position, 100
operator *, 81	eof_read, 100
operator bool, 81	eof_write, 100
operator T *, 81	error, 100
operator!, 81	error_read, 100
operator->, 82	error_transfer, 101
Arc::Counter, 83	error_write, 101
~Counter, 85	for_read, 101
cancel, 85	for_write, 101
changeExcess, 85	is_notwritten, 102
changeLimit, 85	is_read, 102
Counter, 85	is_written, 102, 103
CounterTicket, 89	operator bool, 103
ExpirationReminder, 89	operator[], 103
extend, 86	set, 103
getCounterTicket, 86	speed, 104
getCurrentTime, 86	wait_any, 103
getExcess, 87	wait_eof, 103
getExpirationReminder, 87	wait_eof_read, 103
getExpiryTime, 87	wait_eof_write, 103
getLimit, 87	wait_read, 104
getValue, 88	wait_used, 104
IDType, 85	wait_write, 104
reserve, 88	Arc::DataCallback, 105
setExcess, 88	Arc::DataHandle, 106
setLimit, 89	Arc::DataMover, 107
Arc::CounterTicket, 90	Arc::DataMover
Arc::CounterTicket	∼DataMover, 107
cancel, 91	checks, 108
Counter, 91	DataMover, 107
CounterTicket, 90	force_to_meta, 108
extend, 91	passive, 108
isValid, 91	retry, 108
Arc::CRC32Sum, 92	secure, 108
Arc::CredentialError, 93	set_default_max_inactivity_time, 108
Arc::CredentialError	set_default_min_average_speed, 108
CredentialError, 93	set_default_min_speed, 108
Arc::CredentialStore, 94	Transfer, 109
Arc::Database, 95	verbose, 109, 110
~Database, 95	Arc::DataPoint, 111
,	,

ACCECC INTENCY INDCE 112	RemoveLocations, 119
ACCESS_LATENCY_LARGE, 113	Resolve, 120
ACCESS_LATENCY_SMALL, 113	•
ACCESS_LATENCY_ZERO, 113	SetAccessLatency, 120
Arc::DataPoint	SetAdditionalChecks, 120
~DataPoint, 113	SetCheckSum, 120
AcceptsMeta, 113	SetCreated, 120
AddCheckSumObject, 113	SetMeta, 120
AddLocation, 114	SetSecure, 121
BufNum, 114	SetSize, 121
BufSize, 114	SetTries, 121
Cache, 114	SetValid, 121
Check, 114	SortLocations, 121
CheckCheckSum, 114	StartReading, 121
CheckCreated, 114	StartWriting, 122
CheckSize, 114	StopReading, 122
CheckValid, 115	StopWriting, 122
CompareLocationMetadata, 115	str, 122
CompareMeta, 115	Unregister, 122
CurrentLocation, 115	valid_url_options, 123
CurrentLocationMetadata, 115	WriteOutOfOrder, 123
DataPoint, 113	Arc::DataPointDirect, 124
DataPointAccessLatency, 113	Arc::DataPointDirect
DefaultCheckSum, 115	AcceptsMeta, 125
GetAccessLatency, 115	AddCheckSumObject, 125
GetAdditionalChecks, 115	AddLocation, 125
GetCheckSum, 116	BufNum, 125
GetCreated, 116	BufSize, 125
GetFailureReason, 116	CompareLocationMetadata, 126
GetSecure, 116	CurrentLocation, 126
GetSize, 116	CurrentLocationMetadata, 126
GetTries, 116	GetAdditionalChecks, 126
GetURL, 116	GetSecure, 126
GetUserConfig, 116	HaveLocations, 126
GetValid, 116	IsIndex, 126
HaveLocations, 116	LastLocation, 126
IsIndex, 117	Local, 127
LastLocation, 117	LocationValid, 127
ListFiles, 117	NextLocation, 127
Local, 117	Passive, 127
LocationValid, 117	PostRegister, 127
NextLocation, 117	PreRegister, 127
NextTry, 117	PreUnregister, 128
operator bool, 118	ProvidesMeta, 128
operator!, 118	Range, 128
Passive, 118	ReadOutOfOrder, 128
PostRegister, 118	Registered, 128
PreRegister, 118	RemoveLocation, 129
PreUnregister, 118	RemoveLocations, 129
ProvidesMeta, 119	Resolve, 129
Range, 119	SetAdditionalChecks, 129
ReadOutOfOrder, 119	SetSecure, 129
Registered, 119	SortLocations, 129
Remove, 119	Unregister, 130
RemoveLocation, 119	WriteOutOfOrder, 130
,	

Amari Data Daint Indon 121	act min aread 1/1
Arc::DataPointIndex, 131	set_min_speed, 141
Arc::DataPointIndex	set_progress_indicator, 141
AcceptsMeta, 132	transfer, 142
AddCheckSumObject, 132	transferred_size, 142
AddLocation, 132	verbose, 142
BufNum, 132	Arc::DataStatus, 143
BufSize, 132	CacheError, 144
Check, 133	CheckError, 144
CompareLocationMetadata, 133	CredentialsExpiredError, 144
CurrentLocation, 133	DeleteError, 144
CurrentLocationMetadata, 133	InconsistentMetadataError, 144
GetAccessLatency, 133	IsReadingError, 144
GetAdditionalChecks, 133	IsWritingError, 144
GetSecure, 133	ListError, 144
HaveLocations, 134	LocationAlreadyExistsError, 144
IsIndex, 134	NoLocationError, 144
LastLocation, 134	NotInitializedError, 144
Local, 134	NotSupportedForDirectDataPointsError,
LocationValid, 134	144
NextLocation, 134	PostRegisterError, 144
Passive, 134	PreRegisterError, 144
ProvidesMeta, 134	ReadAcquireError, 144
Range, 135	ReadError, 144
ReadOutOfOrder, 135	ReadResolveError, 144
Registered, 135	ReadStartError, 144
Remove, 135	ReadStopError, 144
RemoveLocation, 135	StageError, 144
RemoveLocations, 135	Success, 144
SetAdditionalChecks, 135	SystemError, 144
SetCheckSum, 136	TransferError, 144
SetMeta, 136	UnimplementedError, 144
SetSecure, 136	UnknownError, 144
SetSize, 136	UnregisterError, 144
SetTries, 136	WriteAcquireError, 144
SortLocations, 136	WriteError, 144
StartReading, 137	WriteResolveError, 144
StartWriting, 137	WriteStartError, 144
StopReading, 137	WriteStopError, 144
StopWriting, 137	Arc::DataStatus
WriteOutOfOrder, 137	DataStatusType, 144
Arc::DataSpeed, 139	Arc::DelegationConsumer, 147
Arc::DataSpeed	Arc::DelegationConsumer
\sim DataSpeed, 140	Acquire, 148
DataSpeed, 139	Backup, 148
get_max_inactivity_time, 140	DelegationConsumer, 147
hold, 140	Generate, 148
max_inactivity_time_failure, 140	ID, 148
min_average_speed_failure, 140	LogError, 148
min_speed_failure, 140	Request, 148
reset, 140	Restore, 148
set_base, 141	Arc::DelegationConsumerSOAP, 149
set_max_data, 141	Arc::DelegationConsumerSOAP
set_max_inactivity_time, 141	DelegateCredentialsInit, 149
set_min_average_speed, 141	DelegatedToken, 149
	, .

DelegationConsumerSOAP, 149	operator bool, 179
UpdateCredentials, 150	operator==, 179
Arc::DelegationContainerSOAP, 151	Release, 179
Arc::DelegationContainerSOAP	SetValid, 180
context_lock_, 151	Start, 180
DelegateCredentialsInit, 151	Stop, 180
DelegatedToken, 151	StopAndDelete, 180
max_duration_, 151	Arc::FileInfo, 183
max_size_, 152	Arc::FileLock, 184
max_usage_, 152	Arc::FileLock
restricted_, 152	\sim FileLock, 184
UpdateCredentials, 151	FileLock, 184
Arc::DelegationProvider, 153	operator bool, 184
Arc::DelegationProvider	operator!, 184
Delegate, 153	Arc::InfoCache, 187
DelegationProvider, 153	Arc::InfoCache
Arc::DelegationProviderSOAP, 155	InfoCache, 187
Arc::DelegationProviderSOAP	Arc::InfoFilter, 188
DelegateCredentialsInit, 156	Arc::InfoFilter
DelegatedToken, 156	Filter, 188
DelegationProviderSOAP, 155	InfoFilter, 188
ID, 156	Arc::InfoRegister, 189
UpdateCredentials, 156	Arc::InfoRegisterContainer, 190
Arc::ExecutionTarget, 171	Arc::InfoRegisterContainer
Arc::ExecutionTarget	addRegistrar, 190
ApplicationEnvironments, 173	addService, 190
ComputingShareName, 173	removeService, 190
ExecutionTarget, 171	Arc::InfoRegisters, 191
GetSubmitter, 172	Arc::InfoRegisters
MaxDiskSpace, 173	InfoRegisters, 191
MaxMainMemory, 173	Arc::InfoRegistrar, 192
MaxVirtualMemory, 173	Arc::InfoRegistrar
OperatingSystem, 173	addService, 192
operator=, 172	registration, 192
Print, 172	removeService, 192
Update, 172	Arc::InformationContainer, 193
Arc::ExpirationReminder, 174	Arc::InformationContainer
Arc::ExpirationReminder	Acquire, 193
Counter, 175	Assign, 193
getExpiryTime, 174	doc_, 194
getReservationID, 174	Get, 194
operator<, 174	InformationContainer, 193
Arc::FileCache, 176	Arc::InformationInterface, 195
Arc::FileCache	Arc::InformationInterface
AddDN, 178	Get, 195
CheckCreated, 178	InformationInterface, 195
CheckDN, 178	lock_, 196
CheckValid, 178	Arc::InformationRequest, 197
Copy, 178	Arc::InformationRequest
File, 179	InformationRequest, 197
FileCache, 177, 178	SOAP, 197
GetCreated, 179	Arc::InformationResponse, 199
GetValid, 179	Arc::InformationResponse
Link, 179	InformationResponse, 199
TITIL, III	Intormacronnesponse, 133

Result, 199	getRootLogger, 219
Arc::IntraProcessCounter, 200	getThreshold, 219
Arc::IntraProcessCounter	Logger, 218
\sim IntraProcessCounter, 201	msg, 219, 220
cancel, 201	removeDestinations, 220
changeExcess, 201	setThreshold, 220
changeLimit, 201	Arc::LogMessage, 221
extend, 201	Arc::LogMessage
getExcess, 202	getLevel, 222
getLimit, 202	Logger, 222
getValue, 202	LogMessage, 221
IntraProcessCounter, 200	operator<<, 222
reserve, 203	setIdentifier, 222
setExcess, 203	Arc::LogStream, 223
setLimit, 203	Arc::LogStream
Arc::Job, 205	log, 224
Job, 205	LogStream, 223
Print, 205	Arc::MCC, 227
Arc::JobController, 206	AddSecHandler, 228
Arc::JobController	logger, 229
FillJobStore, 206	MCC, 228
Migrate, 206	Next, 228
PrintJobStatus, 207	next_, 229
Arc::JobControllerLoader, 208	process, 228
Arc::JobControllerLoader	ProcessSecHandlers, 228
\sim JobControllerLoader, 208	sechandlers_, 229
GetJobControllers, 208	Unlink, 228
JobControllerLoader, 208	Arc::MCC_Status, 230
load, 208	getExplanation, 230
Arc::JobState, 210	getKind, 230
Arc::JobSupervisor, 211	getOrigin, 231
Arc::JobSupervisor	isOk, 231
GetJobControllers, 211	MCC_Status, 230
JobSupervisor, 211	operator bool, 231
Arc::Loader, 212	operator std::string, 231
\sim Loader, 212	operator!, 231
factory_, 212	Arc::MCCInterface, 233
Loader, 212	process, 233
Arc::LogDestination, 213	Arc::MCCLoader, 235
Arc::LogDestination	\sim MCCLoader, 235
log, 213	MCCLoader, 235
LogDestination, 213	operator[], 236
Arc::LogFile, 215	Arc::MD5Sum, 237
Arc::LogFile	Arc::Message, 238
log, 216	∼Message, 239
LogFile, 215	Attributes, 239
operator bool, 216	Auth, 239
operator!, 216	AuthContext, 239
setBackups, 216	Context, 239
setMaxSize, 216	Message, 239
setReopen, 216	operator=, 239
Arc::Logger, 218	Payload, 240
~Logger, 219	Arc::MessageAttributes, 241
addDestination, 219	Arc::MessageAttributes

add, 242	Arc::PathIterator
attributes_, 243	operator *, 258
count, 242	operator bool, 258
get, 242	operator++, 258
getAll, 242	operator-, 258
MessageAttributes, 241	PathIterator, 258
remove, 243	Rest, 258
removeAll, 243	Arc::PayloadRaw, 260
set, 243	Arc::PayloadRaw
Arc::MessageAuth, 244	\sim PayloadRaw, 260
Arc::MessageAuth	Buffer, 260
Export, 244	BufferPos, 260
Filter, 244	BufferSize, 261
get, 244	PayloadRaw, 260
operator[], 245	Size, 261
remove, 245	Arc::PayloadRawInterface, 262
set, 245	Arc::PayloadRawInterface
Arc::MessageAuthContext, 246	Buffer, 262
Arc::MessageContext, 247	BufferPos, 262
Arc::MessageContext	BufferSize, 262
Add, 247	Content, 263
Arc::MessageContextElement, 248	Insert, 263
Arc::MessagePayload, 249	operator[], 263
Arc::ModuleDesc, 250	Size, 263
Arc::ModuleManager, 251	Truncate, 263
Arc::ModuleManager	Arc::PayloadSOAP, 264
find, 251	Arc::PayloadSOAP
findLocation, 251	PayloadSOAP, 264
load, 252	Arc::PayloadStream, 265
makePersistent, 252	Arc::PayloadStream
ModuleManager, 251	~PayloadStream, 265
reload, 252	Get, 266
setCfg, 252	handle , 267
unload, 252	Limit, 266
Arc::MultiSecAttr, 253	operator bool, 266
Arc::MultiSecAttr	operator!, 266
Export, 253	-
-	PayloadStream, 265
operator bool, 253 Arc::MySQLDatabase, 254	Pos, 266
	Put, 266, 267 seekable_, 267
Arc::MySQLDatabase	Size, 267
close, 254	
connect, 254	Timeout, 267
enable_ssl, 254	Arc::PayloadStreamInterface, 268
isconnected, 255	Arc::PayloadStreamInterface
shutdown, 255	Get, 268, 269
Arc::OAuthConsumer, 256	Limit, 269
Arc::OAuthConsumer	operator bool, 269
approveCSR, 256	operator!, 269
OAuthConsumer, 256	Pos, 269
parseDN, 256	Put, 269
processLogin, 256	Size, 270
pushCSR, 256	Timeout, 270
storeCert, 257	Arc::PayloadWSRF, 271
Arc::PathIterator, 258	Arc::PayloadWSRF

PayloadWSRF, 271	Running, 302
Arc::Plexer, 277	Start, 302
\sim Plexer, 277	Wait, 302, 303
logger, 278	WriteStdin, 303
Next, 278	Arc::SAMLToken, 304
Plexer, 277	\sim SAMLToken, 305
process, 278	Authenticate, 306
Arc::PlexerEntry, 279	operator bool, 306
Arc::Plugin, 280	SAMLToken, 305
Arc::PluginArgument, 281	SAMLVersion, 305
Arc::PluginArgument	Arc::SecAttr, 307
get_factory, 281	Arc::SecAttr
get_module, 281	ARCAuth, 308
Arc::PluginDesc, 282	Export, 308
Arc::PluginDescriptor, 283	GACL, 308
Arc::PluginsFactory, 284	Import, 308
Arc::PluginsFactory	operator bool, 308
load, 284	operator!=, 308
PluginsFactory, 284	operator==, 308
report, 284	SAML, 309
scan, 284	SecAttr, 307
TryLoad, 285	XACML, 309
Arc::RegisteredService, 291	Arc::SecAttrFormat, 310
Arc::RegisteredService	Arc::SecAttrValue, 311
RegisteredService, 291	Arc::SecAttrValue
Arc::RegularExpression, 292	operator bool, 311
Arc::RegularExpression	operator!=, 311
~RegularExpression, 292	operator==, 311
getPattern, 292	Arc::Service, 316
hasPattern, 292	AddSecHandler, 317
isOk, 293	getID, 317
match, 293	logger, 317
operator=, 293	ProcessSecHandlers, 317
RegularExpression, 292	RegistrationCollector, 317
Arc::Run, 300	sechandlers_, 317
~Run, 300	Service, 317
Abandon, 301	Arc::SimpleCondition, 319
AssignStderr, 301	Arc::SimpleCondition
AssignStdin, 301	broadcast, 319
AssignStdout, 301	lock, 319
AssignWorkingDirectory, 301	reset, 319
CloseStderr, 301	signal, 319
CloseStdin, 301	signal_nonblock, 319
CloseStdout, 301	unlock, 319
KeepStderr, 301	wait, 320
KeepStdin, 301	wait_nonblock, 320
KeepStdout, 302	Arc::SOAPMessage, 321
Kill, 302	~SOAPMessage, 321
operator bool, 302	Attributes, 321
operator!, 302	Payload, 321, 322
ReadStderr, 302	SOAPMessage, 321
ReadStdout, 302	Arc::Software, 323
Result, 302	ComparisonOperator, 324
Run, 300	ComparisonOperatorEnum, 324
Kuii, 500	compartsonoperacorenum, 324

convert, 326	GetTargets, 348
empty, 326	ModifyFoundTargets, 348
EQUAL, 324	PrintTargetInfo, 348
getFamily, 326	ServiceCounter, 348
getName, 326	TargetGenerator, 346
getVersion, 326	Arc::TargetRetriever, 349
GREATERTHAN, 325	Arc::TargetRetriever
GREATERTHANOREQUAL, 325	GetTargets, 350
LESSTHAN, 325	TargetRetriever, 349
LESSTHANOREQUAL, 325	Arc::TargetRetrieverLoader, 351
NOTEQUAL, 324	Arc::TargetRetrieverLoader
operator std::string, 326	\sim TargetRetrieverLoader, 351
operator!=, 327	GetTargetRetrievers, 351
operator(), 327	load, 351
operator<, 327	TargetRetrieverLoader, 351
operator<<, 330	Arc::ThreadRegistry, 353
operator<=, 328	Arc::ThreadRegistry
operator==, 328	RegisterThread, 353
operator>, 328	UnregisterThread, 353
operator>=, 329	WaitForExit, 353
Software, 325	WaitOrCancel, 353
toString, 329	Arc::Time, 354
VERSIONTOKENS, 330	GetFormat, 355
Arc::SoftwareRequirement, 331	GetTime, 355
Arc::SoftwareRequirement	operator std::string, 355
add, 333	operator!=, 355
clear, 333	operator+, 355
empty, 333	operator-, 355
getComparisonOperatorList, 334	operator<, 355
getSoftwareList, 334	operator<=, 355
isRequiringAll, 334	operator=, 355, 356
isResolved, 334	operator==, 356
isSatisfied, 335, 336	operator>, 356
operator=, 336	operator>=, 356
selectSoftware, 336, 337	SetFormat, 356
setRequirement, 338	SetTime, 356
SoftwareRequirement, 332	str, 356
Arc::Submitter, 343	Time, 354, 355
Migrate, 343	Arc::URLLocation, 359
Submit, 343	~URLLocation, 360
Arc::SubmitterLoader, 344	fullstr, 360
Arc::SubmitterLoader	Name, 360
~SubmitterLoader, 344	name, 360
GetSubmitters, 344	str, 360
load, 344	URLLocation, 359
SubmitterLoader, 344	Arc::UserConfig, 361
Arc::TargetGenerator, 346	Arc::UserConfig
Arc::TargetGenerator	AddBartender, 365
AddIndexServer, 347	AddServices, 365, 366
AddJob, 347	ApplyToConfig, 367
AddService, 347	ARCUSERDIRECTORY, 387
AddTarget, 347	Bartender, 367
FoundJobs, 347	Broker, 368
FoundTargets, 347	CACertificatePath, 369

GNG-orbitished Discrete and 270	205
CACertificatesDirectory, 370	operator=, 395
CertificateLifeTime, 370, 371	ReferenceParameters, 395
CertificatePath, 371	WSAEndpointReference, 394
ClearRejectedServices, 372	Arc::WSAHeader, 396
ClearSelectedServices, 372, 373	Action, 397
CredentialsFound, 373	Check, 397
DEFAULT_BROKER, 387	FaultTo, 397
DEFAULT_TIMEOUT, 387	From, 397
DEFAULTCONFIG, 388	header_allocated_, 398
EXAMPLECONFIG, 388	MessageID, 397
GetRejectedServices, 373	NewReferenceParameter, 397
GetSelectedServices, 373	operator XMLNode, 397
IdPName, 374	ReferenceParameter, 397, 398
InitializeCredentials, 374	RelatesTo, 398
JobListFile, 376	RelationshipType, 398
KeyPassword, 376, 377	ReplyTo, 398
KeyPath, 377	To, 398
KeySize, 378	WSAHeader, 396
LoadConfigurationFile, 379	Arc::WSRF, 399
operator bool, 380	allocated_, 400
operator!, 380	operator bool, 400
OverlayFile, 380, 381	set_namespaces, 400
Password, 381	SOAP, 400
ProxyPath, 382	valid_, 400
SaveToFile, 382	WSRF, 399
SLCS, 383	Arc::WSRFBaseFault, 401
StoreDirectory, 383	Arc::WSRFBaseFault
SYSCONFIG, 388	set_namespaces, 401
SYSCONFIGARCLOC, 388	WSRFBaseFault, 401
Timeout, 384	Arc::WSRP, 403
UserConfig, 364, 365	set_namespaces, 403
UserName, 385	WSRP, 403
UtilsDirPath, 385	Arc::WSRPFault, 405
Verbosity, 386	WSRPFault, 405
VOMSServerPath, 386, 387	Arc::WSRPResourcePropertyChangeFailure,
Arc::UsernameToken, 389	406
Arc::UsernameToken	Arc::WSRPResourcePropertyChangeFailure
Authenticate, 390	WSRPResourcePropertyChangeFailure,
operator bool, 390	406
PasswordType, 389	Arc::X509Token, 407
Username, 390	~X509Token, 408
UsernameToken, 389, 390	Authenticate, 408
Arc::UserSwitch, 391	operator bool, 408
Arc::VOMSTrustList, 392	X509Token, 407
Arc::VOMSTrustList	X509TokenType, 407
AddChain, 393	Arc::XMLNode, 409
AddRegex, 393	~XMLNode, 412
VOMSTrustList, 392	Attribute, 412
Arc::WSAEndpointReference, 394	AttributesSize, 412
Arc::WSAEndpointReference	Child, 412
~WSAEndpointReference, 394	Destroy, 412
Address, 395	Exchange, 412
MetaData, 395	FullName, 413
operator XMLNode, 395	Get, 413

	15 1
GetDoc, 413	VerifyNode, 423
GetRoot, 413	XMLSecNode, 422
GetXML, 413	ARCAuth
is_owner_, 419	Arc::SecAttr, 308
is_temporary_, 419	ArcCredential, 41
MatchXMLName, 419	CERT_TYPE_CA, 41
MatchXMLNamespace, 419	CERT_TYPE_EEC, 41
Move, 413	CERT_TYPE_GSI_2_LIMITED_PROXY, 42
Name, 413, 414	CERT_TYPE_GSI_2_PROXY, 42
Namespace, 414	CERT_TYPE_GSI_3_IMPERSONATION_PROXY,
NamespacePrefix, 414	42
Namespaces, 414	CERT_TYPE_GSI_3_INDEPENDENT_PROXY,
New, 414	42
NewAttribute, 414	CERT_TYPE_GSI_3_LIMITED_PROXY, 42
NewChild, 414, 415	CERT_TYPE_GSI_3_RESTRICTED_PROXY, 42
operator bool, 415	CERT_TYPE_RFC_ANYLANGUAGE_PROXY, 42
operator std::string, 415	CERT_TYPE_RFC_IMPERSONATION_PROXY,
operator!, 415	42
operator!=, 415, 416	CERT_TYPE_RFC_INDEPENDENT_PROXY, 42
operator++, 416	CERT_TYPE_RFC_LIMITED_PROXY, 42
operator-, 416	CERT_TYPE_RFC_RESTRICTED_PROXY, 42
operator=, 416	ArcCredential
operator==, 416	certType, 41
operator[], 417	ArcSec::AlgFactory, 44
Parent, 417	ArcSec::AlgFactory
Path, 417	createAlg, 44
Prefix, 417	ArcSec::Attr, 47
ReadFromFile, 417	ArcSec::AttributeFactory, 48
ReadFromStream, 417	ArcSec::AttributeProxy, 52
Replace, 417	ArcSec::AttributeProxy
Same, 418	getAttribute, 52
SaveToFile, 418	ArcSec::AttributeValue, 53
SaveToStream, 418	ArcSec::AttributeValue
Set, 418	encode, 53
Size, 418	equal, 53
Swap, 418	getId, 53
Validate, 418	getType, 54
XMLNode, 411, 412	ArcSec::Attrs, 55
XPathLookup, 418	ArcSec::AuthzRequestSection, 56
Arc::XMLNodeContainer, 420	<pre>ArcSec::CombiningAlg, 74</pre>
Arc::XMLNodeContainer	ArcSec::CombiningAlg
Add, 420	combine, 74
AddNew, 420	getalgId, 74
Nodes, 421	ArcSec::DateTimeAttribute, 145
operator=, 421	ArcSec::DateTimeAttribute
operator[], 421	encode, 145
Size, 421	equal, 145
XMLNodeContainer, 420	getId, 145
Arc::XMLSecNode, 422	getType, 145
Arc::XMLSecNode	ArcSec::DenyOverridesCombiningAlg, 157
AddSignatureTemplate, 422	ArcSec::DenyOverridesCombiningAlg
DecryptNode, 422	combine, 157
EncryptNode, 423	getalgId, 157
SignNode, 423	ArcSec::DurationAttribute, 159
-	·

ArcSec::DurationAttribute	ArcSec::Policy
encode, 159	addPolicy, 287
equal, 159	eval, 287
getId, 159	getEffect, 287
getType, 159	getEvalName, 287
ArcSec::EqualFunction, 161	getEvalResult, 287
ArcSec::EqualFunction	getName, 287
evaluate, 161	make_policy, 287
getFunctionName, 161	match, 287
ArcSec::EvalResult, 163	operator bool, 288
ArcSec::EvaluationCtx, 164	Policy, 286, 287
ArcSec::EvaluationCtx	setEvalResult, 288
EvaluationCtx, 164	setEvaluatorContext, 288
ArcSec::Evaluator, 165	ArcSec::PolicyParser, 289
ArcSec::Evaluator	ArcSec::PolicyParser
addPolicy, 165	parsePolicy, 289
evaluate, 166	ArcSec::PolicyStore, 290
getAlgFactory, 166	ArcSec::PolicyStore
getAttrFactory, 166	PolicyStore, 290
getFnFactory, 167	ArcSec::Request, 294
getName, 167	ArcSec::Request
setCombiningAlg, 167	addRequestItem, 295
ArcSec::EvaluatorContext, 168	getEvalName, 295
ArcSec::EvaluatorContext	getName, 295
operator AlgFactory *, 168	getRequestItems, 295
operator AttributeFactory *, 168	make_request, 295
operator FnFactory *, 168	Request, 294
ArcSec::EvaluatorLoader, 169	setAttributeFactory, 295
ArcSec::EvaluatorLoader	-
	setRequestItems, 295
getEvaluator, 169 getPolicy, 169	ArcSec::RequestAttribute, 296 ArcSec::RequestAttribute
getRequest, 169, 170	-
ArcSec::FnFactory, 185	duplicate, 296 RequestAttribute, 296
ArcSec::FnFactory	-
1	ArcSec::RequestItem, 297
createFn, 185	ArcSec::RequestItem
ArcSec::Function, 186	RequestItem, 297
ArcSec::Function	ArcSec::Response, 298
evaluate, 186	ArcSec::ResponseItem, 299
ArcSec::MatchFunction, 225	ArcSec::SecHandler, 313
ArcSec::MatchFunction	ArcSec::SecHandlerConfig, 314
evaluate, 225	ArcSec::Security, 315
getFunctionName, 225	ArcSec::Source, 339
ArcSec::PDP, 272	ArcSec::Source
ArcSec::PeriodAttribute, 273	Get, 340
ArcSec::PeriodAttribute	operator bool, 340
encode, 273	Source, 339, 340
equal, 273	ArcSec::SourceFile, 341
getId, 273	ArcSec::SourceFile
getType, 273	SourceFile, 341
ArcSec::PermitOverridesCombiningAlg, 275	ArcSec::SourceURL, 342
ArcSec::PermitOverridesCombiningAlg	ArcSec::SourceURL
combine, 275	SourceURL, 342
getalgId, 275	ArcSec::TimeAttribute, 357
ArcSec::Policy, 286	ArcSec::TimeAttribute

encode, 357	Buffer
equal, 357	Arc::PayloadRaw, 260
getId, 357	Arc::PayloadRawInterface, 262
getType, 357	buffer_size
ARCUSERDIRECTORY	Arc::DataBuffer, 99
Arc::UserConfig, 387	BufferPos
Assign	Arc::PayloadRaw, 260
Arc::InformationContainer, 193	Arc::PayloadRawInterface, 262
AssignStderr	BufferSize
Arc::Run, 301	Arc::PayloadRaw, 261
AssignStdin	Arc::PayloadRawInterface, 262
Arc::Run, 301	BufNum
AssignStdout	Arc::DataPoint, 114
Arc::Run, 301	Arc::DataPointDirect, 125
AssignWorkingDirectory Arc::Run, 301	Arc::DataPointIndex, 132 BufSize
AttrConstIter	Arc::DataPoint, 114
Arc, 29	Arc::DataPointDirect, 125
Attribute	Arc::DataPointIndex, 132
Arc::XMLNode, 412	BUSY ERROR
AttributeIterator	Arc, 30
Arc::AttributeIterator, 49, 50	1120, 00
Attributes	CACertificatePath
Arc::Message, 239	Arc::UserConfig, 369
Arc::SOAPMessage, 321	CACertificatesDirectory
attributes_	Arc::UserConfig, 370
Arc::MessageAttributes, 243	Cache
AttributesSize	Arc::DataPoint, 114
Arc::XMLNode, 412	CacheError
AttrIter	Arc::DataStatus, 144
Arc, 29	cancel
AttrMap	Arc::Counter, 85
Arc, 29	Arc::CounterTicket, 91
Auth	Arc::IntraProcessCounter, 201
Arc::Message, 239	CERT_TYPE_CA
AuthContext	ArcCredential, 41
Arc::Message, 239	CERT_TYPE_EEC
Authenticate	ArcCredential, 41 CERT_TYPE_GSI_2_LIMITED_PROXY
Arc::SAMLToken, 306	ArcCredential, 42
Arc::UsernameToken, 390 Arc::X509Token, 408	CERT_TYPE_GSI_2_PROXY
AutoPointer	ArcCredential, 42
Arc::AutoPointer, 57	CERT_TYPE_GSI_3_IMPERSONATION_PROXY
mic. macor officer, 37	ArcCredential, 42
Backup	CERT_TYPE_GSI_3_INDEPENDENT_PROXY
Arc::DelegationConsumer, 148	ArcCredential, 42
Bartender	CERT_TYPE_GSI_3_LIMITED_PROXY
Arc::UserConfig, 367	ArcCredential, 42
broadcast	CERT_TYPE_GSI_3_RESTRICTED_PROXY
Arc::SimpleCondition, 319	ArcCredential, 42
Broker	CERT_TYPE_RFC_ANYLANGUAGE_PROXY
Arc::UserConfig, 368	ArcCredential, 42
BrokerLoader	CERT_TYPE_RFC_IMPERSONATION_PROXY
Arc::BrokerLoader, 61	ArcCredential, 42

CERT_TYPE_RFC_INDEPENDENT_PROXY	close
ArcCredential, 42	Arc::Database, 96
CERT_TYPE_RFC_LIMITED_PROXY	Arc::MySQLDatabase, 254
ArcCredential, 42	CloseStderr
CERT_TYPE_RFC_RESTRICTED_PROXY	Arc::Run, 301
ArcCredential, 42	CloseStdin
CertificateLifeTime	Arc::Run, 301
Arc::UserConfig, 370, 371	CloseStdout
CertificatePath	Arc::Run, 301
Arc::UserConfig, 371	combine
certType	ArcSec::CombiningAlg, 74
ArcCredential, 41	ArcSec::DenyOverridesCombiningAlg,
changeExcess	157
Arc::Counter, 85	ArcSec::PermitOverridesCombiningAlg,
Arc::IntraProcessCounter, 201	275
changeLimit	CompareLocationMetadata
Arc::Counter, 85	Arc::DataPoint, 115
Arc::IntraProcessCounter, 201	Arc::DataPointDirect, 126
Check	Arc::DataPointIndex, 133 CompareMeta
Arc::DataPoint, 114 Arc::DataPointIndex, 133	Arc::DataPoint, 115
Arc::WSAHeader, 397	ComparisonOperator
CheckCheckSum	Arc::Software, 324
Arc::DataPoint, 114	ComparisonOperatorEnum
CheckCreated	Arc::Software, 324
Arc::DataPoint, 114	ComputingShareName
Arc::FileCache, 178	Arc::ExecutionTarget, 173
CheckDN	Config
Arc::FileCache, 178	Arc::Config, 76, 77
CheckError	ConfusaCertHandler
Arc::DataStatus, 144	Arc::ConfusaCertHandler, 78
checks	connect
Arc::DataMover, 108	Arc::Database, 96
CheckSize	Arc::MySQLDatabase, 254
Arc::DataPoint, 114	Content
checksum_object	Arc::PayloadRawInterface, 263
Arc::DataBuffer, 100	ContentFromPayload
checksum_valid	Arc, 38
Arc::DataBuffer, 100	Context
CheckValid	Arc::Message, 239
Arc::DataPoint, 115	context_lock_
Arc::FileCache, 178	Arc::DelegationContainerSOAP, 151
Child	convert
Arc::XMLNode, 412	Arc::Software, 326
CIStringValue	convert_to_rdn
Arc::CIStringValue, 67	Arc, 34
clear	Copy
Arc::SoftwareRequirement, 333 ClearRejectedServices	Arc::FileCache, 178 count
Arc::UserConfig, 372	Arc::MessageAttributes, 242
ClearSelectedServices	Counter
Arc::UserConfig, 372, 373	Arc::Counter, 85
ClientSOAP	Arc::CounterTicket, 91
Arc::ClientSOAP, 71	Arc::ExpirationReminder, 175
r	1 22 2 2 2 2 2 2 2 2 2 2 2 2 2 2 2 2 2

CounterTicket	DEFAULTCONFIG
Arc::Counter, 89	Arc::UserConfig, 388
<pre>Arc::CounterTicket, 90</pre>	Delegate
createAlg	Arc::DelegationProvider, 153
ArcSec::AlgFactory, 44	DelegateCredentialsInit
createCertRequest	Arc::DelegationConsumerSOAP, 149
Arc::ConfusaCertHandler, 78	Arc::DelegationContainerSOAP, 151
createFn	Arc::DelegationProviderSOAP, 156
ArcSec::FnFactory, 185	DelegatedToken
CreateThreadFunction	Arc::DelegationConsumerSOAP, 149
Arc, 34	Arc::DelegationContainerSOAP, 151
createVOMSAC	Arc::DelegationProviderSOAP, 156
Arc, 35	DelegationConsumer
CredentialError	Arc::DelegationConsumer, 147
Arc::CredentialError, 93	DelegationConsumerSOAP
CredentialLogger	Arc::DelegationConsumerSOAP, 149
Arc, 40	DelegationProvider
CredentialsExpiredError	Arc::DelegationProvider, 153
Arc::DataStatus, 144	DelegationProviderSOAP
CredentialsFound	Arc::DelegationProviderSOAP, 155
Arc::UserConfig, 373	DeleteError
current_	Arc::DataStatus, 144
Arc::AttributeIterator, 51	Destroy
CurrentLocation	Arc::XMLNode, 412
Arc::DataPoint, 115	destroy_doc
Arc::DataPointDirect, 126	Arc::ConfusaParserUtils, 79
Arc::DataPointIndex, 133	DirCreate
CurrentLocationMetadata	Arc, 32
Arc::DataPoint, 115	DirDelete
Arc::DataPointDirect, 126	Arc, 32
Arc::DataPointIndex, 133	DirOpen
Database	Arc, 31
Arc::Database, 95	<pre>doc_ Arc::InformationContainer, 194</pre>
DataBuffer	duplicate
Arc::DataBuffer, 99	ArcSec::RequestAttribute, 296
DataMover	Alebec Requestatelibute, 200
Arc::DataMover, 107	empty
DataPoint	Arc::Software, 326
Arc::DataPoint, 113	Arc::SoftwareRequirement, 333
DataPointAccessLatency	enable_ssl
Arc::DataPoint, 113	Arc::Database, 96
DataSpeed	Arc::MySQLDatabase, 254
Arc::DataSpeed, 139	encode
DataStatusType	ArcSec::AttributeValue, 53
Arc::DataStatus, 144	ArcSec::DateTimeAttribute, 145
DecryptNode	ArcSec::DurationAttribute, 159
Arc::XMLSecNode, 422	ArcSec::PeriodAttribute, 273
DEFAULT_BROKER	ArcSec::TimeAttribute, 357
Arc::UserConfig, 387	EncryptNode
DEFAULT_TIMEOUT	Arc::XMLSecNode, 423
Arc::UserConfig, 387	end_
DefaultCheckSum	Arc::AttributeIterator, 51
Arc::DataPoint, 115	eof_position

	_
Arc::DataBuffer, 100	factory_
eof_read	Arc::Loader, 212
Arc::DataBuffer, 100	FaultTo
eof_write	Arc::WSAHeader, 397 File
Arc::DataBuffer, 100	Arc::FileCache, 179
EQUAL 224	FileCache
Arc::Software, 324	Arc::FileCache, 177, 178
equal	FileCacheHash, 182
Arc::CIStringValue, 68	FileCacheHash
ArcSec::AttributeValue, 53 ArcSec::DateTimeAttribute, 145	getHash, 182
ArcSec::DurationAttribute, 159	maxLength, 182
ArcSec::PeriodAttribute, 273	FileCopy
ArcSec::TimeAttribute, 357	Arc, 31
error	FileLock
Arc::DataBuffer, 100	Arc::FileLock, 184
error read	FileOpen
Arc::DataBuffer, 100	Arc, 31
error transfer	FileStat
Arc::DataBuffer, 101	Arc, 31, 32
error write	FillJobStore
Arc::DataBuffer, 101	Arc::JobController, 206
ETERNAL	Filter
Arc, 39	Arc::InfoFilter, 188
eval	Arc::MessageAuth, 244
ArcSec::Policy, 287	final_xmlsec
evaluate	Arc, 38
ArcSec::EqualFunction, 161	find
ArcSec::Evaluator, 166	Arc::ModuleManager, 251
ArcSec::Function, 186	findLocation
ArcSec::MatchFunction, 225	Arc::ModuleManager, 251
evaluate_path	for_read
Arc::ConfusaParserUtils, 79	Arc::DataBuffer, 101
EvaluationCtx	for_write
ArcSec::EvaluationCtx, 164	Arc::DataBuffer, 101
EXAMPLECONFIG	force_to_meta Arc::DataMover, 108
Arc::UserConfig, 388	FoundJobs
Exchange	Arc::TargetGenerator, 347
Arc::XMLNode, 412	FoundTargets
ExecutionTarget	Arc::TargetGenerator, 347
<pre>Arc::ExecutionTarget, 171</pre>	From
ExpirationReminder	Arc::WSAHeader, 397
Arc::Counter, 89	FullName
Export	Arc::XMLNode, 413
Arc::MessageAuth, 244	fullstr
Arc::MultiSecAttr, 253	Arc::URLLocation, 360
Arc::SecAttr, 308	
extend	GACL
Arc::Counter, 86	Arc::SecAttr, 308
Arc::CounterTicket, 91	Generate
Arc::IntraProcessCounter, 201	Arc::DelegationConsumer, 148
extract_body_information	GENERIC_ERROR
Arc::ConfusaParserUtils, 79	Arc, 30

Get	ArcSec::Evaluator, 166
Arc::ArcLocation, 46	getAttribute
Arc::InformationContainer, 194	ArcSec::AttributeProxy, 52
Arc::InformationInterface, 195	GetBrokers
Arc::PayloadStream, 266	Arc::BrokerLoader, 61
<pre>Arc::PayloadStreamInterface, 268,</pre>	getCertRequestB64
269	Arc::ConfusaCertHandler, 78
Arc::XMLNode, 413	GetCheckSum
ArcSec::Source, 340	Arc::DataPoint, 116
get	getComparisonOperatorList
Arc::MessageAttributes, 242	Arc::SoftwareRequirement, 334
Arc::MessageAuth, 244	getCounterTicket
get_cert_str	Arc::Counter, 86
Arc, 38	GetCreated
get_doc	Arc::DataPoint, 116
<pre>Arc::ConfusaParserUtils, 79</pre>	Arc::FileCache, 179
<pre>get_factory</pre>	getCurrentTime
Arc::PluginArgument, 281	Arc::Counter, 86
<pre>get_key_from_certfile</pre>	GetDoc
Arc, 38	Arc::XMLNode, 413
<pre>get_key_from_certstr</pre>	getEffect
Arc, 39	ArcSec::Policy, 287
<pre>get_key_from_keyfile</pre>	GetEntry
Arc, 38	Arc::ClientSOAP, 71
get_key_from_keystr	GetEnv
Arc, 38	Arc, 34
<pre>get_max_inactivity_time</pre>	getEvalName
Arc::DataSpeed, 140	ArcSec::Policy, 287
get_module	ArcSec::Request, 295
Arc::PluginArgument, 281	getEvalResult
get_node	ArcSec::Policy, 287
Arc, 39	getEvaluator
<pre>get_plugin_instance</pre>	ArcSec::EvaluatorLoader, 169
Arc, 29	getExcess
get_property	Arc::Counter, 87
Arc, 37	Arc::IntraProcessCounter, 202
GetAccessLatency	getExpirationReminder
Arc::DataPoint, 115	Arc::Counter, 87
Arc::DataPointIndex, 133	getExpiryTime
GetAdditionalChecks	Arc::Counter, 87
Arc::DataPoint, 115	Arc::ExpirationReminder, 174
Arc::DataPointDirect, 126	getExplanation
Arc::DataPointIndex, 133	Arc::MCC_Status, 230
getAlgFactory	GetFailureReason
ArcSec::Evaluator, 166	Arc::DataPoint, 116
getalgId	getFamily
ArcSec::CombiningAlg, 74	Arc::Software, 326
ArcSec::DenyOverridesCombiningAlg,	getFileName
157	Arc::Config, 77
ArcSec::PermitOverridesCombiningAlg,	getFnFactory
275	ArcSec::Evaluator, 167
getAll	GetFormat
Arc::MessageAttributes, 242	Arc::Time, 355
getAttrFactory	getFunctionName

ArcSec::EqualFunction, 161	Arc::UserConfig, 373
ArcSec::MatchFunction, 225	GetSize
getHash	Arc::DataPoint, 116
FileCacheHash, 182	getSoftwareList
getID	Arc::SoftwareRequirement, 334
Arc::Service, 317	GetSubmitter
getId	Arc::ExecutionTarget, 172
ArcSec::AttributeValue, 53	GetSubmitters
ArcSec::DateTimeAttribute, 145	Arc::SubmitterLoader, 344
ArcSec::DurationAttribute, 159	GetTargetRetrievers
ArcSec::PeriodAttribute, 273	Arc::TargetRetrieverLoader, 351
ArcSec::TimeAttribute, 357	GetTargets
GetJobControllers	Arc::TargetGenerator, 348
Arc::JobControllerLoader, 208	Arc::TargetRetriever, 350
Arc::JobSupervisor, 211	getThreshold
getKind	Arc::Logger, 219
Arc::MCC_Status, 230	GetTime
getLevel	Arc::Time, 355
Arc::LogMessage, 222	GetTries
getLimit	Arc::DataPoint, 116
Arc::Counter, 87	getType
Arc::IntraProcessCounter, 202	ArcSec::AttributeValue, 54
getName	ArcSec::DateTimeAttribute, 145
Arc::Software, 326	ArcSec::DurationAttribute, 159
ArcSec::Evaluator, 167	ArcSec::PeriodAttribute, 273
ArcSec::Policy, 287	ArcSec::TimeAttribute, 357
ArcSec::Request, 295	GetURL
getOrigin	Arc::DataPoint, 116
Arc::MCC_Status, 231	GetUserConfig
GetOverlay	Arc::DataPoint, 116
Arc::BaseConfig, 60	GetValid
getPattern	Arc::DataPoint, 116
Arc::RegularExpression, 292	Arc::FileCache, 179
GetPlugins	getValue
Arc::ArcLocation, 46	Arc::Counter, 88
getPolicy	Arc::IntraProcessCounter, 202
ArcSec::EvaluatorLoader, 169	getVersion
GetRejectedServices	Arc::Software, 326
Arc::UserConfig, 373	GetXML
getRequest	Arc::XMLNode, 413
ArcSec::EvaluatorLoader, 169, 170	GREATERTHAN
getRequestItems	Arc::Software, 325
ArcSec::Request, 295	GREATERTHANOREQUAL
getReservationID	Arc::Software, 325
Arc::ExpirationReminder, 174	GUID
GetRoot A12	Arc, 32
Arc::XMLNode, 413	h a m all a
getRootLogger	handle_
Arc::Logger, 219	Arc::PayloadStream, 267
GetSecure Arg: DataBoint 116	handle_redirect_step
Arc::DataPoint, 116	Arc::ConfusaParserUtils, 79
Arc::DataPointDirect, 126	HandleOpenSSLError
Arc::DataPointIndex, 133	Arc, 37
GetSelectedServices	hasMore

Arc::AttributeIterator, 50	Arc::DataBuffer, 102
hasPattern	is_temporary_
Arc::RegularExpression, 292	Arc::XMLNode, 419
HaveLocations	is_written
Arc::DataPoint, 116	Arc::DataBuffer, 102, 103
Arc::DataPointDirect, 126	isconnected
Arc::DataPointIndex, 134	Arc::Database, 96
header_allocated_	Arc::MySQLDatabase, 255
Arc::WSAHeader, 398	IsIndex
HISTORIC	Arc::DataPoint, 117
Arc, 39	Arc::DataPointDirect, 126
hold	Arc::DataPointIndex, 134
Arc::DataSpeed, 140	isOk
TD	Arc::MCC_Status, 231
ID	Arc::RegularExpression, 293
Arc::DelegationConsumer, 148	IsReadingError
Arc::DelegationProviderSOAP, 156	Arc::DataStatus, 144
IdPName	isRequiringAll
Arc::UserConfig, 374	Arc::SoftwareRequirement, 334
IDType	isResolved
Arc::Counter, 85	Arc::SoftwareRequirement, 334
Import	isSatisfied
Arc::SecAttr, 308	Arc::SoftwareRequirement, 335, 336
InconsistentMetadataError	istring_to_level
Arc::DataStatus, 144	Arc, 32
InfoCache	isValid
Arc::InfoCache, 187	Arc::CounterTicket, 91
InfoFilter	IsWritingError
Arc::InfoFilter, 188	Arc::DataStatus, 144
InfoRegisters	
Arc::InfoRegisters, 191	Job
InformationContainer	Arc::Job, 205
Arc::InformationContainer, 193	JobControllerLoader
InformationInterface	Arc::JobControllerLoader, 208
Arc::InformationInterface, 195	JobListFile
InformationRequest	Arc::UserConfig, 376
Arc::InformationRequest, 197	JobSupervisor
InformationResponse	Arc::JobSupervisor, 211
Arc::InformationResponse, 199	T. 0.1
Init	KeepStderr
Arc::ArcLocation, 46	Arc::Run, 301
init_xmlsec	KeepStdin
Arc, 38	Arc::Run, 301
InitializeCredentials	KeepStdout
Arc::UserConfig, 374	Arc::Run, 302
Insert	key
Arc::PayloadRawInterface, 263	Arc::AttributeIterator, 50
IntraProcessCounter	KeyPassword
Arc::IntraProcessCounter, 200	Arc::UserConfig, 376, 377
is_notwritten	KeyPath
Arc::DataBuffer, 102	Arc::UserConfig, 377
is_owner_	KeySize
Arc::XMLNode, 419	Arc::UserConfig, 378
is_read	Kill

3.00	D D 107
Arc::Run, 302	Arc::DataPointDirect, 127
LastLocation	Arc::DataPointIndex, 134
Arc::DataPoint, 117	lock
Arc::DataPointDirect, 126	Arc::SimpleCondition, 319
·	lock_
Arc::DataPointIndex, 134	Arc::InformationInterface, 196
LESSTHAN	log
Arc::Software, 325	Arc::LogDestination, 213
LESSTHANOREQUAL	Arc::LogFile, 216
Arc::Software, 325	Arc::LogStream, 224
level_to_string	LogDestination
Arc, 33	Arc::LogDestination, 213
Limit	LogError
Arc::PayloadStream, 266	Arc::DelegationConsumer, 148
Arc::PayloadStreamInterface, 269	LogFile
Link	Arc::LogFile, 215
Arc::FileCache, 179	Logger
ListError	Arc::Logger, 218
Arc::DataStatus, 144	Arc::LogMessage, 222
ListFiles	logger
Arc::DataPoint, 117	Arc::MCC, 229
Load	Arc::Plexer, 278
Arc::ClientSOAP, 72	Arc::Service, 317
load	LogLevel
Arc::BrokerLoader, 61	Arc, 30
Arc::JobControllerLoader, 208	LogMessage
Arc::ModuleManager, 252	Arc::LogMessage, 221
Arc::PluginsFactory, 284	LogStream
Arc::SubmitterLoader, 344	Arc::LogStream, 223
Arc::TargetRetrieverLoader, 351	lower
load_key_from_certfile	Arc, 33
Arc, 39	
load_key_from_certstr	make_policy
Arc, 39	ArcSec::Policy, 287
load_key_from_keyfile	make_request
Arc, 39	ArcSec::Request, 295
load_trusted_cert_file	MakeConfig
Arc, 39	Arc::BaseConfig, 60
load_trusted_cert_str	makePersistent
Arc, 39	Arc::ModuleManager, 252
load_trusted_certs	match
Arc, 39	Arc::RegularExpression, 293
LoadConfigurationFile	ArcSec::Policy, 287
Arc::UserConfig, 379	MatchXMLName
Loader	Arc, 35
Arc::Loader, 212	Arc::XMLNode, 419
	·
Local	MatchXMLNamespace
Arc::DataPoint, 117	Arc, 35
Arc::DataPointDirect, 127	Arc::XMLNode, 419
Arc::DataPointIndex, 134	max_duration_
LocationAlreadyExistsError	Arc::DelegationContainerSOAP, 151
Arc::DataStatus, 144	max_inactivity_time_failure
LocationValid	Arc::DataSpeed, 140
Arc::DataPoint, 117	max_size_

Arc::DelegationContainerSOAP, 152	Arc::XMLNode, 414
max_usage_	NewAttribute
Arc::DelegationContainerSOAP, 152	Arc::XMLNode, 414
MaxDiskSpace	NewChild
Arc::ExecutionTarget, 173	Arc::XMLNode, 414, 415
maxLength	NewReferenceParameter
FileCacheHash, 182	Arc::WSAHeader, 397
MaxMainMemory	Next
Arc::ExecutionTarget, 173	Arc::MCC, 228
MaxVirtualMemory	Arc::Plexer, 278
Arc::ExecutionTarget, 173	next_
MCC	Arc::MCC, 229
Arc::MCC, 228	NextLocation
MCC_Status	Arc::DataPoint, 117
Arc::MCC_Status, 230	Arc::DataPointDirect, 127
MCCLoader	Arc::DataPointIndex, 134
Arc::MCCLoader, 235	NextTry
Message	Arc::DataPoint, 117
Arc::Message, 239	Nodes
MessageAttributes	Arc::XMLNodeContainer, 421
Arc::AttributeIterator, 51	NoLocationError
Arc::MessageAttributes, 241	Arc::DataStatus, 144
MessageID	NOTEQUAL
Arc::WSAHeader, 397	Arc::Software, 324
MetaData	NotInitializedError
Arc::WSAEndpointReference, 395	Arc::DataStatus, 144
Migrate	NotSupportedForDirectDataPointsError
Arc::JobController, 206	Arc::DataStatus, 144
Arc::Submitter, 343	
	· · · · · · · · · · · · · · · · · · ·
min_average_speed_failure	OAuthConsumer
<pre>min_average_speed_failure Arc::DataSpeed, 140</pre>	OAuthConsumer Arc::OAuthConsumer, 256
<pre>Arc::DataSpeed, 140 min_speed_failure</pre>	Arc::OAuthConsumer, 256
Arc::DataSpeed, 140	Arc::OAuthConsumer, 256 old_level_to_level
Arc::DataSpeed, 140 min_speed_failure Arc::DataSpeed, 140 ModifyFoundTargets	Arc::OAuthConsumer, 256 old_level_to_level Arc, 33
Arc::DataSpeed, 140 min_speed_failure Arc::DataSpeed, 140 ModifyFoundTargets Arc::TargetGenerator, 348	Arc::OAuthConsumer, 256 old_level_to_level Arc, 33 OpenSSLInit
Arc::DataSpeed, 140 min_speed_failure Arc::DataSpeed, 140 ModifyFoundTargets Arc::TargetGenerator, 348 ModuleManager	Arc::OAuthConsumer, 256 old_level_to_level Arc, 33 OpenSSLInit Arc, 37
Arc::DataSpeed, 140 min_speed_failure Arc::DataSpeed, 140 ModifyFoundTargets Arc::TargetGenerator, 348	Arc::OAuthConsumer, 256 old_level_to_level Arc, 33 OpenSSLInit Arc, 37 OperatingSystem
Arc::DataSpeed, 140 min_speed_failure Arc::DataSpeed, 140 ModifyFoundTargets Arc::TargetGenerator, 348 ModuleManager Arc::ModuleManager, 251 Move	Arc::OAuthConsumer, 256 old_level_to_level Arc, 33 OpenSSLInit Arc, 37 OperatingSystem Arc::ExecutionTarget, 173
Arc::DataSpeed, 140 min_speed_failure Arc::DataSpeed, 140 ModifyFoundTargets Arc::TargetGenerator, 348 ModuleManager Arc::ModuleManager, 251 Move Arc::XMLNode, 413	Arc::OAuthConsumer, 256 old_level_to_level Arc, 33 OpenSSLInit Arc, 37 OperatingSystem Arc::ExecutionTarget, 173 operator *
Arc::DataSpeed, 140 min_speed_failure Arc::DataSpeed, 140 ModifyFoundTargets Arc::TargetGenerator, 348 ModuleManager Arc::ModuleManager, 251 Move Arc::XMLNode, 413 msg	Arc::OAuthConsumer, 256 old_level_to_level Arc, 33 OpenSSLInit Arc, 37 OperatingSystem Arc::ExecutionTarget, 173 operator * Arc::AttributeIterator, 50
Arc::DataSpeed, 140 min_speed_failure Arc::DataSpeed, 140 ModifyFoundTargets Arc::TargetGenerator, 348 ModuleManager Arc::ModuleManager, 251 Move Arc::XMLNode, 413	Arc::OAuthConsumer, 256 old_level_to_level Arc, 33 OpenSSLInit Arc, 37 OperatingSystem Arc::ExecutionTarget, 173 operator * Arc::AttributeIterator, 50 Arc::AutoPointer, 57
Arc::DataSpeed, 140 min_speed_failure Arc::DataSpeed, 140 ModifyFoundTargets Arc::TargetGenerator, 348 ModuleManager Arc::ModuleManager, 251 Move Arc::XMLNode, 413 msg	Arc::OAuthConsumer, 256 old_level_to_level Arc, 33 OpenSSLInit Arc, 37 OperatingSystem Arc::ExecutionTarget, 173 operator * Arc::AttributeIterator, 50 Arc::AutoPointer, 57 Arc::CountedPointer, 81 Arc::PathIterator, 258
Arc::DataSpeed, 140 min_speed_failure Arc::DataSpeed, 140 ModifyFoundTargets Arc::TargetGenerator, 348 ModuleManager Arc::ModuleManager, 251 Move Arc::XMLNode, 413 msg Arc::Logger, 219, 220 Name	Arc::OAuthConsumer, 256 old_level_to_level Arc, 33 OpenSSLInit Arc, 37 OperatingSystem Arc::ExecutionTarget, 173 operator * Arc::AttributeIterator, 50 Arc::AutoPointer, 57 Arc::CountedPointer, 81 Arc::PathIterator, 258 operator AlgFactory *
Arc::DataSpeed, 140 min_speed_failure Arc::DataSpeed, 140 ModifyFoundTargets Arc::TargetGenerator, 348 ModuleManager Arc::ModuleManager, 251 Move Arc::XMLNode, 413 msg Arc::Logger, 219, 220 Name Arc::URLLocation, 360	Arc::OAuthConsumer, 256 old_level_to_level Arc, 33 OpenSSLInit Arc, 37 OperatingSystem Arc::ExecutionTarget, 173 operator * Arc::AttributeIterator, 50 Arc::AutoPointer, 57 Arc::CountedPointer, 81 Arc::PathIterator, 258 operator AlgFactory * ArcSec::EvaluatorContext, 168
Arc::DataSpeed, 140 min_speed_failure Arc::DataSpeed, 140 ModifyFoundTargets Arc::TargetGenerator, 348 ModuleManager Arc::ModuleManager, 251 Move Arc::XMLNode, 413 msg Arc::Logger, 219, 220 Name	Arc::OAuthConsumer, 256 old_level_to_level Arc, 33 OpenSSLInit Arc, 37 OperatingSystem Arc::ExecutionTarget, 173 operator * Arc::AttributeIterator, 50 Arc::AutoPointer, 57 Arc::CountedPointer, 81 Arc::PathIterator, 258 operator AlgFactory * ArcSec::EvaluatorContext, 168 operator AttributeFactory *
Arc::DataSpeed, 140 min_speed_failure Arc::DataSpeed, 140 ModifyFoundTargets Arc::TargetGenerator, 348 ModuleManager Arc::ModuleManager, 251 Move Arc::XMLNode, 413 msg Arc::Logger, 219, 220 Name Arc::URLLocation, 360 Arc::XMLNode, 413, 414 name	Arc::OAuthConsumer, 256 old_level_to_level Arc, 33 OpenSSLInit Arc, 37 OperatingSystem Arc::ExecutionTarget, 173 operator * Arc::AttributeIterator, 50 Arc::AutoPointer, 57 Arc::CountedPointer, 81 Arc::PathIterator, 258 operator AlgFactory * ArcSec::EvaluatorContext, 168 operator AttributeFactory * ArcSec::EvaluatorContext, 168
Arc::DataSpeed, 140 min_speed_failure Arc::DataSpeed, 140 ModifyFoundTargets Arc::TargetGenerator, 348 ModuleManager Arc::ModuleManager, 251 Move Arc::XMLNode, 413 msg Arc::Logger, 219, 220 Name Arc::URLLocation, 360 Arc::XMLNode, 413, 414 name Arc::URLLocation, 360	Arc::OAuthConsumer, 256 old_level_to_level Arc, 33 OpenSSLInit Arc, 37 OperatingSystem Arc::ExecutionTarget, 173 operator * Arc::AttributeIterator, 50 Arc::AutoPointer, 57 Arc::CountedPointer, 81 Arc::PathIterator, 258 operator AlgFactory * ArcSec::EvaluatorContext, 168 operator AttributeFactory * ArcSec::EvaluatorContext, 168 operator bool
Arc::DataSpeed, 140 min_speed_failure Arc::DataSpeed, 140 ModifyFoundTargets Arc::TargetGenerator, 348 ModuleManager Arc::ModuleManager, 251 Move Arc::XMLNode, 413 msg Arc::Logger, 219, 220 Name Arc::URLLocation, 360 Arc::XMLNode, 413, 414 name Arc::URLLocation, 360 Namespace	Arc::OAuthConsumer, 256 old_level_to_level Arc, 33 OpenSSLInit Arc, 37 OperatingSystem Arc::ExecutionTarget, 173 operator * Arc::AttributeIterator, 50 Arc::AutoPointer, 57 Arc::CountedPointer, 81 Arc::PathIterator, 258 operator AlgFactory * ArcSec::EvaluatorContext, 168 operator AttributeFactory * ArcSec::EvaluatorContext, 168 operator bool Arc::AutoPointer, 57
Arc::DataSpeed, 140 min_speed_failure Arc::DataSpeed, 140 ModifyFoundTargets Arc::TargetGenerator, 348 ModuleManager Arc::ModuleManager, 251 Move Arc::XMLNode, 413 msg Arc::Logger, 219, 220 Name Arc::URLLocation, 360 Arc::XMLNode, 413, 414 name Arc::URLLocation, 360 Namespace Arc::XMLNode, 414	Arc::OAuthConsumer, 256 old_level_to_level Arc, 33 OpenSSLInit Arc, 37 OperatingSystem Arc::ExecutionTarget, 173 operator * Arc::AttributeIterator, 50 Arc::AutoPointer, 57 Arc::CountedPointer, 81 Arc::PathIterator, 258 operator AlgFactory * ArcSec::EvaluatorContext, 168 operator AttributeFactory * ArcSec::EvaluatorContext, 168 operator bool Arc::AutoPointer, 57 Arc::CIStringValue, 68
Arc::DataSpeed, 140 min_speed_failure Arc::DataSpeed, 140 ModifyFoundTargets Arc::TargetGenerator, 348 ModuleManager Arc::ModuleManager, 251 Move Arc::XMLNode, 413 msg Arc::Logger, 219, 220 Name Arc::URLLocation, 360 Arc::XMLNode, 413, 414 name Arc::URLLocation, 360 Namespace Arc::XMLNode, 414 NamespacePrefix	Arc::OAuthConsumer, 256 old_level_to_level Arc, 33 OpenSSLInit Arc, 37 OperatingSystem Arc::ExecutionTarget, 173 operator * Arc::AttributeIterator, 50 Arc::AutoPointer, 57 Arc::CountedPointer, 81 Arc::PathIterator, 258 operator AlgFactory * ArcSec::EvaluatorContext, 168 operator AttributeFactory * ArcSec::EvaluatorContext, 168 operator bool Arc::AutoPointer, 57 Arc::CIStringValue, 68 Arc::CountedPointer, 81
Arc::DataSpeed, 140 min_speed_failure Arc::DataSpeed, 140 ModifyFoundTargets Arc::TargetGenerator, 348 ModuleManager Arc::ModuleManager, 251 Move Arc::XMLNode, 413 msg Arc::Logger, 219, 220 Name Arc::URLLocation, 360 Arc::XMLNode, 413, 414 name Arc::URLLocation, 360 Namespace Arc::XMLNode, 414 NamespacePrefix Arc::XMLNode, 414	Arc::OAuthConsumer, 256 old_level_to_level Arc, 33 OpenSSLInit Arc, 37 OperatingSystem Arc::ExecutionTarget, 173 operator * Arc::AttributeIterator, 50 Arc::AutoPointer, 57 Arc::CountedPointer, 81 Arc::PathIterator, 258 operator AlgFactory * ArcSec::EvaluatorContext, 168 operator AttributeFactory * ArcSec::EvaluatorContext, 168 operator bool Arc::AutoPointer, 57 Arc::CIStringValue, 68 Arc::CountedPointer, 81 Arc::DataBuffer, 103
Arc::DataSpeed, 140 min_speed_failure Arc::DataSpeed, 140 ModifyFoundTargets Arc::TargetGenerator, 348 ModuleManager Arc::ModuleManager, 251 Move Arc::XMLNode, 413 msg Arc::Logger, 219, 220 Name Arc::URLLocation, 360 Arc::XMLNode, 413, 414 name Arc::URLLocation, 360 Namespace Arc::XMLNode, 414 NamespacePrefix Arc::XMLNode, 414 Namespaces	Arc::OAuthConsumer, 256 old_level_to_level Arc, 33 OpenSSLInit Arc, 37 OperatingSystem Arc::ExecutionTarget, 173 operator * Arc::AttributeIterator, 50 Arc::AutoPointer, 57 Arc::CountedPointer, 81 Arc::PathIterator, 258 operator AlgFactory * ArcSec::EvaluatorContext, 168 operator AttributeFactory * ArcSec::EvaluatorContext, 168 operator bool Arc::AutoPointer, 57 Arc::CIStringValue, 68 Arc::CountedPointer, 81 Arc::DataBuffer, 103 Arc::DataPoint, 118
Arc::DataSpeed, 140 min_speed_failure Arc::DataSpeed, 140 ModifyFoundTargets Arc::TargetGenerator, 348 ModuleManager Arc::ModuleManager, 251 Move Arc::XMLNode, 413 msg Arc::Logger, 219, 220 Name Arc::URLLocation, 360 Arc::XMLNode, 413, 414 name Arc::URLLocation, 360 Namespace Arc::XMLNode, 414 NamespacePrefix Arc::XMLNode, 414	Arc::OAuthConsumer, 256 old_level_to_level Arc, 33 OpenSSLInit Arc, 37 OperatingSystem Arc::ExecutionTarget, 173 operator * Arc::AttributeIterator, 50 Arc::AutoPointer, 57 Arc::CountedPointer, 81 Arc::PathIterator, 258 operator AlgFactory * ArcSec::EvaluatorContext, 168 operator AttributeFactory * ArcSec::EvaluatorContext, 168 operator bool Arc::AutoPointer, 57 Arc::CIStringValue, 68 Arc::CountedPointer, 81 Arc::DataBuffer, 103

A I. (1)	and the second s
Arc::LogFile, 216	operator++
Arc::MCC_Status, 231	Arc::AttributeIterator, 50, 51
Arc::MultiSecAttr, 253	Arc::PathIterator, 258
Arc::PathIterator, 258	Arc::XMLNode, 416
Arc::PayloadStream, 266 Arc::PayloadStreamInterface, 269	operator- Arc::Time, 355
Arc::Run, 302	
Arc::SAMLToken, 306	operator-
Arc::SecAttr, 308	Arc::PathIterator, 258 Arc::XMLNode, 416
Arc::SecAttrValue, 311	
•	operator->
Arc::UserConfig, 380 Arc::UsernameToken, 390	Arc::AttributeIterator, 51 Arc::AutoPointer, 58
Arc::WSRF, 400	Arc::CountedPointer, 82
Arc::X509Token, 408	operator<
Arc::XMLNode, 415	Arc::ExpirationReminder, 174
ArcSec::Policy, 288	Arc::Software, 327
ArcSec::Source, 340	Arc::Time, 355
operator FnFactory *	operator<<
ArcSec::EvaluatorContext, 168	Arc, 30, 32
operator PluginsFactory *	Arc::LogMessage, 222
Arc::ChainContext, 64	Arc::Software, 330
operator std::string	operator<=
Arc::MCC_Status, 231	Arc::Software, 328
Arc::Software, 326	Arc::Time, 355
Arc::Time, 355	operator=
Arc::XMLNode, 415	Arc::ExecutionTarget, 172
operator T *	Arc::Message, 239
Arc::AutoPointer, 58	Arc::RegularExpression, 293
Arc::CountedPointer, 81	Arc::SoftwareRequirement, 336
operator XMLNode	Arc::Time, 355, 356
Arc::WSAEndpointReference, 395	Arc::WSAEndpointReference, 395
Arc::WSAHeader, 397	Arc::XMLNode, 416
operator!	Arc::XMLNodeContainer, 421
Arc::AutoPointer, 58	operator==
Arc::CountedPointer, 81	Arc::FileCache, 179
Arc::DataPoint, 118	Arc::SecAttr, 308
Arc::FileLock, 184	Arc::SecAttrValue, 311
Arc::LogFile, 216	Arc::Software, 328
Arc::MCC_Status, 231	Arc::Time, 356
Arc::PayloadStream, 266	Arc::XMLNode, 416
Arc::PayloadStreamInterface, 269	operator>
Arc::Run, 302	Arc::Software, 328
Arc::UserConfig, 380	Arc::Time, 356
Arc::XMLNode, 415	operator>=
operator!=	Arc::Software, 329
Arc::SecAttr, 308	Arc::Time, 356
Arc::SecAttrValue, 311	operator[]
Arc::Software, 327	Arc::DataBuffer, 103
Arc::Time, 355	Arc::MCCLoader, 236
Arc::XMLNode, 415, 416	Arc::MessageAuth, 245
operator()	Arc::PayloadRawInterface, 263
Arc::Software, 327	Arc::XMLNode, 417
operator+	Arc::XMLNodeContainer, 421
Arc::Time, 355	OverlayFile

Arc::UserConfig, 380, 381	PostRegister
Parent	Arc::DataPoint, 118
Arc::XMLNode, 417	Arc::DataPointDirect, 127
	PostRegisterError
parse Arc::Config, 77	Arc::DataStatus, 144
parseDN	Prefix
	Arc::XMLNode, 417
Arc::OAuthConsumer, 256	PreRegister
parsePolicy	Arc::DataPoint, 118
ArcSec::PolicyParser, 289	Arc::DataPointDirect, 127
parseVOMSAC	PreRegisterError
Arc, 36, 37	Arc::DataStatus, 144
PARSING_ERROR	PreUnregister
Arc, 30	Arc::DataPoint, 118
Passive 110	Arc::DataPointDirect, 128
Arc::DataPoint, 118	Print
Arc::DataPointDirect, 127	Arc::ExecutionTarget, 172
Arc::DataPointIndex, 134	Arc::Job, 205
passive	print
Arc::DataMover, 108	Arc::Config, 77
passphrase_callback	PrintJobStatus
Arc, 38	Arc::JobController, 207
Password	PrintTargetInfo
Arc::UserConfig, 381	Arc::TargetGenerator, 348
PasswordType	process
Arc::UsernameToken, 389	Arc::ClientSOAP, 72
Path	Arc::MCC, 228
Arc::XMLNode, 417	Arc::MCCInterface, 233
PathIterator	Arc::Plexer, 278
Arc::PathIterator, 258	processLogin
Payload	Arc::OAuthConsumer, 256
Arc::Message, 240	ProcessSecHandlers
Arc::SOAPMessage, 321, 322	Arc::MCC, 228
PayloadRaw	Arc::Service, 317
Arc::PayloadRaw, 260	PROTOCOL_RECOGNIZED_ERROR
PayloadSOAP	Arc, 30
Arc::PayloadSOAP, 264	ProvidesMeta
PayloadStream	Arc::DataPoint, 119
Arc::PayloadStream, 265	Arc::DataPointDirect, 128
PayloadWSRF	Arc::DataPointIndex, 134
Arc::PayloadWSRF, 271	ProxyPath
Plexer	Arc::UserConfig, 382
Arc::Plexer, 277	pushCSR
plugins_table_name	Arc::OAuthConsumer, 256
Arc, 40	Put
PluginsFactory	Arc::PayloadStream, 266, 267
Arc::PluginsFactory, 284	Arc::PayloadStreamInterface, 269
Policy	,
ArcSec::Policy, 286, 287	Range
PolicyStore	Arc::DataPoint, 119
ArcSec::PolicyStore, 290	Arc::DataPointDirect, 128
Pos	Arc::DataPointIndex, 135
Arc::PayloadStream, 266	ReadAcquireError
Arc::PayloadStreamInterface, 269	Arc::DataStatus, 144
	1110200000000, 111

ReadError	removeAll
Arc::DataStatus, 144	Arc::MessageAttributes, 243
ReadFromFile	removeDestinations
Arc::XMLNode, 417	Arc::Logger, 220
ReadFromStream	RemoveLocation
Arc::XMLNode, 417	Arc::DataPoint, 119
ReadOutOfOrder	Arc::DataPointDirect, 129
Arc::DataPoint, 119	Arc::DataPointIndex, 135
Arc::DataPointDirect, 128	RemoveLocations
Arc::DataPointIndex, 135	Arc::DataPoint, 119
ReadResolveError	Arc::DataPointDirect, 129
Arc::DataStatus, 144	Arc::DataPointIndex, 135
ReadStartError	removeService
Arc::DataStatus, 144	Arc::InfoRegisterContainer, 190
ReadStderr	Arc::InfoRegistrar, 192
Arc::Run, 302	Replace
ReadStdout	Arc::XMLNode, 417
Arc::Run, 302	ReplyTo
ReadStopError	Arc::WSAHeader, 398
Arc::DataStatus, 144	report
ReadURLList	Arc::PluginsFactory, 284
Arc, 34	Request
ReferenceParameter	Arc::DelegationConsumer, 148
Arc::WSAHeader, 397, 398	ArcSec::Request, 294
ReferenceParameters	RequestAttribute
Arc::WSAEndpointReference, 395	ArcSec::RequestAttribute, 296
Registered	RequestItem
Arc::DataPoint, 119	ArcSec::RequestItem, 297
Arc::DataPointDirect, 128	reserve
Arc::DataPointIndex, 135	Arc::Counter, 88
RegisteredService	Arc::IntraProcessCounter, 203
Arc::RegisteredService, 291	reset
RegisterThread	Arc::DataSpeed, 140
Arc::ThreadRegistry, 353	Arc::SimpleCondition, 319
registration	Resolve
Arc::InfoRegistrar, 192	Arc::DataPoint, 120
RegistrationCollector	Arc::DataPointDirect, 129
Arc::Service, 317	Rest
RegularExpression	Arc::PathIterator, 258
Arc::RegularExpression, 292	Restore
RelatesTo	Arc::DelegationConsumer, 148
Arc::WSAHeader, 398	restricted_
RelationshipType	Arc::DelegationContainerSOAP, 152
Arc::WSAHeader, 398	Result
Release	Arc::InformationResponse, 199
Arc::FileCache, 179	Arc::Run, 302
reload	retry
Arc::ModuleManager, 252	Arc::DataMover, 108
Remove	Run
Arc::DataPoint, 119	Arc::Run, 300
Arc::DataPointIndex, 135	Running
remove	Arc::Run, 302
Arc::MessageAttributes, 243	
Arc::MessageAuth, 245	Same

Arc::XMLNode, 418	Arc::DataSpeed, 141
SAML	set_namespaces
Arc::SecAttr, 309	Arc::WSRF, 400
SAMLToken	Arc::WSRFBaseFault, 401
Arc::SAMLToken, 305	Arc::WSRP, 403
SAMLVersion	set_progress_indicator
Arc::SAMLToken, 305	Arc::DataSpeed, 141
save	SetAccessLatency
Arc::Config, 77	Arc::DataPoint, 120
SaveToFile	SetAdditionalChecks
Arc::UserConfig, 382	Arc::DataPoint, 120
Arc::XMLNode, 418	Arc::DataPointDirect, 129
SaveToStream	Arc::DataPointIndex, 135
Arc::XMLNode, 418	setAttributeFactory
scan	ArcSec::Request, 295
Arc::PluginsFactory, 284	setBackups
SecAttr	Arc::LogFile, 216
Arc::SecAttr, 307	setCfq
sechandlers	Arc::ModuleManager, 252
Arc::MCC, 229	SetCheckSum
Arc::Service, 317	Arc::DataPoint, 120
	Arc::DataPointIndex, 136
Arc::DataMover, 108	setCombiningAlg
seekable	
-	ArcSec::Evaluator, 167 SetCreated
Arc::PayloadStream, 267	
selectSoftware	Arc::DataPoint, 120 SetEnv
Arc::SoftwareRequirement, 336, 337 Service	Arc, 34
	setEvalResult
Arc::Service, 317 ServiceCounter	ArcSec::Policy, 288
Arc::TargetGenerator, 348	setEvaluatorContext
SESSION_CLOSE	ArcSec::Policy, 288
Arc, 30	setExcess
Set	Arc::Counter, 88
	,
Arc::XMLNode, 418	Arc::IntraProcessCounter, 203 setFileName
set	
Arc::DataBuffer, 103	Arc::Config, 77
Arc::MessageAttributes, 243	SetFormat 256
Arc::MessageAuth, 245	Arc::Time, 356
set_base	setIdentifier
Arc::DataSpeed, 141	Arc::LogMessage, 222
set_default_max_inactivity_time	setLimit
Arc::DataMover, 108	Arc::Counter, 89
set_default_min_average_speed	Arc::IntraProcessCounter, 203
Arc::DataMover, 108	setMaxSize
set_default_min_speed	Arc::LogFile, 216
Arc::DataMover, 108	SetMeta
set_max_data	Arc::DataPoint, 120
Arc::DataSpeed, 141	Arc::DataPointIndex, 136
set_max_inactivity_time	setReopen
Arc::DataSpeed, 141	Arc::LogFile, 216
set_min_average_speed	setRequestItems
Arc::DataSpeed, 141	ArcSec::Request, 295
set_min_speed	setRequirement

Arc::SoftwareRequirement, 338	ArcSec::SourceURL, 342
SetSecure	speed
Arc::DataPoint, 121	Arc::DataBuffer, 104
Arc::DataPointDirect, 129	StageError
Arc::DataPointIndex, 136 SetSize	Arc::DataStatus, 144 Start
Arc::DataPoint, 121	Arc::FileCache, 180
Arc::DataPointIndex, 136	Arc::Run, 302
setThreshold	StartReading
Arc::Logger, 220	Arc::DataPoint, 121
SetTime	Arc::DataPointIndex, 137
Arc::Time, 356	StartWriting
SetTries	Arc::DataPoint, 122
Arc::DataPoint, 121	Arc::DataPointIndex, 137
Arc::DataPointIndex, 136	STATUS_OK
SetValid	Arc, 30
Arc::DataPoint, 121	StatusKind
Arc::FileCache, 180	Arc, 30
shutdown	Stop
Arc::Database, 96	Arc::FileCache, 180
<pre>Arc::MySQLDatabase, 255</pre>	StopAndDelete
signal	Arc::FileCache, 180
Arc::SimpleCondition, 319	StopReading
signal_nonblock	Arc::DataPoint, 122
Arc::SimpleCondition, 319	Arc::DataPointIndex, 137
SignNode	StopWriting
Arc::XMLSecNode, 423	Arc::DataPoint, 122
Size	Arc::DataPointIndex, 137
Arc::PayloadRaw, 261	storeCert
Arc::PayloadRawInterface, 263	Arc::OAuthConsumer, 257
Arc::PayloadStream, 267	StoreDirectory
Arc::PayloadStreamInterface, 270	Arc::UserConfig, 383
Arc::XMLNode, 418 Arc::XMLNodeContainer, 421	str Arc::DataPoint, 122
SLCS	Arc::DataPoint, 122 Arc::Time, 356
Arc::UserConfig, 383	Arc::URLLocation, 360
SOAP	StrError
Arc::InformationRequest, 197	Arc, 35
Arc::WSRF, 400	string
SOAPMessage	Arc, 37
Arc::SOAPMessage, 321	string_to_level
Software	Arc, 32, 33
Arc::Software, 325	stringto
SoftwareRequirement	Arc, 33
Arc::SoftwareRequirement, 332	strip
SortLocations	Arc, 34
Arc::DataPoint, 121	Submit
Arc::DataPointDirect, 129	Arc::Submitter, 343
<pre>Arc::DataPointIndex, 136</pre>	SubmitterLoader
Source	Arc::SubmitterLoader, 344
ArcSec::Source, 339, 340	Success
SourceFile	Arc::DataStatus, 144
ArcSec::SourceFile, 341	Swap
SourceURL	Arc::XMLNode, 418

SYSCONFIG	Unlink
Arc::UserConfig, 388	Arc::MCC, 228
SYSCONFIGARCLOC	unload
Arc::UserConfig, 388	Arc::ModuleManager, 252
SystemError	unlock
Arc::DataStatus, 144	Arc::SimpleCondition, 319
	Unregister
TargetGenerator	Arc::DataPoint, 122
Arc::TargetGenerator, 346	Arc::DataPointDirect, 130
TargetRetriever	UnregisterError
Arc::TargetRetriever, 349	Arc::DataStatus, 144
TargetRetrieverLoader	UnregisterThread
Arc::TargetRetrieverLoader, 351	Arc::ThreadRegistry, 353
thread_stacksize	UnsetEnv
Arc, 40	Arc, 35
Time	Update
Arc::Time, 354, 355	Arc::ExecutionTarget, 172
TimeFormat	UpdateCredentials
Arc, 30	Arc::DelegationConsumerSOAP, 150
Timeout	Arc::DelegationContainerSOAP, 151
Arc::PayloadStream, 267	Arc::DelegationProviderSOAP, 156
Arc::PayloadStreamInterface, 270	upper
Arc::UserConfig, 384	Arc, 33
TimeStamp	uri_unescape
Arc, 31	Arc, 34
То	URL.h, 425
Arc::WSAHeader, 398	urlencode
tokenize	Arc::ConfusaParserUtils, 80
Arc, 34	urlencode_params
toString	Arc::ConfusaParserUtils, 80
Arc::Software, 329	URLLocation
tostring	Arc::URLLocation, 359
Arc, 33	UserConfig
Transfer	Arc::UserConfig, 364, 365
Arc::DataMover, 109	UserName
transfer	Arc::UserConfig, 385
Arc::DataSpeed, 142	Username
TransferError	Arc::UsernameToken, 390
Arc::DataStatus, 144	UsernameToken
transferred size	Arc::UsernameToken, 389, 390
Arc::DataSpeed, 142	UtilsDirPath
trim	Arc::UserConfig, 385
Arc, 34	UUID
Truncate	Arc, 32
Arc::PayloadRawInterface, 263	
TryLoad	valid
Arc::PluginsFactory, 285	Arc::WSRF, 400
,	valid_url_options
UnimplementedError	Arc::DataPoint, 123
Arc::DataStatus, 144	Validate
UNKNOWN_SERVICE_ERROR	Arc::XMLNode, 418
Arc, 30	verbose
UnknownError	Arc::DataMover, 109, 110
Arc::DataStatus, 144	Arc::DataSpeed, 142

Verbosity Arc::WSAEndpointReference, 394 WSAFault Arc::UserConfig, 386 Arc, 30 VerifyNode Arc::XMLSecNode, 423 WSAFaultAssign VERSIONTOKENS Arc, 38 Arc::Software, 330 WSAFaultExtract VOMSDecode Arc, 38 WSAFaultInvalidAddressingHeader Arc, 37 VOMSServerPath Arc, 30 Arc::UserConfig, 386, 387 WSAFaultUnknown VOMSTrustList Arc, 30 Arc::VOMSTrustList, 392 WSAHeader Arc::WSAHeader, 396 Wait WSRF Arc::Run, 302, 303 Arc::WSRF, 399 wait WSRFBaseFault Arc::SimpleCondition, 320 Arc::WSRFBaseFault, 401 wait_any WSRP Arc::DataBuffer, 103 Arc::WSRP, 403 wait eof WSRPFault Arc::DataBuffer, 103 Arc::WSRPFault, 405 wait eof read WSRPResourcePropertyChangeFailure Arc::DataBuffer, 103 Arc::WSRPResourcePropertyChangewait_eof_write Failure, 406 Arc::DataBuffer, 103 X509Token wait nonblock Arc::X509Token, 407 Arc::SimpleCondition, 320 X509TokenType wait_read Arc::X509Token, 407 Arc::DataBuffer, 104 XACML wait used Arc::SecAttr, 309 Arc::DataBuffer, 104 XMLNode wait_write Arc::XMLNode, 411, 412 Arc::DataBuffer, 104 XMLNodeContainer WaitForExit Arc::XMLNodeContainer, 420 Arc::ThreadRegistry, 353 XMLSecNode WaitOrCancel Arc::ThreadRegistry, 353 Arc::XMLSecNode, 422 WriteAcquireError XPathLookup Arc::XMLNode, 418 Arc::DataStatus, 144 WriteError Arc::DataStatus, 144 WriteOutOfOrder Arc::DataPoint, 123 Arc::DataPointDirect, 130 Arc::DataPointIndex, 137 WriteResolveError Arc::DataStatus, 144 WriteStartError Arc::DataStatus, 144 WriteStdin Arc::Run, 303 WriteStopError Arc::DataStatus, 144

WSAEndpointReference