Hosting Environment (Daemon)

Generated by Doxygen 1.7.1

Tue Oct 12 2010 13:44:56

Contents

1	Nan	nespace	Index		1
	1.1	Names	space List		. 1
2	Data	a Struct	ure Index	K.	3
	2.1	Class l	Hierarchy		. 3
3	Data	a Struct	ure Index	ζ.	11
	3.1	Data S	tructures		. 11
4	File	Index			19
-	4.1		ct		
	7.1	THE L	.st		. 19
5	Nan	ıespace	Documer	ntation	23
	5.1	Arc Na	amespace	Reference	. 23
		5.1.1	Detailed	Description	. 35
		5.1.2	Typedef	Documentation	. 36
			5.1.2.1	AttrConstIter	. 36
			5.1.2.2	AttrIter	. 36
			5.1.2.3	AttrMap	. 36
			5.1.2.4	get_plugin_instance	. 36
		5.1.3	Enumera	ation Type Documentation	. 36
			5.1.3.1	LogLevel	. 36
			5.1.3.2	StatusKind	. 36
			5.1.3.3	WSAFault	. 37
		5.1.4	Function	Documentation	. 37
			5.1.4.1	addVOMSAC	. 37
			5.1.4.2	ContentFromPayload	. 37
			5.1.4.3	CreateThreadFunction	. 37
			5.1.4.4	createVOMSAC	. 38
			5145	FileOpen	38

ii CONTENTS

final_xmlsec	38
get_cert_str	38
get_key_from_certfile	38
get_key_from_certstr	38
get_key_from_keyfile	38
get_key_from_keystr	38
get_node	38
get_property	39
GUID	39
init_xmlsec	39
istring_to_level	39
load_key_from_certfile	39
load_key_from_certstr	39
load_key_from_keyfile	39
load_trusted_cert_file	40
load_trusted_cert_str	40
load_trusted_certs	40
MatchXMLName	40
MatchXMLName	40
MatchXMLName	40
MatchXMLNamespace	40
MatchXMLNamespace	40
MatchXMLNamespace	40
OpenSSLInit	40
operator<<	41
operator<<	41
operator<<	41
parseVOMSAC	41
parseVOMSAC	42
passphrase_callback	42
string	42
TimeStamp	42
TimeStamp	42
VOMSDecode	42
WSAFaultAssign	42
WSAFaultExtract	42
	get_key_from_certfile get_key_from_certstr get_key_from_keyfile get_key_from_keyfile get_key_from_keystr get_node get_property GUID init_xmlsec istring_to_level load_key_from_certstr load_key_from_certstr load_key_from_keyfile load_trusted_cert_file load_trusted_cert_str load_trusted_cert_str load_trusted_certs MatchXMLName MatchXMLName MatchXMLName MatchXMLName MatchXMLNamespace MatchX

		5.1.5	Variable !	Documenta	tion				 	 	 	43
			5.1.5.1	Credential	Logger				 	 	 	43
			5.1.5.2	plugins_ta	ıble_nam	ne			 	 	 	43
			5.1.5.3	thread_sta	cksize .				 	 	 	43
	5.2	ArcCre	edential Na	amespace R	eference				 	 	 	43
		5.2.1	Detailed	Description	١				 	 	 	44
		5.2.2	Enumera	tion Type D	ocumen ^a	tation .			 	 	 	44
			5.2.2.1	certType					 	 	 	44
6	Data	Struct	ure Docur	nentation								45
	6.1	ArcCre	edential::A	CACI Struc	et Refere	ence			 	 	 	45
	6.2	ArcCre	edential::A	CATTHOL	DER Str	uct Refe	erence		 	 	 	45
	6.3	ArcCre	edential::A	CATTR Stı	ruct Refe	erence .			 	 	 	45
	6.4	ArcCre	edential::A	CATTRIBU	JTE Stru	ıct Refe	rence .		 	 	 	45
	6.5	ArcCre	edential::A	.CC Struct l	Referenc	e			 	 	 	45
	6.6	ArcCre	edential::A	CCERTS S	truct Re	ference			 	 	 	46
	6.7	ArcCre	edential::A	CDIGEST	Struct Re	eference			 	 	 	46
	6.8	ArcCre	edential::A	CFORM S	truct Ref	erence			 	 	 	46
	6.9	ArcCre	edential::A	CFULLAT	TRIBUT	ES Stru	ct Refe	rence	 	 	 	46
	6.10	ArcCre	edential::A	CHOLDER	R Struct I	Referenc	ce		 	 	 	46
	6.11	ArcCre	edential::A	CIETFATT	'R Struct	Referer	nce		 	 	 	46
	6.12	ArcCre	edential::A	CINFO Str	uct Refe	rence .			 	 	 	46
	6.13	ArcCre	edential::A	CIS Struct	Referenc	e			 	 	 	47
	6.14	ArcCre	edential::A	.CSEQ Stru	ct Refere	ence			 	 	 	47
	6.15	ArcCre	edential::A	CTARGET	Struct R	Referenc	e		 	 	 	47
	6.16	ArcCre	edential::A	CTARGET	'S Struct	Referen	ice		 	 	 	47
	6.17	ArcCre	edential::A	CVAL Stru	ct Refere	ence			 	 	 	47
	6.18	Arc::A	dler32Sun	n Class Ref	erence .				 	 	 	47
		6.18.1	Detailed	Description	١				 	 	 	48
	6.19	ArcSec	:::AlgFacto	ory Class R	eference				 	 	 	48
		6.19.1	Detailed	Description	1				 	 	 	48
		6.19.2	Member	Function D	ocument	ation .			 	 	 	48
			6.19.2.1	createAlg					 	 	 	48
	6.20	ArcSec	:::AnyURI	Attribute C	lass Refe	erence			 	 	 	49
		6.20.1	Member	Function D	ocument	ation .			 	 	 	49
			6.20.1.1	encode .					 	 	 	49
			6.20.1.2	equal					 	 	 	49

iv CONTENTS

6.20.1.3 getId	49
6.20.1.4 getType	49
6.21 Arc::ApplicationEnvironment Class Reference	50
6.21.1 Detailed Description	50
6.22 Arc::ApplicationType Class Reference	50
6.23 Arc::ARCJSDLParser Class Reference	50
6.24 Arc::ArcLocation Class Reference	51
6.24.1 Detailed Description	51
6.24.2 Member Function Documentation	51
6.24.2.1 GetPlugins	51
6.24.2.2 Init	51
6.25 ArcSec::ArcPeriod Struct Reference	51
6.26 Arc::ARCPolicyHandlerConfig Class Reference	51
6.27 ArcSec::Attr Struct Reference	52
6.27.1 Detailed Description	52
6.28 ArcSec::AttributeFactory Class Reference	52
6.28.1 Detailed Description	52
6.29 Arc::AttributeIterator Class Reference	53
6.29.1 Detailed Description	53
6.29.2 Constructor & Destructor Documentation	53
6.29.2.1 AttributeIterator	53
6.29.2.2 AttributeIterator	54
6.29.3 Member Function Documentation	54
6.29.3.1 hasMore	54
6.29.3.2 key	54
6.29.3.3 operator*	54
6.29.3.4 operator++	54
6.29.3.5 operator++	55
6.29.3.6 operator->	55
6.29.4 Friends And Related Function Documentation	55
6.29.4.1 MessageAttributes	55
6.29.5 Field Documentation	55
6.29.5.1 current	55
6.29.5.2 end	55
6.30 ArcSec::AttributeProxy Class Reference	55
6.30.1 Detailed Description	56

	6.30.2	Member	Function Docum	entation		 	 	 	 	 56
		6.30.2.1	getAttribute .			 	 	 	 	 56
6.31	ArcSec	:::Attribute	Value Class Ref	erence .		 	 	 	 	 56
	6.31.1	Detailed 1	Description			 	 	 	 	 57
	6.31.2	Member 1	Function Docum	entation		 	 	 	 	 57
		6.31.2.1	encode			 	 	 	 	 57
		6.31.2.2	equal			 	 	 	 	 58
		6.31.2.3	getId			 	 	 	 	 58
		6.31.2.4	getType			 	 	 	 	 58
6.32	ArcSec	:::Attrs Cla	ass Reference .			 	 	 	 	 58
	6.32.1	Detailed 1	Description			 	 	 	 	 58
6.33	ArcSec	:::AuthzRe	equest Struct Ref	erence .		 	 	 	 	 59
6.34	ArcSec	:::AuthzRe	equestSection Str	uct Refere	ence .	 	 	 	 	 59
	6.34.1	Detailed 1	Description			 	 	 	 	 59
6.35	Arc::A	utoPointer	< T > Class Ter	nplate Ref	ference		 	 	 	 59
	6.35.1	Detailed 1	Description			 	 	 	 	 59
6.36	Arc::B	ase64 Clas	s Reference			 	 	 	 	 60
6.37	Arc::B	aseConfig	Class Reference			 	 	 	 	 60
	6.37.1	Detailed 1	Description			 	 	 	 	 60
	6.37.2	Member 1	Function Docum	entation		 	 	 	 	 60
		6.37.2.1	AddCADir			 	 	 	 	 60
		6.37.2.2	AddCAFile .			 	 	 	 	 60
		6.37.2.3	AddCertificate			 	 	 	 	 61
		6.37.2.4	AddOverlay .			 	 	 	 	 61
		6.37.2.5	AddPluginsPath	ı		 	 	 	 	 61
		6.37.2.6	AddPrivateKey			 	 	 	 	 61
		6.37.2.7	AddProxy			 	 	 	 	 61
		6.37.2.8	GetOverlay .			 	 	 	 	 61
		6.37.2.9	MakeConfig .			 	 	 	 	 61
6.38	ArcSec	::Boolean	Attribute Class R	Reference		 	 	 	 	 61
	6.38.1	Member	Function Docum	entation		 	 	 	 	 62
		6.38.1.1	encode			 	 	 	 	 62
		6.38.1.2	equal			 	 	 	 	 62
		6.38.1.3	getId			 	 	 	 	 62
		6.38.1.4	getType			 	 	 	 	 62
6.39	Arc::B	roker Class	s Reference			 	 	 	 	 62

vi CONTENTS

	6.39.1	Member Function Documentation	63
		6.39.1.1 GetBestTarget	63
		6.39.1.2 PreFilterTargets	63
		6.39.1.3 SortTargets	63
	6.39.2	Field Documentation	64
		6.39.2.1 PossibleTargets	64
6.40	Arc::B	rokerLoader Class Reference	64
	6.40.1	Detailed Description	64
	6.40.2	Constructor & Destructor Documentation	64
		6.40.2.1 BrokerLoader	64
		6.40.2.2 ~BrokerLoader	64
	6.40.3	Member Function Documentation	65
		6.40.3.1 GetBrokers	65
		6.40.3.2 load	65
6.41	Arc::B	rokerPluginArgument Class Reference	65
6.42	Arc::B	yteArray Class Reference	65
6.43	Arc::C	acheParameters Struct Reference	66
	6.43.1	Detailed Description	66
6.44	ArcCre	dential::cert_verify_context Struct Reference	66
6.45	Arc::C	hainContext Class Reference	66
	6.45.1	Detailed Description	66
	6.45.2	Member Function Documentation	66
		6.45.2.1 operator PluginsFactory *	66
6.46	Arc::C	heckSum Class Reference	67
	6.46.1	Detailed Description	67
6.47	Arc::C	heckSumAny Class Reference	67
	6.47.1	Detailed Description	67
6.48	Arc::C	StringValue Class Reference	67
	6.48.1	Detailed Description	68
	6.48.2	Constructor & Destructor Documentation	68
		6.48.2.1 CIStringValue	68
		6.48.2.2 CIStringValue	68
		6.48.2.3 CIStringValue	68
	6.48.3	Member Function Documentation	68
		6.48.3.1 equal	68
		6.48.3.2 operator bool	69

CONTENTS vii

c 10			٠,
			69
			69
6.51			69
	6.51.1	Detailed Description	70
6.52	Arc::C	lientHTTPwithSAML2SSO Class Reference	70
	6.52.1	Constructor & Destructor Documentation	70
		6.52.1.1 ClientHTTPwithSAML2SSO	70
	6.52.2	Member Function Documentation	70
		6.52.2.1 process	70
6.53	Arc::C	lientInterface Class Reference	71
	6.53.1	Detailed Description	71
6.54	Arc::C	lientSOAP Class Reference	71
	6.54.1	Detailed Description	72
	6.54.2	Constructor & Destructor Documentation	72
		6.54.2.1 ClientSOAP	72
	6.54.3		72
			72
			72
		·	. – 72
			· - 72
		•	 72
6 5 5	ArcC	•	72 73
0.55		Constructor & Destructor Documentation	
	0.55.1	6.55.1.1 ClientSOAPwithSAML2SSO	
	6.55.0		
	6.55.2		73 72
		Ţ	73 - 2
		Ţ	73
6.56			73
		r	74
6.57	Arc::C	lientX509Delegation Class Reference	74
	6.57.1	Constructor & Destructor Documentation	74
		6.57.1.1 ClientX509Delegation	74
	6.57.2	Member Function Documentation	74
		6.57.2.1 acquireDelegation	74
		6.57.2.2 createDelegation	75
6.58	ArcSec	c::CombiningAlg Class Reference	75

viii CONTENTS

	6.58.1	Detailed Description	76
	6.58.2	Member Function Documentation	76
		6.58.2.1 combine	76
		6.58.2.2 getalgId	76
6.59	Arc::Co	onfig Class Reference	76
	6.59.1	Detailed Description	77
	6.59.2	Constructor & Destructor Documentation	77
		6.59.2.1 Config	77
		6.59.2.2 Config	77
		6.59.2.3 Config	77
		6.59.2.4 Config	77
		6.59.2.5 Config	77
		6.59.2.6 Config	78
	6.59.3	Member Function Documentation	78
		6.59.3.1 getFileName	78
		6.59.3.2 parse	78
		6.59.3.3 print	78
		6.59.3.4 save	78
		6.59.3.5 setFileName	78
6.60	Arc::C	onfusaCertHandler Class Reference	78
	6.60.1	Detailed Description	78
	6.60.2	Constructor & Destructor Documentation	79
		6.60.2.1 ConfusaCertHandler	79
	6.60.3	Member Function Documentation	79
		6.60.3.1 createCertRequest	79
		6.60.3.2 getCertRequestB64	79
6.61	Arc::C	onfusaParserUtils Class Reference	79
	6.61.1	Detailed Description	79
	6.61.2	Member Function Documentation	79
		6.61.2.1 destroy_doc	79
		6.61.2.2 evaluate_path	80
		6.61.2.3 extract_body_information	80
		6.61.2.4 get_doc	80
		6.61.2.5 handle_redirect_step	80
		6.61.2.6 urlencode	80
		6.61.2.7 urlencode_params	80

6.62	Arc::C	ountedPointer< T > Class Template Reference	80
	6.62.1	Detailed Description	81
6.63	Arc::Co	ounter Class Reference	81
	6.63.1	Detailed Description	82
	6.63.2	Member Typedef Documentation	83
		6.63.2.1 IDType	83
	6.63.3	Constructor & Destructor Documentation	83
		6.63.3.1 Counter	83
		6.63.3.2 ~Counter	83
	6.63.4	Member Function Documentation	84
		6.63.4.1 cancel	84
		6.63.4.2 changeExcess	84
		6.63.4.3 changeLimit	84
		6.63.4.4 extend	84
		6.63.4.5 getCounterTicket	85
		6.63.4.6 getCurrentTime	85
		6.63.4.7 getExcess	85
		6.63.4.8 getExpirationReminder	86
		6.63.4.9 getExpiryTime	86
		6.63.4.10 getLimit	86
		6.63.4.11 getValue	86
		6.63.4.12 reserve	87
		6.63.4.13 setExcess	87
		6.63.4.14 setLimit	87
6.64	Arc::C	ounterTicket Class Reference	88
	6.64.1	Detailed Description	88
	6.64.2	Constructor & Destructor Documentation	89
		6.64.2.1 CounterTicket	89
	6.64.3	Member Function Documentation	89
		6.64.3.1 cancel	89
		6.64.3.2 extend	89
		6.64.3.3 isValid	89
6.65	Arc::C	RC32Sum Class Reference	89
	6.65.1	Detailed Description	90
6.66	Arc::C	redential Class Reference	90
	6.66.1	Constructor & Destructor Documentation	91

	6.66.1.1	Credential	91
	6.66.1.2	Credential	91
	6.66.1.3	Credential	91
	6.66.1.4	Credential	92
	6.66.1.5	Credential	92
6.66.2	Member 1	Function Documentation	92
	6.66.2.1	AddCertExtObj	92
	6.66.2.2	AddExtension	92
	6.66.2.3	AddExtension	93
	6.66.2.4	GenerateEECRequest	93
	6.66.2.5	GenerateEECRequest	93
	6.66.2.6	GenerateEECRequest	93
	6.66.2.7	GenerateRequest	93
	6.66.2.8	GenerateRequest	93
	6.66.2.9	GenerateRequest	93
	6.66.2.10	GetCert	93
	6.66.2.11	GetCertNumofChain	94
	6.66.2.12	GetCertReq	94
	6.66.2.13	GetDN	94
	6.66.2.14	GetEndTime	94
	6.66.2.15	getFormat	94
	6.66.2.16	GetIdentityName	94
	6.66.2.17	GetLifeTime	94
	6.66.2.18	GetPrivKey	94
	6.66.2.19	GetProxyPolicy	94
	6.66.2.20	GetPubKey	94
	6.66.2.21	GetStartTime	94
	6.66.2.22	GetType	95
	6.66.2.23	GetVerification	95
	6.66.2.24	InitProxyCertInfo	95
	6.66.2.25	InquireRequest	95
	6.66.2.26	InquireRequest	95
	6.66.2.27	InquireRequest	95
	6.66.2.28	LogError	95
	6.66.2.29	OutputCertificate	95
	6.66.2.30	OutputCertificateChain	95

		6.66.2.31 OutputPrivatekey	 	 	96
		6.66.2.32 OutputPublickey	 	 	96
		6.66.2.33 SetLifeTime	 	 	96
		6.66.2.34 SetProxyPolicy	 	 	96
		6.66.2.35 SetStartTime	 	 	96
		6.66.2.36 SignEECRequest	 	 	96
		6.66.2.37 SignEECRequest	 	 	96
		6.66.2.38 SignEECRequest	 	 	96
		6.66.2.39 SignRequest	 	 	97
		6.66.2.40 SignRequest	 	 	97
		6.66.2.41 SignRequest	 	 	97
		6.66.2.42 STACK_OF	 	 	97
6.67	Arc::C	redentialError Class Reference	 	 	97
	6.67.1	Detailed Description	 	 	97
	6.67.2	Constructor & Destructor Documentation	 	 	98
		6.67.2.1 CredentialError	 	 	98
6.68	Arc::C	redentialStore Class Reference	 	 	98
	6.68.1	Detailed Description	 	 	98
6.69	Arc::D	atabase Class Reference	 	 	98
	6.69.1	Detailed Description	 	 	99
	6.69.2	Constructor & Destructor Documentation	 	 	99
		6.69.2.1 Database	 	 	99
		6.69.2.2 Database	 	 	99
		6.69.2.3 Database	 	 	99
		6.69.2.4 ~Database	 	 	99
	6.69.3	Member Function Documentation	 	 	99
		6.69.3.1 close	 	 	99
		6.69.3.2 connect	 	 	99
		6.69.3.3 enable_ssl	 	 	100
		6.69.3.4 isconnected	 	 	100
		6.69.3.5 shutdown	 	 	100
6.70	Arc::D	ataBuffer Class Reference	 	 	100
	6.70.1	Detailed Description	 	 	101
	6.70.2	Constructor & Destructor Documentation	 	 	101
		6.70.2.1 DataBuffer	 	 	101
		6.70.2.2 DataBuffer	 	 	102

xii CONTENTS

6.70.3	Member Function Documentation
	6.70.3.1 add
	6.70.3.2 buffer_size
	6.70.3.3 checksum_object
	6.70.3.4 checksum_valid
	6.70.3.5 eof_read
	6.70.3.6 eof_read
	6.70.3.7 eof_write
	6.70.3.8 eof_write
	6.70.3.9 error
	6.70.3.10 error_read
	6.70.3.11 error_write
	6.70.3.12 for_read
	6.70.3.13 for_read
	6.70.3.14 for_write
	6.70.3.15 for_write
	6.70.3.16 is_notwritten
	6.70.3.17 is_notwritten
	6.70.3.18 is_read
	6.70.3.19 is_read
	6.70.3.20 is_written
	6.70.3.21 is_written
	6.70.3.22 set
	6.70.3.23 wait_any
6.71 Arc::D	ataCallback Class Reference
6.71.1	Detailed Description
6.72 Arc::D	ataHandle Class Reference
6.72.1	Detailed Description
6.73 Arc::D	ataMover Class Reference
6.73.1	Detailed Description
6.73.2	Member Function Documentation
	6.73.2.1 checks
	6.73.2.2 checks
	6.73.2.3 force_to_meta
	6.73.2.4 secure
	6.73.2.5 set_default_max_inactivity_time

CONTENTS xiii

6.73.2.6 set_default_min_average_speed	07
6.73.2.7 set_default_min_speed	07
6.73.2.8 Transfer	08
6.73.2.9 Transfer	08
6.73.2.10 verbose	08
6.74 Arc::DataPoint Class Reference	08
6.74.1 Detailed Description	10
6.74.2 Member Enumeration Documentation	11
6.74.2.1 DataPointAccessLatency	11
6.74.3 Constructor & Destructor Documentation	11
6.74.3.1 DataPoint	11
6.74.4 Member Function Documentation	11
6.74.4.1 AddCheckSumObject	11
6.74.4.2 AddLocation	11
6.74.4.3 Check	12
6.74.4.4 CompareLocationMetadata	12
6.74.4.5 CompareMeta	12
6.74.4.6 CurrentLocationMetadata	12
6.74.4.7 GetFailureReason	12
6.74.4.8 ListFiles	12
6.74.4.9 NextLocation	13
6.74.4.10 Passive	13
6.74.4.11 PostRegister	13
6.74.4.12 PreRegister	13
6.74.4.13 PreUnregister	13
6.74.4.14 ProvidesMeta	14
6.74.4.15 Range	14
6.74.4.16 ReadOutOfOrder	14
6.74.4.17 Registered	14
6.74.4.18 Resolve	14
6.74.4.19 SetAdditionalChecks	15
6.74.4.20 SetMeta	15
6.74.4.21 SetSecure	15
6.74.4.22 SortLocations	15
6.74.4.23 StartReading	15
6.74.4.24 StartWriting	16

6.74.4.25 StopReading	1	116
6.74.4.26 StopWriting	1	116
6.74.4.27 Unregister	1	116
6.74.4.28 WriteOutOfOrder	1	117
6.74.5 Field Documentation	1	117
6.74.5.1 valid_url_options	1	117
5.75 Arc::DataPointDirect Class Reference	1	117
6.75.1 Detailed Description	1	118
6.75.2 Member Function Documentation	1	118
6.75.2.1 AddCheckSumObject	1	118
6.75.2.2 AddLocation	1	118
6.75.2.3 CompareLocationMetadata	1	119
6.75.2.4 CurrentLocationMetadata	1	119
6.75.2.5 NextLocation	1	119
6.75.2.6 Passive	1	119
6.75.2.7 PostRegister	1	119
6.75.2.8 PreRegister	1	119
6.75.2.9 PreUnregister	1	120
6.75.2.10 ProvidesMeta	1	120
6.75.2.11 Range	1	120
6.75.2.12 ReadOutOfOrder	1	120
6.75.2.13 Registered	1	120
6.75.2.14 Resolve	1	121
6.75.2.15 SetAdditionalChecks	1	121
6.75.2.16 SetSecure	1	121
6.75.2.17 SortLocations	1	121
6.75.2.18 Unregister	1	121
6.75.2.19 WriteOutOfOrder	1	122
6.76 Arc::DataPointIndex Class Reference	1	122
6.76.1 Detailed Description	1	123
6.76.2 Member Function Documentation	1	123
6.76.2.1 AddCheckSumObject	1	123
6.76.2.2 AddLocation	1	123
6.76.2.3 Check	1	124
6.76.2.4 CompareLocationMetadata	1	124
6.76.2.5 CurrentLocationMetadata	1	124

		6.76.2.6	NextLocation	 . 1	124
		6.76.2.7	Passive	 . 1	124
		6.76.2.8	ProvidesMeta	 . 1	124
		6.76.2.9	Range	 . 1	124
		6.76.2.10	ReadOutOfOrder	 . 1	125
		6.76.2.11	Registered	 . 1	125
		6.76.2.12	SetAdditionalChecks	 . 1	125
		6.76.2.13	SetMeta	 . 1	125
		6.76.2.14	SetSecure	 . 1	125
		6.76.2.15	SortLocations	 . 1	126
		6.76.2.16	StartReading	 . 1	126
		6.76.2.17	StartWriting	 . 1	126
		6.76.2.18	StopReading	 . 1	126
		6.76.2.19	StopWriting	 . 1	127
		6.76.2.20	WriteOutOfOrder	 . 1	127
6.77	Arc::D	ataPointLo	pader Class Reference	 . 1	127
6.78	Arc::D	ataPointPl	uginArgument Class Reference	 . 1	127
6.79	Arc::D	ataSource'	Type Class Reference	 . 1	128
6.80	Arc::D	ataSpeed (Class Reference	 . 1	128
	6.80.1	Detailed	Description	 . 1	128
	6.80.2	Construc	tor & Destructor Documentation	 . 1	128
		6.80.2.1	DataSpeed	 . 1	128
		6.80.2.2	DataSpeed	 . 1	129
	6.80.3	Member	Function Documentation	 . 1	129
		6.80.3.1	hold	 . 1	129
		6.80.3.2	set_base	 . 1	129
		6.80.3.3	set_max_data	 . 1	129
		6.80.3.4	set_max_inactivity_time	 . 1	129
		6.80.3.5	set_min_average_speed	 . 1	130
		6.80.3.6	set_min_speed	 . 1	130
		6.80.3.7	set_progress_indicator	 . 1	130
		6.80.3.8	transfer	 . 1	130
		6.80.3.9	verbose	 . 1	130
		6.80.3.10	verbose	 . 1	130
6.81	Arc::D	ataStaging	Type Class Reference	 . 1	131
6.82	Arc::D	ataStatus (Class Reference	 . 1	131

	6.82.1	Detailed Description	 	1	131
	6.82.2	Member Enumeration Documentation	 	1	131
		6.82.2.1 DataStatusType	 	1	131
6.83	Arc::D	ataTargetType Class Reference	 	1	132
6.84	Arc::D	ataType Class Reference	 	1	132
6.85	ArcSec	:::DateAttribute Class Reference	 	1	133
	6.85.1	Member Function Documentation	 	1	133
		6.85.1.1 encode	 	1	133
		6.85.1.2 equal	 	1	133
		6.85.1.3 getId	 	1	133
		6.85.1.4 getType	 	1	133
6.86	ArcSec	:::DateTimeAttribute Class Reference	 	1	134
	6.86.1	Detailed Description	 	1	134
	6.86.2	Member Function Documentation	 	1	134
		6.86.2.1 encode	 	1	134
		6.86.2.2 equal	 	1	134
		6.86.2.3 getId	 	1	134
		6.86.2.4 getType	 	1	134
6.87	Arc::D	Branch Class Reference	 	1	135
6.88	Arc::D	elegationConsumer Class Reference	 	1	135
	6.88.1	Detailed Description	 	1	135
	6.88.2	$Constructor \ \& \ Destructor \ Documentation \ \ .$	 	1	136
		6.88.2.1 DelegationConsumer	 	1	136
		6.88.2.2 DelegationConsumer	 	1	136
	6.88.3	Member Function Documentation	 	1	136
		6.88.3.1 Acquire	 	1	136
		6.88.3.2 Acquire	 	1	136
		6.88.3.3 Backup	 	1	136
		6.88.3.4 Generate	 	1	136
		6.88.3.5 ID	 	1	136
		6.88.3.6 LogError	 	1	136
		6.88.3.7 Request	 	1	136
		6.88.3.8 Restore	 	1	136
6.89		elegationConsumerSOAP Class Reference .			
	6.89.1	Detailed Description	 	1	137
	6.89.2	Constructor & Destructor Documentation .	 	1	137

CONTENTS xvii

6.89.2.1 DelegationConsumerSOAP 137 6.89.2.2 DelegationConsumerSOAP 137 6.89.3 Member Function Documentation 137 6.89.3.1 DelegatedToken 138 6.89.3.2 DelegatedToken 138 6.89.3.3 UpdateCredentials 138 6.89.3.4 UpdateCredentials 138 6.90.1 Detailed Description 138 6.90.2 Member Function Documentation 138 6.90.2 DelegatedToken 139 6.90.2.1 DelegateCredentialsInit 139 6.90.2.2 DelegatedToken 139 6.90.3.2 UpdateCredentials 139 6.90.3.3 I context_lock 139 6.90.3 Field Documentation 139 6.90.3.1 context_lock 139 6.90.3.2 max_duration 139 6.90.3.3 max_size 139 6.90.3.4 max_usage 139 6.90.3.5 restricted 139 6.91 Arc::DelegationProvider Class Reference 139 6.91.1 Detailed Description 140 6.91.2 Constructor & Destructor Documentation 140 6.91.2 DelegationProvider Class Reference 140					
6.89.3 Member Function Documentation 137 6.89.3.1 Delegate Credential Shit 137 6.89.3.2 Delegated Token 138 6.89.3.3 Update Credentials 138 6.89.3.4 Update Credentials 138 6.90 Arc::Delegation Container SOAP Class Reference 138 6.90.1 Detailed Description 138 6.90.2 Member Function Documentation 139 6.90.2.1 Delegate Credential Shit 139 6.90.2.2 Delegated Token 139 6.90.3.1 Context_lock_ 139 6.90.3.1 context_lock_ 139 6.90.3.2 max_duration_ 139 6.90.3.3 max_size_ 139 6.90.3.4 max_usage_ 139 6.90.3.5 restricted_ 139 6.91 Arc::DelegationProvider Class Reference 139 6.91.1 Detailed Description 140 6.91.2 DelegationProvider Class Reference 140 6.91.3.1 Delegate 140 6.91.3.1 DelegationProvider 140 6.91.2.2 DelegationProvider 140 6.92.2 Constructor & Destructor Documentation 141 6.92.2 DelegationProviderSOAP 141 6.92.3 Member Functio			6.89.2.1	DelegationConsumerSOAP	137
6.89.3.1 DelegateCredentialSInit 137 6.89.3.2 DelegatedToken 138 6.89.3.3 UpdateCredentialS 138 6.89.3.4 UpdateCredentialS 138 6.89.3.4 UpdateCredentialS 138 6.89.3.4 UpdateCredentialS 138 6.90 Arc::DelegationContainerSOAP Class Reference 138 6.90.1 Detailed Description 138 6.90.2 Member Function Documentation 139 6.90.2.1 DelegateCredentialSInit 139 6.90.2.2 DelegatedToken 139 6.90.3.1 Context_lock 139 6.90.3.1 context_lock 139 6.90.3.2 max_duration 139 6.90.3.3 max_size 139 6.90.3.4 max_usage 139 6.90.3.5 restricted 139 6.90.1.1 Detailed Description 140 6.91.1 Detailed Description 140 6.91.2 DelegationProvider Class Reference 139 6.91.2 DelegationProvider Glass Reference 140 6.91.3.1 DelegationProvider 6.91.2.1 DelegationProvider 6.91.3.1 Delegate 140 6.91.3.1 DelegationProvider 140 6.91.3.1 DelegationProvider 6.91.2.2 DelegationProvider 140 6.91.3.1 DelegationProvider 140 6.92.2 Constructor & Destructor Documentation 140 6.92.3 DelegationProviderSOAP 141 6.92.3.1 DelegationProviderSOAP 141 6.92.3.2 DelegationProviderSOAP 141 6.92.3.3 DelegateCredentialsInit 142			6.89.2.2	DelegationConsumerSOAP	137
6.89.3.2 DelegatedToken 138 6.89.3.3 UpdateCredentials 138 6.89.3.4 UpdateCredentials 138 6.90.1 Detailed Description 138 6.90.1 Detailed Description 138 6.90.2 Member Function Documentation 139 6.90.2.1 DelegateCredentialsInit 139 6.90.2.2 DelegatedToken 139 6.90.3 Field Documentation 139 6.90.3.1 context_lock_ 139 6.90.3.2 max_duration_ 139 6.90.3.3 max_duration_ 139 6.90.3.4 max_usage_ 139 6.90.3.5 restricted_ 139 6.90.3.6 restricted_ 139 6.91 Detailed Description 140 6.91.1 Detailed Description 140 6.91.2 DelegationProvider 140 6.91.3 DelegationProvider 140 6.91.3 DelegationProvider 140 6.92.1 Delajed Description 141 6.92.2 DelegationProviderSO		6.89.3	Member	Function Documentation	137
6.89.3.3 UpdateCredentials 138 6.89.3.4 UpdateCredentials 138 6.90 Arc::DelegationContainerSOAP Class Reference 138 6.90.1 Detailed Description 138 6.90.2 Member Function Documentation 139 6.90.2.1 DelegateCredentialsInit 139 6.90.2.2 DelegatedToken 139 6.90.3 Field Documentation 139 6.90.3 Field Documentation 139 6.90.3.1 context_lock_ 139 6.90.3.2 max_duration_ 139 6.90.3.3 max_size_ 139 6.90.3.4 max_usage_ 139 6.90.3.5 restricted_ 139 6.91 Arc::DelegationProvider Class Reference 139 6.91.1 Detailed Description 140 6.91.2 Constructor & Destructor Documentation 140 6.91.2.1 DelegationProvider 140 6.91.3 Member Function Documentation 140 6.92.1 DelegationProviderSOAP Class Reference 140 6.92.1 DelegationProviderSOAP Destructor & Destructor Documentation 141 6.92.2 DelegationProviderSOAP 141 6.92.3 Member Function Documentation 1			6.89.3.1	DelegateCredentialsInit	137
6.89.3.4 UpdateCredentials 138 6.90 Arc::DelegationContainerSOAP Class Reference 138 6.90.1 Detailed Description 138 6.90.2 Member Function Documentation 139 6.90.2.1 DelegateCredentialsInit 139 6.90.2.2 DelegatedToken 139 6.90.2.3 UpdateCredentials 139 6.90.3 Field Documentation 139 6.90.3.1 context_lock_ 139 6.90.3.2 max_duration_ 139 6.90.3.3 max_size_ 139 6.90.3.4 max_usage_ 139 6.90.3.5 restricted_ 139 6.91 Arc::DelegationProvider Class Reference 139 6.91.1 Detailed Description 140 6.91.2 Constructor & Destructor Documentation 140 6.91.2.1 DelegationProvider 140 6.91.2.1 DelegationProvider Documentation 140 6.91.3 Member Function Documentation 141 6.92.1 DelegationProviderSOAP Class Reference 140 6.92.2 Constructor & Destructor Documentation 141 6.92.2.1 DelegationProviderSOAP 141 6.92.3.1 DelegateCredentialsInit 142			6.89.3.2	DelegatedToken	138
6.90 Are::DelegationContainerSOAP Class Reference 138 6.90.1 Detailed Description 138 6.90.2 Member Function Documentation 139 6.90.2.1 DelegatedToken 139 6.90.2.2 DelegatedToken 139 6.90.2.3 UpdateCredentials 139 6.90.3 Field Documentation 139 6.90.3.2 max_duration_ 139 6.90.3.3 max_size_ 139 6.90.3.4 max_usage_ 139 6.90.3.5 restricted_ 139 6.91 Are::DelegationProvider Class Reference 139 6.91.1 Detailed Description 140 6.91.2 Constructor & Destructor Documentation 140 6.91.2.1 DelegationProvider 140 6.91.3 Member Function Documentation 140 6.92.1 DelegationProviderSOAP Class Reference 140 6.92.2 Constructor & Destructor Documentation 141 6.92.2 DelegationProviderSOAP 141 6.92.2 DelegationProviderSOAP 141 6.92.3 Member Function Documentation 142 6.92.3.1 DelegateCredentialsInit 142 6.92.3.2 DelegateCredentialsInit 142 6.92.3.3 DelegateCredentialsInit 142			6.89.3.3	UpdateCredentials	138
6.90.1 Detailed Description 138 6.90.2 Member Function Documentation 139 6.90.2.1 DelegateCredentialsInit 139 6.90.2.2 DelegatedToken 139 6.90.2.3 UpdateCredentials 139 6.90.3 Field Documentation 139 6.90.3.1 context_lock_ 139 6.90.3.2 max_duration_ 139 6.90.3.3 max_size_ 139 6.90.3.4 max_usage_ 139 6.90.3.5 restricted_ 139 6.91 Arc::DelegationProvider Class Reference 139 6.91.1 Detailed Description 140 6.91.2 Constructor & Destructor Documentation 140 6.91.2 DelegationProvider 140 6.91.3 Member Function Documentation 140 6.92.1 DelegationProviderSOAP Class Reference 140 6.92.2 Constructor & Destructor Documentation 141 6.92.2 Constructor & DelegationProviderSOAP 141 6.92.3 DelegationProviderSOAP 141 6.92.3 DelegationProviderSOAP 141 6.92.3 DelegateCredentialsInit 142 6.92.3.3 DelegateCredentialsInit 142 6.92.3.3 DelegatedToken 142 <			6.89.3.4	UpdateCredentials	138
6.90.2 Member Function Documentation 139 6.90.2.1 DelegateCredentialsInit 139 6.90.2.2 DelegatedToken 139 6.90.3 Field Documentation 139 6.90.3 Field Documentation 139 6.90.3.1 context_lock_ 139 6.90.3.2 max_duration_ 139 6.90.3.3 max_size_ 139 6.90.3.4 max_usage_ 139 6.90.3.5 restricted_ 139 6.91 Arc::DelegationProvider Class Reference 139 6.91.1 Detailed Description 140 6.91.2 Constructor & Destructor Documentation 140 6.91.2.1 DelegationProvider 140 6.91.3 Member Function Documentation 140 6.92 Arc::DelegationProviderSOAP Class Reference 140 6.92.1 Detailed Description 141 6.92.2 Constructor & Destructor Documentation 141 6.92.2 DelegationProviderSOAP 141 6.92.3 Member Function Documentation 141 6.92.3 DelegateCredentialsInit 142 6.92.3.2 DelegateCredentialsInit 142 6.92.3.3 DelegatedToken 142	6.90	Arc::De	elegationC	ContainerSOAP Class Reference	138
6.90.2.1 DelegatedToken 139 6.90.2.2 DelegatedToken 139 6.90.2.3 UpdateCredentials 139 6.90.3 Field Documentation 139 6.90.3.1 context_lock 139 6.90.3.2 max_duration 139 6.90.3.3 max_size 139 6.90.3.4 max_usage 139 6.90.3.5 restricted 139 6.91 Arc::DelegationProvider Class Reference 139 6.91.1 Detailed Description 140 6.91.2 Constructor & Destructor Documentation 140 6.91.2.1 DelegationProvider 140 6.91.2.2 DelegationProvider 140 6.91.3.1 Delegate 140 6.92.2 Detailed Description 141 6.92.1 Detailed Description 141 6.92.2 Constructor & Destructor Documentation 141 6.92.2.1 DelegationProviderSOAP 141 6.92.3.1 DelegationProviderSOAP 141 6.92.3.2 DelegationProviderSOAP 142		6.90.1	Detailed	Description	138
6.90.2.2 DelegatedToken 139 6.90.2.3 UpdateCredentials 139 6.90.3 Field Documentation 139 6.90.3.1 context_lock_ 139 6.90.3.2 max_duration_ 139 6.90.3.3 max_size_ 139 6.90.3.4 max_usage_ 139 6.90.3.5 restricted_ 139 6.91 Arc::DelegationProvider Class Reference 139 6.91.1 Detailed Description 140 6.91.2 Constructor & Destructor Documentation 140 6.91.2.1 DelegationProvider 140 6.91.2.2 DelegationProvider 140 6.91.3 Delegate 140 6.91.3.1 Delegate 140 6.92.1 Detailed Description 141 6.92.1 Detailed Description 141 6.92.2 Constructor & Destructor Documentation 141 6.92.2.1 DelegationProviderSOAP 141 6.92.3.1 DelegateOredentialsInit 142 6.92.3.2 DelegateCredentialsInit 142		6.90.2	Member	Function Documentation	139
6.90.2.3 UpdateCredentials 139 6.90.3 Field Documentation 139 6.90.3.1 context_lock_ 139 6.90.3.2 max_duration_ 139 6.90.3.3 max_size_ 139 6.90.3.4 max_usage_ 139 6.90.3.5 restricted_ 139 6.91 Arc::DelegationProvider Class Reference 139 6.91.1 Detailed Description 140 6.91.2 Constructor & Destructor Documentation 140 6.91.2.1 DelegationProvider 140 6.91.3 Member Function Documentation 140 6.91.3 Member Function Documentation 140 6.92.1 DelegationProviderSOAP Class Reference 140 6.92.1 Detailed Description 141 6.92.2 Constructor & Destructor Documentation 141 6.92.2.1 DelegationProviderSOAP 141 6.92.2.2 DelegationProviderSOAP 141 6.92.3 Member Function Documentation 142 6.92.3.1 DelegateCredentialsInit 142 6.92.3.2 DelegateCredentialsInit 142 6.92.3.3 DelegateCredentialsInit 142 6.92.3.3 DelegateGredentialsInit 142			6.90.2.1	DelegateCredentialsInit	139
6.90.3 Field Documentation 139 6.90.3.1 context_lock_ 139 6.90.3.2 max_duration_ 139 6.90.3.3 max_size_ 139 6.90.3.4 max_usage_ 139 6.91 Arc::DelegationProvider Class Reference 139 6.91 Arc::DelegationProvider Class Reference 139 6.91.1 Detailed Description 140 6.91.2 Constructor & Documentation 140 6.91.2.1 DelegationProvider 140 6.91.2.2 DelegationProvider 140 6.91.3 Member Function Documentation 140 6.92.3 Delegate 140 6.92.1 Detailed Description 141 6.92.2 Constructor & Destructor Documentation 141 6.92.2.1 DelegationProviderSOAP 141 6.92.2.2 DelegationProviderSOAP 141 6.92.3 Member Function Documentation 142 6.92.3.1 DelegateCredentialsInit 142 6.92.3.2 DelegateCredentialsInit 142 6.92.3.3 DelegatedToken </td <td></td> <td></td> <td>6.90.2.2</td> <td>DelegatedToken</td> <td>139</td>			6.90.2.2	DelegatedToken	139
6.90.3.1 context_lock_ 139 6.90.3.2 max_duration_ 139 6.90.3.3 max_size_ 139 6.90.3.4 max_usage_ 139 6.90.3.5 restricted_ 139 6.91 Arc::DelegationProvider Class Reference 139 6.91.1 Detailed Description 140 6.91.2 Constructor & Destructor Documentation 140 6.91.2.1 DelegationProvider 140 6.91.2.2 DelegationProvider 140 6.91.3 Member Function Documentation 140 6.92 Arc::DelegationProviderSOAP Class Reference 140 6.92.1 Detailed Description 141 6.92.2 Constructor & Destructor Documentation 141 6.92.2.1 DelegationProviderSOAP 141 6.92.3 Member Function Documentation 142 6.92.3.1 DelegateCredentialsInit 142 6.92.3.2 DelegateCredentialsInit 142 6.92.3.3 DelegatedToken 142			6.90.2.3	UpdateCredentials	139
6.90.3.2 max_duration_ 139 6.90.3.3 max_size_ 139 6.90.3.4 max_usage_ 139 6.90.3.5 restricted_ 139 6.91 Arc::DelegationProvider Class Reference 139 6.91.1 Detailed Description 140 6.91.2 Constructor & Destructor Documentation 140 6.91.2.1 DelegationProvider 140 6.91.2.2 DelegationProvider 140 6.91.3 Member Function Documentation 140 6.92 Arc::DelegationProviderSOAP Class Reference 140 6.92.1 Detailed Description 141 6.92.2 Constructor & Destructor Documentation 141 6.92.2.1 DelegationProviderSOAP 141 6.92.2.2 DelegationProviderSOAP 141 6.92.3 Member Function Documentation 142 6.92.3.1 DelegateCredentialsInit 142 6.92.3.2 DelegateCredentialsInit 142 6.92.3.3 DelegatedToken 142		6.90.3	Field Doo	cumentation	139
6.90.3.3 max_size_ 139 6.90.3.4 max_usage_ 139 6.90.3.5 restricted_ 139 6.91 Arc::DelegationProvider Class Reference 139 6.91.1 Detailed Description 140 6.91.2 Constructor & Destructor Documentation 140 6.91.2.1 DelegationProvider 140 6.91.2.2 DelegationProvider 140 6.91.3 Member Function Documentation 140 6.92 Arc::DelegationProviderSOAP Class Reference 140 6.92.1 Detailed Description 141 6.92.2 Constructor & Destructor Documentation 141 6.92.2.1 DelegationProviderSOAP 141 6.92.2.2 DelegationProviderSOAP 141 6.92.3.1 DelegateCredentialsInit 142 6.92.3.2 DelegateCredentialsInit 142 6.92.3.3 DelegatedToken 142			6.90.3.1	context_lock	139
6.90.3.4 max_usage_ 139 6.90.3.5 restricted_ 139 6.91 Arc::DelegationProvider Class Reference 139 6.91.1 Detailed Description 140 6.91.2 Constructor & Destructor Documentation 140 6.91.2.1 DelegationProvider 140 6.91.2.2 DelegationProvider 140 6.91.3 Member Function Documentation 140 6.92.3 Potailed Description Decumentation 140 6.92 Arc::DelegationProviderSOAP Class Reference 140 6.92.1 Detailed Description 141 6.92.2 Constructor & Destructor Documentation 141 6.92.2.1 DelegationProviderSOAP 141 6.92.2.2 DelegationProviderSOAP 141 6.92.3 Member Function Documentation 142 6.92.3.2 DelegateCredentialsInit 142 6.92.3.3 DelegateCredentialsInit 142 6.92.3.3 DelegateCredentialsInit 142 6.92.3.3 DelegatedToken 142			6.90.3.2	max_duration	139
6.90.3.5 restricted_ 139 6.91 Arc::DelegationProvider Class Reference 139 6.91.1 Detailed Description 140 6.91.2 Constructor & Destructor Documentation 140 6.91.2.1 DelegationProvider 140 6.91.2.2 DelegationProvider 140 6.91.3 Member Function Documentation 140 6.91.3.1 Delegate 140 6.92 Arc::DelegationProviderSOAP Class Reference 140 6.92.1 Detailed Description 141 6.92.2 Constructor & Destructor Documentation 141 6.92.2.1 DelegationProviderSOAP 141 6.92.2.2 DelegationProviderSOAP 141 6.92.3 Member Function Documentation 142 6.92.3.1 DelegateCredentialsInit 142 6.92.3.2 DelegateCredentialsInit 142 6.92.3.3 DelegatedToken 142			6.90.3.3	max_size	139
6.91 Arc::DelegationProvider Class Reference 139 6.91.1 Detailed Description 140 6.91.2 Constructor & Destructor Documentation 140 6.91.2.1 DelegationProvider 140 6.91.2.2 DelegationProvider 140 6.91.3 Member Function Documentation 140 6.92 Arc::DelegationProviderSOAP Class Reference 140 6.92.1 Detailed Description 141 6.92.2 Constructor & Destructor Documentation 141 6.92.2.1 DelegationProviderSOAP 141 6.92.2.2 DelegationProviderSOAP 141 6.92.3 Member Function Documentation 142 6.92.3.1 DelegateCredentialsInit 142 6.92.3.2 DelegateCredentialsInit 142 6.92.3.3 DelegatedToken 142			6.90.3.4	max_usage	139
6.91.1 Detailed Description 140 6.91.2 Constructor & Destructor Documentation 140 6.91.2.1 DelegationProvider 140 6.91.2.2 DelegationProvider 140 6.91.3 Member Function Documentation 140 6.91.3.1 Delegate 140 6.92 Arc::DelegationProviderSOAP Class Reference 140 6.92.1 Detailed Description 141 6.92.2 Constructor & Destructor Documentation 141 6.92.2.1 DelegationProviderSOAP 141 6.92.3 Member Function Documentation 142 6.92.3.1 DelegateCredentialsInit 142 6.92.3.2 DelegateCredentialsInit 142 6.92.3.3 DelegateCredentialsInit 142 6.92.3.3 DelegatedToken 142			6.90.3.5	restricted	139
6.91.2 Constructor & Destructor Documentation 140 6.91.2.1 DelegationProvider 140 6.91.2.2 DelegationProvider 140 6.91.3 Member Function Documentation 140 6.91.3.1 Delegate 140 6.92 Arc::DelegationProviderSOAP Class Reference 140 6.92.1 Detailed Description 141 6.92.2 Constructor & Destructor Documentation 141 6.92.2.1 DelegationProviderSOAP 141 6.92.2.2 DelegationProviderSOAP 141 6.92.3 Member Function Documentation 142 6.92.3.1 DelegateCredentialsInit 142 6.92.3.2 DelegateCredentialsInit 142 6.92.3.3 DelegatedToken 142	6.91	Arc::De	elegationP	Provider Class Reference	139
6.91.2.1 DelegationProvider 140 6.91.2.2 DelegationProvider 140 6.91.3 Member Function Documentation 140 6.91.3.1 Delegate 140 6.92 Arc::DelegationProviderSOAP Class Reference 140 6.92.1 Detailed Description 141 6.92.2 Constructor & Destructor Documentation 141 6.92.2.1 DelegationProviderSOAP 141 6.92.2.2 DelegationProviderSOAP 141 6.92.3 Member Function Documentation 142 6.92.3.1 DelegateCredentialsInit 142 6.92.3.2 DelegateCredentialsInit 142 6.92.3.3 DelegatedToken 142		6.91.1	Detailed	Description	140
6.91.2.2 DelegationProvider 140 6.91.3 Member Function Documentation 140 6.91.3.1 Delegate 140 6.92 Arc::DelegationProviderSOAP Class Reference 140 6.92.1 Detailed Description 141 6.92.2 Constructor & Destructor Documentation 141 6.92.2.1 DelegationProviderSOAP 141 6.92.2.2 DelegationProviderSOAP 141 6.92.3 Member Function Documentation 142 6.92.3.1 DelegateCredentialsInit 142 6.92.3.2 DelegateCredentialsInit 142 6.92.3.3 DelegatedToken 142		6.91.2	Construc	tor & Destructor Documentation	140
6.91.3 Member Function Documentation 140 6.91.3.1 Delegate 140 6.92 Arc::DelegationProviderSOAP Class Reference 140 6.92.1 Detailed Description 141 6.92.2 Constructor & Destructor Documentation 141 6.92.2.1 DelegationProviderSOAP 141 6.92.2.2 DelegationProviderSOAP 141 6.92.3 Member Function Documentation 142 6.92.3.1 DelegateCredentialsInit 142 6.92.3.2 DelegateCredentialsInit 142 6.92.3.3 DelegatedToken 142			6.91.2.1	DelegationProvider	140
6.91.3.1 Delegate 140 6.92 Arc::DelegationProviderSOAP Class Reference 140 6.92.1 Detailed Description 141 6.92.2 Constructor & Destructor Documentation 141 6.92.2.1 DelegationProviderSOAP 141 6.92.2.2 DelegationProviderSOAP 141 6.92.3 Member Function Documentation 142 6.92.3.1 DelegateCredentialsInit 142 6.92.3.2 DelegateCredentialsInit 142 6.92.3.3 DelegatedToken 142			6.91.2.2	DelegationProvider	140
6.92 Arc::DelegationProviderSOAP Class Reference 140 6.92.1 Detailed Description 141 6.92.2 Constructor & Destructor Documentation 141 6.92.2.1 DelegationProviderSOAP 141 6.92.2.2 DelegationProviderSOAP 141 6.92.3 Member Function Documentation 142 6.92.3.1 DelegateCredentialsInit 142 6.92.3.2 DelegateCredentialsInit 142 6.92.3.3 DelegatedToken 142		6.91.3	Member	Function Documentation	140
6.92.1 Detailed Description 141 6.92.2 Constructor & Destructor Documentation 141 6.92.2.1 DelegationProviderSOAP 141 6.92.2.2 DelegationProviderSOAP 141 6.92.3 Member Function Documentation 142 6.92.3.1 DelegateCredentialsInit 142 6.92.3.2 DelegateCredentialsInit 142 6.92.3.3 DelegatedToken 142			6.91.3.1	Delegate	140
6.92.2 Constructor & Destructor Documentation 141 6.92.2.1 DelegationProviderSOAP 141 6.92.2.2 DelegationProviderSOAP 141 6.92.3 Member Function Documentation 142 6.92.3.1 DelegateCredentialsInit 142 6.92.3.2 DelegateCredentialsInit 142 6.92.3.3 DelegatedToken 142	6.92	Arc::De	elegationP	ProviderSOAP Class Reference	140
6.92.2.1 DelegationProviderSOAP 141 6.92.2.2 DelegationProviderSOAP 141 6.92.3 Member Function Documentation 142 6.92.3.1 DelegateCredentialsInit 142 6.92.3.2 DelegateCredentialsInit 142 6.92.3.3 DelegatedToken 142		6.92.1	Detailed	Description	141
6.92.2.2 DelegationProviderSOAP 141 6.92.3 Member Function Documentation 142 6.92.3.1 DelegateCredentialsInit 142 6.92.3.2 DelegateCredentialsInit 142 6.92.3.3 DelegatedToken 142		6.92.2	Construc	tor & Destructor Documentation	141
6.92.3 Member Function Documentation 142 6.92.3.1 DelegateCredentialsInit 142 6.92.3.2 DelegateCredentialsInit 142 6.92.3.3 DelegatedToken 142			6.92.2.1	DelegationProviderSOAP	141
6.92.3.1DelegateCredentialsInit1426.92.3.2DelegateCredentialsInit1426.92.3.3DelegatedToken142			6.92.2.2	DelegationProviderSOAP	141
6.92.3.2 DelegateCredentialsInit 142 6.92.3.3 DelegatedToken 142		6.92.3	Member	Function Documentation	142
6.92.3.3 DelegatedToken			6.92.3.1	DelegateCredentialsInit	142
			6.92.3.2	DelegateCredentialsInit	142
			6.92.3.3	DelegatedToken	142
6.92.3.4 ID			6.92.3.4	ID	142

xviii CONTENTS

CONTENTS xix

6.103.2.3 evaluate	49
6.103.2.4 evaluate	49
6.103.2.5 evaluate	49
6.103.2.6 evaluate	49
6.103.2.7 evaluate	50
6.103.2.8 evaluate	.50
6.103.2.9 evaluate	.50
6.103.2.10getAlgFactory	50
6.103.2.1 lgetAttrFactory	50
6.103.2.12getFnFactory	50
6.103.2.13getName	50
6.103.2.14setCombiningAlg	50
6.103.2.15setCombiningAlg	50
6.104ArcSec::EvaluatorContext Class Reference	51
6.104.1 Detailed Description	51
6.104.2 Member Function Documentation	51
6.104.2.1 operator AlgFactory *	.51
6.104.2.2 operator AttributeFactory *	51
6.104.2.3 operator FnFactory *	51
6.105ArcSec::EvaluatorLoader Class Reference	.51
6.105.1 Detailed Description	52
6.105.2 Member Function Documentation	52
6.105.2.1 getEvaluator	.52
6.105.2.2 getEvaluator	52
6.105.2.3 getEvaluator	52
6.105.2.4 getPolicy	.52
6.105.2.5 getPolicy	52
6.105.2.6 getRequest	52
6.105.2.7 getRequest	52
6.106Arc::ExecutableType Class Reference	53
6.107 Arc::ExecutionTarget Class Reference	53
6.107.1 Detailed Description	53
6.107.2 Constructor & Destructor Documentation	53
6.107.2.1 ExecutionTarget	53
6.107.2.2 ExecutionTarget	54
6.107.2.3 ExecutionTarget	54

6.107.3 Member Function Documentation
6.107.3.1 GetSubmitter
6.107.3.2 operator=
6.107.3.3 Print
6.107.3.4 Update
6.107.4 Field Documentation
6.107.4.1 ApplicationEnvironments
6.107.4.2 ComputingShareName
6.107.4.3 MaxDiskSpace
6.107.4.4 MaxMainMemory
6.107.4.5 MaxVirtualMemory
6.107.4.6 OperatingSystem
6.108Arc::ExpirationReminder Class Reference
6.108.1 Detailed Description
6.108.2 Member Function Documentation
6.108.2.1 getExpiryTime
6.108.2.2 getReservationID
6.108.2.3 operator<
6.109 Arc::FileCache Class Reference
6.109.1 Detailed Description
6.109.2 Constructor & Destructor Documentation
6.109.2.1 FileCache
6.109.2.2 FileCache
6.109.2.3 FileCache
6.109.2.4 FileCache
6.109.3 Member Function Documentation
6.109.3.1 AddDN
5.107.5.1.1.1.4.1.1.1.1.1.1.1.1.1.1.1.1.1.1.1
6.109.3.2 CheckCreated
6.109.3.2 CheckCreated
6.109.3.2 CheckCreated 159 6.109.3.3 CheckDN 160
6.109.3.2 CheckCreated 159 6.109.3.3 CheckDN 160 6.109.3.4 CheckValid 160
6.109.3.2 CheckCreated 159 6.109.3.3 CheckDN 160 6.109.3.4 CheckValid 160 6.109.3.5 Copy 160
6.109.3.2 CheckCreated 159 6.109.3.3 CheckDN 160 6.109.3.4 CheckValid 160 6.109.3.5 Copy 160 6.109.3.6 File 160
6.109.3.2 CheckCreated 159 6.109.3.3 CheckDN 160 6.109.3.4 CheckValid 160 6.109.3.5 Copy 160 6.109.3.6 File 160 6.109.3.7 GetCreated 160

CONTENTS xxi

6.109.3.1 loperator==
6.109.3.12Release
6.109.3.13SetValid
6.109.3.14Start
6.109.3.15Stop
6.109.3.16StopAndDelete
6.110FileCacheHash Class Reference
6.110.1 Detailed Description
6.110.2 Member Function Documentation
6.110.2.1 getHash
6.110.2.2 maxLength
6.111 Arc::FileInfo Class Reference
6.111.1 Detailed Description
6.112Arc::FileLock Class Reference
6.112.1 Detailed Description
6.113Arc::FileType Class Reference
6.114Arc::FinderLoader Class Reference
6.115ArcSec::FnFactory Class Reference
6.115.1 Detailed Description
6.115.2 Member Function Documentation
6.115.2.1 createFn
6.116ArcSec::Function Class Reference
6.116.1 Detailed Description
6.116.2 Member Function Documentation
6.116.2.1 evaluate
6.116.2.2 evaluate
6.117ArcSec::GenericAttribute Class Reference
6.117.1 Member Function Documentation
6.117.1.1 encode
6.117.1.2 equal
6.117.1.3 getId
6.117.1.4 getType
6.118Arc::GlobusResult Class Reference
6.119Arc::GSSCredential Class Reference
6.120Arc::HakaClient Class Reference
6.120.1 Member Function Documentation

6.120.1.1 processConsent
6.120.1.2 processIdP2Confusa
6.120.1.3 processIdPLogin
6.121 Arc::HTTPClientInfo Struct Reference
6.122Arc::InfoCache Class Reference
6.122.1 Detailed Description
6.122.2 Constructor & Destructor Documentation
6.122.2.1 InfoCache
6.123 Arc::InfoCacheInterface Class Reference
6.123.1 Member Function Documentation
6.123.1.1 Get
6.124Arc::InfoFilter Class Reference
6.124.1 Detailed Description
6.124.2 Constructor & Destructor Documentation
6.124.2.1 InfoFilter
6.124.3 Member Function Documentation
6.124.3.1 Filter
6.124.3.2 Filter
6.125Arc::InfoRegister Class Reference
6.125.1 Detailed Description
6.126Arc::InfoRegisterContainer Class Reference
6.126.1 Detailed Description
6.126.2 Member Function Documentation
6.126.2.1 addRegistrar
6.126.2.2 addService
6.126.2.3 removeService
6.127 Arc::InfoRegisters Class Reference
6.127.1 Detailed Description
6.127.2 Constructor & Destructor Documentation
6.127.2.1 InfoRegisters
6.128Arc::InfoRegistrar Class Reference
6.128.1 Detailed Description
6.128.2 Member Function Documentation
6.128.2.1 addService
6.128.2.2 registration
6.129Arc::InformationContainer Class Reference

6.129.1 Detailed Description
6.129.2 Constructor & Destructor Documentation
6.129.2.1 InformationContainer
6.129.3 Member Function Documentation
6.129.3.1 Acquire
6.129.3.2 Assign
6.129.3.3 Get
6.129.4 Field Documentation
6.129.4.1 doc
6.130Arc::InformationInterface Class Reference
6.130.1 Detailed Description
6.130.2 Constructor & Destructor Documentation
6.130.2.1 InformationInterface
6.130.3 Member Function Documentation
6.130.3.1 Get
6.130.4 Field Documentation
6.130.4.1 lock
6.131 Arc::InformationRequest Class Reference
6.131.1 Detailed Description
6.131.2 Constructor & Destructor Documentation
6.131.2.1 InformationRequest
6.131.2.2 InformationRequest
6.131.2.3 InformationRequest
6.131.2.4 InformationRequest
6.131.3 Member Function Documentation
6.131.3.1 SOAP
6.132Arc::InformationResponse Class Reference
6.132.1 Detailed Description
6.132.2 Constructor & Destructor Documentation
6.132.2.1 InformationResponse
6.132.3 Member Function Documentation
6.132.3.1 Result
6.133 Arc::IniConfig Class Reference
6.134Arc::initializeCredentialsType Class Reference
6.135 ArcSec::InRangeFunction Class Reference
6.135.1 Member Function Documentation

192
192 192
192
193 193
193
193
194
194
194
194
194
194
195
195
195
195
195
196
196
196
196
196
197
197
197
197
197
197
197
198
198
198
198
198

6.157.3.1 log	 . 198
6.158ArcSec::MatchFunction Class Reference	 . 199
6.158.1 Detailed Description	 . 199
6.158.2 Member Function Documentation	 . 199
6.158.2.1 evaluate	 . 199
6.158.2.2 evaluate	 . 200
6.158.2.3 getFunctionName	 . 200
6.159Arc::MCC Class Reference	 . 200
6.159.1 Detailed Description	 . 201
6.159.2 Constructor & Destructor Documentation	 . 201
6.159.2.1 MCC	 . 201
6.159.3 Member Function Documentation	 . 201
6.159.3.1 AddSecHandler	 . 201
6.159.3.2 Next	 . 201
6.159.3.3 process	 . 201
6.159.3.4 ProcessSecHandlers	 . 202
6.159.3.5 Unlink	 . 202
6.159.4 Field Documentation	 . 202
6.159.4.1 logger	 . 202
6.159.4.2 next	 . 202
6.159.4.3 sechandlers	 . 202
6.160Arc::MCC_Status Class Reference	 . 202
6.160.1 Detailed Description	 . 203
6.160.2 Constructor & Destructor Documentation	 . 203
6.160.2.1 MCC_Status	 . 203
6.160.3 Member Function Documentation	 . 203
6.160.3.1 getExplanation	 . 203
6.160.3.2 getKind	 . 203
6.160.3.3 getOrigin	 . 204
6.160.3.4 isOk	 . 204
6.160.3.5 operator bool	 . 204
6.160.3.6 operator std::string	 . 204
6.160.3.7 operator!	 . 204
6.161 Arc::MCCConfig Class Reference	 . 205
6.161.1 Member Function Documentation	 . 205
6.161.1.1 MakeConfig	 . 205

xxviii CONTENTS

6.162Arc::MCCInterface Class Reference
6.162.1 Detailed Description
6.162.2 Member Function Documentation
6.162.2.1 process
6.163 Arc::MCCLoader Class Reference
6.163.1 Detailed Description
6.163.2 Constructor & Destructor Documentation
6.163.2.1 MCCLoader
6.163.2.2 ~MCCLoader
6.163.3 Member Function Documentation
6.163.3.1 operator[]
6.164Arc::MCCPluginArgument Class Reference
6.165 Arc::MD5Sum Class Reference
6.165.1 Detailed Description
6.166Arc::MemoryAllocationException Class Reference
6.167 Arc::Message Class Reference
6.167.1 Detailed Description
6.167.2 Constructor & Destructor Documentation
6.167.2.1 Message
6.167.2.2 Message
6.167.2.3 Message
6.167.2.4 ~ Message
6.167.3 Member Function Documentation
6.167.3.1 Attributes
6.167.3.2 Auth
6.167.3.3 AuthContext
6.167.3.4 AuthContext
6.167.3.5 Context
6.167.3.6 Context
6.167.3.7 operator=
6.167.3.8 Payload
6.167.3.9 Payload
6.168Arc::MessageAttributes Class Reference
6.168.1 Detailed Description
6.168.2 Constructor & Destructor Documentation
6.168.2.1 MessageAttributes

CONTENTS	xxix

(1(0.2)M 1 F 1' D 1 1'
6.168.3 Member Function Documentation
6.168.3.1 add
6.168.3.2 count
6.168.3.3 get
6.168.3.4 getAll
6.168.3.5 remove
6.168.3.6 removeAll
6.168.3.7 set
6.168.4 Field Documentation
6.168.4.1 attributes
6.169Arc::MessageAuth Class Reference
6.169.1 Detailed Description
6.169.2 Member Function Documentation
6.169.2.1 Export
6.169.2.2 Filter
6.170Arc::MessageAuthContext Class Reference
6.170.1 Detailed Description
6.171 Arc::MessageContext Class Reference
6.171.1 Detailed Description
6.171.2 Member Function Documentation
6.171.2.1 Add
6.172Arc::MessageContextElement Class Reference
6.172.1 Detailed Description
6.173 Arc::MessagePayload Class Reference
6.173.1 Detailed Description
6.174Arc::ModuleDesc Class Reference
6.174.1 Detailed Description
6.175 Arc::ModuleManager Class Reference
6.175.1 Detailed Description
6.175.2 Constructor & Destructor Documentation
6.175.2.1 ModuleManager
6.175.3 Member Function Documentation
6.175.3.1 find
6.175.3.2 findLocation
6.175.3.3 load
6.175.3.4 makePersistent
0.1/3.3.7 marci cisistent

6.175.3.5 makePersistent
6.175.3.6 reload
6.175.3.7 setCfg
6.175.3.8 unload
6.175.3.9 unload
6.176Arc::MultiSecAttr Class Reference
6.176.1 Detailed Description
6.176.2 Member Function Documentation
6.176.2.1 Export
6.176.2.2 operator bool
6.177Arc::MySQLDatabase Class Reference
6.177.1 Detailed Description
6.177.2 Member Function Documentation
6.177.2.1 close
6.177.2.2 connect
6.177.2.3 enable_ssl
6.177.2.4 isconnected
6.177.2.5 shutdown
6.178Arc::MySQLQuery Class Reference
6.178.1 Member Function Documentation
6.178.1.1 execute
6.178.1.2 get_array
6.178.1.3 get_num_colums
6.178.1.4 get_num_rows
6.178.1.5 get_row
6.178.1.6 get_row
6.178.1.7 get_row_field
6.179Arc::NotificationType Class Reference
6.180Arc::NS Class Reference
6.181Arc::OAuthConsumer Class Reference
6.181.1 Detailed Description
6.181.2 Constructor & Destructor Documentation
6.181.2.1 OAuthConsumer
6.181.3 Member Function Documentation
6.181.3.1 approveCSR
6.181.3.2 parseDN
<u>r</u>

CONTENTS	xxxi

6.181.3.3 processLogin	25
6.181.3.4 pushCSR	25
6.181.3.5 storeCert	25
6.182Arc::OpenIdpClient Class Reference	25
6.182.1 Member Function Documentation	25
6.182.1.1 processConsent	25
6.182.1.2 processIdP2Confusa	26
6.182.1.3 processIdPLogin	26
6.183Arc::OptionParser Class Reference	26
6.184ArcSec::OrderedCombiningAlg Class Reference	26
6.185 passwd Struct Reference	26
6.186Arc::PathIterator Class Reference	27
6.186.1 Detailed Description	27
6.186.2 Constructor & Destructor Documentation	27
6.186.2.1 PathIterator	27
6.186.3 Member Function Documentation	27
6.186.3.1 operator bool	27
6.186.3.2 operator*	.27
6.186.3.3 operator++	.27
6.186.3.4 operator	.27
6.186.3.5 Rest	28
6.187Arc::PayloadRaw Class Reference	28
6.187.1 Detailed Description	28
6.187.2 Constructor & Destructor Documentation	28
6.187.2.1 PayloadRaw	.28
6.187.2.2 ~PayloadRaw	29
6.187.3 Member Function Documentation	29
6.187.3.1 Buffer	29
6.187.3.2 BufferPos	.29
6.187.3.3 BufferSize	.29
6.187.3.4 Content	.29
6.187.3.5 Insert	.29
6.187.3.6 Insert	.29
6.187.3.7 operator[]	.29
6.187.3.8 Size	
6.187.3.9 Truncate	.30

xxxii CONTENTS

6.188Arc::PayloadRawBuf Struct Reference	30
6.188.1 Field Documentation	30
6.188.1.1 allocated	30
6.188.1.2 length	30
6.188.1.3 size	30
6.189Arc::PayloadRawInterface Class Reference	30
6.189.1 Detailed Description	31
6.189.2 Member Function Documentation	31
6.189.2.1 Buffer	31
6.189.2.2 BufferPos	31
6.189.2.3 BufferSize	32
6.189.2.4 Content	32
6.189.2.5 Insert	32
6.189.2.6 Insert	32
6.189.2.7 operator[]	32
6.189.2.8 Size	32
6.189.2.9 Truncate	32
6.190Arc::PayloadSOAP Class Reference	33
6.190.1 Detailed Description	33
6.190.2 Constructor & Destructor Documentation	33
6.190.2.1 PayloadSOAP	33
6.190.2.2 PayloadSOAP	33
6.190.2.3 PayloadSOAP	33
6.191 Arc::PayloadStream Class Reference	33
6.191.1 Detailed Description	34
6.191.2 Constructor & Destructor Documentation	34
6.191.2.1 PayloadStream	34
6.191.2.2 ~PayloadStream	35
6.191.3 Member Function Documentation	35
6.191.3.1 Get	35
6.191.3.2 Get	35
6.191.3.3 Get	35
6.191.3.4 Limit	35
6.191.3.5 operator bool	35
6.191.3.6 operator!	35
6.191.3.7 Pos	36

CONTENTS	xxxiii
----------	--------

6.191.3.8 Put	236
6.191.3.9 Put	236
6.191.3.10Put	236
6.191.3.11Size	236
6.191.3.12Timeout	236
6.191.3.13Timeout	236
6.191.4 Field Documentation	237
6.191.4.1 handle	237
6.191.4.2 seekable	237
6.192Arc::PayloadStreamInterface Class Reference	237
6.192.1 Detailed Description	238
6.192.2 Member Function Documentation	238
6.192.2.1 Get	238
6.192.2.2 Get	238
6.192.2.3 Get	238
6.192.2.4 Limit	238
6.192.2.5 operator bool	238
6.192.2.6 operator!	238
6.192.2.7 Pos	238
6.192.2.8 Put	239
6.192.2.9 Put	239
6.192.2.10Put	239
6.192.2.11Size	239
6.192.2.12Timeout	239
6.192.2.13Timeout	239
6.193 Arc::PayloadWSRF Class Reference	239
6.193.1 Detailed Description	240
6.193.2 Constructor & Destructor Documentation	240
6.193.2.1 PayloadWSRF	240
6.193.2.2 PayloadWSRF	240
6.193.2.3 PayloadWSRF	240
6.194ArcSec::PDP Class Reference	240
6.194.1 Detailed Description	241
6.195ArcSec::PDPConfigContext Class Reference	
6.196ArcSec::PDPPluginArgument Class Reference	
6.197 Arc::Period Class Reference	

6.197.1 Constructor & Destructor Documentation	12
6.197.1.1 Period	12
6.197.1.2 Period	12
6.197.1.3 Period	12
6.197.1.4 Period	12
6.197.2 Member Function Documentation	12
6.197.2.1 GetPeriod	12
6.197.2.2 istr	12
6.197.2.3 operator std::string	13
6.197.2.4 operator!=	13
6.197.2.5 operator<	13
6.197.2.6 operator<=	13
6.197.2.7 operator=	13
6.197.2.8 operator=	13
6.197.2.9 operator==	13
6.197.2.10operator>	13
6.197.2.1 loperator>=	13
6.197.2.12SetPeriod	13
6.198ArcSec::PeriodAttribute Class Reference	14
6.198.1 Detailed Description	14
6.198.2 Member Function Documentation	14
6.198.2.1 encode	14
6.198.2.2 equal	14
6.198.2.3 getId	14
6.198.2.4 getType	14
6.199ArcSec::PermitOverridesCombiningAlg Class Reference	15
6.199.1 Detailed Description	15
6.199.2 Member Function Documentation	15
6.199.2.1 combine	15
6.199.2.2 getalgId	15
6.200Arc::Plexer Class Reference	16
6.200.1 Detailed Description	16
6.200.2 Constructor & Destructor Documentation	16
6.200.2.1 Plexer	16
6.200.2.2 ~Plexer	17
6.200.3 Member Function Documentation	17

CONTENTS	XXX
----------	-----

6.200.3.1 Next
6.200.3.2 process
6.200.4 Field Documentation
6.200.4.1 logger
6.201 Arc::PlexerEntry Class Reference
6.201.1 Detailed Description
6.202 Arc::Plugin Class Reference
6.202.1 Detailed Description
6.203 Arc::PluginArgument Class Reference
6.203.1 Detailed Description
6.203.2 Member Function Documentation
6.203.2.1 get_factory
6.203.2.2 get_module
6.204Arc::PluginDesc Class Reference
6.204.1 Detailed Description
6.205 Arc::PluginDescriptor Struct Reference
6.205.1 Detailed Description
6.206Arc::PluginsFactory Class Reference
6.206.1 Detailed Description
6.206.2 Constructor & Destructor Documentation
6.206.2.1 PluginsFactory
6.206.3 Member Function Documentation
6.206.3.1 load
6.206.3.2 report
6.206.3.3 scan
6.206.3.4 TryLoad
6.207 ArcSec::Policy Class Reference
6.207.1 Detailed Description
6.207.2 Constructor & Destructor Documentation
6.207.2.1 Policy
6.207.2.2 Policy
6.207.3 Member Function Documentation
6.207.3.1 addPolicy
6.207.3.2 eval
6.207.3.2 eval

6.207.3.5 getEvalResult
6.207.3.6 getName
6.207.3.7 make_policy
6.207.3.8 setEvalResult
6.207.3.9 setEvaluatorContext
6.208ArcSec::PolicyStore::PolicyElement Class Reference
6.209 ArcSec::PolicyParser Class Reference
6.209.1 Detailed Description
6.209.2 Member Function Documentation
6.209.2.1 parsePolicy
6.210ArcSec::PolicyStore Class Reference
6.210.1 Detailed Description
6.210.2 Constructor & Destructor Documentation
6.210.2.1 PolicyStore
6.211 Arc::PrintF< T0, T1, T2, T3, T4, T5, T6, T7 > Class Template Reference
6.212Arc::PrintFBase Class Reference
6.213 Arc::Profile Class Reference
6.214ArcCredential::PROXYCERTINFO_st Struct Reference
6.215 ArcCredential::PROXYPOLICY_st Struct Reference
6.216Arc::Query Class Reference
6.216.1 Constructor & Destructor Documentation
6.216.1.1 Query
6.216.1.2 Query
6.216.1.3 ~Query
6.216.2 Member Function Documentation
6.216.2.1 execute
6.216.2.2 get_array
6.216.2.3 get_num_colums
6.216.2.4 get_num_rows
6.216.2.5 get_row
6.216.2.6 get_row
6.216.2.7 get_row_field
6.217 Arc::Range < T > Class Template Reference
6.218Arc::Register_Info_Type Struct Reference
6.219Arc::RegisteredService Class Reference
6.219.1 Detailed Description

CONTENTS	xxxvii
----------	--------

6.219.2 Constructor & Destructor Documentation	260
6.219.2.1 RegisteredService	260
6.220Arc::RegularExpression Class Reference	260
6.220.1 Detailed Description	261
6.220.2 Member Function Documentation	261
6.220.2.1 match	261
6.221 ArcSec::Request Class Reference	261
6.221.1 Detailed Description	262
6.221.2 Constructor & Destructor Documentation	262
6.221.2.1 Request	262
6.221.2.2 Request	262
6.221.3 Member Function Documentation	262
6.221.3.1 addRequestItem	262
6.221.3.2 getEvalName	262
6.221.3.3 getName	262
6.221.3.4 getRequestItems	262
6.221.3.5 make_request	262
6.221.3.6 setAttributeFactory	263
6.221.3.7 setRequestItems	263
6.222ArcSec::RequestAttribute Class Reference	263
6.222.1 Detailed Description	263
6.222.2 Constructor & Destructor Documentation	263
6.222.2.1 RequestAttribute	263
6.222.3 Member Function Documentation	263
6.222.3.1 duplicate	263
6.223 ArcSec::RequestItem Class Reference	264
6.223.1 Detailed Description	264
6.223.2 Constructor & Destructor Documentation	264
6.223.2.1 RequestItem	264
6.224 ArcSec::RequestTuple Class Reference	264
6.225 Arc::ResourceSlotType Class Reference	264
6.226Arc::ResourcesType Class Reference	264
6.227 Arc::ResourceTargetType Class Reference	265
6.228 ArcSec::Response Class Reference	265
6.228.1 Detailed Description	265
6.229ArcSec::ResponseItem Class Reference	265

xxxviii CONTENTS

6.229.1 Detailed Description
6.230ArcSec::ResponseList Class Reference
6.231 Arc::RSL Class Reference
6.232Arc::RSLBoolean Class Reference
6.233 Arc::RSLConcat Class Reference
6.234Arc::RSLCondition Class Reference
6.235 Arc::RSLList Class Reference
6.236Arc::RSLLiteral Class Reference
6.237 Arc::RSLParser Class Reference
6.238Arc::RSLSequence Class Reference
6.239 Arc::RSLValue Class Reference
6.240 Arc::RSLVariable Class Reference
6.241 Arc::Run Class Reference
6.241.1 Detailed Description
6.241.2 Constructor & Destructor Documentation
6.241.2.1 Run
6.241.2.2 Run
6.241.2.3 ~Run
6.241.3 Member Function Documentation
6.241.3.1 Abandon
6.241.3.2 AssignStderr
6.241.3.3 AssignStdin
6.241.3.4 AssignStdout
6.241.3.5 AssignWorkingDirectory
6.241.3.6 CloseStderr
6.241.3.7 CloseStdin
6.241.3.8 CloseStdout
6.241.3.9 KeepStderr
6.241.3.10KeepStdin
6.241.3.11KeepStdout
6.241.3.12Kill
6.241.3.13operator bool
6.241.3.14operator!
6.241.3.15ReadStderr
6.241.3.16ReadStdout
6.241.3.17Result

CONTENTS	xxxix
CONTENTS	xxxix

6.241.3.18Running	271
6.241.3.19Start	271
6.241.3.20Wait	271
6.241.3.21Wait	272
6.241.3.22WriteStdin	272
6.242Arc::SAML2LoginClient Class Reference	272
6.242.1 Constructor & Destructor Documentation	272
6.242.1.1 SAML2LoginClient	272
6.242.2 Member Function Documentation	272
6.242.2.1 findSimpleSAMLInstallation	272
6.242.2.2 processLogin	273
6.243 Arc::SAML2SSOHTTPClient Class Reference	273
6.243.1 Member Function Documentation	273
6.243.1.1 approveCSR	273
6.243.1.2 parseDN	274
6.243.1.3 processConsent	274
6.243.1.4 processIdP2Confusa	274
6.243.1.5 processIdPLogin	274
6.243.1.6 processLogin	274
6.243.1.7 pushCSR	274
6.243.1.8 storeCert	274
6.244 Arc::SAMLToken Class Reference	275
6.244.1 Detailed Description	275
6.244.2 Member Enumeration Documentation	276
6.244.2.1 SAMLVersion	276
6.244.3 Constructor & Destructor Documentation	276
6.244.3.1 SAMLToken	276
6.244.3.2 SAMLToken	276
6.244.3.3 ~SAMLToken	277
6.244.4 Member Function Documentation	277
6.244.4.1 Authenticate	277
6.244.4.2 Authenticate	277
6.244.4.3 operator bool	277
6.245 Arc::ScalableTime< T > Class Template Reference	277
6.246Arc::ScalableTime< int > Class Template Reference	277
6.247 Arc::SecAttr Class Reference	278

6.247.1 Detailed Description
6.247.2 Member Function Documentation
6.247.2.1 Export
6.247.2.2 Export
6.247.2.3 Import
6.247.2.4 operator bool
6.247.2.5 operator!=
6.247.2.6 operator==
6.248Arc::SecAttrFormat Class Reference
6.248.1 Detailed Description
6.249 Arc::SecAttrValue Class Reference
6.249.1 Detailed Description
6.249.2 Member Function Documentation
6.249.2.1 operator bool
6.249.2.2 operator!=
6.249.2.3 operator==
6.250ArcSec::SecHandler Class Reference
6.250.1 Detailed Description
6.251 Arc::SecHandlerConfig Class Reference
6.252ArcSec::SecHandlerConfig Class Reference
6.252.1 Detailed Description
6.253ArcSec::SecHandlerPluginArgument Class Reference
6.254ArcSec::Security Class Reference
6.254.1 Detailed Description
6.255Arc::Service Class Reference
6.255.1 Detailed Description
6.255.2 Constructor & Destructor Documentation
6.255.2.1 Service
6.255.3 Member Function Documentation
6.255.3.1 AddSecHandler
6.255.3.2 getID
6.255.3.3 ProcessSecHandlers
6.255.3.4 RegistrationCollector
6.255.4 Field Documentation
6.255.4.1 logger
6.255.4.2 sechandlers

CONTENTS xli

6.256Arc::ServicePluginArgument Class Reference		
6.257 Arc::SimpleCondition Class Reference		
6.257.1 Detailed Description		
6.257.2 Member Function Documentation		
6.257.2.1 broadcast		
6.257.2.2 lock		
6.257.2.3 reset		
6.257.2.4 signal		
6.257.2.5 signal_nonblock		
6.257.2.6 unlock		
6.257.2.7 wait		
6.257.2.8 wait		
6.257.2.9 wait_nonblock		
6.258Arc::SimpleCounter Class Reference		
6.258.1 Member Function Documentation		
6.258.1.1 wait		
6.259Arc::SOAPMessage Class Reference		
6.259.1 Detailed Description		
6.259.2 Constructor & Destructor Documentation		
6.259.2.1 SOAPMessage		
6.259.2.2 SOAPMessage		
6.259.2.3 SOAPMessage		
6.259.2.4 ~SOAPMessage		
6.259.3 Member Function Documentation		
6.259.3.1 Attributes		
6.259.3.2 Payload		
6.259.3.3 Payload		
6.260Arc::Software Class Reference		
6.260.1 Detailed Description		
6.260.2 Member Typedef Documentation		
6.260.2.1 ComparisonOperator		
6.260.3 Member Enumeration Documentation		
6.260.3.1 ComparisonOperatorEnum		
6.260.4 Constructor & Destructor Documentation		
6.260.4.1 Software		
6.260.4.2 Software		

xlii CONTENTS

6.260.4.3 Software
6.260.4.4 Software
6.260.5 Member Function Documentation
6.260.5.1 convert
6.260.5.2 empty
6.260.5.3 getFamily
6.260.5.4 getName
6.260.5.5 getVersion
6.260.5.6 operator std::string
6.260.5.7 operator!=
6.260.5.8 operator()
6.260.5.9 operator<
6.260.5.10perator<=
6.260.5.1 loperator==
6.260.5.12operator>
6.260.5.13operator>=
6.260.5.14toString
6.260.6 Friends And Related Function Documentation
6.260.6.1 operator<<
6.260.7 Field Documentation
6.260.7.1 VERSIONTOKENS
6.261 Arc::Software Requirement Class Reference
6.261.1 Detailed Description
6.261.2 Constructor & Destructor Documentation
6.261.2.1 SoftwareRequirement
6.261.2.2 SoftwareRequirement
6.261.2.3 SoftwareRequirement
6.261.2.4 SoftwareRequirement
6.261.3 Member Function Documentation
6.261.3.1 add
6.261.3.2 add
6.261.3.3 clear
6.261.3.4 empty
6.261.3.5 getComparisonOperatorList
6.261.3.6 getSoftwareList
6.261.3.7 isRequiringAll

CONTENTS	xliii
----------	-------

6.261.3.8 isResolved	99
6.261.3.9 isSatisfied	99
6.261.3.10sSatisfied	00
6.261.3.1 lisSatisfied	00
6.261.3.12operator=	01
6.261.3.13selectSoftware	01
6.261.3.14selectSoftware	01
6.261.3.15selectSoftware	02
6.261.3.16setRequirement	02
6.262ArcSec::Source Class Reference	02
6.262.1 Detailed Description	03
6.262.2 Constructor & Destructor Documentation	03
6.262.2.1 Source	03
6.262.2.2 Source	03
6.263ArcSec::SourceFile Class Reference	03
6.263.1 Detailed Description	04
6.264ArcSec::SourceURL Class Reference	04
6.264.1 Detailed Description	04
6.265ArcSec::StringAttribute Class Reference	05
6.265.1 Member Function Documentation	05
6.265.1.1 encode	05
6.265.1.2 equal	05
6.265.1.3 getId	05
6.265.1.4 getType	05
6.266Arc::Submitter Class Reference	06
6.266.1 Detailed Description	06
6.266.2 Member Function Documentation	06
6.266.2.1 Migrate	06
6.266.2.2 Submit	06
6.267 Arc::SubmitterLoader Class Reference	07
6.267.1 Detailed Description	07
6.267.2 Constructor & Destructor Documentation	07
6.267.2.1 SubmitterLoader	07
6.267.2.2 ~SubmitterLoader	07
6.267.3 Member Function Documentation	07
6.267.3.1 GetSubmitters	07

XIIV CONTENTS

6.267.3.2 load
6.268 Arc::SubmitterPluginArgument Class Reference
6.269 Arc::TargetGenerator Class Reference
6.269.1 Detailed Description
6.269.2 Constructor & Destructor Documentation
6.269.2.1 TargetGenerator
6.269.3 Member Function Documentation
6.269.3.1 AddIndexServer
6.269.3.2 AddJob
6.269.3.3 AddService
6.269.3.4 AddTarget
6.269.3.5 FoundJobs
6.269.3.6 FoundTargets
6.269.3.7 GetTargets
6.269.3.8 ModifyFoundTargets
6.269.3.9 PrintTargetInfo
6.269.3.10ServiceCounter
6.270Arc::TargetRetriever Class Reference
6.270.1 Detailed Description
6.270.2 Constructor & Destructor Documentation
6.270.2.1 TargetRetriever
6.270.3 Member Function Documentation
6.270.3.1 GetTargets
6.271 Arc::TargetRetrieverLoader Class Reference
6.271.1 Detailed Description
6.271.2 Constructor & Destructor Documentation
6.271.2.1 TargetRetrieverLoader
6.271.2.2 ~TargetRetrieverLoader
6.271.3 Member Function Documentation
6.271.3.1 GetTargetRetrievers
6.271.3.2 load
6.272Arc::TargetRetrieverPluginArgument Class Reference
6.273 Test::TestMCC Class Reference
6.274Test::TestService Class Reference
6.274.1 Member Function Documentation
6.274.1.1 process

6.275 Arc::ThreadInitializer Class Reference	315
6.276Arc::ThreadRegistry Class Reference	316
6.276.1 Detailed Description	316
6.276.2 Member Function Documentation	316
6.276.2.1 WaitForExit	316
6.276.2.2 WaitOrCancel	316
6.277 Arc::Time Class Reference	316
6.277.1 Detailed Description	317
6.277.2 Constructor & Destructor Documentation	317
6.277.2.1 Time	317
6.277.2.2 Time	317
6.277.2.3 Time	317
6.277.2.4 Time	317
6.277.3 Member Function Documentation	317
6.277.3.1 GetFormat	317
6.277.3.2 GetTime	318
6.277.3.3 operator std::string	318
6.277.3.4 operator!=	318
6.277.3.5 operator+	318
6.277.3.6 operator	318
6.277.3.7 operator	318
6.277.3.8 operator<	318
6.277.3.9 operator<=	318
6.277.3.10operator=	318
6.277.3.1 loperator=	318
6.277.3.12operator=	318
6.277.3.13operator=	319
6.277.3.14operator==	319
6.277.3.15operator>	319
6.277.3.16operator>=	319
6.277.3.17SetFormat	319
6.277.3.18SetTime	319
6.277.3.19SetTime	319
6.277.3.20str	319
6.278ArcSec::TimeAttribute Class Reference	319
6.278.1 Detailed Description	320

xlvi CONTENTS

6.278.2 Member Function Documentation	320
6.278.2.1 encode	
6.278.2.2 equal	
6.278.2.3 getId	
6.278.2.4 getType	
6.279Arc::URL Class Reference	
6.279.1 Member Enumeration Documentation	322
6.279.1.1 Scope	322
6.279.2 Constructor & Destructor Documentation	322
6.279.2.1 URL	322
6.279.2.2 URL	322
6.279.2.3 ~URL	323
6.279.3 Member Function Documentation	323
6.279.3.1 AddLDAPAttribute	323
6.279.3.2 AddMetaDataOption	323
6.279.3.3 AddOption	323
6.279.3.4 BaseDN2Path	323
6.279.3.5 ChangeHost	323
6.279.3.6 ChangeLDAPFilter	323
6.279.3.7 ChangeLDAPScope	323
6.279.3.8 ChangePath	323
6.279.3.9 ChangePort	323
6.279.3.10ChangeProtocol	324
6.279.3.11CommonLocOption	324
6.279.3.12CommonLocOptions	324
6.279.3.13ConnectionURL	324
6.279.3.14FullPath	324
6.279.3.15fullstr	324
6.279.3.16Host	324
6.279.3.17HTTPOption	324
6.279.3.18HTTPOptions	324
6.279.3.19IsSecureProtocol	325
6.279.3.20LDAPAttributes	325
6.279.3.21LDAPFilter	325
6.279.3.22LDAPScope	325
6.279.3.23Locations	325

CONTENTS	xlvii
CONTENTS	xlvii

6.279.3.24MetaDataOption
6.279.3.25MetaDataOptions
6.279.3.26operator bool
6.279.3.27operator<
6.279.3.28operator==
6.279.3.29Option
6.279.3.30Options
6.279.3.31OptionString
6.279.3.32ParseOptions
6.279.3.33Passwd
6.279.3.34Path
6.279.3.35Path2BaseDN
6.279.3.36plainstr
6.279.3.37Port
6.279.3.3&Protocol
6.279.3.39str
6.279.3.40Username
6.279.4 Friends And Related Function Documentation
6.279.4.1 operator<<
6.279.5 Field Documentation
6.279.5.1 commonlocoptions
6.279.5.2 host
6.279.5.3 httpoptions
6.279.5.4 ip6addr
6.279.5.5 Idapattributes
6.279.5.6 ldapfilter
6.279.5.7 ldapscope
6.279.5.8 locations
6.279.5.9 metadataoptions
6.279.5.10passwd
6.279.5.1 lpath
6.279.5.12port
6.279.5.13protocol
6.279.5.14urloptions
6.279.5.15username
6.279.5.16valid

xlviii CONTENTS

6.280Arc::URLLocation Class Reference
6.280.1 Detailed Description
6.280.2 Constructor & Destructor Documentation
6.280.2.1 URLLocation
6.280.2.2 URLLocation
6.280.2.3 URLLocation
6.280.2.4 URLLocation
6.280.2.5 URLLocation
6.280.2.6 ~URLLocation
6.280.3 Member Function Documentation
6.280.3.1 fullstr
6.280.3.2 Name
6.280.3.3 str
6.280.4 Field Documentation
6.280.4.1 name
6.281 Arc::URLMap Class Reference
6.282Arc::User Class Reference
6.283 Arc::UserConfig Class Reference
6.283.1 Detailed Description
6.283.2 Constructor & Destructor Documentation
6.283.2.1 UserConfig
6.283.2.2 UserConfig
6.283.2.3 UserConfig
6.283.2.4 UserConfig
6.283.3 Member Function Documentation
6.283.3 Member Function Documentation
6.283.3.1 AddBartender
6.283.3.1 AddBartender
6.283.3.1 AddBartender 335 6.283.3.2 AddServices 336 6.283.3.3 AddServices 336
6.283.3.1 AddBartender 335 6.283.3.2 AddServices 336 6.283.3.3 AddServices 336 6.283.3.4 ApplyToConfig 337
6.283.3.1 AddBartender 335 6.283.3.2 AddServices 336 6.283.3.3 AddServices 336 6.283.3.4 ApplyToConfig 337 6.283.3.5 Bartender 337
6.283.3.1 AddBartender 335 6.283.3.2 AddServices 336 6.283.3.3 AddServices 336 6.283.3.4 ApplyToConfig 337 6.283.3.5 Bartender 337 6.283.3.6 Bartender 338
6.283.3.1 AddBartender 335 6.283.3.2 AddServices 336 6.283.3.3 AddServices 336 6.283.3.4 ApplyToConfig 337 6.283.3.5 Bartender 337 6.283.3.6 Bartender 338 6.283.3.7 Broker 338
6.283.3.1 AddBartender 335 6.283.3.2 AddServices 336 6.283.3.3 AddServices 336 6.283.3.4 ApplyToConfig 337 6.283.3.5 Bartender 337 6.283.3.6 Bartender 338 6.283.3.7 Broker 338 6.283.3.8 Broker 338
6.283.3.1 AddBartender 335 6.283.3.2 AddServices 336 6.283.3.3 AddServices 336 6.283.3.4 ApplyToConfig 337 6.283.3.5 Bartender 337 6.283.3.6 Bartender 338 6.283.3.7 Broker 338 6.283.3.8 Broker 338 6.283.3.9 Broker 339

CONTENTS	xlix
----------	------

6.283.3.12CACertificatesDirectory
6.283.3.13CACertificatesDirectory
6.283.3.14CertificateLifeTime
6.283.3.15CertificateLifeTime
6.283.3.16CertificatePath
6.283.3.17CertificatePath
6.283.3.18ClearRejectedServices
6.283.3.19ClearRejectedServices
6.283.3.20ClearSelectedServices
6.283.3.21ClearSelectedServices
6.283.3.22CredentialsFound
6.283.3.23GetRejectedServices
6.283.3.24GetSelectedServices
6.283.3.25IdPName
6.283.3.26IdPName
6.283.3.27InitializeCredentials
6.283.3.28JobListFile
6.283.3.29JobListFile
6.283.3.30KeyPassword
6.283.3.31KeyPassword
6.283.3.32KeyPath
6.283.3.33KeyPath
6.283.3.34KeySize
6.283.3.35KeySize
6.283.3.36LoadConfigurationFile
6.283.3.37operator bool
6.283.3.3&perator!
6.283.3.39OverlayFile
6.283.3.40OverlayFile
6.283.3.41Password
6.283.3.42Password
6.283.3.43ProxyPath
6.283.3.44ProxyPath
6.283.3.45SaveToFile
6.283.3.46SLCS
6.283.3.47SLCS

6.283.3.48StoreDirectory	
6.283.3.49StoreDirectory	
6.283.3.50Timeout	
6.283.3.51Timeout	
6.283.3.52UserName	
6.283.3.53UserName	
6.283.3.54UtilsDirPath	
6.283.3.55UtilsDirPath	
6.283.3.56Verbosity	
6.283.3.57Verbosity	
6.283.3.58VOMSServerPath	
6.283.3.59VOMSServerPath	
6.283.4 Field Documentation	
6.283.4.1 ARCUSERDIRECTORY	
6.283.4.2 DEFAULT_BROKER	
6.283.4.3 DEFAULT_TIMEOUT	
6.283.4.4 DEFAULTCONFIG	
6.283.4.5 EXAMPLECONFIG	
6.283.4.6 SYSCONFIG	
6.283.4.7 SYSCONFIGARCLOC	
6.284Arc::UsernameToken Class Reference	
6.284.1 Detailed Description	
6.284.2 Member Enumeration Documentation	
6.284.2.1 PasswordType	
6.284.3 Constructor & Destructor Documentation	
6.284.3.1 UsernameToken	
6.284.3.2 UsernameToken	
6.284.3.3 UsernameToken	
6.284.4 Member Function Documentation	
6.284.4.1 Authenticate	
6.284.4.2 Authenticate	
6.284.4.3 operator bool	
6.284.4.4 Username	
6.285 Arc::UserSwitch Class Reference	
6.285.1 Detailed Description	
6.286Arc::VOMSTrustList Class Reference	

6.286.1 Detailed Description	61
6.286.2 Constructor & Destructor Documentation	61
6.286.2.1 VOMSTrustList	61
6.286.2.2 VOMSTrustList	61
6.286.3 Member Function Documentation	62
6.286.3.1 AddChain	62
6.286.3.2 AddChain	62
6.286.3.3 AddRegex	62
6.287 Arc::WSAEndpointReference Class Reference	62
6.287.1 Detailed Description	63
6.287.2 Constructor & Destructor Documentation	63
6.287.2.1 WSAEndpointReference	63
6.287.2.2 WSAEndpointReference	63
6.287.2.3 WSAEndpointReference	63
6.287.2.4 WSAEndpointReference	63
6.287.2.5 ~WSAEndpointReference	63
6.287.3 Member Function Documentation	63
6.287.3.1 Address	63
6.287.3.2 Address	63
6.287.3.3 MetaData	63
6.287.3.4 operator XMLNode	63
6.287.3.5 operator=	64
6.287.3.6 ReferenceParameters	64
6.288 Arc::WSAHeader Class Reference	64
6.288.1 Detailed Description	65
6.288.2 Constructor & Destructor Documentation	65
6.288.2.1 WSAHeader	65
6.288.2.2 WSAHeader	65
6.288.3 Member Function Documentation	65
6.288.3.1 Action	65
6.288.3.2 Action	65
6.288.3.3 Check	65
6.288.3.4 FaultTo	65
6.288.3.5 From	65
6.288.3.6 MessageID	65
6.288.3.7 MessageID	65

lii CONTENTS

6.293.2 Constructor & Destructor Documentation
6.293.2.1 WSRP
6.293.2.2 WSRP
6.293.3 Member Function Documentation
6.293.3.1 set_namespaces
6.294Arc::WSRPDeleteResourceProperties Class Reference
6.295Arc::WSRPDeleteResourcePropertiesRequest Class Reference
6.296Arc::WSRPDeleteResourcePropertiesRequestFailedFault Class Reference
6.297 Arc::WSRPDeleteResourcePropertiesResponse Class Reference
6.298Arc::WSRPFault Class Reference
6.298.1 Detailed Description
6.298.2 Constructor & Destructor Documentation
6.298.2.1 WSRPFault
6.298.2.2 WSRPFault
6.299Arc::WSRPGetMultipleResourcePropertiesRequest Class Reference
6.300Arc::WSRPGetMultipleResourcePropertiesResponse Class Reference
6.301 Arc::WSRPGetResourcePropertyDocumentRequest Class Reference
6.302Arc::WSRPGetResourcePropertyDocumentResponse Class Reference
6.303Arc::WSRPGetResourcePropertyRequest Class Reference
6.304Arc::WSRPGetResourcePropertyResponse Class Reference
6.305 Arc::WSRPInsertResourceProperties Class Reference
6.306Arc::WSRPInsertResourcePropertiesRequest Class Reference
6.307 Arc::WSRPInsertResourcePropertiesRequestFailedFault Class Reference
6.308Arc::WSRPInsertResourcePropertiesResponse Class Reference
6.309Arc::WSRPInvalidModificationFault Class Reference
6.310Arc::WSRPInvalidResourcePropertyQNameFault Class Reference
6.311Arc::WSRPModifyResourceProperties Class Reference
6.312Arc::WSRPPutResourcePropertyDocumentRequest Class Reference
6.313Arc::WSRPPutResourcePropertyDocumentResponse Class Reference
6.314Arc::WSRPQueryResourcePropertiesRequest Class Reference
6.315Arc::WSRPQueryResourcePropertiesResponse Class Reference
6.316Arc::WSRPResourcePropertyChangeFailure Class Reference
6.316.1 Detailed Description
6.316.2 Constructor & Destructor Documentation
6.316.2.1 WSRPResourcePropertyChangeFailure
6.316.2.2 WSRPResourcePropertyChangeFailure

liv CONTENTS

6.317Arc::WSRPSetResourcePropertiesRequest Class Reference
6.318Arc::WSRPSetResourcePropertiesResponse Class Reference
6.319Arc::WSRPSetResourcePropertyRequestFailedFault Class Reference
6.320Arc::WSRPUnableToModifyResourcePropertyFault Class Reference
6.321 Arc::WSRPUnableToPutResourcePropertyDocumentFault Class Reference 384
6.322Arc::WSRPUpdateResourceProperties Class Reference
6.323 Arc::WSRPUpdateResourcePropertiesRequest Class Reference
6.324Arc::WSRPUpdateResourcePropertiesRequestFailedFault Class Reference
6.325 Arc::WSRPUpdateResourcePropertiesResponse Class Reference
6.326ArcSec::X500NameAttribute Class Reference
6.326.1 Member Function Documentation
6.326.1.1 encode
6.326.1.2 equal
6.326.1.3 getId
6.326.1.4 getType
6.327 Arc::X509Token Class Reference
6.327.1 Detailed Description
6.327.2 Member Enumeration Documentation
6.327.2.1 X509TokenType
6.327.3 Constructor & Destructor Documentation
6.327.3.1 X509Token
6.327.3.2 X509Token
6.327.3.3 ~X509Token
6.327.4 Member Function Documentation
6.327.4.1 Authenticate
6.327.4.2 Authenticate
6.327.4.3 operator bool
6.328Arc::XmlContainer Class Reference
6.329 Arc::XmlDatabase Class Reference
6.330Arc::XMLNode Class Reference
6.330.1 Detailed Description
6.330.2 Constructor & Destructor Documentation
6.330.2.1 XMLNode
6.330.2.2 XMLNode
6.330.2.3 XMLNode
6.330.2.4 XMLNode

6.330.2.5 XMLNode
6.330.2.6 XMLNode
6.330.2.7 XMLNode
6.330.2.8 ~XMLNode
6.330.3 Member Function Documentation
6.330.3.1 Attribute
6.330.3.2 Attribute
6.330.3.3 Attribute
6.330.3.4 AttributesSize
6.330.3.5 Child
6.330.3.6 Destroy
6.330.3.7 Exchange
6.330.3.8 FullName
6.330.3.9 Get
6.330.3.10GetDoc
6.330.3.11GetRoot
6.330.3.12GetXML
6.330.3.13GetXML
6.330.3.14Move
6.330.3.15Name
6.330.3.16Name
6.330.3.17Name
6.330.3.18Namespace
6.330.3.19NamespacePrefix
6.330.3.20Namespaces
6.330.3.21Namespaces
6.330.3.22New
6.330.3.23NewAttribute
6.330.3.24NewAttribute
6.330.3.25NewChild
6.330.3.26NewChild
6.330.3.27NewChild
6.330.3.28NewChild
6.330.3.29NewChild
6.330.3.30 operator bool
6.330.3.3 loperator std::string

lvi CONTENTS

6.330.3.32operator!) 6
6.330.3.33operator!=) 6
6.330.3.34operator!=) 6
6.330.3.35operator!=) 6
6.330.3.36operator!=	€
6.330.3.37operator++	€
6.330.3.3&perator	€
6.330.3.39operator=	€
6.330.3.40perator=	€
6.330.3.4 loperator=	∌ 7
6.330.3.42operator==	} 7
6.330.3.43operator==	∌ 7
6.330.3.44operator==	∌ 7
6.330.3.45operator==	∌ 7
6.330.3.46operator[]	∂ 7
6.330.3.47operator[]	∂ 7
6.330.3.4&operator[]	∌ 7
6.330.3.49Parent	98
6.330.3.50Path	98
6.330.3.5 lPrefix	98
6.330.3.52ReadFromFile	98
6.330.3.53ReadFromStream	98
6.330.3.54Replace	98
6.330.3.55Same	98
6.330.3.56SaveToFile	98
6.330.3.57SaveToStream	98
6.330.3.58Set	98
6.330.3.59Size) 9
6.330.3.60Swap) 9
6.330.3.61Validate) 9
6.330.3.62XPathLookup) 9
6.330.4 Friends And Related Function Documentation) 9
6.330.4.1 MatchXMLName	99
6.330.4.2 MatchXMLName) 9
6.330.4.3 MatchXMLName	99
6.330.4.4 MatchXMLNamespace	99

			6.330.4.5 MatchXMLNamespace
			6.330.4.6 MatchXMLNamespace
		6.330.5	5 Field Documentation
			6.330.5.1 is_owner
			6.330.5.2 is_temporary
	6.33	1 Arc::X	MLNodeContainer Class Reference
		6.331.	Detailed Description
		6.331.2	2 Constructor & Destructor Documentation
			6.331.2.1 XMLNodeContainer
			6.331.2.2 XMLNodeContainer
		6.331.3	3 Member Function Documentation
			6.331.3.1 Add
			6.331.3.2 Add
			6.331.3.3 AddNew
			6.331.3.4 AddNew
			6.331.3.5 Nodes
			6.331.3.6 operator=
			6.331.3.7 operator[]
			6.331.3.8 Size
	6.33	2Arc::X	MLSecNode Class Reference
		6.332.	Detailed Description
		6.332.2	2 Constructor & Destructor Documentation
			6.332.2.1 XMLSecNode
		6.332.3	3 Member Function Documentation
			6.332.3.1 AddSignatureTemplate
			6.332.3.2 DecryptNode
			6.332.3.3 EncryptNode
			6.332.3.4 SignNode
			6.332.3.5 VerifyNode
	6.33	3Arc::X	RSLParser Class Reference
7	Filo	Docum	entation 405
,	7.1		File Reference
	7.1	7.1.1	Detailed Description
		7.1.1	Define Documentation
		1.1.2	7.1.2.1 RC DEFAULT PORT
			,,,, <u>,,</u> ,, ,,, ,,,,,,,,,,,,,,,,,,,,,,,,

Chapter 1

Namespace Index

1.1	Namespace	List

Here is a list of all documented namespaces with brief descriptions:	
Arc (Some utility methods for using xml security library (http://www.aleksey.com/xmlsec/))	23
ArcCredential	43

Namespace Index

Chapter 2

Data Structure Index

2.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

ArcCredential::ACACI
ArcCredential::ACATTHOLDER
ArcCredential::ACATTR
ArcCredential::ACATTRIBUTE
ArcCredential::ACC
ArcCredential::ACCERTS
ArcCredential::ACDIGEST
ArcCredential::ACFORM
ArcCredential::ACFULLATTRIBUTES
ArcCredential::ACHOLDER
ArcCredential::ACIETFATTR
ArcCredential::ACINFO
ArcCredential::ACIS
ArcCredential::ACSEQ
ArcCredential::ACTARGET
ArcCredential::ACTARGETS
ArcCredential::ACVAL
Arc::ApplicationType
Arc::ArcLocation
ArcSec::ArcPeriod
ArcSec::Attr
Arc::AttributeIterator
ArcSec::AttributeProxy
ArcSec::AttributeValue
ArcSec::AnyURIAttribute
ArcSec::BooleanAttribute
ArcSec::DateAttribute
ArcSec::DateTimeAttribute
ArcSec::DurationAttribute
ArcSec::GenericAttribute
ArcSec::PeriodAttribute
ArcSec::StringAttribute
ArcSec: TimeAttribute 319

ArcSec::X500NameAttribute
ArcSec::Attrs
ArcSec::AuthzRequest
ArcSec::AuthzRequestSection
Arc::AutoPointer< T >
Arc::Base64
Arc::BaseConfig
Arc::MCCConfig
Arc::ByteArray
Arc::CacheParameters
ArcCredential::cert_verify_context
Arc::ChainContext
Arc::CheckSum
Arc::Adler32Sum
Arc::CheckSumAny
Arc::CRC32Sum
Arc::MD5Sum
Arc::ClientHTTPwithSAML2SSO
Arc::ClientInterface
Arc::ClientTCP
Arc::ClientSOAP
Arc::ClientSOAPwithSAML2SSO
Arc::ClientX509Delegation
ArcSec::CombiningAlg
ArcSec::DenyOverridesCombiningAlg
$ \begin{array}{llllllllllllllllllllllllllllllllllll$
ArcSec::DenyOverridesCombiningAlg
$ \begin{array}{llllllllllllllllllllllllllllllllllll$
$ \begin{array}{lll} ArcSec::DenyOverridesCombiningAlg & 142\\ ArcSec::OrderedCombiningAlg & 226\\ ArcSec::PermitOverridesCombiningAlg & 245\\ Arc::ConfusaCertHandler & 78\\ Arc::ConfusaParserUtils & 79\\ Arc::CountedPointer< T> & 80\\ Arc::Counter & 81\\ \end{array} $
$ \begin{array}{llllllllllllllllllllllllllllllllllll$
ArcSec::DenyOverridesCombiningAlg 142 ArcSec::OrderedCombiningAlg 226 ArcSec::PermitOverridesCombiningAlg 245 Arc::ConfusaCertHandler 78 Arc::ConfusaParserUtils 79 Arc::CountedPointer<< T > 80 Arc::Counter 81 Arc::IntraProcessCounter 178 Arc::CounterTicket 88
ArcSec::DenyOverridesCombiningAlg 142 ArcSec::OrderedCombiningAlg 226 ArcSec::PermitOverridesCombiningAlg 245 Arc::ConfusaCertHandler 78 Arc::ConfusaParserUtils 79 Arc::CountedPointer<< T > 80 Arc::Counter 81 Arc::IntraProcessCounter 178 Arc::CounterTicket 88 Arc::Credential 90
ArcSec::DenyOverridesCombiningAlg 142 ArcSec::OrderedCombiningAlg 226 ArcSec::PermitOverridesCombiningAlg 245 Arc::ConfusaCertHandler 78 Arc::ConfusaParserUtils 79 Arc::CountedPointer< T > 80 Arc::Counter 81 Arc::IntraProcessCounter 178 Arc::CounterTicket 88 Arc::Credential 90 Arc::CredentialError 97
ArcSec::DenyOverridesCombiningAlg 142 ArcSec::OrderedCombiningAlg 226 ArcSec::PermitOverridesCombiningAlg 245 Arc::ConfusaCertHandler 78 Arc::ConfusaParserUtils 79 Arc::CountedPointer< T > 80 Arc::Counter 81 Arc::IntraProcessCounter 178 Arc::CounterTicket 88 Arc::Credential 90 Arc::CredentialError 97 Arc::CredentialStore 98
ArcSec::DenyOverridesCombiningAlg 142 ArcSec::OrderedCombiningAlg 226 ArcSec::PermitOverridesCombiningAlg 245 Arc::ConfusaCertHandler 78 Arc::ConfusaParserUtils 79 Arc::CountedPointer< T > 80 Arc::Counter 81 Arc::IntraProcessCounter 178 Arc::CounterTicket 88 Arc::Credential 90 Arc::CredentialError 97 Arc::CredentialStore 98 Arc::Database 98 Arc::MySQLDatabase 220
ArcSec::DenyOverridesCombiningAlg 142 ArcSec::OrderedCombiningAlg 226 ArcSec::PermitOverridesCombiningAlg 245 Arc::ConfusaCertHandler 78 Arc::ConfusaParserUtils 79 Arc::CountedPointer<< T > 80 Arc::Counter 81 Arc::IntraProcessCounter 178 Arc::CounterTicket 88 Arc::Credential 90 Arc::CredentialError 97 Arc::CredentialStore 98 Arc::Database 98 Arc::MySQLDatabase 220 Arc::DataBuffer 100
ArcSec::DenyOverridesCombiningAlg 142 ArcSec::OrderedCombiningAlg 226 ArcSec::PermitOverridesCombiningAlg 245 Arc::ConfusaCertHandler 78 Arc::ConfusaParserUtils 79 Arc::CountedPointer<< T > 80 Arc::Counter 81 Arc::IntraProcessCounter 178 Arc::CounterTicket 88 Arc::Credential 90 Arc::CredentialError 97 Arc::CredentialStore 98 Arc::Database 98 Arc::MySQLDatabase 220 Arc::DataBuffer 100
ArcSec::DenyOverridesCombiningAlg 142 ArcSec::OrderedCombiningAlg 226 ArcSec::PermitOverridesCombiningAlg 245 Arc::ConfusaCertHandler 78 Arc::ConfusaParserUtils 79 Arc::CountedPointer< T > 80 Arc::Counter 81 Arc::CounterTicket 88 Arc::Credential 90 Arc::CredentialError 97 Arc::CredentialStore 98 Arc::Database 98 Arc::MySQLDatabase 220 Arc::DataBuffer 100 Arc::DataCallback 105
ArcSec::DenyOverridesCombiningAlg 142 ArcSec::OrderedCombiningAlg 226 ArcSec::PermitOverridesCombiningAlg 245 Arc::ConfusaCertHandler 78 Arc::ConfusaParserUtils 79 Arc::CountedPointer<< T > 80 Arc::Counter 81 Arc::IntraProcessCounter 178 Arc::CounterTicket 88 Arc::Credential 90 Arc::CredentialError 97 Arc::CredentialStore 98 Arc::Database 98 Arc::DataBuffer 100 Arc::DataCallback 105 Arc::DataHandle 106
ArcSec::DenyOverridesCombiningAlg 142 ArcSec::OrderedCombiningAlg 226 ArcSec::PermitOverridesCombiningAlg 245 Arc::ConfusaCertHandler 78 Arc::ConfusaParserUtils 79 Arc::CountedPointer< T > 80 Arc::Counter 81 Arc::IntraProcessCounter 178 Arc::CounterTicket 88 Arc::Credential 90 Arc::CredentialError 97 Arc::CredentialStore 98 Arc::Database 98 Arc::DataBuffer 100 Arc::DataCallback 105 Arc::DataHandle 106 Arc::DataMover 106
ArcSec::DenyOverridesCombiningAlg 142 ArcSec::OrderedCombiningAlg 226 ArcSec::PermitOverridesCombiningAlg 245 Arc::ConfusaCertHandler 78 Arc::ConfusaParserUtils 79 Arc::CountedPointer< T > 80 Arc::Counter 81 Arc::CounterTicket 88 Arc::Credential 90 Arc::Credential 90 Arc::CredentialStore 98 Arc::Database 98 Arc::DataBuffer 100 Arc::DataCallback 105 Arc::DataHandle 106 Arc::DataMover 106 Arc::DataSourceType 128
ArcSec::DenyOverridesCombiningAlg 142 ArcSec::OrderedCombiningAlg 226 ArcSec::PermitOverridesCombiningAlg 245 Arc::ConfusaCertHandler 78 Arc::ConfusaParserUtils 79 Arc::CountedPointer < T > 80 Arc::Counter 81 Arc::IntraProcessCounter 178 Arc::CounterTicket 88 Arc::Credential 90 Arc::CredentialError 97 Arc::CredentialStore 98 Arc::Database 98 Arc::DataBuffer 100 Arc::DataBuffer 105 Arc::DataAlandle 106 Arc::DataMover 106 Arc::DataSourceType 128 Arc::DataSpeed 128
ArcSec::DenyOverridesCombiningAlg 142 ArcSec::OrderedCombiningAlg 226 ArcSec::PermitOverridesCombiningAlg 245 Arc::ConfusaCertHandler 78 Arc::ConfusaParserUtils 79 Arc::CountedPointer< T > 80 Arc::Counter 81 Arc::CounterTicket 88 Arc::Credential 90 Arc::CredentialError 97 Arc::Database 98 Arc::Database 98 Arc::DataBuffer 100 Arc::DataCallback 105 Arc::DataAlandle 106 Arc::DataSourceType 128 Arc::DataSpeed 128 Arc::DataStagingType 131
ArcSec::DenyOverridesCombiningAlg 142 ArcSec::OrderedCombiningAlg 226 ArcSec::PermitOverridesCombiningAlg 245 Arc::ConfusaCertHandler 78 Arc::ConfusaParserUtils 79 Arc::CountedPointer< T > 80 Arc::Counter 81 Arc::CounterTicket 88 Arc::CounterTicket 88 Arc::Credential 90 Arc::CredentialError 97 Arc::CredentialStore 98 Arc::Database 98 Arc::MySQLDatabase 220 Arc::DataBuffer 100 Arc::DataAlandle 105 Arc::DataAlover 106 Arc::DataSourceType 128 Arc::DataSpeed 128 Arc::DataStagingType 131 Arc::DataStatus 131
ArcSec::DenyOverridesCombiningAlg 142 ArcSec::OrderedCombiningAlg 226 ArcSec::PermitOverridesCombiningAlg 245 Arc::ConfusaCertHandler 78 Arc::ConfusaParserUtils 79 Arc::CountedPointer< T > 80 Arc::Counter 81 Arc::IntraProcessCounter 178 Arc::CounterTicket 88 Arc::Credential 90 Arc::CredentialError 97 Arc::Database 98 Arc::Database 98 Arc::Database 98 Arc::DataBuffer 100 Arc::DataCallback 105 Arc::DataMover 106 Arc::DataSourceType 128 Arc::DataSpeed 128 Arc::DataStatus 131 Arc::DataStatus 131 Arc::DataTargetType 132

Arc::DBranch
Arc::DelegationConsumer
Arc::DelegationConsumerSOAP
Arc::DelegationContainerSOAP
Arc::DelegationProvider
Arc::DelegationProviderSOAP
Arc::DiskSpaceRequirementType
Arc::DItem
Arc::DItemString
ArcSec::EvalResult
ArcSec::EvaluationCtx
ArcSec::EvaluatorContext
ArcSec::EvaluatorLoader
Arc::ExecutableType
Arc::ExecutionTarget
Arc::ExpirationReminder
Arc::FileCache
FileCacheHash
Arc::FileInfo
Arc::FileLock
Arc::FinderLoader
ArcSec::Function
ArcSec::EqualFunction
ArcSec::InRangeFunction
ArcSec::MatchFunction
Arc::GlobusResult
Arc::GSSCredential
Arc::HTTPClientInfo
Arc::InfoCache
Arc::InfoFilter
Arc::InfoRegister
Arc::InfoRegisters
Arc::InfoRegistrar
Arc::InformationInterface
Arc::InfoCacheInterface
Arc::InformationContainer
Arc::InformationRequest
Arc::InformationResponse
Arc::initializeCredentialsType
Arc::ISIS_description
Arc::IString
Arc::Job
Arc::JobDescription
Arc::JobDescriptionParser
Arc::ARCJSDLParser
Arc::JDLParser
Arc::XRSLParser
Arc::JobIdentificationType
Arc::JobMetaType
Arc::JobState
Arc: JohSunervisor 188

Arc::LoadableModuleDesciption	
Arc::Loader	9
Arc::BrokerLoader	4
Arc::DataPointLoader	27
Arc::JobControllerLoader	35
Arc::MCCLoader)6
Arc::SubmitterLoader)7
Arc::TargetRetrieverLoader	2
Arc::LogDestination	'n
Arc::Logger	
Arc::LoggerFormat	_
Arc::LogMessage	
Arc::MCC_Status	
Arc::MemoryAllocationException	
Arc::Message	
Arc::MessageAttributes	
Arc::MessageAuth	.3
Arc::MessageAuthContext	4
Arc::MessageContext	5
Arc::MessageContextElement	
ArcSec::PDPConfigContext	
Arc::MessagePayload	
Arc::PayloadRawInterface	
Arc::PayloadRaw	28
Arc::PayloadSOAP	3
Arc::PayloadStreamInterface	7
Arc::PayloadStream	3
Arc::PayloadWSRF	9
Arc::ModuleDesc	
Arc::ModuleManager	
Arc::PluginsFactory	
Arc::ClassLoader	-
Arc::NotificationType	
Arc::NS	:3
Arc::OptionParser	:6
passwd	:6
Arc::PathIterator	:7
Arc::PayloadRawBuf	0
Arc::Period	12
Arc::PlexerEntry	7
Are::Plugin	8
Arc::Broker	52
Arc::DataPoint	8(
Arc::DataPointDirect	
Arc::DataPointIndex	
Arc::JobController	
Arc::MCCInterface	-
Arc::MCC	
Arc::Plexer	6

Test::TestMCC
Test::TestMCC
Arc::Service
Arc::RegisteredService
Test::TestService
Arc::Submitter
Arc::TargetRetriever
ArcSec::AlgFactory
ArcSec::AttributeFactory
ArcSec::Evaluator 148 ArcSec::FnFactory 164
ArcSec::FnFactory 164 ArcSec::PDP 240
ArcSec::Policy
ArcSec::Request
ArcSec::SecHandler
Arc::PluginArgument
Arc::BrokerPluginArgument
Arc::ClassLoaderPluginArgument
Arc::DataPointPluginArgument
Arc::JobControllerPluginArgument
Arc::MCCPluginArgument
Arc::ServicePluginArgument
Arc::SubmitterPluginArgument
Arc::TargetRetrieverPluginArgument
ArcSec::PDPPluginArgument
ArcSec::SecHandlerPluginArgument
Arc::PluginDesc
Arc::PluginDescriptor
ArcSec::PolicyStore::PolicyElement
ArcSec::PolicyParser
ArcSec::PolicyStore
Arc::PrintFBase
Arc::PrintF< T0, T1, T2, T3, T4, T5, T6, T7 >
ArcCredential::PROXYCERTINFO_st
ArcCredential::PROXYPOLICY_st
Arc::Query
Arc::MySQLQuery
Arc::Range< T >
Arc::Register_Info_Type
Arc::RegularExpression
ArcSec::RequestAttribute
ArcSec::RequestItem
ArcSec::RequestTuple
Arc::ResourceSlotType
Arc::ResourcesType
Arc::ResourceTargetType
ArcSec::Response
ArcSec::ResponseItem
ArcSec::ResponseList
Arc::RSL
Arc::RSLBoolean
Arc::RSLCondition

8 Data Structure Index

Arc::RSLParser	267
Arc::RSLValue	268
Arc::RSLConcat	266
Arc::RSLList	267
Arc::RSLLiteral	267
Arc::RSLSequence	268
Arc::RSLVariable	268
Arc::Run	268
Arc::SAML2LoginClient	272
Arc::OAuthConsumer	223
Arc::SAML2SSOHTTPClient	273
Arc::HakaClient	167
Arc::OpenIdpClient	225
Arc::SAMLToken	275
$Arc:: Scalable Time < T > \dots \dots$	
Arc::ScalableTime < int >	
Arc::SecAttr	278
Arc::MultiSecAttr	219
Arc::SecAttrFormat	
Arc::SecAttrValue	
Arc::CIString Value	67
ArcSec::Security	
Arc::SimpleCondition	
Arc::SimpleCounter	
Arc::SOAPMessage	
Arc::Software	
Arc::ApplicationEnvironment	50
Arc::SoftwareRequirement	
ArcSec::Source	
ArcSec::SourceFile	
ArcSec::SourceURL	
Arc::TargetGenerator	
Arc::ThreadRegistry	
Arc::Time	
Arc::URL	
Arc::URLLocation	328
Arc::URLMap	330
Arc::User	331
Arc::UserConfig	331
Arc::UsernameToken	358
Arc::UserSwitch	360
Arc::VOMSTrustList	361
Arc::WSAEndpointReference	362
Arc::WSAHeader	364
Arc::WSRF	367
Arc::WSRFBaseFault	369
Arc::WSRFResourceUnavailableFault	370
Arc::WSRFResourceUnknownFault	370
Arc::WSRPFault	374
Arc::WSRPInvalidResourcePropertyQNameFault	379

Arc::WSRPResourcePropertyChangeFailure	381
Arc::WSRPDeleteResourcePropertiesRequestFailedFault	373
Arc::WSRPInsertResourcePropertiesRequestFailedFault	377
Arc::WSRPInvalidModificationFault	378
Arc::WSRPSetResourcePropertyRequestFailedFault	383
Arc::WSRPUnableToModifyResourcePropertyFault	383
Arc::WSRPUnableToPutResourcePropertyDocumentFault	384
Arc::WSRPUpdateResourcePropertiesRequestFailedFault	385
Arc::WSRP	370
Arc::WSRPDeleteResourcePropertiesRequest	372
Arc::WSRPDeleteResourcePropertiesResponse	373
Arc::WSRPGetMultipleResourcePropertiesRequest	374
Arc::WSRPGetMultipleResourcePropertiesResponse	375
Arc::WSRPGetResourcePropertyDocumentRequest	375
Arc::WSRPGetResourcePropertyDocumentResponse	376
Arc::WSRPGetResourcePropertyRequest	376
Arc::WSRPGetResourcePropertyResponse	376
Arc::WSRPInsertResourcePropertiesRequest	377
Arc::WSRPInsertResourcePropertiesResponse	378
Arc::WSRPPutResourcePropertyDocumentRequest	380
Arc::WSRPPutResourcePropertyDocumentResponse	380
Arc::WSRPQueryResourcePropertiesRequest	380
Arc::WSRPQueryResourcePropertiesResponse	381
Arc::WSRPSetResourcePropertiesRequest	382
Arc::WSRPSetResourcePropertiesResponse	382
Arc::WSRPUpdateResourcePropertiesRequest	384
Arc::WSRPUpdateResourcePropertiesResponse	385
Arc::WSRPModifyResourceProperties	379
Arc::WSRPDeleteResourceProperties	372
Arc::WSRPInsertResourceProperties	377
Arc::WSRPUpdateResourceProperties	384
Arc::X509Token	
Arc::XmlContainer	
Arc::XmlDatabase	
Arc::XMLNode	
Arc::Config	76
Arc::IniConfig	
Arc::Profile	256
Arc::SecHandlerConfig	281
Arc::ARCPolicyHandlerConfig	51
Arc::DNListHandlerConfig	145
Arc::XMLSecNode	402
ArcSec::SecHandlerConfig	281
Arc::XMLNodeContainer	400
	.00

10 Data Structure Index

Chapter 3

Data Structure Index

3.1 Data Structures

Here are the data structures with brief descriptions:

ArcCredential::ACACI	45
ArcCredential::ACATTHOLDER	45
ArcCredential::ACATTR	45
ArcCredential::ACATTRIBUTE	45
	45
ArcCredential::ACCERTS	46
ArcCredential::ACDIGEST	46
ArcCredential::ACFORM	46
ArcCredential::ACFULLATTRIBUTES	46
	46
ArcCredential::ACIETFATTR	46
	46
	47
	47
	47
	47
	47
Arc::Adler32Sum (Implementation of Adler32 checksum)	47
5 ,	48
	49
	50
	50
	50
,	51
	51
v	51
` '1 ' '1 '	52
	52
C I	53
ArcSec::AttributeProxy (Interface for creating the AttributeValue (p. 56) object, it will be used	
	55
ArcSec::AttributeValue (Interface for containing different type of <attribute> node for both</attribute>	
policy and request)	56

12 Data Structure Index

ArcSec::Attrs (Attrs (p. 58) is a container for one or more Attr (p. 52))	58
ArcSec::AuthzRequest	59
ArcSec::AuthzRequestSection	59
Arc::AutoPointer < T > (Wrapper for pointer with automatic destruction)	59
Arc::Base64	60
Arc::BaseConfig	60
ArcSec::BooleanAttribute	61
Arc::Broker	62
Arc::BrokerLoader	64
Arc::BrokerPluginArgument	65
Arc::ByteArray	65
Arc::CacheParameters	66
ArcCredential::cert_verify_context	66
Arc::ChainContext (Interface to chain specific functionality)	66
Arc::CheckSum (Defines interface for variuos checksum manipulations)	67
Arc::CheckSumAny (Wraper for CheckSum (p. 67) class)	67
Arc::CIStringValue (This class implements case insensitive strings as security attributes)	67
Arc::ClassLoader	69
Arc::ClassLoaderPluginArgument	69
Arc::ClientHTTP (Class for setting up a MCC (p. 200) chain for HTTP communication)	69
Arc::ClientHTTPwithSAML2SSO	70
Arc::ClientInterface (Utility base class for MCC (p. 200))	71
Arc::ClientSOAP	71
Arc::ClientSOAPwithSAML2SSO	73
Arc::ClientTCP (Class for setting up a MCC (p. 200) chain for TCP communication)	73
Arc::ClientX509Delegation	74
ArcSec::CombiningAlg (Interface for combining algrithm)	75
Arc::Config (Configuration element - represents (sub)tree of ARC configuration)	76
Arc::ConfusaCertHandler	78
Arc::ConfusaParserUtils	79
Arc::CountedPointer < T > (Wrapper for pointer with automatic destruction and mutiple ref-	
erences)	80
Arc::Counter (A class defining a common interface for counters)	81
Arc::CounterTicket (A class for "tickets" that correspond to counter reservations)	88
Arc::CRC32Sum (Implementation of CRC32 checksum)	89
Arc::Credential	90
Arc::CredentialError	97
Arc::CredentialStore	98
	98
Arc::Database (Interface for calling database client library)	
Arc::DataBuffer (Represents set of buffers)	100
Arc::DataBuffer (Represents set of buffers)	100 105
Arc::DataBuffer (Represents set of buffers)	
Arc::DataBuffer (Represents set of buffers)	105
Arc::DataBuffer (Represents set of buffers)	105 106
Arc::DataBuffer (Represents set of buffers)	105 106 106
Arc::DataBuffer (Represents set of buffers) Arc::DataCallback Arc::DataHandle (This class is a wrapper around the DataPoint (p. 108) class) Arc::DataMover Arc::DataPoint (This base class is an abstraction of URL (p. 320)) Arc::DataPointDirect (This is a kind of generalized file handle) Arc::DataPointIndex (Complements DataPoint (p. 108) with attributes common for Indexing	105 106 106 108
Arc::DataBuffer (Represents set of buffers)	105 106 106 108 117
Arc::DataBuffer (Represents set of buffers) Arc::DataCallback Arc::DataHandle (This class is a wrapper around the DataPoint (p. 108) class) Arc::DataMover Arc::DataPoint (This base class is an abstraction of URL (p. 320)) Arc::DataPointDirect (This is a kind of generalized file handle) Arc::DataPointIndex (Complements DataPoint (p. 108) with attributes common for Indexing	105 106 106 108 117
Arc::DataBuffer (Represents set of buffers) Arc::DataCallback Arc::DataHandle (This class is a wrapper around the DataPoint (p. 108) class) Arc::DataMover Arc::DataPoint (This base class is an abstraction of URL (p. 320)) Arc::DataPointDirect (This is a kind of generalized file handle) Arc::DataPointIndex (Complements DataPoint (p. 108) with attributes common for Indexing Service (p. 282) URLs)	105 106 106 108 117 122 127
Arc::DataBuffer (Represents set of buffers) Arc::DataCallback Arc::DataHandle (This class is a wrapper around the DataPoint (p. 108) class) Arc::DataMover Arc::DataPoint (This base class is an abstraction of URL (p. 320)) Arc::DataPointDirect (This is a kind of generalized file handle) Arc::DataPointIndex (Complements DataPoint (p. 108) with attributes common for Indexing Service (p. 282) URLs) Arc::DataPointLoader	105 106 108 117 122 127 127
Arc::DataBuffer (Represents set of buffers) Arc::DataCallback Arc::DataHandle (This class is a wrapper around the DataPoint (p. 108) class) Arc::DataMover Arc::DataPoint (This base class is an abstraction of URL (p. 320)) Arc::DataPointDirect (This is a kind of generalized file handle) Arc::DataPointIndex (Complements DataPoint (p. 108) with attributes common for Indexing Service (p. 282) URLs) Arc::DataPointLoader Arc::DataPointPluginArgument	105 106 108 117 122 127 127 128
Arc::DataBuffer (Represents set of buffers) Arc::DataCallback Arc::DataHandle (This class is a wrapper around the DataPoint (p. 108) class) Arc::DataMover Arc::DataPoint (This base class is an abstraction of URL (p. 320)) Arc::DataPointDirect (This is a kind of generalized file handle) Arc::DataPointIndex (Complements DataPoint (p. 108) with attributes common for Indexing Service (p. 282) URLs) Arc::DataPointLoader Arc::DataPointPluginArgument Arc::DataSourceType Arc::DataSourceType Arc::DataSpeed (Keeps track of average and instantaneous transfer speed)	105 106 106 108
Arc::DataBuffer (Represents set of buffers) Arc::DataCallback Arc::DataHandle (This class is a wrapper around the DataPoint (p. 108) class) Arc::DataMover Arc::DataPoint (This base class is an abstraction of URL (p. 320)) Arc::DataPointDirect (This is a kind of generalized file handle) Arc::DataPointIndex (Complements DataPoint (p. 108) with attributes common for Indexing Service (p. 282) URLs) Arc::DataPointLoader Arc::DataPointPluginArgument Arc::DataSourceType Arc::DataSpeed (Keeps track of average and instantaneous transfer speed) Arc::DataStagingType	105 106 108 117 122 127 127 128 128
Arc::DataBuffer (Represents set of buffers) Arc::DataCallback Arc::DataHandle (This class is a wrapper around the DataPoint (p. 108) class) Arc::DataMover Arc::DataPoint (This base class is an abstraction of URL (p. 320)) Arc::DataPointDirect (This is a kind of generalized file handle) Arc::DataPointIndex (Complements DataPoint (p. 108) with attributes common for Indexing Service (p. 282) URLs) Arc::DataPointLoader Arc::DataPointPluginArgument Arc::DataSourceType Arc::DataSourceType Arc::DataSpeed (Keeps track of average and instantaneous transfer speed)	105 106 108 117 122 127 128 128 131 131

3.1 Data Structures

Arc::DataType	
ArcSec::DateAttribute	
ArcSec::DateTimeAttribute	134
Arc::DBranch	
Arc::DelegationConsumer	135
Arc::DelegationConsumerSOAP	137
Arc::DelegationContainerSOAP	138
Arc::DelegationProvider	139
	140
ArcSec::DenyOverridesCombiningAlg (Implement the "Deny-Overrides" algorithm) 1	142
	144
Arc::DiskSpaceRequirementType	144
Arc::DItem	144
Arc::DItemString	144
Arc::DNListHandlerConfig	145
ArcSec::DurationAttribute	
	146
ArcSec::EvalResult (Struct to record the xml node and effect, which will be used by Evaluator	
	147
ArcSec::EvaluationCtx (EvaluationCtx (p. 147), in charge of storing some context information	
	147
ArcSec::Evaluator (Interface for policy evaluation. Execute the policy evaluation, based on the	
	148
ArcSec::EvaluatorContext (Context for evaluator. It includes the factories which will be used	
· ·	151
ArcSec::EvaluatorLoader (EvaluatorLoader (p. 151) is implemented as a helper class for	
	151
	153
V.	153 153
8 1 //	156 156
	150 157
FileCacheHash	
Arc::FileInfo (FileInfo (p. 163) stores information about files (metadata))	
	163
Arc::FileType	
Arc::FinderLoader	
ArcSec::FnFactory (Interface for function factory class)	
ArcSec::Function (Interface for function, which is in charge of evaluating two AttributeValue	104
	165
	165 165
	166 166
	160 167
	167 167
	167 168
	168 168
· 1 1 ,	168 168
	169 169
	170 170
· ·	
8	171
	172
Arc::InformationContainer (Information System document container and processor)	170
	172
Arc::InformationInterface (Information System message processor)	172 174 175

14 Data Structure Index

Arc::InformationResponse (Informational response from InfoSystem)	
Arc::IniConfig	
Arc::initializeCredentialsType	
	177
	178
Arc::ISIS_description	182
Arc::IString	182
Arc::JDLParser	182
Arc::Job (Job (p. 182))	182
Arc::JobController (Base class for the JobControllers)	183
Arc::JobControllerLoader	185
Arc::JobControllerPluginArgument	186
Arc::JobDescription	187
Arc::JobDescriptionParser	187
Arc::JobIdentificationType	187
Arc::JobMetaType	187
Arc::JobState	
Arc::JobSupervisor (% JobSupervisor (p. 188) class)	
	189
Arc::Loader (Plugins loader)	
	190
	191
	193
	195
	196
	197
ArcSec::MatchFunction (Evaluate whether arg1 (value in regular expression) matched arg0	-,,
	199
	200
	202
	205
Arc::MCCInterface (Interface for communication between MCC (p. 200), Service (p. 282) and	200
	205
	206
	207
,	208
*	208
	210
	213
	214
	215
	216
	216
	216
	217
	219
micontinuoccatii (Containoi oi munipio occatii (p. 270) attiiutto j	
Arc::MySQLDatabase	220
Arc::MySQLDatabase	220 221
Arc::MySQLDatabase Arc::MySQLQuery Arc::NotificationType	220 221 223
Arc::MySQLDatabase Arc::MySQLQuery Arc::NotificationType Arc::NS	220 221 223 223
Arc::MySQLDatabase Arc::MySQLQuery Arc::NotificationType Arc::NS Arc::OAuthConsumer	220 221 223 223 223
Arc::MySQLDatabase Arc::MySQLQuery Arc::NotificationType Arc::NS Arc::OAuthConsumer Arc::OpenIdpClient	220 221 223 223 223 225

3.1 Data Structures

AugSpan Ondonad Combining Ala	226
ArcSec::OrderedCombiningAlg	
passwd	
Arc::PathIterator (Class to iterate through elements of path)	
Arc::PayloadRaw (Raw byte multi-buffer)	228
Arc::PayloadRawBuf	230
Arc::PayloadRawInterface (Random Access Payload for Message (p. 208) objects)	230
Arc::PayloadSOAP (Payload of Message (p. 208) with SOAP content)	233
Arc::PayloadStream (POSIX handle as Payload)	
Arc::PayloadStreamInterface (Stream-like Payload for Message (p. 208) object)	
Arc::PayloadWSRF (This class combines MessagePayload (p. 216) with WSRF (p. 367))	
ArcSec::PDP (Base class for Policy (p. 252) Decision Point plugins)	
ArcSec::PDPConfigContext	
_	
ArcSec::PDPPluginArgument	
Arc::Period	
ArcSec::PeriodAttribute	
$\label{lem:arcSec::PermitOverridesCombiningAlg} Arc Sec:: PermitOverrides " algorithm) . . .$	
Arc::Plexer (The Plexer (p. 246) class, used for routing messages to services)	
Arc::PlexerEntry (A pair of label (regex) and pointer to MCC (p. 200))	247
Arc::Plugin (Base class for loadable ARC components)	248
Arc::PluginArgument (Base class for passing arguments to loadable ARC components)	249
Arc::PluginDescriptor (Description of ARC lodable component)	
Arc::PluginsFactory (Generic ARC plugins loader)	
ArcSec::Policy (Interface for containing and processing different types of policy)	252
ArcSec::PolicyStore::PolicyElement	254
ArcSec::PolicyParser (A interface which will isolate the policy object from actual policy storage	254
	254
(files, urls, database))	254
ArcSec::PolicyStore (Storage place for policy objects)	255
	256
Arc::Profile	256
ArcCredential::PROXYCERTINFO_st	257
ArcCredential::PROXYPOLICY_st	257
Arc::Query	257
Arc::Range< T >	259
Arc::Register_Info_Type	259
Arc::RegisteredService (RegisteredService (p. 260) - extension of Service (p. 282) performing	
self-registration)	260
Arc::RegularExpression (A regular expression class)	
ArcSec::Request (Base class/Interface for request, includes a container for RequestItems and	200
	261
some operations)	201
ArcSec::RequestAttribute (Wrapper which includes AttributeValue (p. 56) object which is	262
generated according to date type of one spefic node in Request.xml)	263
ArcSec::RequestItem (Interface for request item container, <subjects, actions,="" ctxs="" objects,=""></subjects,>	
tuple)	264
ArcSec::RequestTuple	264
Arc::ResourceSlotType	264
Arc::ResourcesType	264
Arc::ResourceTargetType	265
ArcSec::Response (Container for the evaluation results)	265
ArcSec::ResponseItem (Evaluation result concerning one RequestTuple (p. 264))	
ArcSec::ResponseList	
Arc::RSL	
Arc::RSLBoolean	
	_00

16 Data Structure Index

Arc::RSLConcat	266
Arc::RSLCondition	266
Are::RSLList	267
Arc::RSLLiteral	267
Arc::RSLParser	267
Arc::RSLSequence	268
Arc::RSLValue	268
Arc::RSLVariable	
Arc::Run	268
Arc::SAML2LoginClient	
Arc::SAML2SSOHTTPClient	
Arc::SAMLToken (Class for manipulating SAML Token Profile (p. 256))	
Arc::ScalableTime< T >	
Arc::ScalableTime< int >	
Arc::SecAttr (This is an abstract interface to a security attribute)	
Arc::SecAttrFormat (Export/import format)	
Arc::SecAttrValue (This is an abstract interface to a security attribute)	
ArcSec::SecHandler (Base class for simple security handling plugins)	
Arc::SecHandler Config	
ArcSec::SecHandlerConfig	
ArcSec::SecHandlerPluginArgument	
ArcSec::Security (Common stuff used by security related slasses)	
Arc::Service (Service (p. 282) - last component in a Message (p. 208) Chain)	
Arc::ServicePluginArgument	
Arc::SimpleCondition (Helper function to create simple thread)	
Arc::SimpleCounter	
Arc::SOAPMessage (Message (p. 208) restricted to SOAP payload)	
Arc::Software (Used to represent software (names and version) and comparison)	288
Arc::SoftwareRequirement (Class used to express and resolve version requirements on soft-	
Arc::SoftwareRequirement (Class used to express and resolve version requirements on software)	295
Arc::SoftwareRequirement (Class used to express and resolve version requirements on software)	295 302
Arc::SoftwareRequirement (Class used to express and resolve version requirements on software)	295 302 303
Arc::SoftwareRequirement (Class used to express and resolve version requirements on software)	295 302 303 304
Arc::SoftwareRequirement (Class used to express and resolve version requirements on software)	295 302 303 304 305
Arc::SoftwareRequirement (Class used to express and resolve version requirements on software)	295 302 303 304 305 306
Arc::SoftwareRequirement (Class used to express and resolve version requirements on software) ArcSec::Source (Acquires and parses XML document from specified source) ArcSec::SourceFile (Convenience class for obtaining XML document from file) ArcSec::SourceURL (Convenience class for obtaining XML document from remote URL) ArcSec::StringAttribute Arc::Submitter (Base class for the Submitters) Arc::SubmitterLoader	295 302 303 304 305 306 307
Arc::SoftwareRequirement (Class used to express and resolve version requirements on software) ArcSec::Source (Acquires and parses XML document from specified source) ArcSec::SourceFile (Convenience class for obtaining XML document from file) ArcSec::SourceURL (Convenience class for obtaining XML document from remote URL). ArcSec::StringAttribute Arc::Submitter (Base class for the Submitters) Arc::SubmitterLoader Arc::SubmitterPluginArgument	295 302 303 304 305 306
Arc::SoftwareRequirement (Class used to express and resolve version requirements on software) ArcSec::Source (Acquires and parses XML document from specified source). ArcSec::SourceFile (Convenience class for obtaining XML document from file). ArcSec::SourceURL (Convenience class for obtaining XML document from remote URL). ArcSec::StringAttribute	295 302 303 304 305 306 307
Arc::SoftwareRequirement (Class used to express and resolve version requirements on software) ArcSec::Source (Acquires and parses XML document from specified source) ArcSec::SourceFile (Convenience class for obtaining XML document from file) ArcSec::SourceURL (Convenience class for obtaining XML document from remote URL). ArcSec::StringAttribute Arc::Submitter (Base class for the Submitters) Arc::SubmitterLoader Arc::SubmitterPluginArgument	295 302 303 304 305 306 307 308
Arc::SoftwareRequirement (Class used to express and resolve version requirements on software) ArcSec::Source (Acquires and parses XML document from specified source). ArcSec::SourceFile (Convenience class for obtaining XML document from file). ArcSec::SourceURL (Convenience class for obtaining XML document from remote URL). ArcSec::StringAttribute	295 302 303 304 305 306 307 308 308
Arc::SoftwareRequirement (Class used to express and resolve version requirements on software) ArcSec::Source (Acquires and parses XML document from specified source) ArcSec::SourceFile (Convenience class for obtaining XML document from file) ArcSec::SourceURL (Convenience class for obtaining XML document from remote URL) ArcSec::StringAttribute Arc::Submitter (Base class for the Submitters) Arc::SubmitterLoader Arc::SubmitterPluginArgument Arc::TargetGenerator (Target generation class) Arc::TargetRetriever (TargetRetriever base class)	295 302 303 304 305 306 307 308 308 311
Arc::SoftwareRequirement (Class used to express and resolve version requirements on software) ArcSec::Source (Acquires and parses XML document from specified source). ArcSec::SourceFile (Convenience class for obtaining XML document from file). ArcSec::SourceURL (Convenience class for obtaining XML document from remote URL). ArcSec::StringAttribute	295 302 303 304 305 306 307 308 308 311 312
Arc::SoftwareRequirement (Class used to express and resolve version requirements on software) ArcSec::Source (Acquires and parses XML document from specified source). ArcSec::SourceFile (Convenience class for obtaining XML document from file). ArcSec::SourceURL (Convenience class for obtaining XML document from remote URL). ArcSec::StringAttribute Arc::Submitter (Base class for the Submitters). Arc::SubmitterLoader Arc::SubmitterPluginArgument Arc::TargetGenerator (Target generation class). Arc::TargetRetriever (TargetRetriever base class). Arc::TargetRetrieverLoader Arc::TargetRetrieverPluginArgument	295 302 303 304 305 306 307 308 311 312 314
Arc::SoftwareRequirement (Class used to express and resolve version requirements on software) ArcSec::Source (Acquires and parses XML document from specified source). ArcSec::SourceFile (Convenience class for obtaining XML document from file). ArcSec::SourceURL (Convenience class for obtaining XML document from remote URL). ArcSec::StringAttribute Arc::Submitter (Base class for the Submitters). Arc::SubmitterLoader Arc::SubmitterPluginArgument Arc::TargetGenerator (Target generation class). Arc::TargetRetriever (TargetRetriever base class). Arc::TargetRetrieverLoader Arc::TargetRetrieverPluginArgument Test::TestMCC	295 302 303 304 305 306 307 308 311 312 314 314
Arc::SoftwareRequirement (Class used to express and resolve version requirements on software) ArcSec::Source (Acquires and parses XML document from specified source) ArcSec::SourceFile (Convenience class for obtaining XML document from file) ArcSec::SourceURL (Convenience class for obtaining XML document from remote URL) ArcSec::StringAttribute Arc::Submitter (Base class for the Submitters) Arc::SubmitterLoader Arc::SubmitterPluginArgument Arc::TargetGenerator (Target generation class) Arc::TargetRetriever (TargetRetriever base class) Arc::TargetRetrieverLoader Arc::TargetRetrieverPluginArgument Test::TestMCC Test::TestService Arc::ThreadInitializer	295 302 303 304 305 306 307 308 311 312 314 314 315
Arc::SoftwareRequirement (Class used to express and resolve version requirements on software) ArcSec::Source (Acquires and parses XML document from specified source). ArcSec::SourceFile (Convenience class for obtaining XML document from file). ArcSec::SourceURL (Convenience class for obtaining XML document from remote URL). ArcSec::StringAttribute Arc::Submitter (Base class for the Submitters). Arc::SubmitterLoader Arc::SubmitterPluginArgument Arc::TargetGenerator (Target generation class). Arc::TargetRetriever (TargetRetriever base class). Arc::TargetRetrieverPluginArgument Test::TestMCC Test::TestService Arc::ThreadInitializer Arc::ThreadRegistry	295 302 303 304 305 306 307 308 311 312 314 315 315
Arc::SoftwareRequirement (Class used to express and resolve version requirements on software) ArcSec::Source (Acquires and parses XML document from specified source) ArcSec::SourceFile (Convenience class for obtaining XML document from file) ArcSec::SourceURL (Convenience class for obtaining XML document from remote URL) ArcSec::StringAttribute Arc::Submitter (Base class for the Submitters) Arc::SubmitterLoader Arc::SubmitterPluginArgument Arc::TargetGenerator (Target generation class) Arc::TargetRetriever (TargetRetriever base class) Arc::TargetRetrieverLoader Arc::TargetRetrieverPluginArgument Test::TestMCC Test::TestService Arc::ThreadInitializer	295 302 303 304 305 306 307 308 311 312 314 315 315 315
Arc::SoftwareRequirement (Class used to express and resolve version requirements on software) ArcSec::Source (Acquires and parses XML document from specified source) ArcSec::SourceFile (Convenience class for obtaining XML document from file) ArcSec::SourceURL (Convenience class for obtaining XML document from remote URL) ArcSec::StringAttribute Arc::Submitter (Base class for the Submitters) Arc::SubmitterLoader Arc::SubmitterPluginArgument Arc::TargetGenerator (Target generation class) Arc::TargetRetriever (TargetRetriever base class) Arc::TargetRetrieverLoader Arc::TargetRetrieverPluginArgument Test::TestMCC Test::TestMCC Test::TestService Arc::ThreadInitializer Arc::ThreadRegistry Arc::Time (A class for storing and manipulating times)	295 302 303 304 305 306 307 308 311 312 314 315 315 316 316
Arc::SoftwareRequirement (Class used to express and resolve version requirements on software) ArcSec::Source (Acquires and parses XML document from specified source). ArcSec::SourceFile (Convenience class for obtaining XML document from file) ArcSec::SourceURL (Convenience class for obtaining XML document from remote URL) ArcSec::StringAttribute Arc::Submitter (Base class for the Submitters) Arc::SubmitterLoader Arc::SubmitterPluginArgument Arc::TargetGenerator (Target generation class) Arc::TargetRetriever (TargetRetriever base class) Arc::TargetRetrieverLoader Arc::TargetRetrieverPluginArgument Test::TestMCC Test::TestMCC Test::TestService Arc::ThreadInitializer Arc::ThreadRegistry Arc::Time (A class for storing and manipulating times) ArcSec::TimeAttribute Arc::URL	295 302 303 304 305 306 307 308 311 312 314 315 315 316 316 319
Arc::SoftwareRequirement (Class used to express and resolve version requirements on software) ArcSec::Source (Acquires and parses XML document from specified source) ArcSec::SourceFile (Convenience class for obtaining XML document from file) ArcSec::SourceURL (Convenience class for obtaining XML document from remote URL) ArcSec::StringAttribute Arc::Submitter (Base class for the Submitters) Arc::SubmitterLoader Arc::SubmitterPluginArgument Arc::TargetGenerator (Target generation class) Arc::TargetRetriever (TargetRetriever base class) Arc::TargetRetrieverLoader Arc::TargetRetrieverPluginArgument Test::TestMCC Test::TestMCC Test::TestService Arc::ThreadInitializer Arc::ThreadRegistry Arc::Time (A class for storing and manipulating times) ArcSec::TimeAttribute Arc::URL Arc::URL (Convenience class in soft document from specified source) Arc URL (Convenience class in soft document from specified source) Arc URL (Convenience class for obtaining XML document from file) ArcSec::URL Arc::URL (Convenience class for obtaining XML document from file) ArcSec::SourceURL Arc::URL (Convenience class for obtaining XML document from file) ArcSec::Gura (Acquires and parses XML document from specified source) ArcSec::Gura (Acquires and parses XML document from specified source) ArcSec::Gura (Acquires and parses XML document from specified source) ArcSec::Gura (Acquires and parses XML document from specified source) Arc::Gura (Acquires and parses XML document from specified source) Arc::Gura (Acquires and parses XML document from specified source) Arc::Gura (Acquires and parses XML document from specified source) Arc::Gura (Acquires and parses XML document from specified source) Arc::Gura (Acquires and parses XML document from specified source) Arc::Gura (Acquires and parses XML document from specified source) Arc::Gura (Acquires and parses XML document from specified source) Arc::Gura (Acquires and parses Acquires and parses an	295 302 303 304 305 306 307 308 311 312 314 315 315 316 319 320
Arc::SoftwareRequirement (Class used to express and resolve version requirements on software) ArcSec::Source (Acquires and parses XML document from specified source) ArcSec::SourceFile (Convenience class for obtaining XML document from file) ArcSec::SourceURL (Convenience class for obtaining XML document from remote URL) ArcSec::StringAttribute Arc::Submitter (Base class for the Submitters) Arc::SubmitterLoader Arc::SubmitterPluginArgument Arc::TargetGenerator (Target generation class) Arc::TargetRetriever (TargetRetriever base class) Arc::TargetRetrieverLoader Arc::TargetRetrieverPluginArgument Test::TestMCC Test::TestMCC Test::TestService Arc::ThreadInitializer Arc::ThreadRegistry Arc::Time (A class for storing and manipulating times) ArcSec::TimeAttribute Arc::URL Arc::URL Arc::URLLocation (Class to hold a resolved URL (p. 320) location) Arc::URLMap	295 302 303 304 305 306 307 308 311 312 314 315 315 316 319 320 328
Arc::SoftwareRequirement (Class used to express and resolve version requirements on software) ArcSec::Source (Acquires and parses XML document from specified source). ArcSec::SourceFile (Convenience class for obtaining XML document from file). ArcSec::SourceURL (Convenience class for obtaining XML document from remote URL). ArcSec::StringAttribute Arc::Submitter (Base class for the Submitters). Arc::SubmitterLoader Arc::SubmitterPluginArgument Arc::TargetGenerator (Target generation class). Arc::TargetRetriever (TargetRetriever base class). Arc::TargetRetrieverLoader Arc::TargetRetrieverPluginArgument Test::TestMCC Test::TestMCC Test::TestService Arc::ThreadInitializer Arc::ThreadRegistry Arc::Time (A class for storing and manipulating times). ArcSec::TimeAttribute Arc::URL Arc::URL Arc::URLLocation (Class to hold a resolved URL (p. 320) location). Arc::URLMap Arc::URLMap	295 302 303 304 305 306 307 308 311 312 314 315 315 316 316 319 320 328 330 331
Arc::SoftwareRequirement (Class used to express and resolve version requirements on software) ArcSec::Source (Acquires and parses XML document from specified source) ArcSec::SourceFile (Convenience class for obtaining XML document from file) ArcSec::SourceURL (Convenience class for obtaining XML document from remote URL) ArcSec::StringAttribute Arc::Submitter (Base class for the Submitters) Arc::SubmitterPluginArgument Arc::TargetGenerator (Target generation class) Arc::TargetRetriever (TargetRetriever base class) Arc::TargetRetrieverLoader Arc::TargetRetrieverPluginArgument Test::TestMCC Test::TestMCC Test::TestService Arc::ThreadInitializer Arc::ThreadRegistry Arc::Time (A class for storing and manipulating times) ArcSec::Time (A class for storing and manipulating times) ArcSec::TimeAttribute Arc::URL Arc::URL Arc::URLLocation (Class to hold a resolved URL (p. 320) location) Arc::URLMap Arc::User Arc::UserConfig (User configuration class)	295 302 303 304 305 306 307 308 311 312 314 315 316 316 319 320 328 330
Arc::SoftwareRequirement (Class used to express and resolve version requirements on software) ArcSec::Source (Acquires and parses XML document from specified source). ArcSec::SourceFile (Convenience class for obtaining XML document from file). ArcSec::SourceURL (Convenience class for obtaining XML document from remote URL). ArcSec::StringAttribute Arc::Submitter (Base class for the Submitters). Arc::SubmitterLoader Arc::SubmitterPluginArgument Arc::TargetGenerator (Target generation class). Arc::TargetRetriever (TargetRetriever base class). Arc::TargetRetrieverLoader Arc::TargetRetrieverPluginArgument Test::TestMCC Test::TestMCC Test::TestService Arc::ThreadInitializer Arc::ThreadRegistry Arc::Time (A class for storing and manipulating times). ArcSec::TimeAttribute Arc::URL Arc::URL Arc::URLLocation (Class to hold a resolved URL (p. 320) location). Arc::URLMap Arc::URLMap	295 302 303 304 305 306 307 308 311 312 314 315 315 316 316 319 320 328 330 331

3.1 Data Structures

Arc::UserSwitch	
Arc::VOMSTrustList	
Arc::WSAEndpointReference (Interface for manipulation of WS-Adressing Endpoint Refer-	
ence)	
Arc::WSAHeader (Interface for manipulation WS-Addressing information in SOAP header)	
Arc::WSRF (Base class for every WSRF (p. 367) message)	. 367
Arc::WSRFBaseFault (Base class for WSRF (p. 367) fault messages)	. 369
Arc::WSRFResourceUnavailableFault	. 370
Arc::WSRFResourceUnknownFault	
Arc::WSRP (Base class for WS-ResourceProperties structures)	. 370
Arc::WSRPDeleteResourceProperties	
Arc::WSRPDeleteResourcePropertiesRequest	
Arc::WSRPDeleteResourcePropertiesRequestFailedFault	
Arc::WSRPDeleteResourcePropertiesResponse	
Arc::WSRPFault (Base class for WS-ResourceProperties faults)	
Arc::WSRPGetMultipleResourcePropertiesRequest	
Arc::WSRPGetMultipleResourcePropertiesResponse	
Arc::WSRPGetResourcePropertyDocumentRequest	
Arc::WSRPGetResourcePropertyDocumentResponse	
Arc::WSRPGetResourcePropertyRequest	
Arc::WSRPGetResourcePropertyResponse	
Arc::WSRPInsertResourceProperties	
Arc::WSRPInsertResourcePropertiesRequest	
Arc::WSRPInsertResourcePropertiesRequestFailedFault	
Arc::WSRPInsertResourcePropertiesResponse	
Arc::WSRPInvalidModificationFault	
Arc::WSRPInvalidResourcePropertyQNameFault	
Arc::WSRPModifyResourceProperties	
Arc::WSRPPutResourcePropertyDocumentRequest	
Arc::WSRPPutResourcePropertyDocumentResponse	
Arc::WSRPQueryResourcePropertiesRequest	
Arc::WSRPQueryResourcePropertiesResponse	
Arc::WSRPResourcePropertyChangeFailure	
Arc::WSRPSetResourcePropertiesRequest	
Arc::WSRPSetResourcePropertiesResponse	
Arc::WSRPSetResourcePropertyRequestFailedFault	
Arc::WSRPUnableToModifyResourcePropertyFault	. 383
Arc::WSRPUnableToPutResourcePropertyDocumentFault	. 384
Arc::WSRPUpdateResourceProperties	. 384
Arc::WSRPUpdateResourcePropertiesRequest	
Arc::WSRPUpdateResourcePropertiesRequestFailedFault	. 385
Arc::WSRPUpdateResourcePropertiesResponse	. 385
ArcSec::X500NameAttribute	
Arc::X509Token (Class for manipulating X.509 Token Profile (p. 256))	
Arc::XmlContainer	
Arc::XmlDatabase	
Arc::XMLNode (Wrapper for LibXML library Tree interface)	
Arc::XMLNodeContainer	
Arc::XMLSecNode (Extends XMLNode (p. 389) class to support XML security operation) .	
Arc::XRSLParser	. 404

18 Data Structure Index

Chapter 4

File Index

4.1 File List

Here is a list of all documented files with brief descriptions:

AlgFactory.h	
AnyURIAttribute.h	??
ArcConfig.h	??
ARCJSDLParser.h	
ArcLocation.h	
ArcRegex.h	??
AttributeFactory.h	??
AttributeProxy.h	
AttributeValue.h	??
Base64.h	??
BooleanAttribute.h	??
Broker.h	
ByteArray.h	??
CertUtil.h	??
CheckSum.h	??
CIStringValue.h	??
ClassLoader.h	??
ClientInterface.h	??
ClientSAML2SSO.h	??
ClientX509Delegation.h	??
CombiningAlg.h	??
ConfusaCertHandler.h	
ConfusaParserUtils.h	??
Counter.h	??
Credential.h	??
CredentialStore.h	??
DataBuffer.h	??
DataCallback.h	??
DataHandle.h	??
DataMover.h	??
DataPoint.h	??
DataPointDirect.h	??
DataPointIndex h	99

20 File Index

DataSpeed.h	
DataStatus.h	
DateTime.h	??
DateTimeAttribute.h	??
DBInterface.h	??
DBranch.h	??
DelegationInterface.h	??
DenyOverridesAlg.h	
EqualFunction.h	
EvaluationCtx.h	
Evaluator.h	
EvaluatorLoader.h	
ExecutionTarget.h	
FileCache.h	
FileCacheHash.h	
FileInfo.h	
FileLock.h	
FileUtils.h	
FinderLoader.h	
FnFactory.h	
Function.h	
GenericAttribute.h	
GlobusErrorUtils.h	
GlobusWorkarounds.h	
GSSCredential.h	
GUID.h	
HakaClient.h	
InfoCache.h	
InfoFilter.h	
InfoRegister.h	
InformationInterface.h	
IniConfig.h	
InRangeFunction.h	
IntraProcessCounter.h	
IString.h	??
JDLParser.h	??
Job.h	??
JobController.h	??
JobDescription.h	??
JobDescriptionParser.h	??
JobState.h	??
JobSupervisor.h	??
listfunc.h	??
Loader.h	??
Logger.h	??
MatchFunction.h	
MCC.h	
MCC Status.h	
MCCLoader.h	
Message.h	
MessageAttributes.h	
MessageAuth.h	
e	
ModuleManager.h	
MysqlWrapper.h	??

OAuthConsumer.h	??
OpenIdpClient.h	??
OpenSSL.h	??
OptionParser.h	??
OrderedAlg.h	??
PayloadRaw.h	??
PayloadSOAP.h	??
PayloadStream.h	??
PayloadWSRF.h	??
PDP.h	??
PermitOverridesAlg.h	??
Plexer.h	??
Plugin.h	??
Policy.h	??
PolicyParser.h	??
PolicyStore.h	??
·	??
Profile.h	??
Proxycertinfo.h	
RegisteredService.h	??
Request.h	??
RequestAttribute.h	??
RequestItem.h	??
Response.h	??
Result.h	??
RSLParser.h	??
Run.h	??
SAML2LoginClient.h	??
saml_util.h	??
SAMLToken.h	??
SecAttr.h	??
SecAttrValue.h	??
SecHandler.h	??
Security.h	??
Service.h	??
SOAPEnvelope.h	??
	??
Software.h	??
Source.h	99
StringAttribute.h	??
StringConv.h	??
Submitter.h	??
TargetGenerator.h	??
	??
6	??
loader/TestMCC.h	??
message/TestMCC.h	
TestService.h	??
Thread.h	??
7	105
URLMap.h	??
User.h	??
UserConfig.h	??
UsernameToken.h	??
Utils.h	??
VOMSAttribute.h	??

File Index

VOMSUtil.h				 			 										??
win32.h				 			 			 							??
WSA.h				 			 										??
WSResourceProperties.l	1.			 			 										??
WSRF.h				 			 			 							??
WSRFBaseFault.h				 			 			 							??
X500NameAttribute.h				 			 										??
X509Token.h				 			 										??
XmlContainer.h				 			 										??
XmlDatabase.h				 			 										??
XMLNode.h				 			 										??
XMLSecNode.h				 			 										??
XmlSecUtils.h				 			 										??
XRSLParser.h																	??

Chapter 5

Namespace Documentation

5.1 Arc Namespace Reference

Some utility methods for using xml security library (http://www.aleksey.com/xmlsec/).

Data Structures

- class ARCJSDLParser
- class Broker
- class BrokerLoader
- class BrokerPluginArgument
- class ClientInterface

Utility base class for MCC (p. 200).

class ClientTCP

Class for setting up a MCC (p. 200) chain for TCP communication.

- struct HTTPClientInfo
- class ClientHTTP

Class for setting up a MCC (p. 200) chain for HTTP communication.

- class ClientSOAP
- class SecHandlerConfig
- class DNListHandlerConfig
- class ARCPolicyHandlerConfig
- class ClientHTTPwithSAML2SSO
- class ClientSOAPwithSAML2SSO
- class ClientX509Delegation
- class ConfusaCertHandler
- class ConfusaParserUtils
- · class HakaClient
- class OpenIdpClient
- class OAuthConsumer
- class SAML2LoginClient
- class SAML2SSOHTTPClient

• class ApplicationEnvironment

ApplicationEnvironment (p. 50).

• class ExecutionTarget

ExecutionTarget (p. 153).

- · class JDLParser
- class Job

Job (p. 182).

• class JobController

Base class for the JobControllers.

- class JobControllerLoader
- class JobControllerPluginArgument
- · class Range
- class ScalableTime
- class **ScalableTime**< int >
- class JobIdentificationType
- class ExecutableType
- class NotificationType
- class ApplicationType
- class ResourceSlotType
- class DiskSpaceRequirementType
- class ResourceTargetType
- class ResourcesType
- class DataSourceType
- class DataTargetType
- · class DataType
- class FileType
- class DirectoryType
- class DataStagingType
- class JobMetaType
- class JobDescription
- class JobDescriptionParser
- class JobState
- class JobSupervisor

% JobSupervisor (p. 188) class

- · class RSLValue
- class RSLLiteral
- class RSLVariable
- class RSLConcat
- class RSLList
- · class RSLSequence
- · class RSL
- class RSLBoolean
- class RSLCondition
- class RSLParser
- class Software

Used to represent software (names and version) and comparison.

• class SoftwareRequirement

Class used to express and resolve version requirements on software.

· class Submitter

Base class for the Submitters.

- class SubmitterLoader
- class SubmitterPluginArgument
- class TargetGenerator

Target generation class

• class TargetRetriever

TargetRetriever base class

- class TargetRetrieverLoader
- class TargetRetrieverPluginArgument
- class XRSLParser
- · class Config

Configuration element - represents (sub)tree of ARC configuration.

- class BaseConfig
- class ArcLocation

Determines ARC installation location.

• class RegularExpression

A regular expression class.

- class Base64
- class MemoryAllocationException
- class ByteArray
- class Counter

A class defining a common interface for counters.

• class CounterTicket

A class for "tickets" that correspond to counter reservations.

• class ExpirationReminder

A class intended for internal use within counters.

- · class Period
- class Time

A class for storing and manipulating times.

· class Database

Interface for calling database client library.

- · class Query
- class DItem

- class DBranch
- class DItemString
- · class FileLock

A general file locking class.

- · class IniConfig
- class IntraProcessCounter

A class for counters used by threads within a single process.

- class PrintFBase
- class PrintF
- · class IString
- struct LoggerFormat
- class LogMessage

A class for log messages.

• class LogDestination

A base class for log destinations.

• class LogStream

A class for logging to ostreams.

• class LogFile

A class for logging to files.

· class Logger

A logger class.

- · class MySQLDatabase
- · class MySQLQuery
- class OptionParser
- class Profile
- class Run
- class SimpleCondition

Helper function to create simple thread.

- class SimpleCounter
- class ThreadRegistry
- class ThreadInitializer
- class URL
- class URLLocation

Class to hold a resolved URL (p. 320) location.

• class PathIterator

Class to iterate through elements of path.

- class User
- class UserSwitch
- class initializeCredentialsType
- class UserConfig

User configuration class

· class AutoPointer

Wrapper for pointer with automatic destruction.

• class CountedPointer

Wrapper for pointer with automatic destruction and mutiple references.

- class NS
- class XMLNode

Wrapper for LibXML library Tree interface.

- class XMLNodeContainer
- class CredentialError
- · class Credential
- class VOMSTrustList
- class CredentialStore
- · class CheckSum

Defines interface for variuos checksum manipulations.

• class CRC32Sum

Implementation of CRC32 checksum.

• class MD5Sum

Implementation of MD5 checksum.

• class Adler32Sum

Implementation of Adler32 checksum.

• class CheckSumAny

Wraper for CheckSum (p. 67) class.

· class DataBuffer

Represents set of buffers.

- class DataCallback
- class DataHandle

This class is a wrapper around the **DataPoint** (p. 108) class.

- class DataMover
- class DataPoint

This base class is an abstraction of URL (p. 320).

- class DataPointLoader
- $\bullet \ class \ \textbf{DataPointPluginArgument}$
- $\bullet \ class \ \textbf{DataPointDirect}$

This is a kind of generalized file handle.

• class DataPointIndex

Complements DataPoint (p. 108) with attributes common for Indexing Service (p. 282) URLs.

· class DataSpeed

Keeps track of average and instantaneous transfer speed.

- · class DataStatus
- struct CacheParameters
- class FileCache
- · class FileInfo

FileInfo (p. 163) stores information about files (metadata).

- class URLMap
- · class XmlContainer
- class XmlDatabase
- class DelegationConsumer
- class DelegationProvider
- class DelegationConsumerSOAP
- $\bullet \ class \ \textbf{DelegationProviderSOAP}$
- class DelegationContainerSOAP
- · class GlobusResult
- · class GSSCredential
- · class InfoCache

Stores XML document in filesystem split into parts.

- class InfoCacheInterface
- class InfoFilter

Filters information document according to identity of requestor.

· class InfoRegister

Registration to ISIS interface.

class InfoRegisters

Handling multiple registrations to ISISes.

- struct Register_Info_Type
- struct ISIS description
- · class InfoRegistrar

Registration process associated with particular ISIS.

- class InfoRegisterContainer
- class InformationInterface

Information System message processor.

• class InformationContainer

Information System document container and processor.

• class InformationRequest

Request for information in InfoSystem.

• class InformationResponse

Informational response from InfoSystem.

• class RegisteredService

RegisteredService (p. 260) - extension of Service (p. 282) performing self-registration.

- class FinderLoader
- · class Loader

Plugins loader.

• class LoadableModuleDesciption

• class ModuleManager

Manager of shared libraries.

· class Plugin

Base class for loadable ARC components.

• class PluginArgument

Base class for passing arguments to loadable ARC components.

• struct PluginDescriptor

Description of ARC lodable component.

· class PluginDesc

Description of plugin.

· class ModuleDesc

Description of loadable module.

· class PluginsFactory

Generic ARC plugins loader.

• class MCCInterface

Interface for communication between MCC (p. 200), Service (p. 282) and Plexer (p. 246) objects.

• class MCC

Message (p. 208) Chain Component - base class for every MCC (p. 200) plugin.

- class MCCConfig
- class MCCPluginArgument
- class MCC_Status

A class for communication of MCC (p. 200) processing results.

· class MCCLoader

Creator of Message (p. 208) Component Chains (MCC (p. 200)).

• class ChainContext

Interface to chain specific functionality.

· class MessagePayload

Base class for content of message passed through chain.

• class MessageContextElement

Top class for elements contained in message context.

• class MessageContext

Handler for content of message context.

• class MessageAuthContext

Handler for content of message auth* context.

· class Message

Object being passed through chain of MCCs.

• class AttributeIterator

A const iterator class for accessing multiple values of an attribute.

• class MessageAttributes

A class for storage of attribute values.

class MessageAuth

Contains authencity information, authorization tokens and decisions.

• class PayloadRawInterface

Random Access Payload for Message (p. 208) objects.

• struct PayloadRawBuf

· class PayloadRaw

Raw byte multi-buffer.

class PayloadSOAP

Payload of Message (p. 208) with SOAP content.

• class PayloadStreamInterface

Stream-like Payload for Message (p. 208) object.

• class PayloadStream

POSIX handle as Payload.

class PlexerEntry

A pair of label (regex) and pointer to MCC (p. 200).

· class Plexer

The Plexer (p. 246) class, used for routing messages to services.

• class CIStringValue

This class implements case insensitive strings as security attributes.

• class **SecAttrValue**

This is an abstract interface to a security attribute.

• class SecAttrFormat

Export/import format.

• class SecAttr

This is an abstract interface to a security attribute.

· class MultiSecAttr

Container of multiple SecAttr (p. 278) attributes.

· class Service

Service (p. 282) - last component in a Message (p. 208) Chain.

• class ServicePluginArgument

• class SOAPMessage

Message (p. 208) restricted to SOAP payload.

- class ClassLoader
- class ClassLoaderPluginArgument
- class WSAEndpointReference

Interface for manipulation of WS-Adressing Endpoint Reference.

• class WSAHeader

Interface for manipulation WS-Addressing information in SOAP header.

• class SAMLToken

Class for manipulating SAML Token Profile (p. 256).

• class UsernameToken

Interface for manipulation of WS-Security according to Username Token Profile (p. 256).

• class X509Token

Class for manipulating X.509 Token Profile (p. 256).

· class PayloadWSRF

This class combines MessagePayload (p. 216) with WSRF (p. 367).

· class WSRP

Base class for WS-ResourceProperties structures.

• class WSRPFault

Base class for WS-ResourceProperties faults.

- class WSRPInvalidResourcePropertyQNameFault
- class WSRPResourcePropertyChangeFailure
- class WSRPUnableToPutResourcePropertyDocumentFault
- class WSRPInvalidModificationFault
- class WSRPUnableToModifyResourcePropertyFault
- class WSRPSetResourcePropertyRequestFailedFault
- class WSRPInsertResourcePropertiesRequestFailedFault
- class WSRPUpdateResourcePropertiesRequestFailedFault
- class WSRPDeleteResourcePropertiesRequestFailedFault

- class WSRPGetResourcePropertyDocumentRequest
- class WSRPGetResourcePropertyDocumentResponse
- class WSRPGetResourcePropertyRequest
- class WSRPGetResourcePropertyResponse
- class WSRPGetMultipleResourcePropertiesRequest
- class WSRPGetMultipleResourcePropertiesResponse
- class WSRPPutResourcePropertyDocumentRequest
- class WSRPPutResourcePropertyDocumentResponse
- class WSRPModifyResourceProperties
- class WSRPInsertResourceProperties
- class WSRPUpdateResourceProperties
- class WSRPDeleteResourceProperties
- class WSRPSetResourcePropertiesRequest
- class WSRPSetResourcePropertiesResponse
- $\bullet \ class \ WSRPInsertResource Properties Request$
- class WSRPInsertResourcePropertiesResponse
- class WSRPUpdateResourcePropertiesRequest
- class WSRPUpdateResourcePropertiesResponse
- class WSRPDeleteResourcePropertiesRequest
- class WSRPDeleteResourcePropertiesResponse
- class WSRPQueryResourcePropertiesRequest
- class WSRPQueryResourcePropertiesResponse
- class WSRF

Base class for every WSRF (p. 367) message.

• class WSRFBaseFault

Base class for WSRF (p. 367) fault messages.

- class WSRFResourceUnknownFault
- class WSRFResourceUnavailableFault
- class XMLSecNode

Extends XMLNode (p. 389) class to support XML security operation.

Typedefs

- typedef Plugin *(* get_plugin_instance)(PluginArgument *arg)
- typedef std::multimap< std::string, std::string > **AttrMap**
- typedef AttrMap::const_iterator AttrConstIter
- typedef AttrMap::iterator AttrIter

Enumerations

- enum TimeFormat
- enum LogLevel
- enum StatusKind { ,

STATUS_OK = 1, GENERIC_ERROR = 2, PARSING_ERROR = 4, PROTOCOL_-RECOGNIZED_ERROR = 8,

UNKNOWN_SERVICE_ERROR = 16, BUSY_ERROR = 32, SESSION_CLOSE = 64 }

• enum WSAFault { , WSAFaultUnknown, WSAFaultInvalidAddressingHeader }

Functions

- std::ostream & operator << (std::ostream &, const Period &)
- std::ostream & operator << (std::ostream &, const Time &)
- std::string **TimeStamp** (const **TimeFormat** &=Time::GetFormat())
- std::string **TimeStamp** (**Time**, const **TimeFormat** &=Time::GetFormat())
- int **FileOpen** (const std::string &path, int flags, mode t mode=0600)
- int FileOpen (const std::string &path, int flags, uid_t uid, gid_t gid, mode_t mode=0600)
- bool FileCopy (const std::string &source_path, const std::string &destination_path)
- bool **FileCopy** (const std::string &source_path, int destination_handle)
- bool **FileCopy** (int source_handle, const std::string &destination_path)
- bool **FileCopy** (int source_handle, int destination_handle)
- Glib::Dir * **DirOpen** (const std::string &path)
- Glib::Dir * **DirOpen** (const std::string &path, uid_t uid, gid_t gid)
- bool **FileStat** (const std::string &path, struct stat *st, bool follow_symlinks)
- bool FileStat (const std::string &path, struct stat *st, uid_t uid, gid_t gid, bool follow_symlinks)
- bool **DirCreate** (const std::string &path, mode_t mode, bool with_parents=false)
- bool **DirCreate** (const std::string &path, uid_t uid, gid_t gid, mode_t mode, bool with_parents=false)
- bool **DirDelete** (const std::string &path)
- bool **DirDelete** (const std::string &path, uid_t uid, gid_t gid)
- void **GUID** (std::string &guid)
- std::string **UUID** (void)
- std::ostream & operator<< (std::ostream &os, LogLevel level)
- LogLevel string_to_level (const std::string &str)
- bool istring_to_level (const std::string &llStr, LogLevel &ll)
- bool string_to_level (const std::string &str, LogLevel &ll)
- std::string level_to_string (const LogLevel &level)
- LogLevel old_level_to_level (unsigned int old_level)
- template<typename T >

T **stringto** (const std::string &s)

 $\bullet \ \ template{<} typename \ T>$

bool **stringto** (const std::string &s, T &t)

• template<typename T >

std::string **tostring** (T t, const int width=0, const int precision=0)

- std::string **lower** (const std::string &s)
- std::string **upper** (const std::string &s)
- void tokenize (const std::string &str, std::vector< std::string > &tokens, const std::string &delimiters="")
- std::string **trim** (const std::string &str, const char *sep=NULL)
- std::string **strip** (const std::string &str)
- std::string **uri_unescape** (const std::string &str)
- std::string convert_to_rdn (const std::string &dn)
- bool CreateThreadFunction (void(*func)(void *), void *arg, SimpleCounter *count=NULL)
- std::list< URL > ReadURLList (const URL &urllist)
- std::string **GetEnv** (const std::string &var)
- std::string **GetEnv** (const std::string &var, bool &found)
- bool **SetEnv** (const std::string &var, const std::string &value, bool overwrite=true)
- void **UnsetEnv** (const std::string &var)
- std::string **StrError** (int errnum=errno)
- bool MatchXMLName (const XMLNode &node1, const XMLNode &node2)

- bool MatchXMLName (const XMLNode &node, const char *name)
- bool MatchXMLName (const XMLNode &node, const std::string &name)
- bool MatchXMLNamespace (const XMLNode &node1, const XMLNode &node2)
- bool MatchXMLNamespace (const XMLNode &node, const char *uri)
- bool MatchXMLNamespace (const XMLNode &node, const std::string &uri)
- bool **createVOMSAC** (std::string &codedac, **Credential** &issuer_cred, **Credential** &holder_cred, std::vector< std::string > &fqan, std::vector< std::string > &targets, std::vector< std::string > &attributes, std::string &voname, std::string &uri, int lifetime)
- bool addVOMSAC (ArcCredential::AC **&aclist, std::string &acorder, std::string &decodedac)
- bool **parseVOMSAC** (X509 *holder, const std::string &ca_cert_dir, const std::string &ca_cert_file, const **VOMSTrustList** &vomscert_trust_dn, std::vector< std::string > &output, bool verify=true)
- bool parseVOMSAC (const Credential &holder_cred, const std::string &ca_cert_dir, const std::string &ca_cert_file, const VOMSTrustList &vomscert_trust_dn, std::vector< std::string > &output, bool verify=true)
- char * **VOMSDecode** (const char *data, int size, int *j)
- const std::string **get_property** (const **Arc::Credential** &u, const std::string property)
- bool **OpenSSLInit** (void)
- void HandleOpenSSLError (void)
- void **HandleOpenSSLError** (int code)
- std::string string (StatusKind kind)
- const char * ContentFromPayload (const MessagePayload &payload)
- void WSAFaultAssign (SOAPEnvelope &mesage, WSAFault fid)
- WSAFault WSAFaultExtract (SOAPEnvelope &message)
- int passphrase_callback (char *buf, int size, int rwflag, void *)
- bool init xmlsec (void)
- bool final_xmlsec (void)
- std::string **get_cert_str** (const char *certfile)
- xmlSecKey * **get_key_from_keystr** (const std::string &value)
- xmlSecKey * get_key_from_keyfile (const char *keyfile)
- std::string get_key_from_certfile (const char *certfile)
- xmlSecKey * get_key_from_certstr (const std::string &value)
- xmlSecKeysMngrPtr load_key_from_keyfile (xmlSecKeysMngrPtr *keys_manager, const char *keyfile)
- xmlSecKeysMngrPtr **load_key_from_certfile** (xmlSecKeysMngrPtr *keys_manager, const char *certfile)
- xmlSecKeysMngrPtr load_key_from_certstr (xmlSecKeysMngrPtr *keys_manager, const std::string &certstr)
- xmlSecKeysMngrPtr load_trusted_cert_file (xmlSecKeysMngrPtr *keys_manager, const char *cert_file)
- xmlSecKeysMngrPtr **load_trusted_cert_str** (xmlSecKeysMngrPtr *keys_manager, const std::string &cert_str)
- xmlSecKeysMngrPtr **load_trusted_certs** (xmlSecKeysMngrPtr *keys_manager, const char *cafile, const char *capath)
- XMLNode get_node (XMLNode &parent, const char *name)

Variables

- const Glib::TimeVal ETERNAL
- const Glib::TimeVal HISTORIC
- const size_t thread_stacksize = (16 * 1024 * 1024)
- Logger CredentialLogger
- const char * plugins table name

5.1.1 Detailed Description

Some utility methods for using xml security library (http://www.aleksey.com/xmlsec/). ARCJSDLParser (p. 50) The ARCJSDLParser (p. 50) class, derived from the JobDescriptionParser (p. 187) class, is primarily a job description parser for the consolidated job description language (ARCJSDL), derived from JSDL, described in the following document http://svn.nordugrid.org/trac/nordugrid/browser/arc1/trunk/doc/tech_doc/client/job_description.odt. However it is also capable of parsing regular JSDL (GFD 136), the POSIX-JSDL extension (GFD 136) and the JSDL HPC Profile (p. 256) Application Extension (GFD 111 and GFD 114). When parsing ARCJSDL takes precedence over other non-ARCJSDL, so if a non-ARCJSDL element specifies the same attribute as ARCJSDL, the ARCJSDL element will be saved. The output generated by the ARCJSDLParser::UnParse method will follow that of the ARCJSDL document, see reference above.

JDLParser (p. 182) The **JDLParser** (p. 182) class, derived from the **JobDescriptionParser** (p. 187) class, is a job description parser for the **Job** (p. 182) Description Language (JDL) specified in CREAM **Job** (p. 182) Description Language Attributes Specification for the EGEE middleware (EGEE-JRA1-TEC-592336) and **Job** (p. 182) Description Language Attributes Specification for the gLite middleware (EGEE-JRA1-TEC-590869-JDL-Attributes-v0-8).

JobDescription (p.187) The **JobDescription** (p.187) class is the internal representation of a job description in the ARC-lib. It is structured into a number of other classes/objects which should strictly follow the description given in the job description document $\frac{\text{http://svn.nordugrid.org/trac/nordugrid/browser/arc1/trunk/doc/tech_doc/client/job_description.odt>$.

The class consist of a parsing method JobDescription::Parse which tries to parse the passed source using a number of different parsers. The parser method is complemented by the JobDescription::UnParse method, a method to generate a job description document in one of the supported formats. Additionally the internal representation is contained in public members which makes it directly accessible and modifiable from outside the scope of the class.

JobDescriptionParser (p. 187) The **JobDescriptionParser** (p. 187) class is abstract which provide a interface for job description parsers. A job description parser should inherit this class and overwrite the JobDescriptionParser::Parse and JobDescriptionParser::UnParse methods.

XRSLParser (p. 404) The **XRSLParser** (p. 404) class, derived from the **JobDescriptionParser** (p. 187) class, is a job description parser for the Extended Resource Specification Language (XRSL) specified in the NORDUGRID-MANUAL-4 document.

Credential (p. 90) class covers the functionality about general processing about certificate/key files, including: 1. cerficate/key parsing, information extracting (such as subject name, issuer name, lifetime, etc.), chain verifying, extension processing about proxy certinfo, extension processing about other general certificate extension (such as voms attributes, it should be the extension-specific code itself to create, parse and verify the extension, not the Credential (p. 90) class. For voms, it is some code about writing and parsing voms-implementing Attibute Certificate/RFC3281, the voms-attibute is then be looked as a binary part and embeded into extension of X509 certificate/proxy certificate); 2. certificate request, extension emeding and certificate signing, for both proxy certificate and EEC (end entity certificate) certificate The Crendential class support PEM, DER PKCS12 credential.

Some implicit idea in the ClassLoader/ModuleManager stuff: share_lib_name (e.g. mccsoap) should be global identical plugin_name (e.g. __arc_attrfactory_modules__) should be global identical desc->name (e.g. attr.factory) should also be global identical

5.1.2 Typedef Documentation

5.1.2.1 typedef AttrMap::const_iterator Arc::AttrConstIter

A typedef of a const_iterator for AttrMap.

This typedef is used as a shorthand for a const_iterator for AttrMap. It is used extensively within the **MessageAttributes** (p. 210) class as well as the AttributesIterator class, but is not visible externally.

5.1.2.2 typedef AttrMap::iterator Arc::AttrIter

A typedef of an (non-const) iterator for AttrMap.

This typedef is used as a shorthand for a (non-const) iterator for AttrMap. It is used in one method within the **MessageAttributes** (p. 210) class, but is not visible externally.

5.1.2.3 typedef std::multimap<std::string,std::string> Arc::AttrMap

A typefed of a multimap for storage of message attributes.

This typedef is used as a shorthand for a multimap that uses strings for keys as well as values. It is used within the MesssageAttributes class for internal storage of message attributes, but is not visible externally.

5.1.2.4 typedef Plugin*(* Arc::get plugin instance)(PluginArgument *arg)

Constructor function of ARC lodable component.

This function is called with plugin-specific argument and should produce and return valid instance of plugin. If plugin can't be produced by any reason (for example because passed argument is not applicable) then NULL is returned. No exceptions should be raised.

5.1.3 Enumeration Type Documentation

5.1.3.1 enum Arc::LogLevel

Logging levels.

Logging levels for tagging and filtering log messages. FATAL level designates very severe error events that will presumably lead the application to abort. ERROR level designates error events that might still allow the application to continue running. WARNING level designates potentially harmful situations. INFO level designates informational messages that highlight the progress of the application at coarse-grained level. VERBOSE level designates fine-grained informational events that will give additional information about the application. DEBUG level designates finer-grained informational events which should only be used for debugging purposes.

5.1.3.2 enum Arc::StatusKind

Status kinds (types).

This enum defines a set of possible status kinds.

Enumerator:

STATUS_OK Default status - undefined error.

GENERIC_ERROR No error.

PARSING_ERROR Error does not fit any class.

PROTOCOL_RECOGNIZED_ERROR Error detected while parsing request/response.

UNKNOWN_SERVICE_ERROR Message (p. 208) does not fit into expected protocol.

BUSY_ERROR There is no destination configured for this message.

SESSION_CLOSE Message (p. 208) can't be processed now.

5.1.3.3 enum Arc::WSAFault

WS-Addressing possible faults.

Enumerator:

WSAFaultUnknown This is not a faultWSAFaultInvalidAddressingHeader This is not a WS-Addressing fault

5.1.4 Function Documentation

5.1.4.1 bool Arc::addVOMSAC (ArcCredential::AC **& aclist, std::string & acorder, std::string & decodedac)

Add decoded AC string into a list of AC objects

Parameters

```
aclist The list of AC objects (output)acorder The order of AC objects (output)decodedac The AC string that is decoded from the string returned from voms server (input)
```

5.1.4.2 const char* Arc::ContentFromPayload (const MessagePayload & payload)

Returns pointer to main memory chunk of **Message** (p. 208) payload.

If no buffer is present or if payload is not of PayloadRawInterface (p. 230) type NULL is returned.

5.1.4.3 bool Arc::CreateThreadFunction (void(*)(void *) func, void * arg, SimpleCounter * count = NULL)

This macro behaves like function which makes thread of class' method.

It accepts class instance and full name of method - like class::method. 'method' should not be static member of the class. Result is true if creation of thread succeeded. Specified instance must be valid during whole lifetime of thread. So probably it is safer to destroy 'instance' in 'method' just before exiting. Helper function to create simple thread. It takes care of all pecularities of Glib::Thread API. As result it runs function 'func' with argument 'arg' in a separate thread. If count parameter not NULL then corresponding object will be incremented before function returns and then decremented then thread finished. Returns true on success.

5.1.4.4 bool Arc::createVOMSAC (std::string & codedac, Credential & issuer_cred, Credential & holder_cred, std::vector < std::string > & fqan, std::vector < std::string > & targets, std::vector < std::string > & attributes, std::string & voname, std::string & uri, int lifetime)

Create AC(Attribute Certificate) with voms specific format.

Parameters

codedac The coded AC as output of this method

issuer_cred The issuer credential which is used to sign the AC

holder_cred The holder credential, the holder certificate is the one which carries AC The rest arguments are the same as the above method

5.1.4.5 int Arc::FileOpen (const std::string & path, int flags, mode_t mode = 0600)

Utility functions for handling files and directories.

Open a file and return a file handle

5.1.4.6 bool Arc::final_xmlsec (void)

Finalize the xml security library

5.1.4.7 std::string Arc::get_cert_str (const char * certfile)

Get certificate in string format from certificate file

5.1.4.8 std::string Arc::get_key_from_certfile (const char * certfile)

Get public key in string format from certificate file

5.1.4.9 xmlSecKey* Arc::get_key_from_certstr (const std::string & value)

Get public key in xmlSecKey structure from certificate string (the string under "----BEGIN CERTIFICATE-----" and "-----END CERTIFICATE-----")

5.1.4.10 xmlSecKey* Arc::get_key_from_keyfile (const char * keyfile)

Get key in xmlSecKey structure from key file

5.1.4.11 xmlSecKey* Arc::get_key_from_keystr (const std::string & value)

Get key in xmlSecKey structure from key in string format

5.1.4.12 XMLNode Arc::get_node (XMLNode & parent, const char * name)

Generate a new child XMLNode (p. 389) with specified name

5.1.4.13 const std::string Arc::get_property (const Arc::Credential & u, const std::string property)

Extract the needed field from the certificate

5.1.4.14 void Arc::GUID (std::string & guid)

Utilities for generating unique identifiers in the form 12345678-90ab-cdef-1234-567890abcdef.

Generates a unique identifier using information such as IP address, current time etc.

5.1.4.15 bool Arc::init_xmlsec (void)

Initialize the xml security library, it should be called before the xml security functionality is used.

5.1.4.16 bool Arc::istring_to_level (const std::string & llStr, LogLevel & ll)

Case-insensitive parsing of a string to a LogLevel with error response.

The method will try to parse (case-insensitive) the argument string to a corresponding LogLevel. If the method succeeds, true will be returned and the argument ll will be set to the parsed LogLevel. If the parsing fails false will be returned. The parsing succeeds if llStr match (case-insensitively) one of the names of the LogLevel members.

Parameters

llStr a string which should be parsed to a Arc::LogLevel (p. 36).

**ll a Arc::LogLevel (p. 36) reference which will be set to the matching Arc::LogLevel (p. 36) upon successful parsing.

Returns

true in case of successful parsing, otherwise false.

See also

LogLevel (p. 36)

5.1.4.17 xmlSecKeysMngrPtr Arc::load_key_from_certfile (xmlSecKeysMngrPtr * keys_manager, const char * certfile)

Load public key from a certificate file into key manager

5.1.4.18 xmlSecKeysMngrPtr Arc::load_key_from_certstr (xmlSecKeysMngrPtr * keys_manager, const std::string & certstr)

Load public key from a certificate string into key manager

5.1.4.19 xmlSecKeysMngrPtr Arc::load_key_from_keyfile (xmlSecKeysMngrPtr * keys manager, const char * keyfile)

Load private or public key from a key file into key manager

5.1.4.20 xmlSecKeysMngrPtr Arc::load_trusted_cert_file (xmlSecKeysMngrPtr * keys_manager, const char * cert_file)

Load trusted certificate from certificate file into key manager

5.1.4.21 xmlSecKeysMngrPtr Arc::load_trusted_cert_str (xmlSecKeysMngrPtr * keys_manager, const std::string & cert_str)

Load trusted certificate from cetrtificate string into key manager

5.1.4.22 xmlSecKeysMngrPtr Arc::load_trusted_certs (xmlSecKeysMngrPtr * keys_manager, const char * cafile, const char * capath)

Load trusted cetificates from a file or directory into key manager

5.1.4.23 bool Arc::MatchXMLName (const XMLNode & node1, const XMLNode & node2)

Returns true if underlying XML elements have same names

5.1.4.24 bool Arc::MatchXMLName (const XMLNode & node, const char * name)

Returns true if 'name' matches name of 'node'. If name contains prefix it's checked too

5.1.4.25 bool Arc::MatchXMLName (const XMLNode & node, const std::string & name)

Returns true if 'name' matches name of 'node'. If name contains prefix it's checked too

5.1.4.26 bool Arc::MatchXMLNamespace (const XMLNode & node, const std::string & uri)

Returns true if 'namespace' matches 'node's namespace.

5.1.4.27 bool Arc::MatchXMLNamespace (const XMLNode & node1, const XMLNode & node2)

Returns true if underlying XML elements belong to same namespaces

5.1.4.28 bool Arc::MatchXMLNamespace (const XMLNode & node, const char * uri)

Returns true if 'namespace' matches 'node's namespace.

5.1.4.29 bool Arc::OpenSSLInit (void)

This module contains various convenience utilities for using OpenSSL.

Application may be linked to this module instead of OpenSSL libraries directly. This function initializes OpenSSL library. It may be called multiple times and makes sure everything is done properly and OpenSSL may be used in multi-threaded environment. Because this function makes use of **ArcLocation** (p. 51) it is advisable to call it after **ArcLocation::Init()** (p. 51).

5.1.4.30 std::ostream& Arc::operator<< (std::ostream & , const Period &)

Prints a Period-object to the given ostream -- typically cout.

5.1.4.31 std::ostream& Arc::operator<< (std::ostream & , const Time &)

Prints a Time-object to the given ostream -- typically cout.

5.1.4.32 std::ostream& Arc::operator<< (std::ostream & os, LogLevel level)

Printing of LogLevel values to ostreams.

Output operator so that LogLevel values can be printed in a nicer way.

5.1.4.33 bool Arc::parseVOMSAC (X509 * holder, const std::string & ca_cert_dir, const std::string & ca_cert_file, const VOMSTrustList & vomscert_trust_dn, std::vector < std::string > & output, bool verify = true)

Parse the certificate, and output the attributes.

Parameters

holder The proxy certificate which includes the voms specific formated AC.

- ca_cert_dir The trusted certificates which are used to verify the certificate which is used to sign the
 AC
- ca_cert_file The same as ca_cert_dir except it is a file instead of a directory. Only one of them need to be set
- vomsdir The directory which include *.lsc file for each vo. For instance, a vo called "knowarc.eu" should have file \$prefix/vomsdir/knowarc/voms.knowarc.eu.lsc which contains on the first line the DN of the VOMS server, and on the second line the corresponding CA DN: /O=Grid/O=NorduGrid/OU=KnowARC/CN=voms.knowarc.eu /O=Grid/O=NorduGrid/CN=NorduGrid Certification Authority See more in : https://twiki.cern.ch/twiki/bin/view/LCG/VomsFAQforServiceManagers
- output The parsed attributes (Role and Generic Attribute). Each attribute is stored in element of a vector as a string. It is up to the consumer to understand the meaning of the attribute. There are two types of attributes stored in VOMS AC: AC_IETFATTR, AC_FULL_ATTRIBUTES. The AC_IETFATTR will be like /Role=Employee/Group=Tester/Capability=NULL The AC_FULL_ATTRIBUTES will be like knowarc:Degree=PhD (qualifier::name=value) In order to make the output attribute values be identical, the voms server information is added as prefix of the original attributes in AC. for AC_FULL_ATTRIBUTES, the voname + hostname is added: /voname=knowarc.eu/hostname=arthur.hep.lu.se:15001//knowarc.eu/coredev:attribute1=1 for AC_IETFATTR, the 'VO' (voname) is added: /VO=knowarc.eu/Group=coredev/Role=NULL/Capability=NULL /VO=knowarc.eu/Group=testers/Role=NULL/Capability=NULL

some other redundant attributes is provided: voname=knowarc.eu/hostname=arthur.hep.lu.se:15001

Parameters

verify true: Verify the voms certificate is trusted based on the ca_cert_dir/ca_cert_file which specifies the CA certificates, and the vomscert_trust_dn which specifies the trusted DN chain from voms server certificate to CA certificate.

false: Not verify, which means the issuer of AC (voms server certificate is supposed to be trusted by default). In this case the parameters 'ca_cert_dir', 'ca_cert_file' and 'vomscert_trust_dn' will not effect, and should be set as empty. This case is specifically used by 'arcproxy --info' to list all of the attributes in AC, and not to need to verify if the AC's issuer is trusted.

5.1.4.34 bool Arc::parseVOMSAC (const Credential & holder_cred, const std::string & ca_cert_dir, const std::string & ca_cert_file, const VOMSTrustList & vomscert_trust_dn, std::vector< std::string > & output, bool verify = true)

Parse the certificate. The same as the above one

5.1.4.35 int Arc::passphrase_callback (char * buf, int size, int rwflag, void *)

callback method for inputing passphrase of key file

5.1.4.36 std::string Arc::string (StatusKind kind)

Conversion to string.

Conversion from StatusKind to string.

Parameters

kind The StatusKind to convert.

5.1.4.37 std::string Arc::TimeStamp (Time, const TimeFormat & = Time::GetFormat ())

Returns a time-stamp of some specified time in some format.

5.1.4.38 std::string Arc::TimeStamp (const TimeFormat & = Time::GetFormat())

Returns a time-stamp of the current time in some format.

5.1.4.39 char* Arc:: VOMSDecode (const char * data, int size, int * j)

Decode the data which is encoded by voms server. Since voms code uses some specific coding method (not base64 encoding), we simply copy the method from voms code to here

5.1.4.40 void Arc::WSAFaultAssign (SOAPEnvelope & mesage, WSAFault fid)

Makes WS-Addressing fault.

It fills SOAP Fault message with WS-Addressing fault related information.

5.1.4.41 WSAFault Arc::WSAFaultExtract (SOAPEnvelope & message)

Gets WS-addressing fault.

Analyzes SOAP Fault message and returns WS-Addressing fault it represents.

5.1.5 Variable Documentation

5.1.5.1 Logger Arc::CredentialLogger

Logger (p. 193) to be used by all modules of credentials library

5.1.5.2 const char* Arc::plugins_table_name

Name of symbol refering to table of plugins.

This C null terminated string specifies name of symbol which shared library should export to give an access to an array of **PluginDescriptor** (p. 250) elements. The array is terminated by element with all components set to NULL.

5.1.5.3 const size_t Arc::thread_stacksize = (16 * 1024 * 1024)

This module provides convenient helpers for Glibmm interface for thread management.

So far it takes care of automatic initialization of threading environment and creation of simple detached threads. Always use it instead of glibmm/thread.h and keep among first includes. It safe to use it multiple times and to include it both from source files and other include files. Defines size of stack assigned to every new thread.

5.2 ArcCredential Namespace Reference

Data Structures

- struct cert_verify_context
- struct PROXYPOLICY st
- struct PROXYCERTINFO_st
- struct ACDIGEST
- struct ACIS
- struct ACFORM
- struct ACACI
- struct ACHOLDER
- struct ACVAL
- struct ACIETFATTR
- struct ACTARGET
- struct ACTARGETS
- struct ACATTR
- struct ACINFO
- struct ACC
- struct ACSEO
- struct ACCERTS
- struct ACATTRIBUTE
- struct ACATTHOLDER
- struct ACFULLATTRIBUTES

Enumerations

enum certType {

CERT_TYPE_EEC, CERT_TYPE_CA, CERT_TYPE_GSI_3_IMPERSONATION_PROXY, CERT_TYPE_GSI_3_INDEPENDENT_PROXY,

CERT_TYPE_GSI_3_LIMITED_PROXY, CERT_TYPE_GSI_3_RESTRICTED_PROXY, CERT_TYPE_GSI_2_PROXY, CERT_TYPE_GSI_2_LIMITED_PROXY,

 $\begin{array}{lll} \textbf{CERT_TYPE_RFC_IMPERSONATION_PROXY}, & \textbf{CERT_TYPE_RFC_INDEPENDENT_PROXY}, & \textbf{CERT_TYPE_RFC_LIMITED_PROXY}, & \textbf{CERT_TYPE_RFC_RESTRICTED_PROXY}, \\ \end{array}$

CERT_TYPE_RFC_ANYLANGUAGE_PROXY }

5.2.1 Detailed Description

Functions and constants for maintaining proxy certificates The code is derived from globus gsi, voms, and openssl-0.9.8e. The existing code for maintaining proxy certificates in OpenSSL only covers standard proxies and does not cover old Globus proxies, so here the Globus code is introduced.

Borrow the code about Attribute Certificate from VOMS The **VOMSAttribute.h** (p. ??) and VOMSAttribute.cpp are integration about code written by VOMS project, so here the original license follows.

5.2.2 Enumeration Type Documentation

5.2.2.1 enum ArcCredential::certType

Enumerator:

CERT TYPE EEC A end entity certificate

CERT_TYPE_CA A CA certificate

CERT_TYPE_GSI_3_IMPERSONATION_PROXY A X.509 Proxy Certificate Profile (pre-RFC) compliant impersonation proxy

CERT_TYPE_GSI_3_INDEPENDENT_PROXY A X.509 Proxy Certificate Profile (pre-RFC) compliant independent proxy

CERT_TYPE_GSI_3_LIMITED_PROXY A X.509 Proxy Certificate Profile (pre-RFC) compliant limited proxy

CERT_TYPE_GSI_3_RESTRICTED_PROXY A X.509 Proxy Certificate Profile (pre-RFC) compliant restricted proxy

CERT_TYPE_GSI_2_PROXY A legacy Globus impersonation proxy

CERT_TYPE_GSI_2_LIMITED_PROXY A legacy Globus limited impersonation proxy

CERT_TYPE_RFC_IMPERSONATION_PROXY A X.509 Proxy Certificate Profile RFC compliant impersonation proxy; RFC inheritAll proxy

CERT_TYPE_RFC_INDEPENDENT_PROXY A X.509 Proxy Certificate Profile RFC compliant independent proxy; RFC independent proxy

CERT_TYPE_RFC_LIMITED_PROXY A X.509 Proxy Certificate Profile RFC compliant limited proxy

CERT_TYPE_RFC_RESTRICTED_PROXY A X.509 Proxy Certificate Profile RFC compliant restricted proxy

CERT_TYPE_RFC_ANYLANGUAGE_PROXY RFC anyLanguage proxy

Chapter 6

Data Structure Documentation

6.1 ArcCredential::ACACI Struct Reference

The documentation for this struct was generated from the following file:

· VOMSAttribute.h

6.2 ArcCredential::ACATTHOLDER Struct Reference

The documentation for this struct was generated from the following file:

· VOMSAttribute.h

6.3 ArcCredential::ACATTR Struct Reference

The documentation for this struct was generated from the following file:

• VOMSAttribute.h

6.4 ArcCredential::ACATTRIBUTE Struct Reference

The documentation for this struct was generated from the following file:

• VOMSAttribute.h

6.5 ArcCredential::ACC Struct Reference

The documentation for this struct was generated from the following file:

• VOMSAttribute.h

6.6 ArcCredential::ACCERTS Struct Reference

The documentation for this struct was generated from the following file:

· VOMSAttribute.h

6.7 ArcCredential::ACDIGEST Struct Reference

The documentation for this struct was generated from the following file:

• VOMSAttribute.h

6.8 ArcCredential::ACFORM Struct Reference

The documentation for this struct was generated from the following file:

· VOMSAttribute.h

6.9 ArcCredential::ACFULLATTRIBUTES Struct Reference

The documentation for this struct was generated from the following file:

• VOMSAttribute.h

6.10 ArcCredential::ACHOLDER Struct Reference

The documentation for this struct was generated from the following file:

• VOMSAttribute.h

6.11 ArcCredential::ACIETFATTR Struct Reference

The documentation for this struct was generated from the following file:

· VOMSAttribute.h

6.12 ArcCredential::ACINFO Struct Reference

The documentation for this struct was generated from the following file:

• VOMSAttribute.h

6.13 ArcCredential::ACIS Struct Reference

The documentation for this struct was generated from the following file:

• VOMSAttribute.h

6.14 ArcCredential::ACSEQ Struct Reference

The documentation for this struct was generated from the following file:

• VOMSAttribute.h

6.15 ArcCredential::ACTARGET Struct Reference

The documentation for this struct was generated from the following file:

· VOMSAttribute.h

6.16 ArcCredential::ACTARGETS Struct Reference

The documentation for this struct was generated from the following file:

• VOMSAttribute.h

6.17 ArcCredential::ACVAL Struct Reference

The documentation for this struct was generated from the following file:


• VOMSAttribute.h

6.18 Arc::Adler32Sum Class Reference

Implementation of Adler32 checksum.

#include <CheckSum.h>

Inheritance diagram for Arc::Adler32Sum:



6.18.1 Detailed Description

Implementation of Adler32 checksum.

The documentation for this class was generated from the following file:


· CheckSum.h

6.19 ArcSec::AlgFactory Class Reference

Interface for algorithm factory class.

#include <AlgFactory.h>

Inheritance diagram for ArcSec::AlgFactory:



Public Member Functions

• virtual CombiningAlg * createAlg (const std::string &type)=0

6.19.1 Detailed Description

Interface for algorithm factory class. **AlgFactory** (p. 48) is in charge of creating **CombiningAlg** (p. 75) according to the algorithm type given as argument of method createAlg. This class can be inherited for implementing a factory class which can create some specific combining algorithm objects.

6.19.2 Member Function Documentation

6.19.2.1 virtual CombiningAlg* ArcSec::AlgFactory::createAlg (const std::string & type) [pure virtual]

creat algorithm object based on the type algorithm type

Parameters

type The type of combining algorithm

Returns


The object of **CombiningAlg** (p. 75)

The documentation for this class was generated from the following file:

· AlgFactory.h

6.20 ArcSec::AnyURIAttribute Class Reference

Inheritance diagram for ArcSec::AnyURIAttribute:



Public Member Functions

- virtual bool equal (AttributeValue *other, bool check_id=true)
- virtual std::string encode ()
- std::string getId ()
- virtual std::string getType ()

6.20.1 Member Function Documentation

6.20.1.1 virtual std::string ArcSec::AnyURIAttribute::encode() [inline, virtual]

encode the value in a string format

Implements ArcSec::AttributeValue (p. 57).

6.20.1.2 virtual bool ArcSec::AnyURIAttribute::equal (AttributeValue * value, bool check_id = true) [virtual]

Evluate whether "this" equale to the parameter value

Implements ArcSec::AttributeValue (p. 58).

6.20.1.3 std::string ArcSec::AnyURIAttribute::getId() [inline, virtual]

Get the AttributeId of the <Attribute>

Implements ArcSec::AttributeValue (p. 58).

6.20.1.4 virtual std::string ArcSec::AnyURIAttribute::getType() [inline, virtual]

Get the DataType of the <Attribute>

Implements ArcSec::AttributeValue (p. 58).

The documentation for this class was generated from the following file:


• AnyURIAttribute.h

6.21 Arc::ApplicationEnvironment Class Reference

ApplicationEnvironment (p. 50).

#include <ExecutionTarget.h>

Inheritance diagram for Arc::ApplicationEnvironment:



6.21.1 Detailed Description

ApplicationEnvironment (p. 50). The ApplicationEnvironment is closely related to the definition given in GLUE2. By extending the **Software** (p. 288) class the two GLUE2 attributes AppName and AppVersion are mapped to two private members. However these can be obtained through the inheritaed member methods getName and getVersion.

GLUE2 description: A description of installed application software or software environment characteristics available within one or more Execution Environments.

The documentation for this class was generated from the following file:

· ExecutionTarget.h

6.22 Arc::ApplicationType Class Reference

The documentation for this class was generated from the following file:

· JobDescription.h

6.23 Arc::ARCJSDLParser Class Reference

Inheritance diagram for Arc::ARCJSDLParser:



The documentation for this class was generated from the following file:

• ARCJSDLParser.h

6.24 Arc::ArcLocation Class Reference

Determines ARC installation location.

#include <ArcLocation.h>

Static Public Member Functions

- static void **Init** (std::string path)
- static const std::string & Get ()
- static std::list< std::string > **GetPlugins** ()

6.24.1 Detailed Description

Determines ARC installation location.

6.24.2 Member Function Documentation

6.24.2.1 static std::list<std::string> Arc::ArcLocation::GetPlugins() [static]

Returns ARC plugins directory location.

Main source is value of variable ARC_PLUGIN_PATH, otherwise path is derived from installation location.

6.24.2.2 static void Arc::ArcLocation::Init (std::string path) [static]

Initializes location information.

Main source is value of variable ARC_LOCATION, otherwise path to executable provided in is used. If nothing works then warning message is sent to logger and initial installation prefix is used.

The documentation for this class was generated from the following file:

· ArcLocation.h


6.25 ArcSec::ArcPeriod Struct Reference

The documentation for this struct was generated from the following file:

• DateTimeAttribute.h

6.26 Arc::ARCPolicyHandlerConfig Class Reference

Inheritance diagram for Arc::ARCPolicyHandlerConfig:



The documentation for this class was generated from the following file:

• ClientInterface.h

6.27 ArcSec::Attr Struct Reference

Attr (p. 52) contains a tuple of attribute type and value.

#include <Request.h>

6.27.1 Detailed Description

Attr (p. 52) contains a tuple of attribute type and value.


The documentation for this struct was generated from the following file:

• Request.h

6.28 ArcSec::AttributeFactory Class Reference

#include <AttributeFactory.h>

Inheritance diagram for ArcSec::AttributeFactory:



6.28.1 Detailed Description

Base attribute factory class

The documentation for this class was generated from the following file:

· AttributeFactory.h

6.29 Arc::AttributeIterator Class Reference

A const iterator class for accessing multiple values of an attribute.

```
#include <MessageAttributes.h>
```

Public Member Functions

- AttributeIterator ()
- const std::string & operator* () const
- const std::string * operator-> () const
- const std::string & key (void) const
- const AttributeIterator & operator++ ()
- AttributeIterator operator++ (int)
- bool hasMore () const

Protected Member Functions

• AttributeIterator (AttrConstIter begin, AttrConstIter end)

Protected Attributes

- AttrConstIter current_
- AttrConstIter end

Friends

• class MessageAttributes

6.29.1 Detailed Description

A const iterator class for accessing multiple values of an attribute. This is an iterator class that is used when accessing multiple values of an attribute. The getAll() method of the **MessageAttributes** (p. 210) class returns an **AttributeIterator** (p. 53) object that can be used to access the values of the attribute.

Typical usage is:

```
MessageAttributes attributes;
...
for (AttributeIterator iterator=attributes.getAll("Foo:Bar");
    iterator.hasMore(); ++iterator)
    std::cout << *iterator << std::endl;</pre>
```

6.29.2 Constructor & Destructor Documentation

6.29.2.1 Arc::AttributeIterator::AttributeIterator ()

Default constructor.

The default constructor. Does nothing since all attributes are instances of well-behaving STL classes.

6.29.2.2 Arc::AttributeIterator::AttributeIterator (AttrConstIter *begin*, AttrConstIter *end*) [protected]

Protected constructor used by the MessageAttributes (p. 210) class.

This constructor is used to create an iterator for iteration over all values of an attribute. It is not supposed to be visible externally, but is only used from within the getAll() method of **MessageAttributes** (p. 210) class.

Parameters

begin A const_iterator pointing to the first matching key-value pair in the internal multimap of the **MessageAttributes** (p. 210) class.

end A const_iterator pointing to the first key-value pair in the internal multimap of the MessageAttributes (p. 210) class where the key is larger than the key searched for.

6.29.3 Member Function Documentation

6.29.3.1 bool Arc::AttributeIterator::hasMore () const

Predicate method for iteration termination.

This method determines whether there are more values for the iterator to refer to.

Returns

Returns true if there are more values, otherwise false.

6.29.3.2 const std::string& Arc::AttributeIterator::key (void) const

The key of attribute.

This method returns reference to key of attribute to which iterator refers.

6.29.3.3 const std::string& Arc::AttributeIterator::operator*() const

The dereference operator.

This operator is used to access the current value referred to by the iterator.

Returns

A (constant reference to a) string representation of the current value.

6.29.3.4 const AttributeIterator& Arc::AttributeIterator::operator++ ()

The prefix advance operator.

Advances the iterator to the next value. Works intuitively.

Returns

A const reference to this iterator.

6.29.3.5 AttributeIterator Arc::AttributeIterator::operator++ (int)

The postfix advance operator.

Advances the iterator to the next value. Works intuitively.

Returns

An iterator referring to the value referred to by this iterator before the advance.

6.29.3.6 const std::string* Arc::AttributeIterator::operator-> () const

The arrow operator.

Used to call methods for value objects (strings) conveniently.

6.29.4 Friends And Related Function Documentation

6.29.4.1 friend class MessageAttributes [friend]

The MessageAttributes (p. 210) class is a friend.

The constructor that creates an **AttributeIterator** (p. 53) that is connected to the internal multimap of the **MessageAttributes** (p. 210) class should not be exposed to the outside, but it still needs to be accessible from the getAll() method of the **MessageAttributes** (p. 210) class. Therefore, that class is a friend.

6.29.5 Field Documentation

6.29.5.1 AttrConstIter Arc::AttributeIterator::current_ [protected]

A const_iterator pointing to the current key-value pair.

This iterator is the internal representation of the current value. It points to the corresponding key-value pair in the internal multimap of the **MessageAttributes** (p. 210) class.

6.29.5.2 AttrConstIter Arc::AttributeIterator::end_ [protected]

A const_iterator pointing beyond the last key-value pair.

A const_iterator pointing to the first key-value pair in the internal multimap of the **MessageAttributes** (p. 210) class where the key is larger than the key searched for.

The documentation for this class was generated from the following file:

· MessageAttributes.h

6.30 ArcSec::AttributeProxy Class Reference

Interface for creating the AttributeValue (p. 56) object, it will be used by AttributeFactory (p. 52).

#include <AttributeProxy.h>

Public Member Functions

• virtual AttributeValue * getAttribute (const Arc::XMLNode &node)=0

6.30.1 Detailed Description

Interface for creating the **AttributeValue** (p. 56) object, it will be used by **AttributeFactory** (p. 52). The **AttributeProxy** (p. 55) object will be insert into AttributeFactoty; and the getAttribute(node) method will be called inside AttributeFacroty.createvalue(node), in order to create a specific **AttributeValue** (p. 56)

6.30.2 Member Function Documentation

6.30.2.1 virtual AttributeValue* ArcSec::AttributeProxy::getAttribute(const Arc::XMLNode & node) [pure virtual]

Create a **AttributeValue** (p. 56) object according to the information inside the XMLNode as parameter. The documentation for this class was generated from the following file:


• AttributeProxy.h

6.31 ArcSec::AttributeValue Class Reference

Interface for containing different type of <Attribute> node for both policy and request.

#include <AttributeValue.h>

Inheritance diagram for ArcSec::AttributeValue:



Public Member Functions

- virtual bool equal (AttributeValue *value, bool check_id=true)=0
- virtual std::string **encode** ()=0
- virtual std::string **getType** ()=0
- virtual std::string **getId** ()=0

6.31.1 Detailed Description

Interface for containing different type of <Attribute> node for both policy and request. <Attribute> contains different "Type" definition; Each type of <Attribute> needs different approach to compare the value. Any specific class which is for processing specific "Type" should inherit this class. The "Type" supported so far is: **StringAttribute** (p. 305), **DateAttribute** (p. 133), **TimeAttribute** (p. 319), **DurationAttribute** (p. 145), **PeriodAttribute** (p. 244), **AnyURIAttribute** (p. 49), **X500NameAttribute** (p. 386)

6.31.2 Member Function Documentation

6.31.2.1 virtual std::string ArcSec::AttributeValue::encode() [pure virtual]

encode the value in a string format

Implemented in ArcSec::AnyURIAttribute (p. 49), ArcSec::BooleanAttribute (p. 62), ArcSec::DateTimeAttribute (p. 134), ArcSec::TimeAttribute (p. 320), ArcSec::DateAttribute (p. 133),

ArcSec::DurationAttribute (p. 145), ArcSec::PeriodAttribute (p. 244), ArcSec::GenericAttribute (p. 166), ArcSec::StringAttribute (p. 305), and ArcSec::X500NameAttribute (p. 386).

6.31.2.2 virtual bool ArcSec::AttributeValue::equal (AttributeValue * value, bool check_id = true) [pure virtual]

Evluate whether "this" equale to the parameter value

Implemented in ArcSec::AnyURIAttribute (p. 49), ArcSec::BooleanAttribute (p. 62), ArcSec::DateTimeAttribute (p. 134), ArcSec::TimeAttribute (p. 320), ArcSec::DateAttribute (p. 133), ArcSec::DurationAttribute (p. 146), ArcSec::PeriodAttribute (p. 244), ArcSec::GenericAttribute (p. 166), ArcSec::StringAttribute (p. 305), and ArcSec::X500NameAttribute (p. 386).

6.31.2.3 virtual std::string ArcSec::AttributeValue::getId() [pure virtual]

Get the AttributeId of the <Attribute>

Implemented in ArcSec::AnyURIAttribute (p. 49), ArcSec::BooleanAttribute (p. 62), ArcSec::DateTimeAttribute (p. 134), ArcSec::TimeAttribute (p. 320), ArcSec::DateAttribute (p. 133), ArcSec::DurationAttribute (p. 146), ArcSec::PeriodAttribute (p. 244), ArcSec::GenericAttribute (p. 166), ArcSec::StringAttribute (p. 305), and ArcSec::X500NameAttribute (p. 386).

6.31.2.4 virtual std::string ArcSec::AttributeValue::getType() [pure virtual]

Get the DataType of the <Attribute>

Implemented in ArcSec::AnyURIAttribute (p. 49), ArcSec::BooleanAttribute (p. 62), ArcSec::DateTimeAttribute (p. 134), ArcSec::TimeAttribute (p. 320), ArcSec::DateAttribute (p. 133), ArcSec::DurationAttribute (p. 146), ArcSec::PeriodAttribute (p. 244), ArcSec::GenericAttribute (p. 166), ArcSec::StringAttribute (p. 305), and ArcSec::X500NameAttribute (p. 386).

The documentation for this class was generated from the following file:

• AttributeValue.h

6.32 ArcSec::Attrs Class Reference

Attrs (p. 58) is a container for one or more **Attr** (p. 52).

#include <Request.h>

6.32.1 Detailed Description

Attrs (p. 58) is a container for one or more Attr (p. 52). Attrs (p. 58) includes includes methonds for inserting, getting items, and counting size as well

The documentation for this class was generated from the following file:

· Request.h

6.33 ArcSec::AuthzRequest Struct Reference

The documentation for this struct was generated from the following file:

• PDP.h

6.34 ArcSec::AuthzRequestSection Struct Reference

#include <PDP.h>

6.34.1 Detailed Description

These structure are based on the request schema for **PDP** (p. 240), so far it can apply to the ArcPDP's request schema, see src/hed/pdc/Request.xsd and src/hed/pdc/Request.xml. It could also apply to the XACMLPDP's request schema, since the difference is minor.

Another approach is, the service composes/marshalls the xml structure directly, then the service should use difference code to compose for ArcPDP's request schema and XACMLPDP's schema, which is not so good.

The documentation for this struct was generated from the following file:

• PDP.h

6.35 Arc::AutoPointer< T > Class Template Reference

Wrapper for pointer with automatic destruction.

#include <Utils.h>

Public Member Functions

- AutoPointer (void)
- AutoPointer (T *o)
- ∼**AutoPointer** (void)
- T & operator* (void) const
- T * **operator**-> (void) const
- operator bool (void) const
- bool operator! (void) const
- operator T * (void) const

6.35.1 Detailed Description

template < typename T > class Arc::AutoPointer < T >

Wrapper for pointer with automatic destruction. If ordinary pointer is wrapped in instance of this class it will be automatically destroyed when instance is destroyed. This is useful for maintaing pointers in scope of one function. Only pointers returned by new() are supported.

The documentation for this class was generated from the following file:

• Utils.h

6.36 Arc::Base64 Class Reference


The documentation for this class was generated from the following file:

• Base64.h

6.37 Arc::BaseConfig Class Reference

#include <ArcConfig.h>

Inheritance diagram for Arc::BaseConfig:



Public Member Functions

- void AddPluginsPath (const std::string &path)
- void AddPrivateKey (const std::string &path)
- void AddCertificate (const std::string &path)
- void **AddProxy** (const std::string &path)
- void **AddCAFile** (const std::string &path)
- void AddCADir (const std::string &path)
- void AddOverlay (XMLNode cfg)
- void **GetOverlay** (std::string fname)
- virtual XMLNode MakeConfig (XMLNode cfg) const

6.37.1 Detailed Description

Configuration for client interface. It contains information which can't be expressed in class constructor arguments. Most probably common things like software installation location, identity of user, etc.

6.37.2 Member Function Documentation

6.37.2.1 void Arc::BaseConfig::AddCADir (const std::string & path)

Add CA directory

6.37.2.2 void Arc::BaseConfig::AddCAFile (const std::string & path)

Add CA file

6.37.2.3 void Arc::BaseConfig::AddCertificate (const std::string & path)

Add certificate

6.37.2.4 void Arc::BaseConfig::AddOverlay (XMLNode cfg)

Add configuration overlay

6.37.2.5 void Arc::BaseConfig::AddPluginsPath (const std::string & path)

Adds non-standard location of plugins

6.37.2.6 void Arc::BaseConfig::AddPrivateKey (const std::string & path)

Add private key

6.37.2.7 void Arc::BaseConfig::AddProxy (const std::string & path)

Add credentials proxy

6.37.2.8 void Arc::BaseConfig::GetOverlay (std::string fname)

Read overlay from file

6.37.2.9 virtual XMLNode Arc::BaseConfig::MakeConfig (XMLNode cfg) const [virtual]


Adds configuration part corresponding to stored information into common configuration tree supplied in 'cfg' argument. Returns reference to XML node representing configuration of **ModuleManager** (p. 217) Reimplemented in **Arc::MCCConfig** (p. 205).

The documentation for this class was generated from the following file:

• ArcConfig.h

6.38 ArcSec::BooleanAttribute Class Reference

Inheritance diagram for ArcSec::BooleanAttribute:



Public Member Functions

- virtual bool equal (AttributeValue *o, bool check_id=true)
- virtual std::string encode ()
- std::string getId ()
- std::string getType ()

6.38.1 Member Function Documentation

6.38.1.1 virtual std::string ArcSec::BooleanAttribute::encode() [inline, virtual]

encode the value in a string format

Implements ArcSec::AttributeValue (p. 57).

6.38.1.2 virtual bool ArcSec::BooleanAttribute::equal (AttributeValue * value, bool check_id = true) [virtual]

Evluate whether "this" equale to the parameter value

Implements ArcSec::AttributeValue (p. 58).

6.38.1.3 std::string ArcSec::BooleanAttribute::getId() [inline, virtual]

Get the AttributeId of the <Attribute>

Implements **ArcSec::AttributeValue** (p. 58).

6.38.1.4 std::string ArcSec::BooleanAttribute::getType() [inline, virtual]

Get the DataType of the <Attribute>

Implements ArcSec::AttributeValue (p. 58).

The documentation for this class was generated from the following file:

• BooleanAttribute.h

6.39 Arc::Broker Class Reference

Inheritance diagram for Arc::Broker:



Public Member Functions

- const ExecutionTarget * GetBestTarget ()
- void PreFilterTargets (std::list< ExecutionTarget > &targets, const JobDescription &job)
- void RegisterJobsubmission ()

Protected Member Functions

• virtual void **SortTargets** ()=0

Protected Attributes

- std::list< ExecutionTarget * > PossibleTargets
- bool TargetSortingDone

6.39.1 Member Function Documentation

6.39.1.1 const ExecutionTarget* Arc::Broker::GetBestTarget()

Returns next target from the list of ExecutionTarget (p. 153) objects.

When first called this method will sort its list of **ExecutionTarget** (p. 153) objects, which have been filled by the PreFilterTargets method, and then the first target in the list will be returned.

If this is not the first call then the next target in the list is simply returned.

If there are no targets in the list or the end of the target list have been reached the NULL pointer is returned.

Returns

The pointer to the next **ExecutionTarget** (p. 153) in the list is returned.

6.39.1.2 void Arc::Broker::PreFilterTargets (std::list< ExecutionTarget > & targets, const JobDescription & job)

ExecutionTarget (p. 153) filtering, view-point: enought memory, diskspace, CPUs, etc.

The "bad" targets will be ignored and only the good targets will be added to to the list of **ExecutionTarget** (p. 153) objects which be used for brokering.

Parameters

targets A list of **ExecutionTarget** (p. 153) objects to be considered for addition to the **Broker** (p. 62). *jd* **JobDescription** (p. 187) object of the actual job.

6.39.1.3 virtual void Arc::Broker::SortTargets() [protected, pure virtual]

Custom Brokers should implement this method.

The task is to sort the PossibleTargets list by "custom" way, for example: FastestQueueBroker, **Execution-Target** (p. 153) which has the shortest queue length will be at the beginning of the PossibleTargets list

6.39.2 Field Documentation

6.39.2.1 std::list<ExecutionTarget*> Arc::Broker::PossibleTargets [protected]

This content the Prefilteres ExecutionTargets.

If an Execution Tartget has enought memory, CPU, diskspace, etc. for the actual job requirement than it will be added to the PossibleTargets list


The documentation for this class was generated from the following file:

· Broker.h

6.40 Arc::BrokerLoader Class Reference

#include <Broker.h>

Inheritance diagram for Arc::BrokerLoader:



Public Member Functions

- BrokerLoader ()
- ∼BrokerLoader ()
- Broker * load (const std::string &name, const UserConfig &usercfg)
- const std::list< **Broker** * > & **GetBrokers** () const

6.40.1 Detailed Description

Class responsible for loading **Broker** (p. 62) plugins The **Broker** (p. 62) objects returned by a **Broker-Loader** (p. 64) must not be used after the **Broker-Loader** (p. 64) goes out of scope.

6.40.2 Constructor & Destructor Documentation

6.40.2.1 Arc::BrokerLoader::BrokerLoader()

Constructor Creates a new **BrokerLoader** (p. 64).

6.40.2.2 Arc::BrokerLoader::~BrokerLoader()

Destructor Calling the destructor destroys all Brokers loaded by the **BrokerLoader** (p. 64) instance.

6.40.3 Member Function Documentation

6.40.3.1 const std::list<Broker*>& Arc::BrokerLoader::GetBrokers() const [inline]

Retrieve the list of loaded Brokers.

Returns

A reference to the list of Brokers.

6.40.3.2 Broker* Arc::BrokerLoader::load (const std::string & name, const UserConfig & usercfg)

Load a new Broker (p. 62)

Parameters

```
name The name of the Broker (p. 62) to load.

usercfg The UserConfig (p. 331) object for the new Broker (p. 62).
```

Returns


A pointer to the new **Broker** (p. 62) (NULL on error).

The documentation for this class was generated from the following file:

• Broker.h

6.41 Arc::BrokerPluginArgument Class Reference

Inheritance diagram for Arc::BrokerPluginArgument:



The documentation for this class was generated from the following file:

• Broker.h

6.42 Arc::ByteArray Class Reference

The documentation for this class was generated from the following file:

· ByteArray.h

6.43 Arc::CacheParameters Struct Reference

#include <FileCache.h>

6.43.1 Detailed Description

Contains data on the parameters of a cache.

The documentation for this struct was generated from the following file:

· FileCache.h

6.44 ArcCredential::cert_verify_context Struct Reference

The documentation for this struct was generated from the following file:

· CertUtil.h

6.45 Arc::ChainContext Class Reference

Interface to chain specific functionality.

#include <MCCLoader.h>

Public Member Functions

• operator PluginsFactory * ()

6.45.1 Detailed Description

Interface to chain specific functionality. Object of this class is associated with every **MCCLoader** (p. 206) object. It is accessible for **MCC** (p. 200) and **Service** (p. 282) components and provides an interface to manipulate chains stored in **Loader** (p. 189). This makes it possible to modify chains dynamically - like deploying new services on demand.

6.45.2 Member Function Documentation

6.45.2.1 Arc::ChainContext::operator PluginsFactory * () [inline]

Returns associated PluginsFactory (p. 250) object

References Arc::Loader::factory_.

The documentation for this class was generated from the following file:


• MCCLoader.h

6.46 Arc::CheckSum Class Reference

Defines interface for variuos checksum manipulations.

#include <CheckSum.h>

Inheritance diagram for Arc::CheckSum:



6.46.1 Detailed Description

Defines interface for variuos checksum manipulations. This class is used during data transfers through **DataBuffer** (p. 100) class

The documentation for this class was generated from the following file:


· CheckSum.h

6.47 Arc::CheckSumAny Class Reference

Wraper for CheckSum (p. 67) class.

#include <CheckSum.h>

Inheritance diagram for Arc::CheckSumAny:



6.47.1 Detailed Description

Wraper for **CheckSum** (p. 67) class. To be used for manipulation of any supported checksum type in a transparent way.

The documentation for this class was generated from the following file:


· CheckSum.h

6.48 Arc::CIStringValue Class Reference

This class implements case insensitive strings as security attributes.

#include <CIStringValue.h>

Inheritance diagram for Arc::CIStringValue:



Public Member Functions

- CIStringValue ()
- CIStringValue (const char *ss)
- **CIStringValue** (const std::string &ss)
- virtual operator bool ()

Protected Member Functions

• virtual bool equal (SecAttrValue &b)

6.48.1 Detailed Description

This class implements case insensitive strings as security attributes. This is an example of how to inherit **SecAttrValue** (p. 280). The class is meant to implement security attributes that are case insensitive strings.

6.48.2 Constructor & Destructor Documentation

$\textbf{6.48.2.1} \quad Arc:: CIString Value:: CIString Value (\ \)$

Default constructor

6.48.2.2 Arc::CIStringValue::CIStringValue (const char * ss)

This is a constructor that takes a string litteral.

6.48.2.3 Arc::CIStringValue::CIStringValue (const std::string & ss)

This is a constructor that takes a string object.

6.48.3 Member Function Documentation

6.48.3.1 virtual bool Arc::CIStringValue::equal (SecAttrValue & b) [protected, virtual]

This function returns true if two strings are the same apart from letter case

Reimplemented from Arc::SecAttrValue (p. 280).

6.48.3.2 virtual Arc::CIStringValue::operator bool() [virtual]

This function returns false if the string is empty or uninitialized


Reimplemented from Arc::SecAttrValue (p. 280).

The documentation for this class was generated from the following file:

· CIStringValue.h

6.49 Arc::ClassLoader Class Reference

Inheritance diagram for Arc::ClassLoader:




The documentation for this class was generated from the following file:

· ClassLoader.h

6.50 Arc::ClassLoaderPluginArgument Class Reference

Inheritance diagram for Arc::ClassLoaderPluginArgument:



The documentation for this class was generated from the following file:


· ClassLoader.h

6.51 Arc::ClientHTTP Class Reference

Class for setting up a MCC (p. 200) chain for HTTP communication.

#include <ClientInterface.h>

Inheritance diagram for Arc::ClientHTTP:



6.51.1 Detailed Description

Class for setting up a MCC (p. 200) chain for HTTP communication. The ClientHTTP (p. 69) class inherits from the ClientTCP (p. 73) class and adds an HTTP MCC (p. 200) to the chain.

The documentation for this class was generated from the following file:

• ClientInterface.h

6.52 Arc::ClientHTTPwithSAML2SSO Class Reference

Public Member Functions

- ClientHTTPwithSAML2SSO ()
- MCC_Status process (const std::string &method, PayloadRawInterface *request, HTTPClientInfo *info, PayloadRawInterface **response, const std::string &idp_name, const std::string &username, const std::string &password, const bool reuse_authn=false)

6.52.1 Constructor & Destructor Documentation

6.52.1.1 Arc::ClientHTTPwithSAML2SSO::ClientHTTPwithSAML2SSO() [inline]

Constructor creates MCC (p. 200) chain and connects to server.

6.52.2 Member Function Documentation

6.52.2.1 MCC_Status Arc::ClientHTTPwithSAML2SSO::process (const std::string & method, PayloadRawInterface * request, HTTPClientInfo * info, PayloadRawInterface ** response, const std::string & idp_name, const std::string & username, const std::string & password, const bool reuse_authn = false)

Send HTTP request and receive response.

The documentation for this class was generated from the following file:


• ClientSAML2SSO.h

6.53 Arc::ClientInterface Class Reference

Utility base class for MCC (p. 200).

#include <ClientInterface.h>

Inheritance diagram for Arc::ClientInterface:



6.53.1 Detailed Description

Utility base class for MCC (p. 200). The ClientInterface (p. 71) class is a utility base class used for configuring a client side Message (p. 208) Chain Component (MCC (p. 200)) chain and loading it into memory. It has several specializations of increasing complexity of the MCC (p. 200) chains.


The documentation for this class was generated from the following file:

· ClientInterface.h

6.54 Arc::ClientSOAP Class Reference

#include <ClientInterface.h>

Inheritance diagram for Arc::ClientSOAP:



Public Member Functions

- ClientSOAP ()
- MCC_Status process (PayloadSOAP *request, PayloadSOAP **response)

- MCC_Status process (const std::string &action, PayloadSOAP *request, PayloadSOAP *response)
- MCC * GetEntry ()
- void **AddSecHandler** (**XMLNode** handlercfg, const std::string &libanme="", const std::string &lib-path="")
- virtual bool Load ()

6.54.1 Detailed Description

Class with easy interface for sending/receiving SOAP messages over HTTP(S/G). It takes care of configuring MCC (p. 200) chain and making an entry point.

6.54.2 Constructor & Destructor Documentation

6.54.2.1 Arc::ClientSOAP::ClientSOAP() [inline]

Constructor creates MCC (p. 200) chain and connects to server.

6.54.3 Member Function Documentation

6.54.3.1 void Arc::ClientSOAP::AddSecHandler (XMLNode handlercfg, const std::string & libanme = "", const std::string & libpath = "")

Adds security handler to configuration of SOAP MCC (p. 200)

Reimplemented from Arc::ClientHTTP (p. 69).

6.54.3.2 MCC* Arc::ClientSOAP::GetEntry() [inline]

Returns entry point to SOAP MCC (p. 200) in configured chain. To initialize entry point Load() (p. 72) method must be called.

Reimplemented from Arc::ClientHTTP (p. 69).

6.54.3.3 virtual bool Arc::ClientSOAP::Load() [virtual]

Instantiates pluggable elements according to generated configuration

Reimplemented from Arc::ClientHTTP (p. 69).

6.54.3.4 MCC_Status Arc::ClientSOAP::process (PayloadSOAP * request, PayloadSOAP ** response)

Send SOAP request and receive response.

6.54.3.5 MCC_Status Arc::ClientSOAP::process (const std::string & action, PayloadSOAP * request, PayloadSOAP ** response)

Send SOAP request with specified SOAP action and receive response.

The documentation for this class was generated from the following file:

· ClientInterface.h

6.55 Arc::ClientSOAPwithSAML2SSO Class Reference

Public Member Functions

- ClientSOAPwithSAML2SSO ()
- MCC_Status process (PayloadSOAP *request, PayloadSOAP **response, const std::string &idp_name, const std::string &username, const std::string &password, const bool reuse_-authn=false)
- MCC_Status process (const std::string &action, PayloadSOAP *request, PayloadSOAP *response, const std::string &idp_name, const std::string &username, const std::string &password, const bool reuse_authn=false)

6.55.1 Constructor & Destructor Documentation

6.55.1.1 Arc::ClientSOAPwithSAML2SSO::ClientSOAPwithSAML2SSO() [inline]

Constructor creates MCC (p. 200) chain and connects to server.

6.55.2 Member Function Documentation

6.55.2.1 MCC_Status Arc::ClientSOAPwithSAML2SSO::process (PayloadSOAP * request, PayloadSOAP ** response, const std::string & idp_name, const std::string & username, const std::string & password, const bool reuse_authn = false)

Send SOAP request and receive response.

6.55.2.2 MCC_Status Arc::ClientSOAPwithSAML2SSO::process (const std::string & action, PayloadSOAP * request, PayloadSOAP ** response, const std::string & idp_name, const std::string & username, const std::string & password, const bool reuse_authn = false)

Send SOAP request with specified SOAP action and receive response.

The documentation for this class was generated from the following file:


• ClientSAML2SSO.h

6.56 Arc::ClientTCP Class Reference

Class for setting up a MCC (p. 200) chain for TCP communication.

#include <ClientInterface.h>

Inheritance diagram for Arc::ClientTCP:



6.56.1 Detailed Description

Class for setting up a MCC (p. 200) chain for TCP communication. The ClientTCP (p. 73) class is a specialization of the ClientInterface (p. 71) which sets up a client MCC (p. 200) chain for TCP communication, and optionally with a security layer on top which can be either TLS, GSI or SSL3.

The documentation for this class was generated from the following file:

· ClientInterface.h

6.57 Arc::ClientX509Delegation Class Reference

Public Member Functions

- ClientX509Delegation ()
- bool **createDelegation** (DelegationType deleg, std::string &delegation id)
- bool **acquireDelegation** (DelegationType deleg, std::string &delegation_cred, std::string &delegation_id, const std::string cred_identity="", const std::string cred_delegator_ip="", const std::string username="", const std::string password="")

6.57.1 Constructor & Destructor Documentation

6.57.1.1 Arc::ClientX509Delegation::ClientX509Delegation() [inline]

Constructor creates MCC (p. 200) chain and connects to server.

6.57.2 Member Function Documentation

6.57.2.1 bool Arc::ClientX509Delegation::acquireDelegation (DelegationType deleg, std::string & delegation_cred, std::string & delegation_id, const std::string cred_identity = "", const std::string cred_delegator_ip = "", const std::string username = "", const std::string password = "")

Acquire delegation credential from delegation service. This method should be called by intermediate service ('n+1' service as explained on above) in order to use this delegation credential on behalf of the EEC's holder.

Parameters

deleg Delegation type

delegation_id delegation ID which is used to look up the credential by delegation service *cred_identity* the identity (in case of x509 credential, it is the DN of EEC credential).

cred_delegator_ip the IP address of the credential delegator. Regard of delegation, an intermediate service should accomplish three tasks: 1. Acquire 'n' level delegation credential (which is delegated by 'n-1' level delegator) from delegation service; 1. Create 'n+1' level delegation credential to delegation service; 2. Use 'n' level delegation credential to act on behalf of the EEC's holder. In case of absense of delegation_id, the 'n-1' level delegator's IP address and credential's identity are supposed to be used for look up the delegation credential from delegation service.

6.57.2.2 bool Arc::ClientX509Delegation::createDelegation (DelegationType deleg, std::string & delegation_id)

Create the delegation credential according to the different remote delegation service. This method should be called by holder of EEC(end entity credential) which would delegate its EEC credential, or by holder of delegated credential(normally, the holder is intermediate service) which would further delegate the credential (on behalf of the original EEC's holder) (for instance, the 'n' intermediate service creates a delegation credential, then the 'n+1' intermediate service aquires this delegation credential from the delegation service and also acts on behalf of the EEC's holder by using this delegation credential).

Parameters

deleg Delegation type

delegation_id For gridsite delegation service, the delegation_id is supposed to be created by client side, and sent to service side; for ARC delegation service, the delegation_id is supposed to be created by service side, and returned back. So for gridsite delegation service, this parameter is treated as input, while for ARC delegation service, it is treated as output.

The documentation for this class was generated from the following file:


• ClientX509Delegation.h

6.58 ArcSec::CombiningAlg Class Reference

Interface for combining algrithm.

#include <CombiningAlg.h>

Inheritance diagram for ArcSec::CombiningAlg:



Public Member Functions

- virtual Result combine (EvaluationCtx *ctx, std::list< Policy * > policies)=0
- virtual const std::string & getalgId (void) const =0

6.58.1 Detailed Description

Interface for combining algrithm. This class is used to implement a specific combining algorithm for combining policies.

6.58.2 Member Function Documentation

6.58.2.1 virtual Result ArcSec::CombiningAlg::combine (EvaluationCtx * ctx, std::list< Policy *> policies) [pure virtual]

Evaluate request against policy, and if there are more than one policies, combine the evaluation results according to the combing algorithm implemented inside in the method combine(ctx, policies) itself.

Parameters

ctx The information about request is included

policies The "match" and "eval" method inside each policy will be called, and then those results from each policy will be combined according to the combining algorithm inside CombingAlg class.

Implemented in **ArcSec::DenyOverridesCombiningAlg** (p. 143), and **ArcSec::PermitOverridesCombiningAlg** (p. 245).

6.58.2.2 virtual const std::string& ArcSec::CombiningAlg::getalgId (void) const [pure virtual]

Get the identifier of the combining algorithm class

Returns

The identity of the algorithm

Implemented in **ArcSec::DenyOverridesCombiningAlg** (p. 143), and **ArcSec::PermitOverridesCombiningAlg** (p. 245).

The documentation for this class was generated from the following file:


· CombiningAlg.h

6.59 Arc::Config Class Reference

Configuration element - represents (sub)tree of ARC configuration.

#include <ArcConfig.h>

Inheritance diagram for Arc::Config:



Public Member Functions

- Config ()
- Config (const char *filename)
- Config (const std::string &xml str)
- Config (XMLNode xml)
- Config (long cfg_ptr_addr)
- Config (const Config &cfg)
- void **print** (void)
- void parse (const char *filename)
- const std::string & getFileName (void) const
- void **setFileName** (const std::string &filename)
- void save (const char *filename)

6.59.1 Detailed Description

Configuration element - represents (sub)tree of ARC configuration. This class is intended to be used to pass configuration details to various parts of HED and external modules. Currently it's just a wrapper over XML tree. But than may change in a future, although interface should be preserved. Currently it is capable of loading XML configuration document from file. In future it will be capable of loading more user-readable format and process it into tree-like structure convenient for machine processing (XML-like). So far there are no schema and/or namespaces assigned.

6.59.2 Constructor & Destructor Documentation

6.59.2.1 Arc::Config::Config() [inline]

Creates empty XML tree

6.59.2.2 Arc::Config::Config (const char * filename)

Loads configuration document from file 'filename'

6.59.2.3 Arc::Config::Config (const std::string & xml_str) [inline]

Parse configuration document from memory

6.59.2.4 Arc::Config::Config (XMLNode xml) [inline]

Acquire existing XML (sub)tree. Content is not copied. Make sure XML tree is not destroyed while in use by this object.

6.59.2.5 Arc::Config::Config (long cfg_ptr_addr)

Copy constructor used by language bindings

6.59.2.6 Arc::Config::Config (const Config & cfg)

Copy constructor used by language bindings

6.59.3 Member Function Documentation

6.59.3.1 const std::string& Arc::Config::getFileName(void) const [inline]

Gives back file name of config file or empty string if it was generated from the XMLNode (p. 389) subtree

6.59.3.2 void Arc::Config::parse (const char * filename)

Parse configuration document from file 'filename'

6.59.3.3 void Arc::Config::print (void)

Print structure of document. For debuging purposes. Printed content is not an XML document.

6.59.3.4 void Arc::Config::save (const char * filename)

Save to file

6.59.3.5 void Arc::Config::setFileName (const std::string & filename) [inline]

Set the file name of config file

The documentation for this class was generated from the following file:

• ArcConfig.h

6.60 Arc::ConfusaCertHandler Class Reference

#include <ConfusaCertHandler.h>

Public Member Functions

- ConfusaCertHandler (int keysize, const std::string dn)
- std::string getCertRequestB64 ()
- bool **createCertRequest** (std::string password="", std::string storedir="./")

6.60.1 Detailed Description

Wrapper around Credential (p. 90) handling the Confusa specifics.

6.60.2 Constructor & Destructor Documentation

6.60.2.1 Arc::ConfusaCertHandler::ConfusaCertHandler (int keysize, const std::string dn)

Create a new **ConfusaCertHandler** (p. 78) for DN dn and given keysize Basically Confusa cert handler wraps around **Credential** (p. 90)

6.60.3 Member Function Documentation

6.60.3.1 bool Arc::ConfusaCertHandler::createCertRequest (std::string password = "", std::string storedir = "./")

Create a new end entity certificate, with a private key encrypted with password password. Private key and certificate will be stored in directory storedir.

6.60.3.2 std::string Arc::ConfusaCertHandler::getCertRequestB64()

Get the certificate request managed by this confusa cert handler in base 64 encoding

The documentation for this class was generated from the following file:

· ConfusaCertHandler.h

6.61 Arc::ConfusaParserUtils Class Reference

#include <ConfusaParserUtils.h>

Static Public Member Functions

- static std::string **urlencode** (const std::string url)
- static std::string **urlencode_params** (const std::string url)
- static xmlDocPtr **get_doc** (const std::string xml_file)
- static void **destroy_doc** (xmlDocPtr doc)
- static std::string extract_body_information (const std::string html_string)
- static std::string **handle_redirect_step** (**Arc::MCCConfig** cfg, const std::string remote_url, std::string *cookies=NULL, std::multimap< std::string, std::string > *httpAttributes=NULL)
- static std::string **evaluate_path** (xmlDocPtr doc, const std::string xpathExpr, std::list< std::string > *contentList=NULL)

6.61.1 Detailed Description

Methods often needed in evaluation web pages from the Confusa WebSSO workflow

6.61.2 Member Function Documentation

6.61.2.1 static void Arc::ConfusaParserUtils::destroy doc (xmlDocPtr doc) [static]

Destroy a libxml2 doc representation

6.61.2.2 static std::string Arc::ConfusaParserUtils::evaluate_path (xmlDocPtr doc, const std::string xpathExpr, std::list< std::string > * contentList = NULL) [static]

Evaluate the given xPathExpr on the document ptr. Return a string with the FIRST result if contentList is NULL. Return a string with the first result and all results, including the first one, in contentList if contentList is not null.

6.61.2.3 static std::string Arc::ConfusaParserUtils::extract_body_information (const std::string html_string) [static]

Get the part only within <body> and </body> in a HTML string For parsing, usually only this part is interesting.

6.61.2.4 static xmlDocPtr Arc::ConfusaParserUtils::get_doc(const std::string xml_file) [static]

Construct a lixml2 doc representation from the xml file

6.61.2.5 static std::string Arc::ConfusaParserUtils::handle_redirect_step (Arc::MCCConfig cfg, const std::string remote_url, std::string * cookies = NULL, std::multimap< std::string, std::string > * httpAttributes = NULL) [static]

Handle a single redirect step from the SAML2 WebSSO profile. Store the received cookie in *cookie and pass the given httpAttributes to the site during redirect.

6.61.2.6 static std::string Arc::ConfusaParserUtils::urlencode (const std::string url) [static]

urlencode the passed string

6.61.2.7 static std::string Arc::ConfusaParserUtils::urlencode_params (const std::string url) [static]

Urlencode the passed string with respect to the parameters. The difference to urlencode is that the parameters will keep their seperators, i.e. the ? and & separating parameters will be preserved.

The documentation for this class was generated from the following file:

• ConfusaParserUtils.h

6.62 Arc::CountedPointer< T > Class Template Reference

Wrapper for pointer with automatic destruction and mutiple references.

#include <Utils.h>

Data Structures

• class Base

Public Member Functions

- T & operator* (void) const
- T * operator-> (void) const
- operator bool (void) const
- bool operator! (void) const
- operator T * (void) const

6.62.1 Detailed Description

template<typename T> class Arc::CountedPointer< T>

Wrapper for pointer with automatic destruction and mutiple references. If ordinary pointer is wrapped in instance of this class it will be automatically destroyed when all instances refering to it are destroyed. This is useful for maintaing pointers refered from multiple structures with automatic destruction of original object when last reference is destroyed. It is similar to Java approach with a difference that descruction time is strictly defined. Only pointers returned by new() are supported. This class is not thread-safe

The documentation for this class was generated from the following file:


• Utils.h

6.63 Arc::Counter Class Reference

A class defining a common interface for counters.

#include <Counter.h>

Inheritance diagram for Arc::Counter:



Public Member Functions

- virtual \sim Counter ()
- virtual int **getLimit** ()=0
- virtual int **setLimit** (int newLimit)=0
- virtual int **changeLimit** (int amount)=0
- virtual int **getExcess** ()=0
- virtual int **setExcess** (int newExcess)=0
- virtual int **changeExcess** (int amount)=0
- virtual int **getValue** ()=0
- virtual **CounterTicket reserve** (int amount=1, Glib::TimeVal duration=**ETERNAL**, bool prioritized=false, Glib::TimeVal timeOut=**ETERNAL**)=0

Protected Types

• typedef unsigned long long int IDType

Protected Member Functions

- Counter ()
- virtual void **cancel** (**IDType** reservationID)=0
- virtual void **extend** (**IDType** &reservationID, Glib::TimeVal &expiryTime, Glib::TimeVal duration=**ETERNAL**)=0
- Glib::TimeVal **getCurrentTime** ()
- Glib::TimeVal **getExpiryTime** (Glib::TimeVal duration)
- CounterTicket getCounterTicket (Counter::IDType reservationID, Glib::TimeVal expiryTime, Counter *counter)
- ExpirationReminder getExpirationReminder (Glib::TimeVal expTime, Counter::IDType resID)

Friends

- class CounterTicket
- class ExpirationReminder

6.63.1 Detailed Description

A class defining a common interface for counters. This class defines a common interface for counters as well as some common functionality.

The purpose of a counter is to provide housekeeping some resource such as e.g. disk space, memory or network bandwidth. The counter itself will not be aware of what kind of resource it limits the use of. Neither will it be aware of what unit is being used to measure that resource. Counters are thus very similar to semaphores. Furthermore, counters are designed to handle concurrent operations from multiple threads/processes in a consistent manner.

Every counter has a limit, an excess limit and a value. The limit is a number that specify how many units are available for reservation. The value is the number of units that are currently available for reservation, i.e. has not allready been reserved. The excess limit specify how many extra units can be reserved for high priority needs even if there are no normal units available for reservation. The excess limit is similar to the credit limit of e.g. a VISA card.

The users of the resource must thus first call the counter in order to make a reservation of an appropriate amount of the resource, then allocate and use the resource and finally call the counter again to cancel the reservation.

Typical usage is:

```
// Declare a counter. Replace XYZ by some appropriate kind of
// counter and provide required parameters. Unit is MB.
XYZCounter memory(...);
...
// Make a reservation of memory for 2000000 doubles.
CounterTicket tick = memory.reserve(2*sizeof(double));
// Use the memory.
double* A=new double[2000000];
doSomething(A);
delete[] A;
// Cancel the reservation.
tick.cancel();
```

There are also alternative ways to make reservations, including self-expiring reservations, prioritized reservations and reservations that fail if they cannot be made fast enough.

For self expiring reservations, a duration is provided in the reserve call:

```
tick = memory.reserve(2*sizeof(double), Glib::TimeVal(1,0));
```

A self-expiring reservation can be cancelled explicitly before it expires, but if it is not cancelled it will expire automatically when the duration has passed. The default value for the duration is ETERNAL, which means that the reservation will not be cancelled automatically.

Prioritized reservations may use the excess limit and succeed immediately even if there are no normal units available for reservation. The value of the counter will in this case become negative. A prioritized reservation looks like this:

```
tick = memory.reserve(2*sizeof(double), Glib::TimeVal(1,0), true);
```

Finally, a time out option can be provided for a reservation. If some task should be performed within two seconds or not at all, the reservation can look like this:

6.63.2 Member Typedef Documentation

6.63.2.1 typedef unsigned long long int Arc::Counter::IDType [protected]

A typedef of identification numbers for reservation.

This is a type that is used as identification numbers (keys) for referencing of reservations. It is used internally in counters for book keeping of reservations as well as in the **CounterTicket** (p. 88) class in order to be able to cancel and extend reservations.

6.63.3 Constructor & Destructor Documentation

6.63.3.1 Arc::Counter::Counter() [protected]

Default constructor.

This is the default constructor. Since **Counter** (p. 81) is an abstract class, it should only be used by subclasses. Therefore it is protected. Furthermore, since the **Counter** (p. 81) class has no attributes, nothing needs to be initialized and thus this constructor is empty.

6.63.3.2 virtual Arc::Counter::~Counter() [virtual]

The destructor.

This is the destructor of the **Counter** (p. 81) class. Since the **Counter** (p. 81) class has no attributes, nothing needs to be cleaned up and thus the destructor is empty.

6.63.4 Member Function Documentation

6.63.4.1 virtual void Arc::Counter::cancel (IDType reservationID) [protected, pure virtual]

Cancellation of a reservation.

This method cancels a reservation. It is called by the **CounterTicket** (p. 88) that corresponds to the reservation.

Parameters

reservationID The identity number (key) of the reservation to cancel.

6.63.4.2 virtual int Arc::Counter::changeExcess (int amount) [pure virtual]

Changes the excess limit of the counter.

Changes the excess limit of the counter by adding a certain amount to the current excess limit.

Parameters

amount The amount by which to change the excess limit.

Returns

The new excess limit.

Implemented in Arc::IntraProcessCounter (p. 179).

6.63.4.3 virtual int Arc::Counter::changeLimit(int amount) [pure virtual]

Changes the limit of the counter.

Changes the limit of the counter by adding a certain amount to the current limit.

Parameters

amount The amount by which to change the limit.

Returns

The new limit.

Implemented in Arc::IntraProcessCounter (p. 179).

6.63.4.4 virtual void Arc::Counter::extend (IDType & reservationID, Glib::TimeVal & expiryTime, Glib::TimeVal duration = ETERNAL) [protected, pure virtual]

Extension of a reservation.

This method extends a reservation. It is called by the **CounterTicket** (p. 88) that corresponds to the reservation.

Parameters

reservationID Used for input as well as output. Contains the identification number of the original reservation on entry and the new identification number of the extended reservation on exit.

expiryTime Used for input as well as output. Contains the expiry time of the original reservation on entry and the new expiry time of the extended reservation on exit.

duration The time by which to extend the reservation. The new expiration time is computed based on the current time, NOT the previous expiration time.

6.63.4.5 CounterTicket Arc::Counter::getCounterTicket (Counter::IDType reservationID, Glib::TimeVal expiryTime, Counter * counter) [protected]

A "relay method" for a constructor of the **CounterTicket** (p. 88) class.

This method acts as a relay for one of the constructors of the **CounterTicket** (p. 88) class. That constructor is private, but needs to be accessible from the subclasses of **Counter** (p. 81) (bot not from anywhere else). In order not to have to declare every possible subclass of **Counter** (p. 81) as a friend of **CounterTicket** (p. 88), only the base class **Counter** (p. 81) is a friend and its subclasses access the constructor through this method. (If C++ had supported "package access", as Java does, this trick would not have been necessary.)

Parameters

```
reservationID The identity number of the reservation corresponding to the CounterTicket (p. 88). expiryTime the expiry time of the reservation corresponding to the CounterTicket (p. 88). counter The Counter (p. 81) from which the reservation has been made.
```

Returns

The counter ticket that has been created.

6.63.4.6 Glib::TimeVal Arc::Counter::getCurrentTime() [protected]

Get the current time.

Returns the current time. An "adapter method" for the assign_current_time() method in the Glib::TimeVal class. return The current time.

6.63.4.7 virtual int Arc::Counter::getExcess() [pure virtual]

Returns the excess limit of the counter.

Returns the excess limit of the counter, i.e. by how much the usual limit may be exceeded by prioritized reservations.

Returns

The excess limit.

Implemented in Arc::IntraProcessCounter (p. 180).

6.63.4.8 ExpirationReminder Arc::Counter::getExpirationReminder (Glib::TimeVal expTime, Counter::IDType resID) [protected]

A "relay method" for the constructor of **ExpirationReminder** (p. 156).

This method acts as a relay for one of the constructors of the **ExpirationReminder** (p. 156) class. That constructor is private, but needs to be accessible from the subclasses of **Counter** (p. 81) (bot not from anywhere else). In order not to have to declare every possible subclass of **Counter** (p. 81) as a friend of **ExpirationReminder** (p. 156), only the base class **Counter** (p. 81) is a friend and its subclasses access the constructor through this method. (If C++ had supported "package access", as Java does, this trick would not have been necessary.)

Parameters

expTime the expiry time of the reservation corresponding to the **ExpirationReminder** (p. 156). *resID* The identity number of the reservation corresponding to the **ExpirationReminder** (p. 156).

Returns

The **ExpirationReminder** (p. 156) that has been created.

6.63.4.9 Glib::TimeVal Arc::Counter::getExpiryTime (Glib::TimeVal duration) [protected]

Computes an expiry time.

This method computes an expiry time by adding a duration to the current time.

Parameters

duration The duration.

Returns

The expiry time.

6.63.4.10 virtual int Arc::Counter::getLimit() [pure virtual]

Returns the current limit of the counter.

This method returns the current limit of the counter, i.e. how many units can be reserved simultaneously by different threads without claiming high priority.

Returns

The current limit of the counter.

Implemented in Arc::IntraProcessCounter (p. 180).

6.63.4.11 virtual int Arc::Counter::getValue() [pure virtual]

Returns the current value of the counter.

Returns the current value of the counter, i.e. the number of unreserved units. Initially, the value is equal to the limit of the counter. When a reservation is made, the the value is decreased. Normally, the value should

never be negative, but this may happen if there are prioritized reservations. It can also happen if the limit is decreased after some reservations have been made, since reservations are never revoked.

Returns

The current value of the counter.

Implemented in Arc::IntraProcessCounter (p. 181).

6.63.4.12 virtual CounterTicket Arc::Counter::reserve (int amount = 1, Glib::TimeVal duration = ETERNAL, bool prioritized = false, Glib::TimeVal timeOut = ETERNAL) [pure virtual]

Makes a reservation from the counter.

This method makes a reservation from the counter. If the current value of the counter is too low to allow for the reservation, the method blocks until the reservation is possible or times out.

Parameters

amount The amount to reserve, default value is 1.

duration The duration of a self expiring reservation, default is that it lasts forever.

prioritized Whether this reservation is prioritized and thus allowed to use the excess limit.

timeOut The maximum time to block if the value of the counter is too low, default is to allow "eternal" blocking.

Returns

A **CounterTicket** (p. 88) that can be queried about the status of the reservation as well as for cancellations and extensions.

Implemented in Arc::IntraProcessCounter (p. 181).

6.63.4.13 virtual int Arc::Counter::setExcess (int newExcess) [pure virtual]

Sets the excess limit of the counter.

This method sets a new excess limit for the counter.

Parameters

newExcess The new excess limit, an absolute number.

Returns

The new excess limit.

Implemented in Arc::IntraProcessCounter (p. 181).

6.63.4.14 virtual int Arc::Counter::setLimit(int newLimit) [pure virtual]

Sets the limit of the counter.

This method sets a new limit for the counter.

Parameters

newLimit The new limit, an absolute number.

Returns

The new limit.

Implemented in Arc::IntraProcessCounter (p. 182).

The documentation for this class was generated from the following file:

· Counter.h

6.64 Arc::CounterTicket Class Reference

A class for "tickets" that correspond to counter reservations.

```
#include <Counter.h>
```

Public Member Functions

- CounterTicket ()
- bool isValid ()
- void extend (Glib::TimeVal duration)
- void cancel ()

Friends

• class Counter

6.64.1 Detailed Description

A class for "tickets" that correspond to counter reservations. This is a class for reservation tickets. When a reservation is made from a **Counter** (p. 81), a ReservationTicket is returned. This ticket can then be queried about the validity of a reservation. It can also be used for cancelation and extension of reservations.

Typical usage is:

```
// Declare a counter. Replace XYZ by some appropriate kind of
// counter and provide required parameters. Unit is MB.
XYZCounter memory(...);
...
// Make a reservation of memory for 2000000 doubles.
CounterTicket tick = memory.reserve(2*sizeof(double));
// Use the memory.
double* A=new double[2000000];
doSomething(A);
delete[] A;
// Cancel the reservation.
tick.cancel();
```

6.64.2 Constructor & Destructor Documentation

6.64.2.1 Arc::CounterTicket::CounterTicket()

The default constructor.

This is the default constructor. It creates a **CounterTicket** (p. 88) that is not valid. The ticket object that is created can later be assigned a ticket that is returned by the reserve() method of a **Counter** (p. 81).

6.64.3 Member Function Documentation

6.64.3.1 void Arc::CounterTicket::cancel ()

Cancels a resrvation.

This method is called to cancel a reservation. It may be called also for self-expiring reservations, which will then be cancelled before they were originally planned to expire.

6.64.3.2 void Arc::CounterTicket::extend (Glib::TimeVal duration)

Extends a reservation.

Extends a self-expiring reservation. In order to succeed the extension should be made before the previous reservation expires.

Parameters

duration The time by which to extend the reservation. The new expiration time is computed based on the current time, NOT the previous expiration time.

6.64.3.3 bool Arc::CounterTicket::isValid ()

Returns the validity of a **CounterTicket** (p. 88).

This method checks whether a **CounterTicket** (p. 88) is valid. The ticket was probably returned earlier by the reserve() method of a **Counter** (p. 81) but the corresponding reservation may have expired.

Returns

The validity of the ticket.

The documentation for this class was generated from the following file:


• Counter.h

6.65 Arc::CRC32Sum Class Reference

Implementation of CRC32 checksum.

#include <CheckSum.h>

Inheritance diagram for Arc::CRC32Sum:



6.65.1 Detailed Description

Implementation of CRC32 checksum.

The documentation for this class was generated from the following file:

· CheckSum.h

6.66 Arc::Credential Class Reference

Public Member Functions

- Credential ()
- **Credential** (int keybits)
- **Credential** (const std::string &CAfile, const std::string &CAkey, const std::string &CAserial, bool CAcreateserial, const std::string &extfile, const std::string &extsect, const std::string &passphrase4key="")
- Credential (Time start, Period lifetime=Period("PT12H"), int keybits=1024, std::string proxyversion="rfc", std::string policylang="inheritAll", std::string policy="", int pathlength=-1)
- Credential (const std::string &cert, const std::string &key, const std::string &cadir, const std::string &cafile, const std::string &passphrase4key="", const bool is_file=true)
- void AddCertExtObj (std::string &sn, std::string &oid)
- void LogError (void) const
- bool GetVerification (void) const
- EVP PKEY * GetPrivKev (void) const
- EVP_PKEY * GetPubKey (void) const
- X509 * GetCert (void) const
- X509_REQ * GetCertReq (void) const
- STACK_OF (X509)*GetCertChain(void) const
- int GetCertNumofChain (void) const
- Credformat **getFormat** (BIO *in, const bool is_file=true) const
- std::string GetDN (void) const
- std::string GetIdentityName (void) const
- ArcCredential::certType GetType (void) const
- std::string GetProxyPolicy (void) const
- void **SetProxyPolicy** (const std::string &proxyversion, const std::string &policylang, const std::string &policy, int pathlength)
- bool **OutputPrivatekey** (std::string &content, bool encryption=false, const std::string &passphrase="")
- bool **OutputPublickey** (std::string &content)
- bool **OutputCertificate** (std::string &content, bool is_der=false)
- bool **OutputCertificateChain** (std::string &content, bool is_der=false)
- Period GetLifeTime (void) const

- Time GetStartTime () const
- Time GetEndTime () const
- void **SetLifeTime** (const **Period** &period)
- void **SetStartTime** (const **Time** &start time)
- bool **AddExtension** (std::string name, std::string data, bool crit=false)
- bool **AddExtension** (std::string name, char **binary, bool crit=false)
- bool **GenerateEECRequest** (BIO *reqbio, BIO *keybio, std::string dn="")
- bool GenerateEECRequest (std::string &reqcontent, std::string &keycontent, std::string dn="")
- bool **GenerateEECRequest** (const char *request_filename, const char *key_filename, std::string dn="")
- bool **GenerateRequest** (BIO *bio, bool if_der=false)
- bool **GenerateRequest** (std::string &content, bool if_der=false)
- bool **GenerateRequest** (const char *filename, bool if_der=false)
- bool **InquireRequest** (BIO *reqbio, bool if_eec=false, bool if_der=false)
- bool **InquireRequest** (std::string &content, bool if eec=false, bool if der=false)
- bool **InquireRequest** (const char *filename, bool if_eec=false, bool if_der=false)
- bool **SignRequest** (**Credential** *proxy, BIO *outputbio, bool if_der=false)
- bool **SignRequest** (**Credential** *proxy, std::string &content, bool if_der=false)
- bool **SignRequest** (**Credential** *proxy, const char *filename, bool foamat=false)
- bool SignEECRequest (Credential *eec, const std::string &DN, BIO *outputbio)
- bool **SignEECRequest** (**Credential** *eec, const std::string &DN, std::string &content)
- bool **SignEECRequest** (**Credential** *eec, const std::string &DN, const char *filename)

Static Public Member Functions

• static void **InitProxyCertInfo** (void)

6.66.1 Constructor & Destructor Documentation

6.66.1.1 Arc::Credential::Credential ()

Default constructor, only acts as a container for inquiring certificate request, is meaningless for any other use.

6.66.1.2 Arc::Credential::Credential (int keybits)

Constructor with user-defined keylength. Needed for creation of EE certs, since some applications will only support keys with a certain minimum length > 1024

6.66.1.3 Arc::Credential::Credential (const std::string & CAfile, const std::string & CAkey, const std::string & CAserial, bool CAcreateserial, const std::string & extfile, const std::string & extsect, const std::string & passphrase4key = "")

Constructor, specific constructor for CA certificate is meaningless for any other use.

6.66.1.4 Arc::Credential::Credential (Time start, Period lifetime = Period ("PT12H"), int keybits = 1024, std::string proxyversion = "rfc", std::string policylang = "inheritAll", std::string policy = "", int pathlength = -1)

Constructor, specific constructor for proxy certificate, only acts as a container for constraining certificate signing and/or generating certificate request(only keybits is useful for creating certificate request), is meaningless for any other use. The proxyversion and policylang is for specifying the proxy certificate type and the policy language inside proxy. The definition of proxyversion and policy language is based on http://dev.globus.org/wiki/Security/ProxyCertTypes#RFC_3820_Proxy_Certificates The code is supposed to support proxy version: GSI2(legacy proxy), GSI3(Proxy draft) and RFC(RFC3820 proxy), and correspoding policy language. GSI2(GSI2, GSI2_LIMITED) GSI3 and RFC (IMPERSONATION_PROXY--1.3.6.1.5.5.7.21.1, INDEPENDENT_PROXY--1.3.6.1.5.5.7.21.2, LIMITED_PROXY--1.3.6.1.4.1.3536.1.1.1.9, RESTRICTED_PROXY--policy language undefined) In openssl>=098, there are three types of policy languages: id-ppl-inheritAll--1.3.6.1.5.5.7.21.1, id-ppl-independent--1.3.6.1.5.5.7.21.2, and id-ppl-anyLanguage-1.3.6.1.5.5.7.21.0

Parameters

start, start time of proxy certificate

lifetime, lifetime of proxy certificate

keybits,modulus size for RSA key generation, it should be greater than 1024 if 'this' class is used for generating X509 request; it should be '0' if 'this' class is used for constraing certificate signing.

6.66.1.5 Arc::Credential::Credential (const std::string & cert, const std::string & key, const std::string & cadir, const std::string & cafile, const std::string & passphrase4key = "", const bool is_file = true)

Constructor, specific constructor for usual certificate, constructing from credential files. only acts as a container for parsing the certificate and key files, is meaningless for any other use. this constructor will parse the credential information, and put them into "this" object

Parameters

is_file,specify if the cert/key are from file, otherwise they are supposed to be from string. default is from file

6.66.2 Member Function Documentation

6.66.2.1 void Arc::Credential::AddCertExtObj (std::string & sn, std::string & oid)

General method for adding a new nid into openssl's global const

6.66.2.2 bool Arc::Credential::AddExtension (std::string name, std::string data, bool crit = false)

Add an extension to the extension part of the certificate

Parameters

name,the name of the extension, there OID related with the name should be registered into openssl firstly

data,the data which will be inserted into certificate extension

6.66.2.3 bool Arc::Credential::AddExtension (std::string name, char ** binary, bool crit = false)

Add an extension to the extension part of the certificate

Parameters

binary,the data which will be inserted into certificate extension part as a specific extension there should be specific methods defined inside specific X509V3_EXT_METHOD structure to parse the specific extension format. For example, VOMS attribute certificate is a specific extension to proxy certificate. There is specific X509V3_EXT_METHOD defined in VOMSAttribute.h (p.??) and VOMSAttribute.c for parsing attribute certificate. In opensal, the specific X509V3_EXT_METHOD can be got according to the extension name/id, see X509V3_EXT_get nid(ext nid)

6.66.2.4 bool Arc::Credential::GenerateEECRequest (BIO * reqbio, BIO * keybio, std::string dn = "")

Generate an EEC request, based on the keybits and signing algorithm information inside this object output the certificate request to output BIO

The user will be asked for a private key password

6.66.2.5 bool Arc::Credential::GenerateEECRequest (std::string & reqcontent, std::string & keycontent, std::string dn = "")

Generate an EEC request, output the certificate request to a string

6.66.2.6 bool Arc::Credential::GenerateEECRequest (const char * request_filename, const char * key_filename, std::string dn = "")

Generate an EEC request, output the certificate request and the key to a file

6.66.2.7 bool Arc::Credential::GenerateRequest (BIO * bio, bool if_der = false)

Generate a proxy request, base on the keybits and signing algorithm information inside this object output the certificate request to output BIO

6.66.2.8 bool Arc::Credential::GenerateRequest (std::string & content, bool if_der = false)

Generate a proxy request, output the certificate request to a string

6.66.2.9 bool Arc::Credential::GenerateRequest (const char * filename, bool if_der = false)

Generate a proxy request, output the certificate request to a file

6.66.2.10 X509* Arc::Credential::GetCert (void) const

Get the certificate attached to this object

6.66.2.11 int Arc::Credential::GetCertNumofChain (void) const

Get the number of certificates in the certificate chain attached to this object

6.66.2.12 X509_REQ* Arc::Credential::GetCertReq (void) const

Get the certificate request, if there is any

6.66.2.13 std::string Arc::Credential::GetDN (void) const

Get the DN of the certificate attached to this object

6.66.2.14 Time Arc::Credential::GetEndTime () const

Returns validity end time of certificate or proxy

6.66.2.15 Credformat Arc::Credential::getFormat (BIO * in, const bool is_file = true) const

Get the certificate format, PEM PKCS12 or DER BIO could be memory or file, they should be processed differently.

6.66.2.16 std::string Arc::Credential::GetIdentityName (void) const

Get the Identity name of the certificate attached to this object, the result will not include proxy CN

6.66.2.17 Period Arc::Credential::GetLifeTime (void) const

Returns lifetime of certificate or proxy

6.66.2.18 EVP_PKEY* Arc::Credential::GetPrivKey (void) const

Get the private key attached to this object

6.66.2.19 std::string Arc::Credential::GetProxyPolicy (void) const

Get the proxy policy attached to the "proxy certificate information" extension of the proxy certicate

6.66.2.20 EVP_PKEY* Arc::Credential::GetPubKey (void) const

Get the public key attached to this object

6.66.2.21 Time Arc::Credential::GetStartTime () const

Returns validity start time of certificate or proxy

6.66.2.22 ArcCredential::certType Arc::Credential::GetType (void) const

Get type of the certificate attached to this object

6.66.2.23 bool Arc::Credential::GetVerification (void) const [inline]

Get the verification result about certificate chain checking

6.66.2.24 static void Arc::Credential::InitProxyCertInfo(void) [static]

Initiate nid for proxy certificate extension

Inquire the certificate request from a file

6.66.2.26 bool Arc::Credential::InquireRequest (BIO *
$$reqbio$$
, bool $if_eec = false$, bool $if_der = false$)

Inquire the certificate request from BIO, and put the request information to X509_REQ inside this object, and parse the certificate type from the PROXYCERTINFO of request' extension

Parameters

if_der false for PEM; true for DER

6.66.2.27 bool Arc::Credential::InquireRequest (std::string & content, bool if_eec = false, bool if der = false)

Inquire the certificate request from a string

6.66.2.28 void Arc::Credential::LogError (void) const

Log error information related with openssl

6.66.2.29 bool Arc::Credential::OutputCertificate (std::string & content, bool is_der = false)

Output the certificate into string

Parameters

is_der false for PEM, true for DER

6.66.2.30 bool Arc::Credential::OutputCertificateChain (std::string & content, bool is_der = false)

Output the certificate chain into string

Parameters

is_der false for PEM, true for DER

6.66.2.31 bool Arc::Credential::OutputPrivatekey (std::string & content, bool encryption = false, const std::string & passphrase = "")

Output the private key into string

Parameters

encryption,whether encrypt the output private key or not
passphrase,the passphrase to encrypt the output private key

6.66.2.32 bool Arc::Credential::OutputPublickey (std::string & content)

Output the public key into string

6.66.2.33 void Arc::Credential::SetLifeTime (const Period & period)

Set lifetime of certificate or proxy

6.66.2.34 void Arc::Credential::SetProxyPolicy (const std::string & proxyversion, const std::string & policylang, const std::string & policy, int pathlength)

Set the proxy policy attached to the "proxy certificate information" extension of the proxy certicate

6.66.2.35 void Arc::Credential::SetStartTime (const Time & start_time)

Set start time of certificate or proxy

6.66.2.36 bool Arc::Credential::SignEECRequest (Credential * eec, const std::string & DN, BIO * outputbio)

Sign eec request, and output the signed certificate to output BIO

6.66.2.37 bool Arc::Credential::SignEECRequest (Credential * eec, const std::string & DN, std::string & content)

Sign request and output the signed certificate to a string

6.66.2.38 bool Arc::Credential::SignEECRequest (Credential * eec, const std::string & DN, const char * filename)

Sign request and output the signed certificate to a file

6.66.2.39 bool Arc::Credential::SignRequest (Credential * proxy, BIO * outputbio, bool if_der = false)

Sign request based on the information inside proxy, and output the signed certificate to output BIO

Parameters

if_der false for PEM, true for DER

6.66.2.40 bool Arc::Credential::SignRequest (Credential * proxy, const char * filename, bool foamat = false)

Sign request and output the signed certificate to a file

Parameters

if_der false for PEM, true for DER

6.66.2.41 bool Arc::Credential::SignRequest (Credential * proxy, std::string & content, bool if_der = false)

Sign request and output the signed certificate to a string

Parameters

if_der false for PEM, true for DER

6.66.2.42 Arc::Credential::STACK_OF (X509) const

Get the certificate chain attached to this object

The documentation for this class was generated from the following file:

Credential.h

6.67 Arc::CredentialError Class Reference

#include <Credential.h>

Public Member Functions

• CredentialError (const std::string &what="")

6.67.1 Detailed Description

This is an exception class that is used to handle runtime errors discovered in the Credential (p. 90) class.

6.67.2 Constructor & Destructor Documentation

6.67.2.1 Arc::CredentialError::CredentialError (const std::string & what = "")

This is the constructor of the CredentialError (p. 97) class.

Parameters

what An explanation of the error.

The documentation for this class was generated from the following file:

• Credential.h

6.68 Arc::CredentialStore Class Reference

#include <CredentialStore.h>

6.68.1 Detailed Description

This class provides functionality for storing delegated crdentials and retrieving them from some store services. This is very preliminary implementation and currently support only one type of credentials - X.509 proxies, and only one type of store service - MyProxy. Later it will be extended to support at least following services: ARC delegation service, VOMS service, local file system.

The documentation for this class was generated from the following file:


· CredentialStore.h

6.69 Arc::Database Class Reference

Interface for calling database client library.

#include <DBInterface.h>

Inheritance diagram for Arc::Database:



Public Member Functions

- Database ()
- **Database** (std::string &server, int port)
- Database (const Database &other)
- virtual ~**Database** ()
- virtual bool **connect** (std::string &dbname, std::string &user, std::string &password)=0

- virtual bool **isconnected** () const =0
- virtual void **close** ()=0
- virtual bool **enable_ssl** (const std::string keyfile="", const std::string certfile="", const std::string cafile="", const std::string capath="")=0
- virtual bool **shutdown** ()=0

6.69.1 Detailed Description

Interface for calling database client library. For different types of database client library, different classes should be implemented by implementing this interface.

6.69.2 Constructor & Destructor Documentation

```
6.69.2.1 Arc::Database::Database() [inline]
```

Default constructor

```
6.69.2.2 Arc::Database::Database ( std::string & server, int port ) [inline]
```

Constructor which uses the server's name(or IP address) and port as parametes

```
6.69.2.3 Arc::Database::Database ( const Database & other ) [inline]
```

Copy constructor

```
6.69.2.4 virtual Arc::Database::~Database() [inline, virtual]
```

Deconstructor

6.69.3 Member Function Documentation

```
6.69.3.1 virtual void Arc::Database::close() [pure virtual]
```

Close the connection with database server

Implemented in Arc::MySQLDatabase (p. 220).

6.69.3.2 virtual bool Arc::Database::connect (std::string & dbname, std::string & user, std::string & password) [pure virtual]

Do connection with database server

Parameters

dbname The database name which will be used.

user The username which will be used to access database.

password The password which will be used to access database.

Implemented in Arc::MySQLDatabase (p. 220).

6.69.3.3 virtual bool Arc::Database::enable_ssl (const std::string keyfile = "", const std::string certfile = "", const std::string cafile = "", const std::string capath = "") [pure virtual]

Enable ssl communication for the connection

Parameters

```
keyfile The location of key file.certfile The location of certificate file.cafile The location of ca file.capath The location of ca directory
```

Implemented in Arc::MySQLDatabase (p. 221).

6.69.3.4 virtual bool Arc::Database::isconnected () const [pure virtual]

Get the connection status

Implemented in Arc::MySQLDatabase (p. 221).

6.69.3.5 virtual bool Arc::Database::shutdown() [pure virtual]

Ask database server to shutdown

Implemented in Arc::MySQLDatabase (p. 221).

The documentation for this class was generated from the following file:

• DBInterface.h

6.70 Arc::DataBuffer Class Reference

Represents set of buffers.

#include <DataBuffer.h>

Data Structures

- · struct buf desc
- class checksum_desc

Public Member Functions

- operator bool () const
- **DataBuffer** (unsigned int size=65536, int blocks=3)
- DataBuffer (CheckSum *cksum, unsigned int size=65536, int blocks=3)
- \sim DataBuffer ()
- bool **set** (**CheckSum** *cksum=NULL, unsigned int size=65536, int blocks=3)
- int add (CheckSum *cksum)

- char * operator[] (int n)
- bool for_read (int &handle, unsigned int &length, bool wait)
- bool for_read ()
- bool **is_read** (int handle, unsigned int length, unsigned long long int offset)
- bool **is_read** (char *buf, unsigned int length, unsigned long long int offset)
- bool for_write (int &handle, unsigned int &length, unsigned long long int &offset, bool wait)
- bool for write ()
- bool is_written (int handle)
- bool is_written (char *buf)
- bool is **notwritten** (int handle)
- bool is_notwritten (char *buf)
- void eof_read (bool v)
- void **eof_write** (bool v)
- void **error_read** (bool v)
- void error_write (bool v)
- bool eof_read ()
- bool eof_write()
- bool error read ()
- bool error_write ()
- bool error_transfer ()
- bool error ()
- bool wait_any ()
- bool wait used ()
- bool checksum_valid () const
- const CheckSum * checksum_object () const
- bool wait_eof_read ()
- bool wait_read ()
- bool wait_eof_write ()
- bool wait_write ()
- bool wait_eof()
- unsigned long long int eof position () const
- unsigned int buffer_size () const

Data Fields

· DataSpeed speed

6.70.1 Detailed Description

Represents set of buffers. This class is used used during data transfer using **DataPoint** (p. 108) classes.

6.70.2 Constructor & Destructor Documentation

6.70.2.1 Arc::DataBuffer::DataBuffer (unsigned int size = 65536, int blocks = 3)

Contructor

Parameters

size size of every buffer in bytes.

blocks number of buffers.

6.70.2.2 Arc::DataBuffer::DataBuffer (CheckSum * cksum, unsigned int size = 65536, int blocks = 3)

Contructor

Parameters

size size of every buffer in bytes.

blocks number of buffers.

cksum object which will compute checksum. Should not be destroyed till DataBuffer (p. 100) itself.

6.70.3 Member Function Documentation

6.70.3.1 int Arc::DataBuffer::add (CheckSum * cksum)

Add a checksum object which will compute checksum of buffer.

Parameters

cksum object which will compute checksum. Should not be destroyed till **DataBuffer** (p. 100) itself.

Returns

integer position in the list of checksum objects.

6.70.3.2 unsigned int Arc::DataBuffer::buffer_size () const

Returns size of buffer in object. If not initialized then this number represents size of default buffer.

6.70.3.3 const CheckSum* Arc::DataBuffer::checksum_object () const

Returns CheckSum (p. 67) object specified in constructor, returns NULL if index is not in list.

Parameters

index of the checksum in question.

6.70.3.4 bool Arc::DataBuffer::checksum_valid () const

Returns true if checksum was successfully computed, returns false if index is not in list.

Parameters

index of the checksum in question.

6.70.3.5 bool Arc::DataBuffer::eof_read ()

Returns true if object was informed about end of transfer on 'read' side.

6.70.3.6 void Arc::DataBuffer::eof_read (bool v)

Informs object if there will be no more request for 'read' buffers. v true if no more requests.

6.70.3.7 void Arc::DataBuffer::eof_write (bool v)

Informs object if there will be no more request for 'write' buffers. v true if no more requests.

6.70.3.8 bool Arc::DataBuffer::eof_write()

Returns true if object was informed about end of transfer on 'write' side.

6.70.3.9 bool Arc::DataBuffer::error ()

Returns true if object was informed about error or internal error occured.

6.70.3.10 void Arc::DataBuffer::error_read (bool v)

Informs object if error accured on 'read' side.

Parameters

v true if error.

6.70.3.11 void Arc::DataBuffer::error_write (bool v)

Informs object if error accured on 'write' side.

Parameters

v true if error.

6.70.3.12 bool Arc::DataBuffer::for_read (int & handle, unsigned int & length, bool wait)

Request buffer for READING INTO it.

Parameters

handle returns buffer's number.

length returns size of buffer

wait if true and there are no free buffers, method will wait for one.

Returns

true on success

6.70.3.13 bool Arc::DataBuffer::for_read()

Check if there are buffers which can be taken by **for_read()** (p. 103). This function checks only for buffers and does not take eof and error conditions into account.

6.70.3.14 bool Arc::DataBuffer::for_write (int & handle, unsigned int & length, unsigned long long int & offset, bool wait)

Request buffer for WRITING FROM it.

Parameters

handle returns buffer's number.

length returns size of buffer

wait if true and there are no free buffers, method will wait for one.

6.70.3.15 bool Arc::DataBuffer::for_write ()

Check if there are buffers which can be taken by **for_write()** (p. 104). This function checks only for buffers and does not take eof and error conditions into account.

6.70.3.16 bool Arc::DataBuffer::is_notwritten (int handle)

Informs object that data was NOT written from buffer (and releases buffer).

Parameters

handle buffer's number.

6.70.3.17 bool Arc::DataBuffer::is_notwritten (char * buf)

Informs object that data was NOT written from buffer (and releases buffer).

Parameters

buf - address of buffer

6.70.3.18 bool Arc::DataBuffer::is_read (char * buf, unsigned int length, unsigned long long int offset)

Informs object that data was read into buffer.

Parameters

buf - address of buffer

length amount of data.

offset offset in stream, file, etc.

6.70.3.19 bool Arc::DataBuffer::is_read (int *handle*, unsigned int *length*, unsigned long long int *offset*)

Informs object that data was read into buffer.

Parameters

```
handle buffer's number.
```

length amount of data.

offset offset in stream, file, etc.

6.70.3.20 bool Arc::DataBuffer::is_written (int handle)

Informs object that data was written from buffer.

Parameters

handle buffer's number.

6.70.3.21 bool Arc::DataBuffer::is_written (char * buf)

Informs object that data was written from buffer.

Parameters

buf - address of buffer

6.70.3.22 bool Arc::DataBuffer::set (CheckSum * cksum = NULL, unsigned int size = 65536, int blocks = 3)

Reinitialize buffers with different parameters.

Parameters

size size of every buffer in bytes.

blocks number of buffers.

cksum object which will compute checksum. Should not be destroyed till DataBuffer (p. 100) itself.

6.70.3.23 bool Arc::DataBuffer::wait_any()

Wait (max 60 sec.) till any action happens in object. Returns true if action is eof on any side.

The documentation for this class was generated from the following file:

· DataBuffer.h

6.71 Arc::DataCallback Class Reference

#include <DataCallback.h>

6.71.1 Detailed Description

This class is used by **DataHandle** (p. 106) to report missing space on local filesystem. One of 'cb' functions here will be called if operation initiated by DataHandle::start_reading runs out of disk space.

The documentation for this class was generated from the following file:

· DataCallback.h

6.72 Arc::DataHandle Class Reference

This class is a wrapper around the **DataPoint** (p. 108) class.

#include <DataHandle.h>

6.72.1 Detailed Description

This class is a wrapper around the **DataPoint** (p. 108) class. It simplifies the construction, use and destruction of **DataPoint** (p. 108) objects.

The documentation for this class was generated from the following file:

• DataHandle.h

6.73 Arc::DataMover Class Reference

#include <DataMover.h>

Public Member Functions

- DataMover ()
- ∼DataMover ()
- DataStatus Transfer (DataPoint &source, DataPoint &destination, FileCache &cache, const URLMap &map, callback cb=NULL, void *arg=NULL, const char *prefix=NULL)
- DataStatus Transfer (DataPoint &source, DataPoint &destination, FileCache &cache, const URLMap &map, unsigned long long int min_speed, time_t min_speed_time, unsigned long long int min_average_speed, time_t max_inactivity_time, callback cb=NULL, void *arg=NULL, const char *prefix=NULL)
- bool verbose ()
- void verbose (bool)
- void **verbose** (const std::string &prefix)
- bool retry ()
- void **retry** (bool)
- void secure (bool)
- void passive (bool)
- void force_to_meta (bool)
- bool checks ()
- void **checks** (bool v)
- void **set_default_min_speed** (unsigned long long int min_speed, time_t min_speed_time)
- void **set_default_min_average_speed** (unsigned long long int min_average_speed)
- void **set_default_max_inactivity_time** (time_t max_inactivity_time)

6.73.1 Detailed Description

A purpose of this class is to provide an interface that moves data between two locations specified by URLs. It's main action is represented by methods **DataMover::Transfer** (p. 108). Instance represents only attributes used during transfer.

6.73.2 Member Function Documentation

6.73.2.1 bool Arc::DataMover::checks ()

Check if check for existance of remote file is done before initiating 'reading' and 'writing' operations.

6.73.2.2 void Arc::DataMover::checks (bool v)

Set if to make check for existance of remote file (and probably other checks too) before initiating 'reading' and 'writing' operations.

Parameters

v true if allowed (default is true).

6.73.2.3 void Arc::DataMover::force_to_meta (bool)

Set if file should be transfered and registered even if such LFN is already registered and source is not one of registered locations.

6.73.2.4 void Arc::DataMover::secure (bool)

Set if high level of security (encryption) will be used duirng transfer if available.

6.73.2.5 void Arc::DataMover::set_default_max_inactivity_time (time_t max_inactivity_time) [inline]

Set maximal allowed time for waiting for any data. For more information see description of **DataSpeed** (p. 128) class.

6.73.2.6 void Arc::DataMover::set_default_min_average_speed (unsigned long long int min_average_speed) [inline]

Set minimal allowed average transfer speed (default is 0 averaged over whole time of transfer. For more information see description of **DataSpeed** (p. 128) class.

6.73.2.7 void Arc::DataMover::set_default_min_speed (unsigned long long int min_speed, time_t min_speed_time) [inline]

Set minimal allowed transfer speed (default is 0) to 'min_speed'. If speed drops below for time longer than 'min_speed_time' error is raised. For more information see description of **DataSpeed** (p. 128) class.

6.73.2.8 DataStatus Arc::DataMover::Transfer (DataPoint & source, DataPoint & destination, FileCache & cache, const URLMap & map, callback cb = NULL, void * arg = NULL, const char * prefix = NULL)

Initiates transfer from 'source' to 'destination'.

Parameters

```
source URL (p. 320).
```

destination destination URL (p. 320).

cache controls caching of downloaded files (if destination url is "file://"). If caching is not needed default constructor FileCache() can be used.

map URL (p. 320) mapping/convertion table (for 'source' URL (p. 320)).

cb if not NULL, transfer is done in separate thread and 'cb' is called after transfer completes/fails.arg passed to 'cb'.

prefix if 'verbose' is activated this information will be printed before each line representing current transfer status.

6.73.2.9 DataStatus Arc::DataMover::Transfer (DataPoint & source, DataPoint & destination, FileCache & cache, const URLMap & map, unsigned long long int min_speed, time_t min_speed_time, unsigned long long int min_average_speed, time_t max_inactivity_time, callback cb = NULL, void * arg = NULL, const char * prefix = NULL)

Initiates transfer from 'source' to 'destination'.

Parameters

min_speed minimal allowed current speed.

min_speed_time time for which speed should be less than 'min_speed' before transfer fails.

min_average_speed minimal allowed average speed.

max_inactivity_time time for which should be no activity before transfer fails.

6.73.2.10 void Arc::DataMover::verbose (const std::string & prefix)

Activate printing information about transfer status.

Parameters

prefix use this string if 'prefix' in **DataMover::Transfer** (p. 108) is NULL.

The documentation for this class was generated from the following file:


· DataMover.h

6.74 Arc::DataPoint Class Reference

This base class is an abstraction of URL (p. 320).

#include <DataPoint.h>

Inheritance diagram for Arc::DataPoint:



Public Types

 enum DataPointAccessLatency { ACCESS_LATENCY_ZERO, ACCESS_LATENCY_-SMALL, ACCESS_LATENCY_LARGE }

Public Member Functions

- DataPoint (const URL &url, const UserConfig &usercfg)
- virtual ~**DataPoint** ()
- virtual const URL & GetURL () const
- virtual const UserConfig & GetUserConfig () const
- virtual std::string str () const
- virtual operator bool () const
- virtual bool operator! () const
- virtual **DataStatus StartReading** (**DataBuffer** &buffer)=0
- virtual DataStatus StartWriting (DataBuffer &buffer, DataCallback *space_cb=NULL)=0
- virtual **DataStatus StopReading** ()=0
- virtual **DataStatus StopWriting** ()=0
- virtual **DataStatus Check** ()=0
- virtual **DataStatus Remove** ()=0
- virtual **DataStatus ListFiles** (std::list< **FileInfo** > &files, bool long_list=false, bool resolve=false, bool metadata=false)=0
- virtual void **ReadOutOfOrder** (bool v)=0
- virtual bool WriteOutOfOrder ()=0
- virtual void **SetAdditionalChecks** (bool v)=0
- virtual bool **GetAdditionalChecks** () const =0
- virtual void **SetSecure** (bool v)=0
- virtual bool **GetSecure** () const =0
- virtual void **Passive** (bool v)=0
- virtual DataStatus GetFailureReason (void) const
- virtual void **Range** (unsigned long long int start=0, unsigned long long int end=0)=0
- virtual **DataStatus Resolve** (bool source)=0
- virtual bool **Registered** () const =0
- virtual **DataStatus PreRegister** (bool replication, bool force=false)=0
- virtual **DataStatus PostRegister** (bool replication)=0
- virtual **DataStatus PreUnregister** (bool replication)=0
- virtual **DataStatus Unregister** (bool all)=0
- virtual bool CheckSize () const
- virtual void **SetSize** (const unsigned long long int val)

- virtual unsigned long long int **GetSize** () const
- virtual bool CheckCheckSum () const
- virtual void SetCheckSum (const std::string &val)
- virtual const std::string & GetCheckSum () const
- virtual const std::string **DefaultCheckSum** () const
- virtual bool CheckCreated () const
- virtual void **SetCreated** (const **Time** &val)
- virtual const Time & GetCreated () const
- virtual bool CheckValid () const
- virtual void **SetValid** (const **Time** &val)
- virtual const Time & GetValid () const
- virtual void SetAccessLatency (const DataPointAccessLatency &latency)
- virtual DataPointAccessLatency GetAccessLatency () const
- virtual long long int **BufSize** () const =0
- virtual int **BufNum** () const =0
- virtual bool Cache () const
- virtual bool Local () const =0
- virtual int GetTries () const
- virtual void **SetTries** (const int n)
- virtual void **NextTry** (void)
- virtual bool **IsIndex** () const =0
- virtual bool **AcceptsMeta** ()=0
- virtual bool **ProvidesMeta** ()=0
- virtual void **SetMeta** (const **DataPoint** &p)
- virtual bool CompareMeta (const DataPoint &p) const
- virtual const URL & CurrentLocation () const =0
- virtual const std::string & CurrentLocationMetadata () const =0
- virtual **DataStatus CompareLocationMetadata** () const =0
- virtual bool **NextLocation** ()=0
- virtual bool **LocationValid** () const =0
- virtual bool **LastLocation** ()=0
- virtual bool **HaveLocations** () const =0
- virtual **DataStatus AddLocation** (const **URL** &url, const std::string &meta)=0
- virtual **DataStatus RemoveLocation** ()=0
- virtual **DataStatus RemoveLocations** (const **DataPoint** &p)=0
- virtual int AddCheckSumObject (CheckSum *cksum)=0
- virtual void **SortLocations** (const std::string &pattern, const **URLMap** &url_map)=0

Protected Attributes

• std::list< std::string > valid_url_options

6.74.1 Detailed Description

This base class is an abstraction of **URL** (p. 320). Specializations should be provided for different kind of direct access URLs (file://, ftp://, gsiftp://, http://, https://, https://, https://, or indexing service URLs (rls://, lfc://, ...). **DataPoint** (p. 108) provides means to resolve an indexing service **URL** (p. 320) into multiple URLs and to loop through them.

6.74.2 Member Enumeration Documentation

6.74.2.1 enum Arc::DataPoint::DataPointAccessLatency

Describes the latency to access this **URL** (p. 320).

For now this value is one of a small set specified by the enumeration. In the future with more sophisticated protocols or information it could be replaced by a more fine-grained list of possibilities such as an int value.

Enumerator:

ACCESS_LATENCY_ZERO URL (p. 320) can be accessed instantly.

ACCESS_LATENCY_SMALL URL (p. 320) has low (but non-zero) access latency, for example staged from disk.

ACCESS_LATENCY_LARGE URL (p. 320) has a large access latency, for example staged from tape.

6.74.3 Constructor & Destructor Documentation

6.74.3.1 Arc::DataPoint::DataPoint (const URL & url, const UserConfig & usercfg)

Constructor requires **URL** (p. 320) to be provided.

References to url and usercfg arguments are stored internally and hence corresponding objects must stay available during whole lifetime of this instance.

6.74.4 Member Function Documentation

6.74.4.1 virtual int Arc::DataPoint::AddCheckSumObject (CheckSum * cksum) [pure virtual]

Add a checksum object which will compute checksum during transmission.

Parameters

cksum object which will compute checksum. Should not be destroyed till DataPointer itself.

Returns

integer position in the list of checksum objects.

Implemented in Arc::DataPointDirect (p. 118), and Arc::DataPointIndex (p. 123).

6.74.4.2 virtual DataStatus Arc::DataPoint::AddLocation (const URL & url, const std::string & meta) [pure virtual]

Add URL (p. 320) to list.

Parameters

url Location URL (p. 320) to add.

meta Location meta information.

Implemented in Arc::DataPointDirect (p. 118), and Arc::DataPointIndex (p. 123).

6.74.4.3 virtual DataStatus Arc::DataPoint::Check () [pure virtual]

Query (p. 257) the DataPoint (p. 108) to check if object is accessible.

If possible this method will also try to provide meta information about the object.

Implemented in Arc::DataPointIndex (p. 124).

6.74.4.4 virtual DataStatus Arc::DataPoint::CompareLocationMetadata () const [pure virtual]

Compare metadata of **DataPoint** (p. 108) and current location.

Returns inconsistency error or error encountered during operation, or success

Implemented in Arc::DataPointDirect (p. 119), and Arc::DataPointIndex (p. 124).

6.74.4.5 virtual bool Arc::DataPoint::CompareMeta (const DataPoint & p) const [virtual]

Compare meta information from another object.

Undefined values are not used for comparison.

Parameters

p object to which to compare.

6.74.4.6 virtual const std::string& Arc::DataPoint::CurrentLocationMetadata() const [pure virtual]

Returns meta information used to create current URL (p. 320).

Usage differs between different indexing services.

Implemented in Arc::DataPointDirect (p. 119), and Arc::DataPointIndex (p. 124).

6.74.4.7 virtual DataStatus Arc::DataPoint::GetFailureReason (void)const [virtual]

Returns reason of transfer failure, as reported by callbacks. This could be different from the failure returned by the methods themselves.

6.74.4.8 virtual DataStatus Arc::DataPoint::ListFiles (std::list< FileInfo > & files, bool long_list = false, bool resolve = false, bool metadata = false) [pure virtual]

List file(s).

If the **DataPoint** (p. 108) represents a directory its contents will be listed.

Parameters

files will contain list of file names and optionally their attributes.

long_list if true, list additional properties of each file.

resolve if true, resolve physical locations (relevant for indexing services only).

metadata if true, find all available metadata.

6.74.4.9 virtual bool Arc::DataPoint::NextLocation() [pure virtual]

Switch to next location in list of URLs.

At last location switch to first if number of allowed retries is not exceeded. Returns false if no retries left.

Implemented in Arc::DataPointDirect (p. 119), and Arc::DataPointIndex (p. 124).

6.74.4.10 virtual void Arc::DataPoint::Passive (bool v) [pure virtual]

Request passive transfers for FTP-like protocols.

Parameters

true to request.

Implemented in Arc::DataPointDirect (p. 119), and Arc::DataPointIndex (p. 124).

6.74.4.11 virtual DataStatus Arc::DataPoint::PostRegister (bool replication) [pure virtual]

Index Service (p. 282) postregistration.

Used for same purpose as PreRegister. Should be called after actual transfer of file successfully finished.

Parameters

replication if true, the file is being replicated between two locations registered in Indexing **Service** (p. 282) under same name.

Implemented in Arc::DataPointDirect (p. 119).

6.74.4.12 virtual DataStatus Arc::DataPoint::PreRegister (bool replication, bool force = false) [pure virtual]

Index service preregistration.

This function registers the physical location of a file into an indexing service. It should be called *before* the actual transfer to that location happens.

Parameters

replication if true, the file is being replicated between two locations registered in the indexing service under same name.

force if true, perform registration of a new file even if it already exists. Should be used to fix failures in Indexing **Service** (p. 282).

Implemented in Arc::DataPointDirect (p. 119).

6.74.4.13 virtual DataStatus Arc::DataPoint::PreUnregister (bool replication) [pure virtual]

Index Service (p. 282) preunregistration.

Should be called if file transfer failed. It removes changes made by PreRegister.

Parameters

replication if true, the file is being replicated between two locations registered in Indexing **Service** (p. 282) under same name.

Implemented in Arc::DataPointDirect (p. 120).

6.74.4.14 virtual bool Arc::DataPoint::ProvidesMeta() [pure virtual]

If endpoint can provide at least some meta information directly.

Implemented in Arc::DataPointDirect (p. 120), and Arc::DataPointIndex (p. 124).

6.74.4.15 virtual void Arc::DataPoint::Range (unsigned long long int start = 0, unsigned long long int end = 0) [pure virtual]

Set range of bytes to retrieve.

Default values correspond to whole file.

Implemented in Arc::DataPointDirect (p. 120), and Arc::DataPointIndex (p. 124).

6.74.4.16 virtual void Arc::DataPoint::ReadOutOfOrder (bool v) [pure virtual]

Allow/disallow **DataPoint** (p. 108) to produce scattered data during reading* operation.

Parameters

v true if allowed (default is false).

Implemented in Arc::DataPointDirect (p. 120), and Arc::DataPointIndex (p. 125).

6.74.4.17 virtual bool Arc::DataPoint::Registered () const [pure virtual]

Check if file is registered in Indexing Service (p. 282).

Proper value is obtainable only after Resolve.

Implemented in Arc::DataPointDirect (p. 120), and Arc::DataPointIndex (p. 125).

6.74.4.18 virtual DataStatus Arc::DataPoint::Resolve (bool source) [pure virtual]

Resolves index service URL (p. 320) into list of ordinary URLs.

Also obtains meta information about the file.

Parameters

source true if **DataPoint** (p. 108) object represents source of information.

Implemented in Arc::DataPointDirect (p. 121).

6.74.4.19 virtual void Arc::DataPoint::SetAdditionalChecks (bool v) [pure virtual]

Allow/disallow additional checks.

Check for existance of remote file (and probably other checks too) before initiating reading and writing operations.

Parameters

v true if allowed (default is true).

Implemented in Arc::DataPointDirect (p. 121), and Arc::DataPointIndex (p. 125).

6.74.4.20 virtual void Arc::DataPoint::SetMeta (const DataPoint & p) [virtual]

Copy meta information from another object.

Already defined values are not overwritten.

Parameters

p object from which information is taken.

Reimplemented in Arc::DataPointIndex (p. 125).

6.74.4.21 virtual void Arc::DataPoint::SetSecure (bool v) [pure virtual]

Allow/disallow heavy security during data transfer.

Parameters

v true if allowed (default depends on protocol).

Implemented in Arc::DataPointDirect (p. 121), and Arc::DataPointIndex (p. 125).

6.74.4.22 virtual void Arc::DataPoint::SortLocations (const std::string & pattern, const URLMap & url_map) [pure virtual]

Sort locations according to the specified pattern.

Parameters

pattern a set of strings, separated by |, to match against.

Implemented in Arc::DataPointDirect (p. 121), and Arc::DataPointIndex (p. 126).

6.74.4.23 virtual DataStatus Arc::DataPoint::StartReading (DataBuffer & buffer) [pure virtual]

Start reading data from URL (p. 320).

Separate thread to transfer data will be created. No other operation can be performed while reading is in progress.

Parameters

buffer operation will use this buffer to put information into. Should not be destroyed before stop_reading was called and returned.

Implemented in Arc::DataPointIndex (p. 126).

6.74.4.24 virtual DataStatus Arc::DataPoint::StartWriting (DataBuffer & buffer, DataCallback * $space_cb = NULL$) [pure virtual]

Start writing data to URL (p. 320).

Separate thread to transfer data will be created. No other operation can be performed while writing is in progress.

Parameters

buffer operation will use this buffer to get information from. Should not be destroyed before stop_writing was called and returned.

space_cb callback which is called if there is not enough space to store data. May not implemented for all protocols.

Implemented in Arc::DataPointIndex (p. 126).

6.74.4.25 virtual DataStatus Arc::DataPoint::StopReading() [pure virtual]

Stop reading.

Must be called after corresponding start_reading method, either after all data is transferred or to cancel transfer. Use buffer object to find out when data is transferred. Must return failure if any happened during transfer.

Implemented in Arc::DataPointIndex (p. 126).

6.74.4.26 virtual DataStatus Arc::DataPoint::StopWriting() [pure virtual]

Stop writing.

Must be called after corresponding start_writing method, either after all data is transferred or to cancel transfer. Use buffer object to find out when data is transferred. Must return failure if any happened during transfer.

Implemented in Arc::DataPointIndex (p. 127).

6.74.4.27 virtual DataStatus Arc::DataPoint::Unregister (bool all) [pure virtual]

Index **Service** (p. 282) unregistration.

Remove information about file registered in Indexing Service (p. 282).

Parameters

all if true, information about file itself is (LFN) is removed. Otherwise only particular physical instance is unregistered.

Implemented in Arc::DataPointDirect (p. 121).

6.74.4.28 virtual bool Arc::DataPoint::WriteOutOfOrder() [pure virtual]

Returns true if URL (p. 320) can accept scattered data for *writing* operation.

Implemented in Arc::DataPointDirect (p. 122), and Arc::DataPointIndex (p. 127).

6.74.5 Field Documentation

6.74.5.1 std::list<std::string> Arc::DataPoint::valid_url_options [protected]

Subclasses should add their own specific options to this list

The documentation for this class was generated from the following file:


· DataPoint.h

6.75 Arc::DataPointDirect Class Reference

This is a kind of generalized file handle.

#include <DataPointDirect.h>

Inheritance diagram for Arc::DataPointDirect:



Public Member Functions

- virtual bool IsIndex () const
- virtual long long int BufSize () const
- virtual int BufNum () const
- virtual bool Local () const
- virtual void **ReadOutOfOrder** (bool v)
- virtual bool WriteOutOfOrder ()
- virtual void **SetAdditionalChecks** (bool v)
- virtual bool GetAdditionalChecks () const
- virtual void **SetSecure** (bool v)
- virtual bool GetSecure () const
- virtual void **Passive** (bool v)
- virtual void **Range** (unsigned long long int start=0, unsigned long long int end=0)
- virtual int AddCheckSumObject (CheckSum *cksum)
- virtual DataStatus Resolve (bool source)
- virtual bool Registered () const
- virtual **DataStatus PreRegister** (bool replication, bool force=false)

- virtual **DataStatus PostRegister** (bool replication)
- virtual **DataStatus PreUnregister** (bool replication)
- virtual **DataStatus Unregister** (bool all)
- virtual bool AcceptsMeta ()
- virtual bool ProvidesMeta ()
- virtual const URL & CurrentLocation () const
- virtual const std::string & CurrentLocationMetadata () const
- virtual DataStatus CompareLocationMetadata () const
- virtual bool **NextLocation** ()
- virtual bool **LocationValid** () const
- virtual bool HaveLocations () const
- virtual bool LastLocation ()
- virtual **DataStatus AddLocation** (const **URL** &url, const std::string &meta)
- virtual DataStatus RemoveLocation ()
- virtual **DataStatus RemoveLocations** (const **DataPoint** &p)
- virtual void **SortLocations** (const std::string &pattern, const **URLMap** &url_map)

6.75.1 Detailed Description

This is a kind of generalized file handle. Differently from file handle it does not support operations read() and write(). Instead it initiates operation and uses object of class **DataBuffer** (p. 100) to pass actual data. It also provides other operations like querying parameters of remote object. It is used by higher-level classes DataMove and DataMovePar to provide data transfer service for application.

6.75.2 Member Function Documentation

6.75.2.1 virtual int Arc::DataPointDirect::AddCheckSumObject (CheckSum * cksum) [virtual]

Add a checksum object which will compute checksum during transmission.

Parameters

cksum object which will compute checksum. Should not be destroyed till DataPointer itself.

Returns

integer position in the list of checksum objects.

Implements **Arc::DataPoint** (p. 111).

6.75.2.2 virtual DataStatus Arc::DataPointDirect::AddLocation (const URL & url, const std::string & meta) [virtual]

Add URL (p. 320) to list.

Parameters

```
url Location URL (p. 320) to add.meta Location meta information.
```

Implements Arc::DataPoint (p. 111).

6.75.2.3 virtual DataStatus Arc::DataPointDirect::CompareLocationMetadata () const [virtual]

Compare metadata of **DataPoint** (p. 108) and current location.

Returns inconsistency error or error encountered during operation, or success

Implements Arc::DataPoint (p. 112).

6.75.2.4 virtual const std::string& Arc::DataPointDirect::CurrentLocationMetadata () const [virtual]

Returns meta information used to create current URL (p. 320).

Usage differs between different indexing services.

Implements Arc::DataPoint (p. 112).

6.75.2.5 virtual bool Arc::DataPointDirect::NextLocation() [virtual]

Switch to next location in list of URLs.

At last location switch to first if number of allowed retries is not exceeded. Returns false if no retries left.

Implements **Arc::DataPoint** (p. 113).

6.75.2.6 virtual void Arc::DataPointDirect::Passive (bool v) [virtual]

Request passive transfers for FTP-like protocols.

Parameters

true to request.

Implements **Arc::DataPoint** (p. 113).

6.75.2.7 virtual DataStatus Arc::DataPointDirect::PostRegister (bool replication) [virtual]

Index Service (p. 282) postregistration.

Used for same purpose as PreRegister. Should be called after actual transfer of file successfully finished.

Parameters

replication if true, the file is being replicated between two locations registered in Indexing **Service** (p. 282) under same name.

Implements **Arc::DataPoint** (p. 113).

6.75.2.8 virtual DataStatus Arc::DataPointDirect::PreRegister (bool replication, bool force = false) [virtual]

Index service preregistration.

This function registers the physical location of a file into an indexing service. It should be called *before* the actual transfer to that location happens.

Parameters

replication if true, the file is being replicated between two locations registered in the indexing service under same name.

force if true, perform registration of a new file even if it already exists. Should be used to fix failures in Indexing **Service** (p. 282).

Implements Arc::DataPoint (p. 113).

6.75.2.9 virtual DataStatus Arc::DataPointDirect::PreUnregister (bool replication) [virtual]

Index **Service** (p. 282) preunregistration.

Should be called if file transfer failed. It removes changes made by PreRegister.

Parameters

replication if true, the file is being replicated between two locations registered in Indexing **Service** (p. 282) under same name.

Implements Arc::DataPoint (p. 113).

6.75.2.10 virtual bool Arc::DataPointDirect::ProvidesMeta() [virtual]

If endpoint can provide at least some meta information directly.

Implements Arc::DataPoint (p. 114).

6.75.2.11 virtual void Arc::DataPointDirect::Range (unsigned long long int *start* = 0, unsigned long long int *end* = 0) [virtual]

Set range of bytes to retrieve.

Default values correspond to whole file.

Implements **Arc::DataPoint** (p. 114).

6.75.2.12 virtual void Arc::DataPointDirect::ReadOutOfOrder(bool v) [virtual]

Allow/disallow **DataPoint** (p. 108) to produce scattered data during reading* operation.

Parameters

v true if allowed (default is false).

Implements Arc::DataPoint (p. 114).

6.75.2.13 virtual bool Arc::DataPointDirect::Registered () const [virtual]

Check if file is registered in Indexing Service (p. 282).

Proper value is obtainable only after Resolve.

Implements Arc::DataPoint (p. 114).

6.75.2.14 virtual DataStatus Arc::DataPointDirect::Resolve (bool source) [virtual]

Resolves index service URL (p. 320) into list of ordinary URLs.

Also obtains meta information about the file.

Parameters

source true if **DataPoint** (p. 108) object represents source of information.

Implements Arc::DataPoint (p. 114).

6.75.2.15 virtual void Arc::DataPointDirect::SetAdditionalChecks (bool v) [virtual]

Allow/disallow additional checks.

Check for existance of remote file (and probably other checks too) before initiating reading and writing operations.

Parameters

v true if allowed (default is true).

Implements **Arc::DataPoint** (p. 115).

6.75.2.16 virtual void Arc::DataPointDirect::SetSecure (bool v) [virtual]

Allow/disallow heavy security during data transfer.

Parameters

v true if allowed (default depends on protocol).

Implements Arc::DataPoint (p. 115).

6.75.2.17 virtual void Arc::DataPointDirect::SortLocations (const std::string & pattern, const URLMap & url_map) [inline, virtual]

Sort locations according to the specified pattern.

Parameters

pattern a set of strings, separated by |, to match against.

Implements Arc::DataPoint (p. 115).

6.75.2.18 virtual DataStatus Arc::DataPointDirect::Unregister (bool all) [virtual]

Index Service (p. 282) unregistration.

Remove information about file registered in Indexing Service (p. 282).

Parameters

all if true, information about file itself is (LFN) is removed. Otherwise only particular physical instance is unregistered.

Implements Arc::DataPoint (p. 116).

6.75.2.19 virtual bool Arc::DataPointDirect::WriteOutOfOrder() [virtual]

Returns true if URL (p. 320) can accept scattered data for *writing* operation.

Implements Arc::DataPoint (p. 117).

The documentation for this class was generated from the following file:


· DataPointDirect.h

6.76 Arc::DataPointIndex Class Reference

Complements DataPoint (p. 108) with attributes common for Indexing Service (p. 282) URLs.

#include <DataPointIndex.h>

Inheritance diagram for Arc::DataPointIndex:



Public Member Functions

- virtual const URL & CurrentLocation () const
- virtual const std::string & CurrentLocationMetadata () const
- virtual DataStatus CompareLocationMetadata () const
- virtual bool **NextLocation** ()
- virtual bool LocationValid () const
- virtual bool HaveLocations () const
- virtual bool LastLocation ()
- virtual DataStatus RemoveLocation ()
- virtual DataStatus RemoveLocations (const DataPoint &p)
- virtual **DataStatus AddLocation** (const **URL** &url, const std::string &meta)
- virtual void **SortLocations** (const std::string &pattern, const **URLMap** &url_map)
- virtual bool IsIndex () const
- virtual bool AcceptsMeta ()
- virtual bool **ProvidesMeta** ()
- virtual void **SetMeta** (const **DataPoint** &p)
- virtual void SetCheckSum (const std::string &val)
- virtual void **SetSize** (const unsigned long long int val)
- virtual bool Registered () const
- virtual void **SetTries** (const int n)
- virtual long long int BufSize () const
- virtual int BufNum () const
- virtual bool Local () const

- virtual **DataStatus StartReading** (**DataBuffer** &buffer)
- virtual DataStatus StartWriting (DataBuffer &buffer, DataCallback *space_cb=NULL)
- virtual DataStatus StopReading ()
- virtual DataStatus StopWriting ()
- virtual **DataStatus Check** ()
- virtual DataStatus Remove ()
- virtual void ReadOutOfOrder (bool v)
- virtual bool WriteOutOfOrder ()
- virtual void **SetAdditionalChecks** (bool v)
- virtual bool GetAdditionalChecks () const
- virtual void **SetSecure** (bool v)
- virtual bool GetSecure () const
- virtual DataPointAccessLatency GetAccessLatency () const
- virtual void **Passive** (bool v)
- virtual void **Range** (unsigned long long int start=0, unsigned long long int end=0)
- virtual int AddCheckSumObject (CheckSum *cksum)

6.76.1 Detailed Description

Complements **DataPoint** (p. 108) with attributes common for Indexing **Service** (p. 282) URLs. It should never be used directly. Instead inherit from it to provide a class for specific a Indexing **Service** (p. 282).

6.76.2 Member Function Documentation

6.76.2.1 virtual int Arc::DataPointIndex::AddCheckSumObject (CheckSum * cksum) [virtual]

Add a checksum object which will compute checksum during transmission.

Parameters

cksum object which will compute checksum. Should not be destroyed till DataPointer itself.

Returns

integer position in the list of checksum objects.

Implements Arc::DataPoint (p. 111).

6.76.2.2 virtual DataStatus Arc::DataPointIndex::AddLocation (const URL & url, const std::string & meta) [virtual]

Add URL (p. 320) to list.

Parameters

```
url Location URL (p. 320) to add.meta Location meta information.
```

Implements Arc::DataPoint (p. 111).

6.76.2.3 virtual DataStatus Arc::DataPointIndex::Check() [virtual]

Query (p. 257) the DataPoint (p. 108) to check if object is accessible.

If possible this method will also try to provide meta information about the object.

Implements Arc::DataPoint (p. 112).

6.76.2.4 virtual DataStatus Arc::DataPointIndex::CompareLocationMetadata () const [virtual]

Compare metadata of **DataPoint** (p. 108) and current location.

Returns inconsistency error or error encountered during operation, or success

Implements Arc::DataPoint (p. 112).

6.76.2.5 virtual const std::string& Arc::DataPointIndex::CurrentLocationMetadata () const [virtual]

Returns meta information used to create current URL (p. 320).

Usage differs between different indexing services.

Implements Arc::DataPoint (p. 112).

6.76.2.6 virtual bool Arc::DataPointIndex::NextLocation() [virtual]

Switch to next location in list of URLs.

At last location switch to first if number of allowed retries is not exceeded. Returns false if no retries left.

Implements Arc::DataPoint (p. 113).

6.76.2.7 virtual void Arc::DataPointIndex::Passive (bool v) [virtual]

Request passive transfers for FTP-like protocols.

Parameters

true to request.

Implements Arc::DataPoint (p. 113).

6.76.2.8 virtual bool Arc::DataPointIndex::ProvidesMeta() [virtual]

If endpoint can provide at least some meta information directly.

Implements Arc::DataPoint (p. 114).

6.76.2.9 virtual void Arc::DataPointIndex::Range (unsigned long long int start = 0, unsigned long long int end = 0) [virtual]

Set range of bytes to retrieve.

Default values correspond to whole file.

Implements Arc::DataPoint (p. 114).

$6.76.2.10 \quad virtual\ void\ Arc:: DataPointIndex:: ReadOutOfOrder\ (\ bool\ v\) \quad [\texttt{virtual}]$

Allow/disallow **DataPoint** (p. 108) to produce scattered data during reading* operation.

Parameters

```
v true if allowed (default is false).
```

Implements Arc::DataPoint (p. 114).

6.76.2.11 virtual bool Arc::DataPointIndex::Registered () const [virtual]

Check if file is registered in Indexing Service (p. 282).

Proper value is obtainable only after Resolve.

Implements Arc::DataPoint (p. 114).

6.76.2.12 virtual void Arc::DataPointIndex::SetAdditionalChecks (bool v) [virtual]

Allow/disallow additional checks.

Check for existance of remote file (and probably other checks too) before initiating reading and writing operations.

Parameters

```
v true if allowed (default is true).
```

Implements Arc::DataPoint (p. 115).

6.76.2.13 virtual void Arc::DataPointIndex::SetMeta (const DataPoint & p) [virtual]

Copy meta information from another object.

Already defined values are not overwritten.

Parameters

p object from which information is taken.

Reimplemented from Arc::DataPoint (p. 115).

6.76.2.14 virtual void Arc::DataPointIndex::SetSecure (bool v) [virtual]

Allow/disallow heavy security during data transfer.

Parameters

v true if allowed (default depends on protocol).

Implements Arc::DataPoint (p. 115).

6.76.2.15 virtual void Arc::DataPointIndex::SortLocations (const std::string & pattern, const URLMap & url_map) [virtual]

Sort locations according to the specified pattern.

Parameters

pattern a set of strings, separated by |, to match against.

Implements Arc::DataPoint (p. 115).

6.76.2.16 virtual DataStatus Arc::DataPointIndex::StartReading (DataBuffer & buffer) [virtual]

Start reading data from URL (p. 320).

Separate thread to transfer data will be created. No other operation can be performed while reading is in progress.

Parameters

buffer operation will use this buffer to put information into. Should not be destroyed before stop_reading was called and returned.

Implements Arc::DataPoint (p. 115).

6.76.2.17 virtual DataStatus Arc::DataPointIndex::StartWriting (DataBuffer & buffer, DataCallback * space_cb = NULL) [virtual]

Start writing data to URL (p. 320).

Separate thread to transfer data will be created. No other operation can be performed while writing is in progress.

Parameters

buffer operation will use this buffer to get information from. Should not be destroyed before stop_writing was called and returned.

space_cb callback which is called if there is not enough space to store data. May not implemented for all protocols.

Implements Arc::DataPoint (p. 116).

6.76.2.18 virtual DataStatus Arc::DataPointIndex::StopReading() [virtual]

Stop reading.

Must be called after corresponding start_reading method, either after all data is transferred or to cancel transfer. Use buffer object to find out when data is transferred. Must return failure if any happened during transfer.

Implements Arc::DataPoint (p. 116).

6.76.2.19 virtual DataStatus Arc::DataPointIndex::StopWriting() [virtual]

Stop writing.

Must be called after corresponding start_writing method, either after all data is transferred or to cancel transfer. Use buffer object to find out when data is transferred. Must return failure if any happened during transfer.

Implements Arc::DataPoint (p. 116).

6.76.2.20 virtual bool Arc::DataPointIndex::WriteOutOfOrder() [virtual]

Returns true if URL (p. 320) can accept scattered data for *writing* operation.


Implements Arc::DataPoint (p. 117).

The documentation for this class was generated from the following file:

• DataPointIndex.h

6.77 Arc::DataPointLoader Class Reference

Inheritance diagram for Arc::DataPointLoader:




The documentation for this class was generated from the following file:

• DataPoint.h

6.78 Arc::DataPointPluginArgument Class Reference

Inheritance diagram for Arc::DataPointPluginArgument:



The documentation for this class was generated from the following file:

• DataPoint.h

6.79 Arc::DataSourceType Class Reference

The documentation for this class was generated from the following file:

· JobDescription.h

6.80 Arc::DataSpeed Class Reference

Keeps track of average and instantaneous transfer speed.

#include <DataSpeed.h>

Public Member Functions

- **DataSpeed** (time_t base=DATASPEED_AVERAGING_PERIOD)
- DataSpeed (unsigned long long int min_speed, time_t min_speed_time, unsigned long long int min_average_speed, time_t max_inactivity_time, time_t base=DATASPEED_AVERAGING_-PERIOD)
- ∼**DataSpeed** (void)
- void **verbose** (bool val)
- void **verbose** (const std::string &prefix)
- bool **verbose** (void)
- void **set_min_speed** (unsigned long long int min_speed, time_t min_speed_time)
- void set_min_average_speed (unsigned long long int min_average_speed)
- void **set_max_inactivity_time** (time_t max_inactivity_time)
- time_t get_max_inactivity_time ()
- void **set_base** (time_t base_=DATASPEED_AVERAGING_PERIOD)
- void **set_max_data** (unsigned long long int max=0)
- void **set_progress_indicator** (show_progress_t func=NULL)
- void reset (void)
- bool **transfer** (unsigned long long int n=0)
- void hold (bool disable)
- bool min_speed_failure ()
- bool min_average_speed_failure ()
- bool max_inactivity_time_failure ()
- unsigned long long int transfered_size (void)

6.80.1 Detailed Description

Keeps track of average and instantaneous transfer speed. Also detects data transfer inactivity and other transfer timeouts.

6.80.2 Constructor & Destructor Documentation

6.80.2.1 Arc::DataSpeed::DataSpeed (time t base = DATASPEED AVERAGING PERIOD)

Constructor

Parameters

base time period used to average values (default 1 minute).

6.80.2.2 Arc::DataSpeed::DataSpeed (unsigned long long int min_speed, time_t min_speed_time, unsigned long long int min_average_speed, time_t max_inactivity_time, time_t base = DATASPEED_AVERAGING_PERIOD)

Constructor

Parameters

base time period used to average values (default 1 minute).

min_speed minimal allowed speed (Butes per second). If speed drops and holds below threshold for min_speed_time_ seconds error is triggered.

min_speed_time

min_average_speed_ minimal average speed (Bytes per second) to trigger error. Averaged over whole current transfer time.

max_inactivity_time - if no data is passing for specified amount of time (seconds), error is triggered.

6.80.3 Member Function Documentation

6.80.3.1 void Arc::DataSpeed::hold (bool disable)

Turn off speed control.

Parameters

disable true to turn off.

6.80.3.2 void Arc::DataSpeed::set_base (time_t base_ = DATASPEED_AVERAGING_PERIOD)

Set averaging time period.

Parameters

base time period used to average values (default 1 minute).

6.80.3.3 void Arc::DataSpeed::set_max_data (unsigned long long int max = 0)

Set amount of data to be transfered. Used in verbose messages.

Parameters

max amount of data in bytes.

6.80.3.4 void Arc::DataSpeed::set_max_inactivity_time (time_t max_inactivity_time)

Set inactivity tiemout.

Parameters

max_inactivity_time - if no data is passing for specified amount of time (seconds), error is triggered.

6.80.3.5 void Arc::DataSpeed::set_min_average_speed (unsigned long long int min_average_speed)

Set minmal avaerage speed.

Parameters

min_average_speed_ minimal average speed (Bytes per second) to trigger error. Averaged over whole current transfer time.

6.80.3.6 void Arc::DataSpeed::set_min_speed (unsigned long long int min_speed, time_t min_speed_time)

Set minimal allowed speed.

Parameters

```
min_speed minimal allowed speed (Butes per second). If speed drops and holds below threshold for min_speed_time_ seconds error is triggered.min_speed_time
```

6.80.3.7 void Arc::DataSpeed::set_progress_indicator (show_progress_t func = NULL)

Specify which external function will print verbose messages. If not specified internal one is used.

Parameters

pointer to function which prints information.

6.80.3.8 bool Arc::DataSpeed::transfer (unsigned long long int n = 0)

Inform object, about amount of data has been transfered. All errors are triggered by this method. To make them work application must call this method periodically even with zero value.

Parameters

n amount of data transfered (bytes).

6.80.3.9 void Arc::DataSpeed::verbose (bool val)

Activate printing information about current time speeds, amount of transfered data.

6.80.3.10 void Arc::DataSpeed::verbose (const std::string & prefix)

Print information about current speed and amout of data.

Parameters

'prefix' add this string at the beginning of every string.

The documentation for this class was generated from the following file:

· DataSpeed.h

6.81 Arc::DataStagingType Class Reference

The documentation for this class was generated from the following file:

· JobDescription.h

6.82 Arc::DataStatus Class Reference

```
#include <DataStatus.h>
```

Public Types

```
    enum DataStatusType {
    Success = 0, ReadAcquireError = 1, WriteAcquireError = 2, ReadResolveError = 3,
    WriteResolveError = 4, ReadStartError = 5, WriteStartError = 6, ReadError = 7,
    WriteError = 8, TransferError = 9, ReadStopError = 10, WriteStopError = 11,
    PreRegisterError = 12, PostRegisterError = 13, UnregisterError = 14, CacheError = 15,
    CredentialsExpiredError = 16, DeleteError = 17, NoLocationError = 18, LocationAlreadyExistsError = 19,
    NotSupportedForDirectDataPointsError = 20, UnimplementedError = 21, IsReadingError = 22, IsWritingError = 23,
    CheckError = 24, ListError = 25, NotInitializedError = 26, SystemError = 27,
    StageError = 28, InconsistentMetadataError = 29, UnknownError = 30 }
```

6.82.1 Detailed Description

A class to be used for return types of all major data handling methods. It describes the outcome of the method.

6.82.2 Member Enumeration Documentation

6.82.2.1 enum Arc::DataStatus::DataStatusType

Enumerator:

```
Success Operation completed successfully.

ReadAcquireError Source is bad URL (p. 320) or can't be used due to some reason.

WriteAcquireError Destination is bad URL (p. 320) or can't be used due to some reason.

ReadResolveError Resolving of index service URL (p. 320) for source failed.

WriteResolveError Resolving of index service URL (p. 320) for destination failed.

ReadStartError Can't read from source.

WriteStartError Can't write to destination.

ReadError Failed while reading from source.

WriteError Failed while writing to destination.
```

TransferError Failed while transfering data (mostly timeout).

ReadStopError Failed while finishing reading from source.

WriteStopError Failed while finishing writing to destination.

PreRegisterError First stage of registration of index service **URL** (p. 320) failed. **PostRegisterError** Last stage of registration of index service **URL** (p. 320) failed.

UnregisterError Unregistration of index service URL (p. 320) failed.

CacheError Error in caching procedure.

Credentials Expired Error due to provided credentials are expired.

DeleteError Error deleting location or URL (p. 320).

NoLocationError No valid location available.

LocationAlreadyExistsError No valid location available.

NotSupportedForDirectDataPointsError Operation has no sense for this kind of URL (p. 320).

UnimplementedError Feature is unimplemented.

IsReadingError DataPoint (p. 108) is already reading.

IsWritingError DataPoint (p. 108) is already writing.

CheckError Access check failed.

ListError File listing failed.

NotInitializedError Object initialization failed.

SystemError Error in OS.

StageError Staging error.

InconsistentMetadataError Inconsistent metadata.

UnknownError Undefined.

The documentation for this class was generated from the following file:

· DataStatus.h


6.83 Arc::DataTargetType Class Reference

The documentation for this class was generated from the following file:

· JobDescription.h

6.84 Arc::DataType Class Reference

Inheritance diagram for Arc::DataType:




The documentation for this class was generated from the following file:

· JobDescription.h

6.85 ArcSec::DateAttribute Class Reference

Inheritance diagram for ArcSec::DateAttribute:



Public Member Functions

- virtual bool equal (AttributeValue *other, bool check_id=true)
- virtual std::string encode ()
- virtual std::string **getType** ()
- virtual std::string getId ()

6.85.1 Member Function Documentation

6.85.1.1 virtual std::string ArcSec::DateAttribute::encode() [virtual]

encode the value in a string format

Implements ArcSec::AttributeValue (p. 57).

6.85.1.2 virtual bool ArcSec::DateAttribute::equal (AttributeValue * value, bool check_id = true) [virtual]

Evluate whether "this" equale to the parameter value

Implements ArcSec::AttributeValue (p. 58).

6.85.1.3 virtual std::string ArcSec::DateAttribute::getId() [inline, virtual]

Get the AttributeId of the <Attribute>

Implements ArcSec::AttributeValue (p. 58).

6.85.1.4 virtual std::string ArcSec::DateAttribute::getType() [inline, virtual]

Get the DataType of the <Attribute>

Implements ArcSec::AttributeValue (p. 58).


The documentation for this class was generated from the following file:

• DateTimeAttribute.h

6.86 ArcSec::DateTimeAttribute Class Reference

#include <DateTimeAttribute.h>

Inheritance diagram for ArcSec::DateTimeAttribute:



Public Member Functions

- virtual bool equal (AttributeValue *other, bool check_id=true)
- virtual std::string encode ()
- virtual std::string **getType** ()
- virtual std::string getId ()

6.86.1 Detailed Description

Format: YYYYMMDDHHMMSSZ Day Month DD HH:MM:SS YYYY YYYY-MM-DD HH:MM:SS YYYY-MM-DDTHH:MM:SS+HH:MM YYYY-MM-DDTHH:MM:SSZ

6.86.2 Member Function Documentation

6.86.2.1 virtual std::string ArcSec::DateTimeAttribute::encode() [virtual]

encode the value in a string format

Implements ArcSec::AttributeValue (p. 57).

6.86.2.2 virtual bool ArcSec::DateTimeAttribute::equal (AttributeValue * value, bool check_id = true) [virtual]

Evluate whether "this" equale to the parameter value

Implements ArcSec::AttributeValue (p. 58).

6.86.2.3 virtual std::string ArcSec::DateTimeAttribute::getId() [inline, virtual]

Get the AttributeId of the <Attribute>

Implements ArcSec::AttributeValue (p. 58).

6.86.2.4 virtual std::string ArcSec::DateTimeAttribute::getType() [inline, virtual]

Get the DataType of the <Attribute>

Implements ArcSec::AttributeValue (p. 58).

The documentation for this class was generated from the following file:

• DateTimeAttribute.h

6.87 Arc::DBranch Class Reference


The documentation for this class was generated from the following file:

• DBranch.h

6.88 Arc::DelegationConsumer Class Reference

#include <DelegationInterface.h>

Inheritance diagram for Arc::DelegationConsumer:



Public Member Functions

- **DelegationConsumer** (void)
- **DelegationConsumer** (const std::string &content)
- const std::string & ID (void)
- bool **Backup** (std::string &content)
- bool **Restore** (const std::string &content)
- bool Request (std::string &content)
- bool Acquire (std::string &content)
- bool Acquire (std::string &content, std::string &identity)

Protected Member Functions

- bool Generate (void)
- void LogError (void)

6.88.1 Detailed Description

A consumer of delegated X509 credentials. During delegation procedure this class acquires delegated credentials aka proxy - certificate, private key and chain of previous certificates. Delegation procedure consists of calling **Request()** (p. 136) method for generating certificate request followed by call to **Acquire()** (p. 136) method for making complete credentials from certificate chain.

6.88.2 Constructor & Destructor Documentation

6.88.2.1 Arc::DelegationConsumer::DelegationConsumer (void)

Creates object with new private key

6.88.2.2 Arc::DelegationConsumer::DelegationConsumer (const std::string & content)

Creates object with provided private key

6.88.3 Member Function Documentation

6.88.3.1 bool Arc::DelegationConsumer::Acquire (std::string & content)

Ads private key into certificates chain in 'content' On exit content contains complete delegated credentials.

6.88.3.2 bool Arc::DelegationConsumer::Acquire (std::string & content, std::string & identity)

Includes the functionality in Acquire(content); pluse extracting the credential identity

6.88.3.3 bool Arc::DelegationConsumer::Backup (std::string & content)

Stores content of this object into a string

6.88.3.4 bool Arc::DelegationConsumer::Generate (void) [protected]

Private key

6.88.3.5 const std::string& Arc::DelegationConsumer::ID (void)

Return identifier of this object - not implemented

6.88.3.6 void Arc::DelegationConsumer::LogError(void) [protected]

Creates private key

6.88.3.7 bool Arc::DelegationConsumer::Request (std::string & content)

Make X509 certificate request from internal private key

6.88.3.8 bool Arc::DelegationConsumer::Restore (const std::string & content)

Restores content of object from string


The documentation for this class was generated from the following file:

· DelegationInterface.h

6.89 Arc::DelegationConsumerSOAP Class Reference

#include <DelegationInterface.h>

Inheritance diagram for Arc::DelegationConsumerSOAP:



Public Member Functions

- DelegationConsumerSOAP (void)
- DelegationConsumerSOAP (const std::string &content)
- bool **DelegateCredentialsInit** (const std::string &id, const SOAPEnvelope &in, SOAPEnvelope &out)
- bool UpdateCredentials (std::string &credentials, const SOAPEnvelope &in, SOAPEnvelope &out)
- bool **UpdateCredentials** (std::string &credentials, std::string &identity, const SOAPEnvelope &in, SOAPEnvelope &out)
- bool **DelegatedToken** (std::string &credentials, **XMLNode** token)

6.89.1 Detailed Description

This class extends **DelegationConsumer** (p. 135) to support SOAP message exchange. Implements WS interface http://www.nordugrid.org/schemas/delegation described in delegation.wsdl.

6.89.2 Constructor & Destructor Documentation

6.89.2.1 Arc::DelegationConsumerSOAP::DelegationConsumerSOAP (void)

Creates object with new private key

6.89.2.2 Arc::DelegationConsumerSOAP::DelegationConsumerSOAP (const std::string & content)

Creates object with specified private key

6.89.3 Member Function Documentation

6.89.3.1 bool Arc::DelegationConsumerSOAP::DelegateCredentialsInit (const std::string & id, const SOAPEnvelope & in, SOAPEnvelope & out)

Process SOAP message which starts delagation. Generated message in 'out' is meant to be sent back to DelagationProviderSOAP. Argument 'id' contains identifier of procedure and is used only to produce SOAP message.

6.89.3.2 bool Arc::DelegationConsumerSOAP::DelegatedToken (std::string & credentials, XMLNode token)

Similar to UpdateCredentials but takes only DelegatedToken XML element

6.89.3.3 bool Arc::DelegationConsumerSOAP::UpdateCredentials (std::string & credentials, std::string & identity, const SOAPEnvelope & in, SOAPEnvelope & out)

Includes the functionality in above UpdateCredentials method; plus extracting the credential identity

6.89.3.4 bool Arc::DelegationConsumerSOAP::UpdateCredentials (std::string & credentials, const SOAPEnvelope & in, SOAPEnvelope & out)

Accepts delegated credentials. Process 'in' SOAP message and stores full proxy credentials in 'credentials'. 'out' message is generated for sending to DelagationProviderSOAP.

The documentation for this class was generated from the following file:

· DelegationInterface.h

6.90 Arc::DelegationContainerSOAP Class Reference

#include <DelegationInterface.h>

Public Member Functions

- bool DelegateCredentialsInit (const SOAPEnvelope &in, SOAPEnvelope &out)
- bool UpdateCredentials (std::string &credentials, const SOAPEnvelope &in, SOAPEnvelope &out)
- bool **DelegatedToken** (std::string &credentials, **XMLNode** token)

Protected Attributes

- int max_size_
- int max_duration_
- int max_usage_
- bool context_lock_
- bool restricted

6.90.1 Detailed Description

Manages multiple delegated credentials. Delegation consumers are created automatically with Delegate-CredentialsInit method up to max_size_ and assigned unique identifier. It's methods are similar to those of **DelegationConsumerSOAP** (p. 137) with identifier included in SOAP message used to route execution to one of managed **DelegationConsumerSOAP** (p. 137) instances.

6.90.2 Member Function Documentation

6.90.2.1 bool Arc::DelegationContainerSOAP::DelegateCredentialsInit (const SOAPEnvelope & in, SOAPEnvelope & out)

See DelegationConsumerSOAP::DelegateCredentialsInit (p. 137)

6.90.2.2 bool Arc::DelegationContainerSOAP::DelegatedToken (std::string & credentials, XMLNode token)

See DelegationConsumerSOAP::DelegatedToken (p. 138)

6.90.2.3 bool Arc::DelegationContainerSOAP::UpdateCredentials (std::string & credentials, const SOAPEnvelope & in, SOAPEnvelope & out)

See DelegationConsumerSOAP::UpdateCredentials (p. 138)

6.90.3 Field Documentation

6.90.3.1 bool Arc::DelegationContainerSOAP::context_lock_ [protected]

If true delegation consumer is deleted when connection context is destroyed

6.90.3.2 int Arc::DelegationContainerSOAP::max_duration_ [protected]

Lifetime of unused delegation consumer

6.90.3.3 int Arc::DelegationContainerSOAP::max size [protected]

Max. number of delegation consumers

6.90.3.4 int Arc::DelegationContainerSOAP::max_usage_ [protected]

Max. times same delegation consumer may accept credentials

6.90.3.5 bool Arc::DelegationContainerSOAP::restricted_ [protected]

If true all delegation phases must be performed by same identity


The documentation for this class was generated from the following file:

• DelegationInterface.h

6.91 Arc::DelegationProvider Class Reference

#include <DelegationInterface.h>

Inheritance diagram for Arc::DelegationProvider:



Public Member Functions

- **DelegationProvider** (const std::string &credentials)
- **DelegationProvider** (const std::string &cert_file, const std::string &key_file, std::istream *inpwd=NULL)
- std::string **Delegate** (const std::string &request, const DelegationRestrictions &restrictions=DelegationRestrictions())

6.91.1 Detailed Description

A provider of delegated credentials. During delegation procedure this class generates new credential to be used in proxy/delegated credential.

6.91.2 Constructor & Destructor Documentation

6.91.2.1 Arc::DelegationProvider::DelegationProvider (const std::string & credentials)

Creates instance from provided credentials. Credentials are used to sign delegated credentials. Arguments should contain PEM-encoded certificate, private key and optionally certificates chain.

6.91.2.2 Arc::DelegationProvider::DelegationProvider (const std::string & cert_file, const std::string & key_file, std::istream * inpwd = NULL)

Creates instance from provided credentials. Credentials are used to sign delegated credentials. Arguments should contain filesystem path to PEM-encoded certificate and private key. Optionally cert_file may contain certificates chain.

6.91.3 Member Function Documentation

6.91.3.1 std::string Arc::DelegationProvider::Delegate (const std::string & request, const DelegationRestrictions & restrictions = DelegationRestrictions ()

Perform delegation. Takes X509 certificate request and creates proxy credentials excluding private key. Result is then to be fed into **DelegationConsumer::Acquire** (p. 136)


The documentation for this class was generated from the following file:

• DelegationInterface.h

6.92 Arc::DelegationProviderSOAP Class Reference

#include <DelegationInterface.h>

Inheritance diagram for Arc::DelegationProviderSOAP:



Public Member Functions

- **DelegationProviderSOAP** (const std::string &credentials)
- **DelegationProviderSOAP** (const std::string &cert_file, const std::string &key_file, std::istream *inpwd=NULL)
- bool DelegateCredentialsInit (MCCInterface &mcc_interface, MessageContext *context)
- bool DelegateCredentialsInit (MCCInterface &mcc_interface, MessageAttributes *attributes_in, MessageAttributes *attributes_out, MessageContext *context)
- bool **UpdateCredentials** (**MCCInterface** &mcc_interface, **MessageContext** *context, const DelegationRestrictions &restrictions=DelegationRestrictions())
- bool **UpdateCredentials** (**MCCInterface** &mcc_interface, **MessageAttributes** *attributes_in, **MessageAttributes** *attributes_out, **MessageContext** *context, const DelegationRestrictions &restrictions=DelegationRestrictions())
- bool DelegatedToken (XMLNode parent)
- const std::string & ID (void)

6.92.1 Detailed Description

Extension of **DelegationProvider** (p. 139) with SOAP exchange interface. This class is also a temporary container for intermediate information used during delegation procedure.

6.92.2 Constructor & Destructor Documentation

6.92.2.1 Arc::DelegationProviderSOAP::DelegationProviderSOAP (const std::string & credentials)

Creates instance from provided credentials. Credentials are used to sign delegated credentials.

6.92.2.2 Arc::DelegationProviderSOAP::DelegationProviderSOAP (const std::string & cert_file, const std::string & key_file, std::istream * inpwd = NULL)

Creates instance from provided credentials. Credentials are used to sign delegated credentials. Arguments should contain filesystem path to PEM-encoded certificate and private key. Optionally cert_file may contain certificates chain.

6.92.3 Member Function Documentation

6.92.3.1 bool Arc::DelegationProviderSOAP::DelegateCredentialsInit (MCCInterface & mcc_interface, MessageContext * context)

Performs DelegateCredentialsInit SOAP operation. As result request for delegated credentials is received by this instance and stored internally. Call to UpdateCredentials should follow.

6.92.3.2 bool Arc::DelegationProviderSOAP::DelegateCredentialsInit (MCCInterface & mcc_interface, MessageAttributes * attributes_in, MessageAttributes * attributes_out, MessageContext * context)

Extended version of **DelegateCredentialsInit(MCCInterface&,MessageContext***) (p. 142). Additionally takes attributes for request and response message to make fine control on message processing possible.

6.92.3.3 bool Arc::DelegationProviderSOAP::DelegatedToken (XMLNode parent)

Generates DelegatedToken element. Element is created as child of provided XML element and contains structure described in delegation.wsdl.

6.92.3.4 const std::string& Arc::DelegationProviderSOAP::ID (void) [inline]

Returns the identifier by service accepting delegated credentials. This identifier may then be used to refer to credentials stored at service.

6.92.3.5 bool Arc::DelegationProviderSOAP::UpdateCredentials (MCCInterface & mcc_interface, MessageAttributes * attributes_in, MessageAttributes * attributes_out, MessageContext * context, const DelegationRestrictions & restrictions = DelegationRestrictions())

Extended version of UpdateCredentials(MCCInterface&,MessageContext*). Additionally takes attributes for request and response message to make fine control on message processing possible.

6.92.3.6 bool Arc::DelegationProviderSOAP::UpdateCredentials (MCCInterface & mcc_interface, MessageContext * context, const DelegationRestrictions & restrictions = DelegationRestrictions())

Performs UpdateCredentials SOAP operation. This concludes delegation procedure and passes delagated credentials to **DelegationConsumerSOAP** (p. 137) instance.

The documentation for this class was generated from the following file:


· DelegationInterface.h

6.93 ArcSec::DenyOverridesCombiningAlg Class Reference

Implement the "Deny-Overrides" algorithm.

#include <DenyOverridesAlg.h>

Inheritance diagram for ArcSec::DenyOverridesCombiningAlg:



Public Member Functions

- virtual Result combine (EvaluationCtx *ctx, std::list< Policy * > policies)
- virtual const std::string & getalgId (void) const

6.93.1 Detailed Description

Implement the "Deny-Overrides" algorithm. Deny-Overrides, scans the policy set which is given as the parameters of "combine" method, if gets "deny" result from any policy, then stops scanning and gives "deny" as result, otherwise gives "permit".

6.93.2 Member Function Documentation

6.93.2.1 virtual Result ArcSec::DenyOverridesCombiningAlg::combine (EvaluationCtx * ctx, std::list< Policy * > policies) [virtual]

If there is one policy which return negative evaluation result, then omit the other policies and return DECISION_DENY

Parameters

ctx This object contains request information which will be used to evaluated against policy.policlies This is a container which contains policy objects.

Returns

The combined result according to the algorithm.

Implements ArcSec::CombiningAlg (p. 76).

6.93.2.2 virtual const std::string& ArcSec::DenyOverridesCombiningAlg::getalgId (void) const [inline, virtual]

Get the identifier


Implements ArcSec::CombiningAlg (p. 76).

The documentation for this class was generated from the following file:

· DenyOverridesAlg.h

6.94 Arc::DirectoryType Class Reference

Inheritance diagram for Arc::DirectoryType:



The documentation for this class was generated from the following file:

• JobDescription.h


6.95 Arc::DiskSpaceRequirementType Class Reference

The documentation for this class was generated from the following file:

· JobDescription.h

6.96 Arc::DItem Class Reference

Inheritance diagram for Arc::DItem:




The documentation for this class was generated from the following file:

• DBranch.h

6.97 Arc::DItemString Class Reference

Inheritance diagram for Arc::DItemString:




The documentation for this class was generated from the following file:

• DBranch.h

6.98 Arc::DNListHandlerConfig Class Reference

Inheritance diagram for Arc::DNListHandlerConfig:




The documentation for this class was generated from the following file:

· ClientInterface.h

6.99 ArcSec::DurationAttribute Class Reference

#include <DateTimeAttribute.h>

Inheritance diagram for ArcSec::DurationAttribute:



Public Member Functions

- virtual bool equal (AttributeValue *other, bool check_id=true)
- virtual std::string encode ()
- virtual std::string **getType** ()
- virtual std::string getId ()

6.99.1 Detailed Description

Formate: P??Y??M??DT??H??M??S

6.99.2 Member Function Documentation

6.99.2.1 virtual std::string ArcSec::DurationAttribute::encode() [virtual]

encode the value in a string format

Implements ArcSec::AttributeValue (p. 57).

6.99.2.2 virtual bool ArcSec::DurationAttribute::equal (AttributeValue * value, bool check_id = true) [virtual]

Evluate whether "this" equale to the parameter value

Implements ArcSec::AttributeValue (p. 58).

6.99.2.3 virtual std::string ArcSec::DurationAttribute::getId() [inline, virtual]

Get the AttributeId of the <Attribute>

Implements ArcSec::AttributeValue (p. 58).

6.99.2.4 virtual std::string ArcSec::DurationAttribute::getType() [inline, virtual]

Get the DataType of the <Attribute>

Implements ArcSec::AttributeValue (p. 58).

The documentation for this class was generated from the following file:


• DateTimeAttribute.h

6.100 ArcSec::EqualFunction Class Reference

Evaluate whether the two values are equal.

#include <EqualFunction.h>

Inheritance diagram for ArcSec::EqualFunction:



Public Member Functions

- virtual **AttributeValue** * **evaluate** (**AttributeValue** *arg0, **AttributeValue** *arg1, bool check_id=true)
- virtual std::list< AttributeValue * > evaluate (std::list< AttributeValue * > args, bool check_-id=true)

Static Public Member Functions

• static std::string **getFunctionName** (std::string datatype)

6.100.1 Detailed Description

Evaluate whether the two values are equal.

6.100.2 Member Function Documentation

6.100.2.1 virtual AttributeValue* ArcSec::EqualFunction::evaluate (AttributeValue * arg0, AttributeValue * arg1, bool check_id = true) [virtual]

Evaluate two **AttributeValue** (p. 56) objects, and return one **AttributeValue** (p. 56) object Implements **ArcSec::Function** (p. 165).

6.100.2.2 virtual std::list<AttributeValue*> ArcSec::EqualFunction::evaluate (std::list< AttributeValue *> args, bool check_id = true) [virtual]

Evaluate a list of **AttributeValue** (p. 56) objects, and return a list of Attribute objects Implements **ArcSec::Function** (p. 165).

help function to get the FunctionName

The documentation for this class was generated from the following file:

• EqualFunction.h

6.101 ArcSec::EvalResult Struct Reference

Struct to record the xml node and effect, which will be used by **Evaluator** (p. 148) to get the information about which rule/policy(in xmlnode) is satisfied.

#include <Result.h>

6.101.1 Detailed Description

Struct to record the xml node and effect, which will be used by **Evaluator** (p. 148) to get the information about which rule/policy(in xmlnode) is satisfied.

The documentation for this struct was generated from the following file:

• Result.h

6.102 ArcSec::EvaluationCtx Class Reference

EvaluationCtx (p. 147), in charge of storing some context information for.

#include <EvaluationCtx.h>

Public Member Functions

• EvaluationCtx (Request *request)

6.102.1 Detailed Description

EvaluationCtx (p. 147), in charge of storing some context information for.

6.102.2 Constructor & Destructor Documentation

6.102.2.1 ArcSec::EvaluationCtx::EvaluationCtx (Request * request) [inline]

Construct a new EvaluationCtx (p. 147) based on the given request

The documentation for this class was generated from the following file:


· EvaluationCtx.h

6.103 ArcSec::Evaluator Class Reference

Interface for policy evaluation. Execute the policy evaluation, based on the request and policy.

#include <Evaluator.h>

Inheritance diagram for ArcSec::Evaluator:



Public Member Functions

- virtual **Response** * **evaluate** (**Request** *request)=0
- virtual **Response** * **evaluate** (const **Source** &request)=0
- virtual **Response** * **evaluate** (**Request** *request, const **Source** &policy)=0
- virtual **Response** * **evaluate** (const **Source** &request, const **Source** &policy)=0
- virtual **Response** * **evaluate** (**Request** *request, **Policy** *policyobj)=0
- virtual **Response** * **evaluate** (const **Source** &request, **Policy** *policyobj)=0
- virtual AttributeFactory * getAttrFactory ()=0
- virtual **FnFactory** * **getFnFactory** ()=0
- virtual **AlgFactory** * **getAlgFactory** ()=0
- virtual void addPolicy (const Source &policy, const std::string &id="")=0
- virtual void addPolicy (Policy *policy, const std::string &id="")=0
- virtual void **setCombiningAlg** (EvaluatorCombiningAlg alg)=0
- virtual void setCombiningAlg (CombiningAlg *alg=NULL)=0
- virtual const char * **getName** (void) const =0

Protected Member Functions

• virtual **Response** * **evaluate** (**EvaluationCtx** *ctx)=0

6.103.1 Detailed Description

Interface for policy evaluation. Execute the policy evaluation, based on the request and policy.

6.103.2 Member Function Documentation

6.103.2.1 virtual void ArcSec::Evaluator::addPolicy (const Source & policy, const std::string & id = "") [pure virtual]

Add policy from specified source to the evaluator. **Policy** (p. 252) will be marked with id.

6.103.2.2 virtual void ArcSec::Evaluator::addPolicy (Policy * policy, const std::string & id = "") [pure virtual]

Add policy to the evaluator. **Policy** (p. 252) will be marked with id. The policy object is taken over by this instance and will be destroyed in destructor.

6.103.2.3 virtual Response* ArcSec::Evaluator::evaluate (const Source & request, const Source & policy) [pure virtual]

Evaluate the request from specified source against the policy from specified source. In some implementations all of the existing policie inside the evaluator may be destroyed by this method.

6.103.2.4 virtual Response* ArcSec::Evaluator::evaluate (Request * request) [pure virtual]

Evaluates the request by using a **Request** (p. 261) object. Evaluation is done till at least one of policies is satisfied.

6.103.2.5 virtual Response* ArcSec::Evaluator::evaluate (Request * request, Policy * policyobj) [pure virtual]

Evaluate the specified request against the specified policy. In some implementations all of the existing policy inside the evaluator may be destroyed by this method.

6.103.2.6 virtual Response* ArcSec::Evaluator::evaluate (const Source & request) [pure virtual]

Evaluates the request by using a specified source

6.103.2.7 virtual Response* ArcSec::Evaluator::evaluate (Request * request, const Source & policy) [pure virtual]

Evaluate the specified request against the policy from specified source. In some implementations all of the existing policies inside the evaluator may be destroyed by this method.

6.103.2.8 virtual Response* ArcSec::Evaluator::evaluate (const Source & request, Policy * policyobj) [pure virtual]

Evaluate the request from specified source against the specified policy. In some implementations all of the existing policie inside the evaluator may be destroyed by this method.

6.103.2.9 virtual Response* ArcSec::Evaluator::evaluate (EvaluationCtx * ctx) [protected, pure virtual]

Evaluate the request by using the **EvaluationCtx** (p. 147) object (which includes the information about request). The ctx is destroyed inside this method (why?!?!?).

6.103.2.10 virtual AlgFactory* ArcSec::Evaluator::getAlgFactory() [pure virtual]

Get the **AlgFactory** (p. 48) object

6.103.2.11 virtual AttributeFactory* ArcSec::Evaluator::getAttrFactory() [pure virtual]

Get the AttributeFactory (p. 52) object

6.103.2.12 virtual FnFactory* ArcSec::Evaluator::getFnFactory() [pure virtual]

Get the **FnFactory** (p. 164) object

6.103.2.13 virtual const char* ArcSec::Evaluator::getName(void) const [pure virtual]

Get the name of this evaluator

6.103.2.14 virtual void ArcSec::Evaluator::setCombiningAlg (EvaluatorCombiningAlg alg) [pure virtual]

Specifies one of simple combining algorithms. In case of multiple policies their results will be combined using this algorithm.

6.103.2.15 virtual void ArcSec::Evaluator::setCombiningAlg (CombiningAlg * alg = NULL) [pure virtual]

Specifies loadable combining algorithms. In case of multiple policies their results will be combined using this algorithm. To switch to simple algorithm specify NULL argument.

The documentation for this class was generated from the following file:

· Evaluator.h

6.104 ArcSec::EvaluatorContext Class Reference

Context for evaluator. It includes the factories which will be used to create related objects.

#include <Evaluator.h>

Public Member Functions

- operator AttributeFactory * ()
- operator FnFactory * ()
- operator AlgFactory * ()

6.104.1 Detailed Description

Context for evaluator. It includes the factories which will be used to create related objects.

6.104.2 Member Function Documentation

6.104.2.1 ArcSec::EvaluatorContext::operator AlgFactory * () [inline]

Returns associated AlgFactory (p. 48) object

6.104.2.2 ArcSec::EvaluatorContext::operator AttributeFactory * () [inline]

Returns associated AttributeFactory (p. 52) object

6.104.2.3 ArcSec::EvaluatorContext::operator FnFactory * () [inline]

Returns associated FnFactory (p. 164) object

The documentation for this class was generated from the following file:

• Evaluator.h

6.105 ArcSec::EvaluatorLoader Class Reference

EvaluatorLoader (p. 151) is implemented as a helper class for loading different **Evaluator** (p. 148) objects, like ArcEvaluator.

#include <EvaluatorLoader.h>

Public Member Functions

- Evaluator * getEvaluator (const std::string &classname)
- Evaluator * getEvaluator (const Policy *policy)

- Evaluator * getEvaluator (const Request *request)
- Request * getRequest (const std::string &classname, const Source &requestsource)
- Request * getRequest (const Source &requestsource)
- Policy * getPolicy (const std::string &classname, const Source &policysource)
- Policy * getPolicy (const Source &policysource)

6.105.1 Detailed Description

EvaluatorLoader (p. 151) is implemented as a helper class for loading different **Evaluator** (p. 148) objects, like ArcEvaluator. The object loading is based on the configuration information about evaluator, including information for factory class, request, policy and evaluator itself

6.105.2 Member Function Documentation

6.105.2.1 Evaluator* ArcSec::EvaluatorLoader::getEvaluator (const std::string & classname)

Get evaluator object according to the class name

6.105.2.2 Evaluator* ArcSec::EvaluatorLoader::getEvaluator (const Policy * policy)

Get evaluator object suitable for presented policy

6.105.2.3 Evaluator* ArcSec::EvaluatorLoader::getEvaluator(const Request * request)

Get evaluator object suitable for presented request

6.105.2.4 Policy* ArcSec::EvaluatorLoader::getPolicy (const Source & policysource)

Get proper policy object according to the policy source

6.105.2.5 Policy* ArcSec::EvaluatorLoader::getPolicy (const std::string & classname, const Source & policysource)

Get policy object according to the class name, based on the policy source

6.105.2.6 Request* ArcSec::EvaluatorLoader::getRequest (const std::string & classname, const Source & requestsource)

Get request object according to the class name, based on the request source

6.105.2.7 Request* ArcSec::EvaluatorLoader::getRequest (const Source & requestsource)

Get request object according to the request source

The documentation for this class was generated from the following file:

• EvaluatorLoader.h

6.106 Arc::ExecutableType Class Reference

The documentation for this class was generated from the following file:

· JobDescription.h

6.107 Arc::ExecutionTarget Class Reference

ExecutionTarget (p. 153).

#include <ExecutionTarget.h>

Public Member Functions

- ExecutionTarget ()
- ExecutionTarget (const ExecutionTarget &target)
- ExecutionTarget (const long int addrptr)
- ExecutionTarget & operator= (const ExecutionTarget & target)
- Submitter * GetSubmitter (const UserConfig &ucfg) const
- void **Update** (const **JobDescription** &jobdesc)
- void Print (bool longlist) const

Data Fields

- std::string ComputingShareName
- int64 t MaxMainMemory
- int64_t MaxVirtualMemory
- int64_t MaxDiskSpace
- Software OperatingSystem
- $\bullet \ \ std:: list < \textbf{ApplicationEnvironment} > \textbf{ApplicationEnvironments}$

6.107.1 Detailed Description

ExecutionTarget (p. 153). This class describe a target which accept computing jobs. All of the members contained in this class, with a few exceptions, are directly linked to attributes defined in the GLUE Specification v. 2.0 (GFD-R-P.147).

6.107.2 Constructor & Destructor Documentation

6.107.2.1 Arc::ExecutionTarget::ExecutionTarget ()

Create an ExecutionTarget (p. 153).

Default constructor to create an **ExecutionTarget** (p. 153). Takes no arguments.

6.107.2.2 Arc::ExecutionTarget::ExecutionTarget (const ExecutionTarget & target)

Create an **ExecutionTarget** (p. 153).

Copy constructor.

Parameters

target ExecutionTarget (p. 153) to copy.

6.107.2.3 Arc::ExecutionTarget::ExecutionTarget (const long int addrptr)

Create an ExecutionTarget (p. 153).

Copy constructor? Needed from Python?

Parameters

addrptr

6.107.3 Member Function Documentation

6.107.3.1 Submitter* Arc::ExecutionTarget::GetSubmitter (const UserConfig & ucfg) const

Get Submitter (p. 306) to the computing resource represented by the ExecutionTarget (p. 153).

Method which returns a specialized **Submitter** (p. 306) which can be used for submitting jobs to the computing resource represented by the **ExecutionTarget** (p. 153). In order to return the correct specialized **Submitter** (p. 306) the GridFlavour variable must be correctly set.

Parameters

ucfg UserConfig (p. 331) object with paths to user credentials etc.

6.107.3.2 ExecutionTarget & Arc::ExecutionTarget::operator=(const ExecutionTarget & target)

Create an **ExecutionTarget** (p. 153).

Assignment operator

Parameters

target is ExecutionTarget (p. 153) to copy.

6.107.3.3 void Arc::ExecutionTarget::Print (bool longlist) const

Print the **ExecutionTarget** (p. 153) information to std::cout.

Method to print the ExecutionTarget (p. 153) attributes to std::cout

Parameters

longlist is true for long list printing.

6.107.3.4 void Arc::ExecutionTarget::Update (const JobDescription & jobdesc)

Update **ExecutionTarget** (p. 153) after successful job submission.

Method to update the **ExecutionTarget** (p. 153) after a job successfully has been submitted to the computing resource it represents. E.g. if a job is sent to the computing resource and is expected to enter the queue, then the WaitingJobs attribute is incremented with 1.

Parameters

jobdesc contains all information about the job submitted.

6.107.4 Field Documentation

6.107.4.1 std::list<ApplicationEnvironment> Arc::ExecutionTarget::ApplicationEnvironments

ApplicationEnvironments.

The ApplicationEnvironments member is a list of ApplicationEnvironment's, defined in section 6.7 GLUE2.

6.107.4.2 std::string Arc::ExecutionTarget::ComputingShareName

ComputingShareName String 0..1.

Human-readable name. This variable represents the ComputingShare.Name attribute of GLUE2.

6.107.4.3 int64_t Arc::ExecutionTarget::MaxDiskSpace

MaxDiskSpace UInt64 0..1 GB.

The maximum disk space that a job is allowed use in the working; if the limit is hit, then the LRMS MAY kill the job. A negative value specifies that this member is undefined.

6.107.4.4 int64_t Arc::ExecutionTarget::MaxMainMemory

MaxMainMemory UInt64 0..1 MB.

The maximum physical RAM that a job is allowed to use; if the limit is hit, then the LRMS MAY kill the job. A negative value specifies that this member is undefined.

6.107.4.5 int64_t Arc::ExecutionTarget::MaxVirtualMemory

MaxVirtualMemory UInt64 0..1 MB.

The maximum total memory size (RAM plus swap) that a job is allowed to use; if the limit is hit, then the LRMS MAY kill the job. A negative value specifies that this member is undefined.

6.107.4.6 Software Arc::ExecutionTarget::OperatingSystem

OperatingSystem.

The OperatingSystem member is not present in GLUE2 but contains the three GLUE2 attributes OSFamily, OSName and OSVersion.

- OSFamily OSFamily_t 1 * The general family to which the Execution Environment operating * system belongs.
- OSName OSName_t 0..1 * The specific name of the operating sytem
- OSVersion String 0..1 * The version of the operating system, as defined by the vendor.

The documentation for this class was generated from the following file:

• ExecutionTarget.h

6.108 Arc::ExpirationReminder Class Reference

A class intended for internal use within counters.

#include <Counter.h>

Public Member Functions

- bool operator< (const ExpirationReminder &other) const
- Glib::TimeVal getExpiryTime () const
- Counter::IDType getReservationID () const

Friends

class Counter

6.108.1 Detailed Description

A class intended for internal use within counters. This class is used for "reminder objects" that are used for automatic deallocation of self-expiring reservations.

6.108.2 Member Function Documentation

6.108.2.1 Glib::TimeVal Arc::ExpirationReminder::getExpiryTime () const

Returns the expiry time.

This method returns the expiry time of the reservation that this **ExpirationReminder** (p. 156) is associated with.

Returns

The expiry time.

6.108.2.2 Counter::IDType Arc::ExpirationReminder::getReservationID () const

Returns the identification number of the reservation.

This method returns the identification number of the self-expiring reservation that this **ExpirationReminder** (p. 156) is associated with.

Returns

The identification number.

6.108.2.3 bool Arc::ExpirationReminder::operator< (const ExpirationReminder & other) const

Less than operator, compares "soonness".

This is the less than operator for the **ExpirationReminder** (p. 156) class. It compares the priority of such objects with respect to which reservation expires first. It is used when reminder objects are inserted in a priority queue in order to allways place the next reservation to expire at the top.

The documentation for this class was generated from the following file:

· Counter.h

6.109 Arc::FileCache Class Reference

#include <FileCache.h>

Public Member Functions

- FileCache (std::string cache_path, std::string id, uid_t job_uid, gid_t job_gid)
- FileCache (std::vector< std::string > caches, std::string id, uid_t job_uid, gid_t job_gid)
- **FileCache** (std::vector< std::string > caches, std::vector< std::string > remote_caches, std::vector< std::string > draining_caches, std::string id, uid_t job_uid, gid_t job_gid, int cache_max=100, int cache_min=100)
- FileCache ()
- bool **Start** (std::string url, bool &available, bool &is_locked, bool use_remote=true)
- bool **Stop** (std::string url)
- bool **StopAndDelete** (std::string url)
- std::string File (std::string url)
- bool Link (std::string link_path, std::string url)
- bool Copy (std::string dest_path, std::string url, bool executable=false)
- bool Release ()
- bool AddDN (std::string url, std::string DN, Time expiry_time)
- bool CheckDN (std::string url, std::string DN)
- bool CheckCreated (std::string url)
- Time GetCreated (std::string url)
- bool CheckValid (std::string url)
- Time GetValid (std::string url)
- bool **SetValid** (std::string url, **Time** val)
- $\bullet \ operator \ bool \ ()$
- bool operator== (const FileCache &a)

6.109.1 Detailed Description

FileCache (p. 157) provides an interface to all cache operations to be used by external classes. An instance should be created per job, and all files within the job are managed by that instance. When it is decided a file should be downloaded to the cache, **Start()** (p. 161) should be called, so that the cache file can be prepared and locked. When a transfer has finished successfully, **Link()** (p. 160) or **Copy()** (p. 160) should be called to create a hard link to a per-job directory in the cache and then soft link, or copy the file directly to the session directory so it can be accessed from the user's job. **Stop()** (p. 161) must then be called to release any locks on the cache file.

The cache directory(ies) and the optional directory to link to when the soft-links are made are set in the global configuration file. The names of cache files are formed from a hash of the **URL** (p. 320) specified as input to the job. To ease the load on the file system, the cache files are split into subdirectories based on the first two characters in the hash. For example the file with hash 76f11edda169848038efbd9fa3df5693 is stored in 76/f11edda169848038efbd9fa3df5693. A cache filename can be found by passing the **URL** (p. 320) to Find(). For more information on the structure of the cache, see the Grid Manager Administration Guide.

A metadata file with the '.meta' suffix is stored next to each cache file. This contains the **URL** (p. 320) corresponding to the cache file and the expiry time, if it is available. For example lfc://lfc1.ndgf.org//grid/atlas/test/test/1 20081007151045Z

While cache files are downloaded, they are locked by creating a lock file with the '.lock' suffix next to the cache file. Calling **Start()** (p. 161) creates this lock and **Stop()** (p. 161) releases it. All processes calling **Start()** (p. 161) must wait until they successfully obtain the lock before downloading can begin.

6.109.2 Constructor & Destructor Documentation

6.109.2.1 Arc::FileCache::FileCache (std::string cache_path, std::string id, uid_t job_uid, gid_t job_gid)

Create a new FileCache (p. 157) instance.

Parameters

cache_path The format is "cache_dir[link_path]". path is the path to the cache directory and the optional link_path is used to create a link in case the cache directory is visible under a different name during actual usage. When linking from the session dir this path is used instead of cache_path.

id the job id. This is used to create the per-job dir which the job's cache files will be hard linked from job_uid owner of job. The per-job dir will only be readable by this user job_gid owner group of job

6.109.2.2 Arc::FileCache::FileCache (std::vector < std::string > caches, std::string id, uid_t job_uid, gid_t job_gid)

Create a new **FileCache** (p. 157) instance with multiple cache dirs

Parameters

caches a vector of strings describing caches. The format of each string is "cache_dir[link_path]". id the job id. This is used to create the per-job dir which the job's cache files will be hard linked from job_uid owner of job. The per-job dir will only be readable by this user

job_gid owner group of job

6.109.2.3 Arc::FileCache::FileCache (std::vector< std::string > caches, std::vector< std::string > remote_caches, std::vector< std::string > draining_caches, std::string id, uid_t job_uid, gid_t job_gid, int cache_max = 100, int cache_min = 100)

Create a new **FileCache** (p. 157) instance with multiple cache dirs, remote caches and draining cache directories.

Parameters

caches a vector of strings describing caches. The format of each string is "cache_dir[link_path]".

remote_caches Same format as caches. These are the paths to caches which are under the control of other Grid Managers and are read-only for this process.

draining_caches Same format as caches. These are the paths to caches which are to be drained.

id the job id. This is used to create the per-job dir which the job's cache files will be hard linked from

job_uid owner of job. The per-job dir will only be readable by this user

job_gid owner group of job

cache_max maximum used space by cache, as percentage of the file system

cache_min minimum used space by cache, as percentage of the file system

6.109.2.4 Arc::FileCache::FileCache() [inline]

Default constructor. Invalid cache.

6.109.3 Member Function Documentation

6.109.3.1 bool Arc::FileCache::AddDN (std::string url, std::string DN, Time expiry time)

Add the given DN to the list of cached DNs with the given expiry time

Parameters

url the url corresponding to the cache file to which we want to add a cached DN

DN the DN of the user

expiry_time the expiry time of this DN in the DN cache

6.109.3.2 bool Arc::FileCache::CheckCreated (std::string url)

Check if there is an information about creation time. Returns true if the file exists in the cache, since the creation time is the creation time of the cache file.

Parameters

url the url corresponding to the cache file for which we want to know if the creation date exists

6.109.3.3 bool Arc::FileCache::CheckDN (std::string url, std::string DN)

Check if the given DN is cached for authorisation.

Parameters

url the url corresponding to the cache file for which we want to check the cached DN DN the DN of the user

6.109.3.4 bool Arc::FileCache::CheckValid (std::string url)

Check if there is an information about expiry time.

Parameters

url the url corresponding to the cache file for which we want to know if the expiration time exists

6.109.3.5 bool Arc::FileCache::Copy (std::string dest_path, std::string url, bool executable = false)

Copy the cache file corresponding to url to the dest_path

6.109.3.6 std::string Arc::FileCache::File (std::string url)

Returns the full pathname of the file in the cache which corresponds to the given url.

6.109.3.7 Time Arc::FileCache::GetCreated (std::string url)

Get the creation time of a cached file. If the cache file does not exist, 0 is returned.

Parameters

url the url corresponding to the cache file for which we want to know the creation date

6.109.3.8 Time Arc::FileCache::GetValid (std::string url)

Get expiry time of a cached file. If the time is not available, a time equivalent to 0 is returned.

Parameters

url the url corresponding to the cache file for which we want to know the expiry time

6.109.3.9 bool Arc::FileCache::Link (std::string link_path, std::string url)

Create a hard-link to the per-job dir from the cache dir, and then a soft-link from here to the session directory. This is effectively 'claiming' the file for the job, so even if the original cache file is deleted, eg by some external process, the hard link still exists until it is explicitly released by calling **Release()** (p. 161).

If cache_link_path is set to "." then files will be copied directly to the session directory rather than via the hard link.

Parameters

```
link_path path to the session dir for soft-link or new fileurl url of file to link to or copy
```

6.109.3.10 Arc::FileCache::operator bool (void) [inline]

Returns true if object is useable.

6.109.3.11 bool Arc::FileCache::operator== (const FileCache & a)

Return true if all attributes are equal

```
6.109.3.12 bool Arc::FileCache::Release ( )
```

Release claims on input files for the job specified by id. For each cache directory the per-job directory with the hard-links will be deleted.

6.109.3.13 bool Arc::FileCache::SetValid (std::string url, Time val)

Set expiry time.

Parameters

```
url the url corresponding to the cache file for which we want to set the expiry timeval expiry time
```

6.109.3.14 bool Arc::FileCache::Start (std::string url, bool & available, bool & is_locked, bool use_remote = true)

Prepare cache for downloading file, and lock the cached file. On success returns true. If there is another process downloading the same url, false is returned and is_locked is set to true. In this case the client should wait and retry later. If the lock has expired this process will take over the lock and the method will return as if no lock was present, ie available and is_locked are false.

Parameters

```
url url that is being downloaded
available true on exit if the file is already in cache
is_locked true on exit if the file is already locked, ie cannot be used by this process
remote_caches Same format as caches. These are the paths to caches which are under the control of other Grid Managers and are read-only for this process.
```

6.109.3.15 bool Arc::FileCache::Stop (std::string url)

This method (or stopAndDelete) must be called after file was downloaded or download failed, to release the lock on the cache file. **Stop()** (p. 161) does not delete the cache file. It returns false if the lock file does not exist, or another pid was found inside the lock file (this means another process took over the lock so this process must go back to **Start()** (p. 161)), or if it fails to delete the lock file.

Parameters

url the url of the file that was downloaded

6.109.3.16 bool Arc::FileCache::StopAndDelete (std::string url)

Release the cache file and delete it, because for example a failed download left an incomplete copy, or it has expired. This method also deletes the meta file which contains the url corresponding to the cache file. The logic of the return value is the same as **Stop()** (p. 161).

Parameters

url the url corresponding to the cache file that has to be released and deleted

The documentation for this class was generated from the following file:

· FileCache.h

6.110 FileCacheHash Class Reference

#include <FileCacheHash.h>

Static Public Member Functions

- static std::string getHash (std::string url)
- static int maxLength ()

6.110.1 Detailed Description

FileCacheHash (p. 162) provides methods to make hashes from strings. Currently the md5 hash from the openssl library is used.

6.110.2 Member Function Documentation

6.110.2.1 static std::string FileCacheHash::getHash (std::string url) [static]

Return a hash of the given URL, according to the current hash scheme.

6.110.2.2 static int FileCacheHash::maxLength() [inline, static]

Return the maximum length of a hash string.

The documentation for this class was generated from the following file:

• FileCacheHash.h

6.111 Arc::FileInfo Class Reference

FileInfo (p. 163) stores information about files (metadata).

#include <FileInfo.h>

6.111.1 Detailed Description

FileInfo (p. 163) stores information about files (metadata).

The documentation for this class was generated from the following file:

• FileInfo.h

6.112 Arc::FileLock Class Reference

A general file locking class.

#include <FileLock.h>

Public Member Functions

- FileLock (const std::string &filename)
- ∼FileLock ()
- $\bullet \ operator \ bool \ ()$
- bool operator! ()

6.112.1 Detailed Description


A general file locking class.

The documentation for this class was generated from the following file:

• FileLock.h

6.113 Arc::FileType Class Reference

Inheritance diagram for Arc::FileType:



The documentation for this class was generated from the following file:

· JobDescription.h

6.114 Arc::FinderLoader Class Reference

The documentation for this class was generated from the following file:


• FinderLoader.h

6.115 ArcSec::FnFactory Class Reference

Interface for function factory class.

#include <FnFactory.h>

Inheritance diagram for ArcSec::FnFactory:



Public Member Functions

• virtual **Function** * **createFn** (const std::string &type)=0

6.115.1 Detailed Description

Interface for function factory class. **FnFactory** (p. 164) is in charge of creating **Function** (p. 165) object according to the algorithm type given as argument of method createFn. This class can be inherited for implementing a factory class which can create some specific **Function** (p. 165) objects.

6.115.2 Member Function Documentation

6.115.2.1 virtual Function* ArcSec::FnFactory::createFn (const std::string & type) [pure virtual]

creat algorithm object based on the type algorithm type

Parameters

type The type of **Function** (p. 165)

Returns

The object of **Function** (p. 165)

The documentation for this class was generated from the following file:


· FnFactory.h

6.116 ArcSec::Function Class Reference

Interface for function, which is in charge of evaluating two AttributeValue (p. 56).

#include <Function.h>

Inheritance diagram for ArcSec::Function:



Public Member Functions

- virtual **AttributeValue** * **evaluate** (**AttributeValue** *arg0, **AttributeValue** *arg1, bool check_id=true)=0
- virtual std::list< **AttributeValue** * > **evaluate** (std::list< **AttributeValue** * > args, bool check_id=true)=0

6.116.1 Detailed Description

Interface for function, which is in charge of evaluating two **AttributeValue** (p. 56).

6.116.2 Member Function Documentation

6.116.2.1 virtual AttributeValue* ArcSec::Function::evaluate (AttributeValue * arg0, AttributeValue * arg1, bool check_id = true) [pure virtual]

Evaluate two AttributeValue (p. 56) objects, and return one AttributeValue (p. 56) object

Implemented in ArcSec::EqualFunction (p. 147), ArcSec::InRangeFunction (p. 177), and ArcSec::MatchFunction (p. 199).

6.116.2.2 virtual std::list<AttributeValue*> ArcSec::Function::evaluate (std::list< AttributeValue *> args, bool check_id = true) [pure virtual]

Evaluate a list of Attribute Value (p. 56) objects, and return a list of Attribute objects


Implemented in ArcSec::EqualFunction (p. 147), ArcSec::InRangeFunction (p. 178), and ArcSec::MatchFunction (p. 200).

The documentation for this class was generated from the following file:

• Function.h

6.117 ArcSec::GenericAttribute Class Reference

Inheritance diagram for ArcSec::GenericAttribute:



Public Member Functions

- virtual bool equal (AttributeValue *other, bool check_id=true)
- virtual std::string encode ()
- virtual std::string getType ()
- virtual std::string getId ()

6.117.1 Member Function Documentation

6.117.1.1 virtual std::string ArcSec::GenericAttribute::encode() [inline, virtual]

encode the value in a string format

Implements ArcSec::AttributeValue (p. 57).

6.117.1.2 virtual bool ArcSec::GenericAttribute::equal (AttributeValue * value, bool check_id = true) [virtual]

Evluate whether "this" equale to the parameter value

Implements ArcSec::AttributeValue (p. 58).

6.117.1.3 virtual std::string ArcSec::GenericAttribute::getId() [inline, virtual]

Get the AttributeId of the <Attribute>

Implements ArcSec::AttributeValue (p. 58).

6.117.1.4 virtual std::string ArcSec::GenericAttribute::getType() [inline, virtual]

Get the DataType of the <Attribute>

Implements ArcSec::AttributeValue (p. 58).

The documentation for this class was generated from the following file:

· GenericAttribute.h

6.118 Arc::GlobusResult Class Reference

The documentation for this class was generated from the following file:

• GlobusErrorUtils.h


6.119 Arc::GSSCredential Class Reference

The documentation for this class was generated from the following file:

· GSSCredential.h

6.120 Arc::HakaClient Class Reference

Inheritance diagram for Arc::HakaClient:



Protected Member Functions

- MCC_Status processIdPLogin (const std::string username, const std::string password)
- MCC Status processConsent ()
- MCC_Status processIdP2Confusa ()

6.120.1 Member Function Documentation

6.120.1.1 MCC_Status Arc::HakaClient::processConsent() [protected, virtual]

If the IdP has a consent module and the user has not saved her consent, this method will ask the user for consent to transmission of her data to Confusa

Implements Arc::SAML2SSOHTTPClient (p. 274).

6.120.1.2 MCC_Status Arc::HakaClient::processIdP2Confusa() [protected, virtual]

Redirects the user back from identity provider to the Confusa SP

Implements Arc::SAML2SSOHTTPClient (p. 274).

6.120.1.3 MCC_Status Arc::HakaClient::processIdPLogin (const std::string *username*, const std::string *password*) [protected, virtual]

Actual identity provider parsers for next three methods implemented in subdirectory idp/

Parse identity provider login page and submit username and password in the previsioned way

Implements Arc::SAML2SSOHTTPClient (p. 274).

The documentation for this class was generated from the following file:

• HakaClient.h

6.121 Arc::HTTPClientInfo Struct Reference

The documentation for this struct was generated from the following file:

· ClientInterface.h

6.122 Arc::InfoCache Class Reference

Stores XML document in filesystem split into parts.

#include <InfoCache.h>

Public Member Functions

• InfoCache (const Config &cfg, const std::string &service_id)

6.122.1 Detailed Description

Stores XML document in filesystem split into parts.

6.122.2 Constructor & Destructor Documentation

6.122.2.1 Arc::InfoCache::InfoCache (const Config & cfg, const std::string & service_id)

Creates object according to configuration (see InfoCacheConfig.xsd).


XML configuration is passed in cfg. Argument service_id is used to distiguish between various documents stored under same path - corresponding files will be stored in subdirectory with service_id name.

The documentation for this class was generated from the following file:

• InfoCache.h

6.123 Arc::InfoCacheInterface Class Reference

Inheritance diagram for Arc::InfoCacheInterface:



Protected Member Functions

• virtual void **Get** (const std::list< std::string > &path, **XMLNodeContainer** &result)

6.123.1 Member Function Documentation

6.123.1.1 virtual void Arc::InfoCacheInterface::Get (const std::list< std::string > & path, XMLNodeContainer & result) [protected, virtual]

This method is called by this object's Process method. Real implementation of this class should return (sub)tree of XML document. This method may be called multiple times per single Process call. Here is a set on XML element names specifying how to reach requested node(s).

Reimplemented from Arc::InformationInterface (p. 175).

The documentation for this class was generated from the following file:

• InfoCache.h

6.124 Arc::InfoFilter Class Reference

Filters information document according to identity of requestor.

#include <InfoFilter.h>

Public Member Functions

- InfoFilter (MessageAuth &id)
- bool Filter (XMLNode doc) const
- bool Filter (XMLNode doc, const InfoFilterPolicies &policies, const NS &ns) const

6.124.1 Detailed Description

Filters information document according to identity of requestor. Identity is compared to policies stored inside information document and external ones. Parts of document which do not pass policy evaluation are removed.

6.124.2 Constructor & Destructor Documentation

6.124.2.1 Arc::InfoFilter::InfoFilter (MessageAuth & id)

Creates object and associates identity.

Associated identity is not copied, hence passed argument must not be destroyed while this method is used.

6.124.3 Member Function Documentation

6.124.3.1 bool Arc::InfoFilter::Filter (XMLNode doc) const

Filter information document according to internal policies.

In provided document all policies and nodes which have their policies evaluated to negative result are removed.

6.124.3.2 bool Arc::InfoFilter::Filter (XMLNode *doc*, const InfoFilterPolicies & *policies*, const NS & *ns*) const

Filter information document according to internal and external policies.

In provided document all policies and nodes which have their policies evaluated to negative result are removed. External policies are provided in policies argument. First element of every pair is XPath defining to which XML node policy must be applied. Second element is policy itself. Argument ns defines XML namespaces for XPath evaluation.

The documentation for this class was generated from the following file:

· InfoFilter.h

6.125 Arc::InfoRegister Class Reference

Registration to ISIS interface.

#include <InfoRegister.h>

6.125.1 Detailed Description

Registration to ISIS interface. This class represents service registering to Information Indexing **Service** (p. 282). It does not perform registration itself. It only collects configuration information. Configuration is as described in InfoRegisterConfig.xsd for element InfoRegistration.

The documentation for this class was generated from the following file:

• InfoRegister.h

6.126 Arc::InfoRegisterContainer Class Reference

#include <InfoRegister.h>

Public Member Functions

- InfoRegistrar * addRegistrar (XMLNode doc)
- void addService (InfoRegister *reg, const std::list< std::string > &ids, XMLNode cfg=XMLNode())
- void removeService (InfoRegister *reg)

6.126.1 Detailed Description

Singleton class for scanning configuration and storing refernces to registration elements.

6.126.2 Member Function Documentation

6.126.2.1 InfoRegistrar* Arc::InfoRegisterContainer::addRegistrar (XMLNode doc)

Adds ISISes to list of handled services.

Supplied configuration document is scanned for **InfoRegistrar** (p. 172) elements and those are turned into **InfoRegistrar** (p. 172) classes for handling connection to ISIS service each.

6.126.2.2 void Arc::InfoRegisterContainer::addService (InfoRegister * reg, const std::list < std::string > & ids, XMLNode cfg = XMLNode ())

Adds service to list of handled.

This method must be called first time after last addRegistrar was called - services will be only associated with ISISes which are already added. Argument ids contains list of ISIS identifiers to which service is associated. If ids is empty then service is associated to all ISISes currently added. If argument cfg is available and no ISISes are configured then addRegistrars is called with cfg used as configuration document.

6.126.2.3 void Arc::InfoRegisterContainer::removeService (InfoRegister * reg)

This method must be called if service being destroyed.

The documentation for this class was generated from the following file:

• InfoRegister.h

6.127 Arc::InfoRegisters Class Reference

Handling multiple registrations to ISISes.

#include <InfoRegister.h>

Public Member Functions

• InfoRegisters (XMLNode &cfg, Service *service_)

6.127.1 Detailed Description

Handling multiple registrations to ISISes.

6.127.2 Constructor & Destructor Documentation

6.127.2.1 Arc::InfoRegisters::InfoRegisters (XMLNode & cfg, Service * service_)

Constructor creates **InfoRegister** (p. 170) objects according to configuration.

Inside cfg elements InfoRegistration are found and for each corresponding **InfoRegister** (p. 170) object is created. Those objects are destroyed in destructor of this class.

The documentation for this class was generated from the following file:

· InfoRegister.h

6.128 Arc::InfoRegistrar Class Reference

Registration process associated with particular ISIS.

#include <InfoRegister.h>

Public Member Functions

- void registration (void)
- bool addService (InfoRegister *, XMLNode &)
- bool removeService (InfoRegister *)

6.128.1 Detailed Description

Registration process associated with particular ISIS. Instance of this class starts thread which takes care passing information about associated services to ISIS service defined in configuration. Configuration is as described in InfoRegister.xsd for element **InfoRegistrar** (p. 172).

6.128.2 Member Function Documentation

6.128.2.1 bool Arc::InfoRegistrar::addService (InfoRegister * , XMLNode &)

Adds new service to list of handled services.

Service (p. 282) is described by it's **InfoRegister** (p. 170) object which must be valid as long as this object is functional.

6.128.2.2 void Arc::InfoRegistrar::registration (void)

Performs registartion in a loop.

Never exits unless there is a critical error or requested by destructor.

The documentation for this class was generated from the following file:


• InfoRegister.h

6.129 Arc::InformationContainer Class Reference

Information System document container and processor.

#include <InformationInterface.h>

Inheritance diagram for Arc::InformationContainer:



Public Member Functions

- InformationContainer (XMLNode doc, bool copy=false)
- XMLNode Acquire (void)
- void **Assign** (**XMLNode** doc, bool copy=false)

Protected Member Functions

• virtual void **Get** (const std::list< std::string > &path, **XMLNodeContainer** &result)

Protected Attributes

XMLNode doc_

6.129.1 Detailed Description

Information System document container and processor. This class inherits form **InformationInterface** (p. 174) and offers container for storing informational XML document.

6.129.2 Constructor & Destructor Documentation

6.129.2.1 Arc::InformationContainer::InformationContainer (XMLNode doc, bool copy = false)

Creates an instance with XML document . If is true this method makes a copy of for internal use.

6.129.3 Member Function Documentation

6.129.3.1 XMLNode Arc::InformationContainer::Acquire (void)

Get a lock on contained XML document. To be used in multi-threaded environment. Do not forget to release it with Release()

6.129.3.2 void Arc::InformationContainer::Assign (XMLNode doc, bool copy = false)

Replaces internal XML document with . If is true this method makes a copy of for internal use.

6.129.3.3 virtual void Arc::InformationContainer::Get (const std::list< std::string > & path, XMLNodeContainer & result) [protected, virtual]

This method is called by this object's Process method. Real implementation of this class should return (sub)tree of XML document. This method may be called multiple times per single Process call. Here is a set on XML element names specifying how to reach requested node(s).

Reimplemented from Arc::InformationInterface (p. 175).

6.129.4 Field Documentation

6.129.4.1 XMLNode Arc::InformationContainer::doc_ [protected]

Either link or container of XML document

The documentation for this class was generated from the following file:


• InformationInterface.h

6.130 Arc::InformationInterface Class Reference

Information System message processor.

#include <InformationInterface.h>

Inheritance diagram for Arc::InformationInterface:



Public Member Functions

• InformationInterface (bool safe=true)

Protected Member Functions

• virtual void **Get** (const std::list< std::string > &path, **XMLNodeContainer** &result)

Protected Attributes

Glib::Mutex lock_

6.130.1 Detailed Description

Information System message processor. This class provides callback for 2 operations of WS-ResourceProperties and convenient parsing/generation of corresponding SOAP mesages. In a future it may extend range of supported specifications.

6.130.2 Constructor & Destructor Documentation

6.130.2.1 Arc::InformationInterface::InformationInterface (bool safe = true)

Constructor. If 'safe' is true all calls to Get will be locked.

6.130.3 Member Function Documentation

6.130.3.1 virtual void Arc::InformationInterface::Get (const std::list< std::string > & path, XMLNodeContainer & result) [protected, virtual]

This method is called by this object's Process method. Real implementation of this class should return (sub)tree of XML document. This method may be called multiple times per single Process call. Here is a set on XML element names specifying how to reach requested node(s).

Reimplemented in Arc::InfoCacheInterface (p. 169), and Arc::InformationContainer (p. 173).

6.130.4 Field Documentation

6.130.4.1 Glib::Mutex Arc::InformationInterface::lock_ [protected]

Mutex used to protect access to Get methods in multi-threaded env.

The documentation for this class was generated from the following file:

• InformationInterface.h

6.131 Arc::InformationRequest Class Reference

Request for information in InfoSystem.

#include <InformationInterface.h>

Public Member Functions

- InformationRequest (void)
- **InformationRequest** (const std::list< std::string > &path)
- **InformationRequest** (const std::list< std::string >> &paths)
- InformationRequest (XMLNode query)
- SOAPEnvelope * SOAP (void)

6.131.1 Detailed Description

Request for information in InfoSystem. This is a convenience wrapper creating proper WS-ResourceProperties request targeted InfoSystem interface of service.

6.131.2 Constructor & Destructor Documentation

6.131.2.1 Arc::InformationRequest::InformationRequest (void)

Dummy constructor

6.131.2.2 Arc::InformationRequest::InformationRequest (const std::list< std::string > & path)

Request for attribute specified by elements of path. Currently only first element is used.

Request for attribute specified by elements of paths. Currently only first element of every path is used.

6.131.2.4 Arc::InformationRequest::InformationRequest (XMLNode query)

Request for attributes specified by XPath query.

6.131.3 Member Function Documentation

6.131.3.1 SOAPEnvelope* Arc::InformationRequest::SOAP (void)

Returns generated SOAP message

The documentation for this class was generated from the following file:

• InformationInterface.h

6.132 Arc::InformationResponse Class Reference

Informational response from InfoSystem.

#include <InformationInterface.h>

Public Member Functions

- InformationResponse (SOAPEnvelope &soap)
- std::list< **XMLNode** > **Result** (void)

6.132.1 Detailed Description

Informational response from InfoSystem. This is a convenience wrapper analyzing WS-ResourceProperties response from InfoSystem interface of service.

6.132.2 Constructor & Destructor Documentation

6.132.2.1 Arc::InformationResponse::InformationResponse (SOAPEnvelope & soap)

Constructor parses WS-ResourceProperties ressponse. Provided SOAPEnvelope object must be valid as long as this object is in use.

6.132.3 Member Function Documentation

6.132.3.1 std::list<XMLNode> Arc::InformationResponse::Result (void)


Returns set of attributes which were in SOAP message passed to constructor.

The documentation for this class was generated from the following file:

• InformationInterface.h

6.133 Arc::IniConfig Class Reference

Inheritance diagram for Arc::IniConfig:



The documentation for this class was generated from the following file:

• IniConfig.h

6.134 Arc::initializeCredentialsType Class Reference

The documentation for this class was generated from the following file:

· UserConfig.h

6.135 ArcSec::InRangeFunction Class Reference

Inheritance diagram for ArcSec::InRangeFunction:



Public Member Functions

- virtual **AttributeValue** * **evaluate** (**AttributeValue** *arg0, **AttributeValue** *arg1, bool check_id=true)
- virtual std::list< AttributeValue * > evaluate (std::list< AttributeValue * > args, bool check_-id=true)

6.135.1 Member Function Documentation

6.135.1.1 virtual AttributeValue* ArcSec::InRangeFunction::evaluate (AttributeValue * arg0, AttributeValue * arg1, bool check_id = true) [virtual]

Evaluate two **AttributeValue** (p. 56) objects, and return one **AttributeValue** (p. 56) object Implements **ArcSec::Function** (p. 165).

6.135.1.2 virtual std::list<AttributeValue*> ArcSec::InRangeFunction::evaluate (std::list< AttributeValue *> args, bool check_id = true) [virtual]

Evaluate a list of AttributeValue (p. 56) objects, and return a list of Attribute objects

Implements ArcSec::Function (p. 165).

The documentation for this class was generated from the following file:


• InRangeFunction.h

6.136 Arc::IntraProcessCounter Class Reference

A class for counters used by threads within a single process.

#include <IntraProcessCounter.h>

Inheritance diagram for Arc::IntraProcessCounter:



Public Member Functions

- IntraProcessCounter (int limit, int excess)
- virtual ~IntraProcessCounter ()
- virtual int **getLimit** ()
- virtual int **setLimit** (int newLimit)
- virtual int changeLimit (int amount)
- virtual int **getExcess** ()
- virtual int **setExcess** (int newExcess)
- virtual int changeExcess (int amount)
- virtual int **getValue** ()
- virtual **CounterTicket reserve** (int amount=1, Glib::TimeVal duration=**ETERNAL**, bool prioritized=false, Glib::TimeVal timeOut=**ETERNAL**)

Protected Member Functions

- virtual void cancel (IDType reservationID)
- virtual void **extend** (**IDType** &reservationID, Glib::TimeVal &expiryTime, Glib::TimeVal duration=**ETERNAL**)

6.136.1 Detailed Description

A class for counters used by threads within a single process. This is a class for shared among different threads within a single process. See the **Counter** (p. 81) class for further information about counters and examples of usage.

6.136.2 Constructor & Destructor Documentation

6.136.2.1 Arc::IntraProcessCounter::IntraProcessCounter (int limit, int excess)

Creates an IntraProcessCounter (p. 178) with specified limit and excess.

This constructor creates a counter with the specified limit (amount of resources available for reservation) and excess limit (an extra amount of resources that may be used for prioritized reservations).

Parameters

limit The limit of the counter.

excess The excess limit of the counter.

6.136.2.2 virtual Arc::IntraProcessCounter::~IntraProcessCounter() [virtual]

Destructor.

This is the destructor of the IntraProcessCounter (p. 178) class. Does not need to do anything.

6.136.3 Member Function Documentation

6.136.3.1 virtual void Arc::IntraProcessCounter::cancel (IDType reservationID) [protected, virtual]

Cancellation of a reservation.

This method cancels a reservation. It is called by the **CounterTicket** (p. 88) that corresponds to the reservation.

Parameters

reservationID The identity number (key) of the reservation to cancel.

6.136.3.2 virtual int Arc::IntraProcessCounter::changeExcess (int amount) [virtual]

Changes the excess limit of the counter.

Changes the excess limit of the counter by adding a certain amount to the current excess limit.

Parameters

amount The amount by which to change the excess limit.

Returns

The new excess limit.

Implements Arc::Counter (p. 84).

6.136.3.3 virtual int Arc::IntraProcessCounter::changeLimit(int amount) [virtual]

Changes the limit of the counter.

Changes the limit of the counter by adding a certain amount to the current limit.

Parameters

amount The amount by which to change the limit.

Returns

The new limit.

Implements Arc::Counter (p. 84).

6.136.3.4 virtual void Arc::IntraProcessCounter::extend (IDType & reservationID, Glib::TimeVal & expiryTime, Glib::TimeVal duration = ETERNAL) [protected, virtual]

Extension of a reservation.

This method extends a reservation. It is called by the **CounterTicket** (p. 88) that corresponds to the reservation.

Parameters

reservationID Used for input as well as output. Contains the identification number of the original reservation on entry and the new identification number of the extended reservation on exit.

expiryTime Used for input as well as output. Contains the expiry time of the original reservation on entry and the new expiry time of the extended reservation on exit.

duration The time by which to extend the reservation. The new expiration time is computed based on the current time, NOT the previous expiration time.

6.136.3.5 virtual int Arc::IntraProcessCounter::getExcess() [virtual]

Returns the excess limit of the counter.

Returns the excess limit of the counter, i.e. by how much the usual limit may be exceeded by prioritized reservations.

Returns

The excess limit.

Implements Arc::Counter (p. 85).

6.136.3.6 virtual int Arc::IntraProcessCounter::getLimit() [virtual]

Returns the current limit of the counter.

This method returns the current limit of the counter, i.e. how many units can be reserved simultaneously by different threads without claiming high priority.

Returns

The current limit of the counter.

Implements Arc::Counter (p. 86).

6.136.3.7 virtual int Arc::IntraProcessCounter::getValue() [virtual]

Returns the current value of the counter.

Returns the current value of the counter, i.e. the number of unreserved units. Initially, the value is equal to the limit of the counter. When a reservation is made, the the value is decreased. Normally, the value should never be negative, but this may happen if there are prioritized reservations. It can also happen if the limit is decreased after some reservations have been made, since reservations are never revoked.

Returns

The current value of the counter.

Implements Arc::Counter (p. 86).

6.136.3.8 virtual CounterTicket Arc::IntraProcessCounter::reserve (int amount = 1, Glib::TimeVal duration = ETERNAL, bool prioritized = false, Glib::TimeVal timeOut = ETERNAL) [virtual]

Makes a reservation from the counter.

This method makes a reservation from the counter. If the current value of the counter is too low to allow for the reservation, the method blocks until the reservation is possible or times out.

Parameters

amount The amount to reserve, default value is 1.

duration The duration of a self expiring reservation, default is that it lasts forever.

prioritized Whether this reservation is prioritized and thus allowed to use the excess limit.

timeOut The maximum time to block if the value of the counter is too low, default is to allow "eternal" blocking.

Returns

A CounterTicket (p. 88) that can be queried about the status of the reservation as well as for cancellations and extensions.

Implements Arc::Counter (p. 87).

6.136.3.9 virtual int Arc::IntraProcessCounter::setExcess (int newExcess) [virtual]

Sets the excess limit of the counter.

This method sets a new excess limit for the counter.

Parameters

newExcess The new excess limit, an absolute number.

Returns

The new excess limit.

Implements Arc::Counter (p. 87).

6.136.3.10 virtual int Arc::IntraProcessCounter::setLimit (int newLimit) [virtual]

Sets the limit of the counter.

This method sets a new limit for the counter.

Parameters

newLimit The new limit, an absolute number.

Returns

The new limit.

Implements Arc::Counter (p. 87).

The documentation for this class was generated from the following file:

• IntraProcessCounter.h

6.137 Arc::ISIS_description Struct Reference

The documentation for this struct was generated from the following file:

• InfoRegister.h


6.138 Arc::IString Class Reference

The documentation for this class was generated from the following file:

• IString.h

6.139 Arc::JDLParser Class Reference

Inheritance diagram for Arc::JDLParser:



The documentation for this class was generated from the following file:

· JDLParser.h

6.140 Arc::Job Class Reference

Job (p. 182).

#include <Job.h>

Public Member Functions

- Job ()
- void **Print** (bool longlist) const

6.140.1 Detailed Description

Job (p. 182). This class describe a Grid job. Most of the members contained in this class are directly linked to the ComputingActivity defined in the GLUE Specification v. 2.0 (GFD-R-P.147).

6.140.2 Constructor & Destructor Documentation

6.140.2.1 Arc::Job::Job ()

Create a Job (p. 182) object.

Default constructor. Takes no arguments.

6.140.3 Member Function Documentation

6.140.3.1 void Arc::Job::Print (bool longlist) const

Print the **Job** (p. 182) information to std::cout.

Method to print the Job (p. 182) attributes to std::cout

Parameters

longlist is boolean for long listing (more details).

The documentation for this class was generated from the following file:


• Job.h

6.141 Arc::JobController Class Reference

Base class for the JobControllers.

#include <JobController.h>

Inheritance diagram for Arc::JobController:



Public Member Functions

- void **FillJobStore** (const std::list< **URL** > &jobids)
- bool **PrintJobStatus** (const std::list< std::string > &status, const bool longlist)
- bool **Migrate** (**TargetGenerator** & targetGen, **Broker** *broker, const **UserConfig** & usercfg, const bool forcemigration, std::list< **URL** > & migratedJobIDs)

6.141.1 Detailed Description

Base class for the JobControllers. The **JobController** (p. 183) is the base class for middleware specialized derived classes. The **JobController** (p. 183) base class is also the implementer of all public functionality that should be offered by the middleware specific specializations. In other words all virtual functions of the **JobController** (p. 183) are private. The initialization of a (specialized) **JobController** (p. 183) object takes two steps. First the **JobController** (p. 183) specialization for the required grid flavour must be loaded by the **JobControllerLoader** (p. 185), which sees to that the **JobController** (p. 183) receives information about its Grid flavour and the local joblist file containing information about all active jobs (flavour independent). The next step is the filling of the **JobController** (p. 183) job pool (JobStore) which is the pool of jobs that the **JobController** (p. 183) can manage. Must be specialized for each supported middleware flavour.

6.141.2 Member Function Documentation

6.141.2.1 void Arc::JobController::FillJobStore (const std::list < URL > & jobids)

Fill jobstore.

Method to fill the jobstore with jobs that should be managed.

Parameters

jobids List of jobids to be loaded to the jobstore. If empty all jobs of the specialized grid flavour present in the joblist file (given through the usercfg to the constructor) will be loaded to the jobstore.

6.141.2.2 bool Arc::JobController::Migrate (TargetGenerator & targetGen, Broker * broker, const UserConfig & usercfg, const bool forcemigration, std::list< URL > & migratedJobIDs)

Migrate job from cluster A to Cluster B.

Method to migrate the jobs contained in the jobstore.

Parameters

targetGen TargetGenerator (p. 308) with targets to migrate the job to.

broker Broker (p. 62) to be used when selecting target.

forcemigration boolean which specifies whether a migrated job should persist if the new cluster does not succeed sending a kill/terminate request for the job.

6.141.2.3 bool Arc::JobController::PrintJobStatus (const std::list< std::string > & status, const bool longlist)

Print job status to stdout.

The job status is printed to stdout when calling this method. More specifically the **Job::Print** (p. 183) method is called on each of the **Job** (p. 182) objects stored in this object, and the boolean argument *longlist* is passed directly to the method indicating whether verbose job status should be printed. The *status* argument is a list of strings each representing a job state (**JobState** (p. 187)) which is used to indicate that only jobs with a job state in the list should be considered. If the list *status* is empty all jobs will be considered.

This method is not supposed to be overloaded by extending classes.

Parameters

status a list of strings representing states to be considered.

longlist a boolean indicating whether verbose job information should be printed.

Returns

This method always returns true.

See also

```
GetJobInformation
Job::Print (p. 183)
JobState (p. 187)
```


The documentation for this class was generated from the following file:

• JobController.h

6.142 Arc::JobControllerLoader Class Reference

#include <JobController.h>

Inheritance diagram for Arc::JobControllerLoader:



Public Member Functions

- JobControllerLoader ()
- ~JobControllerLoader ()
- **JobController** * **load** (const std::string &name, const **UserConfig** &usercfg)
- const std::list< **JobController** * > & **GetJobControllers** () const

6.142.1 Detailed Description

Class responsible for loading **JobController** (p. 183) plugins The **JobController** (p. 183) objects returned by a **JobControllerLoader** (p. 185) must not be used after the **JobControllerLoader** (p. 185) goes out of scope.

6.142.2 Constructor & Destructor Documentation

6.142.2.1 Arc::JobControllerLoader::JobControllerLoader ()

Constructor Creates a new JobControllerLoader (p. 185).

6.142.2.2 Arc::JobControllerLoader::~JobControllerLoader ()

Destructor Calling the destructor destroys all JobControllers loaded by the **JobControllerLoader** (p. 185) instance.

6.142.3 Member Function Documentation

6.142.3.1 const std::list<JobController*>& Arc::JobControllerLoader::GetJobControllers() const [inline]

Retrieve the list of loaded JobControllers.

Returns

A reference to the list of JobControllers.

Referenced by Arc::JobSupervisor::GetJobControllers().

6.142.3.2 JobController* Arc::JobControllerLoader::load (const std::string & name, const UserConfig & usercfg)

Load a new **JobController** (p. 183)

Parameters

```
name The name of the JobController (p. 183) to load.usercfg The UserConfig (p. 331) object for the new JobController (p. 183).
```

Returns


A pointer to the new JobController (p. 183) (NULL on error).

The documentation for this class was generated from the following file:

• JobController.h

6.143 Arc::JobControllerPluginArgument Class Reference

Inheritance diagram for Arc::JobControllerPluginArgument:



The documentation for this class was generated from the following file:

· JobController.h


6.144 Arc::JobDescription Class Reference

The documentation for this class was generated from the following file:

· JobDescription.h

6.145 Arc::JobDescriptionParser Class Reference

Inheritance diagram for Arc::JobDescriptionParser:



The documentation for this class was generated from the following file:

• JobDescriptionParser.h

6.146 Arc::JobIdentificationType Class Reference

The documentation for this class was generated from the following file:

• JobDescription.h

6.147 Arc::JobMetaType Class Reference

The documentation for this class was generated from the following file:

· JobDescription.h

6.148 Arc::JobState Class Reference

#include <JobState.h>

6.148.1 Detailed Description

ARC general state model. The class comprise the general state model of the ARC-lib, and are herein used to compare job states from the different middlewares supported by the plugin structure of the ARC-lib. Which is why every ACC plugin should contain a class derived from this class. The derived class should consist of a constructor and a mapping function (a JobStateMap) which maps a std::string to a **JobState** (p. 187):StateType. An example of a constructor in a plugin could be: JobStatePlugin::JobStatePluging(const std::string& state): JobState(state, &pluginStateMap) {} where &pluginStateMap is a reference to the JobStateMap defined by the derived class.

The documentation for this class was generated from the following file:

• JobState.h

6.149 Arc::JobSupervisor Class Reference

% JobSupervisor (p. 188) class

#include <JobSupervisor.h>

Public Member Functions

- **JobSupervisor** (const **UserConfig** &usercfg, const std::list< std::string > &jobs)
- const std::list< JobController * > & GetJobControllers ()

6.149.1 Detailed Description

% **JobSupervisor** (p. 188) class The **JobSupervisor** (p. 188) class is tool for loading **JobController** (p. 183) plugins for managing Grid jobs.

6.149.2 Constructor & Destructor Documentation

6.149.2.1 Arc::JobSupervisor::JobSupervisor (const UserConfig & usercfg, const std::list< std::string > & jobs)

Create a **JobSupervisor** (p. 188) object.

Default constructor to create a **JobSupervisor** (p. 188). Automatically loads **JobController** (p. 183) plugins based upon the input jobids.

Parameters

usercfg Reference to UserConfig (p. 331) object with information about user credentials and joblistfile.

jobs List of jobs(jobid or job name) to be managed.

6.149.3 Member Function Documentation

6.149.3.1 const std::list<JobController*>& Arc::JobSupervisor::GetJobControllers() [inline]

Get list of JobControllers.

Method to get the list of JobControllers loaded by constructor.

References Arc::JobControllerLoader::GetJobControllers().

The documentation for this class was generated from the following file:

• JobSupervisor.h

6.150 Arc::LoadableModuleDescription Class Reference

The documentation for this class was generated from the following file:


· ModuleManager.h

6.151 Arc::Loader Class Reference

Plugins loader.

#include <Loader.h>

Inheritance diagram for Arc::Loader:



Public Member Functions

- Loader (XMLNode cfg)
- ∼Loader ()

Protected Attributes

• PluginsFactory * factory_

6.151.1 Detailed Description

Plugins loader. This class processes XML configration and loads specified plugins. Accepted configuration is defined by XML schema mcc.xsd. "Plugins" elements are parsed by this class and corresponding libraries are loaded.

6.151.2 Constructor & Destructor Documentation

6.151.2.1 Arc::Loader::Loader (XMLNode cfg)

Constructor that takes whole XML configuration and performs common configuration part

6.151.2.2 Arc::Loader::∼Loader ()

Destructor destroys all components created by constructor

6.151.3 Field Documentation

6.151.3.1 PluginsFactory* Arc::Loader::factory_ [protected]

Link to Factory responsible for loading and creation of Plugin (p. 248) and derived objects

Referenced by Arc::ChainContext::operator PluginsFactory *().

The documentation for this class was generated from the following file:


· Loader.h

6.152 Arc::LogDestination Class Reference

A base class for log destinations.

#include <Logger.h>

Inheritance diagram for Arc::LogDestination:



Public Member Functions

• virtual void **log** (const **LogMessage** &message)=0

Protected Member Functions

- LogDestination ()
- LogDestination (const std::string &locale)

6.152.1 Detailed Description

A base class for log destinations. This class defines an interface for LogDestinations. **LogDestination** (p. 190) objects will typically contain synchronization mechanisms and should therefore never be copied.

6.152.2 Constructor & Destructor Documentation

6.152.2.1 Arc::LogDestination::LogDestination() [protected]

Default constructor.

This destination will use the default locale.

6.152.2.2 Arc::LogDestination::LogDestination (const std::string & locale) [protected]

Constructor with specific locale.

This destination will use the specified locale.

The documentation for this class was generated from the following file:


• Logger.h

6.153 Arc::LogFile Class Reference

A class for logging to files.

#include <Logger.h>

Inheritance diagram for Arc::LogFile:



Public Member Functions

- LogFile (const std::string &path)
- LogFile (const std::string &path, const std::string &locale)
- void setMaxSize (int newsize)
- void **setBackups** (int newbackup)
- void **setReopen** (bool newreopen)
- operator bool (void)
- bool operator! (void)
- virtual void log (const LogMessage &message)

6.153.1 Detailed Description

A class for logging to files. This class is used for logging to files. It provides synchronization in order to prevent different LogMessages to appear mixed with each other in the stream. It is possible to limit size of created file. Whenever specified size is exceeded fiel is deleted and new one is created. Old files may be moved into backup files instead of being deleted. Those files have names same as initial file with additional number suffix - similar to those found in /var/log of many Unix-like systems.

6.153.2 Constructor & Destructor Documentation

6.153.2.1 Arc::LogFile::LogFile (const std::string & path)

Creates a LogFile (p. 191) connected to a file.

Creates a **LogFile** (p. 191) connected to the file located at specified path. In order not to break synchronization, it is important not to connect more than one **LogFile** (p. 191) object to a certain file. If file does not exist it will be created.

Parameters

path The path to file to which to write LogMessages.

6.153.2.2 Arc::LogFile::LogFile (const std::string & path, const std::string & locale)

Creates a LogFile (p. 191) connected to a file.

Creates a **LogFile** (p. 191) connected to the file located at specified path. The output will be localised to the specified locale.

6.153.3 Member Function Documentation

6.153.3.1 virtual void Arc::LogFile::log (const LogMessage & message) [virtual]

Writes a LogMessage (p. 196) to the file.

This method writes a **LogMessage** (p. 196) to the file that is connected to this **LogFile** (p. 191) object. If after writing size of file exceeds one set by **setMaxSize**() (p. 192) file is moved to backup and new one is created.

Parameters

```
message The LogMessage (p. 196) to write.
```

Implements Arc::LogDestination (p. 190).

6.153.3.2 void Arc::LogFile::setBackups (int newbackup)

Set number of backups to store.

Set number of backups to store. When file size exceeds one specified with **setMaxSize()** (p. 192) file is closed and moved to one named path.1. If path.1 exists it is moved to path.2 and so on. Number of path.# files is one set in newbackup.

Parameters

newbackup Number of backup files.

6.153.3.3 void Arc::LogFile::setMaxSize (int newsize)

Set maximal allowed size of file.

Set maximal allowed size of file. This value is not obeyed exactly. Spesified size may be exceeded by amount of one **LogMessage** (p. 196). To disable limit specify -1.

Parameters

newsize Max size of log file.

6.153.3.4 void Arc::LogFile::setReopen (bool newreopen)

Set file reopen on every write.

Set file reopen on every write. If set to true file is opened before writing every log record and closed afterward.

Parameters

newreopen If file to be reopened for every log record.

The documentation for this class was generated from the following file:

· Logger.h

6.154 Arc::Logger Class Reference

A logger class.

#include <Logger.h>

Public Member Functions

- Logger (Logger &parent, const std::string &subdomain)
- Logger (Logger &parent, const std::string &subdomain, LogLevel threshold)
- ∼Logger ()
- void addDestination (LogDestination &destination)
- void removeDestinations (void)
- void **setThreshold** (**LogLevel** threshold)
- LogLevel getThreshold () const
- void msg (LogMessage message)
- void msg (LogLevel level, const std::string &str)

Static Public Member Functions

• static Logger & getRootLogger ()

6.154.1 Detailed Description

A logger class. This class defines a Logger (p. 193) to which LogMessages can be sent.

Every **Logger** (p. 193) (except for the rootLogger) has a parent **Logger** (p. 193). The domain of a **Logger** (p. 193) (a string that indicates the origin of LogMessages) is composed by adding a subdomain to the domain of its parent **Logger** (p. 193).

A **Logger** (p. 193) also has a threshold. Every **LogMessage** (p. 196) that have a level that is greater than or equal to the threshold is forwarded to any **LogDestination** (p. 190) connected to this **Logger** (p. 193) as well as to the parent **Logger** (p. 193).

Typical usage of the **Logger** (p. 193) class is to declare a global **Logger** (p. 193) object for each library/module/component to be used by all classes and methods there.

6.154.2 Constructor & Destructor Documentation

6.154.2.1 Arc::Logger::Logger (Logger & parent, const std::string & subdomain)

Creates a logger.

Creates a logger. The threshold is inherited from its parent **Logger** (p. 193).

Parameters

```
parent The parent Logger (p. 193) of the new Logger (p. 193). subdomain The subdomain of the new logger.
```

6.154.2.2 Arc::Logger::Logger (Logger & parent, const std::string & subdomain, LogLevel threshold)

Creates a logger.

Creates a logger.

Parameters

```
parent The parent Logger (p. 193) of the new Logger (p. 193).subdomain The subdomain of the new logger.threshold The threshold of the new logger.
```

6.154.2.3 Arc::Logger::∼Logger ()

Destroys a logger.

Destructor

6.154.3 Member Function Documentation

6.154.3.1 void Arc::Logger::addDestination (LogDestination & destination)

Adds a LogDestination (p. 190).

Adds a **LogDestination** (p. 190) to which to forward LogMessages sent to this logger (if they pass the threshold). Since LogDestinatoins should not be copied, the new **LogDestination** (p. 190) is passed by reference and a pointer to it is kept for later use. It is therefore important that the **LogDestination** (p. 190) passed to this **Logger** (p. 193) exists at least as long as the **Logger** (p. 193) iteslf.

6.154.3.2 static Logger& Arc::Logger::getRootLogger() [static]

The root **Logger** (p. 193).

This is the root **Logger** (p. 193). It is an ancestor of any other **Logger** (p. 193) and allways exists.

6.154.3.3 LogLevel Arc::Logger::getThreshold () const

Returns the threshold.

Returns the threshold.

Returns

The threshold of this **Logger** (p. 193).

6.154.3.4 void Arc::Logger::msg (LogMessage message)

```
Sends a LogMessage (p. 196).
```

Sends a LogMessage (p. 196).

Parameters

```
The LogMessage (p. 196) to send.
```

Referenced by msg(), and Arc::stringto().

6.154.3.5 void Arc::Logger::msg (LogLevel level, const std::string & str) [inline]

Logs a message text.

Logs a message text string at the specified LogLevel. This is a convenience method to save some typing. It simply creates a **LogMessage** (p. 196) and sends it to the other **msg()** (p. 195) method.

Parameters

```
level The level of the message.str The message text.
```

References msg().

6.154.3.6 void Arc::Logger::setThreshold (LogLevel threshold)

Sets the threshold.

This method sets the threshold of the **Logger** (p. 193). Any message sent to this **Logger** (p. 193) that has a level below this threshold will be discarded.

Parameters

The threshold

The documentation for this class was generated from the following file:

• Logger.h

6.155 Arc::LoggerFormat Struct Reference

The documentation for this struct was generated from the following file:

· Logger.h

6.156 Arc::LogMessage Class Reference

A class for log messages.

#include <Logger.h>

Public Member Functions

- LogMessage (LogLevel level, const IString &message)
- LogMessage (LogLevel level, const IString &message, const std::string &identifier)
- LogLevel getLevel () const

Protected Member Functions

• void **setIdentifier** (std::string identifier)

Friends

- · class Logger
- std::ostream & operator<< (std::ostream &os, const LogMessage &message)

6.156.1 Detailed Description

A class for log messages. This class is used to represent log messages internally. It contains the time the message was created, its level, from which domain it was sent, an identifier and the message text itself.

6.156.2 Constructor & Destructor Documentation

6.156.2.1 Arc::LogMessage::LogMessage (LogLevel level, const IString & message)

Creates a LogMessage (p. 196) with the specified level and message text.

This constructor creates a **LogMessage** (p. 196) with the specified level and message text. The time is set automatically, the domain is set by the **Logger** (p. 193) to which the **LogMessage** (p. 196) is sent and the identifier is composed from the process ID and the address of the Thread object corresponding to the calling thread.

Parameters

```
level The level of the LogMessage (p. 196).message The message text.
```

6.156.2.2 Arc::LogMessage::LogMessage (LogLevel level, const IString & message, const std::string & identifier)

Creates a **LogMessage** (p. 196) with the specified attributes.

This constructor creates a **LogMessage** (p. 196) with the specified level, message text and identifier. The time is set automatically and the domain is set by the **Logger** (p. 193) to which the **LogMessage** (p. 196) is sent.

Parameters

```
level The level of the LogMessage (p. 196).message The message text.ident The identifier of the LogMessage (p. 196).
```

6.156.3 Member Function Documentation

6.156.3.1 LogLevel Arc::LogMessage::getLevel () const

Returns the level of the **LogMessage** (p. 196).

Returns the level of the LogMessage (p. 196).

Returns

The level of the **LogMessage** (p. 196).

6.156.3.2 void Arc::LogMessage::setIdentifier (std::string identifier) [protected]

Sets the identifier of the **LogMessage** (p. 196).

The purpose of this method is to allow subclasses (in case there are any) to set the identifier of a **LogMessage** (p. 196).

Parameters

The identifier.

6.156.4 Friends And Related Function Documentation

6.156.4.1 friend class Logger [friend]

The **Logger** (p. 193) class is a friend.

The **Logger** (p. 193) class must have some privileges (e.g. ability to call the setDomain() method), therefore it is a friend.

6.156.4.2 std::ostream& operator<< (std::ostream & os, const LogMessage & message) [friend]

Printing of LogMessages to ostreams.

Output operator so that LogMessages can be printed conveniently by LogDestinations.

The documentation for this class was generated from the following file:


• Logger.h

6.157 Arc::LogStream Class Reference

A class for logging to ostreams.

#include <Logger.h>

Inheritance diagram for Arc::LogStream:



Public Member Functions

- LogStream (std::ostream &destination)
- LogStream (std::ostream &destination, const std::string &locale)
- virtual void log (const LogMessage &message)

6.157.1 Detailed Description

A class for logging to ostreams. This class is used for logging to ostreams (cout, cerr, files). It provides synchronization in order to prevent different LogMessages to appear mixed with each other in the stream. In order not to break the synchronization, LogStreams should never be copied. Therefore the copy constructor and assignment operator are private. Furthermore, it is important to keep a **LogStream** (p. 197) object as long as the **Logger** (p. 193) to which it has been registered.

6.157.2 Constructor & Destructor Documentation

6.157.2.1 Arc::LogStream::LogStream (std::ostream & destination)

Creates a LogStream (p. 197) connected to an ostream.

Creates a **LogStream** (p. 197) connected to the specified ostream. In order not to break synchronization, it is important not to connect more than one **LogStream** (p. 197) object to a certain stream.

Parameters

destination The ostream to which to erite LogMessages.

6.157.2.2 Arc::LogStream::LogStream (std::ostream & destination, const std::string & locale)

Creates a LogStream (p. 197) connected to an ostream.

Creates a **LogStream** (p. 197) connected to the specified ostream. The output will be localised to the specified locale.

6.157.3 Member Function Documentation

6.157.3.1 virtual void Arc::LogStream::log (const LogMessage & message) [virtual]

Writes a **LogMessage** (p. 196) to the stream.

This method writes a **LogMessage** (p. 196) to the ostream that is connected to this **LogStream** (p. 197) object. It is synchronized so that not more than one **LogMessage** (p. 196) can be written at a time.

Parameters

message The LogMessage (p. 196) to write.

Implements Arc::LogDestination (p. 190).

The documentation for this class was generated from the following file:

Logger.h

6.158 ArcSec::MatchFunction Class Reference

Evaluate whether arg1 (value in regular expression) matched arg0 (lable in regular expression).

#include <MatchFunction.h>

Inheritance diagram for ArcSec::MatchFunction:



Public Member Functions

- virtual **AttributeValue** * **evaluate** (**AttributeValue** *arg0, **AttributeValue** *arg1, bool check_id=true)
- virtual std::list< AttributeValue * > evaluate (std::list< AttributeValue * > args, bool check_-id=true)

Static Public Member Functions

• static std::string **getFunctionName** (std::string datatype)

6.158.1 Detailed Description

Evaluate whether arg1 (value in regular expression) matched arg0 (lable in regular expression).

6.158.2 Member Function Documentation

6.158.2.1 virtual AttributeValue* ArcSec::MatchFunction::evaluate (AttributeValue * arg0, AttributeValue * arg1, bool check_id = true) [virtual]

Evaluate two **AttributeValue** (p. 56) objects, and return one **AttributeValue** (p. 56) object Implements **ArcSec::Function** (p. 165).

6.158.2.2 virtual std::list<AttributeValue*> ArcSec::MatchFunction::evaluate (std::list< AttributeValue *> args, bool check_id = true) [virtual]

Evaluate a list of **AttributeValue** (p. 56) objects, and return a list of Attribute objects Implements **ArcSec::Function** (p. 165).

6.158.2.3 static std::string ArcSec::MatchFunction::getFunctionName (std::string datatype) [static]

help function to get the FunctionName

The documentation for this class was generated from the following file:


• MatchFunction.h

6.159 Arc::MCC Class Reference

Message (p. 208) Chain Component - base class for every MCC (p. 200) plugin.

#include <MCC.h>

Inheritance diagram for Arc::MCC:



Public Member Functions

- MCC (Config *)
- virtual void **Next** (**MCCInterface** *next, const std::string &label="")
- virtual void **AddSecHandler** (**Config** *cfg, **ArcSec::SecHandler** *sechandler, const std::string &label="")
- virtual void Unlink ()
- virtual MCC_Status process (Message &, Message &)

Protected Member Functions

• bool ProcessSecHandlers (Message &message, const std::string &label="") const

Protected Attributes

- std::map< std::string, MCCInterface * > next_
- std::map< std::string, std::list< **ArcSec::SecHandler** * > > **sechandlers**_

Static Protected Attributes

• static Logger logger

6.159.1 Detailed Description

Message (p. 208) Chain Component - base class for every **MCC** (p. 200) plugin. This is partially virtual class which defines interface and common functionality for every **MCC** (p. 200) plugin needed for managing of component in a chain.

6.159.2 Constructor & Destructor Documentation

```
6.159.2.1 Arc::MCC::MCC(Config * ) [inline]
```

Example contructor - MCC (p. 200) takes at least it's configuration subtree

6.159.3 Member Function Documentation

```
6.159.3.1 virtual void Arc::MCC::AddSecHandler ( Config * cfg, ArcSec::SecHandler * sechandler, const std::string & label = "" ) [virtual]
```

Add security components/handlers to this MCC (p. 200). Security handlers are stacked into a few queues with each queue identified by its label. The queue labelled 'incoming' is executed for every 'request' message after the message is processed by the MCC (p. 200) on the service side and before processing on the client side. The queue labelled 'outgoing' is run for response message before it is processed by MCC (p. 200) algorithms on the service side and after processing on the client side. Those labels are just a matter of agreement and some MCCs may implement different queues executed at various message processing steps.

6.159.3.2 virtual void Arc::MCC::Next (MCCInterface * next, const std::string & label = "") [virtual]

Add reference to next **MCC** (p. 200) in chain. This method is called by **Loader** (p. 189) for every potentially labeled link to next component which implements **MCCInterface** (p. 205). If next is NULL corresponding link is removed.

Reimplemented in Arc::Plexer (p. 247).

6.159.3.3 virtual MCC_Status Arc::MCC::process (Message & , Message &) [inline, virtual]

Dummy Message (p. 208) processing method. Just a placeholder.

Implements Arc::MCCInterface (p. 206).

Reimplemented in Arc::Plexer (p. 247).

6.159.3.4 bool Arc::MCC::ProcessSecHandlers (Message & message, const std::string & label = "") const [protected]

Executes security handlers of specified queue. Returns true if the message is authorized for further processing or if there are no security handlers which implement authorization functionality. This is a convenience method and has to be called by the implemention of the MCC (p. 200).

6.159.3.5 virtual void Arc::MCC::Unlink() [virtual]

Removing all links. Useful for destroying chains.

6.159.4 Field Documentation

6.159.4.1 Logger Arc::MCC::logger [static, protected]

A logger for MCCs.

A logger intended to be the parent of loggers in the different MCCs.

Reimplemented in Arc::Plexer (p. 247).

6.159.4.2 std::map<std::string, MCCInterface *> Arc::MCC::next_ [protected]

Set of labeled "next" components. Each implemented MCC (p. 200) must call **process**() (p. 201) method of corresponding MCCInterface (p. 205) from this set in own **process**() (p. 201) method.

6.159.4.3 std::map<std::string, std::list<ArcSec::SecHandler *> > Arc::MCC::sechandlers_ [protected]

Set of labeled authentication and authorization handlers. MCC (p. 200) calls sequence of handlers at specific point depending on associated identifier. In most aces those are "in" and "out" for incoming and outgoing messages correspondingly.

The documentation for this class was generated from the following file:

• MCC.h

6.160 Arc::MCC Status Class Reference

A class for communication of MCC (p. 200) processing results.

#include <MCC_Status.h>

Public Member Functions

- MCC_Status (StatusKind kind=STATUS_UNDEFINED, const std::string &origin="???", const std::string &explanation="No explanation.")
- bool isOk () const
- StatusKind getKind () const
- const std::string & getOrigin () const

- const std::string & getExplanation () const
- operator std::string () const
- operator bool (void) const
- bool operator! (void) const

6.160.1 Detailed Description

A class for communication of MCC (p. 200) processing results. This class is used to communicate result status between MCCs. It contains a status kind, a string specifying the origin (MCC (p. 200)) of the status object and an explanation.

6.160.2 Constructor & Destructor Documentation

```
6.160.2.1 Arc::MCC_Status::MCC_Status ( StatusKind kind = STATUS_UNDEFINED, const std::string & origin = "???", const std::string & explanation = "No explanation."
```

The constructor.

Creates a MCC_Status (p. 202) object.

Parameters

```
kind The StatusKind (default: STATUS_UNDEFINED)

origin The origin MCC (p. 200) (default: "????")

explanation An explanation (default: "No explanation.")
```

6.160.3 Member Function Documentation

6.160.3.1 const std::string& Arc::MCC_Status::getExplanation () const

Returns an explanation.

This method returns an explanation of this object.

Returns

An explanation of this object.

6.160.3.2 StatusKind Arc::MCC_Status::getKind () const

Returns the status kind.

Returns the status kind of this object.

Returns

The status kind of this object.

6.160.3.3 const std::string& Arc::MCC_Status::getOrigin () const

Returns the origin.

This method returns a string specifying the origin MCC (p. 200) of this object.

Returns

A string specifying the origin MCC (p. 200) of this object.

6.160.3.4 bool Arc::MCC_Status::isOk () const

Is the status kind ok?

This method returns true if the status kind of this object is STATUS_OK

Returns

```
true if kind==STATUS_OK
```

Referenced by operator bool(), and operator!().

6.160.3.5 Arc::MCC_Status::operator bool (void) const [inline]

Is the status kind ok?

This method returns true if the status kind of this object is STATUS_OK

Returns

```
true if kind==STATUS_OK
```

References isOk().

6.160.3.6 Arc::MCC_Status::operator std::string () const

Conversion to string.

This operator converts a MCC_Status (p. 202) object to a string.

6.160.3.7 bool Arc::MCC_Status::operator! (void) const [inline]

not operator

Returns true if the status kind is not OK

Returns

```
true if kind!=STATUS_OK
```


References isOk().

The documentation for this class was generated from the following file:

• MCC_Status.h

6.161 Arc::MCCConfig Class Reference

Inheritance diagram for Arc::MCCConfig:



Public Member Functions

• virtual XMLNode MakeConfig (XMLNode cfg) const

6.161.1 Member Function Documentation

6.161.1.1 virtual XMLNode Arc::MCCConfig::MakeConfig (XMLNode cfg) const [virtual]

Adds configuration part corresponding to stored information into common configuration tree supplied in 'cfg' argument. Returns reference to XML node representing configuration of **ModuleManager** (p. 217)

Reimplemented from Arc::BaseConfig (p. 61).

The documentation for this class was generated from the following file:


• MCC.h

6.162 Arc::MCCInterface Class Reference

Interface for communication between MCC (p. 200), Service (p. 282) and Plexer (p. 246) objects.

#include <MCC.h>

Inheritance diagram for Arc::MCCInterface:



Public Member Functions

• virtual MCC_Status process (Message &request, Message &response)=0

6.162.1 Detailed Description

Interface for communication between MCC (p. 200), Service (p. 282) and Plexer (p. 246) objects. The Interface consists of the method process() (p. 206) which is called by the previous MCC (p. 200) in the chain. For memory management policies please read the description of the Message (p. 208) class.

6.162.2 Member Function Documentation

6.162.2.1 virtual MCC_Status Arc::MCCInterface::process (Message & request, Message & response) [pure virtual]

Method for processing of requests and responses. This method is called by preceding MCC (p. 200) in chain when a request needs to be processed. This method must call similar method of next MCC (p. 200) in chain unless any failure happens. Result returned by call to next MCC (p. 200) should be processed and passed back to previous MCC (p. 200). In case of failure this method is expected to generate valid error response and return it back to previous MCC (p. 200) without calling the next one.

Parameters

request The request that needs to be processed.

response A **Message** (p. 208) object that will contain the response of the request when the method returns.

Returns

An object representing the status of the call.

Implemented in Test::TestService (p. 315), Arc::MCC (p. 201), and Arc::Plexer (p. 247).

The documentation for this class was generated from the following file:


• MCC.h

6.163 Arc::MCCLoader Class Reference

Creator of Message (p. 208) Component Chains (MCC (p. 200)).

#include <MCCLoader.h>

Inheritance diagram for Arc::MCCLoader:



Public Member Functions

- MCCLoader (Config &cfg)
- ∼MCCLoader ()
- MCC * operator[] (const std::string &id)

6.163.1 Detailed Description

Creator of **Message** (p. 208) Component Chains (**MCC** (p. 200)). This class processes XML configration and creates message chains. Accepted configuration is defined by XML schema mcc.xsd. Supported components are of types **MCC** (p. 200), **Service** (p. 282) and **Plexer** (p. 246). **MCC** (p. 200) and **Service** (p. 282) are loaded from dynamic libraries. For **Plexer** (p. 246) only internal implementation is supported. This object is also a container for loaded componets. All components and chains are destroyed if this object is destroyed. Chains are created in 2 steps. First all components are loaded and corresponding objects are created. Constructors are supplied with corresponding configuration subtrees. During next step components are linked together by calling their Next() methods. Each call creates labeled link to next component in a chain. 2 step method has an advantage over single step because it allows loops in chains and makes loading procedure more simple. But that also means during short period of time components are only partly configured. Components in such state must produce proper error response if **Message** (p. 208) arrives. Note: Current implementation requires all components and links to be labeled. All labels must be unique. Future implementation will be able to assign labels automatically.

6.163.2 Constructor & Destructor Documentation

6.163.2.1 Arc::MCCLoader::MCCLoader (Config & cfg)

Constructor that takes whole XML configuration and creates component chains

 $\textbf{6.163.2.2} \quad Arc::MCCLoader::\sim MCCLoader (\quad)$

Destructor destroys all components created by constructor

6.163.3 Member Function Documentation


6.163.3.1 MCC* Arc::MCCLoader::operator[] (const std::string & id)

Access entry MCCs in chains. Those are components exposed for external access using 'entry' attribute The documentation for this class was generated from the following file:

· MCCLoader.h

6.164 Arc::MCCPluginArgument Class Reference

Inheritance diagram for Arc::MCCPluginArgument:



The documentation for this class was generated from the following file:


• MCC.h

6.165 Arc::MD5Sum Class Reference

Implementation of MD5 checksum.

#include <CheckSum.h>

Inheritance diagram for Arc::MD5Sum:



6.165.1 Detailed Description

Implementation of MD5 checksum.

The documentation for this class was generated from the following file:

· CheckSum.h

6.166 Arc::MemoryAllocationException Class Reference

The documentation for this class was generated from the following file:

• ByteArray.h

6.167 Arc::Message Class Reference

Object being passed through chain of MCCs.

#include <Message.h>

Public Member Functions

- Message (void)
- Message (Message &msg)
- Message (long msg_ptr_addr)
- ∼Message (void)
- Message & operator= (Message &msg)
- MessagePayload * Payload (void)
- MessagePayload * Payload (MessagePayload *payload)
- MessageAttributes * Attributes (void)
- MessageAuth * Auth (void)
- MessageContext * Context (void)
- MessageAuthContext * AuthContext (void)
- void Context (MessageContext *ctx)
- void AuthContext (MessageAuthContext *auth ctx)

6.167.1 Detailed Description

Object being passed through chain of MCCs. An instance of this class refers to objects with main content (MessagePayload (p. 216)), authentication/authorization information (MessageAuth (p. 213)) and common purpose attributes (MessageAttributes (p. 210)). Message (p. 208) class does not manage pointers to objects and their content. It only serves for grouping those objects. Message (p. 208) objects are supposed to be processed by MCCs and Services implementing MCCInterface (p. 205) method process(). All objects constituting content of Message (p. 208) object are subject to following policies:

- 1. All objects created inside call to process() method using new command must be explicitly destroyed within same call using delete command with following exceptions. a) Objects which are assigned to 'response' **Message** (p. 208). b) Objects whose management is completely acquired by objects assigned to 'response' **Message** (p. 208).
- 2. All objects not created inside call to process() method are not explicitly destroyed within that call with following exception. a) Objects which are part of 'response' Method returned from call to next's process() method. Unless those objects are passed further to calling process(), of course.
- 3. It is not allowed to make 'response' point to same objects as 'request' does on entry to process() method. That is needed to avoid double destruction of same object. (Note: if in a future such need arises it may be solved by storing additional flags in **Message** (p. 208) object).
- 4. It is allowed to change content of pointers of 'request' **Message** (p. 208). Calling process() method must not rely on that object to stay intact.
- 5. Called process() method should either fill 'response' **Message** (p. 208) with pointers to valid objects or to keep them intact. This makes it possible for calling process() to preload 'response' with valid error message.

6.167.2 Constructor & Destructor Documentation

6.167.2.1 Arc::Message::Message(void) [inline]

true if auth_ctx_ was created internally Dummy constructor

6.167.2.2 Arc::Message::Message (Message & msg) [inline]

Copy constructor. Ensures shallow copy.

6.167.2.3 Arc::Message::Message (long msg_ptr_addr)

Copy constructor. Used by language bindigs

6.167.2.4 Arc::Message::~Message (void) [inline]

Destructor does not affect refered objects except those created internally

6.167.3 Member Function Documentation

6.167.3.1 MessageAttributes* Arc::Message::Attributes(void) [inline]

Returns a pointer to the current attributes object or creates it if no attributes object has been assigned.

6.167.3.2 MessageAuth* Arc::Message::Auth(void) [inline]

Returns a pointer to the current authentication/authorization object or creates it if no object has been assigned.

6.167.3.3 MessageAuthContext* Arc::Message::AuthContext(void) [inline]

Returns a pointer to the current auth* context object or creates it if no object has been assigned.

6.167.3.4 void Arc::Message::AuthContext (MessageAuthContext * auth_ctx) [inline]

Assigns auth* context object

6.167.3.5 void Arc::Message::Context (MessageContext * ctx) [inline]

Assigns message context object

6.167.3.6 MessageContext* Arc::Message::Context(void) [inline]

Returns a pointer to the current context object or creates it if no object has been assigned. Last case should happen only if first MCC (p. 200) in a chain is connectionless like one implementing UDP protocol.

6.167.3.7 Message& Arc::Message::operator=(Message & msg) [inline]

Assignment. Ensures shallow copy.

6.167.3.8 MessagePayload* Arc::Message::Payload(void) [inline]

Returns pointer to current payload or NULL if no payload assigned.

6.167.3.9 MessagePayload* Arc::Message::Payload (MessagePayload * payload) [inline]

Replaces payload with new one. Returns the old one.

The documentation for this class was generated from the following file:

• Message.h

6.168 Arc::MessageAttributes Class Reference

A class for storage of attribute values.

#include <MessageAttributes.h>

Public Member Functions

- MessageAttributes ()
- void **set** (const std::string &key, const std::string &value)
- void add (const std::string &key, const std::string &value)
- void **removeAll** (const std::string &key)
- void **remove** (const std::string &key, const std::string &value)
- int count (const std::string &key) const
- const std::string & get (const std::string &key) const
- AttributeIterator getAll (const std::string &key) const
- AttributeIterator getAll (void) const

Protected Attributes

AttrMap attributes_

6.168.1 Detailed Description

A class for storage of attribute values. This class is used to store attributes of messages. All attribute keys and their corresponding values are stored as strings. Any key or value that is not a string must thus be represented as a string during storage. Furthermore, an attribute is usually a key-value pair with a unique key, but there may also be multiple such pairs with equal keys.

The key of an attribute is composed by the name of the **Message** (p. 208) Chain Component (**MCC** (p. 200)) which produce it and the name of the attribute itself with a colon (:) in between, i.e. MCC_Name:Attribute_Name. For example, the key of the "Content-Length" attribute of the HTTP **MCC** (p. 200) is thus "HTTP:Content-Length".

There are also "global attributes", which may be produced by different MCCs depending on the configuration. The keys of such attributes are NOT prefixed by the name of the producing MCC (p. 200). Before any new global attribute is introduced, it must be agreed upon by the core development team and added below. The global attributes decided so far are:

• Request-URI Identifies the service to which the message shall be sent. This attribute is produced by e.g. the HTTP MCC (p. 200) and used by the plexer for routing the message to the appropriate service.

6.168.2 Constructor & Destructor Documentation

6.168.2.1 Arc::MessageAttributes::MessageAttributes ()

The default constructor.

This is the default constructor of the **MessageAttributes** (p. 210) class. It constructs an empty object that initially contains no attributes.

6.168.3 Member Function Documentation

6.168.3.1 void Arc::MessageAttributes::add (const std::string & key, const std::string & value)

Adds a value to an attribute.

This method adds a new value to an attribute. Any previous value will be preserved, i.e. the attribute may become multiple valued.

Parameters

key The key of the attribute.

value The (new) value of the attribute.

6.168.3.2 int Arc::MessageAttributes::count (const std::string & key) const

Returns the number of values of an attribute.

Returns the number of values of an attribute that matches a certain key.

Parameters

key The key of the attribute for which to count values.

Returns

The number of values that corresponds to the key.

6.168.3.3 const std::string & Arc::MessageAttributes::get (const std::string & key) const

Returns the value of a single-valued attribute.

This method returns the value of a single-valued attribute. If the attribute is not single valued (i.e. there is no such attribute or it is a multiple-valued attribute) an empty string is returned.

Parameters

key The key of the attribute for which to return the value.

Returns

The value of the attribute.

6.168.3.4 AttributeIterator Arc::MessageAttributes::getAll (const std::string & key) const

Access the value(s) of an attribute.

This method returns an AttributeIterator (p. 53) that can be used to access the values of an attribute.

Parameters

key The key of the attribute for which to return the values.

Returns

An AttributeIterator (p. 53) for access of the values of the attribute.

6.168.3.5 void Arc::MessageAttributes::remove (const std::string & key, const std::string & value)

Removes one value of an attribute.

This method removes a certain value from the attribute that matches a certain key.

Parameters

key The key of the attribute from which the value shall be removed.

value The value to remove.

6.168.3.6 void Arc::MessageAttributes::removeAll (const std::string & key)

Removes all attributes with a certain key.

This method removes all attributes that match a certain key.

Parameters

key The key of the attributes to remove.

6.168.3.7 void Arc::MessageAttributes::set (const std::string & key, const std::string & value)

Sets a unique value of an attribute.

This method removes any previous value of an attribute and sets the new value as the only value.

Parameters

key The key of the attribute.

value The (new) value of the attribute.

6.168.4 Field Documentation

6.168.4.1 AttrMap Arc::MessageAttributes::attributes_ [protected]

Internal storage of attributes.

An AttrMap (multimap) in which all attributes (key-value pairs) are stored.

The documentation for this class was generated from the following file:


· MessageAttributes.h

6.169 Arc::MessageAuth Class Reference

Contains authencity information, authorization tokens and decisions.

#include <MessageAuth.h>

Inheritance diagram for Arc::MessageAuth:



Public Member Functions

- void set (const std::string &key, SecAttr *value)
- void **remove** (const std::string &key)
- SecAttr * get (const std::string &key)
- SecAttr * operator[] (const std::string &key)
- bool Export (SecAttrFormat format, XMLNode &val) const
- MessageAuth * Filter (const std::list< std::string > &selected_keys, const std::list< std::string > &rejected_keys)

6.169.1 Detailed Description

Contains authencity information, authorization tokens and decisions. This class only supports string keys and **SecAttr** (p. 278) values.

6.169.2 Member Function Documentation

6.169.2.1 bool Arc::MessageAuth::Export (SecAttrFormat format, XMLNode & val) const

Returns properly catenated attributes in specified format.

Content of XML node at is replaced with generated information if XML tree is empty. If tree at is not empty then **Export()** (p. 214) tries to merge generated information to already existing like everything would be generated inside same **Export()** (p. 214) method. If does not represent valid node then new XML tree is created.

Creates new instance of MessageAuth (p. 213) with attributes filtered.

In new instance all attributes with keys listed in are removed. If is not empty only corresponding attributes are transfered to new instance. Created instance does not own refered attributes. Hence parent instance must not be deleted as long as this one is in use.

The documentation for this class was generated from the following file:


· MessageAuth.h

6.170 Arc::MessageAuthContext Class Reference

Handler for content of message auth* context.

#include <Message.h>

Inheritance diagram for Arc::MessageAuthContext:



6.170.1 Detailed Description

Handler for content of message auth* context. This class is a container for authorization and authentication information. It gets associated with **Message** (p. 208) object usually by first **MCC** (p. 200) in a chain and is kept as long as connection persists.

The documentation for this class was generated from the following file:

· Message.h

6.171 Arc::MessageContext Class Reference

Handler for content of message context.

#include <Message.h>

Public Member Functions

• void Add (const std::string &name, MessageContextElement *element)

6.171.1 Detailed Description

Handler for content of message context. This class is a container for objects derived from **MessageContextElement** (p. 216). It gets associated with **Message** (p. 208) object usually by first **MCC** (p. 200) in a chain and is kept as long as connection persists.

6.171.2 Member Function Documentation

6.171.2.1 void Arc::MessageContext::Add (const std::string & name, MessageContextElement * element)

Provided element is taken over by this class. It is remembered by it and destroyed when this class is destroyed.

The documentation for this class was generated from the following file:


· Message.h

6.172 Arc::MessageContextElement Class Reference

Top class for elements contained in message context.

#include <Message.h>

Inheritance diagram for Arc::MessageContextElement:



6.172.1 Detailed Description

Top class for elements contained in message context. Objects of classes inherited with this one may be stored in **MessageContext** (p. 215) container.

The documentation for this class was generated from the following file:


· Message.h

6.173 Arc::MessagePayload Class Reference

Base class for content of message passed through chain.

#include <Message.h>

Inheritance diagram for Arc::MessagePayload:



6.173.1 Detailed Description

Base class for content of message passed through chain. It's not intended to be used directly. Instead functional classes must be derived from it.

The documentation for this class was generated from the following file:

· Message.h

6.174 Arc::ModuleDesc Class Reference

Description of loadable module.

#include <Plugin.h>

6.174.1 Detailed Description

Description of loadable module. This class is used for reports

The documentation for this class was generated from the following file:


• Plugin.h

6.175 Arc::ModuleManager Class Reference

Manager of shared libraries.

#include <ModuleManager.h>

Inheritance diagram for Arc::ModuleManager:



Public Member Functions

- ModuleManager (XMLNode cfg)
- Glib::Module * load (const std::string &name, bool probe=false)
- std::string **find** (const std::string &name)
- Glib::Module * reload (Glib::Module *module)
- void **unload** (Glib::Module *module)
- void unload (const std::string &name)
- std::string **findLocation** (const std::string &name)
- bool makePersistent (Glib::Module *module)
- bool makePersistent (const std::string &name)
- void setCfg (XMLNode cfg)

6.175.1 Detailed Description

Manager of shared libraries. This class loads shared libraries/modules. There supposed to be created one instance of it per executable. In such circumstances it would cache handles to loaded modules and not load them multiple times.

6.175.2 Constructor & Destructor Documentation

6.175.2.1 Arc::ModuleManager::ModuleManager (XMLNode cfg)

Cache of handles of loaded modules Constructor. It is supposed to process correponding configuration subtree and tune module loading parameters accordingly.

6.175.3 Member Function Documentation

6.175.3.1 std::string Arc::ModuleManager::find (const std::string & name)

Finds loadable module by 'name' looking in same places as load() (p. 218) does, but does not load it.

6.175.3.2 std::string Arc::ModuleManager::findLocation (const std::string & name)

Finds shared library corresponding to module 'name' and returns path to it

6.175.3.3 Glib::Module* Arc::ModuleManager::load (const std::string & name, bool probe = false)

Finds module 'name' in cache or loads corresponding loadable module

6.175.3.4 bool Arc::ModuleManager::makePersistent (const std::string & name)

Make sure this module is never unloaded. Even if unload() (p. 219) is called.

6.175.3.5 bool Arc::ModuleManager::makePersistent (Glib::Module * module)

Make sure this module is never unloaded. Even if **unload()** (p. 219) is called.

6.175.3.6 Glib::Module* Arc::ModuleManager::reload (Glib::Module * module)

Reload module previously loaded in probe mode. New module is loaded with all symbols resolved and old module handler is unloaded. In case of error old module is not unloaded.

6.175.3.7 void Arc::ModuleManager::setCfg (XMLNode cfg)

Input the configuration subtree, and trigger the module loading (do almost the same as the Constructor); It is function desgined for **ClassLoader** (p. 69) to adopt the singleton pattern

6.175.3.8 void Arc::ModuleManager::unload (const std::string & name)

Unload module by its name

6.175.3.9 void Arc::ModuleManager::unload (Glib::Module * module)

Unload module by its identifier

The documentation for this class was generated from the following file:


· ModuleManager.h

6.176 Arc::MultiSecAttr Class Reference

Container of multiple SecAttr (p. 278) attributes.

#include <SecAttr.h>

Inheritance diagram for Arc::MultiSecAttr:



Public Member Functions

- virtual operator bool () const
- virtual bool Export (SecAttrFormat format, XMLNode &val) const

6.176.1 Detailed Description

Container of multiple **SecAttr** (p. 278) attributes. This class combines multiple attributes. It's export/import methods catenate results of underlying objects. Primary meaning of this class is to serve as base for classes implementing multi level hierarchical tree-like descriptions of user identity. It may also be used for collecting information of same source or kind. Like all information extracted from X509 certificate.

6.176.2 Member Function Documentation

6.176.2.1 virtual bool Arc::MultiSecAttr::Export (SecAttrFormat format, XMLNode & val) const [virtual]

Convert internal structure into specified format. Returns false if format is not supported/suitable for this attribute. XML node referenced by is turned into top level element of specified format.

Reimplemented from Arc::SecAttr (p. 279).

6.176.2.2 virtual Arc::MultiSecAttr::operator bool () const [virtual]

This function should return false if the value is to be considered null, e.g. if it hasn't been set or initialized. In other cases it should return true.

Reimplemented from Arc::SecAttr (p. 279).


The documentation for this class was generated from the following file:

· SecAttr.h

6.177 Arc::MySQLDatabase Class Reference

#include <MysqlWrapper.h>

Inheritance diagram for Arc::MySQLDatabase:



Public Member Functions

- virtual bool **connect** (std::string &dbname, std::string &user, std::string &password)
- virtual bool isconnected () const
- virtual void close ()
- virtual bool **enable_ssl** (const std::string keyfile="", const std::string certfile="", const std::string cafile="", const std::string capath="")
- virtual bool shutdown ()

6.177.1 Detailed Description

Implement the database accessing interface in **DBInterface.h** (p. ??) by using mysql client library for accessing mysql database

6.177.2 Member Function Documentation

6.177.2.1 virtual void Arc::MySQLDatabase::close() [virtual]

Close the connection with database server

Implements Arc::Database (p. 99).

6.177.2.2 virtual bool Arc::MySQLDatabase::connect (std::string & dbname, std::string & user, std::string & password) [virtual]

Do connection with database server

Parameters

dbname The database name which will be used.

password The password which will be used to access database.

user The username which will be used to access database.

Implements Arc::Database (p. 99).

6.177.2.3 virtual bool Arc::MySQLDatabase::enable_ssl (const std::string keyfile = "", const std::string capth = "", const std::string capth = "") [virtual]

Enable ssl communication for the connection

Parameters

keyfile The location of key file.certfile The location of certificate file.cafile The location of ca file.capath The location of ca directory

Implements Arc::Database (p. 100).

6.177.2.4 virtual bool Arc::MySQLDatabase::isconnected () const [inline, virtual]

Get the connection status

Implements Arc::Database (p. 100).

6.177.2.5 virtual bool Arc::MySQLDatabase::shutdown() [virtual]

Ask database server to shutdown


Implements Arc::Database (p. 100).

The documentation for this class was generated from the following file:

• MysqlWrapper.h

6.178 Arc::MySQLQuery Class Reference

Inheritance diagram for Arc::MySQLQuery:



Public Member Functions

- virtual int **get_num_colums** ()
- virtual int **get_num_rows** ()
- virtual bool execute (const std::string &sqlstr)
- virtual QueryRowResult **get_row** (int row_number) const
- virtual QueryRowResult get_row () const
- virtual std::string **get_row_field** (int row_number, std::string &field_name)
- virtual bool **get_array** (std::string &sqlstr, QueryArrayResult &result, std::vector< std::string > &arguments)

6.178.1 Member Function Documentation

6.178.1.1 virtual bool Arc::MySQLQuery::execute (const std::string & sqlstr) [virtual]

Execute the query

Parameters

sqlstr The sql sentence used to query

Implements Arc::Query (p. 258).

6.178.1.2 virtual bool Arc::MySQLQuery::get_array (std::string & sqlstr, QueryArrayResult & result, std::vector< std::string > & arguments) [virtual]

Query (p. 257) the database by using some parameters into sql sentence e.g. "select table.value from table where table.name = ?"

Parameters

sqlstr The sql sentence with some parameters marked with "?".

result The result in an array which includes all of the value in query result.

arguments The argument list which should exactely correspond with the parametes in sql sentence.

Implements Arc::Query (p. 258).

6.178.1.3 virtual int Arc::MySQLQuery::get_num_colums() [virtual]

Get the colum number in the query result

Implements Arc::Query (p. 258).

6.178.1.4 virtual int Arc::MySQLQuery::get_num_rows() [virtual]

Get the row number in the query result

Implements Arc::Query (p. 258).

6.178.1.5 virtual QueryRowResult Arc::MySQLQuery::get_row (int row_number) const [virtual]

Get the value of one row in the query result

Parameters

row_number The number of the row

Returns

A vector includes all the values in the row

Implements Arc::Query (p. 258).

6.178.1.6 virtual QueryRowResult Arc::MySQLQuery::get_row() const [virtual]

Get the value of one row in the query result, the row number will be automatically increased each time the method is called

Implements Arc::Query (p. 259).

6.178.1.7 virtual std::string Arc::MySQLQuery::get_row_field (int row_number, std::string & field_name) [virtual]

Get the value of one specific field in one specific row

Parameters

```
row_number The row number inside the query resultfield_name The field name for the value which will be return
```

Returns

The value of the specified filed in the specified row

Implements Arc::Query (p. 259).

The documentation for this class was generated from the following file:

· MysqlWrapper.h

6.179 Arc::NotificationType Class Reference

The documentation for this class was generated from the following file:

· JobDescription.h

6.180 Arc::NS Class Reference

Public Member Functions

- NS (void)
- NS (const char *prefix, const char *uri)
- NS (const char *nslist[][2])


The documentation for this class was generated from the following file:

• XMLNode.h

6.181 Arc::OAuthConsumer Class Reference

#include <OAuthConsumer.h>

Inheritance diagram for Arc::OAuthConsumer:



Public Member Functions

- OAuthConsumer (const MCCConfig cfg, const URL url, std::list< std::string > idp_stack)
- MCC_Status parseDN (std::string *dn)
- MCC_Status approveCSR (const std::string approve_page)
- MCC_Status pushCSR (const std::string b64_pub_key, const std::string pub_key_hash, std::string *approve_page)
- MCC_Status storeCert (const std::string cert_path, const std::string auth_token, const std::string b64 dn)

Protected Member Functions

• MCC_Status processLogin (const std::string username="", const std::string password="")

6.181.1 Detailed Description

The OAuth functionality depends on the availability of the liboauth C-bindings library

6.181.2 Constructor & Destructor Documentation

6.181.2.1 Arc::OAuthConsumer::OAuthConsumer (const MCCConfig cfg, const URL url, std::list< std::string > idp_stack)

Construct an OAuth consumer with url as service provider. idp_name is currently ignored, since the idp to which the SAML2 redirect will take place is presently a hardcoded value on the SAML2 SP side. This is expected to change in the future.

6.181.3 Member Function Documentation

6.181.3.1 MCC_Status Arc::OAuthConsumer::approveCSR (const std::string approve_page)
[virtual]

Unsupported placeholder function until Confusa supports OAuth.

Implements Arc::SAML2LoginClient (p. 272).

6.181.3.2 MCC_Status Arc::OAuthConsumer::parseDN(std::string * dn) [virtual]

Unsupported placeholder function until Confusa supports OAuth.

Implements Arc::SAML2LoginClient (p. 272).

6.181.3.3 MCC_Status Arc::OAuthConsumer::processLogin (const std::string username = "", const std::string password = "") [protected, virtual]

Main function performing all the OAuth login steps. Username and password will be ignored.

Implements Arc::SAML2LoginClient (p. 273).

6.181.3.4 MCC_Status Arc::OAuthConsumer::pushCSR (const std::string b64_pub_key, const std::string pub_key_hash, std::string * approve_page) [virtual]

Unsupported placeholder function until Confusa supports OAuth.

Implements Arc::SAML2LoginClient (p. 272).

6.181.3.5 MCC_Status Arc::OAuthConsumer::storeCert (const std::string cert_path, const std::string auth_token, const std::string b64_dn) [virtual]

Unsupported placeholder function until Confusa supports OAuth.


Implements Arc::SAML2LoginClient (p. 272).

The documentation for this class was generated from the following file:

• OAuthConsumer.h

6.182 Arc::OpenIdpClient Class Reference

Inheritance diagram for Arc::OpenIdpClient:



Protected Member Functions

- MCC_Status processIdPLogin (const std::string username, const std::string password)
- MCC_Status processConsent ()
- MCC Status processIdP2Confusa ()

6.182.1 Member Function Documentation

6.182.1.1 MCC_Status Arc::OpenIdpClient::processConsent() [protected, virtual]

If the IdP has a consent module and the user has not saved her consent, this method will ask the user for consent to transmission of her data to Confusa

Implements Arc::SAML2SSOHTTPClient (p. 274).

6.182.1.2 MCC_Status Arc::OpenIdpClient::processIdP2Confusa() [protected, virtual]

Redirects the user back from identity provider to the Confusa SP

Implements Arc::SAML2SSOHTTPClient (p. 274).

6.182.1.3 MCC_Status Arc::OpenIdpClient::processIdPLogin (const std::string username, const std::string password) [protected, virtual]

Actual identity provider parsers for next three methods implemented in subdirectory idp/
Parse identity provider login page and submit username and password in the previsioned way
Implements Arc::SAML2SSOHTTPClient (p. 274).

The documentation for this class was generated from the following file:

· OpenIdpClient.h


6.183 Arc::OptionParser Class Reference

The documentation for this class was generated from the following file:

· OptionParser.h

6.184 ArcSec::OrderedCombiningAlg Class Reference

Inheritance diagram for ArcSec::OrderedCombiningAlg:



The documentation for this class was generated from the following file:

· OrderedAlg.h

6.185 passwd Struct Reference

The documentation for this struct was generated from the following file:

• win32.h

6.186 Arc::PathIterator Class Reference

Class to iterate through elements of path.

#include <URL.h>

Public Member Functions

- PathIterator (const std::string &path, bool end=false)
- PathIterator & operator++ ()
- PathIterator & operator-- ()
- operator bool () const
- std::string operator* () const
- std::string Rest () const

6.186.1 Detailed Description

Class to iterate through elements of path.

6.186.2 Constructor & Destructor Documentation

6.186.2.1 Arc::PathIterator::PathIterator (const std::string & path, bool end = false)

Constructor accepts path and stores it internally. If end is set to false iterator is pointing at first element in path. Otherwise selected element is one before last.

6.186.3 Member Function Documentation

6.186.3.1 Arc::PathIterator::operator bool () const

Return false when iterator moved outside path elements

6.186.3.2 std::string Arc::PathIterator::operator*() const

Returns part of initial path from first till and including current

6.186.3.3 PathIterator& Arc::PathIterator::operator++ ()

Advances iterator to point at next path element

6.186.3.4 PathIterator& Arc::PathIterator::operator-- ()

Moves iterator to element before current

6.186.3.5 std::string Arc::PathIterator::Rest () const

Returns part of initial path from one after current till end

The documentation for this class was generated from the following file:


• URL.h

6.187 Arc::PayloadRaw Class Reference

Raw byte multi-buffer.

#include <PayloadRaw.h>

Inheritance diagram for Arc::PayloadRaw:



Public Member Functions

- PayloadRaw (void)
- virtual ∼PayloadRaw (void)
- virtual char **operator**[] (Size_t pos) const
- virtual char * Content (Size_t pos=-1)
- virtual Size_t Size (void) const
- virtual char * **Insert** (Size_t pos=0, Size_t size=0)
- virtual char * Insert (const char *s, Size_t pos=0, Size_t size=-1)
- virtual char * **Buffer** (unsigned int num=0)
- virtual Size_t BufferSize (unsigned int num=0) const
- virtual Size_t **BufferPos** (unsigned int num=0) const
- virtual bool **Truncate** (Size_t size)

6.187.1 Detailed Description

Raw byte multi-buffer. This is implementation of **PayloadRawInterface** (p. 230). Buffers are memory blocks logically placed one after another.

6.187.2 Constructor & Destructor Documentation

6.187.2.1 Arc::PayloadRaw::PayloadRaw(void) [inline]

List of handled buffers. Constructor. Created object contains no buffers.

6.187.2.2 virtual Arc::PayloadRaw::~PayloadRaw(void) [virtual]

Destructor. Frees allocated buffers.

6.187.3 Member Function Documentation

6.187.3.1 virtual char* Arc::PayloadRaw::Buffer (unsigned int num = 0) [virtual]

Returns pointer to num'th buffer

Implements Arc::PayloadRawInterface (p. 231).

6.187.3.2 virtual Size_t Arc::PayloadRaw::BufferPos (unsigned int *num* = 0) const [virtual]

Returns position of num'th buffer

Implements Arc::PayloadRawInterface (p. 231).

6.187.3.3 virtual Size_t Arc::PayloadRaw::BufferSize (unsigned int *num* = 0) const [virtual]

Returns length of num'th buffer

Implements Arc::PayloadRawInterface (p. 232).

6.187.3.4 virtual char* Arc::PayloadRaw::Content (Size_t pos = -1) [virtual]

Get pointer to buffer content at global position 'pos'. By default to beginning of main buffer whatever that means.

Implements Arc::PayloadRawInterface (p. 232).

6.187.3.5 virtual char* Arc::PayloadRaw::Insert (Size_t pos = 0, Size_t size = 0) [virtual]

Create new buffer at global position 'pos' of size 'size'.

 $Implements \ \boldsymbol{Arc::} \boldsymbol{Payload Raw Interface} \ \ (p.~232).$

6.187.3.6 virtual char* Arc::PayloadRaw::Insert (const char * s, Size_t pos = 0, Size_t size = -1) [virtual]

Create new buffer at global position 'pos' of size 'size'. Created buffer is filled with content of memory at 's'. If 'size' is negative content at 's' is expected to be null-terminated.

Implements Arc::PayloadRawInterface (p. 232).

6.187.3.7 virtual char Arc::PayloadRaw::operator[](Size_t pos) const [virtual]

Returns content of byte at specified position. Specified position 'pos' is treated as global one and goes through all buffers placed one after another.

Implements Arc::PayloadRawInterface (p. 232).

6.187.3.8 virtual Size_t Arc::PayloadRaw::Size (void) const [virtual]

Returns logical size of whole structure.

Implements Arc::PayloadRawInterface (p. 232).

6.187.3.9 virtual bool Arc::PayloadRaw::Truncate (Size_t size) [virtual]

Change size of stored information. If size exceeds end of allocated buffer, buffers are not re-allocated, only logical size is extended. Buffers with location behind new size are deallocated.

Implements Arc::PayloadRawInterface (p. 232).

The documentation for this class was generated from the following file:

· PayloadRaw.h

6.188 Arc::PayloadRawBuf Struct Reference

Data Fields

- int size
- int length
- bool allocated

6.188.1 Field Documentation

6.188.1.1 bool Arc::PayloadRawBuf::allocated

size of used memory - size of buffer

6.188.1.2 int Arc::PayloadRawBuf::length

size of allocated memory

6.188.1.3 int Arc::PayloadRawBuf::size

pointer to buffer in memory

The documentation for this struct was generated from the following file:


· PayloadRaw.h

6.189 Arc::PayloadRawInterface Class Reference

Random Access Payload for Message (p. 208) objects.

#include <PayloadRaw.h>

Inheritance diagram for Arc::PayloadRawInterface:



Public Member Functions

- virtual char **operator**[] (Size_t pos) const =0
- virtual char * Content (Size_t pos=-1)=0
- virtual Size_t Size (void) const =0
- virtual char * **Insert** (Size_t pos=0, Size_t size=0)=0
- virtual char * **Insert** (const char *s, Size_t pos=0, Size_t size=-1)=0
- virtual char * **Buffer** (unsigned int num)=0
- virtual Size_t **BufferSize** (unsigned int num) const =0
- virtual Size_t **BufferPos** (unsigned int num) const =0
- virtual bool **Truncate** (Size_t size)=0

6.189.1 Detailed Description

Random Access Payload for **Message** (p. 208) objects. This class is a virtual interface for managing **Message** (p. 208) payload with arbitrarily accessible content. Inheriting classes are supposed to implement memory-resident or memory-mapped content made of optionally multiple chunks/buffers. Every buffer has own size and offset. This class is purely virtual.

6.189.2 Member Function Documentation

6.189.2.1 virtual char* Arc::PayloadRawInterface::Buffer (unsigned int *num*) [pure virtual]

Returns pointer to num'th buffer

Implemented in Arc::PayloadRaw (p. 229).

6.189.2.2 virtual Size_t Arc::PayloadRawInterface::BufferPos (unsigned int *num*) const [pure virtual]

Returns position of num'th buffer

Implemented in Arc::PayloadRaw (p. 229).

6.189.2.3 virtual Size_t Arc::PayloadRawInterface::BufferSize (unsigned int *num*) const [pure virtual]

Returns length of num'th buffer

Implemented in Arc::PayloadRaw (p. 229).

6.189.2.4 virtual char* Arc::PayloadRawInterface::Content (Size_t pos = -1) [pure virtual]

Get pointer to buffer content at global position 'pos'. By default to beginning of main buffer whatever that means.

Implemented in Arc::PayloadRaw (p. 229).

6.189.2.5 virtual char* Arc::PayloadRawInterface::Insert (Size_t pos = 0, Size_t size = 0) [pure virtual]

Create new buffer at global position 'pos' of size 'size'.

Implemented in Arc::PayloadRaw (p. 229).

6.189.2.6 virtual char* Arc::PayloadRawInterface::Insert (const char * s, Size_t pos = 0, Size_t size = -1) [pure virtual]

Create new buffer at global position 'pos' of size 'size'. Created buffer is filled with content of memory at 's'. If 'size' is negative content at 's' is expected to be null-terminated.

Implemented in Arc::PayloadRaw (p. 229).

6.189.2.7 virtual char Arc::PayloadRawInterface::operator[](Size_t pos) const [pure virtual]

Returns content of byte at specified position. Specified position 'pos' is treated as global one and goes through all buffers placed one after another.

Implemented in Arc::PayloadRaw (p. 229).

6.189.2.8 virtual Size_t Arc::PayloadRawInterface::Size (void) const [pure virtual]

Returns logical size of whole structure.

Implemented in Arc::PayloadRaw (p. 230).

6.189.2.9 virtual bool Arc::PayloadRawInterface::Truncate (Size_t size) [pure virtual]

Change size of stored information. If size exceeds end of allocated buffer, buffers are not re-allocated, only logical size is extended. Buffers with location behind new size are deallocated.

Implemented in Arc::PayloadRaw (p. 230).

The documentation for this class was generated from the following file:


· PayloadRaw.h

6.190 Arc::PayloadSOAP Class Reference

Payload of Message (p. 208) with SOAP content.

#include <PayloadSOAP.h>

Inheritance diagram for Arc::PayloadSOAP:



Public Member Functions

- PayloadSOAP (const NS &ns, bool fault=false)
- PayloadSOAP (const SOAPEnvelope &soap)
- PayloadSOAP (const MessagePayload &source)

6.190.1 Detailed Description

Payload of **Message** (p. 208) with SOAP content. This class combines **MessagePayload** (p. 216) with SOAPEnvelope to make it possible to pass SOAP messages through **MCC** (p. 200) chain.

6.190.2 Constructor & Destructor Documentation

6.190.2.1 Arc::PayloadSOAP::PayloadSOAP (const NS & ns, bool fault = false)

Constructor - creates new Message (p. 208) payload

6.190.2.2 Arc::PayloadSOAP::PayloadSOAP (const SOAPEnvelope & soap)

Constructor - creates **Message** (p. 208) payload from SOAP document. Provided SOAP document is copied to new object.

6.190.2.3 Arc::PayloadSOAP::PayloadSOAP (const MessagePayload & source)

Constructor - creates SOAP message from payload. **PayloadRawInterface** (p. 230) and derived classes are supported.

The documentation for this class was generated from the following file:


· PayloadSOAP.h

6.191 Arc::PayloadStream Class Reference

POSIX handle as Payload.

#include <PayloadStream.h>

Inheritance diagram for Arc::PayloadStream:



Public Member Functions

- **PayloadStream** (int h=-1)
- virtual ~PayloadStream (void)
- virtual bool Get (char *buf, int &size)
- virtual bool **Get** (std::string &buf)
- virtual std::string Get (void)
- virtual bool **Put** (const char *buf, Size_t size)
- virtual bool **Put** (const std::string &buf)
- virtual bool **Put** (const char *buf)
- virtual operator bool (void)
- virtual bool operator! (void)
- virtual int Timeout (void) const
- virtual void **Timeout** (int to)
- virtual Size_t Pos (void) const
- virtual Size_t Size (void) const
- virtual Size_t Limit (void) const

Protected Attributes

- int handle
- bool seekable_

6.191.1 Detailed Description

POSIX handle as Payload. This is an implementation of **PayloadStreamInterface** (p. 237) for generic POSIX handle.

6.191.2 Constructor & Destructor Documentation

6.191.2.1 Arc::PayloadStream::PayloadStream (int h = -1)

true if Iseek operation is applicable to open handle Constructor. Attaches to already open handle. Handle is not managed by this class and must be closed by external code.

6.191.2.2 virtual Arc::PayloadStream::~PayloadStream(void) [inline, virtual]

Destructor.

6.191.3 Member Function Documentation

6.191.3.1 virtual bool Arc::PayloadStream::Get (char * buf, int & size) [virtual]

Extracts information from stream up to 'size' bytes. 'size' contains number of read bytes on exit. Returns true in case of success.

Implements Arc::PayloadStreamInterface (p. 238).

6.191.3.2 virtual bool Arc::PayloadStream::Get (std::string & buf) [virtual]

Read as many as possible (sane amount) of bytes into buf.

Implements Arc::PayloadStreamInterface (p. 238).

6.191.3.3 virtual std::string Arc::PayloadStream::Get(void) [inline, virtual]

Read as many as possible (sane amount) of bytes.

Implements Arc::PayloadStreamInterface (p. 238).

References Get().

Referenced by Get().

6.191.3.4 virtual Size_t Arc::PayloadStream::Limit(void)const [inline, virtual]

Returns position at which stream reading will stop if supported. That may be not same as **Size()** (p. 236) if instance is meant to provide access to only part of underlying obejct.

Implements Arc::PayloadStreamInterface (p. 238).

6.191.3.5 virtual Arc::PayloadStream::operator bool (void) [inline, virtual]

Returns true if stream is valid.

Implements Arc::PayloadStreamInterface (p. 238).

References handle_.

6.191.3.6 virtual bool Arc::PayloadStream::operator! (void) [inline, virtual]

Returns true if stream is invalid.

Implements Arc::PayloadStreamInterface (p. 238).

References handle_.

6.191.3.7 virtual Size_t Arc::PayloadStream::Pos (void) const [inline, virtual]

Returns current position in stream if supported.

Implements Arc::PayloadStreamInterface (p. 238).

6.191.3.8 virtual bool Arc::PayloadStream::Put (const char * buf, Size t size) [virtual]

Push 'size' bytes from 'buf' into stream. Returns true on success.

Implements Arc::PayloadStreamInterface (p. 239).

6.191.3.9 virtual bool Arc::PayloadStream::Put(const char * buf) [inline, virtual]

Push null terminated information from 'buf' into stream. Returns true on success.

Implements Arc::PayloadStreamInterface (p. 239).

References Put().

Referenced by Put().

6.191.3.10 virtual bool Arc::PayloadStream::Put (const std::string & buf) [inline, virtual]

Push information from 'buf' into stream. Returns true on success.

Implements Arc::PayloadStreamInterface (p. 239).

References Put().

Referenced by Put().

6.191.3.11 virtual Size_t Arc::PayloadStream::Size(void)const [inline, virtual]

Returns size of underlying object if supported.

Implements Arc::PayloadStreamInterface (p. 239).

6.191.3.12 virtual int Arc::PayloadStream::Timeout (void) const [inline, virtual]

Query (p. 257) current timeout for Get() (p. 235) and Put() (p. 236) operations.

Implements Arc::PayloadStreamInterface (p. 239).

6.191.3.13 virtual void Arc::PayloadStream::Timeout(int to) [inline, virtual]

Set current timeout for **Get()** (p. 235) and **Put()** (p. 236) operations.

Implements Arc::PayloadStreamInterface (p. 239).

6.191.4 Field Documentation

6.191.4.1 int Arc::PayloadStream::handle_ [protected]

Timeout for read/write operations

Referenced by operator bool(), and operator!().

6.191.4.2 bool Arc::PayloadStream::seekable_ [protected]

Handle for operations

The documentation for this class was generated from the following file:


· PayloadStream.h

6.192 Arc::PayloadStreamInterface Class Reference

Stream-like Payload for Message (p. 208) object.

#include <PayloadStream.h>

Inheritance diagram for Arc::PayloadStreamInterface:



Public Member Functions

- virtual bool **Get** (char *buf, int &size)=0
- virtual bool **Get** (std::string &buf)=0
- virtual std::string **Get** (void)=0
- virtual bool **Put** (const char *buf, Size_t size)=0
- virtual bool **Put** (const std::string &buf)=0
- virtual bool **Put** (const char *buf)=0
- virtual **operator bool** (void)=0
- virtual bool **operator!** (void)=0
- virtual int **Timeout** (void) const =0
- virtual void **Timeout** (int to)=0
- virtual Size_t **Pos** (void) const =0
- virtual Size_t Size (void) const =0
- virtual Size t **Limit** (void) const =0

6.192.1 Detailed Description

Stream-like Payload for **Message** (p. 208) object. This class is a virtual interface for managing stream-like source and destination. It's supposed to be passed through **MCC** (p. 200) chain as payload of **Message** (p. 208). It must be treated by MCCs and Services as dynamic payload. This class is purely virtual.

6.192.2 Member Function Documentation

6.192.2.1 virtual bool Arc::PayloadStreamInterface::Get (char * buf, int & size) [pure virtual]

Extracts information from stream up to 'size' bytes. 'size' contains number of read bytes on exit. Returns true in case of success.

Implemented in Arc::PayloadStream (p. 235).

6.192.2.2 virtual bool Arc::PayloadStreamInterface::Get (std::string & buf) [pure virtual]

Read as many as possible (sane amount) of bytes into buf.

Implemented in Arc::PayloadStream (p. 235).

6.192.2.3 virtual std::string Arc::PayloadStreamInterface::Get(void) [pure virtual]

Read as many as possible (sane amount) of bytes.

Implemented in Arc::PayloadStream (p. 235).

6.192.2.4 virtual Size_t Arc::PayloadStreamInterface::Limit (void) const [pure virtual]

Returns position at which stream reading will stop if supported. That may be not same as **Size()** (p. 239) if instance is meant to provide access to only part of underlying obejct.

Implemented in Arc::PayloadStream (p. 235).

6.192.2.5 virtual Arc::PayloadStreamInterface::operator bool (void) [pure virtual]

Returns true if stream is valid.

Implemented in Arc::PayloadStream (p. 235).

6.192.2.6 virtual bool Arc::PayloadStreamInterface::operator! (void) [pure virtual]

Returns true if stream is invalid.

Implemented in Arc::PayloadStream (p. 235).

6.192.2.7 virtual Size_t Arc::PayloadStreamInterface::Pos (void) const [pure virtual]

Returns current position in stream if supported.

Implemented in **Arc::PayloadStream** (p. 236).

6.192.2.8 virtual bool Arc::PayloadStreamInterface::Put (const char * buf, Size_t size) [pure virtual]

Push 'size' bytes from 'buf' into stream. Returns true on success.

Implemented in Arc::PayloadStream (p. 236).

6.192.2.9 virtual bool Arc::PayloadStreamInterface::Put (const char * buf) [pure virtual]

Push null terminated information from 'buf' into stream. Returns true on success.

Implemented in Arc::PayloadStream (p. 236).

$6.192.2.10 \quad \text{virtual bool Arc::PayloadStreamInterface::Put (\ const \ std::string \& \ \textit{buf} \) \quad \texttt{[purevirtual]}$

Push information from 'buf' into stream. Returns true on success.

Implemented in Arc::PayloadStream (p. 236).

6.192.2.11 virtual Size_t Arc::PayloadStreamInterface::Size (void) const [pure virtual]

Returns size of underlying object if supported.

Implemented in Arc::PayloadStream (p. 236).

6.192.2.12 virtual int Arc::PayloadStreamInterface::Timeout (void)const [pure virtual]

Query (p. 257) current timeout for Get() (p. 238) and Put() (p. 239) operations.

Implemented in Arc::PayloadStream (p. 236).

6.192.2.13 virtual void Arc::PayloadStreamInterface::Timeout (int to) [pure virtual]

Set current timeout for **Get()** (p. 238) and **Put()** (p. 239) operations.

Implemented in Arc::PayloadStream (p. 236).

The documentation for this class was generated from the following file:


· PayloadStream.h

6.193 Arc::PayloadWSRF Class Reference

This class combines MessagePayload (p. 216) with WSRF (p. 367).

#include <PayloadWSRF.h>

Inheritance diagram for Arc::PayloadWSRF:



Public Member Functions

- PayloadWSRF (const SOAPEnvelope &soap)
- PayloadWSRF (WSRF &wsrp)
- PayloadWSRF (const MessagePayload &source)

6.193.1 Detailed Description

This class combines **MessagePayload** (p. 216) with **WSRF** (p. 367). It's intention is to make it possible to pass **WSRF** (p. 367) messages through **MCC** (p. 200) chain as one more Payload type.

6.193.2 Constructor & Destructor Documentation

6.193.2.1 Arc::PayloadWSRF::PayloadWSRF (const SOAPEnvelope & soap)

Constructor - creates **Message** (p. 208) payload from SOAP message. Returns invalid **WSRF** (p. 367) if SOAP does not represent WS-ResourceProperties

6.193.2.2 Arc::PayloadWSRF::PayloadWSRF (WSRF & wsrp)

Constructor - creates **Message** (p. 208) payload with acquired **WSRF** (p. 367) message. **WSRF** (p. 367) message will be destroyed by destructor of this object.

6.193.2.3 Arc::PayloadWSRF::PayloadWSRF (const MessagePayload & source)

Constructor - creates **WSRF** (p. 367) message from payload. All classes derived from SOAPEnvelope are supported.

The documentation for this class was generated from the following file:

· PayloadWSRF.h

6.194 ArcSec::PDP Class Reference

Base class for **Policy** (p. 252) Decision Point plugins.

#include <PDP.h>

Inheritance diagram for ArcSec::PDP:



6.194.1 Detailed Description


Base class for **Policy** (p. 252) Decision Point plugins. This virtual class defines method isPermitted() which processes security related information/attributes in Message and makes security decision - permit (true) or deny (false). Configuration of **PDP** (p. 240) is consumed during creation of instance through XML subtree fed to constructor.

The documentation for this class was generated from the following file:

• PDP.h

6.195 ArcSec::PDPConfigContext Class Reference

Inheritance diagram for ArcSec::PDPConfigContext:




The documentation for this class was generated from the following file:

• PDP.h

6.196 ArcSec::PDPPluginArgument Class Reference

Inheritance diagram for ArcSec::PDPPluginArgument:



The documentation for this class was generated from the following file:

• PDP.h

6.197 Arc::Period Class Reference

Public Member Functions

- Period ()
- **Period** (time t)
- **Period** (time_t seconds, uint32_t nanoseconds)
- Period (const std::string &, PeriodBase base=PeriodSeconds)
- **Period** & **operator**= (time_t)
- Period & operator= (const Period &)
- void **SetPeriod** (time t)
- time t GetPeriod () const
- const sigc::slot< const char * > * **istr** () const
- operator std::string () const
- bool **operator**< (const **Period** &) const
- bool operator> (const Period &) const
- bool operator<= (const Period &) const
- bool **operator**>= (const **Period** &) const
- bool operator== (const Period &) const
- bool operator!= (const Period &) const

6.197.1 Constructor & Destructor Documentation

6.197.1.1 Arc::Period::Period ()

Default constructor. The period is set to 0 length.

6.197.1.2 Arc::Period::Period (time_t)

Constructor that takes a time t variable and stores it.

6.197.1.3 Arc::Period::Period (time_t seconds, uint32_t nanoseconds)

Constructor that takes seconds and nanoseconds and stores them.

6.197.1.4 Arc::Period::Period (const std::string & , PeriodBase base = PeriodSeconds)

Constructor that tries to convert a string.

6.197.2 Member Function Documentation

6.197.2.1 time_t Arc::Period::GetPeriod() const

gets the period

6.197.2.2 const sigc::slot<const char*>* Arc::Period::istr () const

For use with **IString** (p. 182)

6.197.2.3 Arc::Period::operator std::string () const

Returns a string representation of the period.

6.197.2.4 bool Arc::Period::operator!= (const Period &) const

Comparing two **Period** (p. 242) objects.

$\textbf{6.197.2.5} \quad bool \ Arc:: Period:: operator < (\ \ const \ Period \ \& \ \) \ const$

Comparing two **Period** (p. 242) objects.

6.197.2.6 bool Arc::Period::operator<= (const Period &) const

Comparing two **Period** (p. 242) objects.

6.197.2.7 Period& Arc::Period::operator= (time_t)

Assignment operator from a time_t.

6.197.2.8 Period& Arc::Period::operator= (const Period &)

Assignment operator from a **Period** (p. 242).

6.197.2.9 bool Arc::Period::operator== (const Period &) const

Comparing two **Period** (p. 242) objects.

$\textbf{6.197.2.10} \quad bool \ Arc:: Period:: operator > (\ \ const \ Period \ \& \ \) \ const$

Comparing two **Period** (p. 242) objects.

6.197.2.11 bool Arc::Period::operator>= (const Period &) const

Comparing two **Period** (p. 242) objects.

6.197.2.12 void Arc::Period::SetPeriod (time_t)

sets the period


The documentation for this class was generated from the following file:

• DateTime.h

6.198 ArcSec::PeriodAttribute Class Reference

#include <DateTimeAttribute.h>

Inheritance diagram for ArcSec::PeriodAttribute:



Public Member Functions

- virtual bool equal (AttributeValue *other, bool check_id=true)
- virtual std::string **encode** ()
- virtual std::string **getType** ()
- virtual std::string getId ()

6.198.1 Detailed Description

Formate: datetime"/"duration datetime"/"datetime duration"/"datetime

6.198.2 Member Function Documentation

6.198.2.1 virtual std::string ArcSec::PeriodAttribute::encode() [virtual]

encode the value in a string format

Implements ArcSec::AttributeValue (p. 57).

6.198.2.2 virtual bool ArcSec::PeriodAttribute::equal (AttributeValue * value, bool check_id = true) [virtual]

Evluate whether "this" equale to the parameter value

Implements ArcSec::AttributeValue (p. 58).

6.198.2.3 virtual std::string ArcSec::PeriodAttribute::getId() [inline, virtual]

Get the AttributeId of the <Attribute>

Implements ArcSec::AttributeValue (p. 58).

6.198.2.4 virtual std::string ArcSec::PeriodAttribute::getType() [inline, virtual]

Get the DataType of the <Attribute>

Implements ArcSec::AttributeValue (p. 58).

The documentation for this class was generated from the following file:


• DateTimeAttribute.h

6.199 ArcSec::PermitOverridesCombiningAlg Class Reference

Implement the "Permit-Overrides" algorithm.

#include <PermitOverridesAlq.h>

Inheritance diagram for ArcSec::PermitOverridesCombiningAlg:



Public Member Functions

- virtual Result **combine** (**EvaluationCtx** *ctx, std::list< **Policy** * > policies)
- virtual const std::string & getalgId (void) const

6.199.1 Detailed Description

Implement the "Permit-Overrides" algorithm. Permit-Overrides, scans the policy set which is given as the parameters of "combine" method, if gets "permit" result from any policy, then stops scanning and gives "permit" as result, otherwise gives "deny".

6.199.2 Member Function Documentation

6.199.2.1 virtual Result ArcSec::PermitOverridesCombiningAlg::combine (EvaluationCtx * ctx, std::list< Policy * > policies) [virtual]

If there is one policy which return positive evaluation result, then omit the other policies and return DECISION PERMIT

Parameters

ctx This object contains request information which will be used to evaluated against policy.policlies This is a container which contains policy objects.

Returns

The combined result according to the algorithm.

Implements ArcSec::CombiningAlg (p. 76).

6.199.2.2 virtual const std::string& ArcSec::PermitOverridesCombiningAlg::getalgId (void) const [inline, virtual]

Get the identifier

Implements ArcSec::CombiningAlg (p. 76).

The documentation for this class was generated from the following file:


• PermitOverridesAlg.h

6.200 Arc::Plexer Class Reference

The **Plexer** (p. 246) class, used for routing messages to services.

#include <Plexer.h>

Inheritance diagram for Arc::Plexer:



Public Member Functions

- Plexer (Config *cfg)
- virtual ∼**Plexer** ()
- virtual void **Next** (**MCCInterface** *next, const std::string &label)
- virtual MCC_Status process (Message &request, Message &response)

Static Public Attributes

• static Logger logger

6.200.1 Detailed Description

The **Plexer** (p. 246) class, used for routing messages to services. This is the **Plexer** (p. 246) class. Its purpose is to route incoming messages to appropriate Services and **MCC** (p. 200) chains.

6.200.2 Constructor & Destructor Documentation

6.200.2.1 Arc::Plexer::Plexer (Config * cfg)

The constructor.

This is the constructor. Since all member variables are instances of "well-behaving" STL classes, nothing needs to be done.

6.200.2.2 virtual Arc::Plexer::~Plexer() [virtual]

The destructor.

This is the destructor. Since all member variables are instances of "well-behaving" STL classes, nothing needs to be done.

6.200.3 Member Function Documentation

6.200.3.1 virtual void Arc::Plexer::Next (MCCInterface * next, const std::string & label) [virtual]

Add reference to next MCC (p. 200) in chain.

This method is called by **Loader** (p. 189) for every potentially labeled link to next component which implements **MCCInterface** (p. 205). If next is set NULL corresponding link is removed.

Reimplemented from **Arc::MCC** (p. 201).

6.200.3.2 virtual MCC_Status Arc::Plexer::process (Message & request, Message & response) [virtual]

Route request messages to appropriate services.

Routes the request message to the appropriate service. Routing is based on the path part of value of the ENDPOINT attribute. Routed message is assigned following attributes: PLEXER:PATTERN - matched pattern, PLEXER:EXTENSION - last unmatched part of ENDPOINT path.

Reimplemented from Arc::MCC (p. 201).

6.200.4 Field Documentation

6.200.4.1 Logger Arc::Plexer::logger [static]

A logger for MCCs.

A logger intended to be the parent of loggers in the different MCCs.

Reimplemented from Arc::MCC (p. 202).

The documentation for this class was generated from the following file:

· Plexer.h

6.201 Arc::PlexerEntry Class Reference

A pair of label (regex) and pointer to MCC (p. 200).

#include <Plexer.h>

6.201.1 Detailed Description

A pair of label (regex) and pointer to MCC (p. 200). A helper class that stores a label (regex) and a pointer to a service.

The documentation for this class was generated from the following file:


• Plexer.h

6.202 Arc::Plugin Class Reference

Base class for loadable ARC components.

#include <Plugin.h>

Inheritance diagram for Arc::Plugin:



6.202.1 Detailed Description

Base class for loadable ARC components. All classes representing loadable ARC components must be either descendants of this class or be wrapped by its offspring.

The documentation for this class was generated from the following file:


• Plugin.h

6.203 Arc::PluginArgument Class Reference

Base class for passing arguments to loadable ARC components.

#include <Plugin.h>

Inheritance diagram for Arc::PluginArgument:



Public Member Functions

- PluginsFactory * get_factory (void)
- Glib::Module * get_module (void)

6.203.1 Detailed Description

Base class for passing arguments to loadable ARC components. During its creation constructor function of ARC loadable component expects instance of class inherited from this one or wrapped in it. Then dynamic type casting is used for obtaining class of expected kind.

6.203.2 Member Function Documentation

6.203.2.1 PluginsFactory* Arc::PluginArgument::get_factory (void)

Returns pointer to factory which instantiated plugin.

Because factory usually destroys/unloads plugins in its destructor it should be safe to keep this pointer inside plugin for later use. But one must always check.

6.203.2.2 Glib::Module* Arc::PluginArgument::get_module (void)

Returns pointer to loadable module/library which contains plugin.

Corresponding factory keeps list of modules till itself is destroyed. So it should be safe to keep that pointer. But care must be taken if module contains persistent plugins. Such modules stay in memory after factory is detroyed. So it is advisable to use obtained pointer only in constructor function of plugin.

The documentation for this class was generated from the following file:

• Plugin.h

6.204 Arc::PluginDesc Class Reference

Description of plugin.

#include <Plugin.h>

6.204.1 Detailed Description

Description of plugin. This class is used for reports

The documentation for this class was generated from the following file:

• Plugin.h

6.205 Arc::PluginDescriptor Struct Reference

Description of ARC lodable component.

#include <Plugin.h>

6.205.1 Detailed Description

Description of ARC lodable component.

The documentation for this struct was generated from the following file:


• Plugin.h

6.206 Arc::PluginsFactory Class Reference

Generic ARC plugins loader.

#include <Plugin.h>

Inheritance diagram for Arc::PluginsFactory:



Public Member Functions

- PluginsFactory (XMLNode cfg)
- void **TryLoad** (bool v=true)
- bool load (const std::string &name)
- bool scan (const std::string &name, ModuleDesc &desc)
- void **report** (std::list< **ModuleDesc** > &descs)

6.206.1 Detailed Description

Generic ARC plugins loader. The instance of this class provides functionality of loading pluggable ARC components stored in shared libraries. For more information please check HED documentation. This class is thread-safe - its methods are proceed from simultaneous use form multiple threads. Current thread protection implementation is suboptimal and will be revised in future.

6.206.2 Constructor & Destructor Documentation

6.206.2.1 Arc::PluginsFactory::PluginsFactory (XMLNode cfg)

Constructor - accepts configuration (not yet used) meant to tune loading of modules.

6.206.3 Member Function Documentation

6.206.3.1 bool Arc::PluginsFactory::load (const std::string & name)

These methods load module named lib'name' and check if it contains ARC plugin(s) of specified 'kind' and 'name'. If there are no specified plugins or module does not contain any ARC plugins it is unloaded. All loaded plugins are also registered in internal list of this instance of **PluginsFactory** (p. 250) class. Returns true if any plugin was loaded.

6.206.3.2 void Arc::PluginsFactory::report (std::list< ModuleDesc > & descs)

Provides information about currently loaded modules and plugins.

6.206.3.3 bool Arc::PluginsFactory::scan (const std::string & name, ModuleDesc & desc)

Collect information about plugins stored in module(s) with specified names. Returns true if any of specified modules has plugins.

6.206.3.4 void Arc::PluginsFactory::TryLoad (bool v = true) [inline]

These methods load module named lib'name', locate plugin constructor functions of specified 'kind' and 'name' (if specified) and call it. Supplied argument affects way plugin instance is created in plugin-specific way. If name of plugin is not specified then all plugins of specified kind are tried with supplied argument till valid instance is created. All loaded plugins are also registered in internal list of this instance of **Plugins-Factory** (p. 250) class. If search is set to false then no attempt is made to find plugins in loadable modules. Only plugins already loaded with previous calls to get_instance() and load() are checked. Returns created instance or NULL if failed. Specifies if loadable module may be loaded while looking for analyzing its content. If set to false only *.apd files are checked. Modules without corresponding *.apd will be ignored. Default is true;

The documentation for this class was generated from the following file:


• Plugin.h

6.207 ArcSec::Policy Class Reference

Interface for containing and processing different types of policy.

#include <Policy.h>

Inheritance diagram for ArcSec::Policy:



Public Member Functions

- Policy ()
- Policy (const Arc::XMLNode)
- Policy (const Arc::XMLNode, EvaluatorContext *)
- virtual **operator bool** (void) const =0
- virtual MatchResult match (EvaluationCtx *)=0
- virtual Result eval (EvaluationCtx *)=0
- virtual void addPolicy (Policy *pl)
- virtual void setEvaluatorContext (EvaluatorContext *)
- virtual void make_policy ()
- virtual std::string **getEffect** () const =0
- virtual EvalResult & getEvalResult ()=0
- virtual void **setEvalResult** (**EvalResult** &res)=0
- virtual const char * **getEvalName** () const =0
- virtual const char * getName () const =0

6.207.1 Detailed Description

Interface for containing and processing different types of policy. Basically, each policy object is a container which includes a few elements e.g., ArcPolicySet objects includes a few ArcPolicy objects; ArcPolicy object includes a few ArcRule objects. There is logical relationship between ArcRules or ArcPolicies, which is called combining algorithm. According to algorithm, evaluation results from the elements are combined, and then the combined evaluation result is returned to the up-level.

6.207.2 Constructor & Destructor Documentation

6.207.2.1 ArcSec::Policy::Policy (const Arc::XMLNode) [inline]

Template constructor - creates policy based on XML document.

If XML document is empty then empty policy is created. If it is not empty then it must be valid policy document - otherwise created object should be invalid.

6.207.2.2 ArcSec::Policy::Policy (const Arc::XMLNode, EvaluatorContext *) [inline]

Template constructor - creates policy based on XML document.

If XML document is empty then empty policy is created. If it is not empty then it must be valid policy document - otherwise created object should be invalid. This constructor is based on the policy node and i the **EvaluatorContext** (p. 151) which includes the factory objects for combining algorithm and function

6.207.3 Member Function Documentation

```
6.207.3.1 virtual void ArcSec::Policy::addPolicy ( Policy * pl ) [inline, virtual]
```

Add a policy element to into "this" object

6.207.3.2 virtual Result ArcSec::Policy::eval (EvaluationCtx *) [pure virtual]

Evaluate policy For the <Rule> of **Arc** (p. 23), only get the "Effect" from rules; For the <Policy> of **Arc** (p. 23), combine the evaluation result from <Rule>; For the <Rule> of XACML, evaluate the <Condition> node by using information from request, and use the "Effect" attribute of <Rule>; For the <Policy> of XACML, combine the evaluation result from <Rule>

6.207.3.3 virtual std::string ArcSec::Policy::getEffect() const [pure virtual]

Get the "Effect" attribute

6.207.3.4 virtual const char* ArcSec::Policy::getEvalName() const [pure virtual]

Get the name of **Evaluator** (p. 148) which can evaluate this policy

6.207.3.5 virtual EvalResult& ArcSec::Policy::getEvalResult() [pure virtual]

Get eveluation result

6.207.3.6 virtual const char* ArcSec::Policy::getName() const [pure virtual]

Get the name of this policy

6.207.3.7 virtual void ArcSec::Policy::make_policy() [inline, virtual]

Parse XMLNode, and construct the low-level Rule object

6.207.3.8 virtual void ArcSec::Policy::setEvalResult (EvalResult & res) [pure virtual]

Set eveluation result

6.207.3.9 virtual void ArcSec::Policy::setEvaluatorContext(EvaluatorContext*) [inline, virtual]

Set Evaluator (p. 148) Context for the usage in creating low-level policy object

The documentation for this class was generated from the following file:

· Policy.h

6.208 ArcSec::PolicyStore::PolicyElement Class Reference

The documentation for this class was generated from the following file:

· PolicyStore.h

6.209 ArcSec::PolicyParser Class Reference

A interface which will isolate the policy object from actual policy storage (files, urls, database).

#include <PolicyParser.h>

Public Member Functions

virtual Policy * parsePolicy (const Source &source, std::string policyclassname, EvaluatorContext *ctx)

6.209.1 Detailed Description

A interface which will isolate the policy object from actual policy storage (files, urls, database). Parse the policy from policy source (e.g. files, urls, database, etc.).

6.209.2 Member Function Documentation

6.209.2.1 virtual Policy* ArcSec::PolicyParser::parsePolicy (const Source & source, std::string policyclassname, EvaluatorContext * ctx) [virtual]

Parse policy

Parameters

```
source location of the policy
policyclassname name of the policy for ClassLoader
ctx EvaluatorContext (p. 151) which includes the **Factory
```

The documentation for this class was generated from the following file:

· PolicyParser.h

6.210 ArcSec::PolicyStore Class Reference

Storage place for policy objects.

#include <PolicyStore.h>

Data Structures

· class PolicyElement

Public Member Functions

• PolicyStore (const std::string &alg, const std::string &policyclassname, EvaluatorContext *ctx)

6.210.1 Detailed Description

Storage place for policy objects.

6.210.2 Constructor & Destructor Documentation

6.210.2.1 ArcSec::PolicyStore::PolicyStore (const std::string & alg, const std::string & policyclassname, EvaluatorContext * ctx)


Creates policy store with specified combing algorithm (alg - not used yet), policy name (policyclassname) and context (ctx)

The documentation for this class was generated from the following file:

· PolicyStore.h

$\begin{array}{ll} \textbf{6.211} & \textbf{Arc::PrintF} \!< \textbf{T0}, \textbf{T1}, \textbf{T2}, \textbf{T3}, \textbf{T4}, \textbf{T5}, \textbf{T6}, \textbf{T7} > \textbf{Class Template} \\ & \textbf{Reference} \end{array}$

Inheritance diagram for Arc::PrintF< T0, T1, T2, T3, T4, T5, T6, T7 >:




template<class T0 = int, class T1 = int, class T2 = int, class T3 = int, class T4 = int, class T5 = int, class T6 = int, class T7 = int> cl

The documentation for this class was generated from the following file:

• IString.h

6.212 Arc::PrintFBase Class Reference

Inheritance diagram for Arc::PrintFBase:




The documentation for this class was generated from the following file:

• IString.h

6.213 Arc::Profile Class Reference

Inheritance diagram for Arc::Profile:



The documentation for this class was generated from the following file:

• Profile.h

6.214 ArcCredential::PROXYCERTINFO_st Struct Reference

The documentation for this struct was generated from the following file:

· Proxycertinfo.h


6.215 ArcCredential::PROXYPOLICY_st Struct Reference

The documentation for this struct was generated from the following file:

· Proxycertinfo.h

6.216 Arc::Query Class Reference

Inheritance diagram for Arc::Query:



Public Member Functions

- **Query** ()
- Query (Database *db)
- virtual ~Query ()
- virtual int **get_num_colums** ()=0
- virtual int **get_num_rows** ()=0
- virtual bool **execute** (const std::string &sqlstr)=0
- virtual QueryRowResult **get_row** (int row_number) const =0
- virtual QueryRowResult **get_row** () const =0
- virtual std::string **get_row_field** (int row_number, std::string &field_name)=0
- virtual bool **get_array** (std::string &sqlstr, QueryArrayResult &result, std::vector< std::string > &arguments)=0

6.216.1 Constructor & Destructor Documentation

6.216.1.1 Arc::Query::Query() [inline]

Default constructor

6.216.1.2 Arc::Query::Query (Database * db) [inline]

Constructor

Parameters

db The database object which will be used by Query (p. 257) class to get the database connection

6.216.1.3 virtual Arc::Query::~Query() [inline, virtual]

Deconstructor

6.216.2 Member Function Documentation

6.216.2.1 virtual bool Arc::Query::execute (const std::string & sqlstr) [pure virtual]

Execute the query

Parameters

sqlstr The sql sentence used to query

Implemented in Arc::MySQLQuery (p. 222).

6.216.2.2 virtual bool Arc::Query::get_array (std::string & sqlstr, QueryArrayResult & result, std::vector< std::string > & arguments) [pure virtual]

Query (p. 257) the database by using some parameters into sql sentence e.g. "select table.value from table where table.name = ?"

Parameters

sqlstr The sql sentence with some parameters marked with "?".

result The result in an array which includes all of the value in query result.

arguments The argument list which should exactly correspond with the parametes in sql sentence.

Implemented in Arc::MySQLQuery (p. 222).

6.216.2.3 virtual int Arc::Query::get_num_colums() [pure virtual]

Get the colum number in the query result

Implemented in Arc::MySQLQuery (p. 222).

6.216.2.4 virtual int Arc::Query::get_num_rows() [pure virtual]

Get the row number in the query result

Implemented in Arc::MySQLQuery (p. 222).

6.216.2.5 virtual QueryRowResult Arc::Query::get_row(int row_number) const [pure virtual]

Get the value of one row in the query result

Parameters

row_number The number of the row

Returns

A vector includes all the values in the row

Implemented in Arc::MySQLQuery (p. 222).

6.216.2.6 virtual QueryRowResult Arc::Query::get_row() const [pure virtual]

Get the value of one row in the query result, the row number will be automatically increased each time the method is called

Implemented in Arc::MySQLQuery (p. 223).

6.216.2.7 virtual std::string Arc::Query::get_row_field (int row_number, std::string & field_name) [pure virtual]

Get the value of one specific field in one specific row

Parameters

```
row_number The row number inside the query resultfield_name The field name for the value which will be return
```

Returns

The value of the specified filed in the specified row

Implemented in Arc::MySQLQuery (p. 223).

The documentation for this class was generated from the following file:

• DBInterface.h

6.217 Arc::Range< T > Class Template Reference

template < class T > class Arc::Range < T >

The documentation for this class was generated from the following file:

· JobDescription.h

6.218 Arc::Register_Info_Type Struct Reference

The documentation for this struct was generated from the following file:


· InfoRegister.h

6.219 Arc::RegisteredService Class Reference

RegisteredService (p. 260) - extension of Service (p. 282) performing self-registration.

#include <RegisteredService.h>

Inheritance diagram for Arc::RegisteredService:



Public Member Functions

• RegisteredService (Config *)

6.219.1 Detailed Description

RegisteredService (p. 260) - extension of Service (p. 282) performing self-registration.

6.219.2 Constructor & Destructor Documentation

6.219.2.1 Arc::RegisteredService::RegisteredService (Config *)

Example contructor - Server takes at least it's configuration subtree

The documentation for this class was generated from the following file:

· RegisteredService.h

6.220 Arc::RegularExpression Class Reference

A regular expression class.

#include <ArcRegex.h>

Public Member Functions

- RegularExpression ()
- **RegularExpression** (std::string pattern)
- RegularExpression (const RegularExpression ®ex)
- ∼RegularExpression ()
- const **RegularExpression** & **operator=** (const **RegularExpression** & regex)

- bool isOk ()
- bool hasPattern (std::string str)
- bool match (const std::string &str) const
- bool **match** (const std::string &str, std::list< std::string > &unmatched, std::list< std::string > &matched) const
- std::string getPattern () const

6.220.1 Detailed Description

A regular expression class. This class is a wrapper around the functions provided in regex.h.

6.220.2 Member Function Documentation

6.220.2.1 bool Arc::RegularExpression::match (const std::string & str, std::list< std::string > & unmatched, std::list< std::string > & matched) const

Returns true if this regex matches the string provided.

Unmatched parts of the string are stored in 'unmatched'. Matched parts of the string are stored in 'matched'. The first entry in matched is the string that matched the regex, and the following entries are parenthesised elements of the regex

The documentation for this class was generated from the following file:


· ArcRegex.h

6.221 ArcSec::Request Class Reference

Base class/Interface for request, includes a container for RequestItems and some operations.

#include <Request.h>

Inheritance diagram for ArcSec::Request:



Public Member Functions

- virtual ReqItemList getRequestItems () const
- virtual void **setRequestItems** (ReqItemList sl)
- virtual void addRequestItem (Attrs &sub, Attrs &res, Attrs &act, Attrs &ctx)
- virtual void **setAttributeFactory** (**AttributeFactory** *attributefactory)=0
- virtual void **make_request** ()=0
- virtual const char * **getEvalName** () const =0
- virtual const char * **getName** () const =0
- Request ()
- Request (const Source &)

6.221.1 Detailed Description

Base class/Interface for request, includes a container for RequestItems and some operations. A **Request** (p. 261) object can has a few <subjects, actions, objects> tuples, i.e. **RequestItem** (p. 264) The **Request** (p. 261) class and any customized class which inherit from it, should be loadable, which means these classes can be dynamically loaded according to the configuration information, see the example configuration below: <Service name="pdp.service" id="pdp_service"> <pdp:PDPConfig> <.....> <pdp:Request (p. 261) name="arc.request" /> <.....> </pdp:PDPConfig> </Service>

There can be different types of subclass which inherit **Request** (p. 261), such like XACMLRequest, ArcRequest, GACLRequest

6.221.2 Constructor & Destructor Documentation

6.221.2.1 ArcSec::Request::Request() [inline]

Default constructor

6.221.2.2 ArcSec::Request::Request (const Source &) [inline]

Constructor: Parse request information from a xml stucture in memory

6.221.3 Member Function Documentation

6.221.3.1 virtual void ArcSec::Request::addRequestItem (Attrs & sub, Attrs & res, Attrs & act, Attrs & ctx) [inline, virtual]

Add request tuple from non-XMLNode

6.221.3.2 virtual const char* ArcSec::Request::getEvalName() const [pure virtual]

Get the name of corresponding evaulator

6.221.3.3 virtual const char* ArcSec::Request::getName() const [pure virtual]

Get the name of this request

6.221.3.4 virtual ReqItemList ArcSec::Request::getRequestItems () const [inline, virtual]

Get all the RequestItem (p. 264) inside RequestItem (p. 264) container

6.221.3.5 virtual void ArcSec::Request::make_request() [pure virtual]

Create the objects included in **Request** (p. 261) according to the node attached to the **Request** (p. 261) object

6.221.3.6 virtual void ArcSec::Request::setAttributeFactory (AttributeFactory * attributefactory) [pure virtual]

Set the attribute factory for the usage of **Request** (p. 261)

6.221.3.7 virtual void ArcSec::Request::setRequestItems (ReqItemList sl) [inline, virtual]

Set the content of the container

The documentation for this class was generated from the following file:

• Request.h

6.222 ArcSec::RequestAttribute Class Reference

Wrapper which includes **AttributeValue** (p. 56) object which is generated according to date type of one spefic node in Request.xml.

#include <RequestAttribute.h>

Public Member Functions

- RequestAttribute (Arc::XMLNode &node, AttributeFactory *attrfactory)
- RequestAttribute & duplicate (RequestAttribute &)

6.222.1 Detailed Description

Wrapper which includes **AttributeValue** (p. 56) object which is generated according to date type of one spefic node in Request.xml.

6.222.2 Constructor & Destructor Documentation

6.222.2.1 ArcSec::RequestAttribute::RequestAttribute (Arc::XMLNode & node, AttributeFactory * attrfactory)

Constructor - create attribute value object according to the "Type" in the node <Attribute attributeid="urn:arc:subject:voms-attribute" type="string">urn:mace:shibboleth:examples</Attribute>

6.222.3 Member Function Documentation

6.222.3.1 RequestAttribute& ArcSec::RequestAttribute::duplicate (RequestAttribute &)

Duplicate the parameter into "this"

The documentation for this class was generated from the following file:

· RequestAttribute.h

6.223 ArcSec::RequestItem Class Reference

Interface for request item container, < subjects, actions, objects, ctxs> tuple.

#include <RequestItem.h>

Public Member Functions

• RequestItem (Arc::XMLNode &, AttributeFactory *)

6.223.1 Detailed Description

Interface for request item container, < subjects, actions, objects, ctxs> tuple.

6.223.2 Constructor & Destructor Documentation

```
6.223.2.1 ArcSec::RequestItem::RequestItem ( Arc::XMLNode & , AttributeFactory * ) [inline]
```

Constructor

Parameters

```
node The XMLNode structure of the request itemattributefactory The AttributeFactory (p. 52) which will be used to generate RequestAttribute (p. 263)
```

The documentation for this class was generated from the following file:

· RequestItem.h

6.224 ArcSec::RequestTuple Class Reference

The documentation for this class was generated from the following file:

• EvaluationCtx.h

6.225 Arc::ResourceSlotType Class Reference

The documentation for this class was generated from the following file:

· JobDescription.h

6.226 Arc::ResourcesType Class Reference

The documentation for this class was generated from the following file:

· JobDescription.h

6.227 Arc::ResourceTargetType Class Reference

The documentation for this class was generated from the following file:

· JobDescription.h

6.228 ArcSec::Response Class Reference

Container for the evaluation results.

#include <Response.h>

6.228.1 Detailed Description

Container for the evaluation results.

The documentation for this class was generated from the following file:

· Response.h

6.229 ArcSec::ResponseItem Class Reference

Evaluation result concerning one **RequestTuple** (p. 264).

#include <Response.h>

6.229.1 Detailed Description

Evaluation result concerning one **RequestTuple** (p. 264). Include the **RequestTuple** (p. 264), related XMLNode, the set of policy objects which give positive evaluation result, and the related XMLNode

The documentation for this class was generated from the following file:

Response.h


6.230 ArcSec::ResponseList Class Reference

The documentation for this class was generated from the following file:

Response.h

6.231 Arc::RSL Class Reference

Inheritance diagram for Arc::RSL:




The documentation for this class was generated from the following file:

• RSLParser.h

6.232 Arc::RSLBoolean Class Reference

Inheritance diagram for Arc::RSLBoolean:




The documentation for this class was generated from the following file:

• RSLParser.h

6.233 Arc::RSLConcat Class Reference

Inheritance diagram for Arc::RSLConcat:




The documentation for this class was generated from the following file:

· RSLParser.h

6.234 Arc::RSLCondition Class Reference

Inheritance diagram for Arc::RSLCondition:




The documentation for this class was generated from the following file:

• RSLParser.h

6.235 Arc::RSLList Class Reference

Inheritance diagram for Arc::RSLList:




The documentation for this class was generated from the following file:

• RSLParser.h

6.236 Arc::RSLLiteral Class Reference

Inheritance diagram for Arc::RSLLiteral:



The documentation for this class was generated from the following file:

· RSLParser.h


6.237 Arc::RSLParser Class Reference

The documentation for this class was generated from the following file:

• RSLParser.h

6.238 Arc::RSLSequence Class Reference

Inheritance diagram for Arc::RSLSequence:




The documentation for this class was generated from the following file:

· RSLParser.h

6.239 Arc::RSLValue Class Reference

Inheritance diagram for Arc::RSLValue:




The documentation for this class was generated from the following file:

· RSLParser.h

6.240 Arc::RSLVariable Class Reference

Inheritance diagram for Arc::RSLVariable:



The documentation for this class was generated from the following file:

· RSLParser.h

6.241 Arc::Run Class Reference

#include <Run.h>

Public Member Functions

- **Run** (const std::string &cmdline)
- **Run** (const std::list< std::string > &argv)
- \sim **Run** (void)
- operator bool (void)
- bool operator! (void)
- bool Start (void)
- bool Wait (int timeout)
- bool Wait (void)
- int **Result** (void)
- bool Running (void)
- int **ReadStdout** (int timeout, char *buf, int size)
- int **ReadStderr** (int timeout, char *buf, int size)
- int WriteStdin (int timeout, const char *buf, int size)
- void **AssignStdout** (std::string &str)
- void AssignStderr (std::string &str)
- void **AssignStdin** (std::string &str)
- void **KeepStdout** (bool keep=true)
- void **KeepStderr** (bool keep=true)
- void **KeepStdin** (bool keep=true)
- void CloseStdout (void)
- void CloseStderr (void)
- void **CloseStdin** (void)
- void **AssignWorkingDirectory** (std::string &wd)
- void **Kill** (int timeout)
- void Abandon (void)

6.241.1 Detailed Description

This class runs external executable. It is possible to read/write it's standard handles or to redirect then to std::string elements.

6.241.2 Constructor & Destructor Documentation

6.241.2.1 Arc::Run::Run (const std::string & cmdline)

Constructor preapres object to run cmdline

6.241.2.2 Arc::Run::Run (const std::list< std::string > & argv)

Constructor preapres object to run executable and arguments specified in argv

6.241.2.3 Arc::Run::~Run (void)

Destructor kills running executable and releases associated resources

6.241.3 Member Function Documentation

6.241.3.1 void Arc::Run::Abandon (void)

Detach this object from running process. After calling this method instance is not associated with external process anymore. As result destructor will not kill process.

6.241.3.2 void Arc::Run::AssignStderr (std::string & str)

Associate stderr handle of executable with string. This method must be called before **Start()** (p. 271). str object must be valid as long as this object exists.

6.241.3.3 void Arc::Run::AssignStdin (std::string & str)

Associate stdin handle of executable with string. This method must be called before **Start**() (p. 271). str object must be valid as long as this object exists.

6.241.3.4 void Arc::Run::AssignStdout (std::string & str)

Associate stdout handle of executable with string. This method must be called before **Start()** (p. 271). str object must be valid as long as this object exists.

6.241.3.5 void Arc::Run::AssignWorkingDirectory (std::string & wd) [inline]

Assign working directtry of the running process

6.241.3.6 void Arc::Run::CloseStderr (void)

Closes pipe associated with stderr handle

6.241.3.7 void Arc::Run::CloseStdin (void)

Closes pipe associated with stdin handle

6.241.3.8 void Arc::Run::CloseStdout (void)

Closes pipe associated with stdout handle

6.241.3.9 void Arc::Run::KeepStderr (bool keep = true)

Keep stderr same as parent's if keep = true

6.241.3.10 void Arc::Run::KeepStdin (bool keep = true)

Keep stdin same as parent's if keep = true

6.241.3.11 void Arc::Run::KeepStdout (bool keep = true)

Keep stdout same as parent's if keep = true

6.241.3.12 void Arc::Run::Kill (int timeout)

Kill running executable. First soft kill signal (SIGTERM) is sent to executable. If after timeout seconds executable is still running it's killed completely. Curently this method does not work for Windows OS

6.241.3.13 Arc::Run::operator bool (void) [inline]

Returns true if object is valid

6.241.3.14 bool Arc::Run::operator! (void) [inline]

Returns true if object is invalid

6.241.3.15 int Arc::Run::ReadStderr (int timeout, char * buf, int size)

Read from stderr handle of running executable. Parameter timeout specifies upper limit for which method will block in milliseconds. Negative means infinite. This method may be used while stderr is directed to string. But result is unpredictable. Returns number of read bytes.

6.241.3.16 int Arc::Run::ReadStdout (int timeout, char * buf, int size)

Read from stdout handle of running executable. Parameter timeout specifies upper limit for which method will block in milliseconds. Negative means infinite. This method may be used while stdout is directed to string. But result is unpredictable. Returns number of read bytes.

6.241.3.17 int Arc::Run::Result (void) [inline]

Returns exit code of execution.

6.241.3.18 bool Arc::Run::Running (void)

Return true if execution is going on.

6.241.3.19 bool Arc::Run::Start (void)

Starts running executable. This method may be called only once.

6.241.3.20 bool Arc::Run::Wait (int timeout)

Wait till execution finished or till timeout seconds expires. Returns true if execution is complete.

6.241.3.21 bool Arc::Run::Wait (void)

Wait till execution finished

6.241.3.22 int Arc::Run::WriteStdin (int timeout, const char * buf, int size)


Write to stdin handle of running executable. Parameter timeout specifies upper limit for which method will block in milliseconds. Negative means infinite. This method may be used while stdin is directed to string. But result is unpredictable. Returns number of written bytes.

The documentation for this class was generated from the following file:

• Run.h

6.242 Arc::SAML2LoginClient Class Reference

Inheritance diagram for Arc::SAML2LoginClient:



Public Member Functions

- SAML2LoginClient (const MCCConfig cfg, const URL url, std::list< std::string > idp stack)
- virtual MCC_Status processLogin (const std::string username="", const std::string password="")=0
- MCC_Status findSimpleSAMLInstallation ()

6.242.1 Constructor & Destructor Documentation

6.242.1.1 Arc::SAML2LoginClient::SAML2LoginClient (const MCCConfig *cfg*, const URL *url*, std::list< std::string > *idp_stack*)

list with the idp for nested wayf For example, Confusa can use betawayf.wayf.dk as an identity provider, which is itself only a wayf and shares the metadata with concrete service providers or even further nested wayfs. Since due to mutual authentication with metadata, we are obliged to follow the SSO redirects from WAYF to WAYF, the WAYFs are stored in a list.

6.242.2 Member Function Documentation

6.242.2.1 MCC Status Arc::SAML2LoginClient::findSimpleSAMLInstallation ()

find the location of the simplesamlphp installation on the SP side Will be stored in (*sso_pages)[SimpleSAML]

6.242.2.2 virtual MCC_Status Arc::SAML2LoginClient::processLogin (const std::string username = "", const std::string password = "") [pure virtual]

Base interface for all login procedures


Implemented in Arc::OAuthConsumer (p. 225), and Arc::SAML2SSOHTTPClient (p. 274).

The documentation for this class was generated from the following file:

• SAML2LoginClient.h

6.243 Arc::SAML2SSOHTTPClient Class Reference

Inheritance diagram for Arc::SAML2SSOHTTPClient:



Public Member Functions

- MCC_Status processLogin (const std::string username, const std::string password)
- MCC_Status parseDN (std::string *dn)
- MCC_Status approveCSR (const std::string approve_page)
- MCC_Status pushCSR (const std::string b64_pub_key, const std::string pub_key_hash, std::string *approve_page)
- MCC_Status storeCert (const std::string cert_path, const std::string auth_token, const std::string b64_dn)

Protected Member Functions

- virtual MCC_Status processIdPLogin (const std::string username, const std::string password)=0
- virtual MCC_Status processConsent ()=0
- virtual MCC_Status processIdP2Confusa ()=0

6.243.1 Member Function Documentation

6.243.1.1 MCC_Status Arc::SAML2SSOHTTPClient::approveCSR (const std::string approve_page) [virtual]

Simulate click on the approve cert signing request link

Implements Arc::SAML2LoginClient (p. 272).

6.243.1.2 MCC_Status Arc::SAML2SSOHTTPClient::parseDN (std::string * dn) [virtual]

Parse the used DN from the Confusa about_you page

Implements Arc::SAML2LoginClient (p. 272).

6.243.1.3 virtual MCC_Status Arc::SAML2SSOHTTPClient::processConsent() [protected, pure virtual]

If the IdP has a consent module and the user has not saved her consent, this method will ask the user for consent to transmission of her data to Confusa

Implemented in Arc::HakaClient (p. 167), and Arc::OpenIdpClient (p. 225).

6.243.1.4 virtual MCC_Status Arc::SAML2SSOHTTPClient::processIdP2Confusa () [protected, pure virtual]

Redirects the user back from identity provider to the Confusa SP

Implemented in Arc::HakaClient (p. 167), and Arc::OpenIdpClient (p. 226).

6.243.1.5 virtual MCC_Status Arc::SAML2SSOHTTPClient::processIdPLogin (const std::string username, const std::string password) [protected, pure virtual]

Actual identity provider parsers for next three methods implemented in subdirectory idp/ Parse identity provider login page and submit username and password in the previsioned way

Implemented in Arc::HakaClient (p. 167), and Arc::OpenIdpClient (p. 226).

6.243.1.6 MCC_Status Arc::SAML2SSOHTTPClient::processLogin (const std::string username, const std::string password) [virtual]

Models complete SAML2 WebSSO authN flow with start -> WAYF -> Login -> (consent) -> start Implements **Arc::SAML2LoginClient** (p. 273).

6.243.1.7 MCC_Status Arc::SAML2SSOHTTPClient::pushCSR (const std::string b64_pub_key, const std::string pub_key_hash, std::string * approve_page) [virtual]

Send the cert signing request to Confusa for signing

Implements Arc::SAML2LoginClient (p. 272).

6.243.1.8 MCC_Status Arc::SAML2SSOHTTPClient::storeCert (const std::string cert_path, const std::string auth_token, const std::string b64_dn) [virtual]

Download the signed certificate from Confusa and store it locally

Implements Arc::SAML2LoginClient (p. 272).

The documentation for this class was generated from the following file:

SAML2LoginClient.h

6.244 Arc::SAMLToken Class Reference

Class for manipulating SAML Token Profile (p. 256).

#include <SAMLToken.h>

Public Types

enum SAMLVersion

Public Member Functions

- **SAMLToken** (SOAPEnvelope &soap)
- SAMLToken (SOAPEnvelope &soap, const std::string &certfile, const std::string &keyfile, SAM-LVersion saml_version=SAML2, XMLNode saml_assertion=XMLNode())
- ∼SAMLToken (void)
- operator bool (void)
- bool **Authenticate** (const std::string &cafile, const std::string &capath)
- bool Authenticate (void)

6.244.1 Detailed Description

Class for manipulating SAML Token **Profile** (p. 256). This class is for generating/consuming SAML Token profile. See WS-Security SAML Token **Profile** (p. 256) v1.1 (www.oasis-open.org/committees/wss) Currently this class is used by samltoken handler (will appears in src/hed/pdc/samltokensh/) It is not a must to directly called this class. If we need to use SAML Token functionality, we only need to configure the samltoken handler into service and client. Currently, only a minor part of the specification has been implemented.

About how to identify and reference security token for signing message, currently, only the "SAML Assertion Referenced from KeyInfo" (part 3.4.2 of WS-Security SAML Token **Profile** (p. 256) v1.1 specification) is supported, which means the implementation can only process SAML assertion "referenced from KeyInfo", and also can only generate SAML Token with SAML assertion "referenced from KeyInfo". More complete support need to implement.

About subject confirmation method, the implementation can process "hold-of-key" (part 3.5.1 of WS-Security SAML Token **Profile** (p. 256) v1.1 specification) subject subject confirmation method.

About SAML vertion, the implementation can process SAML assertion with SAML version 1.1 and 2.0; can only generate SAML assertion with SAML vertion 2.0.

In the SAML Token profile, for the hold-of-key subject confirmation method, there are three interaction parts: the attesting entity, the relying party and the issuing authority. In the hold-of-key subject confirmation method, it is the attesting entity's subject identity which will be inserted into the SAML assertion.

Firstly the attesting entity authenticates to issuing authority by using some authentication scheme such as WSS x509 Token profile (Alterbatively the usename/password authentication scheme or other different authentication scheme can also be used, unless the issuing authority can retrive the key from a trusted certificate server after firmly establishing the subject's identity under the username/password scheme). So then issuing authority is able to make a definitive statement (sign a SAML assertion) about an act of authentication that has already taken place.

The attesting entity gets the SAML assertion and then signs the soap message together with the assertion by using its private key (the relevant certificate has been authenticated by issuing authority, and its relevant public key has been put into SubjectConfirmation element under saml assertion by issuing authority. Only the actual owner of the saml assertion can do this, as only the subject possesses the private key paired with the public key in the assertion. This establishes an irrefutable connection between the author of the SOAP message and the assertion describing an authentication event.)

The relying party is supposed to trust the issuing authority. When it receives a message from the asserting entity, it will check the saml assertion based on its predetermined trust relationship with the SAML issuing authority, and check the signature of the soap message based on the public key in the saml assertion without directly trust relationship with attesting entity (subject owner).

6.244.2 Member Enumeration Documentation

6.244.2.1 enum Arc::SAMLToken::SAMLVersion

Since the specification SAMLVersion is for distinguishing two types of saml version. It is used as the parameter of constructor.

6.244.3 Constructor & Destructor Documentation

6.244.3.1 Arc::SAMLToken::SAMLToken (SOAPEnvelope & soap)

Constructor. Parse SAML Token information from SOAP header. SAML Token related information is extracted from SOAP header and stored in class variables. And then it the **SAMLToken** (p. 275) object will be used for authentication.

Parameters

soap The SOAP message which contains the SAMLToken (p. 275) in the soap header

6.244.3.2 Arc::SAMLToken::SAMLToken (SOAPEnvelope & soap, const std::string & certfile, const std::string & keyfile, SAMLVersion saml_version = SAML2, XMLNode saml_assertion = XMLNode ())

Constructor. Add SAML Token information into the SOAP header. Generated token contains elements SAML token and signature, and is meant to be used for authentication on the consuming side. This constructor is for a specific SAML Token profile usage, in which the attesting entity signs the SAML assertion for itself (self-sign). This usage implicitly requires that the relying party trust the attesting entity. More general (requires issuing authority) usage will be provided by other constructor. And the under-developing SAML service will be used as the issuing authority.

Parameters

soap The SOAP message to which the SAML Token will be inserted.

certfile The certificate file.

keyfile The key file which will be used to create signature.

samlversion The SAML version, only SAML2 is supported currently.

samlassertion The SAML assertion got from 3rd party, and used for protecting the SOAP message; If not present, then self-signed assertion will be generated.

6.244.3.3 Arc::SAMLToken::~SAMLToken (void)

Deconstructor. Nothing to be done except finalizing the xmlsec library.

6.244.4 Member Function Documentation

6.244.4.1 bool Arc::SAMLToken::Authenticate (const std::string & cafile, const std::string & capath)

Check signature by using the trusted certificates It is used by relying parting after calling **SAMLTo-ken(SOAPEnvelope& soap)** (p. 276) This method will check the SAML assertion based on the trusted certificated specified as parameter cafile or capath; and also check the signature to soap message (the signature is generated by attesting entity by signing soap body together witl SAML assertion) by using the public key inside SAML assertion.

Parameters

```
cafile ca file capath ca directory
```

6.244.4.2 bool Arc::SAMLToken::Authenticate (void)

Check signature by using the cert information in soap message

6.244.4.3 Arc::SAMLToken::operator bool (void)

Returns true of constructor succeeded

The documentation for this class was generated from the following file:

• SAMLToken.h

6.245 Arc::ScalableTime< T > Class Template Reference

```
template<class T> class Arc::ScalableTime< T>
```

The documentation for this class was generated from the following file:

· JobDescription.h

6.246 Arc::ScalableTime< int > Class Template Reference

template<> class Arc::ScalableTime< int >

The documentation for this class was generated from the following file:

· JobDescription.h

6.247 Arc::SecAttr Class Reference

This is an abstract interface to a security attribute.

#include <SecAttr.h>

Inheritance diagram for Arc::SecAttr:



Public Member Functions

- SecAttr ()
- bool operator== (const SecAttr &b) const
- bool operator!= (const SecAttr &b) const
- virtual operator bool () const
- virtual bool **Export** (**SecAttrFormat** format, std::string &val) const
- virtual bool Export (SecAttrFormat format, XMLNode &val) const
- virtual bool **Import** (**SecAttrFormat** format, const std::string &val)

Static Public Attributes

- static SecAttrFormat ARCAuth
- static SecAttrFormat XACML
- static SecAttrFormat SAML
- static SecAttrFormat GACL

6.247.1 Detailed Description

This is an abstract interface to a security attribute. This class is meant to be inherited to implement security attributes. Depending on what data it needs to store inheriting classes may need to implement constructor and destructor. They must however override the equality and the boolean operators. The equality is meant to compare security attributes. The prototype implies that all attributes are comparable to all others. This behaviour should be modified as needed by using dynamic_cast operations. The boolean cast operation is meant to embody "nullness" if that is applicable to the particular type.

6.247.2 Member Function Documentation

6.247.2.1 virtual bool Arc::SecAttr::Export (SecAttrFormat format, std::string & val) const [virtual]

Convert internal structure into specified format. Returns false if format is not supported/suitable for this attribute.

6.247.2.2 virtual bool Arc::SecAttr::Export (SecAttrFormat format, XMLNode & val) const [virtual]

Convert internal structure into specified format. Returns false if format is not supported/suitable for this attribute. XML node referenced by is turned into top level element of specified format.

Reimplemented in Arc::MultiSecAttr (p. 219).

6.247.2.3 virtual bool Arc::SecAttr::Import (SecAttrFormat format, const std::string & val) [virtual]

Fills internal structure from external object of specified format. Returns false if failed to do. The usage pattern for this method is not defined and it is provided only to make class symmetric. Hence it's implementation is not required yet.

6.247.2.4 virtual Arc::SecAttr::operator bool () const [virtual]

This function should return false if the value is to be considered null, e.g. if it hasn't been set or initialized. In other cases it should return true.

Reimplemented in Arc::MultiSecAttr (p. 219).

6.247.2.5 bool Arc::SecAttr::operator!=(const SecAttr & b) const [inline]

This is a convenience function to allow the usage of "not equal" conditions and need not be overridden.

6.247.2.6 bool Arc::SecAttr::operator== (const SecAttr & b) const [inline]

This function should (in inheriting classes) return true if this and b are considered to represent same content. Identifying and restricting the type of b should be done using dynamic_cast operations. Currently it is not defined how comparison methods to be used. Hence their implementation is not required.

The documentation for this class was generated from the following file:

· SecAttr.h

6.248 Arc::SecAttrFormat Class Reference

Export/import format.

#include <SecAttr.h>

6.248.1 Detailed Description

Export/import format. Format is identified by textual identity string. Class description includes basic formats only. That list may be extended.

The documentation for this class was generated from the following file:


• SecAttr.h

6.249 Arc::SecAttrValue Class Reference

This is an abstract interface to a security attribute.

#include <SecAttrValue.h>

Inheritance diagram for Arc::SecAttrValue:



Public Member Functions

- bool **operator**== (**SecAttrValue** &b)
- bool operator!= (SecAttrValue &b)
- virtual operator bool ()

6.249.1 Detailed Description

This is an abstract interface to a security attribute. This class is meant to be inherited to implement security attributes. Depending on what data it needs to store inheriting classes may need to implement constructor and destructor. They must however override the equality and the boolean operators. The equality is meant to compare security attributes. The prototype implies that all attributes are comparable to all others. This behaviour should be modified as needed by using dynamic_cast operations. The boolean cast operation is meant to embody "nullness" if that is applicable to the particular type.

6.249.2 Member Function Documentation

6.249.2.1 virtual Arc::SecAttrValue::operator bool() [virtual]

This function should return false if the value is to be considered null, e g if it hasn't been set or initialized. In other cases it should return true.

Reimplemented in **Arc::CIStringValue** (p. 69).

6.249.2.2 bool Arc::SecAttrValue::operator!= (SecAttrValue & b)

This is a convenience function to allow the usage of "not equal" conditions and need not be overridden.

6.249.2.3 bool Arc::SecAttrValue::operator== (SecAttrValue & b)

This function should (in inheriting classes) return true if this and b are considered to be the same. Identifying and restricting the type of b should be done using dynamic_cast operations.

The documentation for this class was generated from the following file:


• SecAttrValue.h

6.250 ArcSec::SecHandler Class Reference

Base class for simple security handling plugins.

#include <SecHandler.h>

Inheritance diagram for ArcSec::SecHandler:



6.250.1 Detailed Description


Base class for simple security handling plugins. This virtual class defines method Handle() which processes security related information/attributes in Message and optionally makes security decision. Instances of such classes are normally arranged in chains abd are called on incoming and outgoing messages in various MCC and Service plugins. Return value of Handle() defines either processing should continie (true) or stop with error (false). Configuration of **SecHandler** (p. 281) is consumed during creation of instance through XML subtree fed to constructor.

The documentation for this class was generated from the following file:

· SecHandler.h

6.251 Arc::SecHandlerConfig Class Reference

Inheritance diagram for Arc::SecHandlerConfig:




The documentation for this class was generated from the following file:

• ClientInterface.h

6.252 ArcSec::SecHandlerConfig Class Reference

#include <SecHandler.h>

Inheritance diagram for ArcSec::SecHandlerConfig:



6.252.1 Detailed Description


Helper class to create Security (p. 282) Handler configuration

The documentation for this class was generated from the following file:

· SecHandler.h

6.253 ArcSec::SecHandlerPluginArgument Class Reference

Inheritance diagram for ArcSec::SecHandlerPluginArgument:



The documentation for this class was generated from the following file:

• SecHandler.h

6.254 ArcSec::Security Class Reference

Common stuff used by security related slasses.

#include <Security.h>

6.254.1 Detailed Description

Common stuff used by security related slasses. This class is just a place where to put common stuff that is used by security related slasses. So far it only contains a logger.

The documentation for this class was generated from the following file:


· Security.h

6.255 Arc::Service Class Reference

Service (p. 282) - last component in a Message (p. 208) Chain.

#include <Service.h>

Inheritance diagram for Arc::Service:



Public Member Functions

- Service (Config *)
- virtual void AddSecHandler (Config *cfg, ArcSec::SecHandler *sechandler, const std::string &label="")
- virtual bool RegistrationCollector (XMLNode &doc)
- virtual std::string **getID** ()

Protected Member Functions

• bool ProcessSecHandlers (Message &message, const std::string &label="") const

Protected Attributes

• std::map< std::string, std::list< **ArcSec::SecHandler** * > > **sechandlers**_

Static Protected Attributes

• static Logger logger

6.255.1 Detailed Description

Service (p. 282) - last component in a Message (p. 208) Chain. This class which defines interface and common functionality for every Service (p. 282) plugin. Interface is made of method process() (p. 206) which is called by Plexer (p. 246) or MCC (p. 200) class. There is one Service (p. 282) object created for every service description processed by Loader (p. 189) class objects. Classes derived from Service (p. 282) class must implement process() (p. 206) method of MCCInterface (p. 205). It is up to developer how internal state of service is stored and communicated to other services and external utilites. Service (p. 282) is free to expect any type of payload passed to it and generate any payload as well. Useful types depend on MCCs in chain which leads to that service. For example if service is expected to by linked to SOAP MCC (p. 200) it must accept and generate messages with PayloadSOAP (p. 233) payload. Method process() (p. 206) of class derived from Service (p. 282) class may be called concurrently in multiple threads. Developers must take that into account and write thread-safe implementation. Simple example of service is provided in /src/tests/echo/echo.cpp of source tree. The way to write client couterpart of corresponding service is undefined yet. For example see /src/tests/echo/test.cpp.

6.255.2 Constructor & Destructor Documentation

6.255.2.1 Arc::Service::Service (Config *)

Example contructor - Server takes at least it's configuration subtree

6.255.3 Member Function Documentation

6.255.3.1 virtual void Arc::Service::AddSecHandler (Config * cfg, ArcSec::SecHandler * sechandler, const std::string & label = "") [virtual]

Add security components/handlers to this MCC (p. 200). For more information please see description of MCC::AddSecHandler (p. 201)

6.255.3.2 virtual std::string Arc::Service::getID() [inline, virtual]

Service (p. 282) may implement own service identitifer gathering method. This method return identifier of service which is used for registering it Information Services.

6.255.3.3 bool Arc::Service::ProcessSecHandlers (Message & message, const std::string & label = "") const [protected]

Executes security handlers of specified queue. For more information please see description of **MCC::ProcessSecHandlers** (p. 202)

6.255.3.4 virtual bool Arc::Service::RegistrationCollector (XMLNode & doc) [virtual]

Service (p. 282) specific registartion collector, used for generate service registartions. In implemented service this method should generate GLUE2 document with part of service description which service wishes to advertise to Information Services.

6.255.4 Field Documentation

6.255.4.1 Logger Arc::Service::logger [static, protected]

Logger (p. 193) object used to print messages generated by this class.

$\textbf{6.255.4.2} \quad \textbf{std::map} < \textbf{std::string,std::list} < \textbf{ArcSec::SecHandler*} > \textbf{Arc::Service::sechandlers} \\ [\texttt{protected}]$


Set of labeled authentication and authorization handlers. MCC (p. 200) calls sequence of handlers at specific point depending on associated identifier. in most aces those are "in" and "out" for incoming and outgoing messages correspondingly.

The documentation for this class was generated from the following file:

• Service.h

6.256 Arc::ServicePluginArgument Class Reference

Inheritance diagram for Arc::ServicePluginArgument:



The documentation for this class was generated from the following file:

· Service.h

6.257 Arc::SimpleCondition Class Reference

Helper function to create simple thread.

#include <Thread.h>

Public Member Functions

- void lock (void)
- void unlock (void)
- void **signal** (void)
- void signal_nonblock (void)
- void **broadcast** (void)
- void wait (void)
- void wait_nonblock (void)
- bool wait (int t)
- void reset (void)

6.257.1 Detailed Description

Helper function to create simple thread. It takes care of all pecularities of Glib::Thread API. As result it runs function 'func' with argument 'arg' in a separate thread. The created thread will be joinable. Returns true on success. This function is currently disable becaueit is not clear if joinability is a needed feature Simple triggered condition. Provides condition and semaphor objects in one element.

6.257.2 Member Function Documentation

6.257.2.1 void Arc::SimpleCondition::broadcast(void) [inline]

Signal about condition to all waiting threads

6.257.2.2 void Arc::SimpleCondition::lock(void) [inline]

Acquire semaphor

6.257.2.3 void Arc::SimpleCondition::reset (void) [inline]

Reset object to initial state

6.257.2.4 void Arc::SimpleCondition::signal(void) [inline]

Signal about condition

6.257.2.5 void Arc::SimpleCondition::signal_nonblock (void) [inline]

Signal about condition without using semaphor

6.257.2.6 void Arc::SimpleCondition::unlock(void) [inline]

Release semaphor

6.257.2.7 bool Arc::SimpleCondition::wait (int t) [inline]

Wait for condition no longer than t milliseconds

6.257.2.8 void Arc::SimpleCondition::wait (void) [inline]

Wait for condition

6.257.2.9 void Arc::SimpleCondition::wait_nonblock(void) [inline]

Wait for condition without using semaphor

The documentation for this class was generated from the following file:

· Thread.h

6.258 Arc::SimpleCounter Class Reference

Public Member Functions

• bool wait (int t)

6.258.1 Member Function Documentation

6.258.1.1 bool Arc::SimpleCounter::wait(int t) [inline]

Wait for condition no longer than t milliseconds

The documentation for this class was generated from the following file:

• Thread.h

6.259 Arc::SOAPMessage Class Reference

Message (p. 208) restricted to SOAP payload.

#include <SOAPMessage.h>

Public Member Functions

- SOAPMessage (void)
- **SOAPMessage** (long msg_ptr_addr)
- SOAPMessage (Message &msg)
- ∼SOAPMessage (void)
- SOAPEnvelope * Payload (void)
- void **Payload** (SOAPEnvelope *new_payload)
- MessageAttributes * Attributes (void)

6.259.1 Detailed Description

Message (p. 208) restricted to SOAP payload. This is a special **Message** (p. 208) intended to be used in language bindings for programming languages which are not flexible enough to support all kinds of Payloads. It is passed through chain of MCCs and works like the **Message** (p. 208) but can carry only SOAP content.

6.259.2 Constructor & Destructor Documentation

6.259.2.1 Arc::SOAPMessage::SOAPMessage(void) [inline]

Dummy constructor

6.259.2.2 Arc::SOAPMessage::SOAPMessage (long msg_ptr_addr)

Copy constructor. Used by language bindigs

6.259.2.3 Arc::SOAPMessage::SOAPMessage (Message & msg)

Copy constructor. Ensures shallow copy.

6.259.2.4 Arc::SOAPMessage::~SOAPMessage (void)

Destructor does not affect refered objects

6.259.3 Member Function Documentation

6.259.3.1 MessageAttributes* Arc::SOAPMessage::Attributes(void) [inline]

Returns a pointer to the current attributes object or NULL if no attributes object has been assigned.

6.259.3.2 SOAPEnvelope* Arc::SOAPMessage::Payload (void)

Returns pointer to current payload or NULL if no payload assigned.

6.259.3.3 void Arc::SOAPMessage::Payload (SOAPEnvelope * new_payload)

Replace payload with a COPY of new one

The documentation for this class was generated from the following file:


· SOAPMessage.h

6.260 Arc::Software Class Reference

Used to represent software (names and version) and comparison.

#include <Software.h>

Inheritance diagram for Arc::Software:



Public Types

- enum ComparisonOperatorEnum {
 NOTEQUAL = 0, EQUAL = 1, GREATERTHAN = 2, LESSTHAN = 3,
 GREATERTHANOREQUAL = 4, LESSTHANOREQUAL = 5 }
- typedef bool(Software::* ComparisonOperator)(const Software &) const

Public Member Functions

- Software ()
- **Software** (const std::string &name_version)
- Software (const std::string &name, const std::string &version)
- Software (const std::string &family, const std::string &name, const std::string &version)
- bool empty () const
- bool operator== (const Software &sw) const
- bool operator!= (const Software &sw) const
- $\bullet \ \ bool\ \textbf{operator}{>}\ (const\ \textbf{Software}\ \&sw)\ const$
- $\bullet \ \ bool\ \ \textbf{operator} < (const\ \textbf{Software}\ \&sw)\ const$
- bool **operator**>= (const **Software** &sw) const
- bool **operator**<= (const **Software** &sw) const
- std::string operator() () const
- operator std::string (void) const
- const std::string & getFamily () const

- const std::string & getName () const
- const std::string & getVersion () const

Static Public Member Functions

- static ComparisonOperator convert (const ComparisonOperatorEnum &co)
- static std::string toString (ComparisonOperator co)

Static Public Attributes

• static const std::string VERSIONTOKENS

Friends

• std::ostream & operator<< (std::ostream &out, const Software &sw)

6.260.1 Detailed Description

Used to represent software (names and version) and comparison. The **Software** (p. 288) class is used to represent the name of a piece of software internally. Generally software are identified by a name and possibly a version number. Some software can also be categorized by type or family (compilers, operating system, etc.). A software object can be compared to other software objects using the comparison operators contained in this class. The basic usage of this class is to test if some specified software requirement (**SoftwareRequirement** (p. 295)) are fulfilled, by using the comparability of the class.

Internally the **Software** (p. 288) object is represented by a family and name identifier, and the software version is tokenized at the characters defined in VERSIONTOKENS, and stored as a list of tokens.

6.260.2 Member Typedef Documentation

6.260.2.1 typedef bool(Software::* Arc::Software::ComparisonOperator)(const Software &) const

Definition of a comparison operator method pointer.

This typedef defines a comparison operator method pointer.

See also

```
operator== (p. 293),
operator!= (p. 292),
operator> (p. 294),
operator<= (p. 293),
operator>= (p. 294),
operator<= (p. 293),
ComparisonOperatorEnum (p. 289).</pre>
```

6.260.3 Member Enumeration Documentation

6.260.3.1 enum Arc::Software::ComparisonOperatorEnum

Comparison operator enum.

The **ComparisonOperatorEnum** (p. 289) enumeration is a 1-1 correspondance between the defined comparison method operators (**Software::ComparisonOperator** (p. 289)), and can be used in circumstances where method pointers are not supported.

Enumerator:

```
NOTEQUAL see operator!= (p. 292)

EQUAL see operator== (p. 293)

GREATERTHAN see operator> (p. 294)

LESSTHAN see operator< (p. 293)

GREATERTHANOREQUAL see operator>= (p. 294)

LESSTHANOREQUAL see operator<= (p. 293)
```

6.260.4 Constructor & Destructor Documentation

6.260.4.1 Arc::Software::Software() [inline]

Dummy constructor.

This constructor creates a empty object.

6.260.4.2 Arc::Software::Software (const std::string & name_version)

Create a Software (p. 288) object.

Create a **Software** (p. 288) object from a single string composed of a name and a version part. The created object will contain a empty family part. The name and version part of the string will be split at the first occurence of a dash (-) which is followed by a digit (0-9). If the string does not contain such a pattern, the passed string will be taken to be the name and version will be empty.

Parameters

name_version should be a string composed of the name and version of the software to represent.

6.260.4.3 Arc::Software::Software (const std::string & name, const std::string & version)

Create a **Software** (p. 288) object.

Create a **Software** (p. 288) object with the specified name and version. The family part will be left empty.

Parameters

```
name the software name to represent.version the software version to represent.
```

6.260.4.4 Arc::Software::Software (const std::string & family, const std::string & name, const std::string & version)

Create a Software (p. 288) object.

Create a **Software** (p. 288) object with the specified family, name and version.

Parameters

family the software family to represent.

name the software name to represent.

version the software version to represent.

6.260.5 Member Function Documentation

6.260.5.1 static ComparisonOperator Arc::Software::convert (const ComparisonOperatorEnum & co) [static]

Convert a ComparisonOperatorEnum (p. 289) value to a comparison method pointer.

The passed **ComparisonOperatorEnum** (p. 289) will be converted to a comparison method pointer defined by the **Software::ComparisonOperator** (p. 289) typedef.

This static method is not defined in language bindings created with Swig, since method pointers are not supported by Swig.

Parameters

co a ComparisonOperatorEnum (p. 289) value.

Returns

A method pointer to a comparison method is returned.

6.260.5.2 bool Arc::Software::empty() const [inline]

Indicates whether the object is empty.

Returns

true if the name of this object is empty, otherwise false.

6.260.5.3 const std::string& Arc::Software::getFamily() const [inline]

Get family.

Returns

The family the represented software belongs to is returned.

6.260.5.4 const std::string& Arc::Software::getName() const [inline]

Get name.

Returns

The name of the represented software is returned.

6.260.5.5 const std::string& Arc::Software::getVersion() const [inline]

Get version.

Returns

The version of the represented software is returned.

6.260.5.6 Arc::Software::operator std::string (void) const [inline]

Cast to string.

This casting operator behaves exactly as **operator**()() (p. 292) does. The cast is used like (std::string) <software-object>.

See also

```
operator()() (p. 292).
```

References operator()().

6.260.5.7 bool Arc::Software::operator!= (const Software & sw) const [inline]

Inequality operator (non-trivial behaviour).

The inequality operator should be used to test if two **Software** (p. 288) objects are of different versions but share the same name and family. So it should not be used to test if two **Software** (p. 288) objects differ in either name, version or family. Two **Software** (p. 288) objects are inequal if they share the same name and family but have different versions and the versions are non-empty.

Parameters

```
sw is the RHS Software (p. 288) object.
```

Returns

true when the two objects are inequal, otherwise false.

6.260.5.8 std::string Arc::Software::operator() () const

Get string representation.

Returns the string representation of this object, which is 'family'-'name'-'version'.

Returns

The string representation of this object is returned.

See also

operator std::string().

Referenced by operator std::string().

6.260.5.9 bool Arc::Software::operator< (const Software & sw) const [inline]

Less-than operator.

The behaviour of this less-than operator is equivalent to the greater-than operator (**operator**>() (p. 294)) with the LHS and RHS swapped.

Parameters

```
sw is the RHS object.
```

Returns

true if the LHS is less than the RHS, otherwise false.

See also

```
operator>() (p. 294).
```

6.260.5.10 bool Arc::Software::operator<= (const Software & sw) const [inline]

Less-than or equal operator.

The LHS object is greater than or equal to the RHS object if the LHS equal the RHS (**operator==**() (p. 293)) or if the LHS is greater than the RHS (**operator**>() (p. 294)).

Parameters

```
sw is the RHS object.
```

Returns

true if the LHS is less than or equal the RHS, otherwise false.

See also

```
operator==() (p. 293),
operator<() (p. 293).</pre>
```

6.260.5.11 bool Arc::Software::operator== (const Software & sw) const [inline]

Equality operator.

Two **Software** (p. 288) objects are equal if they are of the same family, and if they have the same name. If BOTH objects specifies a version they must also equal, for the objects to be equal. Otherwise the two objects does not equal. This operator can also be represented by the **Software::EQUAL** (p. 290) **ComparisonOperatorEnum** (p. 289) value.

Parameters

```
sw is the RHS Software (p. 288) object.
```

Returns

true when the two objects equals, otherwise false.

6.260.5.12 bool Arc::Software::operator> (const Software & sw) const

Greater-than operator.

For the LHS object to be greater than the RHS object they must first share the same family and name and have non-empty versions. Then, the first version token of each object is compared and if they are identical, the two next version tokens will be compared. If not identical, the two tokens will be parsed as integers, and if parsing fails the LHS is not greater than the RHS. If parsing succeeds and the integers equals, the two next tokens will be compared, otherwise the comparison is resolved by the integer comparison.

If the LHS contains more version tokens than the RHS, and the comparison have not been resolved at the point of equal number of tokens, then if the additional tokens contains a token which cannot be parsed to a integer the LHS is not greater than the RHS. If the parsed integer is not 0 then the LHS is greater than the RHS. If the rest of the additional tokens are 0, the LHS is not greater than the RHS.

If the RHS contains more version tokens than the LHS and comparison have not been resolved at the point of equal number of tokens, or simply if comparison have not been resolved at the point of equal number of tokens, then the LHS is not greater than the RHS.

Parameters

sw is the RHS object.

Returns

true if the LHS is greater than the RHS, otherwise false.

6.260.5.13 bool Arc::Software::operator>=(const Software & sw) const [inline]

Greater-than or equal operator.

The LHS object is greater than or equal to the RHS object if the LHS equal the RHS (**operator==**() (p. 293)) or if the LHS is greater than the RHS (**operator**>() (p. 294)).

Parameters

```
sw is the RHS object.
```

Returns

 ${\tt true} \ if \ the \ LHS \ is \ greated \ than \ or \ equal \ the \ RHS, \ otherwise \ {\tt false}.$

See also

```
operator==() (p. 293), operator>() (p. 294).
```

6.260.5.14 static std::string Arc::Software::toString (ComparisonOperator co) [static]

Convert **Software::ComparisonOperator** (p. 289) to a string.

This method is not available in language bindings created by Swig, since method pointers are not supported by Swig.

Parameters

```
co is a Software::ComparisonOperator (p. 289).
```

Returns

The string representation of the passed **Software::ComparisonOperator** (p. 289) is returned.

6.260.6 Friends And Related Function Documentation

6.260.6.1 std::ostream & operator << (std::ostream & out, const Software & sw) [friend]

Write **Software** (p. 288) string representation to a std::ostream.

Write the string representation of a **Software** (p. 288) object to a std::ostream.

Parameters

```
out is a std::ostream to write the string representation of the Software (p. 288) object to.sw is the Software (p. 288) object to write to the std::ostream.
```

Returns

The passed std::ostream out is returned.

6.260.7 Field Documentation

6.260.7.1 const std::string Arc::Software::VERSIONTOKENS [static]

Tokens used to split version string.

This string constant specifies which tokens will be used to split the version string.

The documentation for this class was generated from the following file:

• Software.h

6.261 Arc::SoftwareRequirement Class Reference

Class used to express and resolve version requirements on software.

```
#include <Software.h>
```

Public Member Functions

- **SoftwareRequirement** (bool requiresAll=false)
- SoftwareRequirement (const Software &sw, Software::ComparisonOperator swCo-mOp=&Software::operator==, bool requiresAll=false)
- SoftwareRequirement (const Software &sw, Software::ComparisonOperatorEnum co, bool requiresAll=false)
- SoftwareRequirement & operator= (const SoftwareRequirement &sr)
- SoftwareRequirement (const SoftwareRequirement &sr)
- void **add** (const **Software** &sw, **Software::ComparisonOperator** swCo-mOp=&Software::operator==)
- void add (const Software &sw, Software::ComparisonOperatorEnum co)
- bool isRequiringAll () const

- void **setRequirement** (bool all)
- bool isSatisfied (const Software &sw) const
- bool **isSatisfied** (const std::list< **Software** > &swList) const
- bool **isSatisfied** (const std::list< **ApplicationEnvironment** > &swList) const
- bool **selectSoftware** (const **Software** &sw)
- bool **selectSoftware** (const std::list< **Software** > &swList)
- bool **selectSoftware** (const std::list< **ApplicationEnvironment** > &swList)
- bool isResolved () const
- bool empty () const
- void clear ()
- const std::list< Software > & getSoftwareList () const
- const std::list< Software::ComparisonOperator > & getComparisonOperatorList () const

6.261.1 Detailed Description

Class used to express and resolve version requirements on software. A requirement in this class is defined as a pair composed of a **Software** (p. 288) object and either a **Software::ComparisonOperator** (p. 289) method pointer or equally a **Software::ComparisonOperatorEnum** (p. 289) enum value. A **SoftwareRequirement** (p. 295) object can contain multiple of such requirements, and then it can specified if all these requirements should be satisfied, or if it is enough to satisfy only one of them. The requirements can be satisfied by a single **Software** (p. 288) object or a list of either **Software** (p. 288) or **ApplicationEnvironment** (p. 50) objects, by using the method **isSatisfied**() (p. 300). This class also contain a number of methods (**selectSoftware**() (p. 301)) to select **Software** (p. 288) objects which are satisfying the requirements, and in this way resolving requirements.

6.261.2 Constructor & Destructor Documentation

6.261.2.1 Arc::SoftwareRequirement::SoftwareRequirement (bool requiresAll = false) [inline]

Create a empty **SoftwareRequirement** (p. 295) object.

The created **SoftwareRequirement** (p. 295) object will contain no requirements.

Parameters

requiresAll indicates whether the all requirements have to be satisfied (true) or if only a single one (false), the default is that only a single requirement need to be satisfied.

6.261.2.2 Arc::SoftwareRequirement::SoftwareRequirement (const Software & sw, Software::ComparisonOperator swComOp = &Software::operator==, bool requiresAll = false)

Create a SoftwareRequirement (p. 295) object.

The created **SoftwareRequirement** (p. 295) object will contain one requirement specified by the **Software** (p. 288) object *sw*, and the **Software::ComparisonOperator** (p. 289) *swComOp*.

This constructor is not available in language bindings created by Swig, since method pointers are not supported by Swig, see **SoftwareRequirement(const Software&, Software::ComparisonOperatorEnum, bool)** (p. 297) instead.

Parameters

```
sw is the Software (p. 288) object of the requirement to add.
```

swComOp is the Software::ComparisonOperator (p. 289) of the requirement to add.

requiresAll indicates whether the all requirements have to be satisfied (true) or if only a single one (false), the default is that only a single requirement need to be satisfied.

6.261.2.3 Arc::SoftwareRequirement::SoftwareRequirement (const Software & sw, Software::ComparisonOperatorEnum co, bool requiresAll = false)

Create a **SoftwareRequirement** (p. 295) object.

The created **SoftwareRequirement** (p. 295) object will contain one requirement specified by the **Software** (p. 288) object sw, and the **Software::ComparisonOperatorEnum** (p. 289) co.

Parameters

```
sw is the Software (p. 288) object of the requirement to add.
```

co is the **Software::ComparisonOperatorEnum** (p. 289) of the requirement to add.

requiresAll indicates whether the all requirements have to be satisfied (true) or if only a single one (false), the default is that only a single requirement need to be satisfied.

6.261.2.4 Arc::SoftwareRequirement::SoftwareRequirement (const SoftwareRequirement & sr) [inline]

Copy constructor.

Create a **SoftwareRequirement** (p. 295) object from another **SoftwareRequirement** (p. 295) object.

Parameters

sr is the **SoftwareRequirement** (p. 295) object to make a copy of.

6.261.3 Member Function Documentation

```
6.261.3.1 void Arc::SoftwareRequirement::add ( const Software & sw, Software::ComparisonOperator swComOp = &Software::operator== )
```

Add a **Software** (p. 288) object a corresponding comparion operator to this object.

Adds software name and version to list of requirements and associates the comparison operator with it (equality by default).

This method is not available in language bindings created by Swig, since method pointers are not supported by Swig, see add(const Software&, Software::ComparisonOperatorEnum) (p. 298) instead.

Parameters

```
sw is the Software (p. 288) object to add as part of a requirement.
```

swComOp is the **Software::ComparisonOperator** (p. 289) method pointer to add as part of a requirement, the default operator will be **Software::operator==**() (p. 293).

6.261.3.2 void Arc::SoftwareRequirement::add (const Software & sw, Software::ComparisonOperatorEnum co)

Add a Software (p. 288) object a corresponding comparion operator to this object.

Adds software name and version to list of requirements and associates the comparison operator with it (equality by default).

Parameters

```
sw is the Software (p. 288) object to add as part of a requirement.
```

co is the **Software::ComparisonOperatorEnum** (p. 289) value to add as part of a requirement, the default enum will be **Software::EQUAL** (p. 290).

6.261.3.3 void Arc::SoftwareRequirement::clear () [inline]

Clear the object.

The requirements in this object will be cleared when invoking this method.

6.261.3.4 bool Arc::SoftwareRequirement::empty () const [inline]

Test if the object is empty.

Returns

true if this object do no contain any requirements, otherwise false.

Get list of comparison operators.

Returns

The list of internally stored comparison operators is returned.

See also

```
Software::ComparisonOperator (p. 289), getSoftwareList (p. 298).
```

6.261.3.6 const std::list<Software>& Arc::SoftwareRequirement::getSoftwareList() const [inline]

Get list of Software (p. 288) objects.

Returns

The list of internally stored **Software** (p. 288) objects is returned.

See also

```
Software (p. 288), getComparisonOperatorList (p. 298).
```

6.261.3.7 bool Arc::SoftwareRequirement::isRequiringAll() const [inline]

Indicates whether all requirments has to be satisfied.

This method returns true if all requirements has to be satisfied. If only one requirement has to be satisfied, false is returned.

Returns

true if all requirements has to be satisfied, otherwise false.

See also

setRequirement (p. 302).

6.261.3.8 bool Arc::SoftwareRequirement::isResolved () const

Indicates whether requirements have been resolved or not.

If specified that only one requirement has to be satisfied, then for this object to be resolved it can only contain one requirement and it has use the equal operator (**Software::operator==** (p. 293)).

If specified that all requirements has to be satisfied, then for this object to be resolved each requirement must have a **Software** (p. 288) object with a unique family/name composition, i.e. no other requirements have a **Software** (p. 288) object with the same family/name composition, and each requirement must use the equal operator (**Software::operator==** (p. 293)).

If this object has been resolved then true is returned when invoking this method, otherwise false is returned.

Returns

true if this object have been resolved, otherwise false.

6.261.3.9 bool Arc::SoftwareRequirement::isSatisfied (const std::list< ApplicationEnvironment > & swList) const

Test if requirements are satisfied.

This method behaves in exactly the same way as the **isSatisfied(const Software&) const** (p. 300)method does.

Parameters

swList is the list of **ApplicationEnvironment** (p. 50) objects which should be used to try satisfy the requirements.

Returns

true if requirements are satisfied, otherwise false.

See also

```
isSatisfied(const Software&) const (p. 300),
isSatisfied(const std::list<Software>&) const (p. 300),
selectSoftware(const std::list<ApplicationEnvironment>&) (p. 302),
isResolved() const (p. 299).
```

6.261.3.10 bool Arc::SoftwareRequirement::isSatisfied (const Software & sw) const [inline]

Test if requirements are satisfied.

Returns true if the requirements are satisfied by the specified **Software** (p. 288) sw, otherwise false is returned.

Parameters

sw is the **Software** (p. 288) which should satisfy the requirements.

Returns

true if requirements are satisfied, otherwise false.

See also

```
isSatisfied(const std::list<Software>&) const (p. 300),
isSatisfied(const std::list<ApplicationEnvironment>&) const (p. 299),
selectSoftware(const Software&) (p. 301),
isResolved() const (p. 299).
```

References isSatisfied().

Referenced by isSatisfied().

Test if requirements are satisfied.

Returns true if stored requirements are satisfied by software specified in *swList*, otherwise false is returned.

Note that if all requirements must be satisfied and multiple requirements exist having identical name and family all these requirements should be satisfied by a single **Software** (p. 288) object.

Parameters

swList is the list of Software (p. 288) objects which should be used to try satisfy the requirements.

Returns

true if requirements are satisfied, otherwise false.

See also

```
isSatisfied(const Software&) const (p. 300),
isSatisfied(const std::list<ApplicationEnvironment>&) const (p. 299),
selectSoftware(const std::list<Software>&) (p. 301),
isResolved() const (p. 299).
```

6.261.3.12 SoftwareRequirement& Arc::SoftwareRequirement::operator= (const SoftwareRequirement & sr)

Assignment operator.

Set this object equal to that of the passed **SoftwareRequirement** (p. 295) object sr.

Parameters

sr is the **SoftwareRequirement** (p. 295) object to set object equal to.

6.261.3.13 bool Arc::SoftwareRequirement::selectSoftware (const std::list< Software > & swList)

Select software.

If the passed list of **Software** (p. 288) objects *swList* do not satisfy the requirements false is returned and this object is not modified. If however the list of **Software** (p. 288) objects *swList* do satisfy the requirements true is returned and the **Software** (p. 288) objects satisfying the requirements will replace these with the equality operator (**Software::operator==** (p. 293)) used as the comparator for the new requirements.

Note that if all requirements must be satisfied and multiple requirements exist having identical name and family all these requirements should be satisfied by a single **Software** (p. 288) object and it will replace all these requirements.

Parameters

swList is a list of Software (p. 288) objects used to satisfy requirements.

Returns

true if requirements are satisfied, otherwise false.

See also

```
selectSoftware(const Software&) (p. 301),
selectSoftware(const std::list<ApplicationEnvironment>&) (p. 302),
isSatisfied(const std::list<Software>&) const (p. 300),
isResolved() const (p. 299).
```

6.261.3.14 bool Arc::SoftwareRequirement::selectSoftware(const Software & sw) [inline]

Select software.

If the passed **Software** (p. 288) *sw* do not satisfy the requirements false is returned and this object is not modified. If however the **Software** (p. 288) object *sw* do satisfy the requirements true is returned and the requirements are set to equal the *sw* **Software** (p. 288) object.

Parameters

sw is the **Software** (p. 288) object used to satisfy requirements.

Returns

true if requirements are satisfied, otherwise false.

See also

```
selectSoftware(const std::list<Software>&) (p. 301),
selectSoftware(const std::list<ApplicationEnvironment>&) (p. 302),
isSatisfied(const Software&) const (p. 300),
isResolved() const (p. 299).
```

References selectSoftware().

Referenced by selectSoftware().

6.261.3.15 bool Arc::SoftwareRequirement::selectSoftware (const std::list< ApplicationEnvironment > & swList)

Select software.

This method behaves exactly as the **selectSoftware(const std::list<Software>&)** (p. 301) method does.

Parameters

swList is a list of ApplicationEnvironment (p. 50) objects used to satisfy requirements.

Returns

true if requirements are satisfied, otherwise false.

See also

```
selectSoftware(const Software&) (p. 301),
selectSoftware(const std::list<Software>&) (p. 301),
isSatisfied(const std::list<ApplicationEnvironment>&) const (p. 299),
isResolved() const (p. 299).
```

6.261.3.16 void Arc::SoftwareRequirement::setRequirement (bool all) [inline]

Set relation between requirements.

Specifies if all requirements stored need to be satisfied or if it is enough to satisfy only one of them.

Parameters

all is a boolean specifying if all requirements has to be satisfied.

See also

```
isRequiringAll() (p. 299).
```

The documentation for this class was generated from the following file:


· Software.h

6.262 ArcSec::Source Class Reference

Acquires and parses XML document from specified source.

#include <Source.h>

Inheritance diagram for ArcSec::Source:



Public Member Functions

- Source (const Source &s)
- Source (Arc::XMLNode &xml)
- Source (std::istream &stream)
- Source (Arc::URL &url)
- Source (const std::string &str)
- Arc::XMLNode Get (void) const
- operator bool (void)

6.262.1 Detailed Description

Acquires and parses XML document from specified source. This class is to be used to provide easy way to specify different sources for XML Authorization Policies and Requests.

6.262.2 Constructor & Destructor Documentation

6.262.2.1 ArcSec::Source::Source(const Source & s) [inline]

Copy constructor.

Use this constructor only for temporary objects. Parsed XML document is still owned by copied source and hence lifetime of create object should not exceed that of copied one.

6.262.2.2 ArcSec::Source::Source (Arc::URL & url)

Fetch XML document from specified url and parse it.

This constructor is not implemented yet.

The documentation for this class was generated from the following file:


• Source.h

6.263 ArcSec::SourceFile Class Reference

Convenience class for obtaining XML document from file.

#include <Source.h>

Inheritance diagram for ArcSec::SourceFile:



Public Member Functions

- SourceFile (const SourceFile &s)
- SourceFile (const char *name)
- SourceFile (const std::string &name)

6.263.1 Detailed Description

Convenience class for obtaining XML document from file.

The documentation for this class was generated from the following file:

· Source.h

6.264 ArcSec::SourceURL Class Reference

Convenience class for obtaining XML document from remote URL.

#include <Source.h>

Inheritance diagram for ArcSec::SourceURL:



Public Member Functions

- SourceURL (const SourceURL &s)
- SourceURL (const char *url)
- SourceURL (const std::string &url)

6.264.1 Detailed Description


Convenience class for obtaining XML document from remote URL.

The documentation for this class was generated from the following file:

• Source.h

6.265 ArcSec::StringAttribute Class Reference

Inheritance diagram for ArcSec::StringAttribute:



Public Member Functions

- virtual bool equal (AttributeValue *other, bool check_id=true)
- virtual std::string encode ()
- virtual std::string **getType** ()
- virtual std::string getId ()

6.265.1 Member Function Documentation

6.265.1.1 virtual std::string ArcSec::StringAttribute::encode() [inline, virtual]

encode the value in a string format

Implements ArcSec::AttributeValue (p. 57).

6.265.1.2 virtual bool ArcSec::StringAttribute::equal (AttributeValue * value, bool check_id = true) [virtual]

Evluate whether "this" equale to the parameter value

Implements ArcSec::AttributeValue (p. 58).

6.265.1.3 virtual std::string ArcSec::StringAttribute::getId() [inline, virtual]

Get the AttributeId of the <Attribute>

Implements ArcSec::AttributeValue (p. 58).

6.265.1.4 virtual std::string ArcSec::StringAttribute::getType() [inline, virtual]

Get the DataType of the <Attribute>

Implements ArcSec::AttributeValue (p. 58).

The documentation for this class was generated from the following file:


· StringAttribute.h

6.266 Arc::Submitter Class Reference

Base class for the Submitters.

#include <Submitter.h>

Inheritance diagram for Arc::Submitter:



Public Member Functions

- virtual URL Submit (const JobDescription &jobdesc, const ExecutionTarget &et) const =0
- virtual URL Migrate (const URL &jobid, const JobDescription &jobdesc, const ExecutionTarget &et, bool forcemigration) const =0

6.266.1 Detailed Description

Base class for the Submitters. **Submitter** (p. 306) is the base class for Grid middleware specialized **Submitter** (p. 306) objects. The class submits job(s) to the computing resource it represents and uploads (needed by the job) local input files.

6.266.2 Member Function Documentation

6.266.2.1 virtual URL Arc::Submitter::Migrate (const URL & jobid, const JobDescription & jobdesc, const ExecutionTarget & et, bool forcemigration) const [pure virtual]

This virtual method should be overridden by plugins which should be capable of migrating jobs. The active job which should be migrated is pointed to by the **URL** (p. 320) jobid, and is represented by the **JobDescription** (p. 187) jobdesc. The forcemigration boolean specifies if the migration should succeed if the active job cannot be terminated. The protected method AddJob can be used to save job information. This method should return the **URL** (p. 320) of the migrated job. In case migration fails an empty **URL** (p. 320) should be returned.

6.266.2.2 virtual URL Arc::Submitter::Submit (const JobDescription & jobdesc, const ExecutionTarget & et) const [pure virtual]

This virtual method should be overridden by plugins which should be capable of submitting jobs, defined in the **JobDescription** (p. 187) jobdesc, to the **ExecutionTarget** (p. 153) et. The protected convenience method AddJob can be used to save job information. This method should return the **URL** (p. 320) of the submitted job. In case submission fails an empty **URL** (p. 320) should be returned.


The documentation for this class was generated from the following file:

• Submitter.h

6.267 Arc::SubmitterLoader Class Reference

#include <Submitter.h>

Inheritance diagram for Arc::SubmitterLoader:



Public Member Functions

- SubmitterLoader ()
- \sim SubmitterLoader ()
- Submitter * load (const std::string &name, const UserConfig &usercfg)
- const std::list < Submitter * > & GetSubmitters () const

6.267.1 Detailed Description

Class responsible for loading **Submitter** (p. 306) plugins The **Submitter** (p. 306) objects returned by a **SubmitterLoader** (p. 307) must not be used after the **SubmitterLoader** (p. 307) goes out of scope.

6.267.2 Constructor & Destructor Documentation

6.267.2.1 Arc::SubmitterLoader::SubmitterLoader()

Constructor Creates a new SubmitterLoader (p. 307).

6.267.2.2 Arc::SubmitterLoader::~SubmitterLoader()

Destructor Calling the destructor destroys all Submitters loaded by the **SubmitterLoader** (p. 307) instance.

6.267.3 Member Function Documentation

6.267.3.1 const std::list<Submitter*>& Arc::SubmitterLoader::GetSubmitters () const [inline]

Retrieve the list of loaded Submitters.

Returns

A reference to the list of Submitters.

6.267.3.2 Submitter* Arc::SubmitterLoader::load (const std::string & name, const UserConfig & usercfg)

Load a new Submitter (p. 306)

Parameters

```
name The name of the Submitter (p. 306) to load. usercfg The UserConfig (p. 331) object for the new Submitter (p. 306).
```

Returns


A pointer to the new **Submitter** (p. 306) (NULL on error).

The documentation for this class was generated from the following file:

· Submitter.h

6.268 Arc::SubmitterPluginArgument Class Reference

Inheritance diagram for Arc::SubmitterPluginArgument:



The documentation for this class was generated from the following file:

• Submitter.h

6.269 Arc::TargetGenerator Class Reference

Target generation class

#include <TargetGenerator.h>

Public Member Functions

- TargetGenerator (const UserConfig &usercfg)
- void **GetTargets** (int targetType, int detailLevel)
- const std::list< ExecutionTarget > & FoundTargets () const
- std::list< ExecutionTarget > & ModifyFoundTargets ()
- const std::list< XMLNode * > & FoundJobs () const
- bool AddService (const URL &url)
- bool AddIndexServer (const URL &url)
- void **AddTarget** (const **ExecutionTarget** &target)
- void AddJob (const XMLNode &job)
- void PrintTargetInfo (bool longlist) const
- SimpleCounter & ServiceCounter (void)

6.269.1 Detailed Description

Target generation class The **TargetGenerator** (p. 308) class is the umbrella class for resource discovery and information retrieval (index servers and computing clusters). It can also be used to locate user Grid jobs but does not collect the job details (see the arcsync CLI)). The **TargetGenerator** (p. 308) loads **TargetRetriever** (p. 311) plugins (which implements the actual information retrieval) from **URL** (p. 320) objects found in the **UserConfig** (p. 331) object passed to its constructor using the custem **TargetRetrieverLoader** (p. 312). E.g. if an **URL** (p. 320) pointing to an ARC1 computing resource is found in the **UserConfig** (p. 331) object the TargetRetrieverARC1 is loaded.

6.269.2 Constructor & Destructor Documentation

6.269.2.1 Arc::TargetGenerator::TargetGenerator (const UserConfig & usercfg)

Create a **TargetGenerator** (p. 308) object.

Default constructor to create a TargeGenerator. The constructor reads the computing and index service **URL** (p. 320) objects from the passed **UserConfig** (p. 331) object using the **UserConfig** (p. 331):GetSelectedServices method. From each **URL** (p. 320) a matching specialized **TargetRetriever** (p. 311) plugin is loaded using the **TargetRetrieverLoader** (p. 312).

Parameters

usercfg Reference to **UserConfig** (p. 331) object with **URL** (p. 320) objects to computing and/or index services and paths to user credentials.

6.269.3 Member Function Documentation

6.269.3.1 bool Arc::TargetGenerator::AddIndexServer (const URL & url)

Add a new index server to the foundIndexServers list.

Method to add a new index server to the list of foundIndexServers in a thread secure way. Compares the argument **URL** (p. 320) against the servers returned by **UserConfig::GetRejectedServices** (p. 343) and only allows to add the service if not specifically rejected.

Parameters

url URL (p. 320) pointing to the index server.

6.269.3.2 void Arc::TargetGenerator::AddJob (const XMLNode & job)

Add a new Job (p. 182) to the foundJobs list.

Method to add a new **Job** (p. 182) (usually discovered by a **TargetRetriever** (p. 311)) to the list of found-Jobs in a thread secure way.

Parameters

job XMLNode (p. 389) describing the job.

6.269.3.3 bool Arc::TargetGenerator::AddService (const URL & url)

Add a new computing service to the foundServices list.

Method to add a new service to the list of foundServices in a thread secure way. Compares the argument **URL** (p. 320) against the services returned by **UserConfig::GetRejectedServices** (p. 343) and only allows to add the service if not specifically rejected.

Parameters

url URL (p. 320) pointing to the information system of the computing service.

6.269.3.4 void Arc::TargetGenerator::AddTarget (const ExecutionTarget & target)

Add a new ExecutionTarget (p. 153) to the foundTargets list.

Method to add a new **ExecutionTarget** (p. 153) (usually discovered by a **TargetRetriever** (p. 311)) to the list of foundTargets in a thread secure way.

Parameters

target ExecutionTarget (p. 153) to be added.

6.269.3.5 const std::list<XMLNode*>& Arc::TargetGenerator::FoundJobs () const

Return Grid jobs found by GetTargets.

Method to return the list of Grid jobs found by a call to the GetTargets method.

6.269.3.6 const std::list<ExecutionTarget>& Arc::TargetGenerator::FoundTargets () const

Return targets found by GetTargets.

Method to return a const list of **ExecutionTarget** (p. 153) objects (currently only supported Target type) found by the GetTarget method.

6.269.3.7 void Arc::TargetGenerator::GetTargets (int targetType, int detailLevel)

Find available targets.

Method to prepare a list of chosen Targets with a specified detail level. Current implementation supports finding computing clusters (**ExecutionTarget** (p. 153)) with full detail level and Grid jobs with limited detail level.

Parameters

```
targetType 0 = ExecutionTarget (p. 153), 1 = Grid jobsdetailLevel 1 = All details, 2 = Limited details (not implemented)
```

6.269.3.8 std::list<ExecutionTarget>& Arc::TargetGenerator::ModifyFoundTargets ()

Return targets found by GetTargets.

Method to return the list of **ExecutionTarget** (p. 153) objects (currently only supported Target type) found by the GetTarget method.

6.269.3.9 void Arc::TargetGenerator::PrintTargetInfo (bool longlist) const

Prints target information.

Method to print information of the found targets to std::cout.

Parameters

longlist false for minimal information, true for detailed information

6.269.3.10 SimpleCounter& Arc::TargetGenerator::ServiceCounter(void)

Returns reference to worker counter.

This method returns reference to counter which keeps amount of started worker threads communicating with services asynchronously. The counter must be incremented for every thread started and decremented when thread exits. Main thread will then wait till counters drops to zero.

The documentation for this class was generated from the following file:


• TargetGenerator.h

6.270 Arc::TargetRetriever Class Reference

TargetRetriever base class

#include <TargetRetriever.h>

Inheritance diagram for Arc::TargetRetriever:



Public Member Functions

• virtual void **GetTargets** (**TargetGenerator** &mom, int targetType, int detailLevel)=0

Protected Member Functions

• TargetRetriever (const UserConfig &usercfg, const URL &url, ServiceType st, const std::string &flavour)

6.270.1 Detailed Description

TargetRetriever base class The **TargetRetriever** (p. 311) class is a pure virtual base class to be used for grid flavour specializations. It is designed to work in conjunction with the **TargetGenerator** (p. 308).

6.270.2 Constructor & Destructor Documentation

6.270.2.1 Arc::TargetRetriever::TargetRetriever (const UserConfig & usercfg, const URL & url, ServiceType st, const std::string & flavour) [protected]

TargetRetriever (p. 311) constructor.

Default constructor to create a TargeGenerator. The constructor reads the computing and index service **URL** (p. 320) objects from the

Parameters

```
usercfg
url
st
flavour
```

6.270.3 Member Function Documentation

6.270.3.1 virtual void Arc::TargetRetriever::GetTargets (TargetGenerator & mom, int targetType, int detailLevel) [pure virtual]

Method for collecting targets.

Pure virtual method for collecting targets. Implementation depends on the Grid middleware in question and is thus left to the specialized class.

Parameters

```
mom is the reference to the TargetGenerator (p. 308) which has loaded the TargetRetriever (p. 311) targetType is the identification of targets to find (0=ExecutionTargets, 1=Grid Jobs) detailLevel is the required level of details (1 = All details, 2 = Limited details)
```


The documentation for this class was generated from the following file:

· TargetRetriever.h

6.271 Arc::TargetRetrieverLoader Class Reference

```
#include <TargetRetriever.h>
```

Inheritance diagram for Arc::TargetRetrieverLoader:



Public Member Functions

- TargetRetrieverLoader ()
- ∼TargetRetrieverLoader ()
- TargetRetriever * load (const std::string &name, const UserConfig &usercfg, const URL &url, const ServiceType &st)
- const std::list< TargetRetriever * > & GetTargetRetrievers () const

6.271.1 Detailed Description

Class responsible for loading **TargetRetriever** (p. 311) plugins The **TargetRetriever** (p. 311) objects returned by a **TargetRetrieverLoader** (p. 312) must not be used after the **TargetRetrieverLoader** (p. 312) goes out of scope.

6.271.2 Constructor & Destructor Documentation

$\textbf{6.271.2.1} \quad Arc:: Target Retriever Loader:: Target Retriever Loader (\quad)$

Constructor Creates a new **TargetRetrieverLoader** (p. 312).

6.271.2.2 Arc::TargetRetrieverLoader::~TargetRetrieverLoader()

Destructor Calling the destructor destroys all TargetRetrievers loaded by the **TargetRetrieverLoader** (p. 312) instance.

6.271.3 Member Function Documentation

6.271.3.1 const std::list<TargetRetriever*>& Arc::TargetRetrieverLoader::GetTargetRetrievers
() const [inline]

Retrieve the list of loaded TargetRetrievers.

Returns

A reference to the list of TargetRetrievers.

6.271.3.2 TargetRetriever* Arc::TargetRetrieverLoader::load (const std::string & name, const UserConfig & usercfg, const URL & url, const ServiceType & st)

Load a new **TargetRetriever** (p. 311)

Parameters

```
name The name of the TargetRetriever (p. 311) to load.
usercfg The UserConfig (p. 331) object for the new TargetRetriever (p. 311).
url The URL (p. 320) used to contact the target.
st specifies service type of the target.
```

Returns


A pointer to the new **TargetRetriever** (p. 311) (NULL on error).

The documentation for this class was generated from the following file:

· TargetRetriever.h

6.272 Arc::TargetRetrieverPluginArgument Class Reference

Inheritance diagram for Arc::TargetRetrieverPluginArgument:




The documentation for this class was generated from the following file:

· TargetRetriever.h

6.273 Test::TestMCC Class Reference

Inheritance diagram for Test::TestMCC:




The documentation for this class was generated from the following files:

- loader/TestMCC.h
- · message/TestMCC.h

6.274 Test::TestService Class Reference

Inheritance diagram for Test::TestService:



Public Member Functions

• virtual Arc::MCC_Status process (Arc::Message &request, Arc::Message &response)

6.274.1 Member Function Documentation

6.274.1.1 virtual Arc::MCC_Status Test::TestService::process (Arc::Message & request, Arc::Message & response) [virtual]

Method for processing of requests and responses. This method is called by preceding MCC in chain when a request needs to be processed. This method must call similar method of next MCC in chain unless any failure happens. Result returned by call to next MCC should be processed and passed back to previous MCC. In case of failure this method is expected to generate valid error response and return it back to previous MCC without calling the next one.

Parameters

request The request that needs to be processed.

response A Message object that will contain the response of the request when the method returns.

Returns

An object representing the status of the call.

Implements Arc::MCCInterface (p. 206).

The documentation for this class was generated from the following file:

· TestService.h

6.275 Arc::ThreadInitializer Class Reference

The documentation for this class was generated from the following file:

• Thread.h

6.276 Arc::ThreadRegistry Class Reference

#include <Thread.h>

Public Member Functions

- void RegisterThread (void)
- void UnregisterThread (void)
- bool WaitOrCancel (int timeout)
- bool **WaitForExit** (int timeout=-1)

6.276.1 Detailed Description

This class is a set of conditions, mutexes, etc. conveniently exposed to monitor running child threads and to wait till they exit. There are no protections against race conditions. So use it carefully.

6.276.2 Member Function Documentation

6.276.2.1 bool Arc::ThreadRegistry::WaitForExit (int timeout = -1)

Wait for registered threads to exit. Leave after timeout miliseconds if failed. Returns true if all registered threads reported their exit.

6.276.2.2 bool Arc::ThreadRegistry::WaitOrCancel (int timeout)

Wait for timeout milliseconds or cancel request. Returns true if cancel request received.

The documentation for this class was generated from the following file:

· Thread.h

6.277 Arc::Time Class Reference

A class for storing and manipulating times.

#include <DateTime.h>

Public Member Functions

- Time ()
- Time (time_t)
- **Time** (time t time, uint32 t nanosec)
- **Time** (const std::string &)
- Time & operator= (time_t)
- Time & operator= (const Time &)
- Time & operator= (const char *)
- Time & operator= (const std::string &)
- void **SetTime** (time_t)

- void **SetTime** (time_t time, uint32_t nanosec)
- time_t GetTime () const
- operator std::string () const
- std::string str (const TimeFormat &=time format) const
- bool **operator**< (const **Time** &) const
- bool **operator**> (const **Time** &) const
- bool **operator**<= (const **Time** &) const
- bool **operator**>= (const **Time** &) const
- bool **operator==** (const **Time** &) const
- bool **operator!=** (const **Time** &) const
- Time operator+ (const Period &) const
- Time operator- (const Period &) const
- Period operator- (const Time &) const

Static Public Member Functions

- static void **SetFormat** (const **TimeFormat** &)
- static TimeFormat GetFormat ()

6.277.1 Detailed Description

A class for storing and manipulating times.

6.277.2 Constructor & Destructor Documentation

6.277.2.1 Arc::Time::Time()

Default constructor. The time is put equal the current time.

6.277.2.2 Arc::Time::Time (time_t)

Constructor that takes a time_t variable and stores it.

6.277.2.3 Arc::Time::Time (time_t time, uint32_t nanosec)

Constructor that takes a fine grained time variables and stores them.

6.277.2.4 Arc::Time::Time (const std::string &)

Constructor that tries to convert a string into a time_t.

6.277.3 Member Function Documentation

6.277.3.1 static TimeFormat Arc::Time::GetFormat() [static]

Gets the default format for time strings.

6.277.3.2 time_t Arc::Time::GetTime () const

gets the time

6.277.3.3 Arc::Time::operator std::string () const

Returns a string representation of the time, using the default format.

6.277.3.4 bool Arc::Time::operator!= (const Time &) const

Comparing two **Time** (p. 316) objects.

6.277.3.5 Time Arc::Time::operator+ (const Period &) const

Adding **Time** (p. 316) object with **Period** (p. 242) object.

6.277.3.6 Time Arc::Time::operator-(const Period &) const

Subtracting **Period** (p. 242) object from **Time** (p. 316) object.

6.277.3.7 Period Arc::Time::operator- (const Time &) const

Subtracting **Time** (p. 316) object from the other **Time** (p. 316) object.

6.277.3.8 bool Arc::Time::operator< (const Time &) const

Comparing two Time (p. 316) objects.

6.277.3.9 bool Arc::Time::operator<= (const Time &) const

Comparing two **Time** (p. 316) objects.

6.277.3.10 Time& Arc::Time::operator= (const char *)

Assignment operator from a char pointer.

6.277.3.11 Time& Arc::Time::operator=(const std::string &)

Assignment operator from a string.

6.277.3.12 Time& Arc::Time::operator=(const Time &)

Assignment operator from a **Time** (p. 316).

6.277.3.13 Time& Arc::Time::operator=(time_t)

Assignment operator from a time_t.

6.277.3.14 bool Arc::Time::operator== (const Time &) const

Comparing two Time (p. 316) objects.

6.277.3.15 bool Arc::Time::operator> (const Time &) const

Comparing two **Time** (p. 316) objects.

6.277.3.16 bool Arc::Time::operator>= (const Time &) const

Comparing two Time (p. 316) objects.

6.277.3.17 static void Arc::Time::SetFormat (const TimeFormat &) [static]

Sets the default format for time strings.

6.277.3.18 void Arc::Time::SetTime (time_t)

sets the time

6.277.3.19 void Arc::Time::SetTime (time_t time, uint32_t nanosec)

sets the fine grained time

6.277.3.20 std::string Arc::Time::str (const TimeFormat & = time_format) const

Returns a string representation of the time, using the specified format.


The documentation for this class was generated from the following file:

• DateTime.h

6.278 ArcSec::TimeAttribute Class Reference

#include <DateTimeAttribute.h>

Inheritance diagram for ArcSec::TimeAttribute:



Public Member Functions

- virtual bool equal (AttributeValue *other, bool check_id=true)
- virtual std::string encode ()
- virtual std::string **getType** ()
- virtual std::string getId ()

6.278.1 Detailed Description

Format: HHMMSSZ HH:MM:SS HH:MM:SS+HH:MM HH:MM:SSZ

6.278.2 Member Function Documentation

6.278.2.1 virtual std::string ArcSec::TimeAttribute::encode() [virtual]

encode the value in a string format

Implements ArcSec::AttributeValue (p. 57).

6.278.2.2 virtual bool ArcSec::TimeAttribute::equal (AttributeValue * value, bool check_id = true) [virtual]

Evluate whether "this" equale to the parameter value

Implements ArcSec::AttributeValue (p. 58).

6.278.2.3 virtual std::string ArcSec::TimeAttribute::getId() [inline, virtual]

Get the AttributeId of the <Attribute>

Implements ArcSec::AttributeValue (p. 58).

6.278.2.4 virtual std::string ArcSec::TimeAttribute::getType() [inline, virtual]

Get the DataType of the <Attribute>


Implements ArcSec::AttributeValue (p. 58).

The documentation for this class was generated from the following file:

• DateTimeAttribute.h

6.279 Arc::URL Class Reference

Inheritance diagram for Arc::URL:



Public Types

• enum Scope

Public Member Functions

- **URL** ()
- URL (const std::string &url)
- virtual ∼**URL** ()
- const std::string & Protocol () const
- void ChangeProtocol (const std::string &newprot)
- bool IsSecureProtocol () const
- const std::string & Username () const
- const std::string & Passwd () const
- const std::string & Host () const
- void **ChangeHost** (const std::string &newhost)
- int Port () const
- void **ChangePort** (int newport)
- const std::string & Path () const
- std::string FullPath () const
- void **ChangePath** (const std::string &newpath)
- const std::map< std::string, std::string > & HTTPOptions () const
- const std::string & HTTPOption (const std::string &option, const std::string &undefined="") const
- const std::list< std::string > & LDAPAttributes () const
- void AddLDAPAttribute (const std::string &attribute)
- Scope LDAPScope () const
- void ChangeLDAPScope (const Scope newscope)
- const std::string & LDAPFilter () const
- void ChangeLDAPFilter (const std::string &newfilter)
- const std::map< std::string, std::string > & **Options** () const
- const std::string & Option (const std::string &option, const std::string &undefined="") const
- const std::map< std::string, std::string > & MetaDataOptions () const
- const std::string & MetaDataOption (const std::string &option, const std::string &undefined="") const
- void **AddOption** (const std::string &option, const std::string &value, bool overwrite=true)
- void AddMetaDataOption (const std::string &option, const std::string &value, bool overwrite=true)
- const std::list< URLLocation > & Locations () const
- const std::map< std::string, std::string > & CommonLocOptions () const
- const std::string & CommonLocOption (const std::string &option, const std::string &undefined="") const
- virtual std::string str () const
- virtual std::string **plainstr** () const
- virtual std::string fullstr () const
- virtual std::string ConnectionURL () const
- bool operator< (const URL &url) const
- bool operator== (const URL &url) const
- operator bool () const
- std::map< std::string, std::string > **ParseOptions** (const std::string & optstring, char separator)

Static Public Member Functions

• static std::string **OptionString** (const std::map< std::string, std::string > &options, char separator)

Static Protected Member Functions

- static std::string **BaseDN2Path** (const std::string &)
- static std::string Path2BaseDN (const std::string &)

Protected Attributes

- std::string protocol
- std::string username
- std::string passwd
- std::string host
- · bool ip6addr
- int port
- std::string path
- std::map< std::string, std::string > **httpoptions**
- std::map< std::string, std::string > **metadataoptions**
- std::list< std::string > **ldapattributes**
- Scope Idapscope
- std::string ldapfilter
- std::map< std::string, std::string > **urloptions**
- std::list< URLLocation > locations
- std::map< std::string, std::string > **commonlocoptions**
- bool valid

Friends

• std::ostream & operator<< (std::ostream &out, const URL &u)

6.279.1 Member Enumeration Documentation

6.279.1.1 enum Arc::URL::Scope

Scope for LDAP URLs

6.279.2 Constructor & Destructor Documentation

6.279.2.1 Arc::URL::URL()

Empty constructor. Necessary when the class is part of another class and the like.

6.279.2.2 Arc::URL::URL (const std::string & url)

Constructs a new URL (p. 320) from a string representation.

6.279.2.3 virtual Arc::URL::~URL() [virtual]

URL (p. 320) Destructor

6.279.3 Member Function Documentation

6.279.3.1 void Arc::URL::AddLDAPAttribute (const std::string & attribute)

Adds an LDAP attribute.

6.279.3.2 void Arc::URL::AddMetaDataOption (const std::string & option, const std::string & value, bool overwrite = true)

Adds a metadata option

6.279.3.3 void Arc::URL::AddOption (const std::string & option, const std::string & value, bool overwrite = true)

Adds a URL (p. 320) option.

6.279.3.4 static std::string Arc::URL::BaseDN2Path (const std::string &) [static, protected]

a private method that converts an ldap basedn to a path.

6.279.3.5 void Arc::URL::ChangeHost (const std::string & newhost)

Changes the hostname of the URL (p. 320).

6.279.3.6 void Arc::URL::ChangeLDAPFilter (const std::string & newfilter)

Changes the LDAP filter.

6.279.3.7 void Arc::URL::ChangeLDAPScope (const Scope newscope)

Changes the LDAP scope.

6.279.3.8 void Arc::URL::ChangePath (const std::string & newpath)

Changes the path of the URL (p. 320).

6.279.3.9 void Arc::URL::ChangePort (int newport)

Changes the port of the URL (p. 320).

6.279.3.10 void Arc::URL::ChangeProtocol (const std::string & newprot)

Changes the protocol of the URL (p. 320).

6.279.3.11 const std::string& Arc::URL::CommonLocOption (const std::string & option, const std::string & undefined = "") const

Returns the value of a common location option.

Parameters

```
option The option whose value is returned.undefined This value is returned if the common location option is not defined.
```

6.279.3.12 const std::map<std::string, std::string>& Arc::URL::CommonLocOptions () const

Returns the common location options if any.

```
6.279.3.13 virtual std::string Arc::URL::ConnectionURL() const [virtual]
```

Returns a string representation with protocol, host and port only

```
6.279.3.14 std::string Arc::URL::FullPath ( ) const
```

Returns the path of the URL (p. 320) with all options attached.

```
6.279.3.15 virtual std::string Arc::URL::fullstr() const [virtual]
```

Returns a string representation including options and locations

Reimplemented in Arc::URLLocation (p. 330).

6.279.3.16 const std::string& Arc::URL::Host () const

Returns the hostname of the URL (p. 320).

6.279.3.17 const std::string& Arc::URL::HTTPOption (const std::string & option, const std::string & undefined = "") const

Returns the value of an HTTP option.

Parameters

```
option The option whose value is returned.undefined This value is returned if the HTTP option is not defined.
```

6.279.3.18 const std::map<std::string, std::string>& Arc::URL::HTTPOptions () const

Returns HTTP options if any.

6.279.3.19 bool Arc::URL::IsSecureProtocol() const

Indicates whether the protocol is secure or not.

6.279.3.20 const std::list<std::string>& Arc::URL::LDAPAttributes () const

Returns the LDAP attributes if any.

6.279.3.21 const std::string& Arc::URL::LDAPFilter () const

Returns the LDAP filter.

6.279.3.22 Scope Arc::URL::LDAPScope () const

Returns the LDAP scope.

6.279.3.23 const std::list<URLLocation>& Arc::URL::Locations () const

Returns the locations if any.

6.279.3.24 const std::string& Arc::URL::MetaDataOption (const std::string & option, const std::string & undefined = "") const

Returns the value of a metadata option.

Parameters

option The option whose value is returned.

undefined This value is returned if the metadata option is not defined.

6.279.3.25 const std::map<std::string>& Arc::URL::MetaDataOptions () const

Returns metadata options if any.

6.279.3.26 Arc::URL::operator bool () const

Check if instance holds valid **URL** (p. 320)

6.279.3.27 bool Arc::URL::operator< (const URL & url) const

Compares one URL (p. 320) to another

6.279.3.28 bool Arc::URL::operator== (const URL & url) const

Is one URL (p. 320) equal to another?

6.279.3.29 const std::string& Arc::URL::Option (const std::string & option, const std::string & undefined = "") const

Returns the value of a URL (p. 320) option.

Parameters

option The option whose value is returned. *undefined* This value is returned if the URL (p. 320) option is not defined.

6.279.3.30 const std::map<std::string, std::string>& Arc::URL::Options () const

Returns **URL** (p. 320) options if any.

6.279.3.31 static std::string Arc::URL::OptionString (const std::map < std::string, std::string > & options, char separator) [static]

Returns a string representation of the options given in the options map

6.279.3.32 std::map<std::string, std::string> Arc::URL::ParseOptions (const std::string & optstring, char separator)

Parse a string of options separated by separator into an attribute->value map

6.279.3.33 const std::string& Arc::URL::Passwd () const

Returns the password of the URL (p. 320).

6.279.3.34 const std::string& Arc::URL::Path () const

Returns the path of the URL (p. 320).

6.279.3.35 static std::string Arc::URL::Path2BaseDN (const std::string &) [static, protected]

a private method that converts an ldap path to a basedn.

6.279.3.36 virtual std::string Arc::URL::plainstr() const [virtual]

Returns a string representation of the URL (p. 320) without any options

6.279.3.37 int Arc::URL::Port () const

Returns the port of the URL (p. 320).

6.279.3.38 const std::string& Arc::URL::Protocol () const

Returns the protocol of the URL (p. 320).

6.279.3.39 virtual std::string Arc::URL::str() const [virtual]

Returns a string representation of the URL (p. 320) including meta-options.

Reimplemented in Arc::URLLocation (p. 330).

6.279.3.40 const std::string& Arc::URL::Username () const

Returns the username of the URL (p. 320).

6.279.4 Friends And Related Function Documentation

6.279.4.1 std::ostream & operator << (std::ostream & out, const URL & u) [friend]

Overloaded operator << to print a URL (p. 320).

6.279.5 Field Documentation

6.279.5.1 std::map<std::string, std::string> Arc::URL::commonlocoptions [protected]

common location options for index server URLs.

6.279.5.2 std::string Arc::URL::host [protected]

hostname of the url.

6.279.5.3 std::map<std::string, std::string> Arc::URL::httpoptions [protected]

HTTP options of the url.

6.279.5.4 bool Arc::URL::ip6addr [protected]

if host is IPv6 numerical address notation.

6.279.5.5 std::list<std::string> Arc::URL::ldapattributes [protected]

LDAP attributes of the url.

6.279.5.6 std::string Arc::URL::ldapfilter [protected]

LDAP filter of the url.

6.279.5.7 Scope Arc::URL::ldapscope [protected]

LDAP scope of the url.

6.279.5.8 std::list<URLLocation> Arc::URL::locations [protected]

locations for index server URLs.

6.279.5.9 std::map<std::string, std::string> Arc::URL::metadataoptions [protected]

Meta data options

6.279.5.10 std::string Arc::URL::passwd [protected]

password of the url.

6.279.5.11 std::string Arc::URL::path [protected]

the url path.

6.279.5.12 int Arc::URL::port [protected]

portnumber of the url.

6.279.5.13 std::string Arc::URL::protocol [protected]

the url protocol.

6.279.5.14 std::map<std::string, std::string> Arc::URL::urloptions [protected]

options of the url.

6.279.5.15 std::string Arc::URL::username [protected]

username of the url.

6.279.5.16 bool Arc::URL::valid [protected]

flag to describe validity of URL (p. 320)

The documentation for this class was generated from the following file:


• URL.h

6.280 Arc::URLLocation Class Reference

Class to hold a resolved URL (p. 320) location.

#include <URL.h>

Inheritance diagram for Arc::URLLocation:



Public Member Functions

- URLLocation (const std::string &url)
- URLLocation (const std::string &url, const std::string &name)
- URLLocation (const URL &url)
- URLLocation (const URL &url, const std::string &name)
- URLLocation (const std::map< std::string, std::string > &options, const std::string &name)
- virtual ~URLLocation ()
- const std::string & Name () const
- virtual std::string str () const
- virtual std::string fullstr () const

Protected Attributes

• std::string name

6.280.1 Detailed Description

Class to hold a resolved URL (p. 320) location. It is specific to file indexing service registrations.

6.280.2 Constructor & Destructor Documentation

6.280.2.1 Arc::URLLocation::URLLocation (const std::string & url)

Creates a URLLocation (p. 328) from a string representation.

6.280.2.2 Arc::URLLocation::URLLocation (const std::string & url, const std::string & name)

Creates a **URLLocation** (p. 328) from a string representation and a name.

6.280.2.3 Arc::URLLocation::URLLocation (const URL & url)

Creates a **URLLocation** (p. 328) from a **URL** (p. 320).

6.280.2.4 Arc::URLLocation::URLLocation (const URL & url, const std::string & name)

Creates a URLLocation (p. 328) from a URL (p. 320) and a name.

6.280.2.5 Arc::URLLocation::URLLocation (const std::map< std::string, std::string > & options, const std::string & name)

Creates a URLLocation (p. 328) from options and a name.

6.280.2.6 virtual Arc::URLLocation::~URLLocation() [virtual]

URLLocation (p. 328) destructor.

6.280.3 Member Function Documentation

6.280.3.1 virtual std::string Arc::URLLocation::fullstr() const [virtual]

Returns a string representation including options and locations

Reimplemented from Arc::URL (p. 324).

6.280.3.2 const std::string& Arc::URLLocation::Name () const

Returns the **URLLocation** (p. 328) name.

6.280.3.3 virtual std::string Arc::URLLocation::str() const [virtual]

Returns a string representation of the URLLocation (p. 328).

Reimplemented from Arc::URL (p. 327).

6.280.4 Field Documentation

6.280.4.1 std::string Arc::URLLocation::name [protected]

the **URLLocation** (p. 328) name as registered in the indexing service.

The documentation for this class was generated from the following file:

• URL.h

6.281 Arc::URLMap Class Reference

Data Structures

• class map_entry

The documentation for this class was generated from the following file:

• URLMap.h

6.282 Arc::User Class Reference

The documentation for this class was generated from the following file:

• User.h

6.283 Arc::UserConfig Class Reference

User configuration class

#include <UserConfig.h>

Public Member Functions

- UserConfig (initializeCredentialsType initializeCredentials=initializeCredentialsType())
- UserConfig (const std::string &conffile, initializeCredentialsType initializeCredentials=initializeCredentialsType(), bool loadSysConfig=true)
- UserConfig (const std::string &conffile, const std::string &jfile, initializeCredentialsType initializeCredentials=initializeCredentialsType(), bool loadSysConfig=true)
- **UserConfig** (const long int &ptraddr)
- void InitializeCredentials ()
- bool CredentialsFound () const
- bool LoadConfigurationFile (const std::string &conffile, bool ignoreJobListFile=true)
- bool SaveToFile (const std::string &filename) const
- void ApplyToConfig (BaseConfig &ccfg) const
- operator bool () const
- bool operator! () const
- bool **JobListFile** (const std::string &path)
- const std::string & JobListFile () const
- bool **AddServices** (const std::list< std::string > &services, ServiceType st)
- bool **AddServices** (const std::list< std::string > &selected, const std::list< std::string > &rejected, ServiceType st)
- const URLListMap & GetSelectedServices (ServiceType st) const
- const URLListMap & GetRejectedServices (ServiceType st) const
- void ClearSelectedServices ()
- void **ClearSelectedServices** (ServiceType st)
- void ClearRejectedServices ()
- void **ClearRejectedServices** (ServiceType st)
- bool **Timeout** (int newTimeout)
- int Timeout () const
- bool **Verbosity** (const std::string &newVerbosity)
- const std::string & Verbosity () const
- bool **Broker** (const std::string &name)
- bool **Broker** (const std::string &name, const std::string &argument)
- const std::pair< std::string, std::string > & **Broker** () const
- bool **Bartender** (const std::vector< **URL** > &urls)
- void AddBartender (const URL &url)
- const std::vector< URL > & Bartender () const
- bool VOMSServerPath (const std::string &path)

- const std::string & VOMSServerPath () const
- bool UserName (const std::string &name)
- const std::string & UserName () const
- bool **Password** (const std::string &newPassword)
- const std::string & Password () const
- bool **ProxyPath** (const std::string &newProxyPath)
- const std::string & ProxyPath () const
- bool **CertificatePath** (const std::string &newCertificatePath)
- const std::string & CertificatePath () const
- bool **KeyPath** (const std::string &newKeyPath)
- const std::string & KeyPath () const
- bool **KeyPassword** (const std::string &newKeyPassword)
- const std::string & KeyPassword () const
- bool **KeySize** (int newKeySize)
- int **KeySize** () const
- bool CACertificatePath (const std::string &newCACertificatePath)
- const std::string & CACertificatePath () const
- bool **CACertificatesDirectory** (const std::string &newCACertificatesDirectory)
- const std::string & CACertificatesDirectory () const
- bool **CertificateLifeTime** (const **Period** &newCertificateLifeTime)
- const Period & CertificateLifeTime () const
- bool SLCS (const URL &newSLCS)
- const URL & SLCS () const
- bool **StoreDirectory** (const std::string &newStoreDirectory)
- const std::string & StoreDirectory () const
- bool **IdPName** (const std::string &name)
- const std::string & IdPName () const
- bool **OverlayFile** (const std::string &path)
- const std::string & OverlayFile () const
- bool **UtilsDirPath** (const std::string &dir)
- const std::string & UtilsDirPath () const

Static Public Attributes

- static const std::string ARCUSERDIRECTORY
- static const std::string SYSCONFIG
- static const std::string SYSCONFIGARCLOC
- static const std::string **DEFAULTCONFIG**
- static const std::string EXAMPLECONFIG
- static const int **DEFAULT TIMEOUT** = 20
- static const std::string DEFAULT_BROKER

6.283.1 Detailed Description

User configuration class This class provides a container for a selection of various attributes/parameters which can be configured to needs of the user, and can be read by implementing instances or programs. The class can be used in two ways. One can create a object from a configuration file, or simply set the desired attributes by using the setter method, associated with every setable attribute. The list of attributes which can be configured in this class are:

- certificatepath / CertificatePath(const std::string&) (p. 341)
- keypath / KeyPath(const std::string&) (p. 347)
- proxypath / ProxyPath(const std::string&) (p. 352)
- cacertificatesdirectory / CACertificatesDirectory(const std::string&) (p. 340)
- cacertificatepath / CACertificatePath(const std::string&) (p. 339)
- timeout / **Timeout(int)** (p. 354)
- joblist / JobListFile(const std::string&) (p. 346)
- defaultservices / AddServices(const std::list<std::string>&, const std::list<std::string>&, ServiceType) (p. 336)
- rejectservices / AddServices(const std::list<std::string>&, const std::list<std::string>&, ServiceType) (p. 336)
- verbosity / Verbosity(const std::string&) (p. 356)
- brokername / Broker(const std::string&) (p. 338) or Broker(const std::string&, const std::string&) (p. 338)
- brokerarguments / **Broker(const std::string&)** (p. 338) or **Broker(const std::string&, const std::string&)** (p. 338)
- bartender / Bartender(const std::list<URL>&)
- vomsserverpath / VOMSServerPath(const std::string&) (p. 356)
- username / UserName(const std::string&) (p. 355)
- password / **Password(const std::string&)** (p. 351)
- keypassword / **KeyPassword(const std::string&)** (p. 346)
- keysize / **KeySize(int)** (p. 348)
- certificatelifetime / CertificateLifeTime(const Period&) (p. 340)
- slcs / **SLCS(const URL&)** (p. 353)
- storedirectory / **StoreDirectory(const std::string&)** (p. 353)
- idpname / IdPName(const std::string&) (p. 344)

where the first term is the name of the attribute used in the configuration file, and the second term is the associated setter method (for more information about a given attribute see the description of the setter method).

The configuration file should have a INI-style format and the **IniConfig** (p. 177) class will thus be used to parse the file. The above mentioned attributes should be placed in the common section. Another section is also valid in the configuration file, which is the alias section. Here it is possible to define aliases representing one or multiple services. These aliases can be used in the **AddServices(const std::list<std::string>&**, **ServiceType)** (p. 336) and **AddServices(const std::list<std::string>&**, **ServiceType)** (p. 336) methods.

The **UserConfig** (p. 331) class also provides a method **InitializeCredentials**() (p. 345) for locating user credentials by searching in different standard locations. The **CredentialsFound**() (p. 343) method can be used to test if locating the credentials succeeded.

6.283.2 Constructor & Destructor Documentation

6.283.2.1 Arc::UserConfig::UserConfig (initializeCredentialsType *initializeCredentialsType ()*)

Create a **UserConfig** (p. 331) object.

The **UserConfig** (p. 331) object created by this constructor initializes only default values, and if specified by the *initializeCredentials* boolean credentials will be tried initialized using the **InitializeCredentials**() (p. 345) method. The object is only non-valid if initialization of credentials fails which can be checked with the **operator bool**() (p. 350) method.

Parameters

initializeCredentials is a optional boolean indicating if the **InitializeCredentials**() (p. 345) method should be invoked, the default is true.

See also

```
InitializeCredentials() (p. 345) operator bool() (p. 350)
```

6.283.2.2 Arc::UserConfig::UserConfig (const std::string & conffile, initializeCredentialsType initializeCredentials = initializeCredentialsType (), bool loadSysConfig = true)

Create a UserConfig (p. 331) object.

The **UserConfig** (p. 331) object created by this constructor will, if specified by the *loadSysConfig* boolean, first try to load the system configuration file by invoking the **LoadConfigurationFile**() (p. 349) method, and if this fails a WARNING is reported. Then the configuration file passed will be tried loaded using the before mentioned method, and if this fails an ERROR is reported, and the created object will be non-valid. Note that if the passed file path is empty the example configuration will be tried copied to the default configuration file path specified by DEFAULTCONFIG. If the example file cannot be copied one or more WARNING messages will be reported and no configuration will be loaded. If loading the configurations file succeeded and if *initializeCredentials* is true then credentials will be initialized using the **InitializeCredentials**() (p. 345) method, and if no valid credentials are found the created object will be non-valid.

Parameters

conffile is the path to a INI-configuration file.

initializeCredentials is a boolean indicating if credentials should be initialized, the default is true.

loadSysConfig is a boolean indicating if the system configuration file should be loaded aswell, the default is true.

See also

```
LoadConfigurationFile(const std::string&, bool) (p. 349)
InitializeCredentials() (p. 345)
operator bool() (p. 350)
SYSCONFIG (p. 358)
EXAMPLECONFIG (p. 358)
```

6.283.2.3 Arc::UserConfig::UserConfig (const std::string & conffile, const std::string & jfile, initializeCredentialsType initializeCredentials = initializeCredentialsType (), bool loadSysConfig = true)

Create a **UserConfig** (p. 331) object.

The **UserConfig** (p. 331) object created by this constructor does only differ from the UserConfig(const std::string&, bool, bool) constructor in that it is possible to pass the path of the job list file directly to this constructor. If the job list file *joblistfile* is empty, the behaviour of this constructor is exactly the same as the before mentioned, otherwise the job list file will be initilized by invoking the setter method **JobListFile(const std::string&)** (p. 346). If it fails the created object will be non-valid, otherwise the specified configuration file *conffile* will be loaded with the *ignoreJobListFile* argument set to true.

Parameters

```
conffile is the path to a INI-configuration file
ifile is the path to a (non-)existing job list file.
initializeCredentials is a boolean indicating if credentials should be initialized, the default is true.
loadSysConfig is a boolean indicating if the system configuration file should be loaded aswell, the default is true.
```

See also

```
JobListFile(const std::string&) (p. 346)
LoadConfigurationFile(const std::string&, bool) (p. 349)
InitializeCredentials() (p. 345)
operator bool() (p. 350)
```

6.283.2.4 Arc::UserConfig::UserConfig (const long int & ptraddr)

Language binding constructor.

The passed long int should be a pointer address to a **UserConfig** (p. 331) object, and this address is then casted into this **UserConfig** (p. 331) object.

Parameters

ptraddr is an memory address to a **UserConfig** (p. 331) object.

6.283.3 Member Function Documentation

6.283.3.1 void Arc::UserConfig::AddBartender (const URL & url) [inline]

Set bartenders, used to contact Chelonia.

Takes as input a Bartender URL (p. 320) and adds this to the list of bartenders.

Parameters

url is a URL (p. 320) to be added to the list of bartenders.

See also

```
Bartender(const std::list<URL>&)
Bartender() const (p. 338)
```

6.283.3.2 bool Arc::UserConfig::AddServices (const std::list< std::string > & selected, const std::list< std::string > & rejected, ServiceType st)

Add selected and rejected services.

The only diffence in behaviour of this method compared to the **AddServices(const std::list<std::string>&**, **ServiceType**) (p. 336) method is the input parameters and the format these parameters should follow. Instead of having an optional '-' in front of the string selected and rejected services should be specified in the two different arguments.

Two attributes are indirectly associated with this setter method 'defaultservices' and 'rejectservices'. The values specified with the 'defaultservices' attribute will be added to the list of selected services, and likewise with the 'rejectservices' attribute.

Parameters

selected is a list of services which will be added to the selected services of this object.rejected is a list of services which will be added to the rejected services of this object.st specifies the ServiceType of the services to add.

Returns

This method return false in case an alias cannot be resolved. In any other case true is returned.

See also

```
AddServices(const std::list<std::string>&, ServiceType) (p. 336)
GetSelectedServices() (p. 344)
GetRejectedServices() (p. 343)
ClearSelectedServices() (p. 342)
ClearRejectedServices() (p. 342)
LoadConfigurationFile() (p. 349)
```

6.283.3.3 bool Arc::UserConfig::AddServices (const std::list< std::string > & services, ServiceType st)

Add selected and rejected services.

This method adds selected services and adds services to reject from the specified list *services*, which contains string objects. The syntax of a single element in the list must be expressed in the following two formats:

$$[-] < flavour >:< service \ url > |[-] < alias >$$

where the optional '-' indicate that the service should be added to the private list of services to reject. In the first format the <flavour> part indicates the type of ACC plugin to use when contacting the service, which is specified by the **URL** (p. 320) <service_url>, and in the second format the <alias> part specifies a alias defined in a parsed configuration file, note that the alias must not contain any of the charaters ':', '.', ' or '\t'. If a alias cannot be resolved an ERROR will be reported to the logger and the method will return false. If a element in the list *services* cannot be parsed an ERROR will be reported, and the element is skipped.

Two attributes are indirectly associated with this setter method 'defaultservices' and 'rejectservices'. The values specified with the 'defaultservices' attribute will be added to the list of selected services, and likewise with the 'rejectservices' attribute.

Parameters

services is a list of services to either select or reject.st indicates the type of the specified services.

Returns

This method returns false in case an alias cannot be resolved. In any other case true is returned.

See also

```
AddServices(const std::string&, const std::string&, ServiceType)

GetSelectedServices() (p. 344)

GetRejectedServices() (p. 343)

ClearSelectedServices() (p. 342)

ClearRejectedServices() (p. 342)

LoadConfigurationFile() (p. 349)
```

6.283.3.4 void Arc::UserConfig::ApplyToConfig (BaseConfig & ccfg) const

Apply credentials to **BaseConfig** (p. 60).

This methods sets the **BaseConfig** (p. 60) credentials to the credentials contained in this object. It also passes user defined configuration overlay if any.

See also

```
InitializeCredentials() (p. 345)
CredentialsFound() (p. 343)
BaseConfig (p. 60)
```

Parameters

ccfg a BaseConfig (p. 60) object which will configured with the credentials of this object.

6.283.3.5 bool Arc::UserConfig::Bartender (const std::vector < URL > & urls) [inline]

Set bartenders, used to contact Chelonia.

Takes as input a vector of Bartender URLs.

The attribute associated with this setter method is 'bartender'.

Parameters

urls is a list of URL (p. 320) object to be set as bartenders.

Returns

This method always returns true.

See also

```
AddBartender(const URL&) (p. 335)
Bartender() const (p. 338)
```

6.283.3.6 const std::vector<URL>& Arc::UserConfig::Bartender() const [inline]

Get bartenders.

Returns a list of Bartender URLs

Returns

The list of bartender URL (p. 320) objects is returned.

See also

```
Bartender(const std::list<URL>&)
AddBartender(const URL&) (p. 335)
```

6.283.3.7 bool Arc::UserConfig::Broker (const std::string & name)

Set broker to use in target matching.

The string passed to this method should be in the format:

```
< name > [:< argument >]
```

where the <name> is the name of the broker and cannot contain any ':', and the optional <argument> should contain arguments which should be passed to the broker.

Two attributes are associated with this setter method 'brokername' and 'brokerarguments'.

Parameters

name the broker name and argument specified in the format given above.

Returns

This method allways returns true.

See also

```
Broker (p. 62)
Broker(const std::string&, const std::string&) (p. 338)
Broker() const (p. 339)
DEFAULT_BROKER (p. 357)
```

6.283.3.8 bool Arc::UserConfig::Broker (const std::string & name, const std::string & argument) [inline]

Set broker to use in target matching.

As opposed to the **Broker(const std::string&)** (p. 338) method this method sets broker name and arguments directly from the passed two arguments.

Two attributes are associated with this setter method 'brokername' and 'brokerarguments'.

Parameters

name is the name of the broker.

argument is the arguments of the broker.

Returns

This method always returns true.

See also

```
Broker (p. 62)
Broker(const std::string&) (p. 338)
Broker() const (p. 339)
DEFAULT_BROKER (p. 357)
```

6.283.3.9 const std::pair<std::string, std::string>& Arc::UserConfig::Broker () const [inline]

Get the broker and corresponding arguments.

The returned pair contains the broker name as the first component and the argument as the second.

See also

```
Broker(const std::string&) (p. 338)
Broker(const std::string&, const std::string&) (p. 338)
DEFAULT_BROKER (p. 357)
```

6.283.3.10 bool Arc::UserConfig::CACertificatePath (const std::string & newCACertificatePath) [inline]

Set CA-certificate path.

The path to the file containing CA-certificate will be set when calling this method. This configuration parameter is deprecated - use CACertificatesDirectory instead. Only arcslcs uses it.

The attribute associated with this setter method is 'cacertificatepath'.

Parameters

newCACertificatePath is the path to the CA-certificate.

Returns

This method always returns true.

See also

```
CACertificatePath() const (p. 339)
```

6.283.3.11 const std::string& Arc::UserConfig::CACertificatePath() const [inline]

Get path to CA-certificate.

Retrieve the path to the file containing CA-certificate. This configuration parameter is deprecated.

The path to the CA-certificate is returned.

See also

CACertificatePath(const std::string&) (p. 339)

6.283.3.12 bool Arc::UserConfig::CACertificatesDirectory (const std::string & newCACertificatesDirectory) [inline]

Set path to CA-certificate directory.

The path to the directory containing CA-certificates will be set when calling this method. Note that the **InitializeCredentials()** (p. 345) method will also try to set this path, by searching in different locations.

The attribute associated with this setter method is 'cacertificatesdirectory'.

Parameters

newCACertificatesDirectory is the path to the CA-certificate directory.

Returns

This method always returns true.

See also

```
InitializeCredentials() (p. 345)
CredentialsFound() const (p. 343)
CACertificatesDirectory() const (p. 340)
```

6.283.3.13 const std::string& Arc::UserConfig::CACertificatesDirectory() const [inline]

Get path to CA-certificate directory.

Retrieve the path to the CA-certificate directory.

Returns

The path to the CA-certificate directory is returned.

See also

```
InitializeCredentials() (p. 345)
CredentialsFound() const (p. 343)
CACertificatesDirectory(const std::string&) (p. 340)
```

6.283.3.14 bool Arc::UserConfig::CertificateLifeTime (const Period & newCertificateLifeTime) [inline]

Set certificate life time.

Sets lifetime of user certificate which will be obtained from Short Lived Credentials Service (p. 282).

The attribute associated with this setter method is 'certificatelifetime'.

Parameters

newCertificateLifeTime is the life time of a certificate, as a Period (p. 242) object.

Returns

This method always returns true.

See also

CertificateLifeTime() const (p. 341)

6.283.3.15 const Period& Arc::UserConfig::CertificateLifeTime() const [inline]

Get certificate life time.

Gets lifetime of user certificate which will be obtained from Short Lived Credentials Service (p. 282).

Returns

The certificate life time is returned as a **Period** (p. 242) object.

See also

CertificateLifeTime(const Period&) (p. 340)

6.283.3.16 bool Arc::UserConfig::CertificatePath (const std::string & newCertificatePath) [inline]

Set path to certificate.

The path to user certificate will be set by this method. The path to the correcsponding key can be set with the **KeyPath(const std::string&)** (p. 347) method. Note that the **InitializeCredentials()** (p. 345) method will also try to set this path, by searching in different locations.

The attribute associated with this setter method is 'certificatepath'.

Parameters

newCertificatePath is the path to the new certificate.

Returns

This method always returns true.

See also

InitializeCredentials() (p. 345) CredentialsFound() const (p. 343) CertificatePath() const (p. 342) KeyPath(const std::string&) (p. 347)

6.283.3.17 const std::string& Arc::UserConfig::CertificatePath() const [inline]

Get path to certificate.

The path to the cerficate is returned when invoking this method.

Returns

The certificate path is returned.

See also

```
InitializeCredentials() (p. 345)
CredentialsFound() const (p. 343)
CertificatePath(const std::string&) (p. 341)
KeyPath() const (p. 348)
```

6.283.3.18 void Arc::UserConfig::ClearRejectedServices (ServiceType st)

Clear rejected services with specified ServiceType.

Calling this method will cause the internally stored rejected services with the ServiceType st to be cleared.

See also

```
ClearRejectedServices() (p. 342)
ClearSelectedServices(ServiceType) (p. 343)
AddServices(const std::list<std::string>&, ServiceType) (p. 336)
AddServices(const std::list<std::string>&, const std::list<std::string>&, ServiceType) (p. 336)
GetRejectedServices() (p. 343)
```

6.283.3.19 void Arc::UserConfig::ClearRejectedServices ()

Clear selected services.

Calling this method will cause the internally stored rejected services to be cleared.

See also

```
ClearRejectedServices(ServiceType) (p. 342)
ClearSelectedServices() (p. 342)
AddServices(const std::list<std::string>&, ServiceType) (p. 336)
AddServices(const std::list<std::string>&, const std::list<std::string>&, ServiceType) (p. 336)
GetRejectedServices() (p. 343)
```

6.283.3.20 void Arc::UserConfig::ClearSelectedServices ()

Clear selected services.

Calling this method will cause the internally stored selected services to be cleared.

See also

ClearSelectedServices(ServiceType) (p. 343)

```
ClearRejectedServices() (p. 342)
AddServices(const std::list<std::string>&, ServiceType) (p. 336)
AddServices(const std::list<std::string>&, const std::list<std::string>&, ServiceType) (p. 336)
GetSelectedServices() (p. 344)
```

6.283.3.21 void Arc::UserConfig::ClearSelectedServices (ServiceType st)

Clear selected services with specified ServiceType.

Calling this method will cause the internally stored selected services with the ServiceType st to be cleared.

See also

```
ClearSelectedServices() (p. 342)
ClearRejectedServices(ServiceType) (p. 342)
AddServices(const std::list<std::string>&, ServiceType) (p. 336)
AddServices(const std::list<std::string>&, const std::list<std::string>&, ServiceType) (p. 336)
GetSelectedServices() (p. 344)
```

6.283.3.22 bool Arc::UserConfig::CredentialsFound() const [inline]

Validate credential location.

Valid credentials consists of a combination of a path to existing CA-certificate directory and either a path to existing proxy or a path to existing user key/certificate pair. If valid credentials are found this method returns true, otherwise false is returned.

Returns

true if valid credentials are found, otherwise false.

See also

InitializeCredentials() (p. 345)

6.283.3.23 const URLListMap& Arc::UserConfig::GetRejectedServices (ServiceType st) const

Get rejected services.

Get the rejected services with the ServiceType specified by st.

Parameters

st specifies which ServiceType should be returned by the method.

Returns

The rejected services is returned.

See also

```
AddServices(const std::list<std::string>&, ServiceType) (p. 336)
AddServices(const std::list<std::string>&, const std::list<std::string>&, ServiceType) (p. 336)
GetSelectedServices(ServiceType)
ClearRejectedServices() (p. 342)
```

6.283.3.24 const URLListMap& Arc::UserConfig::GetSelectedServices (ServiceType st) const

Get selected services.

Get the selected services with the ServiceType specified by st.

Parameters

st specifies which ServiceType should be returned by the method.

Returns

The selected services is returned.

See also

```
AddServices(const std::list<std::string>&, ServiceType) (p. 336)
AddServices(const std::list<std::string>&, const std::list<std::string>&, ServiceType) (p. 336)
GetRejectedServices(ServiceType) const (p. 343)
ClearSelectedServices() (p. 342)
```

6.283.3.25 bool Arc::UserConfig::IdPName (const std::string & name) [inline]

Set IdP name.

Sets Identity Provider name (Shibboleth) to which user belongs. It is used for contacting Short Lived Certificate **Service** (p. 282).

The attribute associated with this setter method is 'idpname'.

Parameters

name is the new IdP name.

Returns

This method always returns true.

See also

6.283.3.26 const std::string& Arc::UserConfig::IdPName() const [inline]

Get IdP name.

Gets Identity Provider name (Shibboleth) to which user belongs.

Returns

The IdP name

See also

IdPName(const std::string&) (p. 344)

6.283.3.27 void Arc::UserConfig::InitializeCredentials ()

Initialize user credentials.

The location of the user credentials will be tried located when calling this method and stored internally when found. The method searches in different locations. First the user proxy or the user key/certificate pair is tried located in the following order:

- Proxy path specified by the environment variable X509_USER_PROXY
- Key/certificate path specified by the environment X509_USER_KEY and X509_USER_CERT
- Proxy path specified in either configuration file passed to the contructor or explicitly set using the setter method **ProxyPath(const std::string&)** (p. 352)
- Key/certificate path specified in either configuration file passed to the constructor or explicitly set using the setter methods **KeyPath(const std::string&)** (p. 347) and **CertificatePath(const std::string&)** (p. 341)
- ProxyPath with file name x509up_u concatenated with the user ID located in the OS temporary directory.

If the proxy or key/certificate pair have been explicitly specified only the specified path(s) will be tried, and if not found a ERROR is reported. If the proxy or key/certificate have not been specified and it is not located in the temporary directory a WARNING will be reported and the host key/certificate pair is tried and then the Globus key/certificate pair and a ERROR will be reported if not found in any of these locations.

Together with the proxy and key/certificate pair, the path to the directory containing CA certificates is also tried located when invoking this method. The directory will be tried located in the following order:

- Path specified by the X509_CERT_DIR environment variable.
- Path explicitly specified either in a parsed configuration file using the cacertficatecirectory or by using the setter method **CACertificatesDirectory()** (p. 340).
- Path created by concatenating the output of User::Home() with '.globus' and 'certificates' separated by the directory delimeter.
- Path created by concatenating the output of Glib::get_home_dir() with '.globus' and 'certificates' separated by the directory delimeter.
- Path created by concatenating the output of **ArcLocation::Get()** (p. 51), with 'etc' and 'certificates' separated by the directory delimeter.
- Path created by concatenating the output of **ArcLocation::Get()** (p. 51), with 'etc', 'grid-security' and 'certificates' separated by the directory delimeter.
- Path created by concatenating the output of **ArcLocation::Get()** (p. 51), with 'share' and 'certificates' separated by the directory delimeter.
- Path created by concatenating 'etc', 'grid-security' and 'certificates' separated by the directory delimeter.

If the CA certificate directory have explicitly been specified and the directory does not exist a ERROR is reported. If none of the directories above does not exist a ERROR is reported.

See also

CredentialsFound() (p. 343) ProxyPath(const std::string&) (p. 352) KeyPath(const std::string&) (p. 347) CertificatePath(const std::string&) (p. 341)

CACertificatesDirectory(const std::string&) (p. 340)

6.283.3.28 bool Arc::UserConfig::JobListFile (const std::string & path)

Set path to job list file.

The method takes a path to a file which will be used as the job list file for storing and reading job information. If the specified path *path* does not exist a empty job list file will be tried created. If creating the job list file in any way fails *false* will be returned and a ERROR message will be reported. Otherwise *true* is returned. If the directory containing the file does not exist, it will be tried created. The method will also return *false* if the file is not a regular file.

The attribute associated with this setter method is 'joblist'.

Parameters

path the path to the job list file.

Returns

If the job list file is a regular file or if it can be created *true* is returned, otherwise *false* is returned.

See also

```
JobListFile() const (p. 346)
```

6.283.3.29 const std::string& Arc::UserConfig::JobListFile() const [inline]

Get a reference to the path of the job list file.

The job list file is used to store and fetch information about submitted computing jobs to computing services. This method will return the path to the specified job list file.

Returns

The path to the job list file is returned.

See also

```
JobListFile(const std::string&) (p. 346)
```

6.283.3.30 bool Arc::UserConfig::KeyPassword (const std::string & newKeyPassword) [inline]

Set password for generated key.

Set password to be used to encode private key of credentials obtained from Short Lived Credentials **Service** (p. 282).

The attribute associated with this setter method is 'keypassword'.

Parameters

newKeyPassword is the new password to the key.

Returns

This method always returns true.

See also

```
KeyPassword() const (p. 347)
KeyPath(const std::string&) (p. 347)
KeySize(int) (p. 348)
```

6.283.3.31 const std::string& Arc::UserConfig::KeyPassword() const [inline]

Get password for generated key.

Get password to be used to encode private key of credentials obtained from Short Lived Credentials **Service** (p. 282).

Returns

The key password is returned.

See also

```
KeyPassword(const std::string&) (p. 346)
KeyPath() const (p. 348)
KeySize() const (p. 348)
```

6.283.3.32 bool Arc::UserConfig::KeyPath (const std::string & newKeyPath) [inline]

Set path to key.

The path to user key will be set by this method. The path to the corresponding certificate can be set with the **CertificatePath(const std::string&)** (p. 341) method. Note that the **InitializeCredentials()** (p. 345) method will also try to set this path, by searching in different locations.

The attribute associated with this setter method is 'keypath'.

Parameters

newKeyPath is the path to the new key.

Returns

This method always returns true.

See also

```
InitializeCredentials() (p. 345)
CredentialsFound() const (p. 343)
KeyPath() const (p. 348)
CertificatePath(const std::string&) (p. 341)
KeyPassword(const std::string&) (p. 346)
KeySize(int) (p. 348)
```

6.283.3.33 const std::string& Arc::UserConfig::KeyPath() const [inline]

Get path to key.

The path to the key is returned when invoking this method.

Returns

The path to the user key is returned.

See also

InitializeCredentials() (p. 345) CredentialsFound() const (p. 343) KeyPath(const std::string&) (p. 347) CertificatePath() const (p. 342) KeyPassword() const (p. 347) KeySize() const (p. 348)

6.283.3.34 int Arc::UserConfig::KeySize() const [inline]

Get key size.

Get size/strengt of private key of credentials obtained from Short Lived Credentials Service (p. 282).

Returns

The key size, as an integer, is returned.

See also

```
KeySize(int) (p. 348)
KeyPath() const (p. 348)
KeyPassword() const (p. 347)
```

6.283.3.35 bool Arc::UserConfig::KeySize (int newKeySize) [inline]

Set key size.

Set size/strengt of private key of credentials obtained from Short Lived Credentials Service (p. 282).

The attribute associated with this setter method is 'keysize'.

Parameters

newKeySize is the size, an an integer, of the key.

Returns

This method always returns true.

See also

```
KeySize() const (p. 348)
KeyPath(const std::string&) (p. 347)
KeyPassword(const std::string&) (p. 346)
```

6.283.3.36 bool Arc::UserConfig::LoadConfigurationFile (const std::string & conffile, bool ignoreJobListFile = true)

Load specified configuration file.

The configuration file passed is parsed by this method by using the **IniConfig** (p. 177) class. If the parsing is unsuccessful a WARNING is reported.

The format of the configuration file should follow that of INI, and every attribute present in the file is only allowed once, if otherwise a WARNING will be reported. The file can contain at most two sections, one named common and the other name alias. If other sections exist a WARNING will be reported. Only the following attributes is allowed in the common section of the configuration file:

- certificatepath (CertificatePath(const std::string&) (p. 341))
- keypath (KeyPath(const std::string&) (p. 347))
- proxypath (**ProxyPath(const std::string&)** (p. 352))
- cacertificatesdirectory (CACertificatesDirectory(const std::string&) (p. 340))
- cacertificatepath (CACertificatePath(const std::string&) (p. 339))
- timeout (**Timeout(int)** (p. 354))
- joblist (JobListFile(const std::string&) (p. 346))
- defaultservices (AddServices(const std::list<std::string>&, const std::list<std::string>&, ServiceType) (p. 336))
- rejectservices (AddServices(const std::list<std::string>&, const std::list<std::string>&, ServiceType) (p. 336))
- verbosity (Verbosity(const std::string&) (p. 356))
- brokername (**Broker(const std::string&)** (p. 338) or **Broker(const std::string&, const std::string&)** (p. 338))
- brokerarguments (**Broker(const std::string&)** (p. 338) or **Broker(const std::string&, const std::string&)** (p. 338))
- bartender (Bartender(const std::list<URL>&))
- vomsserverpath (VOMSServerPath(const std::string&) (p. 356))
- username (UserName(const std::string&) (p. 355))
- password (Password(const std::string&) (p. 351))
- keypassword (**KeyPassword(const std::string&)** (p. 346))
- keysize (**KeySize(int**) (p. 348))
- certificatelifetime (CertificateLifeTime(const Period&) (p. 340))
- slcs (**SLCS(const URL&)** (p. 353))
- storedirectory (**StoreDirectory(const std::string&)** (p. 353))
- idpname (**IdPName(const std::string&)** (p. 344))

where the method in parentheses is the associated setter method. If other attributes exist in the common section a WARNING will be reported for each of these attributes. In the alias section aliases can be defined, and should represent a selection of services. The alias can then refered to by input to the **AddServices(const std::list<std::string>&, ServiceType)** (p. 336) and **AddServices(const std::list<std::string>&, ServiceType)** (p. 336) methods. An alias can not contain any of the characters '.', '' or '\t' and should be defined as follows:

```
< alias\_name > = < service\_type > : < flavour > : < service\_url > | < alias\_ref > [...]
```

where <alias_name> is the name of the defined alias, <service_type> is the service type in lower case, <flavour> is the type of middleware plugin to use, <service_url> is the URL (p. 320) which should be used to contact the service and <alias_ref> is another defined alias. The parsed aliases will be stored internally and resolved when needed. If a alias already exist, and another alias with the same name is parsed then this other alias will overwrite the existing alias.

Parameters

conffile is the path to the configuration file.

ignoreJobListFile is a optional boolean which indicates whether the joblistfile attribute in the configuration file should be ignored. Default is to ignored it (true).

Returns

If loading the configuration file succeeds true is returned, otherwise false is returned.

See also

SaveToFile() (p. 352)

6.283.3.37 Arc::UserConfig::operator bool (void) const [inline]

Check for validity.

The validity of an object created from this class can be checked using this casting operator. An object is valid if the constructor did not encounter any errors.

See also

```
operator!() (p. 350)
```

6.283.3.38 bool Arc::UserConfig::operator! (void) const [inline]

Check for non-validity.

See **operator bool**() (p. 350) for a description.

See also

```
operator bool() (p. 350)
```

6.283.3.39 const std::string& Arc::UserConfig::OverlayFile() const [inline]

Get path to configuration overlay file.

The overlay file path

See also

OverlayFile(const std::string&) (p. 351)

6.283.3.40 bool Arc::UserConfig::OverlayFile (const std::string & path) [inline]

Set path to configuration overlay file.

Content of specified file is a backdoor to configuration XML generated from information stored in this class. The content of file is passed to **BaseConfig** (p. 60) class in ApplyToConfig(BaseConfig&) then merged with internal configuration XML representation. This feature is meant for quick prototyping/testing/tuning of functionality without rewriting code. It is meant for developers and most users won't need it.

The attribute associated with this setter method is 'overlayfile'.

Parameters

path is the new overlay file path.

Returns

This method always returns true.

See also

6.283.3.41 bool Arc::UserConfig::Password (const std::string & newPassword) [inline]

Set password.

Set password which is used for requesting credentials from Short Lived Credentials Service (p. 282).

The attribute associated with this setter method is 'password'.

Parameters

newPassword is the new password to set.

Returns

This method always returns true.

See also

Password() const (p. 351)

6.283.3.42 const std::string& Arc::UserConfig::Password() const [inline]

Get password.

Get password which is used for requesting credentials from Short Lived Credentials Service (p. 282).

The password is returned.

See also

Password(const std::string&) (p. 351)

6.283.3.43 bool Arc::UserConfig::ProxyPath (const std::string & newProxyPath) [inline]

Set path to user proxy.

This method will set the path of the user proxy. Note that the **InitializeCredentials()** (p. 345) method will also try to set this path, by searching in different locations.

The attribute associated with this setter method is 'proxypath'

Parameters

newProxyPath is the path to a user proxy.

Returns

This method always returns true.

See also

```
InitializeCredentials() (p. 345)
CredentialsFound() (p. 343)
ProxyPath() const (p. 352)
```

6.283.3.44 const std::string& Arc::UserConfig::ProxyPath() const [inline]

Get path to user proxy.

Retrieve path to user proxy.

Returns

Returns the path to the user proxy.

See also

ProxyPath(const std::string&) (p. 352)

6.283.3.45 bool Arc::UserConfig::SaveToFile (const std::string & filename) const

Save to INI file.

This method will save the object data as a INI file. The saved file can be loaded with the LoadConfigurationFile method.

Parameters

filename the name of the file which the data will be saved to.

false if unable to get handle on file, otherwise true is returned.

See also

LoadConfigurationFile() (p. 349)

6.283.3.46 bool Arc::UserConfig::SLCS (const URL & newSLCS) [inline]

Set the URL (p. 320) to the Short Lived Certificate Service (p. 282) (SLCS).

The attribute associated with this setter method is 'slcs'.

Parameters

newSLCS is the URL (p. 320) to the SLCS

Returns

This method always returns true.

See also

SLCS() const (p. 353)

6.283.3.47 const URL& Arc::UserConfig::SLCS() const [inline]

Get the URL (p. 320) to the Short Lived Certificate Service (p. 282) (SLCS).

Returns

The SLCS is returned.

See also

SLCS(const URL&) (p. 353)

6.283.3.48 bool Arc::UserConfig::StoreDirectory (const std::string & newStoreDirectory) [inline]

Set store directory.

Sets directory which will be used to store credentials obtained from Short Lived Credential (p. 90) Servide.

The attribute associated with this setter method is 'storedirectory'.

Parameters

newStoreDirectory is the path to the store directory.

Returns

This method always returns true.

See also

6.283.3.49 const std::string& Arc::UserConfig::StoreDirectory() const [inline]

Get store diretory.

Sets directory which is used to store credentials obtained from Short Lived Credential (p. 90) Servide.

Returns

The path to the store directory is returned.

See also

StoreDirectory(const std::string&) (p. 353)

6.283.3.50 int Arc::UserConfig::Timeout() const [inline]

Get timeout.

Returns the timeout in seconds.

Returns

timeout in seconds.

See also

```
Timeout(int) (p. 354)
DEFAULT_TIMEOUT (p. 357)
```

6.283.3.51 bool Arc::UserConfig::Timeout (int newTimeout)

Set timeout.

When communicating with a service the timeout specifies how long, in seconds, the communicating instance should wait for a response. If the response have not been recieved before this period in time, the connection is typically dropped, and an error will be reported.

This method will set the timeout to the specified integer. If the passed integer is less than or equal to 0 then false is returned and the timeout will not be set, otherwise true is returned and the timeout will be set to the new value.

The attribute associated with this setter method is 'timeout'.

Parameters

newTimeout the new timeout value in seconds.

Returns

false in case *newTimeout* <= 0, otherwise true.

See also

```
Timeout() const (p. 354)
DEFAULT_TIMEOUT (p. 357)
```

6.283.3.52 const std::string& Arc::UserConfig::UserName() const [inline]

Get user-name.

Get username which is used for requesting credentials from Short Lived Credentials Service (p. 282).

Returns

The username is returned.

See also

UserName(const std::string&) (p. 355)

6.283.3.53 bool Arc::UserConfig::UserName (const std::string & name) [inline]

Set user-name for SLCS.

Set username which is used for requesting credentials from Short Lived Credentials Service (p. 282).

The attribute associated with this setter method is 'username'.

Parameters

name is the name of the user.

Returns

This method always return true.

See also

UserName() const (p. 355)

6.283.3.54 const std::string& Arc::UserConfig::UtilsDirPath() const [inline]

Get path to directory storing utility files for DataPoints.

Returns

The utils dir path

See also

UtilsDirPath(const std::string&) (p. 355)

6.283.3.55 bool Arc::UserConfig::UtilsDirPath (const std::string & dir)

Set path to directory storing utility files for DataPoints.

Some DataPoints can store information on remote services in local files. This method sets the path to the directory containing these files. For example arc* tools set it to ARCUSERDIRECTORY and A-REX sets it to the control directory. The directory is created if it does not exist.

Parameters

path is the new utils dir path.

Returns

This method always returns true.

6.283.3.56 const std::string& Arc::UserConfig::Verbosity() const [inline]

Get the user selected level of verbosity.

The string representation of the verbosity level specified by the user is returned when calling this method. If the user have not specified the verbosity level the empty string will be referenced.

Returns

the verbosity level, or empty if it has not been set.

See also

Verbosity(const std::string&) (p. 356)

6.283.3.57 bool Arc::UserConfig::Verbosity (const std::string & newVerbosity)

Set verbosity.

The verbosity will be set when invoking this method. If the string passed cannot be parsed into a corresponding LogLevel, using the function a WARNING is reported and false is returned, otherwise true is returned.

The attribute associated with this setter method is 'verbosity'.

Returns

true in case the verbosity could be set to a allowed LogLevel, otherwise false.

See also

Verbosity() const (p. 356)

6.283.3.58 bool Arc::UserConfig::VOMSServerPath (const std::string & path) [inline]

Set path to file containing VOMS configuration.

Set path to file which contians list of VOMS services and associated configuration parameters needed to contact those services. It is used by arcproxy.

The attribute associated with this setter method is 'vomsserverpath'.

Parameters

path the path to VOMS configuration file

Returns

This method always return true.

See also

VOMSServerPath() const (p. 357)

6.283.3.59 const std::string& Arc::UserConfig::VOMSServerPath() const [inline]

Get path to file containing VOMS configuration.

Get path to file which contians list of VOMS services and associated configuration parameters.

Returns

The path to VOMS configuration file is returned.

See also

VOMSServerPath(const std::string&) (p. 356)

6.283.4 Field Documentation

6.283.4.1 const std::string Arc::UserConfig::ARCUSERDIRECTORY [static]

Path to ARC user home directory.

The ARCUSERDIRECTORY variable is the path to the ARC home directory of the current user. This path is created using the User::Home() method.

See also

User::Home()

6.283.4.2 const std::string Arc::UserConfig::DEFAULT_BROKER [static]

Default broker.

The *DEFAULT_BROKER* specifies the name of the broker which should be used in case no broker is explicitly chosen.

See also

```
Broker (p. 62)
```

Broker(const std::string&) (p. 338)

Broker(const std::string&, const std::string&) (p. 338)

Broker() const (p. 339)

6.283.4.3 const int Arc::UserConfig::DEFAULT_TIMEOUT = 20 [static]

Default timeout in seconds.

The *DEFAULT_TIMEOUT* specifies interval which will be used in case no timeout interval have been explicitly specified. For a description about timeout see **Timeout(int)** (p. 354).

See also

```
Timeout(int) (p. 354)
Timeout() const (p. 354)
```

6.283.4.4 const std::string Arc::UserConfig::DEFAULTCONFIG [static]

Path to default configuration file.

The *DEFAULTCONFIG* variable is the path to the default configuration file used in case no configuration file have been specified. The path is created from the ARCUSERDIRECTORY object.

6.283.4.5 const std::string Arc::UserConfig::EXAMPLECONFIG [static]

Path to example configuration.

The EXAMPLECONFIG variable is the path to the example configuration file.

6.283.4.6 const std::string Arc::UserConfig::SYSCONFIG [static]

Path to system configuration.

The SYSCONFIG variable is the path to the system configuration file. This variable is only equal to SYSCONFIGARCLOC if ARC is installed in the root (highly unlikely).

6.283.4.7 const std::string Arc::UserConfig::SYSCONFIGARCLOC [static]

Path to system configuration at ARC location.

The SYSCONFIGARCLOC variable is the path to the system configuration file which reside at the ARC installation location.

The documentation for this class was generated from the following file:

· UserConfig.h

6.284 Arc::UsernameToken Class Reference

Interface for manipulation of WS-Security according to Username Token Profile (p. 256).

#include <UsernameToken.h>

Public Types

• enum PasswordType

Public Member Functions

- UsernameToken (SOAPEnvelope &soap)
- **UsernameToken** (SOAPEnvelope &soap, const std::string &username, const std::string &password, const std::string &uid, **PasswordType** pwdtype)
- **UsernameToken** (SOAPEnvelope &soap, const std::string &username, const std::string &id, bool mac, int iteration)
- operator bool (void)
- std::string Username (void)
- bool **Authenticate** (const std::string &password, std::string &derived_key)
- bool **Authenticate** (std::istream &password, std::string &derived_key)

6.284.1 Detailed Description

Interface for manipulation of WS-Security according to Username Token **Profile** (p. 256).

6.284.2 Member Enumeration Documentation

6.284.2.1 enum Arc::UsernameToken::PasswordType

SOAP header element

6.284.3 Constructor & Destructor Documentation

6.284.3.1 Arc::UsernameToken::UsernameToken (SOAPEnvelope & soap)

Link to existing SOAP header and parse Username Token information. Username Token related information is extracted from SOAP header and stored in class variables.

6.284.3.2 Arc::UsernameToken::UsernameToken (SOAPEnvelope & soap, const std::string & username, const std::string & password, const std::string & uid, PasswordType pwdtype)

Add Username Token information into the SOAP header. Generated token contains elements Username and Password and is meant to be used for authentication.

Parameters

```
soap the SOAP message
username <wsse:Username>...</wsse:Username> - if empty it is entered interactively from stdin
password <wsse:Password Type="...">...</wsse:Password> - if empty it is entered interactively
from stdin
uid <wsse:UsernameToken (p. 358) wsu:ID="...">
pwdtype <wsse:Password Type="...">...</wsse:Password>
```

6.284.3.3 Arc::UsernameToken::UsernameToken (SOAPEnvelope & soap, const std::string & username, const std::string & id, bool mac, int iteration)

Add Username Token information into the SOAP header. Generated token contains elements Username and Salt and is meant to be used for deriving Key Derivation.

Parameters

```
soap the SOAP message
username <wsse:Username>...</wsse:Username>
mac if derived key is meant to be used for Message (p. 208) Authentication Code
iteration <wsse11:Iteration>...</wsse11:Iteration>
```

6.284.4 Member Function Documentation

6.284.4.1 bool Arc::UsernameToken::Authenticate (const std::string & password, std::string & derived_key)

Checks parsed/generated token against specified password. If token is meant to be used for deriving a key then key is returned in derived_key. In that case authentication is performed outside of **UsernameToken** (p. 358) class using obtained derived_key.

6.284.4.2 bool Arc::UsernameToken::Authenticate (std::istream & password, std::string & derived_key)

Checks parsed token against password stored in specified stream. If token is meant to be used for deriving a key then key is returned in derived_key

6.284.4.3 Arc::UsernameToken::operator bool (void)

Returns true of constructor succeeded

6.284.4.4 std::string Arc::UsernameToken::Username (void)

Returns username associated with this instance

The documentation for this class was generated from the following file:

• UsernameToken.h

6.285 Arc::UserSwitch Class Reference

#include <User.h>

6.285.1 Detailed Description

If this class is created user identity is switched to provided uid and gid. Due to internal lock there will be only one valid instance of this class. Any attempt to create another instance will block till first one is destroyed. If uid and gid are set to 0 then user identity is not switched. But lock is applied anyway. The lock has dual purpose. First and most important is to protect communication with underlying operating system which may depend on user identity. For that it is advisable for code which talks to operating system to acquire valid instance of this class. Care must be taken for not to hold that instance too long cause that may block other code in multithreaded envoronment. Other purpose of this lock is to provide workaround for glibc bug in __nptl_setxid. That bug causes lockup of seteuid() function if racing with fork. To avoid this problem the lock mentioned above is used by **Run** (p. 268) class while spawning new process.

The documentation for this class was generated from the following file:

• User.h

6.286 Arc::VOMSTrustList Class Reference

#include < VOMSUtil.h>

Public Member Functions

- **VOMSTrustList** (const std::vector< std::string > &encoded_list)
- VOMSTrustList (const std::vector< VOMSTrustChain > &chains, const std::vector< VOMSTrustRegex > ®exs)
- VOMSTrustChain & AddChain (const VOMSTrustChain &chain)
- VOMSTrustChain & AddChain (void)
- RegularExpression & AddRegex (const VOMSTrustRegex ®)

6.286.1 Detailed Description

Stores definitions for making decision if VOMS server is trusted

6.286.2 Constructor & Destructor Documentation

6.286.2.1 Arc::VOMSTrustList::VOMSTrustList (const std::vector< std::string > & encoded_list)

Creates chain lists and regexps from plain list. List is made of chunks delimited by elements containing

pattern "NEXT CHAIN". Each chunk with more than one element is converted into one instance of VOMSTrustChain. Chunks with single element are converted to VOMSTrustChain if element does not have special symbols. Otherwise it is treated as regular expression. Those symbols are '^\','\$' and '*'. Trusted chains can be congicured in two ways: one way is: <tls:VOMSCertTrustDNChain> <tls:VOMSCertTrustDN>/O=Grid/O=NorduGrid/CN=host/arthur.hep.lu.se</tls:VOMSCertTrustDN> <tls:VOMSCertTrustDN>/O=Grid/O=NorduGrid/CN=NorduGrid Certification Authority</tls:VOMSCertTrustDN> <tls:VOMSCertTrustDN>----NEXT CHAIN---</tls:VOMSCertTrustDN> <tls:VOMSCertTrustDN>/DC=ch/DC=cern/OU=computers/CN=voms.cern.ch</tls:VOMSCertTrustDN>/DC=ch/DC=cern/OU=computers/CN=voms.cern.ch</tl> <tls:VOMSCertTrustDN>/DC=ch/DC=cern/CN=CERN Trusted Certification </tl></tls:VOMSCertTrustDNChain> Authority</tls:VOMSCertTrustDN> the other way $<\!tls: VOMSCertTrustDNChain><\!tls: VOMSCertTrustDN>/O=Grid/O=NorduGrid/CN=host/arthur.hep.lu.se<\!/tls: VOMSCertTrustDN>/O=Grid/O=NorduGrid/CN=host/arthur.hep.lu.se<\!/tls: VOMSCertTrustDN>/O=Grid/O=NorduGrid/CN=host/arthur.hep.lu.se<\!/tls: VOMSCertTrustDN>/O=Grid/O=NorduGrid/CN=host/arthur.hep.lu.se<\!/tls: VOMSCertTrustDN>/O=Grid/O=NorduGrid/CN=host/arthur.hep.lu.se<\!/tls: VOMSCertTrustDN>/O=Grid/O=NorduGrid/CN=host/arthur.hep.lu.se<\!/tls: VOMSCertTrustDN>/O=Grid/O=NorduGrid/CN=host/arthur.hep.lu.se<\!/tls: VOMSCertTrustDN>/O=Grid/O=NorduGrid/CN=host/arthur.hep.lu.se<\!/tl>$ <tls:VOMSCertTrustDN>/O=Grid/O=NorduGrid/CN=NorduGrid Certification Authority</tls:VOMSCertTrustDN> </tls:VOMSCertTrustDNChain> <tls:VOMSCertTrustDNChain> <tls:VOMSCertTrustDN>/DC=ch/DC=cern/OU=computers/CN=voms.cern.ch</tls:VOMSCertTrustDN> <tls:VOMSCertTrustDN>/DC=ch/DC=cern/CN=CERN Authority</tls:VOMSCertTrustDN> </tls:VOMSCertTrustDNChain> each chunk is supposed to

6.286.2.2 Arc::VOMSTrustList::VOMSTrustList (const std::vector< VOMSTrustChain > & chains, const std::vector< VOMSTrustRegex > & regexs)

contain a suit of DN of trusted certificate chain, in which the first DN is the DN of the certificate (cert0) which is used to sign the Attribute Certificate (AC), the second DN is the DN of the issuer certificate(cert1) which is used to sign cert0. So if there are one or more intermediate issuers, then there should be 3 or more than 3 DNs in this chunk (considering cert0 and the root certificate, plus the intermediate certificate).

Creates chain lists and regexps from those specified in arguments. See **AddChain()** (p. 362) and **AddRegex()** (p. 362) for more information.

6.286.3 Member Function Documentation

6.286.3.1 VOMSTrustChain& Arc::VOMSTrustList::AddChain (const VOMSTrustChain & chain)

Adds chain of trusted DNs to list. During verification each signature of AC is checked against all stored chains. DNs of chain of certificate used for signing AC are compared against DNs stored in these chains one by one. If needed DN of issuer of last certificate is checked too. Comparison succeeds if DNs in at least one stored chain are same as those in certificate chain. Comparison stops when all DNs in stored chain are compared. If there are more DNs in stored chain than in certificate chain then comparison fails. Empty stored list matches any certificate chain. Taking into account that certificate chains are verified down to trusted CA anyway, having more than one DN in stored chain seems to be useless. But such feature may be found useful by some very strict sysadmins. ??? IMO,DN list here is not only for authentication, it is also kind of ACL, which means the AC consumer only trusts those DNs which issues AC.

6.286.3.2 VOMSTrustChain& Arc::VOMSTrustList::AddChain(void)

Adds empty chain of trusted DNs to list.

6.286.3.3 RegularExpression& Arc::VOMSTrustList::AddRegex (const VOMSTrustRegex & reg)

Adds regular expression to list. During verification each signature of AC is checked against all stored regular expressions. DN of signing certificate must match at least one of stored regular expressions.

The documentation for this class was generated from the following file:

• VOMSUtil.h

6.287 Arc::WSAEndpointReference Class Reference

Interface for manipulation of WS-Adressing Endpoint Reference.

#include <WSA.h>

Public Member Functions

- WSAEndpointReference (XMLNode epr)
- WSAEndpointReference (const WSAEndpointReference &wsa)
- WSAEndpointReference (const std::string &address)
- WSAEndpointReference (void)
- ~WSAEndpointReference (void)
- std::string Address (void) const
- void **Address** (const std::string &uri)
- WSAEndpointReference & operator= (const std::string &address)
- XMLNode ReferenceParameters (void)
- XMLNode MetaData (void)
- operator XMLNode (void)

6.287.1 Detailed Description

Interface for manipulation of WS-Adressing Endpoint Reference. It works on Endpoint Reference stored in XML tree. No information is stored in this object except reference to corresponding XML subtree.

6.287.2 Constructor & Destructor Documentation

6.287.2.1 Arc::WSAEndpointReference::WSAEndpointReference (XMLNode epr)

Link to top level EPR XML node Linking to existing EPR in XML tree

6.287.2.2 Arc::WSAEndpointReference::WSAEndpointReference (const WSAEndpointReference & wsa)

Copy constructor

6.287.2.3 Arc::WSAEndpointReference::WSAEndpointReference (const std::string & address)

Creating independent EPR - not implemented

6.287.2.4 Arc::WSAEndpointReference::WSAEndpointReference (void)

Dummy constructor - creates invalid instance

6.287.2.5 Arc::WSAEndpointReference::~WSAEndpointReference (void)

Destructor. All empty elements of EPR XML are destroyed here too

6.287.3 Member Function Documentation

6.287.3.1 std::string Arc::WSAEndpointReference::Address (void) const

Returns Address (URL (p. 320)) encoded in EPR

6.287.3.2 void Arc::WSAEndpointReference::Address (const std::string & uri)

Assigns new Address value. If EPR had no Address element it is created.

6.287.3.3 XMLNode Arc::WSAEndpointReference::MetaData (void)

Access to MetaData element of EPR. Obtained XML element should be manipulated directly in application-dependent way. If EPR had no MetaData element it is created.

6.287.3.4 Arc::WSAEndpointReference::operator XMLNode (void)

Returns reference to EPR top XML node

6.287.3.5 WSAEndpointReference& Arc::WSAEndpointReference::operator= (const std::string & address)

Same as Address(uri)

6.287.3.6 XMLNode Arc::WSAEndpointReference::ReferenceParameters (void)

Access to ReferenceParameters element of EPR. Obtained XML element should be manipulated directly in application-dependent way. If EPR had no ReferenceParameters element it is created.

The documentation for this class was generated from the following file:

• WSA.h

6.288 Arc::WSAHeader Class Reference

Interface for manipulation WS-Addressing information in SOAP header.

#include <WSA.h>

Public Member Functions

- WSAHeader (SOAPEnvelope &soap)
- WSAHeader (const std::string &action)
- std::string To (void) const
- void **To** (const std::string &uri)
- WSAEndpointReference From (void)
- WSAEndpointReference ReplyTo (void)
- WSAEndpointReference FaultTo (void)
- std::string Action (void) const
- void **Action** (const std::string &uri)
- std::string MessageID (void) const
- void MessageID (const std::string &uri)
- std::string RelatesTo (void) const
- void **RelatesTo** (const std::string &uri)
- std::string **RelationshipType** (void) const
- void **RelationshipType** (const std::string &uri)
- XMLNode ReferenceParameter (int n)
- XMLNode ReferenceParameter (const std::string &name)
- XMLNode NewReferenceParameter (const std::string &name)
- operator XMLNode (void)

Static Public Member Functions

• static bool Check (SOAPEnvelope &soap)

Protected Attributes

• bool header allocated

6.288.1 Detailed Description

Interface for manipulation WS-Addressing information in SOAP header. It works on Endpoint Reference stored in XML tree. No information is stored in this object except reference to corresponding XML subtree.

6.288.2 Constructor & Destructor Documentation

6.288.2.1 Arc::WSAHeader::WSAHeader (SOAPEnvelope & soap)

Linking to a header of existing SOAP message

6.288.2.2 Arc::WSAHeader::WSAHeader (const std::string & action)

Creating independent SOAP header - not implemented

6.288.3 Member Function Documentation

6.288.3.1 std::string Arc::WSAHeader::Action (void) const

Returns content of Action element of SOAP Header.

6.288.3.2 void Arc::WSAHeader::Action (const std::string & uri)

Set content of Action element of SOAP Header. If such element does not exist it's created.

6.288.3.3 static bool Arc::WSAHeader::Check (SOAPEnvelope & soap) [static]

Tells if specified SOAP message has WSA header

6.288.3.4 WSAEndpointReference Arc::WSAHeader::FaultTo (void)

Returns FaultTo element of SOAP Header. If such element does not exist it's created. Obtained element may be manipulted.

6.288.3.5 WSAEndpointReference Arc::WSAHeader::From (void)

Returns From element of SOAP Header. If such element does not exist it's created. Obtained element may be manipulted.

6.288.3.6 std::string Arc::WSAHeader::MessageID (void) const

Returns content of MessageID element of SOAP Header.

6.288.3.7 void Arc::WSAHeader::MessageID (const std::string & uri)

Set content of MessageID element of SOAP Header. If such element does not exist it's created.

6.288.3.8 XMLNode Arc::WSAHeader::NewReferenceParameter (const std::string & name)

Creates new ReferenceParameter element with specified name. Returns reference to created element.

6.288.3.9 Arc::WSAHeader::operator XMLNode (void)

Returns reference to SOAP Header - not implemented

6.288.3.10 XMLNode Arc::WSAHeader::ReferenceParameter (const std::string & name)

Returns first ReferenceParameter element with specified name

6.288.3.11 XMLNode Arc::WSAHeader::ReferenceParameter (int n)

Return n-th ReferenceParameter element

6.288.3.12 void Arc::WSAHeader::RelatesTo (const std::string & uri)

Set content of RelatesTo element of SOAP Header. If such element does not exist it's created.

6.288.3.13 std::string Arc::WSAHeader::RelatesTo (void) const

Returns content of RelatesTo element of SOAP Header.

6.288.3.14 void Arc::WSAHeader::RelationshipType (const std::string & uri)

Set content of RelationshipType element of SOAP Header. If such element does not exist it's created.

6.288.3.15 std::string Arc::WSAHeader::RelationshipType (void) const

Returns content of RelationshipType element of SOAP Header.

6.288.3.16 WSAEndpointReference Arc::WSAHeader::ReplyTo (void)

Returns ReplyTo element of SOAP Header. If such element does not exist it's created. Obtained element may be manipulted.

6.288.3.17 std::string Arc::WSAHeader::To (void) const

Returns content of To element of SOAP Header.

6.288.3.18 void Arc::WSAHeader::To (const std::string & uri)

Set content of To element of SOAP Header. If such element does not exist it's created.

6.288.4 Field Documentation

6.288.4.1 bool Arc::WSAHeader::header_allocated_ [protected]

SOAP header element

The documentation for this class was generated from the following file:


• WSA.h

6.289 Arc::WSRF Class Reference

Base class for every WSRF (p. 367) message.

#include <WSRF.h>

Inheritance diagram for Arc::WSRF:



Public Member Functions

- WSRF (SOAPEnvelope &soap, const std::string &action="")
- WSRF (bool fault=false, const std::string &action="")
- virtual SOAPEnvelope & SOAP (void)
- virtual operator bool (void)

Protected Member Functions

• void set_namespaces (void)

Protected Attributes

- bool allocated
- bool valid_

6.289.1 Detailed Description

Base class for every **WSRF** (p. 367) message. This class is not intended to be used directly. Use it like reference while passing through unknown **WSRF** (p. 367) message or use classes derived from it.

6.289.2 Constructor & Destructor Documentation

6.289.2.1 Arc::WSRF::WSRF (SOAPEnvelope & soap, const std::string & action = "")

Constructor - creates object out of supplied SOAP tree.

```
6.289.2.2 Arc::WSRF::WSRF ( bool fault = false, const std::string & action = "")
```

Constructor - creates new WSRF (p. 367) object

6.289.3 Member Function Documentation

6.289.3.1 virtual Arc::WSRF::operator bool (void) [inline, virtual]

Returns true if instance is valid

References valid_.

6.289.3.2 void Arc::WSRF::set_namespaces (void) [protected]

true if object represents valid **WSRF** (p. 367) message set WS Resource namespaces and default prefixes in SOAP message

Reimplemented in Arc::WSRP (p. 372), and Arc::WSRFBaseFault (p. 370).

6.289.3.3 virtual SOAPEnvelope& Arc::WSRF::SOAP(void) [inline, virtual]

Direct access to underlying SOAP element

6.289.4 Field Documentation

6.289.4.1 bool Arc::WSRF::allocated_ [protected]

Associated SOAP message - it's SOAP message after all

6.289.4.2 bool Arc::WSRF::valid_ [protected]

true if soap_ needs to be deleted in destructor

Referenced by operator bool().

The documentation for this class was generated from the following file:

• WSRF.h

6.290 Arc::WSRFBaseFault Class Reference

Base class for WSRF (p. 367) fault messages.

#include <WSRFBaseFault.h>

Inheritance diagram for Arc::WSRFBaseFault:



Public Member Functions

- WSRFBaseFault (SOAPEnvelope &soap)
- WSRFBaseFault (const std::string &type)

Protected Member Functions

• void set_namespaces (void)

6.290.1 Detailed Description

Base class for WSRF (p. 367) fault messages. Use classes inherited from it for specific faults.

6.290.2 Constructor & Destructor Documentation

6.290.2.1 Arc::WSRFBaseFault::WSRFBaseFault (SOAPEnvelope & soap)

Constructor - creates object out of supplied SOAP tree.

6.290.2.2 Arc::WSRFBaseFault::WSRFBaseFault (const std::string & type)

Constructor - creates new WSRF (p. 367) fault

6.290.3 Member Function Documentation

6.290.3.1 void Arc::WSRFBaseFault::set_namespaces (void) [protected]

set WS-ResourceProperties namespaces and default prefixes in SOAP message


Reimplemented from Arc::WSRF (p. 368).

The documentation for this class was generated from the following file:

· WSRFBaseFault.h

6.291 Arc::WSRFResourceUnavailableFault Class Reference

Inheritance diagram for Arc::WSRFResourceUnavailableFault:




The documentation for this class was generated from the following file:

• WSRFBaseFault.h

6.292 Arc::WSRFResourceUnknownFault Class Reference

Inheritance diagram for Arc::WSRFResourceUnknownFault:



The documentation for this class was generated from the following file:


· WSRFBaseFault.h

6.293 Arc::WSRP Class Reference

Base class for WS-ResourceProperties structures.

#include <WSResourceProperties.h>

Inheritance diagram for Arc::WSRP:



Public Member Functions

- WSRP (bool fault=false, const std::string &action="")
- WSRP (SOAPEnvelope &soap, const std::string &action="")

Protected Member Functions

• void set_namespaces (void)

6.293.1 Detailed Description

Base class for WS-ResourceProperties structures. Inheriting classes implement specific WS-ResourceProperties messages and their properties/elements. Refer to WS-ResourceProperties specifications for things specific to every message.

6.293.2 Constructor & Destructor Documentation

6.293.2.1 Arc::WSRP::WSRP (bool fault = false, const std::string & action = "")

Constructor - prepares object for creation of new WSRP (p. 370) request/response/fault

6.293.2.2 Arc::WSRP::WSRP (SOAPEnvelope & soap, const std::string & action = "")

Constructor - creates object out of supplied SOAP tree. It does not check if 'soap' represents valid WS-ResourceProperties structure. Actual check for validity of structure has to be done by derived class.

6.293.3 Member Function Documentation

6.293.3.1 void Arc::WSRP::set_namespaces (void) [protected]


set WS-ResourceProperties namespaces and default prefixes in SOAP message Reimplemented from **Arc::WSRF** (p. 368).

The documentation for this class was generated from the following file:

· WSResourceProperties.h

6.294 Arc::WSRPDeleteResourceProperties Class Reference

Inheritance diagram for Arc::WSRPDeleteResourceProperties:




The documentation for this class was generated from the following file:

• WSResourceProperties.h

6.295 Arc::WSRPDeleteResourcePropertiesRequest Class Reference


Inheritance diagram for Arc::WSRPDeleteResourcePropertiesRequest:



• WSResourceProperties.h

6.296 Arc::WSRPDeleteResourcePropertiesRequestFailedFault Class Reference

Inheritance diagram for Arc::WSRPDeleteResourcePropertiesRequestFailedFault:




The documentation for this class was generated from the following file:

• WSResourceProperties.h

6.297 Arc::WSRPDeleteResourcePropertiesResponse Class Reference

 $Inheritance\ diagram\ for\ Arc::WSRPDeleteResourcePropertiesResponse:$



• WSResourceProperties.h

6.298 Arc::WSRPFault Class Reference

Base class for WS-ResourceProperties faults.

#include <WSResourceProperties.h>

Inheritance diagram for Arc::WSRPFault:



Public Member Functions

- WSRPFault (SOAPEnvelope &soap)
- WSRPFault (const std::string &type)

6.298.1 Detailed Description

Base class for WS-ResourceProperties faults.

6.298.2 Constructor & Destructor Documentation

6.298.2.1 Arc::WSRPFault::WSRPFault (SOAPEnvelope & soap)

Constructor - creates object out of supplied SOAP tree.

6.298.2.2 Arc::WSRPFault::WSRPFault (const std::string & type)


Constructor - creates new WSRP (p. 370) fault

The documentation for this class was generated from the following file:

· WSResourceProperties.h

6.299 Arc::WSRPGetMultipleResourcePropertiesRequest Class Reference


Inheritance diagram for Arc::WSRPGetMultipleResourcePropertiesRequest:



• WSResourceProperties.h

6.300 Arc::WSRPGetMultipleResourcePropertiesResponse Class Reference

Inheritance diagram for Arc::WSRPGetMultipleResourcePropertiesResponse:




The documentation for this class was generated from the following file:

• WSResourceProperties.h

6.301 Arc::WSRPGetResourcePropertyDocumentRequest Class Reference

Inheritance diagram for Arc::WSRPGetResourcePropertyDocumentRequest:




The documentation for this class was generated from the following file:

• WSResourceProperties.h

6.302 Arc::WSRPGetResourcePropertyDocumentResponse Class Reference

Inheritance diagram for Arc::WSRPGetResourcePropertyDocumentResponse:




The documentation for this class was generated from the following file:

• WSResourceProperties.h

6.303 Arc::WSRPGetResourcePropertyRequest Class Reference

Inheritance diagram for Arc::WSRPGetResourcePropertyRequest:




The documentation for this class was generated from the following file:

• WSResourceProperties.h

6.304 Arc::WSRPGetResourcePropertyResponse Class Reference

Inheritance diagram for Arc::WSRPGetResourcePropertyResponse:




The documentation for this class was generated from the following file:

• WSResourceProperties.h

6.305 Arc::WSRPInsertResourceProperties Class Reference

Inheritance diagram for Arc::WSRPInsertResourceProperties:




The documentation for this class was generated from the following file:

• WSResourceProperties.h

6.306 Arc::WSRPInsertResourcePropertiesRequest Class Reference

Inheritance diagram for Arc::WSRPInsertResourcePropertiesRequest:




The documentation for this class was generated from the following file:

• WSResourceProperties.h

6.307 Arc::WSRPInsertResourcePropertiesRequestFailedFault Class Reference


Inheritance diagram for Arc::WSRPInsertResourcePropertiesRequestFailedFault:



• WSResourceProperties.h

6.308 Arc::WSRPInsertResourcePropertiesResponse Class Reference

Inheritance diagram for Arc::WSRPInsertResourcePropertiesResponse:




The documentation for this class was generated from the following file:

• WSResourceProperties.h

6.309 Arc::WSRPInvalidModificationFault Class Reference


Inheritance diagram for Arc::WSRPInvalidModificationFault:



• WSResourceProperties.h

6.310 Arc::WSRPInvalidResourcePropertyQNameFault Class Reference

Inheritance diagram for Arc::WSRPInvalidResourcePropertyQNameFault:




The documentation for this class was generated from the following file:

• WSResourceProperties.h

6.311 Arc::WSRPModifyResourceProperties Class Reference

Inheritance diagram for Arc::WSRPModifyResourceProperties:




The documentation for this class was generated from the following file:

• WSResourceProperties.h

6.312 Arc::WSRPPutResourcePropertyDocumentRequest Class Reference

Inheritance diagram for Arc::WSRPPutResourcePropertyDocumentRequest:




The documentation for this class was generated from the following file:

• WSResourceProperties.h

6.313 Arc::WSRPPutResourcePropertyDocumentResponse Class Reference

Inheritance diagram for Arc::WSRPPutResourcePropertyDocumentResponse:




The documentation for this class was generated from the following file:

• WSResourceProperties.h

6.314 Arc::WSRPQueryResourcePropertiesRequest Class Reference


Inheritance diagram for Arc::WSRPQueryResourcePropertiesRequest:



• WSResourceProperties.h

6.315 Arc::WSRPQueryResourcePropertiesResponse Class Reference

Inheritance diagram for Arc::WSRPQueryResourcePropertiesResponse:




The documentation for this class was generated from the following file:

• WSResourceProperties.h

6.316 Arc::WSRPResourcePropertyChangeFailure Class Reference

#include <WSResourceProperties.h>

Inheritance diagram for Arc::WSRPResourcePropertyChangeFailure:



Public Member Functions

- WSRPResourcePropertyChangeFailure (SOAPEnvelope &soap)
- WSRPResourcePropertyChangeFailure (const std::string &type)

6.316.1 Detailed Description

Base class for WS-ResourceProperties faults which contain ResourcePropertyChangeFailure

6.316.2 Constructor & Destructor Documentation

6.316.2.1 Arc::WSRPResourcePropertyChangeFailure::WSRPResourcePropertyChangeFailure (SOAPEnvelope & soap) [inline]

Constructor - creates object out of supplied SOAP tree.

6.316.2.2 Arc::WSRPResourcePropertyChangeFailure::WSRPResourcePropertyChangeFailure (const std::string & type) [inline]


Constructor - creates new WSRP (p. 370) fault

The documentation for this class was generated from the following file:

• WSResourceProperties.h

6.317 Arc::WSRPSetResourcePropertiesRequest Class Reference

Inheritance diagram for Arc::WSRPSetResourcePropertiesRequest:




The documentation for this class was generated from the following file:

• WSResourceProperties.h

6.318 Arc::WSRPSetResourcePropertiesResponse Class Reference


 $Inheritance\ diagram\ for\ Arc::WSRPSetResource Properties Response:$



• WSResourceProperties.h

6.319 Arc::WSRPSetResourcePropertyRequestFailedFault Class Reference

Inheritance diagram for Arc::WSRPSetResourcePropertyRequestFailedFault:




The documentation for this class was generated from the following file:

• WSResourceProperties.h

6.320 Arc::WSRPUnableToModifyResourcePropertyFault Class Reference

 $Inheritance\ diagram\ for\ Arc::WSRPU nable To Modify Resource Property Fault:$




The documentation for this class was generated from the following file:

• WSResourceProperties.h

6.321 Arc::WSRPUnableToPutResourcePropertyDocumentFault Class Reference

Inheritance diagram for Arc::WSRPUnableToPutResourcePropertyDocumentFault:




The documentation for this class was generated from the following file:

• WSResourceProperties.h

6.322 Arc::WSRPUpdateResourceProperties Class Reference

Inheritance diagram for Arc::WSRPUpdateResourceProperties:




The documentation for this class was generated from the following file:

• WSResourceProperties.h

6.323 Arc::WSRPUpdateResourcePropertiesRequest Class Reference


Inheritance diagram for Arc::WSRPUpdateResourcePropertiesRequest:



• WSResourceProperties.h

6.324 Arc::WSRPUpdateResourcePropertiesRequestFailedFault Class Reference

Inheritance diagram for Arc::WSRPUpdateResourcePropertiesRequestFailedFault:




The documentation for this class was generated from the following file:

• WSResourceProperties.h

6.325 Arc::WSRPUpdateResourcePropertiesResponse Class Reference


 $Inheritance\ diagram\ for\ Arc::WSRPUpdateResourcePropertiesResponse:$



• WSResourceProperties.h

6.326 ArcSec::X500NameAttribute Class Reference

Inheritance diagram for ArcSec::X500NameAttribute:



Public Member Functions

- virtual bool equal (AttributeValue *other, bool check_id=true)
- virtual std::string **encode** ()
- virtual std::string **getType** ()
- virtual std::string getId ()

6.326.1 Member Function Documentation

6.326.1.1 virtual std::string ArcSec::X500NameAttribute::encode() [inline, virtual]

encode the value in a string format

Implements ArcSec::AttributeValue (p. 57).

6.326.1.2 virtual bool ArcSec::X500NameAttribute::equal (AttributeValue * value, bool check_id = true) [virtual]

Evluate whether "this" equale to the parameter value

Implements ArcSec::AttributeValue (p. 58).

6.326.1.3 virtual std::string ArcSec::X500NameAttribute::getId() [inline, virtual]

Get the AttributeId of the <Attribute>

Implements ArcSec::AttributeValue (p. 58).

6.326.1.4 virtual std::string ArcSec::X500NameAttribute::getType() [inline, virtual]

Get the DataType of the <Attribute>

Implements ArcSec::AttributeValue (p. 58).

The documentation for this class was generated from the following file:

• X500NameAttribute.h

6.327 Arc::X509Token Class Reference

Class for manipulating X.509 Token **Profile** (p. 256).

#include <X509Token.h>

Public Types

• enum X509TokenType

Public Member Functions

- X509Token (SOAPEnvelope &soap, const std::string &keyfile="")
- **X509Token** (SOAPEnvelope &soap, const std::string &certfile, const std::string &keyfile, **X509TokenType** token_type=Signature)
- ~**X509Token** (void)
- operator bool (void)
- bool Authenticate (const std::string &cafile, const std::string &capath)
- bool Authenticate (void)

6.327.1 Detailed Description

Class for manipulating X.509 Token **Profile** (p. 256). This class is for generating/consuming X.509 Token profile. Currently it is used by x509token handler (src/hed/pdc/x509tokensh/) It is not necessary to directly called this class. If we need to use X.509 Token functionality, we only need to configure the x509token handler into service and client.

6.327.2 Member Enumeration Documentation

6.327.2.1 enum Arc::X509Token::X509TokenType

X509TokeType is for distinguishing two types of operation. It is used as the parameter of constuctor.

6.327.3 Constructor & Destructor Documentation

6.327.3.1 Arc::X509Token::X509Token (SOAPEnvelope & soap, const std::string & keyfile = ""

Constructor.Parse X509 Token information from SOAP header. X509 Token related information is extracted from SOAP header and stored in class variables. And then it the **X509Token** (p. 387) object will be used for authentication if the tokentype is Signature; otherwise if the tokentype is Encryption, the encrypted soap body will be decrypted and replaced by decrypted message. keyfile is only needed when the **X509Token** (p. 387) is encryption token

6.327.3.2 Arc::X509Token::X509Token (SOAPEnvelope & soap, const std::string & certfile, const std::string & keyfile, X509TokenType token type = Signature)

Constructor. Add X509 Token information into the SOAP header. Generated token contains elements X509 token and signature, and is meant to be used for authentication on the consuming side.

Parameters

soap The SOAP message to which the X509 Token will be inserted
certfile The certificate file which will be used to encrypt the SOAP body (if parameter tokentype is Encryption), or be used as <wse:BinarySecurityToken/> (if parameter tokentype is Signature).
keyfile The key file which will be used to create signature. Not needed when create encryption.

tokentype Token type: Signature or Encryption.

6.327.3.3 Arc::X509Token::~X509Token (void)

Deconstructor. Nothing to be done except finalizing the xmlsec library.

6.327.4 Member Function Documentation

6.327.4.1 bool Arc::X509Token::Authenticate (const std::string & cafile, const std::string & capath)

Check signature by using the certificare information in **X509Token** (p. 387) which is parsed by the constructor, and the trusted certificates specified as one of the two parameters. Not only the signature (in the **X509Token** (p. 387)) itself is checked, but also the certificate which is supposed to check the signature needs to be trusted (which means the certificate is issued by the ca certificate from CA file or CA directory). At least one the two parameters should be set.

Parameters

```
cafile The CA filecapath The CA directory
```

Returns

true if authentication passes; otherwise false

6.327.4.2 bool Arc::X509Token::Authenticate (void)

Check signature by using the cert information in soap message. Only the signature itself is checked, and it is not guranteed that the certificate which is supposed to check the signature is trusted.

6.327.4.3 Arc::X509Token::operator bool (void)

Returns true of constructor succeeded

The documentation for this class was generated from the following file:

• X509Token.h

6.328 Arc::XmlContainer Class Reference

The documentation for this class was generated from the following file:

• XmlContainer.h

6.329 Arc::XmlDatabase Class Reference

The documentation for this class was generated from the following file:

· XmlDatabase.h

6.330 Arc::XMLNode Class Reference

Wrapper for LibXML library Tree interface.

#include <XMLNode.h>

Inheritance diagram for Arc::XMLNode:



Public Member Functions

- XMLNode (void)
- XMLNode (const XMLNode &node)
- XMLNode (const std::string &xml)
- **XMLNode** (const char *xml, int len=-1)
- XMLNode (long ptr_addr)
- XMLNode (const NS &ns, const char *name)
- ∼XMLNode (void)
- void New (XMLNode &node) const
- void Exchange (XMLNode &node)
- void Move (XMLNode &node)
- void Swap (XMLNode &node)
- operator bool (void) const
- bool operator! (void) const
- bool operator== (const XMLNode &node)
- bool **operator!=** (const **XMLNode** &node)
- bool **Same** (const **XMLNode** &node)
- bool **operator**== (bool val)
- bool **operator!=** (bool val)
- bool **operator==** (const std::string &str)
- bool **operator!=** (const std::string &str)
- bool **operator==** (const char *str)
- bool **operator!=** (const char *str)
- **XMLNode Child** (int n=0)
- XMLNode operator[] (const char *name) const
- XMLNode operator[] (const std::string &name) const
- XMLNode operator[] (int n) const
- void **operator++** (void)
- void operator-- (void)

- int **Size** (void) const
- XMLNode Get (const std::string &name) const
- std::string Name (void) const
- std::string **Prefix** (void) const
- std::string FullName (void) const
- std::string Namespace (void) const
- void Name (const char *name)
- void Name (const std::string &name)
- void GetXML (std::string &out_xml_str, bool user_friendly=false) const
- void **GetXML** (std::string &out_xml_str, const std::string &encoding, bool user_friendly=false)
- void **GetDoc** (std::string &out_xml_str, bool user_friendly=false) const
- operator std::string (void) const
- XMLNode & operator= (const char *content)
- XMLNode & operator= (const std::string &content)
- void **Set** (const std::string &content)
- XMLNode & operator= (const XMLNode &node)
- XMLNode Attribute (int n=0)
- XMLNode Attribute (const char *name)
- XMLNode Attribute (const std::string &name)
- XMLNode NewAttribute (const char *name)
- XMLNode NewAttribute (const std::string &name)
- int AttributesSize (void) const
- void Namespaces (const NS &namespaces, bool keep=false, int recursion=-1)
- NS Namespaces (void)
- std::string NamespacePrefix (const char *urn)
- XMLNode NewChild (const char *name, int n=-1, bool global_order=false)
- XMLNode NewChild (const std::string &name, int n=-1, bool global_order=false)
- XMLNode NewChild (const char *name, const NS &namespaces, int n=-1, bool global_-order=false)
- XMLNode NewChild (const std::string &name, const NS &namespaces, int n=-1, bool global_order=false)
- XMLNode NewChild (const XMLNode &node, int n=-1, bool global_order=false)
- void **Replace** (const **XMLNode** &node)
- void **Destroy** (void)
- XMLNodeList **Path** (const std::string &path)
- XMLNodeList XPathLookup (const std::string &xpathExpr, const NS &nsList)
- XMLNode GetRoot (void)
- XMLNode Parent (void)
- bool **SaveToFile** (const std::string &file_name) const
- bool **SaveToStream** (std::ostream &out) const
- bool **ReadFromFile** (const std::string &file name)
- bool **ReadFromStream** (std::istream &in)
- bool **Validate** (const std::string &schema_file, std::string &err_msg)

Protected Member Functions

• XMLNode (xmlNodePtr node)

Protected Attributes

- bool is_owner_
- bool is_temporary_

Friends

- bool MatchXMLName (const XMLNode &node1, const XMLNode &node2)
- bool MatchXMLName (const XMLNode &node, const char *name)
- bool MatchXMLName (const XMLNode &node, const std::string &name)
- bool MatchXMLNamespace (const XMLNode &node1, const XMLNode &node2)
- bool MatchXMLNamespace (const XMLNode &node, const char *uri)
- bool MatchXMLNamespace (const XMLNode &node, const std::string &uri)

6.330.1 Detailed Description

Wrapper for LibXML library Tree interface. This class wraps XML Node, Document and Property/Attribute structures. Each instance serves as pointer to actual LibXML element and provides convenient (for chosen purpose) methods for manipulating it. This class has no special ties to LibXML library and may be easily rewritten for any XML parser which provides interface similar to LibXML Tree. It implements only small subset of XML capabilities, which is probably enough for performing most of useful actions. This class also filters out (usually) useless textual nodes which are often used to make XML documents human-readable.

6.330.2 Constructor & Destructor Documentation

6.330.2.1 Arc::XMLNode::XMLNode(xmlNodePtr node) [inline, protected]

Private constructor for inherited classes Creates instance and links to existing LibXML structure. Acquired structure is not owned by class instance. If there is need to completely pass control of LibXML document to then instance's is_owner_ variable has to be set to true.

6.330.2.2 Arc::XMLNode::XMLNode(void) [inline]

Constructor of invalid node Created instance does not point to XML element. All methods are still allowed for such instance but produce no results.

6.330.2.3 Arc::XMLNode::XMLNode (const XMLNode & node) [inline]

Copies existing instance. Underlying XML element is NOT copied. Ownership is NOT inherited. Strictly speaking it shuld be no const here - but that conflicts with C++.

6.330.2.4 Arc::XMLNode::XMLNode (const std::string & xml)

Creates XML document structure from textual representation of XML document. Created structure is pointed and owned by constructed instance

6.330.2.5 Arc::XMLNode::XMLNode (const char * xml, int len = -1)

Same as previous

6.330.2.6 Arc::XMLNode::XMLNode (long ptr_addr)

Copy constructor. Used by language bindigs

6.330.2.7 Arc::XMLNode::XMLNode (const NS & ns, const char * name)

Creates empty XML document structure with specified namespaces. Created XML contains only root element named 'name'. Created structure is pointed and owned by constructed instance

6.330.2.8 Arc::XMLNode::~XMLNode (void)

Destructor Also destroys underlying XML document if owned by this instance

6.330.3 Member Function Documentation

6.330.3.1 XMLNode Arc::XMLNode::Attribute (int n = 0)

Returns list of all attributes of node.

Returns XMLNode (p. 389) instance reresenting n-th attribute of node.

Referenced by Attribute().

6.330.3.2 XMLNode Arc::XMLNode::Attribute (const char * name)

Returns XMLNode (p. 389) instance representing first attribute of node with specified by name

6.330.3.3 XMLNode Arc::XMLNode::Attribute (const std::string & name) [inline]

Returns **XMLNode** (p. 389) instance representing first attribute of node with specified by name References Attribute().

6.330.3.4 int Arc::XMLNode::AttributesSize (void) const

Returns number of attributes of node

6.330.3.5 XMLNode Arc::XMLNode::Child (int n = 0)

Returns **XMLNode** (p. 389) instance representing n-th child of XML element. If such does not exist invalid **XMLNode** (p. 389) instance is returned

6.330.3.6 void Arc::XMLNode::Destroy (void)

Destroys underlying XML element. XML element is unlinked from XML tree and destroyed. After this operation **XMLNode** (p. 389) instance becomes invalid

6.330.3.7 void Arc::XMLNode::Exchange (XMLNode & node)

Exchanges XML (sub)trees. Following conbinations are possible If either this ir node are refering owned XML tree (top level node) then references are simply excanged. This operationis fast. If both this and node are refering to XML (sub)tree of different documents then (sub)trees are exchahed between documents. If both this and node are refering to XML (sub)tree of same document then (sub)trees are moved inside document. The main reason for this method is to provide effective way to insert one XML document inside another. One should take into account that if any of exchanged nodes is top level it must be also owner of document. Otherwise method will fail. If both nodes are top level owners and/or invlaid nodes then this method is identical to **Swap()** (p. 399).

6.330.3.8 std::string Arc::XMLNode::FullName (void) const [inline]

Returns prefix:name of XML node

References Name(), and Prefix().

6.330.3.9 XMLNode Arc::XMLNode::Get (const std::string & name) const [inline]

Same as operator[]

References operator[]().

6.330.3.10 void Arc::XMLNode::GetDoc (std::string & out_xml_str, bool user_friendly = false) const

Fills argument with whole XML document textual representation

6.330.3.11 XMLNode Arc::XMLNode::GetRoot (void)

Get the root node from any child node of the tree

6.330.3.12 void Arc::XMLNode::GetXML (std::string & out_xml_str, bool user_friendly = false) const

Fills argument with this instance XML subtree textual representation

6.330.3.13 void Arc::XMLNode::GetXML (std::string & out_xml_str, const std::string & encoding, bool user_friendly = false) const

Fills argument with this instance XML subtree textual representation if the XML subtree is corresponding to the encoding format specified in the argument, e.g. utf-8

6.330.3.14 void Arc::XMLNode::Move (XMLNode & node)

Moves content of this XML (sub)tree to node This operation is similar to New except that XML (sub)tree to referred by this is destroyed. This method is more effective than combination of **New()** (p. 394) and **Destroy()** (p. 393) because internally it is optimized not to copy data if not needed. The main purpose of this is to effectively extract part of XML document.

6.330.3.15 std::string Arc::XMLNode::Name (void) const

Returns name of XML node

Referenced by FullName(), and Name().

6.330.3.16 void Arc::XMLNode::Name (const std::string & name) [inline]

Assigns new name to XML node

References Name().

6.330.3.17 void Arc::XMLNode::Name (const char * name)

Assigns new name to XML node

6.330.3.18 std::string Arc::XMLNode::Namespace (void) const

Returns namespace URI of XML node

6.330.3.19 std::string Arc::XMLNode::NamespacePrefix (const char * urn)

Returns prefix of specified namespace. Empty string if no such namespace.

6.330.3.20 NS Arc::XMLNode::Namespaces (void)

Returns namespaces known at this node

6.330.3.21 void Arc::XMLNode::Namespaces (const NS & namespaces, bool keep = false, int recursion = -1)

Assigns namespaces of XML document at point specified by this instance. If namespace already exists it gets new prefix. New namespaces are added. It is useful to apply this method to XML being processed in order to refer to it's elements by known prefix. If keep is set to false existing namespace definition residing at this instance and below are removed (default beavior). If recursion is set to positive number then depth of prefix replacement is limited by this number (0 limits it to this node only). For unlimited recursion use -1. If recursion is limited then value of keep is ignored and existing namespaces are always kept.

6.330.3.22 void Arc::XMLNode::New (XMLNode & node) const

Creates a copy of XML (sub)tree. If object does not represent whole document - top level document is created. 'new_node' becomes a pointer owning new XML document.

6.330.3.23 XMLNode Arc::XMLNode::NewAttribute (const char * name)

Creates new attribute with specified name.

Referenced by NewAttribute().

6.330.3.24 XMLNode Arc::XMLNode::NewAttribute (const std::string & name) [inline]

Creates new attribute with specified name.

References NewAttribute().

6.330.3.25 XMLNode Arc::XMLNode::NewChild (const char * name, int n = -1, bool $global_order = false$)

Creates new child XML element at specified position with specified name. Default is to put it at end of list. If global order is true position applies to whole set of children, otherwise only to children of same name. Returns created node.

Referenced by NewChild().

6.330.3.26 XMLNode Arc::XMLNode::NewChild (const std::string & name, int n = -1, bool global order = false) [inline]

Same as **NewChild(const char*,int,bool)** (p. 395)

References NewChild().

6.330.3.27 XMLNode Arc::XMLNode::NewChild (const char * name, const NS & namespaces, int n = -1, bool $global_order = false$)

Creates new child XML element at specified position with specified name and namespaces. For more information look at **NewChild(const char*,int,bool)** (p. 395)

6.330.3.28 XMLNode Arc::XMLNode::NewChild (const std::string & name, const NS & namespaces, int n = -1, bool global_order = false) [inline]

Same as NewChild(const char*,const NS&,int,bool) (p. 395)

References NewChild().

6.330.3.29 XMLNode Arc::XMLNode::NewChild (const XMLNode & node, int n = -1, bool $global_order = false$)

Link a copy of supplied XML node as child. Returns instance referring to new child. XML element is a copy of supplied one but not owned by returned instance

6.330.3.30 Arc::XMLNode::operator bool (void) const [inline]

Returns true if instance points to XML element - valid instance

References is_temporary_.

6.330.3.31 Arc::XMLNode::operator std::string (void) const

Returns textual content of node excluding content of children nodes

6.330.3.32 bool Arc::XMLNode::operator! (void) const [inline]

Returns true if instance does not point to XML element - invalid instance References is_temporary_.

6.330.3.33 bool Arc::XMLNode::operator!= (const XMLNode & node) [inline]

Returns false if 'node' represents same XML element

6.330.3.34 bool Arc::XMLNode::operator!= (bool val) [inline]

This operator is needed to avoid ambiguity

6.330.3.35 bool Arc::XMLNode::operator!= (const std::string & str) [inline]

This operator is needed to avoid ambiguity

6.330.3.36 bool Arc::XMLNode::operator!= (const char * str) [inline]

This operator is needed to avoid ambiguity

6.330.3.37 void Arc::XMLNode::operator++ (void)

Convenience operator to switch to next element of same name. If there is no such node this object becomes invalid.

6.330.3.38 void Arc::XMLNode::operator-- (void)

Convenience operator to switch to previous element of same name. If there is no such node this object becomes invalid.

6.330.3.39 XMLNode& Arc::XMLNode::operator=(const char * content)

Sets textual content of node. All existing children nodes are discarded.

Referenced by operator=(), and Set().

6.330.3.40 XMLNode& Arc::XMLNode::operator=(const XMLNode & node)

Make instance refer to another XML node. Ownership is not inherited. Due to nature of **XMLNode** (p. 389) there should be no const here, but that does not fit into C++.

6.330.3.41 XMLNode& Arc::XMLNode::operator=(const std::string & content) [inline]

Sets textual content of node. All existing children nodes are discarded.

References operator=().

6.330.3.42 bool Arc::XMLNode::operator== (bool val) [inline]

This operator is needed to avoid ambiguity

6.330.3.43 bool Arc::XMLNode::operator== (const XMLNode & node) [inline]

Returns true if 'node' represents same XML element

Referenced by Same().

6.330.3.44 bool Arc::XMLNode::operator== (const char * str) [inline]

This operator is needed to avoid ambiguity

6.330.3.45 bool Arc::XMLNode::operator== (const std::string & str) [inline]

This operator is needed to avoid ambiguity

6.330.3.46 XMLNode Arc::XMLNode::operator[] (const char * name) const

Returns **XMLNode** (p. 389) instance representing first child element with specified name. Name may be "namespace_prefix:name" or simply "name". In last case namespace is ignored. If such node does not exist invalid **XMLNode** (p. 389) instance is returned. This method should not be marked const because obtaining unrestricted **XMLNode** (p. 389) of child element allows modification of underlying XML tree. But in order to keep const in other places non-const-handling is passed to programmer. Otherwise C++ compiler goes nuts.

Referenced by Get(), and operator[]().

6.330.3.47 XMLNode Arc::XMLNode::operator[] (const std::string & name) const [inline]

Similar to previous method

References operator[]().

6.330.3.48 XMLNode Arc::XMLNode::operator[] (int *n*) const

Returns **XMLNode** (p. 389) instance representing n-th node in sequence of siblings of same name. It's main purpose is to be used to retrieve element in array of children of same name like node["name"][5]. This method should not be marked const because obtaining unrestricted **XMLNode** (p. 389) of child element allows modification of underlying XML tree. But in order to keep const in other places non-const-handling is passed to programmer. Otherwise C++ compiler goes nuts.

6.330.3.49 XMLNode Arc::XMLNode::Parent (void)

Get the parent node from any child node of the tree

6.330.3.50 XMLNodeList Arc::XMLNode::Path (const std::string & path)

Collects nodes corresponding to specified path. This is a convenience function to cover common use of XPath but without performance hit. Path is made of node_name[/node_name[...]] and is relative to current node. node_names are treated in same way as in operator[]. Returns all nodes which are represented by path.

6.330.3.51 std::string Arc::XMLNode::Prefix (void) const

Returns namespace prefix of XML node

Referenced by FullName().

6.330.3.52 bool Arc::XMLNode::ReadFromFile (const std::string & file_name)

Read XML document from file and associate it with this node

6.330.3.53 bool Arc::XMLNode::ReadFromStream (std::istream & in)

Read XML document from stream and associate it with this node

6.330.3.54 void Arc::XMLNode::Replace (const XMLNode & node)

Makes a copy of supplied XML node and makes this instance refere to it

6.330.3.55 bool Arc::XMLNode::Same (const XMLNode & node) [inline]

Returns true if 'node' represents same XML element - for bindings References operator==().

6.330.3.56 bool Arc::XMLNode::SaveToFile (const std::string & file_name) const

Save string representation of node to file

6.330.3.57 bool Arc::XMLNode::SaveToStream (std::ostream & out) const

Save string representation of node to stream

6.330.3.58 void Arc::XMLNode::Set (const std::string & content) [inline]

Same as operator=. Used for bindings.

References operator=().

6.330.3.59 int Arc::XMLNode::Size (void) const

Returns number of children nodes

6.330.3.60 void Arc::XMLNode::Swap (XMLNode & node)

Swaps XML (sub)trees to this this and node refer. For XML subtrees this method is not anyhow different then using combination **XMLNode** (p. 389) tmp=*this; *this=node; node=tmp; But in case of either this or node owning XML document ownership is swapped too. And this is a main purpose of **Swap()** (p. 399) method.

6.330.3.61 bool Arc::XMLNode::Validate (const std::string & schema_file, std::string & err_msg)

Remove all eye-candy information leaving only informational parts * void Purify(void); XML schema validation against the schema file defined as argument

6.330.3.62 XMLNodeList Arc::XMLNode::XPathLookup (const std::string & xpathExpr, const NS & nsList)

Uses xPath to look up the whole xml structure, Returns a list of **XMLNode** (p. 389) points. The xpathExpr should be like "//xx:child1/" which indicates the namespace and node that you would like to find; The nsList is the namespace the result should belong to (e.g. xx="uri:test"). **Query** (p. 257) is run on whole XML document but only the elements belonging to this XML subtree are returned.

6.330.4 Friends And Related Function Documentation

6.330.4.1 bool MatchXMLName (const XMLNode & node1, const XMLNode & node2) [friend]

Returns true if underlying XML elements have same names

6.330.4.2 bool MatchXMLName (const XMLNode & node, const std::string & name) [friend]

Returns true if 'name' matches name of 'node'. If name contains prefix it's checked too

6.330.4.3 bool MatchXMLName (const XMLNode & node, const char * name) [friend]

Returns true if 'name' matches name of 'node'. If name contains prefix it's checked too

6.330.4.4 bool MatchXMLNamespace (const XMLNode & node1, const XMLNode & node2) [friend]

Returns true if underlying XML elements belong to same namespaces

6.330.4.5 bool MatchXMLNamespace (const XMLNode & node, const std::string & uri) [friend]

Returns true if 'namespace' matches 'node's namespace.

6.330.4.6 bool MatchXMLNamespace (const XMLNode & node, const char * uri) [friend]

Returns true if 'namespace' matches 'node's namespace.

6.330.5 Field Documentation

6.330.5.1 bool Arc::XMLNode::is_owner_ [protected]

If true node is owned by this instance - hence released in destructor. Normally that may be true only for top level node of XML document.

6.330.5.2 bool Arc::XMLNode::is_temporary_ [protected]

This variable is for future

Referenced by operator bool(), and operator!().

The documentation for this class was generated from the following file:

· XMLNode.h

6.331 Arc::XMLNodeContainer Class Reference

#include <XMLNode.h>

Public Member Functions

- XMLNodeContainer (void)
- XMLNodeContainer (const XMLNodeContainer &)
- XMLNodeContainer & operator= (const XMLNodeContainer &)
- void Add (const XMLNode &)
- void **Add** (const std::list< **XMLNode** > &)
- void AddNew (const XMLNode &)
- void **AddNew** (const std::list< **XMLNode** > &)
- int Size (void) const
- XMLNode operator[] (int)
- std::list< **XMLNode** > **Nodes** (void)

6.331.1 Detailed Description

Container for multiple XMLNode (p. 389) elements

6.331.2 Constructor & Destructor Documentation

6.331.2.1 Arc::XMLNodeContainer::XMLNodeContainer (void)

Default constructor

6.331.2.2 Arc::XMLNodeContainer::XMLNodeContainer (const XMLNodeContainer &)

Copy constructor. Add nodes from argument. Nodes owning XML document are copied using **AddNew()** (p. 401). Not owning nodes are linked using **Add()** (p. 401) method.

6.331.3 Member Function Documentation

6.331.3.1 void Arc::XMLNodeContainer::Add (const XMLNode &)

Link XML subtree refered by node to container. XML tree must be available as long as this object is used.

6.331.3.2 void Arc::XMLNodeContainer::Add (const std::list< XMLNode > &)

Link multiple XML subtrees to container.

6.331.3.3 void Arc::XMLNodeContainer::AddNew (const XMLNode &)

Copy XML subtree referenced by node to container. After this operation container refers to independent XML document. This document is deleted when container is destroyed.

6.331.3.4 void Arc::XMLNodeContainer::AddNew (const std::list< XMLNode > &)

Copy multiple XML subtrees to container.

6.331.3.5 std::list<XMLNode> Arc::XMLNodeContainer::Nodes (void)

Returns all stored nodes.

6.331.3.6 XMLNodeContainer& Arc::XMLNodeContainer::operator= (const XMLNodeContainer &)

Same as copy constructor with current nodes being deleted first.

6.331.3.7 XMLNode Arc::XMLNodeContainer::operator[](int)

Returns n-th node in a store.

6.331.3.8 int Arc::XMLNodeContainer::Size (void) const

Return number of refered/stored nodes.

The documentation for this class was generated from the following file:


XMLNode.h

6.332 Arc::XMLSecNode Class Reference

Extends XMLNode (p. 389) class to support XML security operation.

#include <XMLSecNode.h>

Inheritance diagram for Arc::XMLSecNode:



Public Member Functions

- XMLSecNode (XMLNode &node)
- void **AddSignatureTemplate** (const std::string &id_name, const SignatureMethod sign_method, const std::string &incl_namespaces="")
- bool **SignNode** (const std::string &privkey_file, const std::string &cert_file)
- bool **VerifyNode** (const std::string &id_name, const std::string &ca_file, const std::string &ca_path, bool verify_trusted=true)
- bool **EncryptNode** (const std::string &cert_file, const SymEncryptionType encrpt_type)
- bool **DecryptNode** (const std::string &privkey_file, **XMLNode** &decrypted_node)

6.332.1 Detailed Description

Extends **XMLNode** (p. 389) class to support XML security operation. All **XMLNode** (p. 389) methods are exposed by inheriting from **XMLNode** (p. 389). **XMLSecNode** (p. 402) itself does not own node, instead it uses the node from the base class **XMLNode** (p. 389).

6.332.2 Constructor & Destructor Documentation

6.332.2.1 Arc::XMLSecNode::XMLSecNode (XMLNode & node)

Create a object based on an XMLNode (p. 389) instance.

6.332.3 Member Function Documentation

6.332.3.1 void Arc::XMLSecNode::AddSignatureTemplate (const std::string & id_name, const SignatureMethod sign_method, const std::string & incl_namespaces = "")

Add the signature template for later signing.

Parameters

id_name The identifier name under this node which will be used for the <Signature> to refer to.

sign_method The sign method for signing. Two options now, RSA_SHA1, DSA_SHA1

6.332.3.2 bool Arc::XMLSecNode::DecryptNode (const std::string & privkey_file, XMLNode & decrypted node)

Decrypt the <xenc:EncryptedData/> under this node, the decrypted node will be output in the second argument of DecryptNode method. And the <xenc:EncryptedData/> under this node will be removed after decryption.

Parameters

privkey_file The private key file, which is used for decrypting
decrypted_node Output the decrypted node

6.332.3.3 bool Arc::XMLSecNode::EncryptNode (const std::string & cert_file, const SymEncryptionType encrpt_type)

Encrypt this node, after encryption, this node will be replaced by the encrypted node

Parameters

cert_file The certificate file, the public key parsed from this certificate is used to encrypted the symmetric key, and then the symmetric key is used to encrypted the node

encrpt_type The encryption type when encrypting the node, four option in SymEncryptionType

verify_trusted Verify trusted certificates or not. If set to false, then only the signature will be checked (by using the public key from KeyInfo).

6.332.3.4 bool Arc::XMLSecNode::SignNode (const std::string & privkey_file, const std::string & cert_file)

Sign this node (identified by id_name).

Parameters

privkey_file The private key file. The private key is used for signing

incl_namespaces InclusiveNamespaces for Tranform in Signature

6.332.3.5 bool Arc::XMLSecNode::VerifyNode (const std::string & id_name, const std::string & ca_file, const std::string & ca_path, bool verify_trusted = true)

Verify the signature under this node

Parameters

id_name The id of this node, which is used for identifying the node

ca_file The CA file which used as trused certificate when verify the certificate in the <KeyInfo> part of <Signature>


ca_path The CA directory; either ca_file or ca_path should be set.

The documentation for this class was generated from the following file:

• XMLSecNode.h

6.333 Arc::XRSLParser Class Reference

Inheritance diagram for Arc::XRSLParser:



The documentation for this class was generated from the following file:

• XRSLParser.h

Chapter 7

File Documentation

7.1 URL.h File Reference

Class to hold general URL's.

```
#include <iostream>
#include <list>
#include <map>
#include <string>
```

Data Structures

- class Arc::URL
- class Arc::URLLocation

Class to hold a resolved URL (p. 320) location.

• class Arc::PathIterator

Class to iterate through elements of path.

Namespaces

• namespace Arc

Defines

• #define **RC_DEFAULT_PORT** 389

Functions

• std::list< URL > Arc::ReadURLList (const URL &urllist)

406 File Documentation

7.1.1 Detailed Description

Class to hold general URL's. The URL is split into protocol, hostname, port and path. This class tries to follow RFC 3986 for spliting URLs at least for protocol + host part. It also accepts local file paths which are converted to file:path. Usual system dependant file paths are supported. Relative paths are converted to absolute ones by prepending them with current working directory path. File path can't start from # symbol (why?). If string representation of URL starts from '@' then it is treated as path to file containing list of URLs. Simple URL is parsed in following way: [protocol:][//[username:passwd@][host][:port]][:urloptions[:...]][/path[?httpoption[&...]][:metadataoption[:...]]] The 'protocol' and 'host' parts are treated as case-insensitive and to avoid confusion are converted to lowercase in constructor. Note that 'path' is always converted to absolute path in constructor. Meaning of 'absolute' may depend upon URL type. For generic URL and local POSIX file paths that means path starts from / like /path/to/file For Windows paths absolute path may look like C: It is important to note that path still can be empty. For referencing local file using absolute path on POSIX filesystem one may use either file:///path/to/file or file:/path/to/file Relative path will look like file:to/file For local Windows files possible URLs are file:C: file:to URLs representing LDAP resources have different structure of options following 'path' part [scope]/host[sport][surloptions[surloptions[surloptions]]/path[sattributes[scope]/filter]]] For LDAP URLs paths are converted from /key1=value1/.../keyN=valueN notation to keyN=valueN,...,key1=value1 and hence path does not contain leading /. If LDAP URL initially had path in second notation leading / is treated as separator only and is stripped. URLs of indexing services optionally may have locations specified before 'host' part protocol://[location[;location[;...]]@][host][:port]... The structure of 'location' element is protocol specific.

7.1.2 Define Documentation

7.1.2.1 #define RC_DEFAULT_PORT 389

Default ports for different protocols

Index

~BrokerLoader	Arc::XMLNode, 392
Arc::BrokerLoader, 64	
~Counter	Abandon
Arc::Counter, 83	Arc::Run, 270
~Database	ACCESS_LATENCY_LARGE
Arc::Database, 99	Arc::DataPoint, 111
~IntraProcessCounter	ACCESS_LATENCY_SMALL
Arc::IntraProcessCounter, 179	Arc::DataPoint, 111
~JobControllerLoader	ACCESS_LATENCY_ZERO
Arc::JobControllerLoader, 186	Arc::DataPoint, 111
~Loader	Acquire
Arc::Loader, 189	Arc::DelegationConsumer, 136
~Logger	Arc::InformationContainer, 173
Arc::Logger, 194	acquireDelegation
~MCCLoader	Arc::ClientX509Delegation, 74
Arc::MCCLoader, 207	Action
~Message	Arc::WSAHeader, 365
Arc::Message, 209	Add
~PayloadRaw	Arc::MessageContext, 215
Arc::PayloadRaw, 228	Arc::XMLNodeContainer, 401
~PayloadStream	add
Arc::PayloadStream, 234	Arc::DataBuffer, 102
~Plexer	Arc::MessageAttributes, 211
Arc::Plexer, 246	Arc::SoftwareRequirement, 297
~Query	AddBartender
Arc::Query, 258	Arc::UserConfig, 335
~Run	AddCADir
Arc::Run, 269	Arc::BaseConfig, 60
~SAMLToken	AddCAFile
Arc::SAMLToken, 276	Arc::BaseConfig, 60
	AddCertExtObj
~SOAPMessage	Arc::Credential, 92
Arc::SOAPMessage, 287	AddCertificate
~SubmitterLoader	
Arc::SubmitterLoader, 307	Arc::BaseConfig, 60
~TargetRetrieverLoader	AddChain
Arc::TargetRetrieverLoader, 313	Arc::VOMSTrustList, 362
~URL	AddCheckSumObject
Arc::URL, 322	Arc::DataPoint, 111
~URLLocation	Arc::DataPointDirect, 118
Arc::URLLocation, 330	Arc::DataPointIndex, 123
~WSAEndpointReference	addDestination
Arc::WSAEndpointReference, 363	Arc::Logger, 194
~X509Token	AddDN
Arc::X509Token, 388	Arc::FileCache, 159
~XMLNode	AddExtension

408 INDEX

A C dti1 02	A Devilee ID Def 220
Arc::Credential, 92 AddIndexServer	Arc::PayloadRawBuf, 230 allocated_
Arc::TargetGenerator, 309	Arc::WSRF, 368
AddJob	ApplicationEnvironments
Arc::TargetGenerator, 309	Arc::ExecutionTarget, 155
AddLDAPAttribute	ApplyToConfig
Arc::URL, 323	Arc::UserConfig, 337
AddLocation	approveCSR
Arc::DataPoint, 111	Arc::OAuthConsumer, 224
Arc::DataPointDirect, 118	Arc::SAML2SSOHTTPClient, 273
Arc::DataPointIndex, 123	Arc, 23
AddMetaDataOption	addVOMSAC, 37
Arc::URL, 323	AttrConstIter, 36
AddNew	AttrIter, 36
Arc::XMLNodeContainer, 401	AttrMap, 36
AddOption	BUSY_ERROR, 37
Arc::URL, 323	ContentFromPayload, 37
AddOverlay	CreateThreadFunction, 37
Arc::BaseConfig, 61	createVOMSAC, 37
AddPluginsPath	CredentialLogger, 43
Arc::BaseConfig, 61	FileOpen, 38
addPolicy	final_xmlsec, 38
ArcSec::Evaluator, 149	GENERIC_ERROR, 36
ArcSec::Policy, 253	get_cert_str, 38
AddPrivateKey	get_key_from_certfile, 38
Arc::BaseConfig, 61	get_key_from_certstr, 38
AddProxy	get_key_from_keyfile, 38
Arc::BaseConfig, 61	get_key_from_keystr, 38
AddRegex	get_node, 38
Arc::VOMSTrustList, 362	get_plugin_instance, 36
addRegistrar	get_property, 38
Arc::InfoRegisterContainer, 170	GUID, 39
addRequestItem	init_xmlsec, 39
ArcSec::Request, 262	istring_to_level, 39
Address	load_key_from_certfile, 39
Arc::WSAEndpointReference, 363	load_key_from_certstr, 39
AddSecHandler	load_key_from_keyfile, 39
Arc::ClientSOAP, 72	load_trusted_cert_file, 39
Arc::MCC, 201	load_trusted_cert_str, 40
Arc::Service, 284	load_trusted_certs, 40
AddService	LogLevel, 36
Arc::TargetGenerator, 309	MatchXMLName, 40
addService	MatchXMLNamespace, 40
Arc::InfoRegisterContainer, 171	OpenSSLInit, 40
Arc::InfoRegistrar, 172	operator <<, 40, 41
AddServices	parseVOMSAC, 41, 42
Arc::UserConfig, 335, 336	PARSING_ERROR, 37
AddSignatureTemplate	passphrase_callback, 42
Arc::XMLSecNode, 402	plugins_table_name, 43
AddTarget	PROTOCOL_RECOGNIZED_ERROR, 37
Arc::TargetGenerator, 310	SESSION_CLOSE, 37
addVOMSAC	STATUS_OK, 36
Arc, 37	StatusKind, 36
allocated	string, 42

thread_stacksize, 43	Arc::CheckSum, 67
TimeStamp, 42	Arc::CheckSumAny, 67
UNKNOWN_SERVICE_ERROR, 37	Arc::CIStringValue, 67
VOMSDecode, 42	CIStringValue, 68
WSAFault, 37	equal, 68
WSAFaultAssign, 42	operator bool, 68
WSAFaultExtract, 42	Arc::ClassLoader, 69
WSAFaultInvalidAddressingHeader, 37	Arc::ClassLoaderPluginArgument, 69
WSAFaultUnknown, 37	Arc::ClientHTTP, 69
Arc::Adler32Sum, 47	Arc::ClientHTTPwithSAML2SSO, 70
Arc::ApplicationEnvironment, 50	ClientHTTPwithSAML2SSO, 70
Arc::ApplicationType, 50	process, 70
Arc::ARCJSDLParser, 50	Arc::ClientInterface, 71
Arc::ArcLocation, 51	Arc::ClientSOAP, 71
GetPlugins, 51	AddSecHandler, 72
Init, 51	ClientSOAP, 72
Arc::ARCPolicyHandlerConfig, 51	GetEntry, 72
Arc::AttributeIterator, 53	Load, 72
AttributeIterator, 53	process, 72
current_, 55	Arc::ClientSOAPwithSAML2SSO, 73
end_, 55	ClientSOAPwithSAML2SSO, 73
hasMore, 54	process, 73
key, 54	Arc::ClientTCP, 73
MessageAttributes, 55	Arc::ClientX509Delegation, 74
operator*, 54	acquireDelegation, 74
operator++, 54	ClientX509Delegation, 74
operator->, 55	createDelegation, 75
Arc::AutoPointer, 59	Arc::Config, 76
Arc::Base64, 60	Config, 77
Arc::BaseConfig, 60	getFileName, 78
AddCADir, 60	parse, 78
AddCAFile, 60	print, 78
AddCertificate, 60	save, 78
AddOverlay, 61	setFileName, 78
AddPluginsPath, 61	Arc::ConfusaCertHandler, 78
AddPrivateKey, 61	ConfusaCertHandler, 79
AddProxy, 61	createCertRequest, 79
GetOverlay, 61	getCertRequestB64, 79
MakeConfig, 61	Arc::ConfusaParserUtils, 79
Arc::Broker, 62	destroy_doc, 79
GetBestTarget, 63	evaluate_path, 79
PossibleTargets, 64	extract_body_information, 80
PreFilterTargets, 63	get_doc, 80
SortTargets, 63	handle_redirect_step, 80
Arc::BrokerLoader, 64	urlencode, 80
~BrokerLoader, 64	urlencode_params, 80
BrokerLoader, 64	Arc::CountedPointer, 80
GetBrokers, 65	Arc::Counter, 81
load, 65	~Counter, 83
Arc::BrokerPluginArgument, 65	cancel, 84
Arc::ByteArray, 65	changeExcess, 84
Arc::CacheParameters, 66	changeLimit, 84
Arc::ChainContext, 66	Counter, 83
operator PluginsFactory *, 66	extend, 84

getCounterTicket, 85	~Database, 99
getCurrentTime, 85	close, 99
getExcess, 85	connect, 99
getExpirationReminder, 85	Database, 99
getExpiryTime, 86	enable_ssl, 99
getLimit, 86	isconnected, 100
getValue, 86	shutdown, 100
IDType, 83	Arc::DataBuffer, 100
reserve, 87	add, 102
setExcess, 87	buffer_size, 102
setLimit, 87	checksum_object, 102
Arc::CounterTicket, 88	checksum_valid, 102
cancel, 89	DataBuffer, 101
CounterTicket, 89	eof_read, 102
extend, 89	eof_write, 103
isValid, 89	error, 103
Arc::CRC32Sum, 89	error_read, 103
Arc::Credential, 90	error_write, 103
AddCertExtObj, 92	for_read, 103
AddExtension, 92	for_write, 103, 104
Credential, 91, 92	is_notwritten, 104
GenerateEECRequest, 93	is_read, 104
GenerateRequest, 93	is_written, 105
GetCert, 93	set, 105
GetCertNumofChain, 93	wait_any, 105
GetCertReq, 94	Arc::DataCallback, 105
GetDN, 94	Arc::DataHandle, 106
GetEndTime, 94	Arc::DataMover, 106
getFormat, 94	checks, 107
GetIdentityName, 94	force_to_meta, 107
GetLifeTime, 94	secure, 107
GetPrivKey, 94	set_default_max_inactivity_time, 107
GetProxyPolicy, 94	set_default_min_average_speed, 107
GetPubKey, 94	set_default_min_speed, 107
GetStartTime, 94	Transfer, 107, 108
GetType, 94	verbose, 108
GetVerification, 95	Arc::DataPoint, 108
InitProxyCertInfo, 95	ACCESS_LATENCY_LARGE, 111
InquireRequest, 95	ACCESS_LATENCY_SMALL, 111
LogError, 95	ACCESS_LATENCY_ZERO, 111
OutputCertificate, 95	AddCheckSumObject, 111
OutputCertificateChain, 95	AddLocation, 111
OutputPrivatekey, 96	Check, 111
OutputPublickey, 96	CompareLocationMetadata, 112
SetLifeTime, 96	CompareMeta, 112
SetProxyPolicy, 96	CurrentLocationMetadata, 112
SetStartTime, 96	DataPoint, 111
SignEECRequest, 96	DataPointAccessLatency, 111
SignRequest, 96, 97	GetFailureReason, 112
STACK_OF, 97	ListFiles, 112
Arc::CredentialError, 97	NextLocation, 112
CredentialError, 98	
	Passive, 113
Arc::CredentialStore, 98	PostRegister, 113
Arc::Database, 98	PreRegister, 113

D. II. 112	0, 377.22 106
PreUnregister, 113	StartWriting, 126
ProvidesMeta, 114	StopReading, 126
Range, 114	StopWriting, 126
ReadOutOfOrder, 114	WriteOutOfOrder, 127
Registered, 114	Arc::DataPointLoader, 127
Resolve, 114	Arc::DataPointPluginArgument, 127
SetAdditionalChecks, 114	Arc::DataSourceType, 128
SetMeta, 115	Arc::DataSpeed, 128
SetSecure, 115	DataSpeed, 128
SortLocations, 115	hold, 129
StartReading, 115	set_base, 129
StartWriting, 116	set_max_data, 129
StopReading, 116	set_max_inactivity_time, 129
StopWriting, 116	set_min_average_speed, 129
Unregister, 116	set_min_speed, 130
valid_url_options, 117	set_progress_indicator, 130
WriteOutOfOrder, 116	transfer, 130
Arc::DataPointDirect, 117	verbose, 130
AddCheckSumObject, 118	Arc::DataStagingType, 131
AddLocation, 118	Arc::DataStatus, 131
CompareLocationMetadata, 118	CacheError, 132
CurrentLocationMetadata, 119	CheckError, 132
NextLocation, 119	CredentialsExpiredError, 132
Passive, 119	DataStatusType, 131
PostRegister, 119	DeleteError, 132
PreRegister, 119	InconsistentMetadataError, 132
PreUnregister, 120	IsReadingError, 132
ProvidesMeta, 120	IsWritingError, 132
Range, 120	ListError, 132
ReadOutOfOrder, 120	LocationAlreadyExistsError, 132
Registered, 120	NoLocationError, 132
Resolve, 120	NotInitializedError, 132
SetAdditionalChecks, 121	NotSupportedForDirectDataPointsError, 132
SetSecure, 121	**
,	PostRegisterError, 132
SortLocations, 121	PreRegisterError, 132
Unregister, 121	ReadAcquireError, 131
WriteOutOfOrder, 121	ReadError, 131
Arc::DataPointIndex, 122	ReadResolveError, 131
AddCheckSumObject, 123	ReadStartError, 131
AddLocation, 123	ReadStopError, 132
Check, 123	StageError, 132
CompareLocationMetadata, 124	Success, 131
CurrentLocationMetadata, 124	SystemError, 132
NextLocation, 124	TransferError, 131
Passive, 124	UnimplementedError, 132
ProvidesMeta, 124	UnknownError, 132
Range, 124	UnregisterError, 132
ReadOutOfOrder, 125	WriteAcquireError, 131
Registered, 125	WriteError, 131
SetAdditionalChecks, 125	WriteResolveError, 131
SetMeta, 125	WriteStartError, 131
SetSecure, 125	WriteStopError, 132
SortLocations, 125	Arc::DataTargetType, 132
StartReading, 126	Arc::DataType, 132

A DD 1 127	. 157
Arc::DBranch, 135	operator<, 157
Arc::DelegationConsumer, 135	Arc::FileCache, 157
Acquire, 136	AddDN, 159
Backup, 136	CheckCreated, 159
DelegationConsumer, 136	CheckDN, 159
Generate, 136	CheckValid, 160
ID, 136	Copy, 160
LogError, 136	File, 160
Request, 136	FileCache, 158, 159
Restore, 136	GetCreated, 160
Arc::DelegationConsumerSOAP, 137	GetValid, 160
DelegateCredentialsInit, 137	Link, 160
DelegatedToken, 137	operator bool, 161
DelegationConsumerSOAP, 137	operator==, 161
UpdateCredentials, 138	Release, 161
Arc::DelegationContainerSOAP, 138	SetValid, 161
context_lock_, 139	Start, 161
DelegateCredentialsInit, 139	Stop, 161
DelegatedToken, 139	StopAndDelete, 162
max_duration_, 139	Arc::FileInfo, 163
max_size_, 139	Arc::FileLock, 163
max_usage_, 139	Arc::FileType, 163
restricted_, 139	Arc::FinderLoader, 164
UpdateCredentials, 139	Arc::GlobusResult, 166
Arc::DelegationProvider, 139	Arc::GSSCredential, 167
Delegate, 140	Arc::HakaClient, 167
DelegationProvider, 140	processConsent, 167
Arc::DelegationProviderSOAP, 140	processIdP2Confusa, 167
DelegateCredentialsInit, 142	processIdPLogin, 167
DelegatedToken, 142	Arc::HTTPClientInfo, 168
DelegationProviderSOAP, 141	Arc::InfoCache, 168
ID, 142	InfoCache, 168
UpdateCredentials, 142	Arc::InfoCacheInterface, 168
Arc::DirectoryType, 144	Get, 169
Arc::DiskSpaceRequirementType, 144	Arc::InfoFilter, 169
Arc::DiskspaceRequirement Type, 144 Arc::DItem, 144	Filter, 169
Arc::Ditem, 144 Arc::DItemString, 144	InfoFilter, 169
Arc::DNListHandlerConfig, 145	Arc::InfoRegister, 170
Arc::ExecutableType, 153	Arc::InfoRegisterContainer, 170
Arc::ExecutionTarget, 153	addRegistrar, 170
	_
ApplicationEnvironments, 155	addService, 171
ComputingShareName, 155	removeService, 171
ExecutionTarget, 153, 154	Arc::InfoRegisters, 171
GetSubmitter, 154	InfoRegisters, 171
MaxDiskSpace, 155	Arc::InfoRegistrar, 172
MaxMainMemory, 155	addService, 172
MaxVirtualMemory, 155	registration, 172
OperatingSystem, 155	Arc::InformationContainer, 172
operator=, 154	Acquire, 173
Print, 154	Assign, 173
Update, 154	doc_, 174
Arc::ExpirationReminder, 156	Get, 173
getExpiryTime, 156	InformationContainer, 173
getReservationID, 156	Arc::InformationInterface, 174

0 . 155	T. D. d. d. 100 404
Get, 175	LogDestination, 190, 191
InformationInterface, 174	Arc::LogFile, 191
lock_, 175	log, 192
Arc::InformationRequest, 175	LogFile, 191, 192
InformationRequest, 175, 176	setBackups, 192
SOAP, 176	setMaxSize, 192
Arc::InformationResponse, 176	setReopen, 192
InformationResponse, 176	Arc::Logger, 193
Result, 176	~Logger, 194
Arc::IniConfig, 177	addDestination, 194
Arc::initializeCredentialsType, 177	getRootLogger, 194
Arc::IntraProcessCounter, 178	getThreshold, 194
~IntraProcessCounter, 179	Logger, 194
cancel, 179	msg, 195
changeExcess, 179	setThreshold, 195
changeLimit, 179	Arc::LoggerFormat, 195
extend, 180	Arc::LogMessage, 196
getExcess, 180	getLevel, 197
getLimit, 180	Logger, 197
getValue, 180	LogMessage, 196
IntraProcessCounter, 179	operator<<, 197
reserve, 181	setIdentifier, 197
setExcess, 181	Arc::LogStream, 197
setLimit, 181	log, 198
Arc::ISIS_description, 182	LogStream, 198
Arc::IString, 182	Arc::MCC, 200
Arc::JDLParser, 182	AddSecHandler, 201
Arc::Job, 182	logger, 202
Job, 183	MCC, 201
Print, 183	Next, 201
Arc::JobController, 183	next_, 202
FillJobStore, 184	process, 201
Migrate, 184	ProcessSecHandlers, 201
PrintJobStatus, 184	sechandlers_, 202
Arc::JobControllerLoader, 185	Unlink, 202
~JobControllerLoader, 186	Arc::MCC_Status, 202
GetJobControllers, 186	getExplanation, 203
JobControllerLoader, 186	getKind, 203
load, 186	getOrigin, 203
Arc::JobControllerPluginArgument, 186	isOk, 204
Arc::JobDescription, 187	MCC_Status, 203
Arc::JobDescriptionParser, 187	operator bool, 204
Arc::JobIdentificationType, 187	operator std::string, 204
Arc::JobMetaType, 187	Arc::MCCConfig, 205
Arc::JobState, 187	MakeConfig, 205
Arc::JobSupervisor, 188	Arc::MCCInterface, 205
GetJobControllers, 188	process, 206
JobSupervisor, 188	Arc::MCCLoader, 206
Arc::LoadableModuleDesciption, 189	~MCCLoader, 207
Arc::Loader, 189	MCCLoader, 207
~Loader, 189	operator[], 207
factory_, 190	Arc::MCCPluginArgument, 207
Loader, 189	Arc::MD5Sum, 208
Arc::LogDestination, 190	Arc::MemoryAllocationException, 208

Arc::Message, 208	Arc::NS, 223
~Message, 209	Arc::OAuthConsumer, 223
Attributes, 209	approveCSR, 224
Auth, 209	OAuthConsumer, 224
AuthContext, 210	parseDN, 224
Context, 210	processLogin, 224
Message, 209	pushCSR, 225
operator=, 210	storeCert, 225
Payload, 210	Arc::OpenIdpClient, 225
Arc::MessageAttributes, 210	processConsent, 225
add, 211	processIdP2Confusa, 225
attributes_, 213	processIdPLogin, 226
count, 212	Arc::OptionParser, 226
get, 212	Arc::PathIterator, 227
getAll, 212	operator bool, 227
MessageAttributes, 211	÷
remove, 212	operator*, 227
•	operator++, 227
removeAll, 213	operator, 227
set, 213	PathIterator, 227
Arc::MessageAuth, 213	Rest, 227
Export, 214	Arc::PayloadRaw, 228
Filter, 214	~PayloadRaw, 228
Arc::MessageAuthContext, 214	Buffer, 229
Arc::MessageContext, 215	BufferPos, 229
Add, 215	BufferSize, 229
Arc::MessageContextElement, 216	Content, 229
Arc::MessagePayload, 216	Insert, 229
Arc::ModuleDesc, 216	operator[], 229
Arc::ModuleManager, 217	PayloadRaw, 228
find, 218	Size, 230
findLocation, 218	Truncate, 230
load, 218	Arc::PayloadRawBuf, 230
makePersistent, 218	allocated, 230
ModuleManager, 218	length, 230
reload, 218	size, 230
setCfg, 218	Arc::PayloadRawInterface, 230
unload, 218	Buffer, 231
Arc::MultiSecAttr, 219	BufferPos, 231
Export, 219	BufferSize, 231
operator bool, 219	Content, 232
Arc::MySQLDatabase, 220	Insert, 232
close, 220	operator[], 232
connect, 220	Size, 232
enable_ssl, 220	Truncate, 232
isconnected, 221	Arc::PayloadSOAP, 233
shutdown, 221	PayloadSOAP, 233
Arc::MySQLQuery, 221	Arc::PayloadStream, 233
execute, 222	~PayloadStream, 234
	•
get_array, 222	Get, 235
get_num_colums, 222	handle_, 237
get_num_rows, 222	Limit, 235
get_row, 222	operator bool, 235
get_row_field, 223	PayloadStream, 234
Arc::NotificationType, 223	Pos, 235

Put, 236	get_row, 258, 259
seekable_, 237	get_row_field, 259
Size, 236	Query, 257
Timeout, 236	Arc::Range, 259
	•
Arc::PayloadStreamInterface, 237	Arc::Register_Info_Type, 259
Get, 238	Arc::RegisteredService, 260
Limit, 238	RegisteredService, 260
operator bool, 238	Arc::RegularExpression, 260
Pos, 238	match, 261
Put, 239	Arc::ResourceSlotType, 264
Size, 239	Arc::ResourcesType, 264
Timeout, 239	Arc::ResourceTargetType, 265
Arc::PayloadWSRF, 239	Arc::RSL, 265
PayloadWSRF, 240	Arc::RSLBoolean, 266
Arc::Period, 242	Arc::RSLConcat, 266
GetPeriod, 242	Arc::RSLCondition, 266
istr, 242	Arc::RSLList, 267
operator std::string, 242	Arc::RSLLiteral, 267
operator<, 243	Arc::RSLParser, 267
operator<=, 243	Arc::RSLSequence, 268
operator>, 243	Arc::RSLValue, 268
operator>=, 243	Arc::RSLVariable, 268
operator=, 243	Arc::Run, 268
operator==, 243	∼Run, 269
Period, 242	Abandon, 270
SetPeriod, 243	AssignStderr, 270
Arc::Plexer, 246	AssignStdin, 270
\sim Plexer, 246	AssignStdout, 270
logger, 247	AssignWorkingDirectory, 270
Next, 247	CloseStderr, 270
Plexer, 246	CloseStdin, 270
process, 247	CloseStdout, 270
Arc::PlexerEntry, 247	KeepStderr, 270
Arc::Plugin, 248	KeepStdin, 270
Arc::PluginArgument, 249	KeepStdout, 270
get_factory, 249	Kill, 271
get_module, 250	operator bool, 271
Arc::PluginDesc, 250	ReadStderr, 271
Arc::PluginDescriptor, 250	ReadStdout, 271
Arc::PluginsFactory, 250	Result, 271
load, 251	Run, 269
PluginsFactory, 251	Running, 271
report, 251	Start, 271
scan, 251	Wait, 271
TryLoad, 251	WriteStdin, 272
Arc::PrintF, 256	Arc::SAML2LoginClient, 272
Arc::PrintFBase, 256	findSimpleSAMLInstallation, 272
Arc::Profile, 256	processLogin, 272
Arc::Query, 257	SAML2LoginClient, 272
~Query, 258	Arc::SAML2SSOHTTPClient, 273
execute, 258	approveCSR, 273
get_array, 258	parseDN, 273
get_num_colums, 258	processConsent, 274
get_num_cotums, 258 get_num_rows, 258	processIdP2Confusa, 274
50t_Hum_10ws, 250	processiai 200musa, 274

processIdPLogin, 274	getName, 291
processLogin, 274	getVersion, 291
pushCSR, 274	GREATERTHAN, 290
storeCert, 274	GREATERTHANOREQUAL, 290
Arc::SAMLToken, 275	LESSTHAN, 290
~SAMLToken, 276	LESSTHANOREQUAL, 290
Authenticate, 277	NOTEQUAL, 290
operator bool, 277	operator std::string, 292
SAMLToken, 276	operator<, 292
SAMLVersion, 276	operator<<, 295
Arc::ScalableTime, 277	operator<=, 293
Arc::ScalableTime< int >, 277	operator>, 293
Arc::SecAttr, 278	operator>=, 294
Export, 278	operator(), 292
Import, 279	operator==, 293
operator bool, 279	Software, 290
operator==, 279	toString, 294
Arc::SecAttrFormat, 279	VERSIONTOKENS, 295
Arc::SecAttrValue, 280	Arc::SoftwareRequirement, 295
operator bool, 280	add, 297
operator==, 280	clear, 298
Arc::SecHandlerConfig, 281	empty, 298
Arc::Service, 282	getComparisonOperatorList, 298
AddSecHandler, 284	getSoftwareList, 298
getID, 284	isRequiringAll, 299
_	isResolved, 299
logger, 284	
ProcessSecHandlers, 284	isSatisfied, 299, 300
RegistrationCollector, 284	operator=, 300
sechandlers_, 284	selectSoftware, 301, 302
Service, 284	setRequirement, 302
Arc::ServicePluginArgument, 285	SoftwareRequirement, 296, 297
Arc::SimpleCondition, 285	Arc::Submitter, 306
broadcast, 285	Migrate, 306
lock, 285	Submit, 306
reset, 285	Arc::SubmitterLoader, 307
signal, 286	~SubmitterLoader, 307
signal_nonblock, 286	GetSubmitters, 307
unlock, 286	load, 307
wait, 286	SubmitterLoader, 307
wait_nonblock, 286	Arc::SubmitterPluginArgument, 308
Arc::SimpleCounter, 286	Arc::TargetGenerator, 308
wait, 286	AddIndexServer, 309
Arc::SOAPMessage, 287	AddJob, 309
\sim SOAPMessage, 287	AddService, 309
Attributes, 287	AddTarget, 310
Payload, 287, 288	FoundJobs, 310
SOAPMessage, 287	FoundTargets, 310
Arc::Software, 288	GetTargets, 310
ComparisonOperator, 289	ModifyFoundTargets, 310
ComparisonOperatorEnum, 289	PrintTargetInfo, 311
convert, 291	ServiceCounter, 311
empty, 291	TargetGenerator, 309
EQUAL, 290	Arc::TargetRetriever, 311
getFamily, 291	GetTargets, 312
<u> </u>	5 /

TargetRetriever, 312	LDAPFilter, 325
Arc::TargetRetrieverLoader, 312	ldapfilter, 327
~TargetRetrieverLoader, 313	LDAPScope, 325
GetTargetRetrievers, 313	ldapscope, 327
load, 313	Locations, 325
TargetRetrieverLoader, 313	locations, 327
Arc::TargetRetrieverPluginArgument, 314	MetaDataOption, 325
Arc::ThreadInitializer, 315	MetaDataOptions, 325
Arc::ThreadRegistry, 316	metadataoptions, 328
WaitForExit, 316	operator bool, 325
WaitOrCancel, 316	operator<, 325
Arc::Time, 316	operator<<, 327
GetFormat, 317	operator==, 325
GetTime, 317	Option, 325
operator std::string, 318	Options, 326
operator<, 318	OptionString, 326
operator<=, 318	ParseOptions, 326
operator>, 319	Passwd, 326
operator>=, 319	passwd, 328
operator+, 318	Path, 326
÷	•
operator-, 318	path, 328
operator=, 318	Path2BaseDN, 326
operator==, 319	plainstr, 326
SetFormat, 319	Port, 326
SetTime, 319	port, 328
str, 319	Protocol, 326
Time, 317	protocol, 328
Are::URL, 320	Scope, 322
\sim URL, 322	str, 326
AddLDAPAttribute, 323	URL, 322
AddMetaDataOption, 323	urloptions, 328
AddOption, 323	Username, 327
BaseDN2Path, 323	username, 328
ChangeHost, 323	valid, 328
ChangeLDAPFilter, 323	Arc::URLLocation, 328
ChangeLDAPScope, 323	~URLLocation, 330
ChangePath, 323	fullstr, 330
ChangePort, 323	Name, 330
ChangeProtocol, 323	
•	name, 330
CommonLocOption, 324	str, 330
CommonLocOptions, 324	URLLocation, 329
commonlocoptions, 327	Arc::URLMap, 330
ConnectionURL, 324	Arc::User, 331
FullPath, 324	Arc::UserConfig, 331
fullstr, 324	AddBartender, 335
Host, 324	AddServices, 335, 336
host, 327	ApplyToConfig, 337
HTTPOption, 324	ARCUSERDIRECTORY, 357
HTTPOptions, 324	Bartender, 337
httpoptions, 327	Broker, 338, 339
ip6addr, 327	CACertificatePath, 339
IsSecureProtocol, 324	CACertificatesDirectory, 340
LDAPAttributes, 325	CertificateLifeTime, 340, 341
Idapattributes, 327	CertificatePath, 341
13uputt10ut05, 521	Cordinated till, 571

ClearRejectedServices, 342	From, 365
ClearSelectedServices, 342, 343	header_allocated_, 367
CredentialsFound, 343	MessageID, 365
DEFAULT_BROKER, 357	NewReferenceParameter, 365
DEFAULT_TIMEOUT, 357	operator XMLNode, 366
DEFAULTCONFIG, 357	ReferenceParameter, 366
EXAMPLECONFIG, 358	RelatesTo, 366
GetRejectedServices, 343	RelationshipType, 366
GetSelectedServices, 343	ReplyTo, 366
IdPName, 344	* •
InitializeCredentials, 344	To, 366
JobListFile, 346	WSAHeader, 365
KeyPassword, 346, 347	Arc::WSRF, 367
KeyPath, 347	allocated_, 368
KeySize, 348	operator bool, 368
LoadConfigurationFile, 348	set_namespaces, 368
operator bool, 350	SOAP, 368
OverlayFile, 350, 351	valid_, 368
Password, 351	WSRF, 368
ProxyPath, 352	Arc::WSRFBaseFault, 369
SaveToFile, 352	set_namespaces, 370
SLCS, 353	WSRFBaseFault, 369
StoreDirectory, 353	Arc::WSRFResourceUnavailableFault, 370
SYSCONFIG, 358	Arc::WSRFResourceUnknownFault, 370
SYSCONFIGARCLOC, 358	Arc::WSRP, 370
Timeout, 354	set_namespaces, 372
	WSRP, 372
UserConfig, 334, 335	Arc::WSRPDeleteResourceProperties, 372
UserName, 354, 355	Arc::WSRPDeleteResourcePropertiesRequest, 372
UtilsDirPath, 355	Arc::WSRPDeleteResourcePropertiesRequestFailedFault,
Verbosity, 356	373
VOMSServerPath, 356, 357	Arc::WSRPDeleteResourcePropertiesResponse,
Arc::UsernameToken, 358	373
Authenticate, 360	Arc::WSRPFault, 374
operator bool, 360	WSRPFault, 374
PasswordType, 359	Arc::WSRPGetMultipleResourcePropertiesRequest,
Username, 360	374
UsernameToken, 359	Arc::WSRPGetMultipleResourcePropertiesResponse,
Arc::UserSwitch, 360	375
Arc::VOMSTrustList, 361	Arc::WSRPGetResourcePropertyDocumentRequest,
AddChain, 362	375
AddRegex, 362	Arc::WSRPGetResourcePropertyDocumentResponse,
VOMSTrustList, 361	376
Arc::WSAEndpointReference, 362	Arc::WSRPGetResourcePropertyRequest, 376
~WSAEndpointReference, 363	Arc::WSRPGetResourcePropertyResponse, 376
Address, 363	Arc::WSRPInsertResourceProperties, 377
MetaData, 363	Arc::WSRPInsertResourcePropertiesRequest, 377
operator XMLNode, 363	* *
operator=, 363	Arc::WSRPInsertResourcePropertiesRequestFailedFault,
ReferenceParameters, 364	377
WSAEndpointReference, 363	Arc::WSRPInsertResourcePropertiesResponse, 378
Arc::WSAHeader, 364	Arc::WSRPInvalidModificationFault, 378
Action, 365	Arc::WSRPInvalidResourcePropertyQNameFault,
Check, 365	379
FaultTo, 365	Arc::WSRPModifyResourceProperties, 379

A WODDD D D D	N. 61.11.207
Arc::WSRPPutResourcePropertyDocumentRequest,	NewChild, 395
380	operator bool, 395
Arc::WSRPPutResourcePropertyDocumentResponse	
380	operator++, 396
Arc::WSRPQueryResourcePropertiesRequest, 380	operator, 396
Arc::WSRPQueryResourcePropertiesResponse,	operator=, 396
381	operator==, 397
Arc::WSRPResourcePropertyChangeFailure, 381	operator[], 397
WSRPResourcePropertyChangeFailure, 382	Parent, 397
Arc::WSRPSetResourcePropertiesRequest, 382	Path, 398
Arc::WSRPSetResourcePropertiesResponse, 382	Prefix, 398
Arc:: WSRPS et Resource Property Request Failed Fault,	ReadFromFile, 398
383	ReadFromStream, 398
Arc::WSRPUnableToModifyResourcePropertyFault,	Replace, 398
383	Sama 308
Arc::WSRPUnableToPutResourcePropertyDocument	Fault, Save To File 398
384	SaveToStream, 398
Arc::WSRPUpdateResourceProperties, 384	Set, 398
Arc::WSRPUpdateResourcePropertiesRequest, 384	g: 200
Arc::WSRPUpdateResourcePropertiesRequestFailed	Size, 398 Fault, Same 200
385	
Arc::WSRPUpdateResourcePropertiesResponse,	Validate, 399
385	XMLNode, 391, 392
Arc::X509Token, 387	XPathLookup, 399
~X509Token, 388	Arc::XMLNodeContainer, 400
Authenticate, 388	Add, 401
operator bool, 388	AddNew, 401
X509Token, 387	Nodes, 401
X509TokenType, 387	operator=, 401
7.2	operator[], 401
Arc::XmlContainer, 388	Size, 401
Arc::XmlDatabase, 389	XMLNodeContainer, 401
Arc::XMLNode, 389	Arc::XMLSecNode, 402
~XMLNode, 392	AddSignatureTemplate, 402
Attribute, 392	DecryptNode, 403
AttributesSize, 392	EncryptNode, 403
Child, 392	SignNode, 403
Destroy, 392	VerifyNode, 403
Exchange, 393	
FullName, 393	XMLSecNode, 402
Get, 393	Arc::XRSLParser, 404
GetDoc, 393	ArcCredential, 43
GetRoot, 393	CERT_TYPE_CA, 44
GetXML, 393	CERT_TYPE_EEC, 44
is_owner_, 400	CERT_TYPE_GSI_2_LIMITED_PROXY, 44
is_temporary_, 400	CERT_TYPE_GSI_2_PROXY, 44
MatchXMLName, 399	CERT_TYPE_GSI_3_IMPERSONATION
MatchXMLNamespace, 399, 400	PROXY, 44
Move, 393	CERT_TYPE_GSI_3_INDEPENDENT
Name, 394	PROXY, 44
Namespace, 394	CERT_TYPE_GSI_3_LIMITED_PROXY, 44
NamespacePrefix, 394	CERT_TYPE_GSI_3_RESTRICTED
Namespaces, 394	PROXY, 44
New, 394	CERT_TYPE_RFC_ANYLANGUAGE
NewAttribute, 394, 395	PROXY, 44
1.0.1.1.0010000000000000000000000000000	

CERT TURE REG II DEPROMETEL	
CERT_TYPE_RFC_IMPERSONATION	combine, 76
PROXY, 44	getalgId, 76
CERT_TYPE_RFC_INDEPENDENT	ArcSec::DateAttribute, 133
PROXY, 44	encode, 133
CERT_TYPE_RFC_LIMITED_PROXY, 44	equal, 133
CERT_TYPE_RFC_RESTRICTED_PROXY,	getId, 133
44	getType, 133
certType, 44	ArcSec::DateTimeAttribute, 134
ArcCredential::ACACI, 45	encode, 134
ArcCredential::ACATTHOLDER, 45	equal, 134
ArcCredential::ACATTR, 45	getId, 134
ArcCredential::ACATTRIBUTE, 45	getType, 134
ArcCredential::ACC, 45	ArcSec::DenyOverridesCombiningAlg, 142
ArcCredential::ACCERTS, 46	combine, 143
ArcCredential::ACDIGEST, 46	getalgId, 143
ArcCredential::ACFORM, 46	ArcSec::DurationAttribute, 145
ArcCredential::ACFULLATTRIBUTES, 46	encode, 145
ArcCredential::ACHOLDER, 46	equal, 146
ArcCredential::ACIETFATTR, 46	getId, 146
ArcCredential::ACINFO, 46	getType, 146
ArcCredential::ACIS, 47	ArcSec::EqualFunction, 146
ArcCredential::ACSEQ, 47	evaluate, 147
ArcCredential::ACTARGET, 47	getFunctionName, 147
ArcCredential::ACTARGETS, 47	ArcSec::EvalResult, 147
ArcCredential::ACVAL, 47	ArcSec::EvaluationCtx, 147
ArcCredential::cert_verify_context, 66	EvaluationCtx, 148
ArcCredential::PROXYCERTINFO_st, 257	ArcSec::Evaluator, 148
ArcCredential::PROXYPOLICY_st, 257	addPolicy, 149
ArcSec::AlgFactory, 48	evaluate, 149, 150
createAlg, 48	getAlgFactory, 150
ArcSec::AnyURIAttribute, 49	getAttrFactory, 150
encode, 49	getFnFactory, 150
equal, 49	getName, 150
getId, 49	setCombiningAlg, 150
getType, 49	ArcSec::EvaluatorContext, 151
ArcSec::ArcPeriod, 51	operator AlgFactory *, 151
ArcSec::Attr, 52	operator AttributeFactory *, 151
ArcSec::AttributeFactory, 52	operator FnFactory *, 151
ArcSec::AttributeProxy, 55	ArcSec::EvaluatorLoader, 151
getAttribute, 56	getEvaluator, 152
ArcSec::AttributeValue, 56	getPolicy, 152
encode, 57	getRequest, 152
equal, 58	ArcSec::FnFactory, 164
getId, 58	createFn, 164
getType, 58	ArcSec::Function, 165
ArcSec::Attrs, 58	evaluate, 165
ArcSec::AuthzRequest, 59	ArcSec::GenericAttribute, 165
ArcSec::AuthzRequestSection, 59	encode, 166
ArcSec::BooleanAttribute, 61	equal, 166
encode, 62	getId, 166
equal, 62	getType, 166
getId, 62	ArcSec::InRangeFunction, 177
getType, 62	evaluate, 177
ArcSec::CombiningAlg, 75	ArcSec::MatchFunction, 199

evaluate, 199	ArcSec::SourceFile, 303
getFunctionName, 200	ArcSec::SourceURL, 304
ArcSec::OrderedCombiningAlg, 226	ArcSec::StringAttribute, 305
ArcSec::PDP, 240	encode, 305
ArcSec::PDPConfigContext, 241	equal, 305
ArcSec::PDPPluginArgument, 241	getId, 305
ArcSec::PeriodAttribute, 244	getType, 305
encode, 244	ArcSec::TimeAttribute, 319
equal, 244	encode, 320
getId, 244	equal, 320
getType, 244	getId, 320
ArcSec::PermitOverridesCombiningAlg, 245	getType, 320
combine, 245	ArcSec::X500NameAttribute, 386
getalgId, 245	encode, 386
ArcSec::Policy, 252	equal, 386
addPolicy, 253	getId, 386
eval, 253	getType, 386
getEffect, 253	ARCUSERDIRECTORY
getEvalName, 253	Arc::UserConfig, 357
getEvalResult, 253	Assign
getName, 253	Arc::InformationContainer, 173
make_policy, 254	AssignStderr
Policy, 253	Arc::Run, 270
setEvalResult, 254	AssignStdin
setEvaluatorContext, 254	Arc::Run, 270
ArcSec::PolicyParser, 254	AssignStdout
parsePolicy, 255	Arc::Run, 270
ArcSec::PolicyStore, 255	AssignWorkingDirectory
PolicyStore, 255	Arc::Run, 270
ArcSec::PolicyStore::PolicyElement, 254	AttrConstIter
ArcSec::Request, 261	Arc, 36
addRequestItem, 262	Attribute
getEvalName, 262	Arc::XMLNode, 392
	AttributeIterator
getName, 262	
getRequestItems, 262	Arc::AttributeIterator, 53
make_request, 262	Attributes
Request, 262	Arc::Message, 209
setAttributeFactory, 262	Arc::SOAPMessage, 287
setRequestItems, 263	attributes_
ArcSec::RequestAttribute, 263	Arc::MessageAttributes, 213
duplicate, 263	AttributesSize
RequestAttribute, 263	Arc::XMLNode, 392
ArcSec::RequestItem, 264	AttrIter
RequestItem, 264	Arc, 36
ArcSec::RequestTuple, 264	AttrMap
ArcSec::Response, 265	Arc, 36
ArcSec::ResponseItem, 265	Auth
ArcSec::ResponseList, 265	Arc::Message, 209
ArcSec::SecHandler, 281	AuthContext
ArcSec::SecHandlerConfig, 281	Arc::Message, 210
ArcSec::SecHandlerPluginArgument, 282	Authenticate
ArcSec::Security, 282	Arc::SAMLToken, 277
ArcSec::Source, 302	Arc::UsernameToken, 360
Source, 303	Arc::X509Token, 388

Backup ArcCredential, 44 Arc::DelegationConsumer, 136 CERT_TYPE_RFC_IMPERSONATION_PROXY ArcCredential, 44 Bartender CERT_TYPE_RFC_INDEPENDENT_PROXY Arc::UserConfig, 337 BaseDN2Path ArcCredential, 44 Arc::URL, 323 CERT_TYPE_RFC_LIMITED_PROXY broadcast ArcCredential, 44 CERT_TYPE_RFC_RESTRICTED_PROXY Arc::SimpleCondition, 285 Broker ArcCredential, 44 Arc::UserConfig, 338, 339 CertificateLifeTime BrokerLoader Arc::UserConfig, 340, 341 Arc::BrokerLoader, 64 CertificatePath Buffer Arc::UserConfig, 341 Arc::PayloadRaw, 229 certType Arc::PayloadRawInterface, 231 ArcCredential, 44 buffer size changeExcess Arc::DataBuffer, 102 Arc::Counter, 84 Arc::IntraProcessCounter, 179 BufferPos Arc::PayloadRaw, 229 ChangeHost Arc::URL, 323 Arc::PayloadRawInterface, 231 BufferSize ChangeLDAPFilter Arc::URL, 323 Arc::PayloadRaw, 229 Arc::PayloadRawInterface, 231 ChangeLDAPScope **BUSY ERROR** Arc::URL, 323 changeLimit Arc. 37 Arc::Counter, 84 CACertificatePath Arc::IntraProcessCounter, 179 Arc::UserConfig, 339 ChangePath CACertificatesDirectory Arc::URL, 323 Arc::UserConfig, 340 ChangePort CacheError Arc::URL, 323 Arc::DataStatus, 132 ChangeProtocol cancel Arc::URL, 323 Arc::Counter, 84 Check Arc::CounterTicket, 89 Arc::DataPoint, 111 Arc::IntraProcessCounter, 179 Arc::DataPointIndex, 123 CERT_TYPE_CA Arc::WSAHeader, 365 ArcCredential, 44 CheckCreated CERT_TYPE_EEC Arc::FileCache, 159 ArcCredential, 44 CheckDN CERT_TYPE_GSI_2_LIMITED_PROXY Arc::FileCache, 159 CheckError ArcCredential, 44 CERT_TYPE_GSI_2_PROXY Arc::DataStatus, 132 ArcCredential, 44 checks CERT_TYPE_GSI_3_IMPERSONATION_-Arc::DataMover, 107 **PROXY** checksum_object ArcCredential, 44 Arc::DataBuffer, 102 CERT_TYPE_GSI_3_INDEPENDENT_PROXY checksum valid ArcCredential, 44 Arc::DataBuffer, 102 CERT_TYPE_GSI_3_LIMITED_PROXY CheckValid Arc::FileCache, 160 ArcCredential, 44 CERT_TYPE_GSI_3_RESTRICTED_PROXY Child ArcCredential, 44 Arc::XMLNode, 392 CERT_TYPE_RFC_ANYLANGUAGE_PROXY **CIStringValue**

Arc::CIStringValue, 68 Arc::URL, 324 clear Content Arc::SoftwareRequirement, 298 Arc::PayloadRaw, 229 ClearRejectedServices Arc::PayloadRawInterface, 232 Arc::UserConfig, 342 ContentFromPayload ClearSelectedServices Arc, 37 Arc::UserConfig, 342, 343 Context ClientHTTPwithSAML2SSO Arc::Message, 210 Arc::ClientHTTPwithSAML2SSO, 70 context lock Arc::DelegationContainerSOAP, 139 ClientSOAP Arc::ClientSOAP, 72 convert ClientSOAPwithSAML2SSO Arc::Software, 291 Arc::ClientSOAPwithSAML2SSO, 73 Copy ClientX509Delegation Arc::FileCache, 160 Arc::ClientX509Delegation, 74 count close Arc::MessageAttributes, 212 Arc::Database, 99 Counter Arc::MySQLDatabase, 220 Arc::Counter, 83 CloseStderr CounterTicket Arc::Run, 270 Arc::CounterTicket, 89 CloseStdin createAlg Arc::Run, 270 ArcSec::AlgFactory, 48 CloseStdout createCertRequest Arc::Run, 270 Arc::ConfusaCertHandler, 79 combine createDelegation ArcSec::CombiningAlg, 76 Arc::ClientX509Delegation, 75 ArcSec::DenyOverridesCombiningAlg, 143 createFn ArcSec::PermitOverridesCombiningAlg, 245 ArcSec::FnFactory, 164 CommonLocOption CreateThreadFunction Arc::URL, 324 Arc. 37 CommonLocOptions createVOMSAC Arc::URL, 324 Arc. 37 commonlocoptions Credential Arc::URL, 327 Arc::Credential, 91, 92 CompareLocationMetadata CredentialError Arc::DataPoint, 112 Arc::CredentialError, 98 Arc::DataPointDirect, 118 CredentialLogger Arc::DataPointIndex, 124 Arc, 43 CompareMeta CredentialsExpiredError Arc::DataStatus, 132 Arc::DataPoint, 112 ComparisonOperator CredentialsFound Arc::Software, 289 Arc::UserConfig, 343 ComparisonOperatorEnum current Arc::Software, 289 Arc::AttributeIterator, 55 ComputingShareName CurrentLocationMetadata Arc::ExecutionTarget, 155 Arc::DataPoint, 112 Config Arc::DataPointDirect, 119 Arc::Config, 77 Arc::DataPointIndex, 124 ConfusaCertHandler Arc::ConfusaCertHandler, 79 Database Arc::Database, 99 connect Arc::Database, 99 DataBuffer Arc::MySQLDatabase, 220 Arc::DataBuffer, 101 ConnectionURL **DataPoint**

A . D . A	
Arc::DataPoint, 111	ArcSec::DateAttribute, 133
DataPointAccessLatency	ArcSec::DateTimeAttribute, 134
Arc::DataPoint, 111	ArcSec::DurationAttribute, 145
DataSpeed	ArcSec::GenericAttribute, 166
Arc::DataSpeed, 128	ArcSec::PeriodAttribute, 244
DataStatusType	ArcSec::StringAttribute, 305
Arc::DataStatus, 131	ArcSec::TimeAttribute, 320
DecryptNode	ArcSec::X500NameAttribute, 386
Arc::XMLSecNode, 403	EncryptNode
DEFAULT_BROKER	Arc::XMLSecNode, 403
Arc::UserConfig, 357	end_
DEFAULT_TIMEOUT	Arc::AttributeIterator, 55
Arc::UserConfig, 357	eof_read
DEFAULTCONFIG	Arc::DataBuffer, 102
Arc::UserConfig, 357	eof_write
Delegate	Arc::DataBuffer, 103
Arc::DelegationProvider, 140	EQUAL
DelegateCredentialsInit	Arc::Software, 290
Arc::DelegationConsumerSOAP, 137	equal
Arc::DelegationContainerSOAP, 139	Arc::CIStringValue, 68
Arc::DelegationProviderSOAP, 142	ArcSec::AnyURIAttribute, 49
DelegatedToken	ArcSec::AttributeValue, 58
Arc::DelegationConsumerSOAP, 137	ArcSec::BooleanAttribute, 62
Arc::DelegationContainerSOAP, 139	ArcSec::DateAttribute, 133
Arc::DelegationProviderSOAP, 142	ArcSec::DateTimeAttribute, 134
DelegationConsumer	ArcSec::DurationAttribute, 146
Arc::DelegationConsumer, 136	ArcSec::GenericAttribute, 166
DelegationConsumerSOAP	ArcSec::PeriodAttribute, 244
Arc::DelegationConsumerSOAP, 137	ArcSec::StringAttribute, 305
DelegationProvider	ArcSec::TimeAttribute, 320
Arc::DelegationProvider, 140	ArcSec::X500NameAttribute, 386
DelegationProviderSOAP	error
Arc::DelegationProviderSOAP, 141	Arc::DataBuffer, 103
DeleteError	error read
Arc::DataStatus, 132	Arc::DataBuffer, 103
Destroy	error_write
	Arc::DataBuffer, 103
Arc::XMLNode, 392	eval
destroy_doc Arc::ConfusaParserUtils, 79	ArcSec::Policy, 253
doc	evaluate
	ArcSec::EqualFunction, 147
Arc::InformationContainer, 174	ArcSec::Evaluator, 149, 150
duplicate	ArcSec::Evaluator, 149, 130 ArcSec::Function, 165
ArcSec::RequestAttribute, 263	
ametri	ArcSec::InRangeFunction, 177
empty 201	ArcSec::MatchFunction, 199
Arc::Software, 291	evaluate_path
Arc::SoftwareRequirement, 298	Arc::ConfusaParserUtils, 79
enable_ssl	EvaluationCtx
Arc::Database, 99	ArcSec::EvaluationCtx, 148
Arc::MySQLDatabase, 220	EXAMPLECONFIG
encode	Arc::UserConfig, 358
ArcSec::AnyURIAttribute, 49	Exchange
ArcSec::AttributeValue, 57	Arc::XMLNode, 393
ArcSec::BooleanAttribute, 62	execute

Arc::MySQLQuery, 222	Arc::XMLNode, 393
Arc::Query, 258	FullPath
ExecutionTarget	Arc::URL, 324
Arc::ExecutionTarget, 153, 154	fullstr
Export	Arc::URL, 324
Arc::MessageAuth, 214	Arc::URLLocation, 330
Arc::MultiSecAttr, 219	
Arc::SecAttr, 278	Generate
extend	Arc::DelegationConsumer, 136
Arc::Counter, 84	GenerateEECRequest
Arc::CounterTicket, 89	Arc::Credential, 93
Arc::IntraProcessCounter, 180	GenerateRequest
extract_body_information	Arc::Credential, 93
Arc::ConfusaParserUtils, 80	GENERIC_ERROR
	Arc, 36
factory_	Get
Arc::Loader, 190	Arc::InfoCacheInterface, 169
FaultTo	Arc::InformationContainer, 173
Arc::WSAHeader, 365	Arc::InformationInterface, 175
File	Arc::PayloadStream, 235
Arc::FileCache, 160	Arc::PayloadStreamInterface, 238
FileCache	Arc::XMLNode, 393
Arc::FileCache, 158, 159	
	get
FileCacheHash, 162	Arc::MessageAttributes, 212
getHash, 162	get_array
maxLength, 162	Arc::MySQLQuery, 222
FileOpen	Arc::Query, 258
Arc, 38	get_cert_str
FillJobStore	Arc, 38
Arc::JobController, 184	get_doc
Filter	Arc::ConfusaParserUtils, 80
Arc::InfoFilter, 169	get_factory
Arc::MessageAuth, 214	Arc::PluginArgument, 249
final_xmlsec	get_key_from_certfile
Arc, 38	Arc, 38
find	get_key_from_certstr
Arc::ModuleManager, 218	Arc, 38
findLocation	get_key_from_keyfile
Arc::ModuleManager, 218	Arc, 38
findSimpleSAMLInstallation	get_key_from_keystr
Arc::SAML2LoginClient, 272	Arc, 38
for_read	get_module
Arc::DataBuffer, 103	Arc::PluginArgument, 250
for_write	get_node
Arc::DataBuffer, 103, 104	Arc, 38
force_to_meta	get_num_colums
Arc::DataMover, 107	Arc::MySQLQuery, 222
FoundJobs	Arc::Query, 258
Arc::TargetGenerator, 310	get_num_rows
FoundTargets	Arc::MySQLQuery, 222
Arc::TargetGenerator, 310	Arc::Query, 258
From	get_plugin_instance
Arc::WSAHeader, 365	Arc, 36
FullName	get_property

Arc, 38	getEvaluator
get_row	ArcSec::EvaluatorLoader, 152
Arc::MySQLQuery, 222	getExcess
Arc::Query, 258, 259	Arc::Counter, 85
get_row_field	Arc::IntraProcessCounter, 180
Arc::MySQLQuery, 223	getExpirationReminder
Arc::Query, 259	Arc::Counter, 85
getAlgFactory	getExpiryTime
ArcSec::Evaluator, 150	Arc::Counter, 86
getalgId	Arc::ExpirationReminder, 156
ArcSec::CombiningAlg, 76	getExplanation
ArcSec::DenyOverridesCombiningAlg, 143	Arc::MCC_Status, 203
ArcSec::PermitOverridesCombiningAlg, 245	GetFailureReason
getAll	Arc::DataPoint, 112
Arc::MessageAttributes, 212	getFamily
getAttrFactory	Arc::Software, 291
ArcSec::Evaluator, 150	getFileName
getAttribute	Arc::Config, 78
ArcSec::AttributeProxy, 56	getFnFactory
GetBestTarget	ArcSec::Evaluator, 150
Arc::Broker, 63	GetFormat
GetBrokers	Arc::Time, 317
Arc::BrokerLoader, 65	getFormat
GetCert	Arc::Credential, 94
Arc::Credential, 93	getFunctionName
GetCertNumofChain	ArcSec::EqualFunction, 147
Arc::Credential, 93	ArcSec::MatchFunction, 200
GetCertReq	getHash
Arc::Credential, 94	FileCacheHash, 162
getCertRequestB64	getID
Arc::ConfusaCertHandler, 79	Arc::Service, 284
getComparisonOperatorList	getId
Arc::SoftwareRequirement, 298	ArcSec::AnyURIAttribute, 49
getCounterTicket	ArcSec::AttributeValue, 58
Arc::Counter, 85	ArcSec::BooleanAttribute, 62
GetCreated	ArcSec::DateAttribute, 133
Arc::FileCache, 160	ArcSec::DateTimeAttribute, 134
getCurrentTime	ArcSec::DurationAttribute, 146
Arc::Counter, 85	ArcSec::GenericAttribute, 166
GetDN	ArcSec::PeriodAttribute, 244
Arc::Credential, 94	ArcSec::StringAttribute, 305
GetDoc	ArcSec::TimeAttribute, 320
Arc::XMLNode, 393	ArcSec::X500NameAttribute, 386
getEffect	GetIdentityName
ArcSec::Policy, 253	Arc::Credential, 94
GetEndTime	GetJobControllers
Arc::Credential, 94	Arc::JobControllerLoader, 186
GetEntry	Arc::JobSupervisor, 188
Arc::ClientSOAP, 72	getKind
getEvalName	Arc::MCC_Status, 203
ArcSec::Policy, 253	getLevel
ArcSec::Request, 262	Arc::LogMessage, 197
getEvalResult	GetLifeTime
ArcSec::Policy, 253	Arc::Credential, 94
Alester oney, 255	AICCituthidi, 94

Arc::Time, 317 getLimit GetType Arc::Counter, 86 Arc::IntraProcessCounter, 180 Arc::Credential, 94 getName getType Arc::Software, 291 ArcSec::AnyURIAttribute, 49 ArcSec::Evaluator, 150 ArcSec::AttributeValue, 58 ArcSec::Policy, 253 ArcSec::BooleanAttribute, 62 ArcSec::Request, 262 ArcSec::DateAttribute, 133 getOrigin ArcSec::DateTimeAttribute, 134 Arc::MCC_Status, 203 ArcSec::DurationAttribute, 146 GetOverlay ArcSec::GenericAttribute, 166 Arc::BaseConfig, 61 ArcSec::PeriodAttribute, 244 GetPeriod ArcSec::StringAttribute, 305 Arc::Period, 242 ArcSec::TimeAttribute, 320 GetPlugins ArcSec::X500NameAttribute, 386 Arc::ArcLocation, 51 GetValid getPolicy Arc::FileCache, 160 ArcSec::EvaluatorLoader, 152 getValue GetPrivKey Arc::Counter, 86 Arc::Credential, 94 Arc::IntraProcessCounter, 180 GetProxyPolicy **GetVerification** Arc::Credential, 94 Arc::Credential, 95 GetPubKey getVersion Arc::Credential, 94 Arc::Software, 291 **GetRejectedServices** GetXML Arc::UserConfig, 343 Arc::XMLNode, 393 getRequest **GREATERTHAN** ArcSec::EvaluatorLoader, 152 Arc::Software, 290 getRequestItems **GREATERTHANOREOUAL** ArcSec::Request, 262 Arc::Software, 290 getReservationID **GUID** Arc::ExpirationReminder, 156 Arc, 39 GetRoot Arc::XMLNode, 393 handle getRootLogger Arc::PayloadStream, 237 Arc::Logger, 194 handle_redirect_step GetSelectedServices Arc::ConfusaParserUtils, 80 Arc::UserConfig, 343 hasMore getSoftwareList Arc::AttributeIterator, 54 Arc::SoftwareRequirement, 298 header_allocated_ GetStartTime Arc::WSAHeader, 367 Arc::Credential, 94 hold GetSubmitter Arc::DataSpeed, 129 Arc::ExecutionTarget, 154 Host GetSubmitters Arc::URL, 324 Arc::SubmitterLoader, 307 host GetTargetRetrievers Arc::URL, 327 Arc::TargetRetrieverLoader, 313 GetTargets **HTTPOption** Arc::URL, 324 Arc::TargetGenerator, 310 Arc::TargetRetriever, 312 **HTTPOptions** getThreshold Arc::URL, 324 Arc::Logger, 194 httpoptions GetTime Arc::URL, 327

ID Arc::MySQLDatabase, 221 Arc::DelegationConsumer, 136 isOk Arc::DelegationProviderSOAP, 142 Arc::MCC_Status, 204 **IdPName** IsReadingError Arc::UserConfig, 344 Arc::DataStatus, 132 **IDType** isRequiringAll Arc::Counter, 83 Arc::SoftwareRequirement, 299 **Import** isResolved Arc::SecAttr, 279 Arc::SoftwareRequirement, 299 InconsistentMetadataError isSatisfied Arc::DataStatus, 132 Arc::SoftwareRequirement, 299, 300 InfoCache **IsSecureProtocol** Arc::InfoCache, 168 Arc::URL, 324 InfoFilter istr Arc::InfoFilter, 169 Arc::Period, 242 InfoRegisters istring_to_level Arc::InfoRegisters, 171 Arc, 39 InformationContainer isValid Arc::InformationContainer, 173 Arc::CounterTicket, 89 InformationInterface **IsWritingError** Arc::InformationInterface, 174 Arc::DataStatus, 132 InformationRequest Arc::InformationRequest, 175, 176 Job InformationResponse Arc::Job, 183 Arc::InformationResponse, 176 JobControllerLoader Init Arc::JobControllerLoader, 186 Arc::ArcLocation, 51 JobListFile init_xmlsec Arc::UserConfig, 346 Arc, 39 **JobSupervisor** InitializeCredentials Arc::JobSupervisor, 188 Arc::UserConfig, 344 InitProxyCertInfo KeepStderr Arc::Credential, 95 Arc::Run, 270 InquireRequest KeepStdin Arc::Credential, 95 Arc::Run, 270 Insert KeepStdout Arc::PayloadRaw, 229 Arc::Run, 270 Arc::PayloadRawInterface, 232 key IntraProcessCounter Arc::AttributeIterator, 54 Arc::IntraProcessCounter, 179 KevPassword ip6addr Arc::UserConfig, 346, 347 Arc::URL, 327 **KeyPath** is notwritten Arc::UserConfig, 347 Arc::DataBuffer, 104 KeySize is_owner_ Arc::UserConfig, 348 Arc::XMLNode, 400 Kill is_read Arc::Run, 271 Arc::DataBuffer, 104 **LDAPAttributes** is_temporary_ Arc::XMLNode, 400 Arc::URL, 325 is_written **Idapattributes** Arc::DataBuffer, 105 Arc::URL, 327 isconnected **LDAPFilter** Arc::Database, 100 Arc::URL, 325

ldapfilter	lock_
Arc::URL, 327	Arc::InformationInterface, 175
LDAPScope	log
Arc::URL, 325	Arc::LogFile, 192
ldapscope	Arc::LogStream, 198
Arc::URL, 327	LogDestination
length	Arc::LogDestination, 190, 191
Arc::PayloadRawBuf, 230	LogError
LESSTHAN	Arc::Credential, 95
Arc::Software, 290	Arc::DelegationConsumer, 136
LESSTHANOREQUAL	LogFile
Arc::Software, 290	Arc::LogFile, 191, 192
Limit	Logger
Arc::PayloadStream, 235	Arc::Logger, 194
Arc::PayloadStreamInterface, 238	Arc::LogMessage, 197
Link	logger
Arc::FileCache, 160	Arc::MCC, 202
ListError	Arc::Plexer, 247
Arc::DataStatus, 132	Arc::Service, 284
ListFiles	LogLevel
Arc::DataPoint, 112	Arc, 36
Load	LogMessage
Arc::ClientSOAP, 72	Arc::LogMessage, 196
load	LogStream
Arc::BrokerLoader, 65	Arc::LogStream, 198
Arc::JobControllerLoader, 186	Then Logotteum, 190
Arc::ModuleManager, 218	make_policy
Arc::PluginsFactory, 251	ArcSec::Policy, 254
Arc::SubmitterLoader, 307	make_request
Arc::TargetRetrieverLoader, 313	ArcSec::Request, 262
load_key_from_certfile	MakeConfig
Arc, 39	Arc::BaseConfig, 61
load_key_from_certstr	Arc::MCCConfig, 205
Arc, 39	makePersistent
load_key_from_keyfile	Arc::ModuleManager, 218
Arc, 39	match
load_trusted_cert_file	Arc::RegularExpression, 261
Arc, 39	MatchXMLName
load_trusted_cert_str	Arc, 40
Arc, 40	Arc::XMLNode, 399
load_trusted_certs	MatchXMLNamespace
Arc, 40	Arc, 40
LoadConfigurationFile	Arc::XMLNode, 399, 400
Arc::UserConfig, 348	max_duration_
Loader	Arc::DelegationContainerSOAP, 139
Arc::Loader, 189	max_size_
LocationAlreadyExistsError	Arc::DelegationContainerSOAP, 139
Arc::DataStatus, 132	max_usage_
Locations	Arc::DelegationContainerSOAP, 139
Arc::URL, 325	MaxDiskSpace
locations	Arc::ExecutionTarget, 155
Arc::URL, 327	maxLength
lock	FileCacheHash, 162
Arc::SimpleCondition, 285	MaxMainMemory

Arc::ExecutionTarget, 155 Arc::WSAHeader, 365 MaxVirtualMemory Next Arc::ExecutionTarget, 155 Arc::MCC, 201 Arc::Plexer, 247 MCC Arc::MCC, 201 next MCC Status Arc::MCC, 202 Arc::MCC_Status, 203 NextLocation **MCCLoader** Arc::DataPoint, 112 Arc::MCCLoader, 207 Arc::DataPointDirect, 119 Arc::DataPointIndex, 124 Message Arc::Message, 209 Nodes MessageAttributes Arc::XMLNodeContainer, 401 Arc::AttributeIterator, 55 NoLocationError Arc::MessageAttributes, 211 Arc::DataStatus, 132 NOTEQUAL MessageID Arc::WSAHeader, 365 Arc::Software, 290 MetaData NotInitializedError Arc::WSAEndpointReference, 363 Arc::DataStatus, 132 MetaDataOption NotSupportedForDirectDataPointsError Arc::URL, 325 Arc::DataStatus, 132 MetaDataOptions Arc::URL, 325 **OAuthConsumer** Arc::OAuthConsumer, 224 metadataoptions OpenSSLInit Arc::URL, 328 Arc, 40 Migrate OperatingSystem Arc::JobController, 184 Arc::ExecutionTarget, 155 Arc::Submitter, 306 operator AlgFactory * ModifyFoundTargets ArcSec::EvaluatorContext, 151 Arc::TargetGenerator, 310 operator AttributeFactory * ModuleManager ArcSec::EvaluatorContext, 151 Arc::ModuleManager, 218 operator bool Move Arc::CIStringValue, 68 Arc::XMLNode, 393 Arc::FileCache, 161 msg Arc::MCC_Status, 204 Arc::Logger, 195 Arc::MultiSecAttr, 219 Name Arc::PathIterator, 227 Arc::URLLocation, 330 Arc::PayloadStream, 235 Arc::XMLNode, 394 Arc::PayloadStreamInterface, 238 Arc::Run, 271 name Arc::URLLocation, 330 Arc::SAMLToken, 277 Namespace Arc::SecAttr, 279 Arc::XMLNode, 394 Arc::SecAttrValue, 280 NamespacePrefix Arc::URL, 325 Arc::XMLNode, 394 Arc::UserConfig, 350 Arc::UsernameToken, 360 Namespaces Arc::XMLNode, 394 Arc::WSRF, 368 New Arc::X509Token, 388 Arc::XMLNode, 394 Arc::XMLNode, 395 NewAttribute operator FnFactory * ArcSec::EvaluatorContext, 151 Arc::XMLNode, 394, 395 NewChild operator PluginsFactory * Arc::XMLNode, 395 Arc::ChainContext, 66 NewReferenceParameter operator std::string

Arc::MCC_Status, 204	Arc::Time, 318
Arc::Period, 242	Arc::WSAEndpointReference, 363
Arc::Software, 292	Arc::XMLNode, 396
Arc::Time, 318	Arc::XMLNodeContainer, 401
Arc::XMLNode, 395	operator==
operator XMLNode	Arc::FileCache, 161
Arc::WSAEndpointReference, 363	Arc::Period, 243
Arc::WSAHeader, 366	Arc::SecAttr, 279
operator<	Arc::SecAttrValue, 280
Arc::ExpirationReminder, 157	Arc::Software, 293
Arc::Period, 243	Arc::Time, 319
Arc::Software, 292	Arc::URL, 325
Arc::Time, 318	Arc::XMLNode, 397
Arc::URL, 325	operator[]
operator<<	Arc::MCCLoader, 207
Arc, 40, 41	Arc::PayloadRaw, 229
Arc::LogMessage, 197	Arc::PayloadRawInterface, 232
Arc::Software, 295	Arc::XMLNode, 397
Arc::URL, 327	Arc::XMLNodeContainer, 401
operator<=	Option
Arc::Period, 243	Arc::URL, 325
Arc::Software, 293	Options
Arc::Time, 318	Arc::URL, 326
operator>	OptionString
Arc::Period, 243	Arc::URL, 326
Arc::Software, 293	OutputCertificate
Arc::Time, 319	Arc::Credential, 95
operator>=	OutputCertificateChain
Arc::Period, 243	Arc::Credential, 95
Arc::Software, 294	OutputPrivatekey
Arc::Time, 319	Arc::Credential, 96
operator*	OutputPublickey
Arc::AttributeIterator, 54	Arc::Credential, 96
Arc::PathIterator, 227	OverlayFile
operator()	Arc::UserConfig, 350, 351
Arc::Software, 292	
operator+	Parent
Arc::Time, 318	Arc::XMLNode, 397
operator++	parse
Arc::AttributeIterator, 54	Arc::Config, 78
Arc::PathIterator, 227	parseDN
Arc::XMLNode, 396	Arc::OAuthConsumer, 224
operator-	Arc::SAML2SSOHTTPClient, 273
Arc::Time, 318	ParseOptions
operator->	Arc::URL, 326
Arc::AttributeIterator, 55	parsePolicy
operator	ArcSec::PolicyParser, 255
Arc::PathIterator, 227	parseVOMSAC
Arc::XMLNode, 396	Arc, 41, 42
operator=	PARSING_ERROR
Arc::ExecutionTarget, 154	Arc, 37
Arc::Message, 210	Passive
Arc::Period, 243	Arc::DataPoint, 113
Arc::SoftwareRequirement, 300	Arc::DataPointDirect, 119

A D . D . J 1 104	D D
Arc::DataPointIndex, 124	PostRegister
passphrase_callback	Arc::DataPoint, 113
Arc, 42	Arc::DataPointDirect, 119
Passwd	PostRegisterError
Arc::URL, 326	Arc::DataStatus, 132
passwd, 226	PreFilterTargets
Arc::URL, 328	Arc::Broker, 63
Password	Prefix
Arc::UserConfig, 351	Arc::XMLNode, 398
PasswordType	PreRegister
Arc::UsernameToken, 359	Arc::DataPoint, 113
Path	Arc::DataPointDirect, 119
Arc::URL, 326	PreRegisterError
Arc::XMLNode, 398	Arc::DataStatus, 132
path	PreUnregister
Arc::URL, 328	Arc::DataPoint, 113
Path2BaseDN	Arc::DataPointDirect, 120
Arc::URL, 326	Print
PathIterator	Arc::ExecutionTarget, 154
Arc::PathIterator, 227	Arc::Job, 183
Payload	print
Arc::Message, 210	Arc::Config, 78
Arc::SOAPMessage, 287, 288	PrintJobStatus
PayloadRaw	Arc::JobController, 184
Arc::PayloadRaw, 228	PrintTargetInfo
PayloadSOAP	Arc::TargetGenerator, 311
Arc::PayloadSOAP, 233	process
PayloadStream	Arc::ClientHTTPwithSAML2SSO, 70
Arc::PayloadStream, 234	Arc::ClientSOAP, 72
PayloadWSRF	Arc::ClientSOAPwithSAML2SSO, 73
Arc::PayloadWSRF, 240	Arc::MCC, 201
Period	Arc::MCCInterface, 206
Arc::Period, 242	Arc::Plexer, 247
plainstr	Test::TestService, 315
Arc::URL, 326	processConsent
Plexer	Arc::HakaClient, 167
Arc::Plexer, 246	Arc::OpenIdpClient, 225
plugins_table_name	Arc::SAML2SSOHTTPClient, 274
Arc, 43	processIdP2Confusa
PluginsFactory	Arc::HakaClient, 167
Arc::PluginsFactory, 251	Arc::OpenIdpClient, 225
Policy	Arc::SAML2SSOHTTPClient, 274
ArcSec::Policy, 253	processIdPLogin
PolicyStore	Arc::HakaClient, 167
ArcSec::PolicyStore, 255	Arc::OpenIdpClient, 226
Port	Arc::SAML2SSOHTTPClient, 274
Arc::URL, 326	processLogin
port	Arc::OAuthConsumer, 224
Arc::URL, 328	Arc::SAML2LoginClient, 272
Pos	Arc::SAML2SSOHTTPClient, 274
Arc::PayloadStream, 235	ProcessSecHandlers
Arc::PayloadStreamInterface, 238	Arc::MCC, 201
PossibleTargets	Arc::Service, 284
Arc::Broker, 64	Protocol

Arc::URL, 326 Arc::DataPoint, 114 Arc::DataPointDirect, 120 protocol Arc::DataPointIndex, 125 Arc::URL, 328 PROTOCOL_RECOGNIZED_ERROR RegisteredService Arc, 37 Arc::RegisteredService, 260 ProvidesMeta registration Arc::DataPoint, 114 Arc::InfoRegistrar, 172 RegistrationCollector Arc::DataPointDirect, 120 Arc::DataPointIndex, 124 Arc::Service, 284 ProxyPath RelatesTo Arc::WSAHeader, 366 Arc::UserConfig, 352 RelationshipType pushCSR Arc::WSAHeader, 366 Arc::OAuthConsumer, 225 Arc::SAML2SSOHTTPClient, 274 Release Put Arc::FileCache, 161 Arc::PayloadStream, 236 reload Arc::ModuleManager, 218 Arc::PayloadStreamInterface, 239 remove Query Arc::MessageAttributes, 212 Arc::Query, 257 removeAll Arc::MessageAttributes, 213 Range removeService Arc::DataPoint, 114 Arc::InfoRegisterContainer, 171 Arc::DataPointDirect, 120 Replace Arc::DataPointIndex, 124 Arc::XMLNode, 398 RC_DEFAULT_PORT ReplyTo URL.h, 406 Arc::WSAHeader, 366 ReadAcquireError report Arc::DataStatus, 131 Arc::PluginsFactory, 251 ReadError Request Arc::DataStatus, 131 Arc::DelegationConsumer, 136 ReadFromFile ArcSec::Request, 262 Arc::XMLNode, 398 RequestAttribute ReadFromStream ArcSec::RequestAttribute, 263 Arc::XMLNode, 398 RequestItem ReadOutOfOrder ArcSec::RequestItem, 264 Arc::DataPoint, 114 reserve Arc::DataPointDirect, 120 Arc::Counter, 87 Arc::DataPointIndex, 125 Arc::IntraProcessCounter, 181 ReadResolveError Arc::DataStatus, 131 Arc::SimpleCondition, 285 ReadStartError Resolve Arc::DataStatus, 131 Arc::DataPoint, 114 ReadStderr Arc::DataPointDirect, 120 Arc::Run, 271 Rest ReadStdout Arc::PathIterator, 227 Arc::Run, 271 Restore ReadStopError Arc::DelegationConsumer, 136 Arc::DataStatus, 132 restricted_ ReferenceParameter Arc::DelegationContainerSOAP, 139 Arc::WSAHeader, 366 Result ReferenceParameters Arc::InformationResponse, 176 Arc::WSAEndpointReference, 364 Arc::Run, 271

Run

Registered

Arc::Run, 269 Arc::DataSpeed, 129 Running set min average speed Arc::Run, 271 Arc::DataSpeed, 129 set_min_speed Same Arc::DataSpeed, 130 Arc::XMLNode, 398 set_namespaces SAML2LoginClient Arc::WSRF, 368 Arc::SAML2LoginClient, 272 Arc::WSRFBaseFault, 370 SAMLToken Arc::WSRP, 372 Arc::SAMLToken, 276 set progress indicator SAMLVersion Arc::DataSpeed, 130 Arc::SAMLToken, 276 SetAdditionalChecks save Arc::DataPoint, 114 Arc::Config, 78 Arc::DataPointDirect, 121 SaveToFile Arc::DataPointIndex, 125 Arc::UserConfig, 352 setAttributeFactory Arc::XMLNode, 398 ArcSec::Request, 262 SaveToStream setBackups Arc::XMLNode, 398 Arc::LogFile, 192 scan setCfg Arc::PluginsFactory, 251 Arc::ModuleManager, 218 Scope setCombiningAlg Arc::URL, 322 ArcSec::Evaluator, 150 sechandlers_ setEvalResult Arc::MCC, 202 ArcSec::Policy, 254 Arc::Service, 284 setEvaluatorContext secure ArcSec::Policy, 254 Arc::DataMover, 107 setExcess seekable_ Arc::Counter, 87 Arc::PayloadStream, 237 Arc::IntraProcessCounter, 181 selectSoftware setFileName Arc::SoftwareRequirement, 301, 302 Arc::Config, 78 Service SetFormat Arc::Service, 284 Arc::Time, 319 ServiceCounter setIdentifier Arc::TargetGenerator, 311 Arc::LogMessage, 197 SESSION_CLOSE SetLifeTime Arc, 37 Arc::Credential, 96 Set setLimit Arc::XMLNode, 398 Arc::Counter, 87 Arc::IntraProcessCounter, 181 set Arc::DataBuffer, 105 setMaxSize Arc::MessageAttributes, 213 Arc::LogFile, 192 SetMeta Arc::DataSpeed, 129 Arc::DataPoint, 115 set_default_max_inactivity_time Arc::DataPointIndex, 125 Arc::DataMover, 107 SetPeriod set_default_min_average_speed Arc::Period, 243 Arc::DataMover, 107 SetProxyPolicy Arc::Credential, 96 set_default_min_speed Arc::DataMover, 107 setReopen set max data Arc::LogFile, 192 Arc::DataSpeed, 129 setRequestItemsset_max_inactivity_time ArcSec::Request, 263

. D	A G G 202
setRequirement	ArcSec::Source, 303
Arc::SoftwareRequirement, 302	STACK_OF
SetSecure	Arc::Credential, 97
Arc::DataPoint, 115	StageError
Arc::DataPointDirect, 121	Arc::DataStatus, 132
Arc::DataPointIndex, 125	Start
SetStartTime	Arc::FileCache, 161
Arc::Credential, 96	Arc::Run, 271
setThreshold	StartReading
Arc::Logger, 195	Arc::DataPoint, 115
SetTime	Arc::DataPointIndex, 126
Arc::Time, 319	StartWriting
SetValid	Arc::DataPoint, 116
Arc::FileCache, 161	Arc::DataPointIndex, 126
shutdown	STATUS_OK
Arc::Database, 100	Arc, 36
Arc::MySQLDatabase, 221	StatusKind
signal	Arc, 36
Arc::SimpleCondition, 286	Stop
signal_nonblock	-
Arc::SimpleCondition, 286	Arc::FileCache, 161
SignEECRequest	StopAndDelete
Arc::Credential, 96	Arc::FileCache, 162
SignNode	StopReading
Arc::XMLSecNode, 403	Arc::DataPoint, 116
SignRequest	Arc::DataPointIndex, 126
Arc::Credential, 96, 97	StopWriting
Size	Arc::DataPoint, 116
Arc::PayloadRaw, 230	Arc::DataPointIndex, 126
Arc::PayloadRawInterface, 232	storeCert
Arc::PayloadStream, 236	Arc::OAuthConsumer, 225
Arc::PayloadStreamInterface, 239	Arc::SAML2SSOHTTPClient, 274
•	StoreDirectory
Arc::XMLNode, 398	Arc::UserConfig, 353
Arc::XMLNodeContainer, 401	str
size	Arc::Time, 319
Arc::PayloadRawBuf, 230	Arc::URL, 326
SLCS	Are::URLLocation, 330
Arc::UserConfig, 353	string
SOAP	Arc, 42
Arc::InformationRequest, 176	Submit
Arc::WSRF, 368	
SOAPMessage	Arc::Submitter, 306
Arc::SOAPMessage, 287	SubmitterLoader
Software	Arc::SubmitterLoader, 307
Arc::Software, 290	Success
SoftwareRequirement	Arc::DataStatus, 131
Arc::SoftwareRequirement, 296, 297	Swap
SortLocations	Arc::XMLNode, 399
Arc::DataPoint, 115	SYSCONFIG
Arc::DataPointDirect, 121	Arc::UserConfig, 358
Arc::DataPointIndex, 125	SYSCONFIGARCLOC
SortTargets	Arc::UserConfig, 358
Arc::Broker, 63	SystemError
Source	Arc::DataStatus, 132
	1 1 2 1 1 2 1 1 1 1 1 1 1 1 1 1 1 1 1 1

TargetGenerator **UpdateCredentials** Arc::TargetGenerator, 309 Arc::DelegationConsumerSOAP, 138 TargetRetriever Arc::DelegationContainerSOAP, 139 Arc::TargetRetriever, 312 Arc::DelegationProviderSOAP, 142 TargetRetrieverLoader **URL** Arc::TargetRetrieverLoader, 313 Arc::URL, 322 Test::TestMCC, 314 URL.h, 405 Test::TestService, 315 RC_DEFAULT_PORT, 406 process, 315 urlencode thread stacksize Arc::ConfusaParserUtils, 80 Arc. 43 urlencode_params Time Arc::ConfusaParserUtils, 80 Arc::Time, 317 **URLLocation** Timeout Arc::URLLocation, 329 Arc::PayloadStream, 236 urloptions Arc::PayloadStreamInterface, 239 Arc::URL, 328 Arc::UserConfig, 354 UserConfig **TimeStamp** Arc::UserConfig, 334, 335 Arc, 42 UserName To Arc::UserConfig, 354, 355 Arc::WSAHeader, 366 Username toString Arc::URL, 327 Arc::Software, 294 Arc::UsernameToken, 360 Transfer username Arc::DataMover, 107, 108 Arc::URL, 328 transfer UsernameToken Arc::DataSpeed, 130 Arc::UsernameToken, 359 TransferError UtilsDirPath Arc::DataStatus, 131 Arc::UserConfig, 355 Truncate Arc::PayloadRaw, 230 valid Arc::PayloadRawInterface, 232 Arc::URL, 328 TryLoad valid Arc::PluginsFactory, 251 Arc::WSRF, 368 valid_url_options UnimplementedError Arc::DataPoint, 117 Arc::DataStatus, 132 Validate UNKNOWN_SERVICE_ERROR Arc::XMLNode, 399 Arc, 37 verbose UnknownError Arc::DataMover, 108 Arc::DataStatus, 132 Arc::DataSpeed, 130 Unlink Verbosity Arc::MCC, 202 Arc::UserConfig, 356 unload VerifyNode Arc::ModuleManager, 218 Arc::XMLSecNode, 403 unlock **VERSIONTOKENS** Arc::SimpleCondition, 286 Arc::Software, 295 Unregister Arc::DataPoint, 116 VOMSDecode Arc, 42 Arc::DataPointDirect, 121 VOMSServerPath UnregisterError Arc::DataStatus, 132 Arc::UserConfig, 356, 357 Update VOMSTrustList Arc::ExecutionTarget, 154 Arc::VOMSTrustList, 361

Wait

Arc::Run, 271

wait

Arc::SimpleCondition, 286 Arc::SimpleCounter, 286

wait_any

Arc::DataBuffer, 105

wait nonblock

Arc::SimpleCondition, 286

WaitForExit

Arc::ThreadRegistry, 316

WaitOrCancel

Arc::ThreadRegistry, 316

WriteAcquireError

Arc::DataStatus, 131

WriteError

Arc::DataStatus, 131

WriteOutOfOrder

Arc::DataPoint, 116

Arc::DataPointDirect, 121

Arc::DataPointIndex, 127

WriteResolveError

Arc::DataStatus, 131

WriteStartError

Arc::DataStatus, 131

WriteStdin

Arc::Run, 272

WriteStopError

Arc::DataStatus, 132

WSAEndpointReference

Arc::WSAEndpointReference, 363

WSAFault

Arc, 37

WSAFaultAssign

Arc, 42

WSAFaultExtract

Arc, 42

WSAF ault Invalid Addressing Header

Arc, 37

WSAFaultUnknown

Arc. 37

WSAHeader

Arc::WSAHeader, 365

WSRF

Arc::WSRF, 368

WSRFBaseFault

Arc::WSRFBaseFault, 369

WSRP

Arc::WSRP, 372

WSRPFault

Arc::WSRPFault, 374

WSRPResourcePropertyChangeFailure

Arc::WSRPResourcePropertyChangeFailure,

382

X509Token

Arc::X509Token, 387

X509TokenType

Arc::X509Token, 387

XMLNode

Arc::XMLNode, 391, 392

XMLNodeContainer

Arc::XMLNodeContainer, 401

XMLSecNode

Arc::XMLSecNode, 402

XPathLookup

Arc::XMLNode, 399