Command Line Interface for IBM Aspera products

Laurent MARTIN

2023/09/21

Contents

1		1
2	BUGS, FEATURES, CONTRIBUTION	8
3	When to use and when not to use	g
4	Notations, Shell, Examples	10
5		11 11 12
6	6.1 Container 6.1.1 Container: quick start 6.1.2 Container: Details 6.1.3 Container: Sample start script 6.1.4 Container: Offline installation 6.1.5 Container: aspera.conf 6.1.6 Container: Singularity 6.2 Ruby 6.2.1 Generic: RVM: single user installation (not root) 6.2.2 Generic: RVM: global installation (as root) 6.2.3 Windows: Installer 6.2.4 macOS: pre-installed or brew 6.2.5 Linux: package 6.2.6 Other Unixes (AIX) 6.3 aspera-cli gem 6.4 FASP Protocol	13 14 15 15 16 16 17 17 17 17 17
7	Command Line Interface: ascli 7.1 ascp command line 7.2 Command line parsing, Special Characters 7.2.1 Shell parsing for Unix-like systems: Linux, macOS, AIX 7.2.2 Shell parsing for Windows 7.2.3 Extended Values (JSON, Ruby,) 7.2.4 Testing Extended Values 7.2.5 Using a shell variable, parsed by shell, in an extended value 7.2.6 Double quote in strings in command line 7.2.7 Shell and JSON or Ruby special characters in extended value 7.2.8 Reading special characters interactively 7.2.9 Command line arguments from a file 7.2.10 Extended value using special characters read from environmental variables or files 7.3 Commands, Options, Positional Values 7.3.1 Commands 7.3.2 Options	21 21 21 22 22 23 23 23 24 24 24

		Positional Values	
7.4	Interac	ctive Input	 25
		t	
		Types of output data	
		Format of output	
		Option: select: Filter on columns values for object_list	
		entity identifier	
		Verbosity of output	
		Selection of output object properties	
		ded Value Syntax	
		ured Value	
		guration and Persistency Folder	
		guration file	
		Option preset	
		Special Option preset: config	
		Special Option preset: default	
		Plugin: config: Configuration	
		Config sample commands	
	7.9.6	Format of file	 31
	7.9.7	Options evaluation order	 32
		Shares Examples	
		t Vault	
		Vault: System key chain	
		2 Vault: Encrypted file	
		3 Vault: Operations	
		Configuration Finder	
		Securing passwords and secrets	
		e Key	
		ascli for key generation	
		ssh-keygen	
		openssl	
		CA certificate bundle	
		ns	
		Create your own plugin	
		Plugins: Application URL and Authentication	
7.14	Loggin	ng, Debugging	 36
7.15	Learni	ing Aspera Product APIs (REST)	 36
		socket parameters	36
7.17	Graphi	iical Interactions: Browser and Text Editor	
		for REST and HTTPGW	
		for Legacy Aspera HTTP/S Fallback	
		proxy (forward) for transfers	
		configuration	38
1 .22		Show path of currently used ascp	38
		· · · · · · · · · · · · · · · · · · ·	
		2 Selection of ascp location for direct agent	38
		B List locally installed Aspera Transfer products	39
		Selection of local client for ascp for direct agent	39
		Installation of Connect Client on command line	39
7.23		fer Clients: Agents	39
		Direct	40
	7.23.2	P. IBM Aspera Connect Client GUI	 42
	7.23.3	B Aspera Node API: Node to node transfers	 42
		HTTP Gateway	42
	7.23.5	is Transfer SDK	 43
7.24	Transf	fer Specification	 43
		fer Parameters	
-		Destination folder for transfers	
		List of files for transfers	45

		7.25.3 Source directory structure on destination	. 46
		7.25.4 Support of multi-session	. 47
		7.25.5 Content protection	. 48
		7.25.6 Transfer Spec Examples	. 48
	7.26	Scheduler	
		7.26.1 Windows Scheduler	. 48
		7.26.2 Unix-like Scheduler	. 48
	7.27	Locking for exclusive execution	. 49
	7.28	B "Provençale"	. 49
	7.29	9 faux: for testing	. 50
	7.30) Usage	. 51
	7.31	Bulk creation and deletion of resources	. 56
8		gin: aoc: IBM Aspera on Cloud	57
		Configuration: using Wizard	
	8.2	Configuration: using manual setup	
		8.2.1 Configuration details	
		8.2.2 Optional: API Client Registration	
		8.2.3 option preset for Aspera on Cloud	
		8.2.4 Activation of JSON Web Token (JWT) for direct authentication	
		8.2.5 User key registration	
		8.2.6 option preset modification for JWT	
		8.2.7 First Use	
		Calling AoC APIs from command line	
	8.4	Administration	
		8.4.1 Listing resources	
		8.4.2 Selecting a resource	
		8.4.3 Creating a resource	
		8.4.4 Access Key secrets	
		8.4.5 Activity	
		8.4.6 Transfer: Using specific transfer ports	
		8.4.7 Using ATS	
		8.4.8 Files with type link	
		8.4.9 Example: Bulk creation of users	
		8.4.10 Example: Find with filter and delete	
		8.4.11 Example: Find deactivated users since more than 2 years	
		8.4.12 Example: Display current user's workspaces	
		8.4.13 Example: Create a sub access key in a "node"	
		8.4.14 Example: Display transfer events (ops/transfer)	
		8.4.15 Example: Display node events (events)	
		8.4.16 Example: Display members of a workspace	
		8.4.17 Example: add all members of a workspace to another workspace	
		8.4.18 Example: Get users who did not log since a date	
		8.4.19 Example: List "Limited" users	
		8.4.20 Example: create a group, add to workspace and add user to group	
		8.4.21 Example: Perform a multi Gbps transfer between two remote shared folders	
		8.4.22 Example: create registration key to register a node	
		8.4.23 Example: delete all registration keys	
		8.4.24 Example: Create a Node	
		List of files to transfer	
	8.6	Packages	
		8.6.1 Send a Package	
		8.6.2 Example: Send a package with one file to two users, using their email	
		8.6.3 Example: Send a package to a shared inbox with metadata	
		8.6.4 Example: List packages in a given shared inbox	
		8.6.5 Example: Receive all packages from a given shared inbox	
		8.6.6 Example: Send a package with files from the Files app	
		8.6.7 Receive new packages only (Cargo)	
	8 7	Files	69

		8.7.1																															
		8.7.2																															
		8.7.3			_																												
		8.7.4																															
	8.8	AoC s	am	ple co	mma	ands	3.																										70
_	Б.							e	^		_																						۰.
9		gin: ats																															73
		IBM C																															
		ATS A			•		•																										
	9.3																																
	9.4	ATS s	am	oie coi	HIIII	ınas	<i>.</i>		٠.	•			٠.	•		٠.	•		•			•			•				٠		•	•	74
10	Pluc	gin: seı	rve	r· IBN	Λ Δς	ner	a Hi	ah S	Sne	ed	Tra	nsf	er S	Serv	/er	(89	(H																75
. •		Serve																															
	10.2	2 Auther	ntic	ation (on S	erve	r wi	th S	SH	ses	 ssio	 n	•	•		•	•	•	•	•	•	•	•	•	•	•	•	•	•	•	•	•	76
		Other																															
		Exam																															
	. •	_,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,	p.00	. 202										•	-				-						•				-		-	-	•
11	Plug	gin: noo	de:	IBM A	\ spe	ra F	վigh	Spo	eed	l Tr	ans	fer	Ser	vei	· No	ode	•																78
	11.1	File O	per	ations																													78
	11.2	Centra	al .																														78
	11.3	FASP	Str	eam																													78
		Watch																															
		Out of																															
	11.6	Exam	ple:	SHO	D to	ATS	3.																										79
	11.7	node f	file	nform	atior	n .																											79
		Create																															
	11.9	Node	sar	nple c	omm	าand	ls .																										80
40	Divi			ID			F			=																							00
12		gin: fas																															82
		Faspe																															
		? Faspe																															
		Faspe																															
		Faspe																															
		Faspe																															
		Faspe																															
		Faspe			•		_																										
		Faspe Faspe																															
		0Faspe 1Faspe																															
		2Faspe																															
		3Faspe																															
		4Faspe																															
		5 Faspe																															
	12.1	a aspe	,, 0	. i uop	/CX ¬	Oly	ic p	σσιρ	100	.000	,,,,,	•		•			•		•			•			•				•		•	•	00
13	Plug	gin: fas	spe	x: IBN	/I As	pera	a Fa	spe	X V	4																							87
	13.1	Listing	, Pa	ckage	es .																												87
		13.1.1	-	-																													
		13.1.2																															
		13.1.3																															
		13.1.4																															
	13.2	Receiv					-	-																									
		Sendir																															
		Email																															
		Opera																															
		Remo																															
		' Autom																															
		Faspe																															

14	Plugin: shares: IBM Aspera Shares v1 14.1 Shares 1 sample commands	90 90
15	Plugin: console: IBM Aspera Console 15.1 Console sample commands	91 91
16	Plugin: orchestrator:IBM Aspera Orchestrator 16.1 Orchestrator sample commands	92 92
17	Plugin: cos: IBM Cloud Object Storage	93
	17.1 Using endpoint, apikey and Resource Instance ID (CRN)	93
	17.2 Using service credential file	
	17.3 Operations, transfers	
	17.4 COS sample commands	94
18	Plugin: async: IBM Aspera Sync	95
	18.1 async native JSON	
	18.2 async options as JSON	
	16.5 Syric sample confinances	90
19	Plugin: preview: Preview generator for AoC	96
	19.1 Aspera Server configuration	
	19.2 External tools: Linux	
	19.2.1 Image: ImageMagick and optipng	
	19.2.3 Office: Unoconv and Libreoffice	
	19.3 Configuration	
	19.4 Options for generated files	
	19.5 Execution	
	19.6 Configuration for Execution in scheduler	
	19.7 Candidate detection for creation or update (or deletion)	
	19.8 Preview File types	
	19.9 Supported input Files types	
	19.10mimemagic	
	19.12Preview sample commands	
		.00
20	SMTP for email notifications	101
	20.1 Example of configuration	101
	20.2 Email templates	
	20.4 Notifications for transfer status	
21	Tool: assession	103
	21.1 Comparison of interfaces	
	21.3 Asynchronous commands and Persistent session	
	21.4 Example of language wrapper	
	21.5 Help	
00		405
22	Hot folder 22.1 Requirements	105
	22.1 Requirements	
	22.2.1 ascp features	
	22.2.2 server side and configuration	
	22.2.3 Scheduling	
	22.3 Example: upload hot folder	
	22.4 Example: unidirectional synchronization (upload) to server	
	22.5 Example: unidirectional synchronization (download) from Aspera on Cloud Files	106

23 Health check and Nagios	107
24 Ruby Module: Aspera	108
25 Changes (Release notes)	109
26 History	110
27 Common problems 27.1 Error: "Remote host is not who we expected"	. 111

Version: 4.14.0.pre Laurent/2016-2023

This gem provides the ascli Command Line Interface to IBM Aspera software.

ascli is a also great tool to learn Aspera APIs.

Ruby Gem: https://rubygems.org/gems/aspera-cli Ruby Doc: https://www.rubydoc.info/gems/aspera-cli

Minimum required Ruby version: >= 2.6.

Deprecation notice: the minimum Ruby version will be 3.0 in a future version.

Aspera APIs on IBM developer Link 2
Release notes: see CHANGELOG.md
openssf best practices in progress 96%

BUGS, FEATURES, CONTRIBUTION

Refer to BUGS.md and CONTRIBUTING.md.

One can also create one's own plugin.

When to use and when not to use

ascli is designed to be used as a command line tool to:

- · Execute commands remotely on Aspera products
- Transfer to/from Aspera products

So it is designed for:

- Interactive operations on a text terminal (typically, VT100 compatible), e.g. for maintenance
- Scripting, e.g. batch operations in (shell) scripts (e.g. cron job)

ascli can be seen as a command line tool integrating:

- A configuration file (config.yaml)
- · Advanced command line options
- cURL (for REST calls)
- Aspera transfer (ascp)

If the need is to perform operations programmatically in languages such as: C, Go, Python, nodejs, ... then it is better to directly use Aspera APIs

- Product APIs (REST): e.g. AoC, Faspex, node
- Transfer SDK: with gRPC interface and language stubs (C, C++, Python, .NET/C#, java, Ruby, etc...)

Using APIs (application REST API and transfer SDK) will prove to be easier to develop and maintain.

For scripting and ad'hoc command line operations, ascli is perfect.

Notations, Shell, Examples

Command line operations examples are shown using a shell such: bash or zsh.

Command line parameters in examples beginning with my_, like my_param_value are user-provided value and not fixed value commands.

ascli is an API Client toward the remote Aspera application Server (Faspex, HSTS, etc...)

Some commands will start an Aspera-based transfer (e.g. upload). The transfer is not directly implemented in ascli, rather ascli uses an external Aspera Client called **Transfer Agents**.

Note: The transfer agent is a client for the remote Transfer Server (HSTS). The transfer agent may be local or remote... For example a remote Aspera Server may be used as a transfer agent (using node API). i.e. using option --transfer=node

Quick Start

This section guides you from installation, first use and advanced use.

First, follow the section: Installation (Ruby, Gem, FASP) to start using ascli.

Once the gem is installed, ascli shall be accessible:

```
ascli --version
4.14.0.pre
```

5.1 First use

Once installation is completed, you can proceed to the first use with a demo server:

If you want to test with Aspera on Cloud, jump to section: Wizard

To test with Aspera demo transfer server, setup the environment and then test:

```
ascli config initdemo
ascli server browse /
```

	zuid	zgid	size	•	name
drwxr-xr-x dr-xr-xr-x dr-xr-xr-x dr-xr-xr-x	asperaweb asperaweb asperaweb	asperaweb asperaweb asperaweb asperaweb	90112 4096 4096 4096	2023-04-05 15:31:21 +0200 2022-10-27 16:08:16 +0200 2022-10-27 16:08:17 +0200 2022-10-27 16:08:17 +0200	Upload aspera-test-dir-large aspera-test-dir-small aspera-test-dir-tiny

If you want to use ascli with another server, and in order to make further calls more convenient, it is advised to define a option preset for the server's authentication options. The following example will:

- create a option preset
- define it as default for server plugin
- · list files in a folder
- · download a file

```
ascli config preset update myserver --url=ssh://demo.asperasoft.com:33001 --username=asperaweb --password=my_updated: myserver
ascli config preset set default server myserver
updated: default → server to myserver
ascli server browse /aspera-test-dir-large
```

zmode	zuid	zgid	size	mtime	name
-r-xr-x -r-xr-x	asperaweb asperaweb asperaweb asperaweb asperaweb asperaweb	asperaweb asperaweb asperaweb asperaweb asperaweb	104857600 10737418240 500000000000 524288000 1048576000 5368709120	2022-10-27 16:06:38 +0200 2022-10-27 16:08:12 +0200 2022-10-27 16:06:26 +0200 2022-10-27 14:53:00 +0200 2022-10-27 16:06:37 +0200 2022-10-27 14:53:47 +0200 2022-10-27 14:53:47 +0200	100MB 10GB 500GB 500MB 1GB

ascli server download /aspera-test-dir-large/200MB

Time: 00:00:02 ========= 100% 100 Mbps Time: 00:00:00 complete

5.2 Going further

Get familiar with configuration, options, commands: Command Line Interface.

Then, follow the section relative to the product you want to interact with (Aspera on Cloud, Faspex, ...) : Application Plugins

Installation

It is possible to install **either** directly on the host operating system (Linux, macOS, Windows) or as a container (docker).

The direct installation is recommended and consists in installing:

- Ruby
- aspera-cli
- Aspera SDK (ascp)

Ruby version: >= 2.6.

Deprecation notice: the minimum Ruby version will be 3.0 in a future version.

The following sections provide information on the various installation methods.

An internet connection is required for the installation. If you don't have internet for the installation, refer to section Installation without internet access.

6.1 Container

The container image is: martinlaurent/ascli. The container contains: Ruby, ascli and the Aspera Transfer SDK. To use the container, ensure that you have podman (or docker) installed.

```
podman --version
```

6.1.1 Container: quick start

Wanna start quickly? With an interactive shell? Execute this:

```
podman run --tty --interactive --entrypoint bash martinlaurent/ascli:latest
```

Then, execute individual ascli commands such as:

```
ascli conf init
ascli conf preset overview
ascli conf ascp info
ascli server ls /
```

That is simple, but there are limitations:

- Everything happens in the container
- Any generated file in the container will be lost on container (shell) exit. Including configuration files and downloaded files.
- · No possibility to upload files located on the host system

6.1.2 Container: Details

The container image is built from this Dockerfile: the entry point is ascli and the default command is help.

If you want to run the image with a shell, execute with option: --entrypoint bash, and give argument -1 (bash login option to override the help default argument)

The container can also be executed for individual commands like this: (add ascli commands and options at the end of the command line, e.g. -v to display the version)

```
podman run --rm --tty --interactive martinlaurent/ascli:latest
```

For more convenience, you may define a shell alias:

```
alias ascli='podman run --rm --tty --interactive martinlaurent/ascli:latest'
```

Then, you can execute the container like a local command:

```
ascli -v
```

```
4.14.0.pre
```

In order to keep persistency of configuration on the host, you should specify your user's config folder as a volume for the container. To enable write access, a possibility is to run as root in the container (and set the default configuration folder to /home/cliuser/.aspera/ascli). Add options:

```
--user root --env ASCLI_HOME=/home/cliuser/.aspera/ascli --volume $HOME/.aspera/ascli:/home/cliuser/.aspera/a
```

Note: if you are using a podman machine, e.g. on macOS, make sure that the folder is also shared between the VM and the host, so that sharing is: container \rightarrow VM \rightarrow Host: podman machine init ... --volume="/Users:/Users"

As shown in the quick start, if you prefer to keep a running container with a shell and ascli available, you can change the entry point, add option:

```
--entrypoint bash
```

asclish

You may also probably want that files downloaded in the container are directed to the host. In this case you need also to specify the shared transfer folder as a volume:

```
--volume $HOME/xferdir:/xferfiles
```

Note: ascli is run inside the container, so transfers are also executed inside the container and do not have access to host storage by default.

And if you want all the above, simply use all the options:

```
alias asclish="podman run --rm --tty --interactive --user root --env ASCLI_HOME=/home/cliuser/.aspera/ascli -
export xferdir=$HOME/xferdir
mkdir -p $xferdir
chmod -R 777 $xferdir
mkdir -p $HOME/.aspera/ascli
```

6.1.3 Container: Sample start script

A convenience sample script is also provided: download the script dascli from the GIT repo:

Note: If you have installed ascli, the script dascli can also be found: cp \$(ascli conf gem path)/../examples/dascli ascli

Some environment variables can be set for this script to adapt its behavior:

env var	description	default	example
ASCLI_HOME docker_args image version	configuration folder (persistency) additional options to podman container image name container image version	\$HOME/.aspera/ascli <empty> martinlaurent/ascli latest</empty>	\$HOME/.ascliconfigvolume /Users:/Users 4.8.0.pre

env var description	default	example	
---------------------	---------	---------	--

The wrapping script maps the folder \$ASCLI_HOME on host to /home/cliuser/.aspera/ascli in the container. (value expected in the container). This allows having persistent configuration on the host.

To add local storage as a volume, you can use the env var docker_args:

Example of use:

```
curl -o ascli https://raw.githubusercontent.com/IBM/aspera-cli/main/examples/dascli
chmod a+x ascli
export xferdir=$HOME/xferdir
mkdir -p $xferdir
chmod -R 777 $xferdir
export docker_args="--volume $xferdir:/xferfiles"

./ascli conf init

echo 'Local file to transfer' > $xferdir/samplefile.txt
./ascli server upload /xferfiles/samplefile.txt --to-folder=/Upload

Note: The local file (samplefile.txt) is specified relative to storage view from container (/xferfiles)
mapped to the host folder $HOME/xferdir
```

Note: Do not use too many volumes, as the AUFS limits the number.

6.1.4 Container: Offline installation

· First create the image archive:

Then, on an-gapped system.

```
{\tt podman \ load \ -i \ ascli\_image\_latest.tar.gz}
```

6.1.5 Container: aspera.conf

ascp's configuration file aspera.conf is located in the container at: /aspera_sdk/aspera.conf (see Dockerfile). As the container is immutable, it is not recommended to modify this file. If one wants to change the content, it is possible to tell ascp to use another file using ascp option -f, e.g. by locating it on the host folder \$HOME/.aspera/ascli mapped to the container folder /home/cliuser/.aspera/ascli:

```
echo '<CONF/>' > $HOME/.aspera/ascli/aspera.conf
Then, tell ascp to use that other conf file:
--transfer-info=@json:'{"ascp_args":["-f","/home/cliuser/.aspera/ascli/aspera.conf"]}'
```

6.1.6 Container: Singularity

Singularity is another type of use of container.

```
On Linux install:
```

```
dnf install singularity-ce
Build an image like this:
    singularity build ascli.sif docker://martinlaurent/ascli
The use like this:
    singularity run ascli.sif
```

Or get a shell with access to the tool like this:

```
singularity shell ascli.sif
```

6.2 Ruby

Use this method to install on the native host.

A Ruby interpreter is required to run the tool or to use the gem and tool.

Required Ruby version: >= 2.6.

Deprecation notice: the minimum Ruby version will be 3.0 in a future version.

Ruby can be installed using any method: rpm, yum, dnf, rvm, brew, windows installer,

In priority, refer to the official Ruby documentation:

- Download Ruby
- Installation Guide

Else, refer to the following sections for a proposed method for specific operating systems.

The recommended installation method is rvm for Unix-like systems (Linux, AIX, macOS, Windows with cygwin, etc...). If the generic install is not suitable (e.g. Windows, no cygwin), you can use one of OS-specific install method. If you have a simpler better way to install Ruby: use it!

6.2.1 Generic: RVM: single user installation (not root)

Use this method which provides more flexibility.

```
Install rvm: follow https://rvm.io/:
```

Execute the shell/curl command. As regular user, it install in the user's home: ~/.rvm.

```
\curl -sSL https://get.rvm.io | bash -s stable
```

Follow on-screen instructions to install keys, and then re-execute the command.

If you keep the same terminal (not needed if re-login):

```
source ~/.rvm/scripts/rvm
```

It is advised to get one of the pre-compiled Ruby version, you can list with:

```
rvm list --remote
```

Install the chosen pre-compiled Ruby version:

```
rvm install 3.2.2
```

Ruby is now installed for the user, go to Gem installation.

6.2.2 Generic: RVM: global installation (as root)

Follow the same method as single user install, but execute as "root".

As root, it installs by default in /usr/local/rvm for all users and creates /etc/profile.d/rvm.sh. One can install in another location with :

```
curl -sSL https://get.rvm.io | bash -s -- --path /usr/local
```

As root, make sure this will not collide with other application using Ruby (e.g. Faspex). If so, one can rename the login script: mv /etc/profile.d/rvm.sh.ok. To activate Ruby (and ascli) later, source it:

```
source /etc/profile.d/rvm.sh.ok
```

rvm version

6.2.3 Windows: Installer

Install Latest stable Ruby:

- Navigate to https://rubyinstaller.org/ → Downloads.
- Download the latest Ruby installer with devkit. (Msys2 is needed to install some native extensions, such as grpc)
- Execute the installer which installs by default in: C:\RubyVV-x64 (VV is the version number)
- At the end of the installation procedure, the Msys2 installer is automatically executed, select option 3 (msys and mingw)

6.2.4 macOS: pre-installed or brew

macOS 10.13+ (High Sierra) comes with a recent Ruby. So you can use it directly. You will need to install aspera-cli using sudo:

```
sudo gem install aspera-cli --pre
```

Alternatively, if you use Homebrew already you can install Ruby with it:

```
brew install ruby
```

6.2.5 Linux: package

If your Linux distribution provides a standard Ruby package, you can use it provided that the version supported.

Example: RHEL 8+, Rocky Linux 8+, Centos 8 Stream: with extensions to compile native gems

Check available ruby versions:

```
dnf module list ruby
```

• If ruby was already installed with an older version, remove it:

```
dnf module -y reset ruby
```

Install packages needed to build native gems:

```
dnf install -y make automake gcc gcc-c++ kernel-devel
```

• Enable the Ruby version you want:

```
dnf module -y enable ruby:3.1
dnf install -y ruby-devel
```

Other examples:

```
yum install -y ruby ruby-devel rubygems ruby-json apt install -y ruby ruby-dev rubygems ruby-json
```

One can cleanup the whole yum-installed Ruby environment like this to uninstall:

```
gem uninstall $(ls $(gem env gemdir)/gems/|sed -e 's/-[^-]*$//'|sort -u)
```

6.2.6 Other Unixes (AIX)

Ruby is sometimes made available as installable package through third party providers. For example for AIX, one can look at:

https://www.ibm.com/support/pages/aix-toolbox-open-source-software-downloads-alpha#R

If your Unix does not provide a pre-built Ruby, you can get it using one of those methods.

For instance to build from source, and install in /opt/ruby:

```
wget https://cache.ruby-lang.org/pub/ruby/2.7/ruby-2.7.2.tar.gz
gzip -d ruby-2.7.2.tar.gz
tar xvf ruby-2.7.2.tar
```

```
cd ruby-2.7.2
./configure --prefix=/opt/ruby
make ruby.imp
make
make install
```

If you already have a Java JVM on your system (java), it is possible to use jruby:

https://www.jruby.org/download

Note: Using jruby the startup time is longer than the native Ruby, but the transfer speed is not impacted (executed by ascp binary).

6.3 aspera-cli gem

Once you have Ruby and rights to install gems: Install the gem and its dependencies:

```
gem install aspera-cli --pre
```

To upgrade to the latest version:

```
gem update aspera-cli
```

ascli checks every week if a new version is available and notify the user in a WARN log. To de-activate this feature, globally set the option version_check_days to 0, or specify a different period in days.

To check if a new version is available (independently of version_check_days):

ascli conf check_update

6.4 FASP Protocol

Most file transfers will be done using the FASP protocol, using ascp. Only two additional files are required to perform an Aspera Transfer, which are part of Aspera SDK:

- ascp
- aspera-license (in same folder, or ../etc)

This can be installed either be installing an Aspera transfer software, or using an embedded command:

```
ascli conf ascp install
```

If a local SDK installation is preferred instead of fetching from internet: one can specify the location of the SDK file:

```
curl -Lso SDK.zip https://ibm.biz/aspera_sdk
ascli conf ascp install --sdk-url=file:///SDK.zip
```

The format is: file:///<path>, where <path> can be either a relative path (not starting with /), or an absolute path.

If the embedded method is not used, the following packages are also suitable:

- IBM Aspera Connect Client (Free)
- IBM Aspera Desktop Client (Free)
- IBM Aspera High Speed Transfer Server (Licensed)
- IBM Aspera High Speed Transfer EndPoint (Licensed)

For instance, Aspera Connect Client can be installed by visiting the page: https://www.ibm.com/aspera/connect/.

ascli will detect most of Aspera transfer products in standard locations and use the first one found. Refer to section FASP for details on how to select a client or set path to the FASP protocol.

Several methods are provided to start a transfer. Use of a local client (direct transfer agent) is one of them, but other methods are available. Refer to section: Transfer Agents

6.5 Installation in air gapped environment

Note: no pre-packaged version is provided.

A method to build one is provided here:

The procedure:

- Follow the non-root installation procedure with RVM, including gem
- Archive (zip, tar) the main RVM folder (includes ascli):

```
cd $HOME && tar zcvf rvm-ascli.tgz .rvm
```

· Get the Aspera SDK.

```
ascli conf --show-config --fields=sdk_url
```

· Download the SDK archive from that URL.

```
curl -Lso SDK.zip https://ibm.biz/aspera_sdk
```

- Transfer those 2 files to the target system
- On target system

```
cd $HOME
```

```
tar zxvf rvm-ascli.tgz
source ~/.rvm/scripts/rvm
ascli conf ascp install --sdk-url=file:///SDK.zip
```

• Add those lines to shell init (.profile)

source ~/.rvm/scripts/rvm

Command Line Interface: ascli

The aspera-cli Gem provides a command line interface (CLI) which interacts with Aspera Products (mostly using REST APIs):

- IBM Aspera High Speed Transfer Server (FASP and Node)
- IBM Aspera on Cloud (including ATS)
- IBM Aspera Faspex
- · IBM Aspera Shares
- IBM Aspera Console
- IBM Aspera Orchestrator
- · and more...

ascli provides the following features:

- Supports most Aspera server products (on-premise and SaaS)
- Any command line options (products URL, credentials or any option) can be provided on command line, in configuration file, in env var, in files
- Supports Commands, Option values and Parameters shortcuts
- FASP Transfer Agents can be: local ascp, or Connect Client, or any transfer node
- Transfer parameters can be altered by modification of *transfer-spec*, this includes requiring multi-session
- Allows transfers from products to products, essentially at node level (using the node transfer agent)
- Supports FaspStream creation (using Node API)
- Supports Watchfolder creation (using Node API)
- Additional command plugins can be written by the user
- · Supports download of faspex and Aspera on Cloud "external" links
- Supports "legacy" ssh based FASP transfers and remote commands (ascmd)

Basic usage is displayed by executing:

ascli -h

Refer to sections: Usage.

Not all ascli features are fully documented here, the user may explore commands on the command line.

7.1 ascp command line

If you want to use ascp directly as a command line, refer to IBM Aspera documentation of either Desktop Client, Endpoint or Transfer Server where a section on ascp can be found.

Using ascli with plugin server for command line gives advantages over ascp:

- · automatic resume on error
- · configuration file
- · choice of transfer agents
- · integrated support of multi-session

Moreover all ascp options are supported either through transfer spec parameters and with the possibility to provide ascp arguments directly when the direct agent is used (ascp_args).

7.2 Command line parsing, Special Characters

ascli is typically executed in a shell, either interactively or in a script. ascli receives its arguments from this shell (through Operating System).

7.2.1 Shell parsing for Unix-like systems: Linux, macOS, AIX

Linux command line parsing is easy: It is fully documented in the shell's documentation.

On Unix-like environments, this is typically a POSIX shell (bash, zsh, ksh, sh). In this environment the shell parses the command line, possibly replacing variables, etc... See bash shell operation. The shell builds the list of arguments and then fork/exec Ruby with that list. Ruby receives a list parameters from shell and gives it to ascli. So special character handling (quotes, spaces, env vars, ...) is handled by the shell for any command executed.

7.2.2 Shell parsing for Windows

MS Windows command line parsing is not easy: It is not hasndled by the shell (cmd.exe), not handled by the operating system, but it is handled by the application (here Ruby).

As far as ascli is concerned: it is close to a Linux shell parsing.

Thanksfully, ascli provides a command to check the value of an argument after parsing: config echo. One can also run ascli with option --log-level=debug to display the command line after parsing.

The following examples give the same result on Windows:

· single quote protects the double quote

```
conf echo @json:'{"url":"https://..."}'
```

· triple double quotes are replaced with a single double quote

```
conf echo @json:{"""url""":""https://..."""}
```

double quote is escaped with backslash within double quotes

```
conf echo @json:"{\"url\":\"https://...\"}"
```

On Windows, cmd.exe is typically used to start. cmd.exe handles some special characters: $\"<\$ |%&. Basically it handles I/O redirections (<>|), shell variables (%), multiple commands (&) and handles those special characters from the command line. Eventually, all those special characters are removed from the command line unless escaped with " or ". " are kept and given to the program.

Then, Windows CreateProcess is called with just the whole command line as a single string, unlike Unix-like systems where the command line is split into arguments by the shell.

It's up to the program to split arguments:

- · Windows: How Command Line Parameters Are Parsed
- · Understand Quoting and Escaping of Windows Command Line Arguments

is a Ruby program, so Ruby parses the command line into arguments and provides them to the program. Ruby vaguely follows the Microsoft C/C++ parameter parsing rules. (See w32 cmdvector in Ruby source win32.c):

- space characters: split arguments (space, tab, newline)
- backslash: \ escape single special character
- globbing characters: *?[]{} for file globbing
- · double quotes: "
- single quotes: '

7.2.3 Extended Values (JSON, Ruby, ...)

Some of the ascli parameters are expected to be Extended Values, i.e. not a simple strings, but a complex structure (Hash, Array). Typically, the @json: modifier is used, it expects a JSON string. JSON itself has some special syntax: for example " is used to denote strings.

7.2.4 Testing Extended Values

In case of doubt of argument values after parsing, one can test using command <code>config echo</code>. <code>config echo</code> takes exactly **one** argument which can use the Extended Value syntax. Unprocessed command line arguments are shown in the error message.

Example: The shell parses three arguments (as strings: 1, 2 and 3), so the additional two arguments are not processed by the echo command.

```
ascli conf echo 1 2 3
"1"
ERROR: Argument: unprocessed values: ["2", "3"]
```

config echo displays the value of the **first** argument using Ruby syntax: it surrounds a string with " and add \ before special characters.

Note: It gets its value after shell command line parsing and ascli extended value parsing.

In the following examples (using a POSIX shell, such as bash), several sample commands are provided when equivalent. For all example, most of special character handling is not specific to ascli: It depends on the underlying syntax: shell, JSON, etc... Depending on the case, a different format is used to display the actual value.

For example, in the simple string Hello World, the space character is special for the shell, so it must be escaped so that a single value is represented.

Double quotes are processed by the shell to create a single string argument. For **POSIX shells**, single quotes can also be used in this case, or protect the special character (space) with a backslash.

```
ascli conf echo "Hello World" --format=text
ascli conf echo 'Hello World' --format=text
ascli conf echo Hello\ World --format=text
Hello World
```

7.2.5 Using a shell variable, parsed by shell, in an extended value

To be evaluated by shell, the shell variable must not be in single quotes. Even if the variable contains spaces it makes only one argument to ascli because word parsing is made before variable expansion by shell.

Note: we use a shell variable here: the variable is not necessarily an environment variable (export).

```
MYVAR="Hello World"
ascli conf echo @json:'{"title":"'$MYVAR'"}' --format=json
ascli conf echo @json:{\"title\":\"$MYVAR\"} --format=json
{"title":"Hello World"}
```

7.2.6 Double quote in strings in command line

Double quote is a shell special character. Like any shell special character, it can be protected either by preceding with a backslash or by enclosing in a single quote.

```
ascli conf echo \"
ascli conf echo \"
"
```

Double quote in JSON is a little tricky because " is special both for the shell and JSON. Both shell and JSON syntax allow to protect ", but only the shell allows protection using single quote.

```
ascli conf echo @json:'"\""" --format=text
ascli conf echo @json:\"\\"\" --format=text
ascli conf echo @ruby:\'\"\' --format=text
...
```

Here a single quote or a backslash protects the double quote to avoid shell processing, and then an additional \ is added to protect the " for JSON. But as \ is also shell special, then it is protected by another \.

7.2.7 Shell and JSON or Ruby special characters in extended value

Construction of values with special characters is done like this:

- First select a syntax to represent the extended value, e.g. JSON or Ruby
- Write the expression using this syntax, for example, using JSON:

```
{"title":"Test \" ' & \\"}
or using Ruby:
{"title"=>"Test \" ' & \\"}
{'title'=>%q{Test " ' & \\}}
```

Both " and \ are special characters for JSON and Ruby and can be protected with \ (unless Ruby's extended single quote notation %q is used).

• Then, since the value will be evaluated by shell, any shell special characters must be protected, either using preceding \ for each character to protect, or by enclosing in single quote:

7.2.8 Reading special characters interactively

If ascli is used interactively (a user typing on terminal), it is easy to require the user to type values:

```
ascli conf echo @ruby:"{'title'=>gets.chomp}" --format=json
```

gets is Ruby's method of terminal input (terminated by \n), and chomp removes the trailing \n.

7.2.9 Command line arguments from a file

If you need to provide a list of command line argument from lines that are in a file, on Linux you can use the xargs command:

```
xargs -a lines.txt -d \\n ascli conf echo
This is equivalent to execution of:
ascli conf echo [line1] [line2] [line3] ...
```

If there are spaces in the lines, those are not taken as separator, as we provide option -d \\n to xargs.

7.2.10 Extended value using special characters read from environmental variables or files

Using a text editor or shell: create a file title.txt (and env var) that contains exactly the text required: Test " ' & $\$:

```
export MYTITLE='Test " '\'' & \' echo -n $MYTITLE > title.txt
```

Using those values will not require any escaping of characters since values do not go through shell or JSON parsing.

If the value is to be assigned directly to an option of ascli, then you can directly use the content of the file or env var using the <code>@file: or @env: readers:</code>

```
ascli conf echo @file:title.txt --format=text
ascli conf echo @env:MYTITLE --format=text
Test " ' & \
```

If the value to be used is in a more complex structure, then the @ruby: modifier can be used: it allows any Ruby code in expression, including reading from file or env var. In those cases, there is no character to protect because values are not parsed by the shell, or JSON or even Ruby.

```
ascli conf echo @ruby:"{'title'=>File.read('title.txt')}" --format=json
ascli conf echo @ruby:"{'title'=>ENV['MYTITLE']}" --format=json
{"title":"Test \" ' & \\"}
```

7.3 Commands, Options, Positional Values

Command line arguments are the units of command line, as parsed by the shell, typically separated by spaces (and called "argy").

ascli considers three types of command line arguments:

- Commands
- Options
- · Positional Values

ascli command subcommand --option-name=VAL1 VAL2

- executes command: command subcommand
- with one option: option name and its value: VAL1
- the command has one additional mandatory argument: VAL2

When the value of a command, option or argument is constrained by a fixed list of values. It is possible to use the first letters of the value only, provided that it uniquely identifies a value. For example ascli conf ov is the same as ascli config overview.

The value of options and arguments is evaluated with the Extended Value Syntax.

7.3.1 Commands

Commands are typically entity types or verbs to act on those entities.

Example:

ascli conf ascp info

- ascli is the executable executed by the shell
- conf is the first level command, and is also the name f the plugin to be used
- ascp is the second level command, and is also the name of the component (singleton)
- info is the third level command, and is also the action to be performed

Typically, commands are located at the beginning of the command line. Order is significant. The provided command must match one of the supported commands in the given context. If a wrong, or no command is provided when expected, an error message is displayed and the list of supported commands is displayed.

7.3.2 Options

All options, e.g. --log-level=debug, are command line arguments that:

- start with --
- have a name, in lowercase, using as word separator in name (e.g. --log-level=debug)
- have a value, separated from name with a =
- can be used by prefix, provided that it is unique. E.g. --log-l=debug is the same as --log-level=debug (avoid)

Exceptions:

• some options accept a short form, e.g. -Ptoto is equivalent to --preset=toto, refer to the manual or -h.

- some options (flags) don't take a value, e.g. -r
- the special option -- stops option processing and is ignored, following command line arguments are taken as arguments, including the ones starting with a -. Example:

```
ascli config echo -- --sample
"--sample"
```

Note: Here, --sample is taken as an argument, and not as an option, due to --.

Options may have an (hardcoded) default value.

Options can be placed anywhere on command line and evaluated in order.

Options are typically either:

- optional : typically to change the default behavior
- mandatory: typically, connection information are options that are mandatory (so they can be placed in a config file)

The value for *any* options can come from the following locations (in this order, last value evaluated overrides previous value):

- · Configuration file.
- · Environment variable
- · Command line

Environment variable starting with prefix: ASCLI_ are taken as option values, e.g. ASCLI_OPTION_NAME is for --option-name.

Options values can be displayed for a given command by providing the --show-config option: ascli node --show-config

7.3.3 Positional Values

Positional Values are typically mandatory values for a command, such as entity creation data.

If a Positional Values begins with –, then either use the <code>@val:</code> syntax (see Extended Values), or use the –- separator (see above).

The advantages of using a positional value instead of an option for the same are that the command line is shorter(no option name, just the position) and the value is clearly mandatory.

The disadvantage is that it is not possible to define a default value in a config file or environment variable like for options. Nevertheless, Extended Values syntax is supported, so it is possible to retrieve a value from the config file or environment variable.

7.4 Interactive Input

Some options and parameters are mandatory and other optional. By default, the tool will ask for missing mandatory options or parameters for interactive execution.

The behavior can be controlled with:

- --interactive=<yes|no> (default=yes if STDIN is a terminal, else no)
 - yes: missing mandatory parameters/options are asked to the user
 - no : missing mandatory parameters/options raise an error message
- --ask-options=<yes|no> (default=no)
 - optional parameters/options are asked to user

7.5 Output

Command execution will result in output (terminal, stdout/stderr). The information displayed depends on the action.

7.5.1 Types of output data

Depending on action, the output will contain:

- single_object: displayed as a 2 dimensional table: one line per attribute, first column is attribute name, and second is attribute value. Nested hashes are collapsed.
- object_list: displayed as a 2 dimensional table: one line per item, one column per attribute.
- value list: a table with one column.
- empty: nothingstatus: a message
- other_struct: a complex structure that cannot be displayed as an array

7.5.2 Format of output

By default, result of type single_object and object_list are displayed using format table. The table style can be customized with parameter: table_style (horizontal, vertical and intersection characters) and is ::: by default.

In a table format, when displaying "objects" (single, or list), by default, sub object are flattened (option flat_hash). So, object {"user":{"id":1,"name":"toto"}} will have attributes: user.id and user.name. Setting flat_hash to false will only display one field: "user" and value is the sub hash table. When in flatten mode, it is possible to filter fields by "dotted" field name.

Object lists are displayed one per line, with attributes as columns. Single objects are transposed: one attribute per line. If transposition of single object is not desired, use option: transpose_single set to no.

The style of output can be set using the format parameter, supporting:

text: Value as Stringtable: Text tableruby: Ruby codejson: JSON code

• jsonpp: JSON pretty printed

• yaml: YAML

· csv: Comma Separated Values

7.5.3 Option: select: Filter on columns values for object_list

+-----

Table output can be filtered using the select parameter. Example:

Note: select filters selected elements from the result of API calls, while the query parameters gives filtering parameters to the API when listing elements.

7.5.4 entity identifier

When a command is executed on a single entity, the entity is identified by a unique identifier that follows the command: e.g. ascli acc admin res user show 1234 where 1234 is the user identifier.

Note: The legacy option id is deprecated: --id=1234 as it does not provide the possibility to have sub-entities.

Only some commands provide the following capability: If the entity can also be uniquely identified by a name, then the name can be used instead of the identifier, using the **percent selector**: ascli aoc admin res user show %name:john where john is the user name.

Syntax: %<field>:<value>

7.5.5 Verbosity of output

Output messages are categorized in 3 types:

- info output contain additional information, such as number of elements in a table
- data output contain the actual output of the command (object, or list of objects)
- erroroutput contain error messages

The option display controls the level of output:

- info displays all messages: info, data, and error
- · data display data and error messages
- error display only error messages.

By default, secrets are removed from output: option show_secrets defaults to no, unless display is data, to allows piping results. To hide secrets from output, set option show secrets to no.

7.5.6 Selection of output object properties

By default, a table output will display one line per entry, and columns for each entries. Depending on the command, columns may include by default all properties, or only some selected properties. It is possible to define specific columns to be displayed, by setting the fields option to one of the following value:

- DEF: default display of columns (that's the default, when not set)
- · ALL : all columns available
- a,b,c: the list of attributes specified by the comma separated list
- Array extended value: for instance, @json:'["a","b","c"]' same as above
- +a,b,c : add selected properties to the default selection.
- -a,b,c : remove selected properties from the default selection.

7.6 Extended Value Syntax

Some options and arguments are specified by a simple string. But sometime it is convenient to read a value from a file, or decode it, or have a value more complex than a string (e.g. Hash table).

The extended value syntax is:

<0 or more decoders><nothing or some text value>

Decoders act like a function of value on right hand side. Decoders are recognized by the prefix: @ and suffix :

The following decoders are supported:

decoder	parameter	returns	description
base64	String	String	decode a base64 encoded string
csvt	String	Array	decode a titled CSV value
env	String	String	read from a named env var name, e.gpassword=@env:MYPASSVAR
file	String	String	read value from specified file (prefix ~/ is replaced with the users home folder), e.gkey=@fil
incps	Hash	Hash	include values of presets specified by key incps in input hash
json	String	any	decode JSON values (convenient to provide complex structures)
lines	String	Array	split a string in multiple lines and return an array
list	String	Array	split a string in multiple items taking first character as separator and return an array
path	String	String	performs path expansion on specified path (prefix ~/ is replaced with the users home folder), e.
preset	String	Hash	get whole option preset value by name. Sub-values can also be used using . as separator. e.g.
ruby	String	any	execute specified Ruby code
secret	None	String	Ask password interactively (hides input)
stdin	None	String	read from stdin (no value on right)
uri	String	String	read value from specified URL, e.gfpac=@uri:http://serv/f.pac
val	String	String	prevent decoders on the right to be decoded. e.gkey=@val:@file:foo sets the option key to
zlib	String	String	un-compress data

To display the result of an extended value, use the config echo command.

Example: read the content of the specified file, then, base64 decode, then unzip:

```
ascli config echo @zlib:@base64:@file:myfile.dat
```

Example: Create a value as a hash, with one key and the value is read from a file:

```
ascli config echo @ruby:'{"token_verification_key"=>File.read("mykey.txt")}'
```

Example: read a csv file and create a list of hash for bulk provisioning:

```
cat test.csv
name,email
lolo,laurent@example.com
toto,titi@tutu.tata
ascli config echo @csvt:@file:test.csv
+----+
| name | email |
+----+
| lolo | laurent@example.com |
| toto | titi@tutu.tata |
+-----+
```

Example: create a hash and include values from preset named "config" of config file in this hash

```
ascli config echo @incps:@json:'{"hello":true,"incps":["config"]}'
{"version"=>"0.9", "hello"=>true}
```

Note: @incps:@json:'{"incps":["config"]}' or @incps:@ruby:'{"incps"=>["config"]}' are equivalent to: @preset:config

7.7 Structured Value

Some options and parameters expect a Extended Value, i.e. a value more complex than a simple string. This is usually a Hash table or an Array, which could also contain sub structures.

For instance, a *transfer-spec* is expected to be a Extended Value.

Structured values shall be described using the Extended Value Syntax. A convenient way to specify a Extended Value is to use the @json: decoder, and describe the value in JSON format. The @ruby: decoder can also be used. For an array of hash tables, the @csvt: decoder can be used.

It is also possible to provide a Extended Value in a file using @json:@file:<path>

7.8 Configuration and Persistency Folder

ascli configuration and other runtime files (token cache, file lists, persistency files, SDK) are stored [config folder]: [User's home folder]/.aspera/ascli.

Note: [User's home folder] is found using Ruby's Dir.home (rb_w32_home_dir). It uses the HOME env var primarily, and on MS Windows it also looks at %HOMEDRIVE%%HOMEPATH% and %USERPROFILE%. ascli sets the env var %HOME% to the value of %USERPROFILE% if set and exists. So, on Windows %USERPROFILE% is used as it is more reliable than %HOMEDRIVE%%HOMEPATH%.

The [config folder] can be displayed using:

```
ascli config folder
/Users/kenji/.aspera/ascli
```

It can be overridden using the environment variable ASCLI_HOME.

Example (Windows):

```
set ASCLI_HOME=C:\Users\Kenji\.aspera\ascli
ascli config folder
```

When OAuth is used (AoC, Faspex4 api v4, Faspex5) ascli keeps a cache of generated bearer tokens in [config folder]/persist_store by default. Option cache_tokens (yes/no) allows to control if Oauth tokens are cached on file system, or generated for each request. The command config flush_tokens deletes all existing tokens. Tokens are kept on disk for a maximum of 30 minutes (TOKEN_CACHE_EXPIRY_SEC) and garbage collected after that. Tokens that can be refreshed are refreshed. Else tokens are re-generated if expired.

7.9 Configuration file

C:\Users\Kenji\.aspera\ascli

On the first execution of ascli, an empty configuration file is created in the configuration folder. Nevertheless, there is no mandatory information required in this file, the use of it is optional as any option can be provided on the command line.

Although the file is a standard YAML file, ascli provides commands to read and modify it using the config command.

All options for ascli can be set on command line, or by env vars, or using option presets in the configuration file.

A configuration file provides a way to define default values, especially for authentication parameters, thus avoiding to always having to specify those parameters on the command line.

The default configuration file is: \$HOME/.aspera/ascli/config.yaml (this can be overridden with option --config-file=path or equivalent env var).

The configuration file is simply a catalog of pre-defined lists of options, called: option presets. Then, instead of specifying some common options on the command line (e.g. address, credentials), it is possible to invoke the ones of a option preset (e.g. mypreset) using the option: -Pmypreset or --preset=mypreset.

7.9.1 Option preset

A option preset is simply a collection of parameters and their associated values in a named section in the configuration file

A named option preset can be modified directly using ascli, which will update the configuration file:

```
ascli config preset set|delete|show|initialize|update <option preset>
```

The command update allows the easy creation of option preset by simply providing the options in their command line format, e.g. :

ascli config preset update demo_server --url=ssh://demo.asperasoft.com:33001 --username=asperaweb --password=

• This creates a option preset demo_server with all provided options.

The command set allows setting individual options in a option preset.

```
ascli config preset set demo_server password my_password_here
```

The command initialize, like update allows to set several parameters at once, but it deletes an existing configuration instead of updating it, and expects a *Structured Value*.

```
ascli config preset initialize demo_server @json:'{"url":"ssh://demo.asperasoft.com:33001","username":"aspera
```

A full terminal based overview of the configuration can be displayed using:

```
ascli config preset over
```

A list of option preset can be displayed using:

```
ascli config preset list
```

A good practice is to not manually edit the configuration file and use modification commands instead. If necessary, the configuration file can opened in a text editor with:

```
ascli config open
```

Note: this starts the editor specified by env var EDITOR if defined.

Older format for commands are still supported:

```
ascli config preset set|delete|show|initialize|update <name>
ascli config preset over
ascli config preset list
```

7.9.2 Special Option preset: config

This preset name is reserved and contains a single key: version. This is the version of ascli which created the file.

7.9.3 Special Option preset: default

This preset name is reserved and contains an array of key-value, where the key is the name of a plugin, and the value is the name of another preset.

When a plugin is invoked, the preset associated with the name of the plugin is loaded, unless the option --no-default (or -N) is used.

Note: Special plugin name: config can be associated with a preset that is loaded initially, typically used for default values.

Operations on this preset are done using regular config operations:

```
ascli config preset set default _plugin_name_ _default_preset_for_plugin_
ascli config preset get default _plugin_name_
"_default_preset_for_plugin_"
```

7.9.4 Plugin: config: Configuration

Plugin config provides general commands for ascli:

- · Option preset, config file operations
- · wizard
- vault
- ascp

The default configuration for config is read for any plugin invocation, this allows setting global options, such as --log-level or --interactive. When ascli starts, it looks for the default Option preset and checks the value for config. If set, it loads the option values for any plugin used.

Note: If no global default is set by the user, the tool will use global_common_defaults when setting global parameters (e.g. conf ascp use)

Show current default (global) Option preset (config plugin):

```
$ ascli conf preset get default config
global_common_defaults
ascli conf preset set global_common_defaults version_check_days 0
If the default global Option preset is not set:
ascli conf preset set default config global_common_defaults
```

7.9.5 Config sample commands

```
config ascp connect info 'Aspera Connect for Windows' config ascp connect list config ascp connect version 'Aspera Connect for Windows' download 'Windows Installer' --to-folder=. config ascp connect version 'Aspera Connect for Windows' list config ascp connect version 'Aspera Connect for Windows' open documentation config ascp errors
```

```
config ascp info --sdk-folder=Tsdk_test_dir
config ascp install --sdk-folder=Tsdk_test_dir
config ascp products list
config ascp show
config ascp spec
config check_update
config coffee
config coffee --ui=text
config detect --url=https://faspex4.example.com/path
config detect --url=https://my_aoc_org.ibmaspera.com
config detect --url=https://node_simple.example.com/path
config doc
config doc transfer-parameters
config echo 'hello'
config echo @base64:SGVsbG8gV29ybGQK
config echo @csvt:@stdin:
config echo @env:USER
config echo @lines:@stdin:
config echo @list:,1,2,3
config echo @uri:/etc/hosts
config echo @uri:file:/etc/hosts
config echo @uri:http://www.ibm.com
config echo @uri:https://www.ibm.com
config echo @val:@file:no_such_file
config echo @zlib:@stdin:
config email_test --notif-to=my_recipient_email
config export
config flush_tokens
config genkey mykey
config plugin create mycommand T
config plugin list
config proxy_check --fpac=@file:examples/proxy.pac https://eudemo.asperademo.com
config wiz --url=https://my_aoc_org.ibmaspera.com --config-file=SAMPLE_CONFIG_FILE --pkeypath= --username=my_
config wiz --url=https://my_aoc_org.ibmaspera.com --config-file=SAMPLE_CONFIG_FILE --pkeypath= --username=my_
```

7.9.6 Format of file

The configuration file is a hash in a YAML file. Example:

```
config:
  version: 0.3.7
default:
  config: cli_default
  server: demo_server
cli_default:
  interactive: no
demo_server:
  url: ssh://demo.asperasoft.com:33001
  username: asperaweb
  password: my_password_here
```

We can see here:

- The configuration was created with ascli version 0.3.7
- the default option preset to load for server plugin is : demo_server
- the option preset demo_server defines some parameters: the URL and credentials
- the default option preset to load in any case is : cli_default

Two option presets are reserved:

config contains a single value: version showing the version used to create the configuration file. It is used to

check compatibility.

default is reserved to define the default option preset name used for known plugins.

The user may create as many option presets as needed. For instance, a particular option preset can be created for a particular application instance and contain URL and credentials.

Values in the configuration also follow the Extended Value Syntax.

Note: if the user wants to use the Extended Value Syntax inside the configuration file, using the config preset update command, the user shall use the @val: prefix. Example:

```
ascli config preset set my_aoc_org private_key @val:@file:"$HOME/.aspera/ascli/my_private_key"
```

This creates the option preset:

```
...
my_aoc_org:
    private_key: @file:"/Users/laurent/.aspera/ascli/my_private_key"
```

So, the key file will be read only at execution time, but not be embedded in the configuration file.

7.9.7 Options evaluation order

Some options are global, some options are available only for some plugins. (the plugin is the first level command).

Options are loaded using this algorithm:

- If option --no-default (or -N) is specified, then no default value is loaded for the plugin
- else it looks for the name of the plugin as key in section default, the value is the name of the default option preset for it, and loads it.
- If option --preset=<name or extended value hash> is specified (or -Pxxxx), this reads the option preset specified from the configuration file, or of the value is a Hash, it uses it as options values.
- · Environment variables are evaluated
- · Command line options are evaluated

Parameters are evaluated in the order of command line.

To avoid loading the default option preset for a plugin, use: -N

On command line, words in parameter names are separated by a dash, in configuration file, separator is an underscore. E.g. --xxx-yyy on command line gives xxx_yyy in configuration file.

The main plugin name is config, so it is possible to define a default option preset for the main plugin with:

```
ascli config preset set cli_default interactive no ascli config preset set default config cli_default
```

A option preset value can be removed with unset:

```
ascli config preset unset cli_default interactive
```

Example: Define options using command line:

```
ascli -N --url=_url_here_ --password=my_password_here --username=_name_here_ node --show-config
```

Example: Define options using a hash:

```
ascli -N --preset=@json:'{"url":"_url_here_","password":"my_password_here","username":"_name_here_"}' node --
```

7.9.8 Shares Examples

For Faspex, Shares, Node (including ATS, Aspera Transfer Service), Console, only username/password and url are required (either on command line, or from config file). Those can usually be provided on the command line:

```
ascli shares repo browse / --url=https://10.25.0.6 --username=john --password=my_password_here
```

This can also be provisioned in a config file:

· Build option preset

```
ascli config preset set shares06 url https://10.25.0.6 ascli config preset set shares06 username john ascli config preset set shares06 password my_password_here
```

This can also be done with one single command:

```
ascli config preset init shares06 @json:'{"url":"https://10.25.0.6","username":"john","password":"my_password or
```

ascli config preset update shares06 --url=https://10.25.0.6 --username=john --password=my_password_here

• Define this option preset as the default option preset for the specified plugin (shares)

ascli config preset set default shares shares06

Display the content of configuration file in table format

ascli config preset overview

· Execute a command on the shares application using default parameters

ascli shares repo browse /

7.10 Secret Vault

Password and secrets are command options. They can be provided on command line, env vars, files etc. A more secure option is to retrieve values from a secret vault.

The vault is used with options vault and vault_password.

vault defines the vault to be used and shall be a Hash, example:

```
{"type": "system", "name": "ascli"}
```

vault_password specifies the password for the vault. Although it can be specified on command line, for security reason you can hide the value. For example it can be securely specified on command line like this:

```
export ASCLI_VAULT_PASSWORD
read -s ASCLI_VAULT_PASSWORD
```

7.10.1 Vault: System key chain

Note: macOS only

It is possible to manage secrets in macOS key chain (only read supported currently).

```
--vault=@json:'{"type":"system","name":"ascli"}'
```

7.10.2 Vault: Encrypted file

It is possible to store and use secrets encrypted in a file.

```
--vault=@json:'{"type":"file","name":"vault.bin"}'
```

name is the file path, absolute or relative to the config folder ASCLI HOME.

7.10.3 Vault: Operations

For this use the config vault command.

Then secrets can be manipulated using commands:

- create
- show
- list

• delete

```
ascli conf vault create mylabel @json:'{"password":"my password here","description":"for this account"}'
```

7.10.4 Configuration Finder

When a secret is needed by a sub command, the command can search for existing configurations in the config file.

The lookup is done by comparing the service URL and username (or access key).

7.10.5 Securing passwords and secrets

A passwords can be saved in clear in a option preset together with other account information (URL, username, etc...). Example:

```
`ascli` conf preset update myconf --url=... --username=... --password=...

For a more secure storage one can do:

`ascli` conf preset update myconf --url=... --username=... --password=@val:@vault:myconf.password
`ascli` conf vault create myconf @json:'{"password":"my_password_here"}'
```

Note: use @val: in front of @vault: so that the extended value is not evaluated.

7.11 Private Key

Some applications allow the user to be authenticated using a private key (Server, AoC, Faspex5, ...). It consists in using a pair of keys: the private key and its associated public key. The same key can be used for multiple applications. Technically, a private key contains the public key, which can be extracted from it. The file containing the private key can optionally be protected by a passphrase. If the key is protected by a passphrase, then it will be prompted when used. (some plugins support option passphrase)

The following commands use the shell variable PRIVKEYFILE. Set it to the desired safe location of the private key. Typically, located in folder \$HOME/.ssh or \$HOME/.aspera/ascli:

```
PRIVKEYFILE=~/.aspera/ascli/my_private_key
```

Several methods can be used to generate a key pair.

The format expected for private keys is PEM.

7.11.1 ascli for key generation

The generated key is of type RSA, by default: 4096 bit. For convenience, the public key is also extracted with extension .pub. The key is not passphrase protected.

```
ascli config genkey ${PRIVKEYFILE} 4096
```

7.11.2 ssh-keygen

Both private and public keys are generated, option -N is for passphrase.

```
ssh-keygen -t rsa -b 4096 -m PEM -N '' -f ${PRIVKEYFILE}
```

7.11.3 openssl

To generate a private key pair with a passphrase the following can be used on any system:

```
openssl genrsa -passout pass:_passphrase_here_ -out ${PRIVKEYFILE} 4096 openssl rsa -pubout -in ${PRIVKEYFILE} -out ${PRIVKEYFILE}.pub
```

openss1 is sometimes compiled to support option -nodes (no DES, i.e. no passphrase, e.g. on macOS). In that case, add option -nodes instead of -passout pass:_passphrase_here_ to generate a key without passphrase.

If option -nodes is not available, the passphrase can be removed using this method:

```
openssl rsa -passin pass:_passphrase_here_ -in ${PRIVKEYFILE} -out ${PRIVKEYFILE}.no_des
mv ${PRIVKEYFILE}.no_des ${PRIVKEYFILE}

To change (or add) the passphrase for a key do:
openssl rsa -des3 -in ${PRIVKEYFILE} -out ${PRIVKEYFILE}.with_des
mv ${PRIVKEYFILE}.with_des ${PRIVKEYFILE}
```

7.12 SSL CA certificate bundle

ascli uses the Ruby openssl gem, which uses the openssl library. Certificates are checked against the Ruby default certificate store OpenSSL::X509::DEFAULT_CERT_FILE and OpenSSL::X509::DEFAULT_CERT_DIR, which are typically the ones of openssl on Unix-like systems (Linux, macOS, etc..).

To display the current root certificate store locations:

```
ascli conf echo @ruby:'[OpenSSL::X509::DEFAULT_CERT_FILE,OpenSSL::X509::DEFAULT_CERT_DIR]'
```

Ruby's default values can be overridden by env vars: SSL_CERT_FILE and SSL_CERT_DIR.

ascp also needs to validate certificates when using **WSS**. By default, ascp uses primarily certificates from hard-coded path (e.g. on macOS: /Library/Aspera/ssl) for WSS. ascli overrides and sets the default Ruby certificate path as well for ascp using -i switch.

To update ascli trusted root certificates, just update your system's root certificates or use env vars specified here above.

7.13 Plugins

ascli uses a plugin mechanism. The first level command (just after ascli on the command line) is the name of the concerned plugin which will execute the command. Each plugin usually represents commands sent to a specific application. For instance, the plugin faspex allows operations on the application "Aspera Faspex".

Available plugins can be found using command:

ascli conf plugin list

7.13.1 Create your own plugin

By default plugins are looked-up in folders specified by (multi-value) option plugin_folder:

```
ascli --show-config --select=@json:'{"key":"plugin_folder"}'
```

You can create the skeleton of a new plugin like this:

```
ascli conf plugin create foo .
Created ./foo.rb
ascli --plugin-folder=. foo
```

7.13.2 Plugins: Application URL and Authentication

ascli comes with several Aspera application plugins.

REST APIs of Aspera legacy applications (Aspera Node, Faspex, Shares, Console, Orchestrator, Server) use simple username/password authentication: HTTP Basic Authentication.

Those are using options:

- url
- username
- · password

Those can be provided using command line, parameter set, env var, see section above.

Aspera on Cloud relies on Oauth, refer to the Aspera on Cloud section.

7.14 Logging, Debugging

The gem is equipped with traces, mainly for debugging and learning APIs. By default logging level is warn and the output channel is stderr. To increase debug level, use parameter log_level (e.g. using command line --log-level=xx, env var ASCLI_LOG_LEVEL, or a parameter in the configuration file).

It is also possible to activate traces before log facility initialization using env var ASCLI_LOG_LEVEL.

By default passwords and secrets are removed from logs. Use option log_secrets set to yes to reveal secrets in logs.

Available loggers: stdout, stderr, syslog.

Available levels: debug, info, warn, error.

Note: When using the direct agent (ascp), additional transfer logs can be activated using ascp options and ascp_args, see direct.

Examples:

display debugging log on stdout:

```
ascli conf pre over --log-level=debug --logger=stdout
```

• log errors to syslog:

```
ascli conf pre over --log-level=error --logger=syslog
```

When ascli is used interactively in a shell, the shell itself will usually log executed commands in the history file.

7.15 Learning Aspera Product APIs (REST)

ascli uses mainly Aspera applications REST APIs. To display HTTP calls, use argument -r or --rest-debug, this is useful to display exact content of HTTP requests and responses.

In order to get traces of execution, use argument: --log-level=debug

7.16 HTTP socket parameters

If the server does not provide a valid certificate, use option: --insecure=yes.

HTTP socket parameters can be adjusted using option http_options:

parameter	default
read_timeout	60
write_timeout	60
open_timeout	60
keep_alive_timeout	2

Values are in set *seconds* and can be of type either integer or float. Default values are the ones of Ruby: refer to the Ruby library: Net::HTTP.

Like any other option, those can be set either on command line, or in config file, either in a global preset or server-specific one.

Example:

```
ascli aoc admin res package list --http-options=@json:'{"read timeout":10.0}'
```

7.17 Graphical Interactions: Browser and Text Editor

Some actions may require the use of a graphical tool:

- a browser for Aspera on Cloud authentication (web auth method)
- · a text editor for configuration file edition

By default ascli assumes that a graphical environment is available on windows, and on other systems, rely on the presence of the DISPLAY environment variable. It is also possible to force the graphical mode with option --ui:

- --ui=graphical forces a graphical environment, a browser will be opened for URLs or a text editor for file edition.
- --ui=text forces a text environment, the URL or file path to open is displayed on terminal.

7.18 Proxy

There are several types of network connections, each of them use a different mechanism to define a (forward) proxy:

- Ruby HTTP: REST and HTTPGW client
- Legacy Aspera HTTP/S Fallback
- Aspera FASP

Refer to the following sections.

7.19 Proxy for REST and HTTPGW

There are two possibilities to define an HTTP proxy to be used when Ruby HTTP is used.

The http_proxy environment variable (lower case, preferred) can be set to the URL of the proxy, e.g. http://myproxy.org.net:31 Refer to Ruby find proxy.

Note: Ruby expects a URL and myproxy.org.net:3128 alone is not accepted.

```
export http_proxy=http://proxy.example.com:3128
```

The fpac option (function for proxy auto config) can be set to a Proxy Auto Configuration (PAC) javascript value. To read the script from a URL (http:, https: and file:), use prefix: @uri:. A minimal script can be specified to define the use of a local proxy:

```
ascli --fpac='function FindProxyForURL(url, host){return "PROXY localhost:3128"}' ...
```

The result of a PAC file can be tested with command: config proxy_check. Example, using command line option:

```
ascli conf proxy_check --fpac='function FindProxyForURL(url, host) {return "PROXY proxy.example.com:3128;DIRECT

ascli config proxy_check --fpac=@file:./proxy.pac http://www.example.com

PROXY proxy.example.com:8080
```

```
PROXY proxy.example.com:8080
```

If the proxy requires credentials, then use option proxy_credentials with username and password provided as an Array:

```
ascli --proxy-credentials=@json:'["__username_here__","__password_here__"]' ...
ascli --proxy-credentials=@list::_username_here__:_password_here__ ...
```

ascli config proxy_check --fpac=@uri:http://server/proxy.pac http://www.example.com

7.20 Proxy for Legacy Aspera HTTP/S Fallback

Only supported with the direct agent: To specify a proxy for legacy HTTP fallback, use ascp_native option -x and ascp_args: --transfer-info=@json:'{"ascp_args":["-x","url_here"]}'. Alternatively, set the *transfer-spec* parameter: EX_http_proxy_url.

7.21 FASP proxy (forward) for transfers

To specify a FASP proxy (forward), set the *transfer-spec* parameter: proxy (only supported with the direct agent).

7.22 FASP configuration

The config plugin also allows specification for the use of a local FASP **client**. It provides the following commands for ascp subcommand:

- show: shows the path of ascp used
- use : list,download connect client versions available on internet
- products: list Aspera transfer products available locally
- · connect: list,download connect client versions available on internet

7.22.1 Show path of currently used ascp

7.22.2 Selection of ascp location for direct agent

By default, ascli uses any found local product with ascp, including SDK.

To temporarily use an alternate ascp path use option ascp_path (--ascp-path=)

For a permanent change, the command config ascp use sets the same parameter for the global default.

Using a POSIX shell:

```
ascli config ascp use @path:'~/Applications/Aspera CLI/bin/ascp'
ascp version: 4.0.0.182279
Updated: global_common_defaults: ascp_path <- /Users/laurent/Applications/Aspera CLI/bin/ascp
Saved to default global preset global_common_defaults
Windows:
ascli config ascp use C:\Users\admin\.aspera\ascli\sdk\ascp.exe
ascp version: 4.0.0.182279
Updated: global_common_defaults: ascp_path <- C:\Users\admin\.aspera\ascli\sdk\ascp.exe
Saved to default global preset global_common_defaults
```

If the path has spaces, read section: Shell and Command line parsing.

7.22.3 List locally installed Aspera Transfer products

Locally installed Aspera products can be listed with:

ascli config ascp products list

+	++ app_root
IBM Aspera SDK Aspera Connect IBM Aspera CLI IBM Aspera High-Speed Transfer Server	/Users/laurent/.aspera/ascli/sdk /Applications/Aspera Connect.app /Users/laurent/Applications/Aspera CLI /Library/Aspera

7.22.4 Selection of local client for ascp for direct agent

If no ascp is selected, this is equivalent to using option: --use-product=FIRST.

Using the option use_product finds the ascp binary of the selected product.

To permanently use the ascp of a product:

```
ascli config ascp products use 'Aspera Connect' saved to default global preset /Users/laurent/Applications/Aspera Connect.app/Contents/Resources/ascp
```

7.22.5 Installation of Connect Client on command line

ascli config ascp connect list

+	title	version
urn:uuid:589F9EE5-0489-4F73-9982-A612FAC70C4E urn:uuid:A3820D20-083E-11E2-892E-0800200C9A66 urn:uuid:589F9EE5-0489-4F73-9982-A612FAC70C4E urn:uuid:55425020-083E-11E2-892E-0800200C9A66 urn:uuid:D8629AD2-6898-4811-A46F-2AF386531BFF urn:uuid:97F94DF0-22B1-11E2-81C1-0800200C9A66	Aspera Connect for Windows Aspera Connect for Windows 64-bit Aspera Connect for Windows XP Aspera Connect for Windows XP Aspera Connect for Mac Intel	3.11.2.63 3.11.2.63 3.11.2.63 3.11.2.63 3.11.2.63 3.11.2.63

ascli config ascp connect version 'Aspera Connect for Mac Intel' list

title	Ċ	type	•	href
Mac Intel Installer Mac Intel Installer Aspera Connect for Mac HTML Documentation Aspera Connect for Mac Release Notes			1	bin/IBMAsperaConnectInstaller-3.11.2 bin/IBMAsperaConnectInstallerOneClic https://www.ibm.com/docs/en/aspera-c https://www.ibm.com/docs/en/aspera-c

ascli config ascp connect version 'Aspera Connect for Mac Intel' download enclosure --to-folder=.

Time: 00:00:02 ========= 100% 27766 KB/sec Time: 00:00:02 Downloaded: IBMAsperaConnectInstaller-3.11.2.63.dmg

7.23 Transfer Clients: Agents

Some of the actions on Aspera Applications lead to file transfers (upload and download) using the FASP protocol (ascp).

When a transfer needs to be started, a *transfer-spec* has been internally prepared. This *transfer-spec* will be executed by a transfer client, here called **Transfer Agent**.

There are currently 3 agents, set with option transfer:

- direct: a local execution of ascp
- connect: use of a local Connect Client
- node: use of an Aspera Transfer Node (potentially remote).
- httpgw: use of an Aspera HTTP Gateway
- trsdk: use of Aspera Transfer SDK

Note: All transfer operations are seen from the point of view of the agent. For example, a node agent executing an "upload", or "package send" operation will effectively push files to the related server from the agent node.

ascli standardizes on the use of a *transfer-spec* instead of *native* ascp options to provide parameters for a transfer session, as a common method for those three Transfer Agents.

Specific options for agents are provided with option transfer_info, cumulatively.

7.23.1 Direct

The direct agent directly executes a local ascp. This is the default agent for ascli. This is equivalent to option --transfer=direct. ascli will detect locally installed Aspera products, including SDK, and use ascp from that component. Refer to section FASP.

The transfer_info option accepts the following optional parameters to control multi-session, Web Socket Session and Resume policy:

Name	Туре	Description
WSS	Bool	Web Socket SessionEnable use of web socket session in case it is availableDefault: true
ascp_args	Array	Array of strings with native ascp argumentsUse this instead of deprecated EX_ascp_args.Default:
spawn_timeout_sec	Float	Multi sessionVerification time that ascp is runningDefault: 3
spawn delay sec	Float	Multi sessionDelay between startup of sessionsDefault: 2
multi incr udp	Bool	Multi SessionIncrement UDP port on multi-sessionIf true, each session will have a different UDP p
resume	Hash	ResumeparametersSee below
resume.iter_max	int	ResumeMax number of retry on errorDefault: 7
resume.sleep_initial	int	ResumeFirst Sleep before retryDefault: 2
resume.sleep_factor	int	ResumeMultiplier of sleep period between attemptsDefault: 2
resume.sleep_max	int	ResumeDefault: 60

In case of transfer interruption, the agent will **resume** a transfer up to iter_max time. Sleep between iterations is:

```
max( sleep_max , sleep_initial * sleep_factor ^ (iter_index-1) )
```

Some transfer errors are considered "retryable" (e.g. timeout) and some other not (e.g. wrong password). The list of known protocol errors and retry level can be listed:

```
ascli config ascp errors
```

Examples:

```
ascli ... --transfer-info=@json:'{"wss":true,"resume":{"iter_max":20}}'
ascli ... --transfer-info=@json:'{"spawn_delay_sec":2.5,"multi_incr_udp":false}'
```

Note: The direct agent supports additional transfer_spec parameters starting with EX_ (extended). But it is preferred to use the option transfer_info with parameter ascp_args.

This can be useful to activate logging using option -L of ascp. For example the option --transfer-info=@json:'{"ascp_args":["-will activate debug level 2 for ascp (DD), and display those logs on the terminal (-). This is useful if the transfer fails. To store ascp logs in file aspera-scp-transfer.log in a folder, use --transfer-info=@json:'{"ascp_args":["-L","/path/to/folder"]]

Note: When transfer agent <u>direct</u> is used, the list of files to transfer is provided to <u>ascp</u> using either <u>--file-list</u> or <u>--file-pair-list</u> and a file list (or pair) file generated in a temporary folder. (unless <u>--file-list</u> or <u>--file-pair-list</u> is provided using transfer_info parameter ascp_args).

In addition to standard methods described in section File List, it is possible to specify the list of file using those additional methods:

Using the pseudo transfer-spec parameter EX_file_list

```
--sources=@ts --ts=@json:'{"EX_file_list":"file_list.txt"}'

• Using option transfer_info parameter ascp_args
--sources=@ts --transfer-info=@json:'{"ascp_args":["--file-list","myfilelist"]}'
```

Note: File lists is shown here, there are also similar options for file pair lists.

Note: Those 2 additional methods avoid the creation of a copy of the file list: if the standard options --sources=@lines:@file:... --src-type=... are used, then the file is list read and parsed, and a new file list is created in a temporary folder.

Note: Those methods have limitations: they apply **only** to the **direct** transfer agent (i.e. local ascp) and not for Aspera on Cloud.

This agent supports a local configuration file: aspera.conf where Virtual links can be configured:

On a server (HSTS), the following commands can be used to set a global virtual link:

```
asconfigurator -x 'set_trunk_data;id,1;trunk_name,in;trunk_capacity,45000;trunk_on,true'
asconfigurator -x 'set_trunk_data;id,2;trunk_name,out;trunk_capacity,45000;trunk_on,true'
asconfigurator -x 'set_node_data;transfer_in_bandwidth_aggregate_trunk_id,1'
asconfigurator -x 'set_node_data;transfer_out_bandwidth_aggregate_trunk_id,2'
```

But this command is not available on clients, so edit the file aspera.conf, you can find the location with: ascli conf ascp info --fields=aspera_conf and modify the sections default and trunks like this for a global 100 Mbps virtual link:

```
<?xml version='1.0' encoding='UTF-8'?>
<CONF version="2">
    <default>
        <transfer>
            <in>
                <bandwidth>
                     <aggregate>
                         <trunk_id>1</trunk_id>
                     </aggregate>
                </bandwidth>
            </in>
            <011t>
                <bandwidth>
                     <aggregate>
                         <trunk_id>2</trunk_id>
                     </aggregate>
                </bandwidth>
            </out>
        </transfer>
    </default>
    <trunks>
        <trunk>
            <id>1</id>
            <name>in</name>
            <on>true</on>
            <capacity>
                <schedule format="ranges">1000000</schedule>
            </capacity>
        </trunk>
        <trunk>
            <id>2</id>
            <name>out</name>
            <capacity>
                <schedule format="ranges">1000000</schedule>
```

It is also possible to set a schedule with different time and days, for example for the value of schedule:

start=08 end=19 days=mon,tue,wed,thu capacity=900000;1000000

7.23.2 IBM Aspera Connect Client GUI

By specifying option: --transfer=connect, ascli will start transfers using the locally installed Aspera Connect Client. There are no option for transfer_info.

7.23.3 Aspera Node API: Node to node transfers

By specifying option: --transfer=node, ascli starts transfers in an Aspera Transfer Server using the Node API, either on a local or remote node. Parameters provided in option transfer_info are:

Name	Type	Description
url	string	URL of the node APIMandatory
username	string	node api user or access keyMandatory
password	string	password, secret or bearer tokenMandatory
root_id	string	password or secretMandatory only for bearer token

Like any other option, transfer_info can get its value from a pre-configured option preset: --transfer-info=@preset:_name_here or be specified using the extended value syntax: --transfer-info=@json:'{"url":"https://...", "username":"_user_here_"

If transfer_info is not specified and a default node has been configured (name in node for section default) then this node is used by default.

If the password value begins with Bearer then the username is expected to be an access key and the parameter root_id is mandatory and specifies the root file id on the node. It can be either the access key's root file id, or any authorized file id underneath it.

7.23.4 HTTP Gateway

If it possible to send using a HTTP gateway, in case FASP is not allowed.

Parameters provided in option transfer_info are:

Name	Туре	Description
url upload_bar_refresh_sec upload_chunk_size api_version synchronous	string float int string bool	URL of the HTTP GWMandatory Refresh rate for upload progress bar Size in bytes of chunks for upload v1 or v2, for force use of version wait for each message acknowledgment

Example:

ascli faspex package recv 323 --transfer=httpgw --transfer-info=@json:'{"url":"https://asperagw.example.com:9

Note: The gateway only supports transfers authorized with a token.

7.23.5 Transfer SDK

Another possibility is to use the Transfer SDK daemon (asperatransferd).

By default it will listen on local port 55002 on 127.0.0.1.

The gem grpc was removed from dependencies, as it requires compilation of a native part. So, to use the Transfer SDK you should install this gem:

```
gem install grpc
```

On Windows the compilation may fail for various reasons (3.1.1):

- cannot find -lx64-ucrt-ruby310 → copy the file [Ruby main dir]\lib\libx64-ucrt-ruby310.dll.a to [Ruby main dir]\lib\libx64-ucrt-ruby310.a (remove the dll extension)
- conflicting types for 'gettimeofday' \rightarrow edit the file [Ruby main dir]/include/ruby-[version]/ruby/win32.h and change the signature of gettimeofday to gettimeofday(struct timeval *, void *), i.e. change struct timezone to void

7.24 Transfer Specification

Some commands lead to file transfer (upload/download). All parameters necessary for this transfer are described in a *transfer-spec* (Transfer Specification), such as:

- · server address
- · transfer user name
- credentials
- file list
- etc...

ascli builds the *transfer-spec* internally, so it is not necessary to provide additional parameters on the command line for this transfer.

The *transfer-spec* is a Hash (dictionary), so it is described on the command line with the Extended Value Syntax.

It is possible to modify or add any of the supported *transfer-spec* parameter using the ts option. The ts option accepts a Structured Value containing one or several *transfer-spec* parameters in a Hash. Multiple ts options on command line are cumulative, and Hash is deeply merged. To remove a (deep) key from transfer spec, set the value to null.

Note: Default transfer spec values can be displayed with command: config ascp info --flat-hash=no under field ts.

It is possible to specify ascp options when the transfer option is set to direct using transfer_info option parameter: ascp_args. Example: --transfer-info=@json:'{"ascp_args":["-1","100m"]}'. This is especially useful for ascp command line parameters not supported in the transfer spec.

The use of a *transfer-spec* instead of ascp parameters has the advantage of:

- common to all Transfer Agent
- not dependent on command line limitations (special characters...)

7.25 Transfer Parameters

All standard *transfer-spec* parameters can be specified. *transfer-spec* can also be saved/overridden in the config file.

References:

- Aspera Node API Documentation → /opt/transfers
- Aspera Transfer SDK Documentation → Guides → API Ref → Transfer Spec V1
- Aspera Connect SDK → search The parameters for starting a transfer.

Parameters can be displayed with commands:

```
ascli config ascp spec
ascli config ascp spec --select=@json:'{"d":"Y"}' --fields=-d,n,c
```

Columns:

- D=Direct (local ascp execution)
- N=Node API

• C=Connect Client

ascp argument or environment variable is provided in description.

Fields with EX_ prefix are extensions to transfer agent direct. (only in ascli).

Field	Туре	D	Ν	С	Description
apply_local_docroot	bool	Υ			(apply-local-docroot)
authentication	string			Υ	value=token for SSH bypass keys, else password asked if not provid
cipher	string	Υ	Υ	Υ	In transit encryption type. Allowed values: none, aes-128, aes-192, a
cipher_allowed	string	Υ	Υ	Υ	returned by node API. Valid literals include "aes-128" and "none".
content_protection	string	Υ	Υ	Υ	Enable client-side encryption at rest. (CSEAR, content protection)All
content_protection_password	string	Υ	Υ	Υ	Specifies CSEAR password. (content protection)(env:ASPERA_SCF
cookie	string	Υ	Υ	Υ	Metadata for transfer specified by application(env:ASPERA_SCP_C
create_dir	bool	Υ	Υ	Υ	Specifies whether to create new directories.(-d)
delete_before_transfer	bool	Υ	Υ	Υ	Before transfer, delete files that exist at the destination but not at the
delete_source	bool	Υ	Υ		Remove SRC files after transfer success(remove-after-transfer)
destination_root	string	Υ	Υ	Υ	Destination root directory.
dgram_size	int	Υ	Υ	Υ	UDP datagram size in bytes(-Z {int})
direction	string	Υ	Υ	Υ	Direction of transfer (on client side)Allowed values: send, receive(r
exclude_newer_than	int	Υ			skip src files with mtime > arg(exclude-newer-than {int})
exclude_older_than	int	Υ			skip src files with mtime < arg(exclude-older-than {int})
fasp_port	int	Υ	Υ	Υ	Specifies fasp (UDP) port.(-O {int})
file_checksum	string	Υ	Υ		Enable checksum reporting for transferred files by specifying the has
http_fallback	boolstring	Υ	Υ	Υ	When true(1), attempts to perform an HTTP transfer if a FASP transf
http fallback port	int	Υ			Specifies http port when no cipher is used(-t {int})
https_fallback_port	int	Υ	Υ	Υ	Specifies https port when cipher is used(-t {int})
lock_min_rate	bool	Υ	Υ	Υ	
lock_min_rate_kbps	bool	Υ	Υ	Υ	
lock_rate_policy	bool	Υ	Υ	Υ	
lock_target_rate	bool	Υ	Υ	Υ	
lock_target_rate_kbps	bool	Υ	Υ	Υ	
min_rate_cap_kbps	int	Υ	Υ	Υ	
min_rate_kbps	int	Υ	Υ	Υ	Set the minimum transfer rate in kilobits per second.(-m {int})
move_after_transfer	string	Υ	Υ		The relative path to which the files will be moved after the transfer at
multi_session	int	Υ	Υ	Υ	Use multi-session transfer. max 128.Each participant on one host ne
multi_session_threshold	int	Υ	Υ		Split files across multiple ascp sessions if their size in bytes is greate
overwrite	string	Υ	Υ	Υ	Overwrite destination files with the source files of the same name. All
password	string		Υ		Password for local Windows user when transfer user associated with
paths	array	Υ	Υ	Υ	Array of path to the source (required) and a path to the destination (o
precalculate_job_size	bool	Υ	Υ	Υ	Specifies whether to precalculate the job size.(precalculate-job-size
preserve_access_time	bool	Υ	Υ	Υ	(preserve-access-time)
preserve_acls	string	Υ			Preserve access control lists. Allowed values: none, native, metafile(
preserve_creation_time	bool	Υ	Υ	Υ	(preserve-creation-time)
preserve_file_owner_gid	bool	Υ			Preserve the group ID for a file owner(preserve-file-owner-gid)
preserve_file_owner_uid	bool	Υ			Preserve the user ID for a file owner(preserve-file-owner-uid)
preserve_modification_time	bool	Υ	Υ	Υ	(preserve-modification-time)
preserve_remote_acls	string	Υ			Preserve remote access control lists. Allowed values: none, native, n
preserve_source_access_time	bool	Υ			Preserve the time logged for when the source file was accessed(pr
preserve_times	bool	Υ	Υ	Υ	(preserve-times)
proxy	string	Υ			Specify the address of the Aspera high-speed proxy server.dnat(s)://
rate_policy	string	Y	Υ	Υ	The transfer rate policy to use when sharing bandwidth. Allowed value
rate_policy_allowed	string			Y	Specifies most aggressive rate policy that is allowed.Returned by no
remote_host	string	Υ	Υ	Ϋ́	IP or fully qualified domain name of the remote server(host {string})
		-	-		in a second seco
remote_password	string	Υ	Υ	Υ	SSH session password(env:ASPERA_SCP_PASS)

emove_empty_directories bool Y Y Specifies whether to remove empty directories.(-remove-empty-directories and remove empty_source_directory bool Y Y Y Must also have remove_after_transfer set to true, Defaults to false esume_policy string Y Y Y Must also have remove_after_transfer set to true, Defaults to false esume_policy string Y Y Y Path to be prepended to each source path. This is either a conventifucure_root_id string Y Y Path to be prepended to each source path. This is either a conventifucure_root_id string Y Y Specifies how long to wait before retrying transfer. (e.g. "5min") Y Path to be prepended to each source path. This is either a conventifucure_root_id string Y Y Specifies SSH (TCP) port. Default: local:22, other-33001(-P (int)) Private key used for SSH authentication. Shall look like:BEGIN The passphrase associated with the transfer user's SSH private key used for SSH authentication. Shall look like:BEGIN The passphrase associated with the transfer user's SSH private key used for SSH authentication. Shall look like:BEGIN The passphrase associated with the transfer user's SSH private key used for SSH authentication. Shall look like:	Field	Туре	D	N	С	Description
emove_empty_source_directory bool y y y y Must also have remove_after_transfer set to true, Defaults to false sesume_policy string y y y y Earth to be prepended to each source path. This is either a convention cource_root string y y y y Specifies how long to wait before retrying transfer. (e.g. "5min") source_root string y y y Path to be prepended to each source path. This is either a convention cource_root directory. Required when using Bears specify the prefix to be stripped off from each source object. The rest sh_port int y y y Specifies SSH (TCP) port. Default: local:22, other:33001(-P {int}) Private key used for SSH authentication. Shall look like: ——BEGIN sh_private_key_passphrase string y y y Check it against server SSH host key fingerprint(—check-sshfp {string y y y Metadata for transfer as JSON(—tags64 (conversion){hash}) arget_rate_kbps int y Returned by upload/download_setup node API. Specifies desired speed for the transfer. (-I {int}) arget_rate_percentage string y y y y title string y y y title string y y y y Specifies desired speed for the transfer. (-I {int}) arget_rate_percentage string y y y y title private y title y tring y y y y title private y title y tring y y y y title private y title y tring y y y y title y	remove_after_transfer	bool	Υ	Υ		Remove SRC files after transfer success(remove-after-transfer)
emove_skipped bool Y Y Y Must also have remove_after_transfer set to true, Defaults to false esume_policy string Y Y Y If a transfer is interrupted or fails to finish, resume without re-transfer terry_duration stringint Y Y Specifies how long to wait before retrying transfer. (e.g. "5min") source_root string Y Y Path to be prepended to each source path.This is either a convention to the source root directory. Required when using Beare ric base string Y Y Specifies SSH (Tc) be stripped off from each source object. The resh port int Y Y Y Specifies SSH (Tc) port. Default: local:22, other:33001(-P (int)) rivate_key string Y Specifies SSH (Tc) port. Default: local:22, other:33001(-P (int)) rivate_key_passphrase string Y String Y Specifies SSH (Tc) port. Default: local:22, other:33001(-P (int)) rivate_key_passphrase string Y String Y Specifies SSH (Tc) port. Default: local:22, other:33001(-P (int)) rivate_key_passphrase string Y String Y Specifies SSH (Tc) port. Default: local:22, other:33001(-P (int)) rivate_key_passphrase string Y Y Specifies SSH (Tc) port. Default: local:22, other:33001(-P (int)) rivate_key_passphrase string Y Y Y Handle source side symbolic linksAllowed values: follow, copy, copy ags hash Y Y Y Handle source side symbolic linksAllowed values: follow, copy, copy ags hash Y Y Y Metadata for transfer as JSON(-tags64 (conversion){hash}} arget_rate_cap_kbps int Y Returned by upload/wonload_setup node API. arget_rate_percentage string Y Y Y Specifies desired speed for the transfer.(-I {int}) arget_rate_percentage string Y Y Y Title of the transfer set to true, default ascp looks for license file near no read source(-no-read) secify version of protocol secify per sion of protocol int Y Y Y TCP port used for websocket service feed DEPRECATED: Use parameter ascp_args in option transfer_infoA DEPRECATED: Use standard spec parameter: content_protection source file list source file pair list Specify the proxy server address used by HTTP Fallback(-x {string Y Server password set of the stransfer proxy server	remove_empty_directories	bool	Υ	Υ		Specifies whether to remove empty directories.(remove-empty-dire
esume_policy string Y Y Y If a transfer is interrupted or fails to finish, resume without re-transfetry_duration stringint Y Y Specifies how long to wait before retrying transfer. (e.g. "5min") source_root string Y Y Path to be prepended to each source path.This is either a conventive source proot in string Y Y Specifies Set on the prepended to each source path.This is either a conventive source proot directory. Required when using Beare Set on Set on the string Y Y Specifies SSH (TCP) port. Default: local:22, other:33001(-P (int)) sh_private_key string Y Y Specifies SSH (TCP) port. Default: local:22, other:33001(-P (int)) sh_private_key_passphrase string Y Y Specifies SSH (TCP) port. Default: local:22, other:33001(-P (int)) sh_private_key_passphrase string Y Y Y Check it against server SSH host key fingerprint(check-sshfp (str) symlink_policy string Y Y Y Metadata for transfer as JSON(tags64 (conversion){hash}) arget_rate_cap_kbps int Y Y Y Specifies desired speed for the transfer.(-I {int}) arget_rate_percentage string Y Y Y Title of the transfer sasic or ATM (Also arg -W)(env:ASPE specify version of protocol vss_enabled bool Y Y Server has Web Socket service enabled vss_port int Y Y Y TCP port used for websocket service feed DEPRECATED: Use standard spec parameter: content_protection_source file pair list X_file_pair_list string Y Specify the prefix to be stripped off from each source object. The refix to be stripped off from each source object. The refix to be stripped off from each source object. The refix to be stripped off from each source object. The refix to be stripped off from each source object. The refix to be stripped off from each source object. The refix to be stripped off from each source object. The refix to be stripped off from each source file pair list Specify the prefix to be stripped off from each source. The fixed object. The refix to be stripped off from each source of the transfer. (-I {int}) arget_rate_stripped object. The refix to be stripped off from each source. The fixed objec	remove_empty_source_directory	bool	Υ			Remove empty source subdirectories and remove the source director
etry_duration string to tring the try_duration string to troce protection string to the transfer (e.g. "5min") source protection string to the transfer (e.g. "5min") source protection string the trock to the transfer (e.g. "5min") to the prepended to each source path. This is either a convention to the transfer (e.g. "5min") the prepended to each source path. This is either a convention to the transfer (e.g. "5min") the prepended to each source path. This is either a convention to the transfer using the transfer using the prefix to be stripped off from each source object. The resemble of the source root directory. Required when using Bears to the transfer using the prefix to be stripped off from each source object. The resemble of the source root directory. Required when using Bears to the transfer as the provided when using Bears to the source strip to the transfer to be stripped off from each source object. The resemble of the source root directory. Required when using Bears to the source strips to the stripped off from each source object. The resemble of the source root directory. Required when using Bears to the string the prefix to be stripped off from each source object. The resemble of the source strips the prefix to be stripped off from each source object. The resemble of the source strips and the strips and the private key specify the prefix to be stripped off from each source object. The resemble of the source strips and the strips as surports. The file I bot of the source strips as the strip than the transfer is source file pair list. The proxy are address used by HTTP Fallback(-x {string the prefix to be stripped off from each source on the provided of the source and used for Aspera proxy server authentication. May be over the preparation of the stripped off the source strips and the stripped off the source strips and the stripped off from each source on the stripped off from each source on the stripped off the source restricts of the substripped of the source from the stripped off stripped off stri	remove_skipped	bool	Υ	Υ	Υ	Must also have remove_after_transfer set to true, Defaults to false, i
source_root string Y Y Y Path to be prepended to each source path.This is either a convention source_root_id string Y Y The file ID of the source root directory. Required when using Bears strice base string Y Y Specifies SSH (TCP) port. Default: local:22, other:33001(-P (intt)) sh_private_key string Y Private key used for SSH authentication.Shall look like:BEGIN The passphrase associated with the transfer user's SSH private key shall be string Y Y Y Check it against server SSH host key fingerprint(check-shfp {string Y Y Y Handle source side symbolic links.Allowed values: follow, copy, copy aga hash Y Y Y Metadata for transfer as JSON(tags64 (conversion){hash}) arget_rate_cap_kbps int Y Y Specifies desired speed for the transfer.(-I {int}) arget_rate_bps int Y Y Y Specifies desired speed for the transfer.(-I {int}) arget_rate_percentage string Y Y Y Authorization token: Bearer, Basic or ATM (Also arg -W)(env:ASPE use_ascp4 bool Y Y Server has Web Socket service enabled use_port int Y Y Y Server has Web Socket service feed bool Y Y Y Server has Web Socket service enabled use_port int Y Y Y Server has Web Socket service feed benefits string Y Server has Web Socket service feed benefits string Y Server has Web Socket service feed benefits string Y Server has Web Socket service feed benefits string Y Server has Web Socket service feed benefits string Y Server has Web Socket service feed Server file pair list string Y Sepecifies string Y Sepecifies string Y Sepecifies file list Server grameter string Y Sepecifies file list Server grameter string Y Sepecifies file list Server grameter string Y Sepecifies file list Sep	resume_policy	string	Υ	Υ	Υ	If a transfer is interrupted or fails to finish, resume without re-transfe
tronger or tot id string bears string bears string bears as sociated with the transfer user's SSH private key ship bears as sociated with the transfer user's SSH private key ship bears as sociated with the transfer user's SSH private key ship bears as sociated with the transfer user's SSH private key ship bears as sociated with the transfer user's SSH private key ship bears as sociated with the transfer user's SSH private key ship bears as sociated with the transfer user's SSH private key ship bears as sociated with the transfer user's SSH private key ship bears as sociated with the transfer user's SSH private key ship bears as sociated with the transfer user's SSH private key ship bears as sociated with the transfer user's SSH private key ship bears as sociated with the transfer user's SSH private key user's SSH authentication. Shall look like:	retry_duration	stringint		Υ	Υ	Specifies how long to wait before retrying transfer. (e.g. "5min")
string base string y y Specify the prefix to be stripped off from each source object. The resh port int y y y Specifies SSH (TCP) port. Default: local:22, other:33001(-P {int}) private key string y Private key used for SSH authentication. Shall look like:BEGIN The passphrase associated with the transfer user's SSH private key shfp string y y y Check it against server SSH host key fingerprint(check-sshfp {string y y y Handle source side symbolic linksAllowed values: follow, copy, copy ags hash y y y Metadata for transfer as JSON(tags64 (conversion){hash}) arget_rate_cap_kbps int y Returned by upload/download_setup node API. arget_rate_percentage string y y y title of the transfer string y y y title of the transfer string y y y title of the transfer string y y y y title of the transfer string y y y y to the prefix to be stripped off from each source object. The resh should into the call 22, other:3301(-P {int}) into the call 22 other:3301(-P {int}) into the passphrase string y y y y to the prefix to be stripped off from each source object. The resh should into the call 22 other:3301(-P {int}) into the call 22 other:3301(-P {int}) into the passphrase associated with the transfer into the passphrase associated with the transfer string y y the passphrase associated with the transfer into the passphrase associated with the transfer in	source_root	string	Υ	Υ	Υ	Path to be prepended to each source path. This is either a conventio
int Y Y Specifies SSH (TCP) port. Default: local:22, other:33001(-P {int}) ssh_private_key string Y Private key used for SSH authentication. Shall look like:BEGIN The passphrase associated with the transfer user's SSH private key shafp string Y Y Y Check it against server SSH host key fingerprint(check-shfp {string y Y Y Handle source side symbolic linksAllowed values: follow, copy, copy ags hash Y Y Metadata for transfer as JSON(tags64 (conversion){hash}) arget_rate_cap_kbps int Y Y Specifies desired by upload/download_setup node API. arget_rate_beproentage string Y Y Y Handle source side symbolic linksAllowed values: follow, copy, copy ags hash Y Y Y Metadata for transfer as JSON(tags64 (conversion){hash}) arget_rate_kbps int Y Y Specifies desired speed for the transfer.(-I {int}) arget_rate_percentage string Y Y Y Y Title of the transfer searce percentage string Y Y Y Authorization token: Bearer, Basic or ATM (Also arg -W)(env:ASPE specify version of protocol version of protoco	source_root_id	string		Υ		The file ID of the source root directory. Required when using Bearer
ring y y y hetadata for transfer as JSON(-tags64 (conversion){hash}) arget_rate_bercentage int y y y y hetadata for transfer by y y y hetadata for transfer as JSON(-tags64 (conversion){hash}) arget_rate_percentage isting y y y y hustoper bool y y y specify version of protocol was_northing y y y y hetadata for transfer as JSON(-tags64 (conversion){hash}) arget_rate_percentage int y y y hustoper bool y y y specify version of protocol was_northing y y y y y y y y y y y y y y y y y y y	src_base	string	Υ	Υ		Specify the prefix to be stripped off from each source object. The rem
The passphrase associated with the transfer user's SSH private key shift string by the string by the shift shift shift shift be shift shift by the s	ssh_port	int	Υ	Υ	Υ	Specifies SSH (TCP) port. Default: local:22, other:33001(-P {int})
string string Y Y Y Check it against server SSH host key fingerprint(check-sshfp {string symlink_policy} string Y Y Y Handle source side symbolic linksAllowed values: follow, copy, copy ags hash Y Y Y Metadata for transfer as JSON(-tags64 (conversion){hash}) arget_rate_cap_kbps int Y Y Specifies desired speed for the transfer.(-l {int}) arget_rate_percentage string Y Y Y Title of the transfer speed for the transfer.(-l {int}) arget_rate_percentage string Y Y Y Title of the transfer speed for the transfer.(-l {int}) arget_rate_percentage string Y Y Y Title of the transfer speed for the transfer.(-l {int}) arget_rate_percentage string Y Y Y Authorization token: Bearer, Basic or ATM (Also arg -W)(env:ASPE specify version of protocol specify version	ssh_private_key	string	Υ			Private key used for SSH authentication. Shall look like:BEGIN F
symlink_policy ags hash Y Y Y Metadata for transfer as JSON(tags64 (conversion){hash}) arget_rate_cap_kbps int Y Y Y Sectifies desired speed for the transfer.(-I {int}) arget_rate_percentage string Y Y Y Authorization token: Bearer, Basic or ATM (Also arg -W)(env:ASPE specify version of protocol vss_enabled bool Y Y Y Server has Web Socket service enabled vss_port int Y Y Y TCP port used for websocket service feed EX_at_rest_password string Y Y DEPRECATED: Use parameter ascp_args in option transfer_infoA EX_file_list string Y Specify the proxy server address used by HTTP Fallback(-x {string Y Specify the proxy server address used by HTTP Fallback(-x {string Y Specify the proxy server address used by HTTP Fallback(-x {string Y License file text override.By default ascp looks for license file near no read source(-no-read) EX_no_write bool Y Password used for Aspera proxy server authentication.May be ove	ssh_private_key_passphrase	string	Υ			The passphrase associated with the transfer user's SSH private key
hash Y Y Y Metadata for transfer as JSON(tags64 (conversion){hash}) arget_rate_cap_kbps int Y Y Specifies desired speed for the transfer.(-I {int}) arget_rate_percentage int Y Y Y Specifies desired speed for the transfer.(-I {int}) arget_rate_percentage string Y Y Y itle of the transfer string Y Y Y Authorization token: Bearer, Basic or ATM (Also arg -W)(env:ASPE specify version of protocol ves_enabled bool Y Y Server has Web Socket service enabled ves_port int Y Y Y TCP port used for websocket service feed beat string Y DEPRECATED: Use parameter ascp_args in option transfer_infoA beat string Y Source file list string Y Source file pair list string Y Specify the proxy server address used by HTTP Fallback(-x {string EX_http_transfer_ipeg int Y License_text string Y License file text override.By default ascp looks for license file near no read source(no-read) no write on destination(no-write) Password used for Aspera proxy server authentication.May be over	sshfp	string	Υ	Υ	Υ	Check it against server SSH host key fingerprint(check-sshfp {strin
int Y Returned by upload/download_setup node API. arget_rate_kbps int Y Y Y Specifies desired speed for the transfer.(-I {int}) arget_rate_percentage string Y Y Y itle string Y Y Y Title of the transfer oken string Y Y Y Authorization token: Bearer, Basic or ATM (Also arg -W)(env:ASPE specify version of protocol vss_enabled bool Y Y Server has Web Socket service enabled vss_port int Y Y Y TCP port used for websocket service feed EX_ascp_args array Y DEPRECATED: Use parameter ascp_args in option transfer_infoA ext_rest_password EX_file_list string Y source file list EX_file_pair_list string Y source file pair list EX_http_proxy_url string Y Specify the proxy server address used by HTTP Fallback(-x {string EX_http_transfer_jpeg int Y HTTP transfers as JPEG file(-j {int}) EX_license_text string Y License file text override.By default ascp looks for license file near no read source(no-read) EX_proxy_password string Y Password used for Aspera proxy server authentication.May be ove	symlink_policy	string	Υ	Υ	Υ	Handle source side symbolic linksAllowed values: follow, copy, copy
int Y Y Y Specifies desired speed for the transfer.(-I {int}) arget_rate_kbps int Y Y Y Specifies desired speed for the transfer.(-I {int}) arget_rate_percentage string Y Y Y Title of the transfer oken string Y Y Y Authorization token: Bearer, Basic or ATM (Also arg -W)(env:ASPE use_ascp4 bool Y Y Server has Web Socket service enabled vss_enabled bool Y Y Y Server has Web Socket service feed ext_ascp_args array Y DEPRECATED: Use parameter ascp_args in option transfer_infoA ext_al_rest_password string Y Source file list ext_file_pair_list string Y Specify the proxy server address used by HTTP Fallback(-x {string} X Specify the proxy server address used by HTTP Fallback(-x {string} X License_text string Y License file text override.By default ascp looks for license file near no read source(no-read) ext_no_write bool Y Password used for Aspera proxy server authentication.May be ove	tags	hash	Υ	Υ	Υ	Metadata for transfer as JSON(tags64 (conversion){hash})
arget_rate_percentage string Y Y Y Strible of the transfer string string Y Y Y Authorization token: Bearer, Basic or ATM (Also arg -W)(env:ASPE ase_ascp4 bool Y Y Server has Web Socket service enabled bool y Y Y Server has Web Socket service enabled int Y Y Y TCP port used for websocket service feed EX_ascp_args array Y DEPRECATED: Use parameter ascp_args in option transfer_infoA EX_at_rest_password string Y DEPRECATED: Use standard spec parameter: content_protection source file list suring Y source file pair list EX_file_pair_list string Y Specify the proxy server address used by HTTP Fallback(-x {string EX_http_transfer_jpeg int Y Specify the proxy server address used by HTTP Fallback(-x {string EX_license_text string Y License file text override.By default ascp looks for license file near no read source(no-read) no write on destination(no-write) EX_proxy_password string Y Password used for Aspera proxy server authentication.May be ove	target_rate_cap_kbps	int			Υ	Returned by upload/download_setup node API.
string Y Y Title of the transfer oken string Y Y Y Authorization token: Bearer, Basic or ATM (Also arg -W)(env:ASPE use_ascp4 bool Y Y Server has Web Socket service enabled vss_enabled bool Y Y Y Server has Web Socket service enabled vss_port int Y Y Y TCP port used for websocket service feed EX_ascp_args array Y DEPRECATED: Use parameter ascp_args in option transfer_infoA EX_at_rest_password string Y DEPRECATED: Use standard spec parameter: content_protection EX_file_list string Y source file list EX_file_pair_list string Y source file pair list EX_http_proxy_url string Y Specify the proxy server address used by HTTP Fallback(-x {string EX_http_transfer_jpeg int Y HTTP transfers as JPEG file(-j {int}) EX_license_text string Y License file text override.By default ascp looks for license file near no read source(no-read) EX_no_read bool Y no write on destination(no-write) EX_proxy_password string Y Password used for Aspera proxy server authentication.May be ove	target_rate_kbps	int	Υ			Specifies desired speed for the transfer.(-I {int})
string Y Y Y Authorization token: Bearer, Basic or ATM (Also arg -W)(env:ASPE spe_ascp4 bool Y Y specify version of protocol vss_enabled bool Y Y Y Server has Web Socket service enabled vss_port int Y Y Y TCP port used for websocket service feed EX_ascp_args array Y DEPRECATED: Use parameter ascp_args in option transfer_infoA EX_at_rest_password string Y Source file list string Y source file list EX_file_pair_list string Y source file pair list EX_http_proxy_url string Y Specify the proxy server address used by HTTP Fallback(-x {string EX_http_transfer_jpeg int Y HTTP transfers as JPEG file(-j {int}) EX_license_text string Y License file text override.By default ascp looks for license file near no read source(-no-read) no write on destination(no-write) Password used for Aspera proxy server authentication.May be over	target_rate_percentage	string	Υ	Υ	Υ	
bool Y Y specify version of protocol vss_enabled bool Y Y Server has Web Socket service enabled vss_port int Y Y Y TCP port used for websocket service feed EX_ascp_args array Y DEPRECATED: Use parameter ascp_args in option transfer_infoA EX_at_rest_password string Y DEPRECATED: Use standard spec parameter: content_protection EX_file_list string Y source file list EX_file_pair_list string Y source file pair list EX_http_proxy_url string Y Specify the proxy server address used by HTTP Fallback(-x {string EX_http_transfer_jpeg int Y HTTP transfers as JPEG file(-j {int}) EX_license_text string Y License file text override.By default ascp looks for license file near no read source(no-read) EX_no_write bool Y no write on destination(no-write) EX_proxy_password string Y Password used for Aspera proxy server authentication.May be ove	title	string			Υ	Title of the transfer
vss_enabled bool Y Y Y Server has Web Socket service enabled vss_port int Y Y Y TCP port used for websocket service feed EX_ascp_args array Y DEPRECATED: Use parameter ascp_args in option transfer_infoA DEPRECATED: Use standard spec parameter: content_protection source file list string Y source file pair list EX_file_pair_list string Y Specify the proxy server address used by HTTP Fallback(-x {string EX_http_transfer_jpeg int Y Specify the proxy server address used by HTTP Fallback(-x {string EX_http_transfer_jpeg int Y License file text override.By default ascp looks for license file near no read source(no-read) no write on destination(no-write) EX_proxy_password string Y Password used for Aspera proxy server authentication.May be ove	token	string	Υ	Υ	Υ	Authorization token: Bearer, Basic or ATM (Also arg -W)(env:ASPEF
int Y Y Y TCP port used for websocket service feed EX_ascp_args array Y DEPRECATED: Use parameter ascp_args in option transfer_infoA EX_at_rest_password string Y DEPRECATED: Use standard spec parameter: content_protection EX_file_list string Y source file list EX_file_pair_list string Y source file pair list EX_http_proxy_url string Y Specify the proxy server address used by HTTP Fallback(-x {string EX_http_transfer_jpeg int Y HTTP transfers as JPEG file(-j {int}) EX_license_text string Y License file text override.By default ascp looks for license file near no read source(no-read) EX_no_write bool Y no write on destination(no-write) EX_proxy_password string Y Password used for Aspera proxy server authentication.May be ove	use_ascp4	bool	Υ	Υ		specify version of protocol
EX_ascp_args array Y DEPRECATED: Use parameter ascp_args in option transfer_infoA EX_at_rest_password string Y DEPRECATED: Use standard spec parameter: content_protection source file list EX_file_pair_list string Y source file pair list EX_http_proxy_url string Y Specify the proxy server address used by HTTP Fallback(-x {string EX_http_transfer_jpeg int Y HTTP transfers as JPEG file(-j {int}) EX_license_text string Y License file text override.By default ascp looks for license file near no read source(no-read) no write on destination(no-write) EX_proxy_password string Y Password used for Aspera proxy server authentication.May be ove	wss_enabled	bool	Υ		Υ	Server has Web Socket service enabled
EX_at_rest_password string Y DEPRECATED: Use standard spec parameter: content_protection source file list string Y source file list source file pair list SX_file_pair_list string Y source file pair list SX_http_proxy_url string Y Specify the proxy server address used by HTTP Fallback(-x {string EX_http_transfer_jpeg int Y HTTP transfers as JPEG file(-j {int}) License_text string Y License file text override.By default ascp looks for license file near no read source(no-read) no write on destination(no-write) Password string Y Password used for Aspera proxy server authentication.May be ove	wss_port	int	Υ	Υ	Υ	TCP port used for websocket service feed
EX_file_list string Y source file list EX_file_pair_list string Y source file pair list EX_http_proxy_url string Y Specify the proxy server address used by HTTP Fallback(-x {string EX_http_transfer_jpeg int Y HTTP transfers as JPEG file(-j {int}) EX_license_text string Y License file text override.By default ascp looks for license file near no read source(no-read) EX_no_read bool Y no write on destination(no-write) EX_proxy_password string Y Password used for Aspera proxy server authentication.May be ove	EX_ascp_args	array	Υ			DEPRECATED: Use parameter ascp_args in option transfer_infoAd
SX_file_pair_list string Y source file pair list EX_http_proxy_url string Y Specify the proxy server address used by HTTP Fallback(-x {string EX_http_transfer_jpeg int Y HTTP transfers as JPEG file(-j {int}) EX_license_text string Y License file text override.By default ascp looks for license file near no read source(no-read) EX_no_write bool Y no write on destination(no-write) EX_proxy_password string Y Password used for Aspera proxy server authentication.May be ove	EX_at_rest_password	string	Υ			DEPRECATED: Use standard spec parameter: content_protection_i
EX_http_proxy_url string Y Specify the proxy server address used by HTTP Fallback(-x {string EX_http_transfer_jpeg int Y HTTP transfers as JPEG file(-j {int}) EX_license_text string Y License file text override.By default ascp looks for license file near no read source(no-read) EX_no_write bool Y no write on destination(no-write) EX_proxy_password string Y Password used for Aspera proxy server authentication.May be ove	EX_file_list	string				source file list
EX_http_transfer_jpeg int Y HTTP transfers as JPEG file(-j {int}) EX_license_text string Y License file text override.By default ascp looks for license file near no read source(no-read) EX_no_write bool Y no write on destination(no-write) EX_proxy_password string Y Password used for Aspera proxy server authentication.May be ove	EX_file_pair_list	string	Υ			source file pair list
EX_license_text string Y License file text override.By default ascp looks for license file near bool Y no read source(no-read) EX_no_write bool Y no write on destination(no-write) EX_proxy_password string Y Password used for Aspera proxy server authentication.May be ove	EX_http_proxy_url	string	Υ			Specify the proxy server address used by HTTP Fallback(-x {string})
EX_no_read bool Y no read source(no-read) EX_no_write bool Y no write on destination(no-write) EX_proxy_password string Y Password used for Aspera proxy server authentication.May be ove	EX_http_transfer_jpeg	int	Υ			HTTP transfers as JPEG file(-j {int})
EX_no_read bool Y no read source(no-read) EX_no_write bool Y no write on destination(no-write) EX_proxy_password string Y Password used for Aspera proxy server authentication.May be ove	EX_license_text	string	Υ			License file text override. By default ascp looks for license file near e
EX_proxy_password string Y Password used for Aspera proxy server authentication. May be ove	EX_no_read		Υ			no read source(no-read)
	EX_no_write	bool	Υ			no write on destination(no-write)
EX_ssh_key_paths array Y Use public key authentication for SSH and specify the private key f	EX_proxy_password	string	Υ			Password used for Aspera proxy server authentication. May be overr
	EX_ssh_key_paths	array	Υ			Use public key authentication for SSH and specify the private key file

7.25.1 Destination folder for transfers

The destination folder is set by ascli by default to:

- · . for downloads
- / for uploads

It is specified by the *transfer-spec* parameter destination_root. As such, it can be modified with option: --ts=@json:'{"destination_root":"<path>"}'. The option to_folder provides an equivalent and convenient way to change this parameter: --to-folder=<path>.

7.25.2 List of files for transfers

When uploading, downloading or sending files, the user must specify the list of files to transfer.

By default the list of files to transfer is simply provided on the command line.

The list of (source) files to transfer is specified by (extended value) option <code>sources</code> (default: <code>@args</code>). The list is either simply the list of source files, or a combined source/destination list (see below) depending on value of option <code>src_type</code> (default: <code>list</code>).

In ascli, all transfer parameters, including file list, are provided to the transfer agent in a *transfer-spec* so that execution of a transfer is independent of the transfer agent (direct, connect, node, transfer sdk...). So, eventually, the list of files to transfer is provided to the transfer agent using the *transfer-spec* field: "paths" which is a list (array) of pairs of "source"

(mandatory) and "destination" (optional). The sources and src_type options provide convenient ways to populate the transfer spec with the source file list.

Possible values for option sources are:

• @args: (default) the list of files (or file pair) is directly provided on the command line (after commands): unused arguments (not starting with -) are considered as source files. So, by default, the list of files to transfer will be simply specified on the command line. Example:

```
ascli server upload ~/first.file secondfile

This is the same as (with default values):

ascli server upload --sources=@args --src-type=list ~/mysample.file secondfile
```

an Extended Value with type Array of String

Note: extended values can be tested with the command conf echo

Examples:

- Using extended value

Create the file list:

```
echo ~/mysample.file > myfilelist.txt
echo secondfile >> myfilelist.txt
```

Use the file list: one path per line:

```
--sources=@lines:@file:myfilelist.txt
```

Using JSON array

```
--sources=@json:'["file1","file2"]'
```

- Using STDIN, one path per line

```
--sources=@lines:@stdin:
```

Using Ruby code (one path per line in file)

```
--sources=@ruby:'File.read("myfilelist.txt").split("\n")'
```

- @ts: the user provides the list of files directly in the paths field of transfer spec (option ts). Examples:
 - Using transfer spec

```
--sources=@ts --ts=@json:'{"paths":[{"source":"file1"},{"source":"file2"}]}'
```

The option src_type allows specifying if the list specified in option sources is a simple file list or if it is a file pair list.

Note: Option src_type is not used if option sources is set to @ts

Supported values for src_type are:

- list: (default) the path of destination is the same as source and each entry is a source file path
- pair: the first element is the first source, the second element is the first destination, and so on.

Example: Source file 200KB.1 is renamed sample1 on destination:

```
ascli server upload --src-type=pair ~/Documents/Samples/200KB.1 /Upload/sample1
```

Note: There are some specific rules to specify a file list when using **Aspera on Cloud**, refer to the AoC plugin section.

7.25.3 Source directory structure on destination

This section is not specific to ascli, it is ascp behaviour.

The transfer destination is normally expected to designate a destination folder.

But there is one exception: The destination specifies the new item name when the following are met:

• there is a single source item (file or folder)

- transfer spec create_dir is not set to true (ascp option -d not provided)
- · destination is not an existing folder
- the dirname of destination is an existing folder

For this reason it is recommended to set <code>create_dir</code> to <code>true</code> for consistent behaviour between single and multiple items transfer, this is the default in <code>ascli</code>.

If a simple source file list is provided (no destination in paths, i.e. no file_pair_list provided), the destination folder is used as destination folder for each source file, and source file folder names are not preserved.

The inner structure of source items that are folder is preserved on destination.

A leading / on destination is ignored (relative to docroot) unless docroot is not set (relative to home).

In the following table source folder d3 contains 2 files: f1 and d4/f2.

Source files	Destination	Folders on Dest.	create_dir	Destination Files
f1	d/f	-	false	Error: d does not exist.
f1	d/f	d	false	d/f (renamed)
f1	d/f/.	d	false	d/f (renamed)
f1	d/f	d/f	false	d/f/f1
f1 f2	d	d	false	d/f1 d/f2
d3	d	-	false	d/f1 d/f2 (renamed)
f1	d	-	true	d/f1
f1 f2	d	-	true	d/f1 d/f2
d1/f1 d2/f2	d	-	true	d/f1 d/f2
d3	d	-	true	d/d3/f1 d/d3/d4/f2

If a file par list is provided then it is possible to rename or specify a different destination folder for each source (relative to the destination).

If transfer spec has a src_base, it has the side effect that the simple source file list is considered as a file pair list, and so the lower structure of source folders is preserved on destination.

Source files	Destination	src_base	Destination Files
d1/d2/f2 d1/d3/f3	d	d1	d/d2/f2 d/d3/f3

Advanced Example: Send files ./file1 and ./folder2/files2 to server (e.g. /Upload) and keep the original file names and folders, i.e. send file1 to /Upload/file1 and files2 to /Upload/folder2/files2.

- If files are specified as ./file1 ./folder2/files2, then destination will be: /Upload/file1 /Upload/files2
- One possibility is to specify a file pair list: --src-type=pair file1 file1 folder2/files2 folder2/files2
- Another possibility is to specify a source base: --src-base=\$PWD \$PWD/file1 \$PWD/folder2/files2 (note that . cannot be used as source base)
- Similarly, create a temporary soft link (Linux): ln -s . tmp_base and use --src-base=tmp_base tmp_base/file1 tmp_base/folder2/files2
- One can also similarly use --sources=@ts and specify the list of files in the paths field of transfer spec with both source and destination for each file.

7.25.4 Support of multi-session

Multi session, i.e. starting a transfer of a file set using multiple sessions (one ascp process per session) is supported on direct and node agents, not yet on connect.

• --transfer=node

--ts=0json:'{"multi_session":10,"multi_session_threshold":1}'

Multi-session is directly supported by the node daemon.

• --transfer=direct

```
--ts=@json:'{"multi_session":5,"multi_session_threshold":1,"resume_policy":"none"}'
```

Note: resume_policy set to attr may cause problems: none or sparse_csum shall be preferred.

ascli starts multiple ascp for Multi-session using direct agent.

When multi-session is used, one separate UDP port is used per session (refer to ascp manual page).

7.25.5 Content protection

Also known as Client-side encryption at rest (CSEAR), content protection allows a client to send files to a server which will store them encrypted (upload), and decrypt files as they are being downloaded from a server, both using a passphrase, only known by users sharing files. Files stay encrypted on server side.

Activating CSEAR consists in using transfer spec parameters:

- content_protection: activate encryption (encrypt for upload) or decryption (decrypt for download)
- content_protection_password: the passphrase to be used.

Example: parameter to download a faspex package and decrypt on the fly

```
--ts=@json:'{"content_protection":"decrypt","content_protection_password":"my_password_here"}'
```

7.25.6 Transfer Spec Examples

Change target rate

```
--ts=@json:'{"target_rate_kbps":500000}'
```

• Override the FASP SSH port to a specific TCP port:

```
--ts=@json:'{"ssh_port":33002}'
```

· Force http fallback mode:

```
--ts=@json:'{"http_fallback":"force"}'
```

Activate progress when not activated by default on server

```
--ts=@json:'{"precalculate_job_size":true}'
```

7.26 Scheduler

It is useful to configure automated scheduled execution. ascli does not provide an internal scheduler. Instead, use the service provided by the Operating system:

7.26.1 Windows Scheduler

Windows provides the Task Scheduler. It can be configured:

- Using utility schtasks.exe
- Using powershell function scheduletasks
- Using taskschd.msc (UI)

7.26.2 Unix-like Scheduler

Unix-like systems (Linux, ...) provide cron, configured using a crontab

Linux also provides anacron, if tasks are hourly or daily.

For example, on Linux it is convenient to create a wrapping script, e.g. cron_ascli that will setup the environment (e.g. Ruby) to properly start ascli:

Note: The logging options are kept here in the cronfile instead of conf file to allow execution on command line with output on command line.

7.27 Locking for exclusive execution

In some cases one needs to ensure that ascli is not executed several times in parallel.

When ascli is executed automatically on a schedule basis, one generally desires that a new execution is not started if a previous execution is still running because an on-going operation may last longer than the scheduling period:

- Executing instances may pile-up and kill the system
- The same file may be transferred by multiple instances at the same time.
- preview may generate the same files in multiple instances.

Usually the OS native scheduler already provides some sort of protection against parallel execution:

- · The Windows scheduler does this by default
- Linux cron can leverage the utility flock to do the same:

```
/usr/bin/flock -w 0 /var/cron.lock ascli ...
```

ascli natively supports a locking mechanism with option lock_port. (Technically, this opens a local TCP server port, and fails if this port is already used, providing a local lock. Lock is released when process exits).

Testing ascli locking:

Run this same command in two separate terminals within less than 30 seconds:

```
ascli config echo @ruby: 'sleep(30)' --lock-port=12345
```

The first instance will sleep 30 seconds, the second one will immediately exit like this:

```
WARN --: Another instance is already running (Address already in use - bind(2) for "127.0.0.1" port 12345).
```

7.28 "Provençale"

ascp, the underlying executable implementing Aspera file transfer using FASP, has a capability to not only access the local file system (using system's open,read,write,close primitives), but also to do the same operations on other data storage such as S3, Hadoop and others. This mechanism is call *PVCL*. Several *PVCL* adapters are available, some are embedded in ascp, some are provided om shared libraries and must be activated. (e.g. using trapd)

The list of supported PVCL adapters can be retrieved with command:

```
| product_name
                   | IBM Aspera SDK
| product_version
                   4.0.1.182389
process
                   | pvcl
shares
                   | pvcl
noded
                   | pvcl
| faux
                   | pvcl
| file
                   | pvcl
| stdio
                   | pvcl
| stdio-tar
                   | pvcl
```

Here we can see the adapters: process, shares, noded, faux, file, stdio, stdio-tar.

Those adapters can be used wherever a file path is used in ascp including configuration. They act as a pseudo "drive".

The simplified format is:

```
<adapter>:///<sub file path>?<arg1>=<val1>&...
```

One of the adapters, used in this manual, for testing, is faux. It is a pseudo file system allowing generation of file data without actual storage (on source or destination).

7.29 faux: for testing

This is an extract of the man page of ascp. This feature is a feature of ascp, not ascli.

This adapter can be used to simulate a file or a directory.

To discard data at the destination, the destination argument is set to faux://.

To send uninitialized data in place of an actual source file, the source file is replaced with an argument of the form:

faux:///filename?filesize

where:

- filename is the name that will be assigned to the file on the destination
- filesize is the number of bytes that will be sent (in decimal).

Note: characters? and & are shell special characters (wildcard and background), so faux file specification on command line should be protected (using quotes or \). If not, the shell may give error: no matches found or equivalent.

For all sizes, a suffix can be added (case insensitive) to the size: k,m,g,t,p,e (values are power of 2, e.g. 1M is 220, i.e. 1 mebibyte, not megabyte). The maximum allowed value is 8*260. Very large faux file sizes (petabyte range and above) will likely fail due to lack of destination storage unless destination is faux://.

To send uninitialized data in place of a source directory, the source argument is replaced with an argument of the form:

```
faux:///dirname?<arg1>=<val1>&...
```

where:

- dirname is the folder name and can contain / to specify a subfolder.
- supported arguments are:

Name	Туре	Description
count	int	mandatory
file	string	Basename for filesDefault: "file"
size	int	Size of first file.Default: 0
inc	int	Increment applied to determine next file sizeDefault: 0
seq	enum	Sequence in determining next file sizeValues: random, sequentialDefault: sequential
buf init	enum	How source data is initializedOption 'none' is not allowed for downloads. Values:none, zero, randomDefault:zero

The sequence parameter is applied as follows:

- If seq is random then each file size is:
 - size +/- (inc * rand())
 - Where rand is a random number between 0 and 1
 - Note that file size must not be negative, inc will be set to size if it is greater than size
 - Similarly, overall file size must be less than 8260. If size + inc is greater, inc will be reduced to limit size + inc to 7260.
- If seq is sequential then each file size is:
 - size + ((file_index 1) * inc)
 - Where first file is index 1
 - So file1 is size bytes, file2 is size + inc bytes, file3 is size + inc * 2 bytes, etc.
 - As with random, inc will be adjusted if size + (count * inc) is not less then 8*260.

Filenames generated are of the form: <file>_<00000 ... count>_<filesize>

Examples:

Upload 20 gibibytes of random data to file myfile to directory /Upload

```
ascli server upload faux:///myfile\?20g --to-folder=/Upload
```

· Upload a file /tmp/sample but do not save results to disk (no docroot on destination)

```
ascli server upload /tmp/sample --to-folder=faux://
```

Upload a faux directory mydir containing 1 million files, sequentially with sizes ranging from 0 to 2 Mebibyte - 2
bytes, with the basename of each file being testfile to /Upload

ascli server upload "faux:///mydir?file=testfile&count=1m&size=0&inc=2&seq=sequential" --to-folder=/Upload

7.30 Usage

```
ascli -h
NAME
        ascli -- a command line tool for Aspera Applications (v4.14.0.pre)
SYNOPSIS
        ascli COMMANDS [OPTIONS] [ARGS]
DESCRIPTION
        Use Aspera application to perform operations on command line.
        Documentation and examples: https://rubygems.org/gems/aspera-cli
        execute: ascli conf doc
        or visit: https://www.rubydoc.info/gems/aspera-cli
        source repo: https://github.com/IBM/aspera-cli
ENVIRONMENT VARIABLES
        ASCLI_HOME config folder, default: $HOME/.aspera/ascli
        Any option can be set as an environment variable, refer to the manual
COMMANDS
        To list first level commands, execute: ascli
        Note that commands can be written shortened (provided it is unique).
OPTIONS
        Options begin with a '-' (minus), and value is provided on command line.
        Special values are supported beginning with special prefix Opfx:, where pfx is one of:
        base64, csvt, env, file, json, lines, list, path, ruby, secret, stdin, uri, val, zlib, preset, incps,
```

Dates format is 'DD-MM-YY HH:MM:SS', or 'now' or '-<num>h'

ARGS

Some commands require mandatory arguments, e.g. a path.

OPTIONS: global

--interactive=ENUM Use interactive input of missing params: [no], yes

--ask-options=ENUM Ask even optional options: [no], yes

--format=ENUM Output format: text, nagios, ruby, json, jsonpp, yaml, [table], csv

--display=ENUM Output only some information: [info], data, error --fields=VALUE Comma separated list of fields, or ALL, or DEF

--select=VALUE Select only some items in lists: column, value (Hash)

--table-style=VALUE Table display style

--flat-hash=ENUM Display deep values as additional keys: no, [yes] --transpose-single=ENUM Single object fields output vertically: no, [yes]

--show-secrets=ENUM Show secrets on command output: [no], yes

-h, --help Show this message

--bash-comp Generate bash completion for command

--show-config Display parameters used for the provided action

-r, --rest-debug More debug for HTTP calls (REST)

-v, --version Display version

-w, --warnings Check for language warnings

--ui=ENUM Method to start browser: text, [graphical]

--log-level=ENUM Log level: debug, info, [warn], error, fatal, unknown

--logger=ENUM Logging method: [stderr], stdout, syslog

--lock-port=VALUE Prevent dual execution of a command, e.g. in cron

--http-options=VALUE Options for http socket (Hash)

--insecure=ENUM Do not validate HTTPS certificate: [no], yes
--once-only=ENUM Process only new items (some commands): [no], yes

--log-secrets=ENUM Show passwords in logs: [no], yes --cache-tokens=ENUM Save and reuse Oauth tokens: no, [yes]

COMMAND: config

SUBCOMMANDS: ascp check_update coffee detect documentation echo email_test file flush_tokens folder gem genke OPTIONS:

--query=VALUE Additional filter for for some commands (list/delete) (Hash)

--value=VALUE Value for create, update, list filter (Hash) (deprecated: Use positional

--property=VALUE Name of property to set (modify operation)

--id=VALUE Resource identifier (deprecated: Use identifier after verb (modify,delet bulk=ENUM Bulk operation (only some): [no], yes

--bfail=ENUM Bulk operation error handling: no, [yes]
--config-file=VALUE Read parameters from file in YAML format, current=/usershome/.aspera/asc

-N, --no-default Do not load default configuration for plugin

--override=ENUM Wizard: override existing value: [no], yes

--use-generic-client=ENUM Wizard: AoC: use global or org specific jwt client id: no, [yes]

--default=ENUM Wizard: set as default configuration for specified plugin (also: update)

--test-mode=ENUM Wizard: skip private key check step: [no], yes

-P, --presetVALUE Load the named option preset from current config file

--pkeypath=VALUE Wizard: path to private key for JWT

--ascp-path=VALUE Path to ascp

--use-product=VALUE Use ascp from specified product --smtp=VALUE SMTP configuration (Hash)

--fpac=VALUE Proxy auto configuration script

--proxy-credentials=VALUE HTTP proxy credentials (Array with user and password)

--secret=VALUE Secret for access keys
--vault=VALUE Vault for secrets

--vault-password=VALUE Vault password
--sdk-url=VALUE URL to get SDK
--sdk-folder=VALUE SDK folder path

--notif-to=VALUE Email recipient for notification of transfers
--notif-template=VALUE Email ERB template for notification of transfers
--version-check-days=VALUE Period in days to check new version (zero to disable)

--plugin-folder=VALUE Folder where to find additional plugins --ts=VALUE Override transfer spec values (Hash)

Destination folder for transferred files --to-folder=VALUE

--sources=VALUE How list of transferred files is provided (@args,@ts,Array)

--src-type=ENUM Type of file list: [list], pair

Type of transfer agent: [direct], node, connect, httpgw, trsdk --transfer=ENUM

--transfer-info=VALUE Parameters for transfer agent (Hash)

Type of progress bar: none, [native], multi --progress=ENUM

COMMAND: shares

SUBCOMMANDS: admin files health

OPTIONS:

URL of application, e.g. https://org.asperafiles.com --url=VALUE

--username=VALUE Username to log in --password=VALUE User's password

--type=ENUM Type of user/group for operations: [any], local, ldap, saml

COMMAND: node

SUBCOMMANDS: access_key api_details asperabrowser async basic_token browse central delete download events hea

OPTIONS:

URL of application, e.g. https://org.asperafiles.com --url=VALUE

--username=VALUE Username to log in --password=VALUE User's password

--validator=VALUE Identifier of validator (optional for central)

URL for simple aspera web ui --asperabrowserurl=VALUE

--sync-name=VALUE

Use standard FASP ports or get from node api (gen4): no, [yes] --default-ports=ENUM

COMMAND: orchestrator

SUBCOMMANDS: health info plugins processes workflow

OPTIONS:

URL of application, e.g. https://org.asperafiles.com --url=VALUE

--username=VALUE Username to log in --password=VALUE User's password

Start parameters (Hash) --params=VALUE

--result=VALUE Specify result value as: 'work step:parameter' --synchronous=ENUM Work step:parameter expected as result: [no], yes --ret-style=ENUM How return type is requested in api: header, [arg], ext --auth-style=ENUM Authentication type: arg_pass, [head_basic], apikey

COMMAND: bss

SUBCOMMANDS: subscription

OPTIONS:

URL of application, e.g. https://org.asperafiles.com --url=VALUE

--username=VALUE Username to log in --password=VALUE User's password

COMMAND: alee

SUBCOMMANDS: entitlement

OPTIONS:

--url=VALUE URL of application, e.g. https://org.asperafiles.com

--username=VALUE Username to log in --password=VALUE User's password

COMMAND: ats

SUBCOMMANDS: access_key api_key aws_trust_policy cluster

OPTIONS:

--ibm-api-key=VALUE IBM API key, see https://cloud.ibm.com/iam/apikeys

--instance=VALUE ATS instance in ibm cloud --ats-key=VALUE ATS key identifier (ats_xxx)

--ats-secret=VALUE ATS key secret

--params=VALUE Parameters access key creation (@json:)

--cloud=VALUE Cloud provider --region=VALUE Cloud region

COMMAND: faspex5

SUBCOMMANDS: admin bearer_token gateway health packages postprocessing shared_folders user version

OPTIONS:

--url=VALUE URL of application, e.g. https://org.asperafiles.com

--username=VALUE Username to log in --password=VALUE User's password

--client-id=VALUE OAuth client identifier --client-secret=VALUE OAuth client secret

--redirect-uri=VALUE OAuth redirect URI for web authentication

--auth=ENUM OAuth type of authentication: boot, link, web, [jwt]

--private-key=VALUE OAuth JWT RSA private key PEM value (prefix file path with @file:)

--passphrase=VALUE OAuth JWT RSA private key passphrase

--link=VALUE Public link authorization (specific operations)

--box=VALUE Package inbox, either shared inbox name or one of ["inbox", "inbox_histor

--shared-folder=VALUE Send package with files from shared folder

COMMAND: cos SUBCOMMANDS: node

OPTIONS:

--bucket=VALUE Bucket name

--endpoint=VALUE Storage endpoint url
--apikey=VALUE Storage API key
--crn=VALUE Resource instance id

--service-credentials=VALUE IBM Cloud service credentials (Hash)

--region=VALUE Storage region

--identity=VALUE Authentication url (https://iam.cloud.ibm.com/identity)

COMMAND: faspex

SUBCOMMANDS: address_book dropbox health login_methods me package source v4

OPTIONS:

--url=VALUE URL of application, e.g. https://org.asperafiles.com

--username=VALUE Username to log in --password=VALUE User's password

--link=VALUE Public link for specific operation
--delivery-info=VALUE Package delivery information (Hash)

--source-name=VALUE Create package from remote source (by name)

--storage=VALUE Faspex local storage definition

COMMAND: preview

SUBCOMMANDS: check events scan test trevents

OPTIONS:

--url=VALUE URL of application, e.g. https://org.asperafiles.com

--username=VALUE Username to log in --password=VALUE User's password

--skip-format=ENUM Skip this preview format (multiple possible): png, mp4

--folder-reset-cache=ENUM Force detection of generated preview by refresh cache: [no], header, rea

--skip-types=VALUE Skip types in comma separated list --previews-folder=VALUE Preview folder in storage root

--temp-folder=VALUE Path to temp folder --skip-folders=VALUE List of folder to skip

--case=VALUE Basename of output for for test

--scan-path=VALUE Subpath in folder id to start scan in (default=/)

--scan-id=VALUE Folder id in storage to start scan in, default is access key main folder

--mimemagic=ENUM Use Mime type detection of gem mimemagic: [no], yes
--overwrite=ENUM When to overwrite result file: always, never, [mtime]
--file-access=ENUM How to read and write files in repository: [local], remote

--max-size=VALUE Maximum size (in bytes) of preview file
--thumb-vid-scale=VALUE Png: video: size (ffmpeg scale argument)
--thumb-vid-fraction=VALUE Png: video: time percent position of snapshot

--thumb-img-size=VALUE Png: non-video: height (and width)

--thumb-text-font=VALUE Png: plaintext: font to render text with imagemagick convert (identify -

--video-conversion=ENUM Mp4: method for preview generation: [reencode], blend, clips --video-png-conv=ENUM Mp4: method for thumbnail generation: [fixed], animated

--video-scale=VALUE Mp4: all: video scale (ffmpeg)

--video-start-sec=VALUE Mp4: all: start offset (seconds) of video preview

--reencode-ffmpeg=VALUE Mp4: reencode: options to ffmpeg

--blend-keyframes=VALUE Mp4: blend: # key frames
--blend-pauseframes=VALUE Mp4: blend: # pause frames

--blend-transframes=VALUE Mp4: blend: # transition blend frames

--blend-fps=VALUE Mp4: blend: frame per second --clips-count=VALUE Mp4: clips: number of clips

--clips-length=VALUE Mp4: clips: length in seconds of each clips

COMMAND: sync

SUBCOMMANDS: admin start

OPTIONS:

--sync-info=VALUE Information for sync instance and sessions (Hash)

--sync-session=VALUE Name of session to use for admin commands. default: first in parameters

COMMAND: aoc

SUBCOMMANDS: admin automation bearer_token files gateway organization packages reminder servers tier_restrict OPTIONS:

--url=VALUE URL of application, e.g. https://org.asperafiles.com

--username=VALUE Username to log in --password=VALUE User's password

--auth=ENUM OAuth type of authentication: web, [jwt]
--operation=ENUM Client operation for transfers: [push], pull

--client-id=VALUE OAuth API client identifier
--client-secret=VALUE OAuth API client secret
--redirect-uri=VALUE OAuth API client redirect URI

--private-key=VALUE OAuth JWT RSA private key PEM value (prefix file path with @file:)

--scope=VALUE OAuth scope for AoC API calls
--passphrase=VALUE RSA private key passphrase

--workspace=VALUE Name of workspace

--name=VALUE Resource name (prefer to use keyword name)

--link=VALUE Public link to shared resource

--new-user-option=VALUE New user creation option for unknown package recipients

--from-folder=VALUE Source folder for Folder-to-Folder transfer

--validate-metadata=ENUM Validate shared inbox metadata: no, [yes]

COMMAND: node

SUBCOMMANDS: access_key api_details asperabrowser async basic_token browse central delete download events hea

OPTIONS:

--validator=VALUE Identifier of validator (optional for central)

--sync-name=VALUE Sync name

--default-ports=ENUM Use standard FASP ports or get from node api (gen4): no, [yes]

COMMAND: server

SUBCOMMANDS: browse cp delete df download du health info ls md5sum mkdir mv rename rm sync upload

OPTIONS:

--url=VALUE URL of application, e.g. https://org.asperafiles.com

--username=VALUE Username to log in --password=VALUE User's password

--ssh-keys=VALUE SSH key path list (Array or single)

--passphrase=VALUE SSH private key passphrase

--ssh-options=VALUE SSH options (Hash)

COMMAND: console

SUBCOMMANDS: health transfer

OPTIONS:

--url=VALUE URL of application, e.g. https://org.asperafiles.com

--username=VALUE Username to log in
--password=VALUE User's password
--filter-from=DATE Only after date
--filter-to=DATE Only before date

Note: commands and parameter values can be written in short form.

7.31 Bulk creation and deletion of resources

Bulk creation and deletion of resources are possible using option bulk (yes,no(default)). In that case, the operation expects an Array of Hash instead of a simple Hash using the Extended Value Syntax. This option is available only for some of the resources: if you need it: try and see if the entities you try to create or delete support this option.

Chapter 8

Plugin: aoc: IBM Aspera on Cloud

Aspera on Cloud uses the more advanced Oauth v2 mechanism for authentication (HTTP Basic authentication is not supported).

It is recommended to use the wizard to set it up, but manual configuration is also possible.

8.1 Configuration: using Wizard

```
ascli provides a configuration wizard. Here is a sample invocation:
```

```
ascli config wizard
option: url> https://myorg.ibmaspera.com
Detected: Aspera on Cloud
Preparing preset: aoc_myorg
Please provide path to your private RSA key, or empty to generate one:
option: pkeypath>
using existing key:
/Users/myself/.aspera/ascli/aspera_aoc_key
Using global client_id.
option: username> john@example.com
Updating profile with new key
creating new config preset: aoc_myorg
Setting config preset as default for aspera
saving config file
Done.
You can test with:
ascli aoc user profile show
```

Optionally, it is possible to create a new organization-specific "integration", i.e. client application identification. For this, specify the option: --use-generic-client=no.

This will guide you through the steps to create.

If the wizard does not detect the application but you know the application, you can force it using option query:

```
ascli config wizard --query=aoc
```

8.2 Configuration: using manual setup

Note: If you used the wizard (recommended): skip this section.

8.2.1 Configuration details

Several types of OAuth authentication are supported:

- JSON Web Token (JWT): authentication is secured by a private key (recommended for ascli)
- · Web based authentication : authentication is made by user using a browser
- URL Token: external users authentication with url tokens (public links)

The authentication method is controlled by option auth.

For a *quick start*, follow the mandatory and sufficient section: API Client Registration (auth=web) as well as [option preset for Aspera on Cloud](#aocpreset).

For a more convenient, browser-less, experience follow the JWT section (auth=jwt) in addition to Client Registration.

In Oauth, a "Bearer" token are generated to authenticate REST calls. Bearer tokens are valid for a period of time.ascli saves generated tokens in its configuration folder, tries to re-use them or regenerates them when they have expired.

8.2.2 Optional: API Client Registration

If you use the built-in client_id and client_secret, skip this and do not set them in next section.

Else you can use a specific OAuth API client_id, the first step is to declare ascli in Aspera on Cloud using the admin interface.

(AoC documentation: Registering an API Client).

Let's start by a registration with web based authentication (auth=web):

- Open a web browser, log to your instance: e.g. https://myorg.ibmaspera.com/
- Go to Apps \rightarrow Admin \rightarrow Organization \rightarrow Integrations
- · Click "Create New"
 - Client Name: ascli
 - Redirect URIs: http://localhost:12345
 - Origins: localhost
 - uncheck "Prompt users to allow client to access"
 - leave the JWT part for now
- Save

Note: for web based authentication, ascli listens on a local port (e.g. specified by the redirect_uri, in this example: 12345), and the browser will provide the OAuth code there. For "ascli', HTTP is required, and 12345 is the default port.

Once the client is registered, a "Client ID" and "Secret" are created, these values will be used in the next step.

8.2.3 option preset for Aspera on Cloud

If you did not use the wizard, you can also manually create a option preset for ascli in its configuration file.

Lets create an option preset called: my_aoc_org using ask interactive input (client info from previous step):

```
ascli config preset ask my_aoc_org url client_id client_secret
option: url> https://myorg.ibmaspera.com/
option: client_id> my_client_id_here
option: client_secret> my_client_secret_here
updated: my_aoc_org
```

(This can also be done in one line using the command config preset update my_aoc_org --url=...)

Define this option preset as default configuration for the aspera plugin:

```
ascli config preset set default aoc my_aoc_org
```

Note: Default auth method is web and default redirect_uri is http://localhost:12345. Leave those default values.

8.2.4 Activation of JSON Web Token (JWT) for direct authentication

For a Browser-less, Private Key-based authentication, use the following steps.

In order to use JWT for Aspera on Cloud API client authentication, a private/public key pair must be used.

8.2.4.1 API Client JWT activation

If you are not using the built-in client_id and secret, JWT needs to be authorized in Aspera on Cloud. This can be done in two manners:

- · Graphically
 - Open a web browser, log to your instance: https://myorg.ibmaspera.com/
 - Go to Apps → Admin → Organization → Integrations
 - Click on the previously created application
 - select tab: "JSON Web Token Auth"
 - Modify options if necessary, for instance: activate both options in section "Settings"
 - Click "Save"
- · Using command line

ascli aoc admin res client modify my_BJbQiFw @json:'{"jwt_grant_enabled":true,"explicit_authorization_require modified

8.2.5 User key registration

The public key must be assigned to your user. This can be done in two manners:

8.2.5.1 Graphically

Open the previously generated public key located here: \$HOME/.aspera/ascli/my_private_key.pub

- Open a web browser, log to your instance: https://myorg.ibmaspera.com/
- Click on the user's icon (top right)
- Select "Account Settings"
- Paste the Public Key in the "Public Key" section
- · Click on "Submit"

8.2.5.2 Using command line

ascli aoc admin res user list
+----+
| id | name |
+----+
| 109952 | Tech Support |
| 109951 | LAURENT MARTIN |
+----+

ascli aoc user profile modify @ruby:'{"public_key"=>File.read(File.expand_path("~/.aspera/ascli/my_private_keymodified

Note: the aspera user info show command can be used to verify modifications.

8.2.6 option preset modification for JWT

To activate default use of JWT authentication for ascli using the option preset, do the following:

- change auth method to JWT
- provide location of private key

provide username to login as (OAuth "subject")

Execute:

```
ascli config preset update my_aoc_org --auth=jwt --private-key=@val:@file:~/.aspera/ascli/my_private_key --us
```

Note: the private key argument represents the actual PEM string. In order to read the content from a file, use the <code>@file:</code> prefix. But if the <code>@file:</code> argument is used as is, it will read the file and set in the config file. So to keep the "@file" tag in the configuration file, the <code>@val:</code> prefix is added.

After this last step, commands do not require web login anymore.

8.2.7 First Use

Once client has been registered and option preset created: ascli can be used:

```
ascli aoc files br /
Current Workspace: Default Workspace (default)
empty
```

8.3 Calling AoC APIs from command line

The command ascli acc bearer can be used to generate an OAuth token suitable to call any AoC API (use the scope option to change the scope, default is user:all). This can be useful when a command is not yet available.

Example:

```
curl -s -H "Authorization: $(ascli aoc bearer_token)" 'https://api.ibmaspera.com/api/v1/group_memberships?emb
It is also possible to get the bearer token for node, as user or as admin using:

ascli aoc files bearer_token_node /

ascli aoc admin res node v4 1234 --secret=_ak_secret_here_ bearer_token_node /
```

8.4 Administration

The admin command allows several administrative tasks (and require admin privilege).

It allows actions (create, update, delete) on "resources": users, group, nodes, workspace, etc... with the admin resource command.

8.4.1 Listing resources

The command aoc admin res <type> list lists all entities of given type. It uses paging and multiple requests if necessary.

The option query can be optionally used. It expects a Hash using Extended Value Syntax, generally provided using: --query=@json:{...}. Values are directly sent to the API call and used as a filter on server side.

The following parameters are supported:

- q: a filter on name of resource (case insensitive, matches if value is contained in name)
- sort: name of fields to sort results, prefix with for reverse order.
- max: maximum number of items to retrieve (stop pages when the maximum is passed)
- pmax: maximum number of pages to request (stop pages when the maximum is passed)
- · page: native api parameter, in general do not use (added by
- per_page : native api parameter, number of items par api call, in general do not use
- Other specific parameters depending on resource type.

Both max and pmax are processed internally in ascli, not included in actual API call and limit the number of successive pages requested to API. ascli will return all values using paging if not provided.

Other parameters are directly sent as parameters to the GET request on API.

page and per_page are normally added by ascli to build successive API calls to get all values if there are more than 1000. (AoC allows a maximum page size of 1000).

q and sort are available on most resource types.

Other parameters depend on the type of entity (refer to AoC API).

Examples:

• List users with laurent in name:

```
ascli aoc admin res user list --query=--query=@json:'{"q":"laurent"}'
```

List users who logged-in before a date:

```
ascli aoc admin res user list --query=@json:'{"q":"last_login_at:<2018-05-28"}'
```

List external users and sort in reverse alphabetical order using name:

```
ascli aoc admin res user list --query=@json:'{"member_of_any_workspace":false,"sort":"-name"}'
```

Refer to the AoC API for full list of query parameters, or use the browser in developer mode with the web UI.

Note: The option select can also be used to further refine selection, refer to section earlier.

8.4.2 Selecting a resource

Resources are identified by a unique id, as well as a unique name (case insensitive).

To execute an action on a specific resource, select it using one of those methods:

- recommended: give id directly on command line after the action: aoc admin res node show 123
- · give name on command line after the action: aoc admin res node show name abc
- provide option id: aoc admin res node show 123
- provide option name: aoc admin res node show --name=abc

8.4.3 Creating a resource

New resources (users, groups, workspaces, etc..) can be created using a command like:

```
ascli aoc admin res create <resource type> @json:'{<...parameters...>}'
```

Some of the API endpoints are described here. Sadly, not all.

Nevertheless, it is possible to guess the structure of the creation value by simply dumping an existing resource, and use the same parameters for the creation.

```
ascli aoc admin res group show 12345 --format=json
```

```
{"created_at":"2018-07-24T21:46:39.000Z","description":null,"id":"12345","manager":false,"name":"A8Demo WS1",
```

Remove the parameters that are either obviously added by the system: id, created_at, updated_at or optional.

And then craft your command:

ascli aoc admin res group create @json:'{"description":"test to delete", "name":"test 1 to delete", "saml_group

If the command returns an error, example:

Well, remove the offending parameters and try again.

Note: Some properties that are shown in the web UI, such as membership, are not listed directly in the resource, but instead another resource is created to link a user and its group: group_membership

8.4.4 Access Key secrets

In order to access some administrative actions on **nodes** (in fact, access keys), the associated secret is required. The secret is provided using the secret option. For example in a command like:

```
ascli aoc admin res node 123 --secret="my_secret_here" v3 info
```

It is also possible to store secrets in the secret vault and then automatically find the related secret using the config finder.

8.4.5 Activity

The activity app can be gueried with:

```
ascli aoc admin analytics transfers
```

It can also support filters and send notification using option notif_to. a template is defined using option notif_template .

mytemplate.erb:

```
From: <%=from_name%> <<%=from_email%>>
To: <<%=ev['user_email']%>>
Subject: <%=ev['files_completed']%> files received

Dear <%=ev[:user_email.to_s]%>,
We received <%=ev['files_completed']%> files for a total of <%=ev['transferred_bytes']%> bytes, starting with <%=ev['content']%>
```

Thank you.

The environment provided contains the following additional variable:

· ev : all details on the transfer event

Example:

```
ascli aoc admin analytics transfers --once-only=yes --lock-port=12345 \
--query=@json:'{"status":"completed","direction":"receive"}' \
--notif-to=active --notif-template=@file:mytemplate.erb
```

Options:

- · once_only keep track of last date it was called, so next call will get only new events
- query filter (on API call)
- notify send an email as specified by template, this could be places in a file with the @file modifier.

Note: This must not be executed in less than 5 minutes because the analytics interface accepts only a period of time between 5 minutes and 6 months. The period is [date of previous execution]..[now].

8.4.6 Transfer: Using specific transfer ports

By default transfer nodes are expected to use ports TCP/UDP 33001. The web UI enforces that. The option default_ports ([yes]/no) allows ascli to retrieve the server ports from an API call (download_setup) which reads the information from aspera.conf on the server.

8.4.7 Using ATS

Refer to section "Examples" of ATS and substitute command ats with aoc admin ats.

8.4.8 Files with type link

Aspera on Cloud Shared folders are implemented through a special type of file: link. A link is the equivalent of a symbolic link on a file system: it points to another folder (not file).

Listing a link (in terminal position of path) will information on the link itself, not the content of the folder it points to. To list the target folder content, add a / a the end of the path.

Example:

```
$ ascli aoc files br the_link
Current Workspace: Default (default)
   +----+
              | 2021-04-28T09:17:14Z | edit
| the_link | link |
+----+
$ ascli aoc files br the_link/
Current Workspace: Default (default)
+----+
     | type | recursive_size | size | modified_time
+----+
              | 2021-04-26T09:00:00Z | edit
| file_inside | file |
+----+
```

8.4.9 Example: Bulk creation of users

```
ascli aoc admin res user create --bulk=yes @json:'[{"email":"dummyuser1@example.com"},{"email":"dummyuser2@ex
+-----+
| id | status |
+-----+
| 98398 | created |
| 98399 | created |
+-----+
```

8.4.10 Example: Find with filter and delete

| 98399 | deleted | +----+

```
ascli aoc admin res user list --query='@json:{"q":"dummyuser"}' --fields=id,email
+----+
| id |
             email
+----+
| 98398 | dummyuser1@example.com |
| 98399 | dummyuser2@example.com |
+----+
thelist=$(ascli aoc admin res user list --query='@json:{"q":"dummyuser"}' --fields=id --format=json --display
echo $thelist
["113501", "354061"]
ascli aoc admin res user delete @json:"$thelist" --bulk=yes
+----+
| id | status |
+----+
| 98398 | deleted |
```

8.4.11 Example: Find deactivated users since more than 2 years

ascli aoc admin res user list --query=@ruby:'{"deactivated"=>true,"q"=>"last_login_at:<#{(DateTime.now.to_time.now

8.4.12 Example: Display current user's workspaces

ascli aoc user workspaces list

+ id +	name	-+ -+
	Engineering Marketing Sales	 -

8.4.13 Example: Create a sub access key in a "node"

Creation of a sub-access key is like creation of access key with the following difference: authentication to node API is made with accesskey (master access key) and only the path parameter is provided: it is relative to the storage root of the master key. (id and secret are optional)

ascli aoc admin resource node --name=_node_name_ --secret=_secret_ v4 access_key create @json:'{"storage":{"p

8.4.14 Example: Display transfer events (ops/transfer)

```
ascli aoc admin res node --secret_secret_ v3 transfer list --query=@json:'[["q","*"],["count",5]]'
Examples of query (TODO: cleanup):
```

{"q":"type(file_upload OR file_delete OR file_download OR file_rename OR folder_create OR folder_delete OR f

8.4.15 Example: Display node events (events)

ascli aoc admin res node --secret=_secret_ v3 events

8.4.16 Example: Display members of a workspace

ascli aoc admin res workspace_membership list --fields=member_type,manager,member.email --query=@json:'{"embe

member_type	manager	member.email
user user user user group user	true false false false false false	john.curtis@email.com

Other query parameters:

{"workspace_membership_through":true, "include_indirect":true}

8.4.17 Example: add all members of a workspace to another workspace

```
a- Get id of first workspace
```

```
WS1='First Workspace'
WS1ID=$(ascli aoc admin res workspace list --query=@json:'{"q":"'"$WS1"'"}' --select=@json:'{"name":"'"$WS1"'"}b- Get id of second workspace
WS2='Second Workspace'
WS2ID=$(ascli aoc admin res workspace list --query=@json:'{"q":"'"$WS2"'"}' --select=@json:'{"name":"'"$WS2"'"}c- Extract membership information
ascli aoc admin res workspace_membership list --fields=manager,member_id,member_type,workspace_id --query=@json:'d-Convert to creation data for second workspace:
grep -Eve '(direct|effective_manager|_count|storage|"id")' ws1_members.json|sed '/workspace_id/ s/"'"$WS1ID"'
or, using jq:
jq '[.[] | {member_type,member_id,workspace_id,manager,workspace_id:"'"$WS2ID"'"}]' ws1_members.json > ws2_me
e-Add members to second workspace
ascli aoc admin res workspace_membership create --bulk=yes @json:@file:ws2_members.json
```

8.4.18 Example: Get users who did not log since a date

8.4.19 Example: List "Limited" users

```
ascli aoc admin res user list --fields=email --select=@json:'{"member_of_any_workspace":false}'
```

8.4.20 Example: create a group, add to workspace and add user to group

Create the group and take note of id

```
ascli aoc admin res group create @json:'{"name":"group 1","description":"my super group"}'
Group: 11111
```

· Get the workspace id

ascli aoc admin res workspace list --query=@json:'{"q":"myworkspace"}' --fields=id --format=csv --display=dat Workspace: 22222

Add group to workspace

• Get a user's id

ascli aoc admin res user list --query=@json:'{"q":"manu.macron@example.com"}' --fields=id --format=csv --disp

User: 33333

ascli aoc admin res workspace_membership create @json:'{"workspace_id":22222,"member_type":"user","member_id"

· Add user to group

ascli aoc admin res group_membership create @json:'{"group_id":11111,"member_type":"user","member_id":33333}'

8.4.21 Example: Perform a multi Gbps transfer between two remote shared folders

In this example, a user has access to a workspace where two shared folders are located on different sites, e.g. different cloud regions.

First, setup the environment (skip if already done)

```
ascli conf wizard --url=https://sedemo.ibmaspera.com --username=laurent.martin.aspera@fr.ibm.com
Detected: Aspera on Cloud
Preparing preset: aoc_sedemo
Using existing key:
/Users/laurent/.aspera/ascli/aspera_aoc_key
Using global client_id.
Please Login to your Aspera on Cloud instance.
Navigate to your "Account Settings"
Check or update the value of "Public Key" to be:
----BEGIN PUBLIC KEY----
SOME PUBLIC KEY PEM DATA HERE
----END PUBLIC KEY----
Once updated or validated, press enter.
creating new config preset: aoc_sedemo
Setting config preset as default for aspera
saving config file
Done.
You can test with:
ascli aoc user profile show
```

This creates the option preset "aoc_<org name>" to allow seamless command line access and sets it as default for aspera on cloud.

Then, create two shared folders located in two regions, in your files home, in a workspace.

Then, transfer between those:

```
ascli -Paoc_show aoc files transfer --from-folder='IBM Cloud SJ' --to-folder='AWS Singapore' 100GB.file --ts=
```

8.4.22 Example: create registration key to register a node

```
ascli aoc admin res client create @json:'{"data":{"name":"laurentnode","client_subject_scopes":["alee","aejd" jfqslfdjlfdjfhdjklqfhdkl
```

8.4.23 Example: delete all registration keys

ascli aoc admin res client list --fields=id --format=csv|ascli aoc admin res client delete @lines:@stdin: --b

```
+----+
| id | status |
+----+
| 99 | deleted |
| 100 | deleted |
| 101 | deleted |
| 102 | deleted |
```

8.4.24 Example: Create a Node

AoC nodes as actually composed with two related entities:

- · An access key created on the Transfer Server (HSTS/ATS)
- a node resource in the AoC application.

The web UI allows creation of both entities in one shot. For more flexibility, ascli allows this in two separate steps.

Note: When selecting "Use existing access key" in the web UI, this actually skips access key creation (first step).

So, for example, the creation of a node using ATS in IBM Cloud looks like (see other example in this manual):

Create the access key on ATS

The creation options are the ones of ATS API, refer to the section on ATS for more details and examples.

```
ascli aoc admin ats access_key create --cloud=softlayer --region=eu-de --params=@json:'{"storage":{"type
```

Once executed, the access key id and secret, randomly generated by the node api, is displayed.

Note: Once returned by the API, the secret will not be available anymore, so store this preciously. ATS secrets can only be reset by asking to IBM support.

Create the AoC node entity

First, Retrieve the ATS node address

```
ascli aoc admin ats cluster show --cloud=softlayer --region=eu-de --fields=transfer_setup_url --format=c
```

```
Then use the returned address for the {\tt url} key to actually create the AoC Node entity:
```

```
ascli aoc admin res node create @json:'{"name":"myname","access_key":"myaccesskeyid","ats_access_key":treation of a node with a self-managed node is similar, but the command aoc admin ats access_key create is replaced
```

Creation of a node with a self-managed node is similar, but the command acc admin ats access_key create is replaced with node access_key create on the private node itself.

8.5 List of files to transfer

Source files are provided as a list with the sources option. Refer to section File list

Note: A special case is when the source files are located on **Aspera on Cloud** (i.e. using access keys and the file id API).

Source files are located on "Aspera on cloud", when :

- · the server is Aspera on Cloud, and executing a download or recv
- · the agent is Aspera on Cloud, and executing an upload or send

In this case:

- If there is a single file : specify the full path
- Else, if there are multiple files:
 - All source files must be in the same source folder
 - Specify the source folder as first item in the list
 - followed by the list of file names.

8.6 Packages

The webmail-like application.

8.6.1 Send a Package

General syntax:

ascli aoc packages send [package extended value] [other parameters such as file list and transfer parameters]

Notes:

- Package creation parameter are sent as positional mandatory parameter. Refer to the AoC package creation API, or display an existing package in JSON to list attributes.
- List allowed shared inbox destinations with: ascli aoc packages shared_inboxes list
- Use fields: recipients and/or bcc_recipients to provide the list of recipients: user or shared inbox.

- Provide either ids as expected by API: "recipients": [{"type": "dropbox", "id": "1234"}]
- or just names: "recipients": [{"The Dest"}] . ascli will resolve the list of email addresses and dropbox names to the expected type/id list, based on case insensitive partial match.
- If a user recipient (email) is not already registered and the workspace allows external users, then the package is sent to an external user, and
 - if the option new_user_option is @json:{"package_contact":true} (default), then a public link is sent and the external user does not need to create an account
 - if the option new_user_option is @json:{}, then external users are invited to join the workspace

8.6.2 Example: Send a package with one file to two users, using their email

ascli aoc packages send @json:'{"name":"my title", "note":"my note", "recipients":["laurent.martin.aspera@fr.ib

8.6.3 Example: Send a package to a shared inbox with metadata

ascli aoc packages send --workspace=eudemo @json:'{"name":"my pack title","recipients":["Shared Inbox With Me It is also possible to use identifiers and API parameters:

ascli aoc packages send --workspace=eudemo @json:'{"name":"my pack title","recipients":[{"type":"dropbox","id

8.6.4 Example: List packages in a given shared inbox

When user packages are listed, the following query is used:

```
{"archived":false, "exclude_dropbox_packages":true, "has_content":true, "received":true}
```

To list packages in a shared inbox, the query has to be specified with the the shared inbox by name or its identifier. Additional parameters can be specified, as supported by the API (to find out available filters, consult the API definition, or use the web interface in developer mode). The current workspace is added unless specified in the query.

Using shared inbox name:

```
ascli aoc packages list --query=@json:'{"dropbox_name":"My Shared Inbox","archived":false,"received":true,"ha
```

Using shared inbox identifier: first retrieve the id of the shared inbox, and then list packages with the appropriate filter.

```
shared_box_id=$(ascli aoc packages shared_inboxes show name 'My Shared Inbox' --format=csv --display=data --f ascli aoc packages list --query=0json:'{"dropbox_id":"'$shared_box_id'","archived":false,"received":true,"has
```

8.6.5 Example: Receive all packages from a given shared inbox

```
ascli aoc packages recv ALL --workspace__workspace_ --once-only=yes --lock-port=12345 --query=@json:'{"dropbo
```

8.6.6 Example: Send a package with files from the Files app

Find files in Files app:

ascli aoc files browse /src_folder

n	aame	type	recursive_size	size	modified_time	access_level
1 1	ample_video 00G .0M.dat 'est.pdf	link file file file		 107374182400 10485760 1265103	2020-11-29T22:49:09Z 2021-04-21T18:19:25Z 2021-05-18T08:22:39Z 2022-06-16T12:49:55Z	edit edit

Let's send a package with the file 10M.dat from subfolder /src_folder in a package:

ascli aoc files node_info /src_folder --format=json --display=data | ascli aoc packages send @json:'{"name":"

8.6.7 Receive new packages only (Cargo)

It is possible to automatically download new packages, like using Aspera Cargo:

ascli aoc packages recv ALL --once-only=yes --lock-port=12345

- · ALL (case sensitive) will download all packages
- --once-only=yes keeps memory of any downloaded package in persistency files located in the configuration folder
- --lock-port=12345 ensures that only one instance is started at the same time, to avoid running two downloads in parallel

Typically, one would execute this command on a regular basis, using the method of your choice: see Scheduler.

8.7 Files

The Files application presents a **Home** folder to users in a given workspace. Files located here are either user's files, or shared folders.

8.7.1 Download Files

The general download command is:

```
ascli aoc files download <source folder path> <source filename 1> ...
```

I.e. the first argument is the source folder, and the following arguments are the source file names in this folder.

If a single file or folder is to be downloaded, then a single argument can be provided.

```
ascli aoc files download <single file path>
```

8.7.2 Shared folders

Shared folder created by users are managed through **permissions**. For creation, parameters are the same as for node api permissions. ascli expects the same payload for creation, but it will automatically populate required tags if needed. Also, the pseudo key with is available: it will lookup the name in the contacts and fill the proper type and id. The pseudo parameter link_name allows changing default "shared as" name.

· List permissions on a shared folder as user

```
ascli aoc files perm /shared_folder_test1 list
```

Share a personal folder with other users

```
ascli aoc files perm /shared_folder_test1 create @json:'{"with":"laurent"}'
```

· Revoke shared access

ascli aoc files perm /shared_folder_test1 delete 6161

8.7.3 Cross Organization transfers

It is possible to transfer files directly between organizations without having to first download locally and then upload...

Although optional, the creation of option preset is recommended to avoid placing all parameters in the command line.

Procedure to send a file from org1 to org2:

- Get access to Organization 1 and create a option preset: e.g. org1, for instance, use the Wizard
- Check that access works and locate the source file e.g. mysourcefile, e.g. using command files browse
- Get access to Organization 2 and create a option preset: e.g. org2
- Check that access works and locate the destination folder mydestfolder
- · execute the following:

ascli -Porg1 aoc files node_info /mydestfolder --format=json --display=data | ascli -Porg2 aoc files upload m Explanation:

- -Porg1 aoc use Aspera on Cloud plugin and load credentials for org1
- files node_info /mydestfolder generate transfer information including node api credential and root id, suitable for the next command
- --format=json format the output in JSON (instead of default text table)
- --display=data display only the result, and remove other information, such as workspace name
- I the standard output of the first command is fed into the second one
- -Porg2 aoc use Aspera on Cloud plugin and load credentials for org2
- files upload mysourcefile upload the file named mysourcefile (located in org1)
- --transfer=node use transfer agent type node instead of default direct
- --transfer-info=@json:@stdin: provide node transfer agent information, i.e. node API credentials, those are expected in JSON format and read from standard input

8.7.4 Find Files

The command acc files find [--query=expression] will recursively scan storage to find files matching the expression criteria. It works also on node resource using the v4 command. (see examples)

The expression can be of 3 formats:

- empty (default): all files, equivalent to value: exec:true
- not starting with exec: : the expression is a regular expression, using Ruby Regex syntax, equivalent to value: exec:f['name'].match(/expression/)

For instance, to find files with a special extension, use --query='\.myext\$'

• starting with exec: : the Ruby code after the prefix is executed for each entry found. The entry variable name is f. The file is displayed if the result of the expression is true.

Examples of expressions: (using like this: --query=exec: '<expression>')

Find files more recent than 100 days

```
f["type"].eql?("file") and (DateTime.now-DateTime.parse(f["modified_time"]))<100
```

Find files older than 1 year on a given node and store in file list

```
f["type"].eq1?("file") and (DateTime.now-DateTime.parse(f["modified_time"]))<100
ascli aoc admin res node --name='my node name' --secret='my_secret_here' v4 find / --fields=path --query
```

• Find files larger than 1MB

```
f["type"].eql?("file") and f["size"].to_i>1000000
```

· Delete the files, one by one

```
cat my_file_list.txt|while read path;do echo ascli aoc admin res node --name='my node name' --secret='my
```

Delete the files in bulk

```
cat my_file_list.txt | ascli aoc admin res node --name='my node name' --secret='my_secret_here' v3 delet
```

8.8 AoC sample commands

```
aoc admin analytics transfers --query=@json:'{"status":"completed","direction":"receive"}' --notif-to=my_reci
aoc admin ats access_key create --cloud=aws --region=my_aws_bucket_region --params=@json:'{"id":"ak_aws","nam
aoc admin ats access_key create --cloud=softlayer --region=my_icos_bucket_region --params=@json:'{"id":"ak1ib
aoc admin ats access_key delete ak1ibmcloud
aoc admin ats access_key list --fields=name,id
aoc admin ats access_key node ak1ibmcloud --secret=my_secret_here browse /
aoc admin ats cluster clouds
aoc admin ats cluster list
aoc admin ats cluster show --cloud=aws --region=eu-west-1
aoc admin ats cluster show 1f412ae7-869a-445c-9c05-02ad16813be2
aoc admin auth_providers list
```

```
aoc admin res application list
aoc admin res client list
aoc admin res client access key list
aoc admin res client_registration_token create @json:'{"data":{"name":"test_client_reg1","client_subject_scop
aoc admin res client_registration_token delete my_clt_reg_id
aoc admin res client_registration_token list
aoc admin res contact list
aoc admin res dropbox list
aoc admin res dropbox_membership list
aoc admin res group list
aoc admin res kms_profile list
aoc admin res node list
aoc admin res operation list
aoc admin res organization show
aoc admin res package list --http-options=@json:'{"read_timeout":120.0}'
aoc admin res saml_configuration list
aoc admin res self show
aoc admin res short_link list
aoc admin res user list
aoc admin res workspace_membership list
aoc admin resource node --name=my_aoc_ak_name --secret=my_aoc_ak_secret do browse /
aoc admin resource node --name=my_aoc_ak_name --secret=my_aoc_ak_secret do delete /folder1
aoc admin resource node --name=my_aoc_ak_name --secret=my_aoc_ak_secret do mkdir /folder1
aoc admin resource node --name=my_aoc_ak_name --secret=my_aoc_ak_secret do v3 access_key create @json:'{"id":
aoc admin resource node --name=my_aoc_ak_name --secret=my_aoc_ak_secret do v3 events
aoc admin resource node do name my_aoc_ak_name --secret=my_aoc_ak_secret v3 access_key delete testsub1
aoc admin resource workspace list
aoc admin resource workspace_membership list --fields=ALL --query=@json:'{"page":1,"per_page":50,"embed":"mem
aoc admin subscription
aoc automation workflow action my_wf_id create @json:'{"name":"toto"}' \
aoc automation workflow create @json:'{"name":"test_workflow"}'
aoc automation workflow delete my_wf_id
aoc automation workflow list
aoc automation workflow list --query=@json:'{"show_org_workflows":"true"}' --scope=admin:all
aoc automation workflow list --select=@json:'{"name":"test_workflow"}' --fields=id --format=csv --display=dat
aoc bearer_token --display=data --scope=user:all
aoc faspex
aoc files bearer /
aoc files bearer_token_node / --cache-tokens=no
aoc files browse /
aoc files browse / --link=my_aoc_publink_folder
aoc files delete /testsrc
aoc files download --transfer=connect /200KB.1
aoc files find / --query='\.partial$'
aoc files http_node_download --to-folder=. /200KB.1
aoc files mkdir /testsrc
aoc files modify my_aoc_test_folder
aoc files permission my_aoc_test_folder list
aoc files rename /somefolder testdst
aoc files short_link create /testdst private
aoc files short_link create testdst public
aoc files short_link list /testdst private
aoc files show %id:my_file_id
aoc files show /200KB.1
aoc files sync ad st --sync-info=@json:'{"name":"syncv2", "reset":true, "direction":"pull", "local":{"path":"my_
aoc files sync ad st --sync-info=@json:'{"sessions":[{"name":"syncv1","direction":"pull","local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_dir":"my_local_
aoc files sync start --sync-info=@json:'{"name":"syncv2","reset":true,"direction":"pull","local":{"path":"my_
aoc files sync start --sync-info=@json:'{"sessions":[{"name":"syncv1","direction":"pull","local_dir":"my_local
```

aoc files thumbnail my_aoc_media_file

```
aoc files transfer --from-folder=/testsrc --to-folder=/testdst testfile.bin
aoc files upload --to-folder=/ testfile.bin --link=my_aoc_publink_folder
aoc files upload --to-folder=/testsrc testfile.bin
aoc files upload Test.pdf --transfer=node --transfer-info=@json:@stdin:
aoc files v3 info
aoc gateway https://localhost:12345/aspera/faspex
aoc org --link=my_aoc_publink_recv_from_aocuser
aoc organization
aoc packages browse "my_package_id" /contents
aoc packages list
aoc packages list --query=@json:'{"dropbox_name":"my_aoc_shbx_name", "sort":"-received_at", "archived":false, "r
aoc packages recv "my_package_id" --to-folder=.
aoc packages recv ALL --to-folder=. --once-only=yes --lock-port=12345
aoc packages recv ALL --to-folder=. --once-only=yes --lock-port=12345 --query=@json:'{"dropbox_name":"my_aoc_
aoc packages send --workspace="my_aoc_shbx_ws" @json:'{"name":"Important files delivery", "recipients":["my_aoc_shbx_ws" @json:'t"]
aoc packages send --workspace="my_aoc_shbx_ws" @json:'{"name":"Important files delivery", "recipients":["my_aoc_shbx_ws" @json:'("name":"Important files delivery", "recipients"]
aoc packages send --workspace="my_aoc_shbx_ws" @json:'{"name":"Important files delivery", "recipients":["my_aoc_shbx_ws" @json:'t"]
aoc packages send @json:'{"name":"Important files delivery", "recipients":["my_email_external_user"]}' --new-u
aoc packages send @json:'{"name":"Important files delivery", "recipients":["my_email_internal_user"], "note":"m
aoc packages send @json:'{"name":"Important files delivery"}' testfile.bin --link=my aoc publink send aoc use
aoc packages send @json:'{"name":"Important files delivery"}' testfile.bin --link=my_aoc_publink_send_shd_inb
aoc packages shared_inboxes list
aoc remind --username=my_aoc_user_email
aoc servers
aoc user profile modify @json:'{"name":"dummy change"}'
aoc user profile show
aoc user workspaces current
aoc user workspaces list
```

Plugin: ats: IBM Aspera Transfer Service

ATS is usable either:

- from an AoC subscription : ascli aoc admin ats : use AoC authentication
- or from an IBM Cloud subscription : ascli ats : use IBM Cloud API key authentication

9.1 IBM Cloud ATS: creation of api key

This section is about using ATS with an IBM cloud subscription. If you are using ATS as part of AoC, then authentication is through AoC, not IBM Cloud.

First get your IBM Cloud APIkey. For instance, it can be created using the IBM Cloud web interface, or using command line:

```
ibmcloud iam api-key-create mykeyname -d 'my sample key'
OK
API key mykeyname was created
```

Please preserve the API key! It cannot be retrieved after it's created.

Name mykeyname

Description my sample key

Created At 2019-09-30T12:17+0000

API Key my_secret_api_key_here

Locked false

UUID ApiKey-05b8fadf-e7fe-4bc4-93a9-6fd348c5ab1f

References:

- https://console.bluemix.net/docs/iam/userid keys.html#userapikey
- https://ibm.ibmaspera.com/helpcenter/transfer-service

Then, to register the key by default for the ats plugin, create a preset. Execute:

9.2 ATS Access key creation parameters

When creating an ATS access key, the option params must contain an extended value with the creation parameters. Those are directly the parameters expected by the ATS API.

9.3 Misc. Examples

ascli ats api_key create

```
Example: create access key on IBM Cloud (softlayer):

ascli ats access_key create --cloud=softlayer --region=ams --params=@json:'{"storage":{"type":"softlayer_swift
Example: create access key on AWS:

ascli ats access_key create --cloud=aws --region=eu-west-1 --params=@json:'{"id":"myaccesskey","name":"laurent
Example: create access key on Azure SAS:

ascli ats access_key create --cloud=azure --region=eastus --params=@json:'{"id":"myaccesskey","name":"laurent
(Note that the blob name is mandatory after server address and before parameters. and that parameter sr=c is mandatory.)

Example: create access key on Azure:

ascli ats access_key create --cloud=azure --region=eastus --params=@json:'{"id":"myaccesskey","name":"laurent
delete all my access keys:

ascli ats access_key list --field=id --format=csv | ascli ats access_key delete @lines:@stdin: --bulk=yes
The parameters provided to ATS for access key creation are the ones of ATS API for the POST /access_keys endpoint.
```

9.4 ATS sample commands

```
ats access_key cluster ak2ibmcloud --secret=my_secret_here
ats access_key create --cloud=aws --region=my_aws_bucket_region --params=@json:'{"id":"ak_aws","name":"my tes
ats access_key create --cloud=softlayer --region=my_icos_bucket_region --params=@json:'{"id":"ak2ibmcloud","s
ats access_key delete ak2ibmcloud
ats access_key delete ak_aws
ats access_key entitlement ak2ibmcloud
ats access_key list --fields=name,id
ats access_key node ak2ibmcloud browse / --secret=my_secret_here
ats access_key show ak2ibmcloud
ats api_key create
ats api_key instances
ats api_key list
ats cluster clouds
ats cluster list
ats cluster show --cloud=aws --region=eu-west-1
ats cluster show 1f412ae7-869a-445c-9c05-02ad16813be2
```

Plugin: server: IBM Aspera High Speed Transfer Server (SSH)

The server plugin is used for operations on Aspera HSTS using SSH authentication. It is the legacy way of accessing an Aspera Server, often used for server to server transfers. An SSH session is established, authenticated with either a password or an SSH private key, then commands ascp (for transfers) and ascmd (for file operations) are executed.

Note: The URL to be provided is usually: ssh://_server_address_:33001

10.1 Server sample commands

```
server browse /
server browse NEW_SERVER_FOLDER/testfile.bin
server browse folder_1/target_hot
server cp NEW_SERVER_FOLDER/testfile.bin folder_1/200KB.2
server delete NEW_SERVER_FOLDER
server delete folder_1/target_hot
server delete folder_1/to.delete
server download NEW_SERVER_FOLDER/testfile.bin --to-folder=. --transfer-info=@json:'{"wss":false,"resume":{"i
server download NEW_SERVER_FOLDER/testfile.bin --to-folder=folder_1 --transfer=node
server du /
server health transfer --to-folder=folder_1 --format=nagios
server md5sum NEW_SERVER_FOLDER/testfile.bin
server mkdir NEW_SERVER_FOLDER --logger=stdout
server mkdir folder_1/target_hot
server mv folder_1/200KB.2 folder_1/to.delete
server sync admin status --sync-info=@json:'{"name":"sync2","local":{"path":"my_local_sync_dir"}}'
server sync admin status --sync-session=mysync --sync-info=@json:'{"sessions":[{"name":"mysync","local_dir":"
server sync start --sync-info=@json:'{"name":"sync2","local":{"path":"my_local_sync_dir"},"remote":{"path":"'
server sync start --sync-info=@json:'{"sessions":[{"name":"mysync","direction":"pull","remote_dir":"'"NEW_SER
server upload --sources=@ts --ts=@json:'{"EX_ascp_args":["--file-list","'"filelist.txt"'"]}' --to-folder=NEW_
server upload --sources=@ts --ts=@json:'{"EX_ascp_args":["--file-pair-list","'"filepairlist.txt"'"]}'
server upload --sources=0ts --ts=0json:'{"EX_file_list":"'"filelist.txt"'"}' --to-folder=NEW_SERVER_FOLDER
server upload --sources=@ts --ts=@json:'{"EX_file_pair_list":"'"filepairlist.txt"'"}'
server upload --sources=@ts --ts=@json:'{"paths":[{"source":"testfile.bin","destination":"NEW_SERVER_FOLDER/c
server upload --src-type=pair --sources=@json:'["testfile.bin","NEW_SERVER_FOLDER/othername"]'
server upload --src-type=pair testfile.bin NEW_SERVER_FOLDER/othername --notif-to=my_recipient_email --transf
server upload --src-type=pair testfile.bin folder_1/with_options --ts=@json:'{"cipher":"aes-192-gcm","content
server upload --to-folder=folder_1/target_hot --lock-port=12345 --ts=@json:'{"EX_ascp_args":["--remove-after-
```

server upload testfile.bin --to-folder=NEW_SERVER_FOLDER --ts=@json:'{"multi_session":3,"multi_session_thresh

10.2 Authentication on Server with SSH session

If SSH is the session protocol (by default i.e. not WSS), then following session authentication methods are supported:

- password: SSH password
- ssh_keys: SSH keys (Multiple SSH key paths can be provided.)

If username is not provided then the default transfer user xfer is used.

If no SSH password or key is provided and a transfer token is provided in transfer spec (option ts), then standard SSH bypass keys are used. Example:

```
ascli server --url=ssh://_server_address_:33001 ... --ts=@json:'{"token":"Basic _token_here_"}'
```

Note: If you need to use the Aspera public keys, then specify an empty token: --ts=@json:'{"token":""}'
: Aspera public SSH keys will be used, but the protocol will ignore the empty token.

The value of the ssh_keys option can be a single value or an Array. Each value is a **path** to a private key and is expanded (~ is replaced with the user's home folder).

Examples:

```
ascli server --ssh-keys=@/list:,~/.ssh/id_rsa
ascli server --ssh-keys=@/list:,~/.ssh/id_rsa
ascli server --ssh-keys=@/json:'["~/.ssh/id_rsa"]'
```

For file operation command (browse, delete), the Ruby SSH client library Net::SSH is used and provides several options settable using option ssh_options.

For a list of SSH client options, refer to the Ruby documentation of Net::SSH.

Some of the 50 available SSH options:

- verbose
- use_agent
- passphrase

By default the SSH library will check if a local ssh-agent is running.

On Linux, if you get an error message such as:

```
ERROR -- net.ssh.authentication.agent: could not connect to ssh-agent: Agent not configured or on Windows:
```

ERROR -- net.ssh.authentication.agent: could not connect to ssh-agent: pageant process not running

This means that your environment suggests to use an agent but you don't have such an SSH agent running, then:

- Check env var: SSH_AGENT_SOCK
- Check your file: \$HOME/.ssh/config
- Check if the SSH key is protected with a passphrase (then, use the passphrase SSH option)
- Check the Ruby SSH manual
- To disable the use of ssh-agent, use the option ssh options like this:

```
ascli server --ssh-options=@json:'{"use_agent": false}' ...
```

Note: This can also be set using a preset.

If one of the SSH private keys is passphrase-protected, then option passphrase can be used. It is equivalent to setting both options ssh_options.passphrase and ts.ssh_private_key_passphrase.

10.3 Other session channels for server

URL schemes local and https are also supported (mainly for testing purpose). (--url=local: , --url=https://...)

- local will execute ascmd locally, instead of using an SSH connection.
- https will use Web Socket Session: This requires the use of a transfer token. For example a Basic token can be used.

As, most of the time, SSH is used, if an http scheme is provided without token, the plugin will fallback to SSH and port 33001.

10.4 Examples: server

One can test the server application using the well known demo server:

```
ascli config initdemo
ascli server browse /aspera-test-dir-large
ascli server download /aspera-test-dir-large/200MB
```

initdemo creates a option preset demoserver and set it as default for plugin server.

If an SSH private key is used for authentication with a passphrase, the passphrase needs to be provided to both options: $ssh_options$, for browsing, and ts for transfers:

ascli server --url=ssh://_server_address_here_:33001 --username=_user_here_ --ssh_keys=_private_key_path_here

Plugin: node: IBM Aspera High Speed Transfer Server Node

This plugin gives access to capabilities provided by HSTS node API.

Note: capabilities of this plugin are used in other plugins which access to the node API, such as aoc.

11.1 File Operations

It is possible to:

- browse
- transfer (upload / download)
- ...

11.2 Central

The central subcommand uses the "reliable query" API (session and file). It allows listing transfer sessions and transferred files.

Filtering can be applied:

ascli node central file list

by providing the validator option, offline transfer validation can be done.

11.3 FASP Stream

It is possible to start a FASPStream session using the node API:

Use the "node stream create" command, then arguments are provided as a transfer-spec.

```
ascli node stream create --ts=@json:'{"direction":"send","source":"udp://233.3.3.4:3000?loopback=1&ttl=2","de
```

11.4 Watchfolder

Refer to Aspera documentation for watch folder creation.

ascli supports remote operations through the node API. Operations are:

- · Start watchd and watchfolderd services running as a system user having access to files
- · configure a watchfolder to define automated transfers

```
ascli node service create @json:'{"id":"mywatchd","type":"WATCHD","run_as":{"user":"user1"}}'
ascli node service create @json:'{"id":"mywatchfolderd","type":"WATCHFOLDERD","run_as":{"user1":"user1"}}'
ascli node watch_folder create @json:'{"id":"mywfolder","source_dir":"/watch1","target_dir":"/","transport":{
```

11.5 Out of Transfer File Validation

Follow the Aspera Transfer Server configuration to activate this feature.

11.6 Example: SHOD to ATS

Scenario: Access to a **Shares on Demand** (SHOD) server on AWS is provided by a partner. We need to transfer files from this third party SHOD instance into our Azure BLOB storage. Simply create an **Aspera Transfer Service** instance, which provides access to the node API. Then create a configuration for the **SHOD** instance in the configuration file: in section "shares", a configuration named: aws_shod. Create another configuration for the Azure ATS instance: in section "node", named azure ats. Then execute the following command:

```
ascli node download /share/sourcefile --to-folder=/destination_folder --preset=aws_shod --transfer=node --tran
```

11.7 node file information

When node api is used with an Access key, extra information can be retrieved, such as preview.

Note: Display of preview on terminal requires installation of extra gem: rmagick

```
dnf install -y ImageMagick-devel
gem install rmagick rainbow
```

For example it is possible to display the preview of a file, if it exists, using:

```
ascli aoc files thumbnail /preview_samples/Aspera.mpg
```

Using direct node access and an access key, one can do:

```
ascli node access_key do self thumbnail /preview_samples/Aspera.mpg
```

Note: To specify the file by its file id, use the selector syntax: %id:_file_id_here_

Note: To force textual display of the preview on iTerm, prefix command with: $env - u TERM_PROGRAM - u LC_TERMINAL$

11.8 Create access key

```
ascli node access_key create @json:'{"id":"myaccesskey", "secret": "my_secret_here", "storage": {"type": "local", "
```

11.9 Node sample commands

```
node access_key create @json:'{"id":"testingAK1","storage":{"type":"local","path":"/"}}'
node access_key delete testingAK1
node access_key do my_aoc_ak_name browse /
node access_key do my_aoc_ak_name delete /folder2
node access_key do my_aoc_ak_name delete testfile1
node access_key do my_aoc_ak_name download testfile1 --to-folder=.
node access_key do my_aoc_ak_name find /
node access_key do my_aoc_ak_name mkdir /folder1
node access_key do my_aoc_ak_name node_info /
node access_key do my_aoc_ak_name rename /folder1 folder2
node access_key do my_aoc_ak_name show %id:1
node access_key do my_aoc_ak_name show /testfile1
node access_key do my_aoc_ak_name thumbnail /testfile1
node access_key do my_aoc_ak_name upload 'faux:///testfile1?1k' --default_ports=no
node access_key list
node api_details
node async bandwidth 1
node async counters 1
node async files 1
node async list
node async show 1
node async show ALL
node basic token
node browse / -r
node delete /todelete
node delete @list:,folder_1/todelete,folder_1/tdlink,folder_1/delfile
node delete folder_1/10MB.2
node delete testfile.bin
node download testfile.bin --to-folder=.
node health
node info --fpac='function FindProxyForURL(url,host){return "DIRECT"}'
node license
node mkdir folder_1/todelete
node mkfile folder_1/delfile1 "hello world"
node mklink folder_1/todelete folder_1/tdlink
node rename folder_1 delfile1 delfile
node search / --query=@json:'{"sort":"mtime"}'
node service create @json:'{"id":"service1","type":"WATCHD","run_as":{"user":"user1"}}'
node service delete service1
node service list
node space /
node ssync bandwidth my_syncid
node ssync counters my_syncid
node ssync create @json:'{"configuration":{"name":"sync1","local":{"path":"my_local_path"},"remote":{"host":"
node ssync delete my_syncid
node ssync files my_syncid
node ssync list
node ssync show my_syncid
node ssync start my_syncid
node ssync state my_syncid
node ssync stop my_syncid
node ssync summary my_syncid
node sync ad st --sync-info=@json:'{"name":"syncv2","reset":true,"direction":"pull","local":{"path":"my_local
node sync ad st --sync-info=@json:'{"sessions":[{"name":"syncv1","direction":"pull","local_dir":"my_local_syn
node sync start --sync-info=@json:'{"name":"syncv2","reset":true,"direction":"pull","local":{"path":"my_local
node sync start --sync-info=@json:'{"sessions":[{"name":"syncv1","direction":"pull","local_dir":"my_local_syn
node transfer list --query=@json:'{"active_only":true}'
```

```
node upload --to-folder=folder_1 --sources=@ts --ts=@json:'{"paths":[{"source":"/aspera-test-dir-small/10MB.2 node upload --username=my_aoc_ak_name --password=my_aoc_ak_secret testfile.bin node upload testfile.bin --to-folder=folder_1 --ts=@json:'{"target_rate_cap_kbps":10000}'
```

Plugin: faspex5: IBM Aspera Faspex v5

IBM Aspera's newer self-managed application.

3 authentication methods are supported:

- · jwt : general purpose, private-key based authentication
- · link: public link authentication
- · web : requires authentication with web browser
- boot: use authentication token copied from browser (experimental)

12.1 Faspex 5 JWT authentication

This is the general purpose and **recommended** method to use.

Activation is in two steps:

· The admninistrator must create an API client in Faspex with JWT support

This operation is generally done only once:

- As Admin, Navigate to the web UI: Admin → Configurations → API Clients → Create
- Give a name. like ascli
- Activate JWT
- There is an option to set a general public key allowing the owner of the private key to impersonate any user.
 Unless you want to do this, leave this field empty.
- Click on Create Button
- Take note of Client Id (and Client Secret, but not used in current version)
- The user uses a private key and sets the public key in his faspex 5 profile

This operation is done by each user using the CLI.

- As user, click on the user logo, left to the app switcher on top right.
- Select Account Settings
- on the bottom in the text field: Public key in PEM format paste the public key corresponding to the private key used by the user.

Note: If you don't have any refer to section Private Key

Then use these options:

```
--auth=jwt
--client-id=_client_id_here_
--client-secret=my_secret_here
--username=_username_here_
--private-key=@file:.../path/to/key.pem
```

Note: The private_key option must contain the PEM **value** (not file path) of the private key which can be read from a file using the modifier: @file:, e.g. @file:/path/to/key.pem.

As usual, typically a user will create preset to avoid having to type these options each time.

Example:

```
ascli conf preset update myf5 --auth=jwt --client-id=_client_id_here_ --client-secret=my_secret_here --userna ascli conf preset set default faspx5 myf5 ascli faspex5 user profile show
```

12.2 Faspex 5 web authentication

The admninistrator must create an API client in Faspex for an external web app support:

- As Admin, Navigate to the web UI: Admin → Configurations → API Clients → Create
- · Do not Activate JWT
- Set Redirect URI to https://127.0.0.1:8888
- Click on Create Button
- · Take note of Client Id (and Client Secret, but not used in current version)

The user will use the following options:

```
--auth=web
--client-id=_client_id_here_
--client-secret=my_secret_here
--redirect-uri=https://127.0.0.1:8888
```

12.3 Faspex 5 bootstrap authentication

For boot method: (will be removed in future)

- · As user: Open a Web Browser
- Start developer mode
- Login to Faspex 5
- Find the first API call with Authorization header, and copy the value of the token (series of base64 values with dots)

Use this token as password and use --auth=boot.

```
ascli conf preset update f5boot --url=https://localhost/aspera/faspex --auth=boot --password=_token_here_
```

12.4 Faspex 5 sample commands

Most commands are directly REST API calls. Parameters to commands are carried through option query, as extended value, for list, or through positional parameter for creation. One can conveniently use the JSON format with prefix @json:.

Note: The API is listed in Faspex 5 API Reference under IBM Aspera Faspex API.

```
faspex5 admin res accounts list
faspex5 admin res contacts list
faspex5 admin res jobs list
faspex5 admin res metadata_profiles list
faspex5 admin res node list
faspex5 admin res oauth_clients list
faspex5 admin res registrations list
faspex5 admin res saml_configs list
faspex5 admin res shared_inboxes invite %name:'ascli shinbox' johnny@example.com
faspex5 admin res shared_inboxes members %name:'ascli shinbox' create %name:john@example.com
faspex5 admin res shared_inboxes members %name:'ascli shinbox' delete %name:john@example.com
```

```
faspex5 admin res shared_inboxes members %name: 'ascli shinbox' delete %name: johnny@example.com
faspex5 admin res shared_inboxes members %name: 'ascli shinbox' list
faspex5 admin res workgroups list
faspex5 admin smtp show
faspex5 admin smtp test my_email_external
faspex5 bearer_token
faspex5 gateway https://localhost:12345/aspera/faspex
faspex5 health
faspex5 packages list --box=my_faspex5_shinbox
faspex5 packages list --query=@json:'{"mailbox":"inbox","state":["released"]}'
faspex5 packages receive "my_package_id" --to-folder=. --ts=@json:'{"content_protection_password":"abc123_you
faspex5 packages receive --box=my_faspex5_shinbox "my_package_id" --to-folder=.
faspex5 packages receive ALL --once-only=yes --to-folder=.
faspex5 packages receive INIT --once-only=yes
faspex5 packages send @json: '{"title": "test title", "recipients": ["my_shinbox"], "metadata": {"Options": "Opt1", "
faspex5 packages send @json:'{"title":"test title","recipients":[{"name":"my_f5_user"}]}' testfile.bin --ts=@
faspex5 packages show "my_package_id"
faspex5 packages show --box=my_faspex5_shinbox "my_package_id"
faspex5 postprocessing @json: '{"url": "https://localhost:8443/domain", "processing": {"script_folder": "tests"}, "
faspex5 user profile modify @json:'{"preference":{"connect disabled":false}}'
faspex5 user profile show
```

12.5 Faspex 5: inbox selection

By default, package operations (send, receive, list) are done on the user's inbox.

To select another inbox, use option box with one of the following values:

- inbox : user's inbox
- outbox : user's sent packages
- · name of a shared inbox

12.6 Faspex 5: Send a package

The Hash creation parameter provided to command faspex5 packages send corresponds to the Faspex 5 API: POST /packages.

Required fields are title and recipients. Example using @json: format:

```
{"title": "some title", "recipients": [{"recipient_type": "user", "name": "user@example.com"}]}
recipient_type is one of (Refer to API):
```

- user
- workgroup
- external user
- · distribution list
- shared_inbox

ascli adds some convenience: The API expects the field recipients to be an Array of Hash, each with field name and optionally recipient_type. It is also possible to provide an Array of String, with simply a recipient name. Then ascli will lookup existing contacts among all possible types, use it if a single match is found, and set the name and recipient_type accordingly. Else an exception is sent.

Note: The lookup is case insensitive and on partial matches.

```
{"title": "some title", "recipients": ["user@example.com"]}
```

If the lookup needs to be only on certain types, you can specify the field: recipient_types with either a single value or an Array of values (from the list above). e.g. :

```
{"title":"test title", "recipient_types": "user", "recipients": ["user1@example.com", "user2@example.com"]}
```

12.7 Faspex 5: Send a package with metadata

The interface is the one of the API (Refer to API documentation, or look at request in browser):

ascli faspex5 packages send @json:'{"title":"test title","recipients":["my shared inbox"],"metadata":{"Confidence of the confidence of the

12.8 Faspex 5: Receive a package

The (numeric) identifier of the package t receive is given as argument to command faspex5 packages receive.

Note: option box applies.

12.9 Faspex 5: List packages

The following parameters in option query are supported:

- q: a filter on name (case insensitive, matches if value is contained in name)
- max: maximum number of items to retrieve (stop pages when the maximum is passed)
- pmax: maximum number of pages to request (stop pages when the maximum is passed)
- offset: native api parameter, in general do not use (added by ascli)
- limit: native api parameter, number of items par api call, in general do not use (added by ascli)

Admin only: If the value ALL is provided to option box, then all packages are selected.

12.10 Faspex 5: List all shared inboxes

```
ascli faspex5 admin res shared list --query=@json:'{"all":true}' --fields=id,name
```

Shared inbox members can also be listed, added, removed, and external users can be invited to a shared inbox.

```
ascli faspex5 admin res shared_inboxes invite '%name:ascli shinbox' john@example.com
It is equivalent to:
```

ascli faspex5 admin res shared_inboxes invite '%name:ascli shinbox' @json:'{"email_address":"john@example.com Other payload parameters are possible in Hash format:

```
{"description": "blah", "prevent_http_upload": true, "custom_link_expiration_policy": false, "invitation_expires_af
```

12.11 Faspex 5: Create Metadata profile

```
ascli faspex5 admin res metadata_profiles create @json:'{"name":"the profile","default":false,"title":{"max_l
```

12.12 Faspex 5: Create a Shared inbox with specific metadata profile

```
ascli faspex5 admin res shared create @json:'{"name":"the shared inbox", "metadata_profile_id":1}'
```

12.13 Faspex 5: List content in Shared folder and send package from remote source

12.14 Faspex 5: receive all packages (cargo)

To receive all packages, only once, through persistency of already received packages:

```
ascli faspex5 packages receive ALL --once-only=yes
```

%<field>:<value>. e.g. --shared-folder=3

To initialize, and skip all current package so that next time ALL is used, only newer packages are downloaded:

ascli faspex5 packages receive INIT --once-only=yes

12.15 Faspex 5: Faspex 4-style postprocessing

ascli provides command postprocessing in plugin faspex5 to emulate Faspex 4 postprocessing. It implements Faspex 5 web hooks, and calls a local script with the same environment as Faspex 4.

It is invoked like this:

```
ascli faspex5 postprocessing @json:'{"url":"http://localhost:8080/processing"}'
```

The following parameters are supported:

parameter	type	default	description
url	string	http://localhost:8080	Defines the base url on which requests are listened
certificate	hash	nil	used to define certificate if https is used
certificate.key	string	nil	path to private key file
certificate.cert	string	nil	path to certificate
certificate.chain	string	nil	path to intermediary certificates
processing	hash	nil	behavior of post processing
processing.script folder	string		prefix added to script path
processing.fail on error	bool	false	if true and process exit with non zero, then fail
processing.timeout_seconds	integer	60	processing script is killed if takes more time

Parameter url defines:

- · if http or https is used
- the local port
- · the "domain", i.e. main path of url

When a request is received the following happens:

- · the processor get the path of the url called
- it removes the "domain
- it prepends it with the value of script_folder
- it executes the script
- · upon success, a success code is returned

In Faspex 5, configure like this:

Webhook endpoint URI: http://localhost:8080/processing/script1.sh

Then, the postprocessing script executed will be script1.sh.

Environment variables at set to the values provided by the web hook which are the same as Faspex 4 postprocessing.

Plugin: faspex: IBM Aspera Faspex v4

Notes:

- The command v4 requires the use of APIv4, refer to the Faspex Admin manual on how to activate.
- For full details on Faspex API, refer to: Reference on Developer Site

13.1 Listing Packages

Command: faspex package list

13.1.1 Option box

By default it looks in box inbox, but the following boxes are also supported: archive and sent, selected with option box.

13.1.2 Option recipient

A user can receive a package because the recipient is:

- the user himself (default)
- the user is member of a dropbox/workgroup: filter using option recipient set with value *<name of dropbox/workgroup>

13.1.3 Option query

As inboxes may be large, it is possible to use the following query parameters:

- count : (native) number items in one API call (default=0, equivalent to 10)
- page: (native) id of page in call (default=0)
- startIndex: (native) index of item to start, default=0, oldest index=0
- max: maximum number of items
- pmax: maximum number of pages

(SQL query is LIMIT <startIndex>, <count>)

The API is listed in Faspex 4 API Reference under "Services (API v.3)".

If no parameter max or pmax is provided, then all packages will be listed in the inbox, which result in paged API calls (using parameter: count and page). By default count is 0 (10), it can be increased to issue less HTTP calls.

13.1.4 Example: list packages in dropbox

```
ascli faspex package list --box=inbox --recipient='*my_dropbox' --query=@json:'{"max":20,"pmax":2,"count":20}
```

List a maximum of 20 items grouped by pages of 20, with maximum 2 pages in received box (inbox) when received in dropbox *my_dropbox.

13.2 Receiving a Package

The command is package recv, possible methods are:

- provide a package id with option id
- provide a public link with option link
- provide a faspe: URI with option link

```
ascli faspex package recv 12345 ascli faspex package recv --link=faspe://...
```

If the package is in a specific **dropbox/workgroup**, add option recipient for both the list and recv commands.

```
ascli faspex package list --recipient='*dropbox_name'
ascli faspex package recv 125 --recipient='*dropbox_name'
```

if id is set to ALL, then all packages are downloaded, and if option once_only is used, then a persistency file is created to keep track of already downloaded packages.

13.3 Sending a Package

The command is faspex package send. Package information (title, note, metadata, options) is provided in option delivery_info. The contents of delivery_info is directly the contents of the send v3 API of Faspex 4, consult it for extended supported parameters.

Example:

```
ascli faspex package send --delivery-info=@json:'{"title":"my title","recipients":["laurent.martin.aspera@fr.
```

If the recipient is a dropbox or workgroup: provide the name of the dropbox or workgroup preceded with * in the recipients field of the delivery_info option: "recipients":["*MyDropboxName"]

Additional optional parameters in delivery_info:

- Package Note: : "note": "note this and that"
- Package Metadata: "metadata":{"Meta1":"Val1", "Meta2":"Val2"}

13.4 Email notification on transfer

Like for any transfer, a notification can be sent by email using parameters: notif_to and notif_template.

Example:

```
ascli faspex package send --delivery-info=@json:'{"title":"test pkg 1", "recipients":["aspera.user1@gmail.com"
```

In this example the notification template is directly provided on command line. Package information placed in the message are directly taken from the tags in transfer spec. The template can be placed in a file using modifier: <code>@file:</code>

13.5 Operation on dropboxes

Example:

```
ascli faspex v4 dropbox create @json:'{"dropbox":{"e_wg_name":"test1","e_wg_desc":"test1"}}' ascli faspex v4 dropbox list ascli faspex v4 dropbox delete 36
```

13.6 Remote sources

Faspex lacks an API to list the contents of a remote source (available in web UI). To workaround this, the node API is used, for this it is required to add a section ":storage" that links a storage name to a node config and sub path.

Example:

```
my_faspex_conf:
    url: https://10.25.0.3/aspera/faspex
    username: admin
    password: MyUserPassword
    storage:
        my_storage:
        node: "@preset:my_faspex_node"
        path: /mydir
my_faspex_node:
    url: https://10.25.0.3:9092
    username: node_faspex
    password: MyNodePassword
```

In this example, a faspex storage named my_storage exists in Faspex, and is located under the docroot in /mydir (this must be the same as configured in Faspex). The node configuration name is "my faspex node" here.

Note: the v4 API provides an API for nodes and shares.

13.7 Automated package download (cargo)

It is possible to tell ascli to download newly received packages, much like the official cargo client, or drive. Refer to the same section in the Aspera on Cloud plugin:

```
ascli faspex packages recv ALL --once-only=yes --lock-port=12345
```

13.8 Faspex 4 sample commands

```
faspex address_book
faspex dropbox list --recipient="*my_faspex_dbx"
faspex dropbox list --recipient="*my_faspex_wkg"
faspex health
faspex login_methods
faspex me
faspex package list
faspex package list --box=sent --fields=package_id --format=csv --display=data --query=@json:'{"max":1}'
faspex package list --fields=package_id --format=csv --display=data --query=@json:'{"max":1}'
faspex package list --recipient="*my_faspex_dbx" --format=csv --fields=package_id --query=@json:'{"max":1}'
faspex package list --recipient="*my_faspex_wkg" --format=csv --fields=package_id --query=@json:'{"max":1}'
faspex package recv "my_package_id" --to-folder=.
faspex package recv "my_package_id" --to-folder=. --box=sent
faspex package recv --to-folder=. --link=https://app.example.com/recv_from_user_path
faspex package recv ALL --to-folder=. --once-only=yes
faspex package recv my_pkgid --recipient="*my_faspex_dbx" --to-folder=.
faspex package recv my_pkgid --recipient="*my_faspex_wkg" --to-folder=.
faspex package send --delivery-info=@json:'{"title":"Important files delivery", "recipients": ["*my_faspex_dbx"
faspex package send --delivery-info=@json:'{"title":"Important files delivery", "recipients": ["*my_faspex_wkg"
faspex package send --delivery-info=@json:'{"title":"Important files delivery", "recipients": ["my_email_intern
faspex package send --link=https://app.example.com/send_to_dropbox_path --delivery-info=@json:'{"title":"Impo
faspex package send --link=https://app.example.com/send_to_user_path --delivery-info=@json:'{"title":"Importa
faspex source list
faspex source name my_faspex_src info
faspex source name my_faspex_src node br /
faspex v4 dmembership list
faspex v4 dropbox list
faspex v4 metadata_profile list
faspex v4 user list
faspex v4 wmembership list
faspex v4 workgroup list
```

Plugin: shares: IBM Aspera Shares v1

Aspera Shares supports the "node API" for the file transfer part.

14.1 Shares 1 sample commands

```
shares admin group list
shares admin node list
shares admin share list --fields=-status, status_message
shares admin share user_permissions 1 list
shares admin user add --type=ldap the_name
shares admin user app_authorizations 1 modify @json:'{"app_login":true}'
shares admin user app_authorizations 1 show
shares admin user import --type=saml @json:'{"id":"the_id", "name_id":"the_name"}'
shares admin user list
shares admin user share_permissions 1 list
shares admin user share_permissions 1 show 1
shares files browse /
shares files delete my_shares_upload/testfile.bin
shares files download --to-folder=. my_shares_upload/testfile.bin
shares files download --to-folder=. my_shares_upload/testfile.bin --transfer=httpgw --transfer-info=@json:'{"
shares files upload --to-folder=my_shares_upload testfile.bin
shares files upload --to-folder=my_shares_upload testfile.bin --transfer=httpgw --transfer-info=@json:'{"url"
shares health
```

Plugin: console: IBM Aspera Console

15.1 Console sample commands

```
console health
console transfer current list
console transfer smart list
console transfer smart sub my_job_id @json:'{"source":{"paths":["my_file_name"]},"source_type":"user_selected
```

Plugin: orchestrator: IBM Aspera Orchestrator

16.1 Orchestrator sample commands

```
orchestrator info
orchestrator plugins
orchestrator processes
orchestrator workflow details my_orch_workflow_id
orchestrator workflow export my_orch_workflow_id
orchestrator workflow inputs my_orch_workflow_id
orchestrator workflow list
orchestrator workflow start my_orch_workflow_id --params=@json:'{"Param":"world !"}'
orchestrator workflow start my_orch_workflow_id --params=@json:'{"Param":"world !"}'
orchestrator workflow start my_orch_workflow_id --params=@json:'{"Param":"world !"}' --result=ResultStep:Comporchestrator workflow status ALL
orchestrator workflow status my_orch_workflow_id
```

Plugin: cos: IBM Cloud Object Storage

The IBM Cloud Object Storage provides the possibility to execute transfers using FASP. It uses the same transfer service as Aspera on Cloud, called Aspera Transfer Service (ATS). Available ATS regions: https://status.aspera.io

There are two possibilities to provide credentials. If you already have the endpoint, apikey and CRN, use the first method. If you don't have credentials but have access to the IBM Cloud console, then use the second method.

17.1 Using endpoint, apikey and Resource Instance ID (CRN)

If you have those parameters already, then following options shall be provided:

- bucket bucket name
- endpoint storage endpoint url, e.g. https://s3.hkg02.cloud-object-storage.appdomain.cloud
- apikey API Key
- · crn resource instance id

For example, let us create a default configuration:

```
ascli conf preset update mycos --bucket=mybucket --endpoint=https://s3.us-east.cloud-object-storage.appdomain ascli conf preset set default cos mycos
```

Then, jump to the transfer example.

17.2 Using service credential file

If you are the COS administrator and don't have yet the credential: Service credentials are directly created using the IBM cloud Console (web UI). Navigate to:

- → Navigation Menu
- → Resource List
- → Storage
- → Select your storage instance
- → Service Credentials
- → New credentials (Leave default role: Writer, no special options)
- → Copy to clipboard

Then save the copied value to a file, e.g.: \$HOME/cos_service_creds.json

or using the IBM Cloud CLI:

```
ibmcloud resource service-keys ibmcloud resource service-key _service_key_name_here_ --output JSON|jq '.[0].credentials'>$HOME/service_creds (if you don't have jq installed, extract the structure as follows)
```

It consists in the following structure:

```
{
   "apikey": "my_api_key_here",
   "cos_hmac_keys": {
      "access_key_id": "my_access_key_here",
      "secret_access_key": "my_secret_here"
},
   "endpoints": "https://control.cloud-object-storage.cloud.ibm.com/v2/endpoints",
   "iam_apikey_description": "my_description_here",
   "iam_apikey_name": "my_key_name_here",
   "iam_role_crn": "crn:v1:bluemix:public:iam::::serviceRole:Writer",
   "iam_serviceid_crn": "crn:v1:bluemix:public:iam-identity::a/xxxxxxxx....",
   "resource_instance_id": "crn:v1:bluemix:public:cloud-object-storage:global:a/xxxxxxx...."
}
```

The field resource_instance_id is for option crn

The field apikey is for option apikey

(If needed: endpoints for regions can be found by querying the endpoints URL.)

The required options for this method are:

- bucket bucket name
- region bucket region, e.g. eu-de
- service_credentials see below

For example, let us create a default configuration:

```
ascli conf preset update mycos --bucket=laurent --service-credentials=@val:@json:@file:~/service_creds.json ascli conf preset set default cos mycos
```

17.3 Operations, transfers

Let's assume you created a default configuration from once of the two previous steps (else specify the access options on command lines).

A subset of node plugin operations are supported, basically node API:

```
ascli cos node info
ascli cos node upload 'faux:///sample1G?1g'
```

Note: we generate a dummy file sample1G of size 2GB using the faux PVCL (man ascp and section above), but you can of course send a real file by specifying a real file instead.

17.4 COS sample commands

```
cos --bucket=my_icos_bucket_name --endpoint=my_icos_bucket_endpoint --apikey=my_icos_bucket_apikey --crn=my_icos_bucket=my_icos_bucket_name --region=my_icos_bucket_region --service-credentials=@json:@file:service_credentials=@json:@file:service_credentials=@json:@file:service_credentials=cos node access_key show self cos node download testfile.bin --to-folder=.

cos node info cos node upload testfile.bin
```

Plugin: async: IBM Aspera Sync

A basic plugin to start an async using ascli. The main advantage over bare async command line is the possibility to use a configuration file, using standard options of ascli.

The sync command is also made available through the server sync, acc files sync and node sync commands. In this case, some of the sync parameters are filled by the related plugin using transfer spec parameters (including token).

Note: All sync commands require an async enabled license and availability of the async executable (and asyncadmin).

Two JSON syntax are supported for option sync_info.

18.1 async native JSON

It is the same payload as specified on the async option --conf or in the latest node API. This is the preferred syntax and allows a single session definition. But there is no progress output nor error messages.

Documentation on Async node API can be found on IBM Developer Portal.

18.2 async options as JSON

This is specific to ascli. It is based on a JSON representation of async command line options. It allows definition of multiple sync sessions in a single command, although usually only one sync session is defined.

18.3 Sync sample commands

```
sync admin status --sync-info=@json:'{"sessions":[{"name":"test","local_dir":"contents"}]}'
sync start --sync-info=@json:'{"instance":{"quiet":true},"sessions":[{"name":"test","reset":true,"remote_dir"
```

Plugin: preview: Preview generator for AoC

The preview generates thumbnails (office, images, video) and video previews on storage for use primarily in the Aspera on Cloud application. It uses the **node API** of Aspera HSTS and requires use of Access Keys and it's **storage root**. Several parameters can be used to tune several aspects:

- · Methods for detection of new files needing generation
- · Methods for generation of video preview
- · Parameters for video handling

19.1 Aspera Server configuration

Specify the previews folder as shown in:

https://ibmaspera.com/help/admin/organization/installing the preview maker

By default, the preview plugin expects previews to be generated in a folder named previews located in the storage root. On the transfer server execute:

```
PATH=/opt/aspera/bin:$PATH
asconfigurator -x "server;preview_dir,previews"
asnodeadmin --reload
```

Note: the configuration <code>preview_dir</code> is *relative* to the storage root, no need leading or trailing /. In general just set the value to <code>previews</code>

If another folder is configured on the HSTS, then specify it to ascli using the option previews folder.

The HSTS node API limits any preview file to a parameter: max_request_file_create_size_kb (1 KB is 1024 bytes). This size is internally capped to 1<<24 Bytes (16777216), i.e. 16384 KBytes.

To change this parameter in aspera.conf, use asconfigurator. To display the value, use asuserdata:

```
asuserdata -a | grep max_request_file_create_size_kb

max_request_file_create_size_kb: "1024"

asconfigurator -x "server; max_request_file_create_size_kb,16384"
```

If you use a value different than 16777216, then specify it using option max_size.

Note: the HSTS parameter (max_request_file_create_size_kb) is in *kiloBytes* while the generator parameter is in *Bytes* (factor of 1024).

19.2 External tools: Linux

The tool requires the following external tools available in the PATH:

• ImageMagick: convert composite

• OptiPNG: optipng

FFmpeg: ffmpeg ffprobeLibreoffice: libreoffice

Here shown on Redhat/CentOS.

Other OSes should work as well, but are note tested.

To check if all tools are found properly, execute:

ascli preview check

19.2.1 Image: ImageMagick and optipng

```
dnf install -y ImageMagick optipng
```

You may also install <code>ghostscript</code> which adds fonts to ImageMagick. Available fonts, used to generate png for text, can be listed with <code>magick identify -list font</code>. Prefer ImageMagick version >=7.

19.2.2 Video: FFmpeg

The easiest method is to download and install the latest released version of ffmpeg with static libraries from https://johnvansickle.com/ffmpeg/

curl -s https://johnvansickle.com/ffmpeg/releases/ffmpeg-release-amd64-static.tar.xz|(mkdir -p /opt && cd /op

19.2.3 Office: Unoconv and Libreoffice

If you don't want to have preview for office documents or if it is too complex you can skip office document preview generation by using option: --skip-types=office

The generation of preview in based on the use of unoconv and libreoffice

CentOS 8

dnf install unoconv

Amazon Linux

```
amazon-linux-extras enable libreoffice
yum clean metadata
yum install libreoffice-core libreoffice-calc libreoffice-opensymbol-fonts libreoffice-ure libreoffice-writer
wget https://raw.githubusercontent.com/unoconv/unoconv/master/unoconv
mv unoconv /usr/bin
chmod a+x /usr/bin/unoconv
```

19.3 Configuration

The preview generator should be executed as a non-user. When using object storage, any user can be used, but when using local storage it is usually better to use the user xfer, as uploaded files are under this identity: this ensures proper access rights. (we will assume this)

Like any ascli commands, parameters can be passed on command line or using a configuration option preset. The configuration file must be created with the same user used to run so that it is properly used on runtime.

The xfer user has a special protected shell: aspshell, so in order to update the configuration, and when changing identity, specify an alternate shell. E.g.:

```
su -s /bin/bash - xfer
ascli config preset update mypreviewconf --url=https://localhost:9092 --username=my_access_key --password=my_
ascli config preset set default preview mypreviewconf
```

Here we assume that Office file generation is disabled, else remove this option. lock_port prevents concurrent execution of generation when using a scheduler.

One can check if the access key is well configured using:

```
ascli -Ppreviewconf node browse /
```

This shall list the contents of the storage root of the access key.

19.4 Options for generated files

When generating preview files, some options are provided by default. Some values for the options can be modified on command line. For video preview, the whole set of options can be overridden with option reencode_ffmpeg: it is a Hash with two keys: in and out, each is an array of strings with the native options to ffmpeg.

19.5 Execution

The tool intentionally supports only a **one shot** mode (no infinite loop) in order to avoid having a hanging process or using too many resources (calling REST api too quickly during the scan or event method). It needs to be run on a regular basis to create or update preview files. For that use your best reliable scheduler, see Scheduler.

Typically, for **Access key** access, the system/transfer is xfer. So, in order to be consistent have generate the appropriate access rights, the generation process should be run as user xfer.

Lets do a one shot test, using the configuration previously created:

```
su -s /bin/bash - xfer
ascli preview scan --overwrite=always
```

When the preview generator is first executed it will create a file: .aspera_access_key in the previews folder which contains the access key used. On subsequent run it reads this file and check that previews are generated for the same access key, else it fails. This is to prevent clash of different access keys using the same root.

19.6 Configuration for Execution in scheduler

Details are provided in section Scheduler.

Shorter commands can be specified if a configuration preset was created as shown previously.

For example the timeout value can be differentiated depending on the option: event versus scan:

```
case "$*" in *trev*) tmout=10m ;; *) tmout=30m ;; esac
```

19.7 Candidate detection for creation or update (or deletion)

The tool generates preview files using those commands:

- trevents: only recently uploaded files will be tested (transfer events)
- events: only recently uploaded files will be tested (file events: not working)
- scan: recursively scan all files under the access key's "storage root"
- test: test using a local file

Once candidate are selected, once candidates are selected, a preview is always generated if it does not exist already, else if a preview already exist, it will be generated using one of three values for the overwrite option:

- always: preview is always generated, even if it already exists and is newer than original
- never: preview is generated only if it does not exist already
- mtime: preview is generated only if the original file is newer than the existing

Deletion of preview for deleted source files: not implemented yet (TODO).

If the scan or events detection method is used, then the option: skip_folders can be used to skip some folders. It expects a list of path relative to the storage root (docroot) starting with slash, use the @json: notation, example:

```
ascli preview scan --skip-folders=@json:'["/not_here"]'
```

The option folder_reset_cache forces the node service to refresh folder contents using various methods.

When scanning the option query has the same behavior as for the node find command.

For instance to filter out files beginning with . _ do:

```
--query='exec:!f["name"].start_with?("._") or f["name"].eql?(".DS_Store")'
```

19.8 Preview File types

Two types of preview can be generated:

- png: thumbnail
- mp4: video preview (only for video)

Use option skip_format to skip generation of a format.

19.9 Supported input Files types

The preview generator supports rendering of those file categories:

- image
- pdf
- plaintext
- · office
- · video

To avoid generation for some categories, specify a list using option skip_types.

Each category has a specific rendering method to produce the png thumbnail.

The mp4 video preview file is only for category video

File type is primarily based on file extension detected by the node API and translated info a mime type returned by the node API.

19.10 mimemagic

By default, the Mime type used for conversion is the one returned by the node API, based on file name extension.

It is also possible to detect the mime type using option mimemagic. To use it, set option mimemagic to yes: --mimemagic=yes.

This requires to manually install the mimemagic gem: gem install mimemagic.

In this case the preview command will first analyze the file content using mimemagic, and if no match, will try by extension.

If the mimemagic gem complains about missing mime info file:

- any OS:
 - Examine the error message
 - Download the file: freedesktop.org.xml.in
 - move and rename this file to one of the locations expected by mimemagic as specified in the error message
- · Windows:
 - Download the file: freedesktop.org.xml.in
 - Place this file in the root of Ruby (or elsewhere): C:\RubyVV-x64\freedesktop.org.xml.in

- Set a global variable using SystemPropertiesAdvanced.exe or using cmd (replace VV with version) to the exact path of this file:

```
SETX FREEDESKTOP MIME TYPES PATH C:\RubyVV-x64\freedesktop.org.xml.in
```

- Close the cmd and restart a new one if needed to get refreshed env vars
- Linux RHEL 8+:

```
dnf install shared-mime-info
     macOS:
```

brew install shared-mime-info

19.11 Generation: Read source files and write preview

Standard open source tools are used to create thumbnails and video previews. Those tools require that original files are accessible in the local file system and also write generated files on the local file system. The tool provides 2 ways to read and write files with the option: file_access

If the preview generator is run on a system that has direct access to the file system, then the value local can be used. In this case, no transfer happen, source files are directly read from the storage, and preview files are directly written to the storage.

If the preview generator does not have access to files on the file system (it is remote, no mount, or is an object storage), then the original file is first downloaded, then the result is uploaded, use method remote.

19.12 Preview sample commands

```
preview check --skip-types=office

preview scan --scan-id=1 --skip-types=office --log-level=info --file-access=remote --ts=@json:'{"target_rate_
preview scan --skip-types=office --log-level=info

preview test --case=test mp4 my_file_mxf --video-conversion=blend --log-level=debug

preview test --case=test mp4 my_file_mxf --video-conversion=reencode --log-level=debug

preview test --case=test mp4 my_file_mxf --video-conversion=reencode --log-level=debug

preview test --case=test png my_file_dcm --log-level=debug

preview test --case=test png my_file_mxf --video-png-conv=animated --log-level=debug

preview test --case=test png my_file_mxf --video-png-conv=fixed --log-level=debug

preview test --case=test png my_file_mxf --video-png-conv=fixed --log-level=debug

preview test --case=test png my_file_pdf --log-level=debug

preview trevents --once-only=yes --skip-types=office --log-level=info
```

SMTP for email notifications

ascli can send email, for that setup SMTP configuration. This is done with option smtp.

The smtp option is a hash table (extended value) with the following fields:

field	default	example	description
server	-	smtp.gmail.com	SMTP server address
tls	true	true	enable STARTTLS (port 587)
ssl	false	false	enable TLS (port 465)
port	587 or 465 or 25	587	port for service
domain	domain of server	gmail.com	email domain of user
username	-	john@example.com	user to authenticate on SMTP server, leave empty for open auth.
password	-	my password here	password for above username
from_email	username if defined	johnny@example.com	address used if receiver replies
from_name	same as email	John Wayne	display name of sender

20.1 Example of configuration

```
ascli config preset set smtp_google server smtp.google.com
ascli config preset set smtp_google username john@gmail.com
ascli config preset set smtp_google password my_password_here

or
ascli config preset init smtp_google @json:'{"server":"smtp.google.com","username":"john@gmail.com","password
or
ascli config preset update smtp_google --server=smtp.google.com --username=john@gmail.com --password=my_passw
Set this configuration as global default, for instance:
ascli config preset set cli_default smtp @val:@preset:smtp_google
ascli config preset set default config cli_default
```

20.2 Email templates

Sent emails are built using a template that uses the ERB syntax.

The template is the full SMTP message, including headers.

The following variables are defined by default:

- from_name
- from_email

Other variables are defined depending on context.

20.3 Test

Check settings with smtp_settings command. Send test email with email_test.

```
ascli config --smtp=@preset:smtp_google smtp
ascli config --smtp=@preset:smtp_google email --notif-to=sample.dest@example.com
```

20.4 Notifications for transfer status

An e-mail notification can be sent upon transfer success and failure (one email per transfer job, one job being possibly multi session, and possibly after retry).

To activate, use option notif_to.

A default e-mail template is used, but it can be overridden with option notif_template.

The environment provided contains the following additional variables:

- subject
- body
- global_transfer_status
- ts

Example of template:

```
From: <%=from_name%> <<%=from_email%>>
To: <<%=to%>>
Subject: <%=subject%>
Transfer is: <%=global_transfer_status%>
```

Tool: asession

This gem comes with a second executable tool providing a simplified standardized interface to start a FASP session: assession.

It aims at simplifying the startup of a FASP session from a programmatic stand point as formatting a transfer-spec is:

- common to Aspera Node API (HTTP POST /ops/transfer)
- common to Aspera Connect API (browser javascript startTransfer)
- · easy to generate by using any third party language specific JSON library

Hopefully, IBM integrates this directly in ascp, and this tool is made redundant.

This makes it easy to integrate with any language provided that one can spawn a sub process, write to its STDIN, read from STDOUT, generate and parse JSON.

The tool expect one single argument: a *transfer-spec*.

If no argument is provided, it assumes a value of: @json:@stdin:, i.e. a JSON formatted transfer-spec on stdin.

Note: If JSON is the format, specify @json: to tell ascli to decode the hash using JSON syntax.

During execution, it generates all low level events, one per line, in JSON format on stdout.

There are special "extended" transfer-spec parameters supported by assission:

- EX_loglevel to change log level of the tool
- EX_file_list_folder to set the folder used to store (exclusively, because of garbage collection) generated file lists. By default it is [system tmp folder]/[username]_asession_filelists

Note: In addition, many "EX_" *transfer-spec* parameters are supported for the direct transfer agent (used by assision), refer to section *transfer-spec*.

21.1 Comparison of interfaces

feature/tool	asession	ascp
language integration	any	any
required additional components to ascp	RubyAspera	-
startup	JSON on stdin(standard APIs:JSON.generateProcess.spawn)	command line argume
events	JSON on stdout	none by defaultor need
platforms	any with Ruby and ascp	any with ascp (and SD

21.2 Simple session

Create a file session. json with:

{"remote host": "demo.asperasoft.com", "remote user": "asperaweb", "ssh port": 33001, "remote password": "my passwor

```
asession < session.json
```

21.3 Asynchronous commands and Persistent session

asession also supports asynchronous commands (on the management port). Instead of the traditional text protocol as described in ascp manual, the format for commands is: one single line per command, formatted in JSON, where parameters shall be "snake" style, for example: LongParameter -> long_parameter

This is particularly useful for a persistent session (with the *transfer-spec* parameter: "keepalive":true)

```
asession
```

```
{"remote_host":"demo.asperasoft.com","ssh_port":33001,"remote_user":"asperaweb","remote_password":"my_password
{"type":"START","source":"/aspera-test-dir-tiny/200KB.2"}
{"type":"DONE"}
```

(events from FASP are not shown in above example. They would appear after each command)

21.4 Example of language wrapper

Nodejs: https://www.npmjs.com/package/aspera

21.5 Help

```
asession -h
USAGE
    asession
    asession -h|--help
    asession <transfer spec extended value>
    If no argument is provided, default will be used: @json:@stdin
    -h, --help display this message
    <transfer spec extended value> a JSON value for transfer_spec, using the prefix: @json:
    The value can be either:
       the JSON description itself, e.g. @json:'{"xx":"yy",...}'
       @json:@stdin, if the JSON is provided from stdin
       @json:@file:<path>, if the JSON is provided from a file
    Asynchronous commands can be provided on STDIN, examples:
       {"type": "START", "source": "/aspera-test-dir-tiny/200KB.2"}
       {"type": "START", "source": "xx", "destination": "yy"}
       {"type":"DONE"}
Note: debug information can be placed on STDERR, using the "EX_loglevel" parameter in transfer spec (debug=0)
EXAMPLES
    asession @json: '{"remote_host": "demo.asperasoft.com", "remote_user": "asperaweb", "ssh_port": 33001, "remote_p
    echo '{"remote_host":...}'|asession @json:@stdin
```

Hot folder

22.1 Requirements

ascli maybe used as a simple hot folder engine. A hot folder being defined as a tool that:

- · locally (or remotely) detects new files in a top folder
- send detected files to a remote (respectively, local) repository
- · only sends new files, do not re-send already sent files
- · optionally: sends only files that are not still "growing"
- · optionally: after transfer of files, deletes or moves to an archive

In addition: the detection should be made "continuously" or on specific time/date.

22.2 Setup procedure

The general idea is to rely on:

- · existing ascp features for detection and transfer
- take advantage of ascli configuration capabilities and server side knowledge
- the OS scheduler for reliability and continuous operation

22.2.1 ascp features

Interesting ascp features are found in its arguments: (see ascp manual):

- ascp already takes care of sending only new files: option -k 1,2,3 (resume_policy)
- ascp has some options to remove or move files after transfer: --remove-after-transfer, --move-after-transfer, --remove-empty-directories (remove after transfer, move after transfer, remove empty directories)
- ascp has an option to send only files not modified since the last X seconds: --exclude-newer-than, --exclude-older-than (exclude_newer_than, exclude_older_than)
- --src-base (src_base) if top level folder name shall not be created on destination

Note: ascli takes transfer parameters exclusively as a *transfer-spec*, with ts option.

Note: Most, but not all, native ascp arguments are available as standard transfer-spec parameters.

Note: Only for the <u>direct</u> transfer agent (not others, like connect or node), native <u>ascp</u> arguments can be provided with parameter <u>ascp_args</u> of option transfer_info.

22.2.2 server side and configuration

Virtually any transfer on a "repository" on a regular basis might emulate a hot folder.

Note: file detection is not based on events (inotify, etc...), but on a simple folder scan on source side.

Note: parameters may be saved in a option preset and used with -P.

22.2.3 Scheduling

Once ascli parameters are defined, run the command using the OS native scheduler, e.g. every minutes, or 5 minutes, etc... Refer to section Scheduler. (on use of option lock_port)

22.3 Example: upload hot folder

```
ascli server upload source_hot --to-folder=/Upload/target_hot --lock-port=12345 --ts=@json:'{"remove_after_tr
```

The local folder (here, relative path: <code>source_hot</code>) is sent (upload) to an aspera server. Source files are deleted after transfer. Growing files will be sent only once they don't grow anymore (based on an 8-second cool-off period). If a transfer takes more than the execution period, then the subsequent execution is skipped (<code>lock_port</code>) preventing multiple concurrent runs.

22.4 Example: unidirectional synchronization (upload) to server

```
ascli server upload source_sync --to-folder=/Upload/target_sync --lock-port=12345 --ts=@json:'{"resume_policy This can also be used with other folder-based applications: Aspera on Cloud, Shares, Node:
```

22.5 Example: unidirectional synchronization (download) from Aspera on Cloud Files

```
ascli aoc files download . --to-folder=. --lock-port=12345 --progress=none --display=data \
--ts=@json:'{"resume_policy":"sparse_csum","target_rate_kbps":50000,"exclude_newer_than":-8,"delete_before_tr
```

Note: option delete_before_transfer will delete files locally, if they are not present on remote side.

Note: options progress and display limit output for headless operation (e.g. cron job)

Health check and Nagios

Most plugin provide a health command that will check the health status of the application. Example:

ascli console health

+-		+-		+-		+
			component		0	1
•	ok	•	console api	•		
+		+-		+-		+

Typically, the health check uses the REST API of the application with the following exception: the server plugin allows checking health by:

- issuing a transfer to the server
- checking web app status with asctl all:status
- · checking daemons process status

ascli can be called by Nagios to check the health status of an Aspera server. The output can be made compatible to Nagios with option --format=nagios:

```
ascli server health transfer --to-folder=/Upload --format=nagios --progress=none

OK - [transfer:ok]

ascli server health asctl status --cmd_prefix='sudo ' --format=nagios

OK - [NP:running, MySQL:running, Mongrels:running, Background:running, DS:running, DB:running, Email:running,
```

Ruby Module: Aspera

Main components:

- Aspera generic classes for REST and OAuth
- Aspera::Fasp: starting and monitoring transfers. It can be considered as a FASPManager class for Ruby.
- Aspera::Cli: ascli.

Working examples can be found in repo: https://github.com/laurent-martin/aspera-api-examples in Ruby examples.

Changes (Release notes)

See CHANGELOG.md

History

When I joined Aspera, there was only one CLI: ascp, which is the implementation of the FASP protocol, but there was no CLI to access the various existing products (Server, Faspex, Shares). Once, Serban (founder) provided a shell script able to create a Faspex Package using Faspex REST API. Since all products relate to file transfers using FASP (ascp), I thought it would be interesting to have a unified CLI for transfers using FASP. Also, because there was already the ascp tool, I thought of an extended tool: eascp.pl which was accepting all ascp options for transfer but was also able to transfer to Faspex and Shares (destination was a kind of URI for the applications).

There were a few pitfalls:

- The tool was written in the aging perl language while most Aspera web application products (but the Transfer Server) are written in ruby.
- The tool was only for transfers, but not able to call other products APIs

So, it evolved into ascli:

- portable: works on platforms supporting ruby (and ascp)
- · easy to install with the gem utility
- supports transfers with multiple Transfer Agents, that's why transfer parameters moved from ascp command line to *transfer-spec* (more reliable, more standard)
- ruby is consistent with other Aspera products

Over the time, a supported command line tool aspera was developed in C++, it was later on deprecated. It had the advantage of being relatively easy to installed, as a single executable (well, still using ascp), but it was too limited IMHO, and lacked a lot of the features of this CLI.

Enjoy a coffee on me:

```
ascli conf coffee
ascli conf coffee --ui=text
```

Common problems

27.1 Error: "Remote host is not who we expected"

Cause: ascp >= 4.x checks fingerprint of highest server host key, including ECDSA. ascp < 4.0 (3.9.6 and earlier) support only to RSA level (and ignore ECDSA presented by server). aspera.conf supports a single fingerprint.

Workaround on client side: To ignore the certificate (SSH fingerprint) add option on client side (this option can also be added permanently to the config file):

```
--ts=@json:'{"sshfp":null}'
```

Workaround on server side: Either remove the fingerprint from aspera.conf, or keep only RSA host keys in sshd_config.

References: ES-1944 in release notes of 4.1 and to HSTS admin manual section "Configuring Transfer Server Authentication With a Host-Key Fingerprint".

27.2 Error "can't find header files for ruby"

Some Ruby gems dependencies require compilation of native parts (C). This also requires Ruby header files. If Ruby was installed as a Linux Packages, then also install Ruby development package: ruby-dev ir ruby-devel, depending on distribution.

27.3 ED255519 key not supported

ED25519 keys are deactivated since version 0.9.24 so this type of key will just be ignored.

Without this deactivation, if such key was present the following error was generated:

OpenSSH keys only supported if ED25519 is available

Which meant that you do not have Ruby support for ED25519 SSH keys. You may either install the suggested Gems, or remove your ed25519 key from your .ssh folder to solve the issue.