**Note:** This tutorial assumes that you have completed the previous tutorials: Understanding ROS services and parameters (/ROS/Tutorials/UnderstandingServicesParams).

Flease ask about problems and questions regarding this tutorial on ● answers.ros.org (http://answers.ros.org). Don't forget to include in your question the link to this page, the versions of your OS & ROS, and also add appropriate tags.

# Using rqt\_console and roslaunch

**Description:** This tutorial introduces ROS using rqt\_console (/rqt\_console) and rqt\_logger\_level (/rqt\_logger\_level) for debugging and roslaunch (/roslaunch) for starting many nodes at once. If you use ROS\_fuerte or ealier distros where rqt (/rqt) isn't fully available, please see this page with this page (/ROS/Tutorials/UsingRxconsoleRoslaunch) that uses old rx based tools.

Tutorial Level: BEGINNER

Next Tutorial: Using rosed (/ROS/Tutorials/UsingRosEd)

#### Contents

- 1. Prerequisites rgt and turtlesim package
- 2. Using rqt\_console and rqt\_logger\_level
  - 1. Quick Note about logger levels
  - 2. Using roslaunch
  - 3. The Launch File
  - 4. The Launch File Explained
  - 5. roslaunching

## 1. Prerequisites rqt and turtlesim package

The tutorial uses both the rgt and turtlesim packages. To do this tutorial, please install both packages, if you have not yet done so.

```
$ sudo apt-get install ros-<distro>-rqt ros-<distro>-rqt-common-plugins ros-<distro>-turtlesim
```

Replace <distro> with the name of your ROS distribution (e.g. indigo, jade, kinetic).

**NOTE**: you may have already built rqt and turtlesim for one of the previous tutorials. If you are not sure, installing them again will not hurt anything.

# 2. Using rqt\_console and rqt\_logger\_level


rqt\_console attaches to ROS's logging framework to display output from nodes. rqt\_logger\_level allows us to change the verbosity level (DEBUG, WARN, INFO, and ERROR) of nodes as they run.


Now let's look at the turtlesim output in rqt\_console and switch logger levels in rqt\_logger\_level as we use turtlesim. Before we start the turtlesim, **in two new terminals** start rqt\_console and rqt\_logger\_level:

```
$ rosrun rqt_console rqt_console
```

```
$ rosrun rqt_logger_level rqt_logger_level
```

You will see two windows popup:







Now let's start turtlesim in a **new terminal**:

```
$ rosrun turtlesim_node
```

Since the default logger level is INFO you will see any info that the turtlesim publishes when it starts up, which should look like:



Now let's change the logger level to Warn by refreshing the nodes in the rqt\_logger\_level window and selecting Warn as shown below:




Now let's run our turtle into the wall and see what is displayed in our rqt\_console:

#### For ROS Hydro and later,

```
rostopic pub /turtle1/cmd_vel geometry_msgs/Twist -r 1 -- '{linear: {x: 2.0, y: 0.0, z: 0.0}, angular: {x: 0.0,y: 0.0,z: 0.0}}'
```

#### For ROS Groovy and earlier,

```
rostopic pub /turtle1/command_velocity turtlesim/Velocity -r 1 -- 2.0 0.0
```



## 2.1 Quick Note about logger levels

Logging levels are prioritized in the following order:

```
Fatal
Error
Warn
Info
Debug
```

Fatal has the highest priority and Debug has the lowest. By setting the logger level, you will get all messages of that priority level or higher. For example, by setting the level to Warn, you will get all Warn, Error, and Fatal logging messages.

Let's Ctrl-C our turtlesim and let's use roslaunch to bring up multiple turtlesim nodes and a mimicking node to cause one turtlesim to mimic another:

### 2.2 Using roslaunch

roslaunch starts nodes as defined in a launch file.

Usage:

```
$ roslaunch [package] [filename.launch]
```

First go to the beginner\_tutorials package we created (/ROS/Tutorials/CreatingPackage) and built (/ROS/Tutorials/BuildingPackages) earlier:

```
$ roscd beginner_tutorials
```

If roscd says similar to roscd: No such package/stack 'beginner\_tutorials', you will need to source the environment setup file like you did at the end of the create a workspace (/catkin/Tutorials/create a workspace) tutorial:

```
$ cd ~/catkin_ws
$ source devel/setup.bash
$ roscd beginner_tutorials
```

Then let's make a launch directory:

```
$ mkdir launch
$ cd launch
```

NOTE: The directory to store launch files don't necessarily have to be named as launch. In fact you don't even need to store them in a directory. roslaunch command automatically looks into the passed package and detect available launch files. However, it turned out to be a good practice.

#### 2.3 The Launch File

Now let's create a launch file called turtlemimic.launch and paste the following:

```
Toggle line numbers
   1 <launch>
       <group ns="turtlesim1">
       <node pkg="turtlesim" name="sim" type="turtlesim node"/>
       </group>
       <group ns="turtlesim2">
        <node pkg="turtlesim" name="sim" type="turtlesim node"/>
       </aroup>
   9
 10
       <node pkg="turtlesim" name="mimic" type="mimic">
 11
        <remap from="input" to="turtlesim1/turtle1"/>
 12
 13
       <remap from="output" to="turtlesim2/turtle1"/>
       </node>
 14
 15
 16 </launch>
```

## 2.4 The Launch File Explained

Now, let's break the launch xml down.

# Toggle line numbers 1 <launch>

Here we start the launch file with the launch tag, so that the file is identified as a launch file.

Here we start two groups with a namespace tag of turtlesim1 and turtlesim2 with a turtlesim node with a name of sim. This allows us to start two simulators without having name conflicts.

Here we start the mimic node with the topics input and output renamed to turtlesim1 and turtlesim2. This renaming will cause turtlesim2 to mimic turtlesim1.

```
Toggle line numbers

16 </launch>
```

This closes the xml tag for the launch file.

## 2.5 roslaunching

Now let's roslaunch the launch file:

```
$ roslaunch beginner_tutorials turtlemimic.launch
```

Two turtlesims will start and in a **new terminal** send the rostopic command:

For ROS Hydro and later,

```
$ rostopic pub /turtlesim1/turtle1/cmd_vel geometry_msgs/Twist -r 1 -- '[2.0, 0.0, 0.0]' '[0.0, 0.0, -1.
8]'
```

For ROS Groovy and earlier,

```
$ rostopic pub /turtlesim1/turtle1/command_velocity turtlesim/Velocity -r 1 -- 2.0 -1.8
```

You will see the two turtlesims start moving even though the publish command is only being sent to turtlesim1.




We can also use rqt\_graph (/rqt\_graph) to better understand what our launch file did. Run rqt (/rqt)'s main window and select rqt\_graph (/rqt\_graph):

\$ rqt

Or simply:

\$ rqt\_graph



Now that you have successfully used rqt\_console and roslaunch, let's learn about editor options for ROS (/ROS/Tutorials/UsingRosEd). You can Ctrl-C all your turtlesims, as you will not need them for the next tutorials.

Except where otherwise noted, the ROS wiki is licensed under the Creative Commons Attribution 3.0 (http://creativecommons.org/licenses/by/3.0/) | Find us on Google+ (https://plus.google.com/113789706402978299308)

Wiki: ROS/Tutorials/UsingRqtconsoleRoslaunch (last edited 2016-09-27 13:34:26 by yoyekw (/yoyekw))

Brought to you by: Open Source Robotics Foundation

(http://www.osrfoundation.org)