Note: This tutorial assumes that you have completed the previous tutorials: creating a ROS msg and srv (/ROS/Tutorials/CreatingMsgAndSrv).

Figure 1. Please ask about problems and questions regarding this tutorial on ● answers.ros.org (http://answers.ros.org). Don't forget to include in your question the link to this page, the versions of your OS & ROS, and also add appropriate tags.

Writing a Simple Publisher and Subscriber (Python)

Description: This tutorial covers how to write a publisher and subscriber node in python.

Tutorial Level: BEGINNER

Next Tutorial: Examining the simple publisher and subscriber (/ROS/Tutorials/ExaminingPublisherSubscriber)

catkin rosbuild

Contents

- 1. Writing the Publisher Node
 - 1. The Code
 - 2. The Code Explained
- 2. Writing the Subscriber Node
 - 1. The Code
 - 2. The Code Explained
- 3. Building your nodes
 - 1. Additional Resources
 - 1. Video Tutorial

1. Writing the Publisher Node

"Node" is the ROS term for an executable that is connected to the ROS network. Here we'll create the publisher ("talker") node which will continually broadcast a message.

Change directory into the beginner_tutorials package, you created in the earlier tutorial, creating a package (/ROS/Tutorials/CreatingPackage):

```
$ roscd beginner_tutorials
```

1.1 The Code

First lets create a 'scripts' folder to store our Python scripts in:

```
$ mkdir scripts
$ cd scripts
```

Then download the example script • talker.py (https://raw.github.com/ros/ros_tutorials/kinetic-devel/rospy_tutorials/001_talker_listener/talker.py) to your new scripts directory and make it executable:

```
$ wget https://raw.github.com/ros/ros_tutorials/kinetic-devel/rospy_tutorials/001_talker_listener/talker.py
$ chmod +x talker.py
```

You can view and edit the file with \$ rosed beginner_tutorials talker.py or just look below.

```
1 #!/usr/bin/env python
 2 # license removed for brevity
 3 import rospy
 4 from std msgs.msg import String
 6 def talker():
      pub = rospy.Publisher('chatter', String, queue size=10)
      rospy.init node('talker', anonymous=True)
      rate = rospy.Rate(10) # 10hz
      while not rospy.is shutdown():
10
           hello str = "hello world %s" % rospy.get time()
11
          rospy.loginfo(hello str)
12
13
          pub.publish(hello str)
        rate.sleep()
14
15
16 if name == ' main ':
17
       try:
18
           talker()
      except rospy.ROSInterruptException:
19
20
           pass
```

1.2 The Code Explained

Now, let's break the code down.

```
Toggle line numbers

1 #!/usr/bin/env python
```

Every Python ROS Node (/Nodes) will have this declaration at the top. The first line makes sure your script is executed as a Python script.

```
3 import rospy
4 from std_msgs.msg import String
```

You need to import rospy if you are writing a ROS Node (/Nodes). The std_msgs.msg import is so that we can reuse the std_msgs/String message type (a simple string container) for publishing.

```
Toggle line numbers

7    pub = rospy.Publisher('chatter', String, queue_size=10)

8    rospy.init_node('talker', anonymous=True)
```

This section of code defines the talker's interface to the rest of ROS. pub = rospy.Publisher("chatter", String, queue_size=10) declares that your node is publishing to the chatter topic using the message type String. String here is actually the class std_msgs.msg.String. The queue_size argument is **New in ROS hydro** and limits the amount of queued messages if any subscriber is not receiving the them fast enough. In older ROS distributions just omit the argument.

The next line, rospy.init_node(NAME), is very important as it tells rospy the name of your node -- until rospy has this information, it cannot start communicating with the ROS Master (/Master). In this case, your node will take on the name talker. NOTE: the name must be a base name (/Names), i.e. it cannot contain any slashes "/".

```
Toggle line numbers

9 rate = rospy.Rate(10) # 10hz
```

This line creates a Rate object rate. With the help of its method sleep(), it offers a convenient way for looping at the desired rate. With its argument of 10, we should expect to go through the loop 10 times per second (as long as our processing time does not exceed 1/10th of a second!)

```
while not rospy.is_shutdown():
    hello_str = "hello world %s" % rospy.get_time()
    rospy.loginfo(hello_str)
    pub.publish(hello_str)
    rate.sleep()
```

This loop is a fairly standard rospy construct: checking the rospy.is_shutdown() flag and then doing work. You have to check is_shutdown() to check if your program should exit (e.g. if there is a Ctrl-C or otherwise). In this case, the "work" is a call to pub.publish(hello_str) that publishes a string to our chatter topic. The loop calls r.sleep(), which sleeps just long enough to maintain the desired rate through the loop.

(You may also run across rospy.sleep() which is similar to time.sleep() except that it works with simulated time as well (see Clock (/Clock)).)

This loop also calls rospy.loginfo(str), which performs triple-duty: the messages get printed to screen, it gets written to the Node's log file, and it gets written to rosout (/rosout). rosout (/rosout) is a handy for debugging: you can pull up messages using rqt_console (/rqt_console) instead of having to find the console window with your Node's output.

std_msgs.msg.String is a very simple message type, so you may be wondering what it looks like to publish more complicated types. The general rule of thumb is that *constructor args are in the same order as in the .msg file*. You can also pass in no arguments and initialize the fields directly, e.g.

```
msg = String()
msg.data = str
```

or you can initialize some of the fields and leave the rest with default values:

```
String(data=str)
```

You may be wondering about the last little bit:

```
17 try:
18 talker()
19 except rospy.ROSInterruptException:
20 pass
```

In addition to the standard Python __main__ check, this catches a rospy.ROSInterruptException exception, which can be thrown by rospy.sleep() and rospy.Rate.sleep() methods when Ctrl-C is pressed or your Node is otherwise shutdown. The reason this exception is raised is so that you don't accidentally continue executing code after the sleep().

Now we need to write a node to receive the messages.

2. Writing the Subscriber Node

2.1 The Code

Download the listener.py (https://raw.github.com/ros/ros_tutorials/kinetic-devel/rospy_tutorials/001_talker_listener.py) file into your scripts directory:

```
$ roscd beginner_tutorials/scripts/
$ wget https://raw.github.com/ros/ros_tutorials/kinetic-devel/rospy_tutorials/001_talker_listener/listener.py
```

The file contents look close to:

```
1 #!/usr/bin/env python
 2 import rospy
 3 from std msgs.msg import String
 5 def callback(data):
       rospy.loginfo(rospy.get caller id() + "I heard %s", data.data)
 8 def listener():
10
       # In ROS, nodes are uniquely named. If two nodes with the same
11
       # node are launched, the previous one is kicked off. The
12
       # anonymous=True flag means that rospy will choose a unique
1.3
       # name for our 'listener' node so that multiple listeners can
14
       # run simultaneously.
      rospy.init node('listener', anonymous=True)
15
16
17
       rospy.Subscriber("chatter", String, callback)
18
19
       # spin() simply keeps python from exiting until this node is stopped
20
      rospy.spin()
21
22 if name == ' main ':
23
      listener()
```

Don't forget to make the node executable:

```
$ chmod +x listener.py
```

2.2 The Code Explained

The code for listener.py is similar to talker.py, except we've introduced a new callback-based mechanism for subscribing to messages.

```
rospy.init_node('listener', anonymous=True)

rospy.Subscriber("chatter", String, callback)

spin() simply keeps python from exiting until this node is stopped rospy.spin()
```

This declares that your node subscribes to the chatter topic which is of type std_msgs.msgs.String. When new messages are received, callback is invoked with the message as the first argument.

We also changed up the call to <code>rospy.init_node()</code> somewhat. We've added the anonymous=True keyword argument. ROS requires that each node have a unique name. If a node with the same name comes up, it bumps the previous one. This is so that malfunctioning nodes can easily be kicked off the network. The anonymous=True flag tells <code>rospy</code> to generate a unique name for the node so that you can have multiple <code>listener.py</code> nodes run easily.

The final addition, rospy.spin() simply keeps your node from exiting until the node has been shutdown. Unlike roscpp, rospy.spin() does not affect the subscriber callback functions, as those have their own threads.

3. Building your nodes

We use CMake as our build system and, yes, you have to use it even for Python nodes. This is to make sure that the autogenerated Python code for messages and services is created.

Go to your catkin workspace and run catkin_make:

```
$ cd ~/catkin_ws
$ catkin_make
```


Now that you have written a simple publisher and subscriber, let's examine the simple publisher and subscriber (/ROS/Tutorials/ExaminingPublisherSubscriber).

3.1 Additional Resources

Here are some additional resources contributed by the community.

3.0.1 Video Tutorial

The following video presents a small tutorial explaining how to write and test a publisher and subscriber in ROS with C++ and Python based on the talker/listener example above



Except where otherwise noted, the ROS wiki is licensed under the

Wiki: ROS/Tutorials/WritingPublisherSubscriber(python) (last edited 2015-08-04 18:16:29 by WilliamWoodall (/WilliamWoodall))

Creative Commons Attribution 3.0

(http://creativecommons.org/licenses/by/3.0/) | Find us on Google+ (https://plus.google.com/113789706402978299308)

Brought to you by: Open Source Robotics Foundation

(http://www.osrfoundation.org)