Modules: module API

The Module object

• {Object}

Provides general utility methods when interacting with instances of <code>Module</code>, the <code>module</code> variable often seen in <code>CommonJS</code> modules. Accessed via <code>import 'module'</code> or <code>require('module')</code>.

module.builtinModules

• {string[]}

A list of the names of all modules provided by Node.js. Can be used to verify if a module is maintained by a third party or not.

module in this context isn't the same object that's provided by the <u>module wrapper</u>. To access it, require the <u>Module module</u>:

```
// module.mjs
// In an ECMAScript module
import { builtinModules as builtin } from 'module';
```

```
// module.cjs
// In a CommonJS module
const builtin = require('module').builtinModules;
```

module.createRequire(filename)

- filename {string|URL} Filename to be used to construct the require function. Must be a file URL object, file URL string, or absolute path string.
- Returns: {require} Require function

```
import { createRequire } from 'module';
const require = createRequire(import.meta.url);

// sibling-module.js is a CommonJS module.
const siblingModule = require('./sibling-module');
```

module.syncBuiltinESMExports()

The module.syncBuiltinESMExports() method updates all the live bindings for builtin <u>ES Modules</u> to match the properties of the <u>CommonJS</u> exports. It does not add or remove exported names from the <u>ES Modules</u>.

```
const fs = require('fs');
const assert = require('assert');
const { syncBuiltinESMExports } = require('module');

fs.readFile = newAPI;
```

```
delete fs.readFileSync;

function newAPI() {
    // ...
}

fs.newAPI = newAPI;

syncBuiltinESMExports();

import('fs').then((esmFS) => {
    // It syncs the existing readFile property with the new value assert.strictEqual(esmFS.readFile, newAPI);
    // readFileSync has been deleted from the required fs assert.strictEqual('readFileSync' in fs, false);
    // syncBuiltinESMExports() does not remove readFileSync from esmFS assert.strictEqual('readFileSync' in esmFS, true);
    // syncBuiltinESMExports() does not add names assert.strictEqual(esmFS.newAPI, undefined);
});
```

Source map v3 support

Stability: 1 - Experimental

Helpers for interacting with the source map cache. This cache is populated when source map parsing is enabled and source map include directives are found in a modules' footer.

To enable source map parsing, Node.js must be run with the flag --enable-source-maps, or with code coverage enabled by setting NODE V8 COVERAGE=dir.

```
// module.mjs
// In an ECMAScript module
import { findSourceMap, SourceMap } from 'module';
```

```
// module.cjs
// In a CommonJS module
const { findSourceMap, SourceMap } = require('module');
```

module.findSourceMap(path)

- path {string}
- Returns: {module.SourceMap}

path is the resolved path for the file for which a corresponding source map should be fetched.

Class: module.SourceMap

new SourceMap(payload)

• payload {Object}

Creates a new sourceMap instance.

payload is an object with keys matching the Source map v3 format:

file: {string}version: {number}

sources: {string[]}sourcesContent: {string[]}

names : {string[]}mappings : {string}sourceRoot : {string}

sourceMap.payload

• Returns: {Object}

Getter for the payload used to construct the <u>SourceMap</u> instance.

sourceMap.findEntry(lineNumber, columnNumber)

lineNumber {number}columnNumber {number}

• Returns: {Object}

Given a line number and column number in the generated source file, returns an object representing the position in the original file. The object returned consists of the following keys:

• generatedLine: {number}

• generatedColumn: {number}

originalSource: {string}originalLine: {number}originalColumn: {number}

• name: {string}