# Building Bitcoin Core with Visual Studio

#### Introduction

Solution and project files to build Bitcoin Core with msbuild or Visual Studio can be found in the build\_msvc directory. The build has been tested with Visual Studio 2019 (building with earlier versions of Visual Studio should not be expected to work).

To build Bitcoin Core from the command-line, it is sufficient to only install the Visual Studio Build Tools component.

Building with Visual Studio is an alternative to the Linux based cross-compiler build.

## Prerequisites

To build dependencies (except for Qt), the default approach is to use the vcpkg package manager from Microsoft:

- 1. Install vcpkg.
- 2. By default, vcpkg makes both release and debug builds for each package. To save build time and disk space, one could skip debug builds (example uses PowerShell):

Add-Content -Path "vcpkg\triplets\x64-windows-static.cmake" -Value "set(VCPKG\_BUILD\_TYPE red

## $\mathbf{Q}\mathbf{t}$

To build Bitcoin Core with the GUI, a static build of Qt is required.

- Download a single ZIP archive of Qt source code from https://download.qt.io/official\_releases/qt/ (e.g., qt-everywhere-opensource-src-5.15.3.zip), and expand it into a dedicated folder. The following instructions assume that this folder is C:\dev\qt-source.
- 2. Open "x64 Native Tools Command Prompt for VS 2019", and input the following commands:

```
cd C:\dev\qt-source
mkdir build
cd build
...\configure -release -silent -opensource -confirm-license -opengl desktop -static -static-nmake
nmake install
```

One could speed up building with jom, a replacement for nmake which makes use of all CPU cores.

To build Bitcoin Core without Qt, unload or disable the bitcoin-qt, libbitcoin\_qt and test\_bitcoin-qt projects.

#### Building

1. Use Python to generate \*.vcxproj from Makefile:

PS >py -3 msvc-autogen.py

- 2. An optional step is to adjust the settings in the build\_msvc directory and the common.init.vcxproj file. This project file contains settings that are common to all projects such as the runtime library version and target Windows SDK version. The Qt directories can also be set. To specify a non-default path to a static Qt package directory, use the QTBASEDIR environment variable.
- 3. To build from the command-line with the Visual Studio 2019 toolchain use:

msbuild -property:Configuration=Release -maxCpuCount -verbosity:minimal bitcoin.sln Alternatively, open the build\_msvc/bitcoin.sln file in Visual Studio 2019.

### Security

Base address randomization is used to make Bitcoin Core more secure. When building Bitcoin using the build\_msvc process base address randomization can be disabled by editing common.init.vcproj to change RandomizedBaseAddress from true to false and then rebuilding the project.

To check if bitcoind has RandomizedBaseAddress enabled or disabled run

.\dumpbin.exe /headers src/bitcoind.exe

If is it enabled then in the output Dynamic base will be listed in the DLL characteristics under OPTIONAL HEADER VALUES as shown below

8160 DLL characteristics
High Entropy Virtual Addresses
Dynamic base
NX compatible
Terminal Server Aware

This may not disable all stack randomization as versions of windows employ additional stack randomization protections. These protections must be turned off in the OS configuration.