NAME

rgbds — object file format documentation

DESCRIPTION

This is the description of the object files used by rgbasm(1) and rgblink(1). Please, note that the specifications may change. This toolchain is in development and new features may require adding more information to the current format, or modifying some fields, which would break compatibility with older versions.

FILE STRUCTURE

The following types are used:

LONG is a 32âbit integer stored in littleâendian format (Intel). BYTE is an 8âbit integer. STRING is a 0âterminated string of BYTE.

```
; Header
                         ; "RGB6"
BYTE
        NumberOfSymbols ; The number of symbols used in this file
LONG
        NumberOfSections; The number of sections used in this file
LONG
; Symbols
                         ; Number of symbols defined in this object file.
REPT
        NumberOfSymbols
    STRING Name
                          ; The name of this symbol. Local symbols are stored
                          ; as "Scope.Symbol".
    BYTE
                          ; 0 = LOCAL symbol only used in this file.
            Type
                          ; 1 = IMPORT this symbol from elsewhere (unused).
                          ; 2 = EXPORT this symbol to other objects.
            Type != 1
    IF
                          ; If symbol is defined in this object file.
        STRING FileName ; File where the symbol is defined.
                         ; Line number in the file where the symbol is defined.
        LONG
                LineNum
        LONG
                SectionID; The section number (of this object file) in which
                          ; this symbol is defined. If it doesn't belong to any
                          ; specific section (like a constant), this field has
                          ; the value -1.
        LONG
                Value
                          ; The symbols value. It's the offset into that
                          ; symbol's section.
    ENDC
ENDR
; Sections
REPT NumberOfSections
```

STRING Name ; Name of the section

```
LONG
       Size ; Size in bytes of this section
BYTE
       Type ; 0 = WRAM0
             i 1 = VRAM
             i = ROMX
             ; 3 = ROM0
             ; 4 = HRAM
             ; 5 = WRAMX
             ; 6 = SRAM
             7 = OAM
LONG
       Org ; Address to fix this section at. -1 if the linker should
             ; decide (floating address).
LONG
       Bank ; Bank to load this section into. -1 if the linker should
             ; decide (floating bank). This field is only valid for ROMX,
             ; VRAM, WRAMX and SRAM sections.
LONG
       Align; Alignment of this section (expressed as number of low bits
             ; to leave as 0). -1 if not defined.
IF
        (Type == ROMX) \mid | (Type == ROM0) ; Sections that can contain data.
   BYTE
           Data[Size] ; Raw data of the section.
   LONG
           NumberOfPatches; Number of patches to apply.
    ; These types of sections may have patches
           NumberOfPatches
       STRING SourceFile ; Name of the source file (for printing error
                            ; messages).
                           ; The line of the source file.
       LONG
               Line
       LONG
               Offset
                           ; Offset into the section where patch should
                            ; be applied (in bytes).
                            ; 0 = BYTE patch.
       BYTE
               Type
                            ; 1 = little endian WORD patch.
                            ; 2 = little endian LONG patch.
                            ; 3 = JR offset value BYTE patch.
               RPNSize
                         ; Size of the buffer with the RPN.
       LONG
                            ; expression.
              RPN[RPNSize] ; RPN expression. Definition below.
       BYTE
   ENDR
ENDC
```

ENDR

RPN DATA

Expressions in the object file are stored as RPN. This is an expression of the form "2 5 +". This will first push the value "2" to the stack. Then "5". The "+" operator pops two arguments from the stack, adds them, and then pushes the result on the stack, effectively replacing the two top arguments with their sum. In the RGB format, RPN expressions are stored as BYTEs with some bytes being special prefixes for integers and symbols.

```
Value Meaning
$00
      + operator
$01
      - operator
$02
      * operator
$03
      / operator
$04
      % operator
$05
      unary -
$10
      operator
$11
      & operator
$12
      ^ operator
$13
    unary ~
$21
      && comparison
$22
    || comparison
$23
      unary!
$30
      == comparison
     != comparison
$31
$32
      > comparison
$33
      < comparison
$34
    >= comparison
$35 <= comparison
$40
      << comparison
$41
      >> comparison
$50
      BANK (symbol), a LONG Symbol ID follows.
      BANK (section_name), a null-terminated string follows.
$51
$52
      Current BANK().
$60
      HRAMCheck. Check if the value is in HRAM, AND it with 0xFF.
$80
      LONG integer follows.
$81
      LONG Symbol ID follows.
```

SEE ALSO

rgbasm(1), rgblink(1), rgbds(7), gbz80(7)

HISTORY

rgbds was originally written by Carsten Sørensen as part of the ASMotor package, and was later packaged in RGBDS by Justin Lloyd. It is now maintained by a number of contributors at https://github.com/rednex/rgbds