Semantic Thermodynamic Engineering Specification

1. Overview

Semantic Thermodynamic within Kimera SWM defines the rules governing how semantic constructs (e.g., Echoforms, EcoForms, Geoid interactions) gain, dissipate, and transfer "semantic energy." This system ensures consistency in activation, resonance, and decay across modules. It focuses strictly on engineering constructs: memory structures, data schemas, routing logic, threshold values, and pseudocode. All speculative commentary is omitted.

2. Functional Requirements

1. Semantic Energy Representation

- Each semantic unit (e.g., Echoform, EcoForm, Geoid) maintains a scalar
 Semantic Energy (SE).
- SE decays over time according to exponential laws and can be boosted via interaction events (e.g., reactivation, resonance).
- Modules must provide APIs to guery and modify SE values atomically.

2. Energy Decay & Temperature Analogy

- **Decay Law**: $SE(t) = SE_0 \cdot exp(-\lambda \cdot \Delta t)$ where:
 - SE₀: initial energy.
 - λ : decay coefficient specific to semantic class (e.g., 'echoform': λ_e , 'ecoform': λ_o , 'geoid': λ_g).
 - \blacksquare Δt : time since last update (seconds).
- Semantic Temperature (T_sem): Derived from SE and local context density:
 - $T_{sem} = SE / (1 + \rho)$ where $\rho = local$ semantic density (number of overlapping units within a semantic radius R).
- When T_sem falls below a threshold, the unit is marked "thermally inactive."

3. Energy Transfer & Resonance

- When two semantic units interact (e.g., overlapping geoid fields, matching Echoforms), a Resonance Event can occur if their similarity ≥ ρ_res = 0.75.
- Energy Transfer Rule:

```
■ \Delta SE = \kappa \cdot min(SE_1, SE_2) where:
```

- κ : coupling coefficient (0 < κ ≤ 1).
- SE₁, SE₂: current energies of the interacting units.
- The higher-SE unit loses \triangle SE, the lower-SE unit gains \triangle SE.
- Resonance API: Modules must call Resonate(unitA_id, unitB_id, current_time) to compute and apply energy transfer.

4. Thermodynamic Constraints

Maximum Semantic Capacity (C_max) per unit type:

```
■ Echoform: C_max_e = 1.0
```

■ EcoForm: C_max_o = 1.0

```
■ Geoid: C_{max_g} = 5.0
```

- After boosting (e.g., reactivation), clamp SE ≤ C_max.
- Entropy Generation: Each interaction generates a small entropy increment:

```
\blacksquare \triangle S = \alpha \cdot |\triangle SE| where \alpha = 0.01 (entropy coefficient).
```

Store cumulative entropy per unit in entropy_accumulated field.

5. APIs & Integration

- GetEnergy(unit_type, unit_id): Returns { SE_current, last_update_time }.
- UpdateEnergy(unit_type, unit_id, new_SE, current_time): Atomically set SE and update timestamp.

- Resonate(unitA_type, unitA_id, unitB_type, unitB_id, current_time):
 Compute and apply energy transfer and entropy increment.
- DecayAll(current_time): Module invokes per-cycle to decay SE of all active units of a given type.

3. Data Structures & Schemas

3.1 Semantic Unit Record (Generic)

Applicable schema fields for Echoform, EcoForm, Geoid:

```
SemanticUnit:
```

```
unit id: UUID
```

unit_type: String # "Echoform" | "EcoForm" | "Geoid"

SE_current: Float # Current Semantic Energy

SE_initial: Float # Initial Energy at creation or last boost

decay_rate: Float # λ specific to unit type

last update time: ISO8601 String

C max: Float # Maximum semantic capacity

entropy_accumulated: Float # Total entropy generated so far status: String # "Active" | "ThermallyInactive" | "Archived" metadata: JSON Object # Additional fields specific to unit type

Decay Rates (λ):

```
\circ Echoform: \lambda_e = 0.003
```

 \circ EcoForm: $\lambda_0 = 0.002$

 \circ Geoid: $\lambda_g = 0.001$

Status Transition:

```
o If T_sem < T_min (e.g., T_min = 0.05), set status =
ThermallyInactive.</pre>
```

 Archived when unit-specific archival criteria met (e.g., Echoform after T_archive_e).

3.2 Geoid-Specific Fields

Geoid:

```
semantic unit: SemanticUnit
 local density: Integer
                          # Number of nearby units within radius R_sem
 resonance partners: [UUID]
                              # IDs of units currently in resonance
 metadata:
  phase vector: Float[D phase]
  spectral_signature: Float[D_spec]
   • D_phase = 64, D_spec = 16.
3.3 Echoform & EcoForm-Specific Fields
Echoform:
 semantic unit: SemanticUnit
 geoid_payload: [UUID]
                           # Associated Geoids
 embedding vector: Float[D emb] # D emb = 512
 residual schema: JSON
                             # { grammar_vector_residual, orthography_residual }
 metadata:
  origin_context: JSON
                          # { module, cycle number, source language }
EcoForm:
 semantic unit: SemanticUnit
 grammar tree: JSON
                           # Serialized parse tree
 grammar_vector: Float[D_g] # D_g = 128
 orthography_vector: JSON # See Section 3.2 in EcoForm spec
```

4. Routing Logic

metadata: JSON

residual schema: JSON

Semantic Thermodynamic operations are coordinated by a **Thermodynamic Engine**. Sequence:

{ origin context, feature flags }

1. Input Modules Trigger

Echoform/EcoForm creation or reactivation events call UpdateEnergy(...)
 with boost.

{ grammar vector residual, orthography residual }

 Geoid interactions (e.g., new contradiction) call UpdateEnergy(Geoid, geoid_id, new_SE, time).

2. Decay Scheduler

o Runs every DecayInterval = 60 s.

- For each unit in each type (Echoform, EcoForm, Geoid):
 - \blacksquare $\Delta t = now last_update_time.$
 - SE_current = SE_current $\cdot \exp(-\text{decay_rate} \cdot \Delta t)$.
 - Compute T_sem = SE_current / (1 + local_density).
 - If T_sem < T_min = 0.05, set status = ThermallyInactive.
 - Update last_update_time = now.

3. Resonance Dispatcher

- When two units have overlapping semantic contexts, call Resonate(...).
- Compute similarity (embedding/grammar) to verify $\geq \rho_{res} = 0.75$.
- Apply energy transfer and entropy increment.

4. Archival Manager

- Periodically check:
 - Echoform archived after T_archive_e = 2,592,000 s.
 - EcoForm archived after T_archive_o = 2,592,000 s.
 - Geoid archived only on manual decommission.

5. Threshold Values & Configuration

```
semantic_thermo_config:

# Decay Rates
decay_rate_e: 0.003 # Echoform
decay_rate_o: 0.002 # EcoForm
decay_rate_g: 0.001 # Geoid

# Temperature Threshold
T_min: 0.05 # Minimum semantic temperature to remain active

# Coupling & Resonance
rho_res: 0.75 # Similarity threshold for resonance
kappa: 0.50 # Energy transfer coefficient
```

```
alpha_entropy: 0.01 # Entropy generation coefficient
```

```
# Maximum Capacities

C_max_e: 1.0  # Echoform

C_max_o: 1.0  # EcoForm

C_max_g: 5.0  # Geoid

# Scheduler Intervals (seconds)

DecayInterval: 60

ArchivalInterval: 3600
```

6. Core Algorithms & Pseudocode

6.1 UpdateEnergy API

```
function UpdateEnergy(unit_type, unit_id, new_SE, current_time):
  unit = LookupUnit(unit_type, unit_id)
  if unit is null:
     return ERROR "UNIT_NOT_FOUND"
  # Clamp to capacity
  if new SE > unit.C max:
     unit.SE current = unit.C max
  else:
     unit.SE_current = new SE
  unit.last_update_time = current_time
  # Compute T sem
  local_density = unit.metadata.get("local_density", 0)
  T sem = unit.SE current / (1 + local density)
  if T sem < T min:
     unit.status = "ThermallyInactive"
  else:
     unit.status = "Active"
  return SUCCESS
```

6.2 DecayAll Routine

```
function DecayAll(current_time): for each unit_type in ["Echoform", "EcoForm", "Geoid"]: for each unit in Registry[unit_type]: if unit.status == "Active": \Delta t = (current\_time - unit.last\_update\_time).seconds \\ unit.SE\_current = unit.SE\_current * exp(- unit.decay\_rate * \Delta t) \\ unit.last\_update\_time = current\_time \\ \# Recompute T\_sem \\ local\_density = unit.metadata.get("local\_density", 0) \\ T\_sem = unit.SE\_current / (1 + local\_density) \\ if T\_sem < T\_min:
```

6.3 Resonate API

```
function Resonate(typeA, idA, typeB, idB, current time):
  unitA = LookupUnit(typeA, idA)
  unitB = LookupUnit(typeB, idB)
  if unitA is null or unitB is null:
     return ERROR "UNIT NOT FOUND"
  # Compute similarity depending on type
  sim = ComputeSimilarity(unitA, unitB) # cosine of embeddings or grammar
  if sim < rho res:
     return ERROR "LOW SIMILARITY"
  # Determine energy transfer
  minSE = min(unitA.SE current, unitB.SE current)
  deltaSE = kappa * minSE
  # Apply transfer
  if unitA.SE_current >= unitB.SE_current:
     unitA.SE_current -= deltaSE
     unitB.SE_current += deltaSE
  else:
     unitB.SE current -= deltaSE
     unitA.SE_current += deltaSE
  # Clamp both
  unitA.SE current = min(unitA.SE current, unitA.C max)
  unitB.SE_current = min(unitB.SE_current, unitB.C_max)
  # Update timestamps
  unitA.last_update_time = current_time
  unitB.last update time = current time
  # Increment entropy
  deltaS = alpha_entropy * deltaSE
  unitA.entropy_accumulated += deltaS
  unitB.entropy accumulated += deltaS
  return SUCCESS
```

7. Integration Points

1. Echoform Module

- On creation: call UpdateEnergy("Echoform", echoform_id, SE_initial_e, time) where SE_initial_e = 1.0.
- On reactivation: same API with boosted SE.

Decay scheduler invokes DecayAll periodically.

2. EcoForm Module

- On creation/reactivation: call UpdateEnergy("EcoForm", ecoform_id, SE_initial_o, time) where SE_initial_o = 1.0.
- Decay scheduler as above.

3. Geoid Module

- On contradiction or new resonance: call UpdateEnergy("Geoid", geoid_id, new_SE, time).
- o Local density computed via spatial index of geoid neighbors.

4. Resonance Manager

- Detects possible unit pairs to resonate based on embedding/grammar similarity.
- o Calls Resonate(...) for each pair meeting ρ _res.

8. Testing & Validation

1. Unit Tests

- \circ Create a mock unit with SE_initial, run DecayAll over known Δt , verify SE_current = SE_initial $\cdot \exp(-\lambda \cdot \Delta t)$.
- Test UpdateEnergy clamps values correctly and updates status based on T_sem.
- Test Resonate transfers correct ΔSE for unit pairs with known SEs.

2. Integration Tests

- \circ Simulate Echoform-Echoform resonance: two echoforms with SEs [0.8, 0.2], κ =0 . 5, verify final SEs [0.6, 0.4].
- Validate geoid local density effect on temperature: geoid with SE_current=0.1, local_density=4, T_sem=0.02 < T_min, status

becomes ThermallyInactive.

3. Performance Tests

- Bulk decay: 100,000 units, ensure DecayAll runs within 500 ms.
- Bulk resonance: 10,000 resonance checks/sec, ensure Resonate calls handle latency < 5 ms each.

9. Monitoring & Metrics

Expose the following metrics via /metrics endpoint:

- Gauge: semantic_SE_current{unit_type} Sum of SE_current across all active units by type.
- **Gauge**: semantic_inactive_count{unit_type} Count of units with status = ThermallyInactive.
- Counter: semantic_resonate_total Total successful Resonate calls.
- Histogram: semantic_decay_duration_seconds Duration of DecayAll executions.
- **Gauge**: semantic_entropy_total{unit_type} Cumulative entropy across units by type.

10. Security & Compliance

- Access Control: Only authenticated modules may call UpdateEnergy, Resonate, and DecayAll.
- Encryption: All API calls over mTLS; at-rest storage of SE and entropy must use AES-256.
- Audit Logging: Append-only log entries for all Resonate and UpdateEnergy calls, capturing timestamps, unit IDs, and energy values.

End of Semantic Thermodynamic Engineering Specification