Advanced SIMD Optimizations

Mainack Mondal Sandip Chakraborty

CS 60203 Autumn 2024



Outline

- SSE Memory Operations
 - Kinds of Memory operations
 - Memory Alignment
 - Pointer Aliasing
- GCC Auto Vectorization
- Fused-Multiply-Add (FMA)
 - What is FMA? Why FMA?
 - Family of FMA
 - Advantages

SSE Memory Operations

(Slides partially taken from Marat Dukhan and Andreas Schmitz)

SSE Memory Operations

We have already seen two kinds of load/store instructions

- Aligned (eg: _mm_load_ps)
 - Mandate that pointer is aligned on 16-byte boundary
 - Pros: Faster loads/stores (why?)
 - Cons: Can cause segmentation faults if misaligned data is loaded
- Mis-Aligned (eg: _mm_loadu_ps)
 - Can work with any pointers
 - But, has computation overhead
 - Multiple reads necessary
 - Additional code to extract the data

Memory Alignment in C/C++

But ... How do you align memory?

The answer is: Using specific *compiler directives*

- Directives to control alignment behavior:
 - GCC specific [FSF15, 6.38]
 - __attribute__ ((aligned (ALIGN)))
 - __attribute__ ((packed))
 - C11 Standard [ISO 11, 6.2.8, 7.22.3]
 - aligned_alloc(size_t alignment, size_t size)
 - _ _Alignas(expression) and _Alignas(type)

Memory Alignment Examples

- struct V{short s[3];} __attribute__ ((aligned(8));
 size of V = 6 bytes + 2 bytes (padding)
 char c[2] __attribute__ ((aligned(8)));
 size of c = 2 bytes + 6 bytes (padding)
- struct A{char a; int b;} __attribute__((packed));
 size of A = 1 byte + 4 bytes (no padding because packed)

Pointer Aliasing

- Refers to memory addressed by different names
- Example: char b; char *a = &b;
- Needs to be considered by the compiler
- Can result in code overhead (will see in examples)

Pointer Aliasing Examples

```
void foo(int *a, int *b, int *c)
{
    *a = 42;
    *b = 23;
    *c = *a;
}
```

due to aliasing

```
Assembly

mov DWORD PTR [rdi], 42
mov DWORD PTR [rsi], 23
mov edx, DWORD PTR [rdi]
mov DWORD PTR [rdx], edx
```

Pointer Aliasing Examples

How do you stop aliasing? Use restrict keyword (C99 standard)

```
void foo(int * restrict a, int * restrict b, int *c)
{
    *a = 42;
    *b = 23;
    *c = *a;
}
```

```
Assembly mov DWORD PTR [rdi], 42 mov DWORD PTR [rsi], 23 No aliasing mov DWORD PTR [rdx], 42
```

Pointer Aliasing - Remarks

- restrict needs to be used carefully
- Programmer is responsible for proper usage
- Mishandling can lead to wrong programs

Outline

- SSE Memory Operations
 - Kinds of Memory operations
 - Memory Alignment
 - Pointer Aliasing

GCC Auto Vectorization

- Fused-Multiply-Add (FMA)
 - What is FMA? Why FMA?
 - Family of FMA
 - Advantages

GCC Auto Vectorization

Auto-vectorization related Flags

- -0 -ftree-vectorize
 - Activates auto-vectorization
- -03
 - Optimizations including auto vectorization
- -fopt-info-vec, -fopt-info-vec-missed
 - List (not) vectorized loops + additional information
- -march=native
 - Use instructions supported by the local CPU
- -falign-functions=32, -falign-loops=32
 - Aligns the address of functions / loops to be a multiple of 32 bytes

GCC Auto-Vectorization Examples

Simple Loop

Compiler Output:

optimized: loop vectorized using 32 byte vectors optimized: loop versioned for vectorization because of possible aliasing

compile this with:

```
-0 -ftree-vectorize, -fopt-info-vec,
-fopt-info-vec-missed, -march=native
```

GCC Auto-Vectorization Examples (contd.)

2 versions

\$524288, %rax

```
Simple Loop (asm output)
```

```
.L3:
  vmovupd (%rdi,%rax), %ymm1
  vaddpd (%rsi,%rax), %ymm1, %ymm0
  vmovupd %ymm0, (%rdi,%rax)
  addq
        $32, %rax
                              .L2:
       $524288, %rax
  cmpq
                                        (%rdi,%rax), %xmm0
                                 vmovsd
  jne .L3
                                 vaddsd
                                        (%rsi,%rax), %xmm0, %xmm0
  ret
                                         %xmm0, (%rdi,%rax)
                                 vmovsd
                                 addq
                                         $8, %rax
```

cmpq

ret

jne .L2

Let's make it better

GCC Auto-Vectorization Examples (Contd.)

Improved Loop

```
# define SIZE (1 << 16)
void simpleLoop ( double * restrict a, double * restrict b)
{
    for ( int i = 0; i < SIZE ; i++)
        {
            a[i] += b[i];
        }
}</pre>
```

Compiler Output:

optimized: loop vectorized using 32 byte vectors

GCC Auto-Vectorization Examples (contd.)

Improved Loop (asm output)

```
.L2:
vmovupd (%rdi,%rax), %ymm1
vaddpd (%rsi,%rax), %ymm1, %ymm0
vmovupd %ymm0, (%rdi,%rax)
addq $32, %rax
cmpq $524288, %rax
jne .L2
ret
```

No versions

Scope for further improvement?

Yes, it uses unaligned load/store

Let's make it even better

GCC Auto-Vectorization Examples (Contd.)

Optimised Loop

```
#define SIZE (1 << 16)
#define GCC_ALN(var, alignment) \
__builtin_assume_aligned(var, alignment)
void optimized_Loop(double *restrict a, double *restrict b)
    a = (double *)GCC_ALN(a, 32);
    b = (double *)GCC_ALN(b, 32);
    for (int i = 0; i < SIZE; i++)
                                      Compiler Output:
        a[i] += b[i];
                                      optimized: loop vectorized using 32 byte vectors
```

GCC Auto-Vectorization Examples (contd.)

Optimized Loop (asm output)

```
.L2:
    vmovapd (%rdi,%rax), %ymm1
    vaddpd (%rsi,%rax), %ymm1, %ymm0
    vmovapd %ymm0, (%rdi,%rax)
    addq $32, %rax
    cmpq $524288, %rax
    jne .L2
    ret
```

aligned load/store

GCC Auto-Vectorization Examples (Contd.)

Optimised Loop (C11 Compatible)

```
#include <stdalign.h>
#define SIZE (1 << 16)
struct data {
    alignas(32) double vec[SIZE];
void optimized_Loop(struct data *restrict a, struct data *restrict b){
    for (int i = 0; i < SIZE; i++)
        a->vec[i] += b->vec[i];
                                       Compiler Output:
                                        optimized: loop vectorized using 32 byte vectors
```

Note: This produces the same assembly code as previous

Auto-vectorization Requirements and Limitations

- Countable loops
- No backward loop-carried dependencies
- No function calls: Except vectorizable math functions e.g. sin, sqrt,...
- Straight-line code (only one control flow: no switch)
- Loop to be vectorized must be innermost loop if nested

References: Intel: requirements for vectorizable loops

Outline

- SSE Memory Operations
 - Kinds of Memory operations
 - Memory Alignment
 - Pointer Aliasing
- GCC Auto Vectorization
- Fused-Multiply-Add (FMA)
 - What is FMA? Why FMA?
 - Family of FMA
 - Advantages

FMA: Fused-Multiply-Add

What is FMA?

- Basically combining multiplication and Addition
 - o computes x*y + z
- Introduced by IBM in their POWER Architecture in 1990s

FMA Family

- FMA(x, y, c)-Fused Multiply-Add \rightarrow x * y + c
- FMS(x, y, c) Fused Multiply-Subtract \rightarrow x * y c
- FNMA(x, y, c) Fused Negative Multiply-Add $\rightarrow -x*y + c$
- FNMS(x, y, c) Fused Negative Multiply-Subtract $\rightarrow -x * y c$

Why FMA?

Let's see a comparison between FMA and Multiply-then-add:

- Multiply + Add:
 - First, (x * y) is computed and rounded to double precision
 - Then, (x * y) + c is computed and also rounded to double
- Fused Multiply-Add:
 - Single operation
 - Computed without intermediate rounding after multiplication

Advantages of FMA

Higher accuracy (How?)

Higher performance

- Performs addition and multiplication at the cost of single multiplication
 - *AMD Bulldozer*: FP ADD/MUL/FMA latency = 5
- Allows high-performance implementation of other floating-point algorithms eg: division, sqrt etc.

Resources on FMA

For further information see

- "Handbook of Floating Point Arithmetic" (2009), Muller, Brisebarre, de Dinechin, Jeannerod, Lefèvre
- "IA64 and Elementary Functions" (2000), Peter Markstein
- Wikipedia article on FMA: <u>Link</u>
- FMA Instruction set: Link