

Puma User Manual

Puma User Manual

Language: English
Target audience: Administrators and operators

1. Purpose and Scope


Puma is the central system for authentication and permission management across multiple applications. Users log in to Puma; applications use the permissions provided by Puma to decide which functions are enabled. This eliminates the need to manage users, roles, and groups separately in each application.

This manual describes:

- the Puma server with an SQLite or PostgreSQL database,
- local users, roles, groups, and product-specific permissions,
- the integration of custom Qt/C++ applications via `AuthClientSdk`,
- the integration of custom servers via `AuthServerSdk`,
- Windows domain login via the LDAP layer implemented in `ImtCore`,
- Personal Access Tokens (PATs) for non-interactive access,
- typical operational, security, and error scenarios.

The description is based on Puma and the underlying authentication implementation in ImagingTools/ImtCore. It describes the functionality currently present in the source code; specific menu names may vary depending on the embedded administration interface.

2. Puma at a Glance




Puma separates four responsibilities:

1. **Identity:** Who is accessing the system?
2. **Authentication:** Is the presented credential valid?
3. **Authorization:** Which product-specific actions are permitted?
4. **Persistence:** Where are users, roles, groups, sessions, and PATs stored?

2.1 Puma Server Variants


Variant	Database	Typical use
PumaServerSl	SQLite	Single installation, development, small local installation
PumaServerPg	PostgreSQL	Central multi-user operation and production server installation

Both variants use the same Puma server base. Each server application includes the appropriate repositories and SQL scripts for its database.



3. Role and Permission Model

Puma does not manage permissions as freely editable user properties, but through roles:




- **Users** have an internal, stable object ID and a login name.
- **Roles** bundle permissions and are product-specific.
- **Groups** bundle users and are assigned roles.
- **Permissions** are case-sensitive IDs defined by the application.
- **Product ID** limits the context in which roles and permissions apply.

A user receives the union of:

- permissions from directly assigned roles and
- permissions from the roles of their groups.

Important: Administrative operations use the internal user ID, not the login name. An application sets its product ID before login.

3.1 Recommended Administration Model



The superuser is used for initial setup. For day-to-day work, personalized administrator accounts with an appropriate administrator role should be used. This avoids the need to share superuser credentials.


4. Commissioning the Puma Server

4.1 Preparation

1. Select the server variant.
2. For PostgreSQL, prepare the database, database user, and connectivity.
3. Define the HTTP and WebSocket ports.
4. Provide a server certificate and a private key for production systems.
5. Open the firewall only for the required ports.
6. Verify write permissions for settings, the database, and logs.

By default, persistent Puma settings are stored in `Puma/Puma Server/PumaServerSettings.xml` under the application-specific system path.


4.2 Startup Sequence



After startup, verify in particular that:

- the database connection was successful,
- the HTTP and WebSocket ports are bound,
- the certificate and key are loaded,
- there are no migration or repository errors,
- the client can reach the server.


4.3 Initial Setup



The SDK sequence consists of `SuperuserExists()`, followed by `CreateSuperuser()` if necessary, then login and creation of the role model. The Puma tests use the login `su` for the initial account; production credentials must be chosen securely, must differ from it, and must be kept safe.

4.4 Transport Encryption

Puma uses separate ports for HTTP(S) and WebSocket(S). As soon as clients access the system from outside an isolated development machine, HTTPS and WSS must be used.



Production rules:

- Use TLS 1.2 or later.
- Do not disable certificate verification.
- Make the private key readable only by the server process.
- Do not store passphrases in source code or presentations.
- Use HTTP/WS without TLS only in controlled test environments.


5. Detailed Use Cases

UC-01: Create and Authorize a Local User

Actor: Administrator

Precondition: The administrator is logged in and has the necessary administrative permissions.

1. Create a user with a display name, unique login, initial password, and email address.
2. Obtain the internal user ID from the result.
3. Assign an existing role or create a role first.
4. Optionally add the user to a group.
5. The user logs in.
6. The application checks the expected permissions.




Result: The user receives permissions from direct roles and group roles. A user who is already logged in may need to log in again for the application to receive updated session permissions.

UC-02: Manage a Team Through a Group

Actor: Administrator

1. Create a functional role with the required permissions.
2. Create a group for the team or department.
3. Assign the role to the group.
4. Add users to the group.
5. Remove users from the group when they leave.




Benefit: Role changes apply centrally to all group members.

UC-03: Login and Function-Specific Access

Actor: End user

1. The application configures the connection and product ID.
2. The user enters a login and password.
3. Puma validates the credentials.
4. Puma creates a session and returns the token, user name, product ID, and permissions.
5. The application enables only permitted functions.
6. Puma invalidates the session on logout.



Invalid credentials, a locked account, a missing connection, or missing server components are reported as a failed login.

UC-04: Change Permissions


1. The administrator changes a role or group assignment.
2. The application ends the old session or requests another login.
3. The user logs in again.
4. The application builds its interface using the new permissions.

Hiding a button is not a substitute for server-side verification. Every protected server operation must validate the permission again.

UC-05: Deactivate or Remove a User

The existing client SDK provides `RemoveUser ( )` for permanent deletion. Before deleting a user, check the applicable retention and audit requirements. Role and group assignments are removed with the user. For a temporary lockout, use the account status function provided by the specific administration interface; otherwise, revoke access through role assignments and session management.

UC-06: Integrate a Custom Application



The minimum sequence in the C++ client is:

```
AuthClientSdk::CAuthorizationController auth;

AuthClientSdk::ServerConfig server;
server.host = "puma.example.org";
server.httpPort = 443;
server.wsPort = 8443;
server.sslConfig = AuthClientSdk::SslConfig{};

auth.SetConnectionParam(server);
auth.SetProductId("MeineAnwendung");


AuthClientSdk::Login session;
if (auth.Login(login, password, session) &&
    auth.HasPermission("messung.lesen")) {
    // Enable protected function.
}
auth.Logout();
```

Security-relevant notes:

- Transmit passwords only over TLS.
- Do not log session tokens.
- Login() automatically ends a previous session of the controller.
- Call Logout() explicitly; the destructor also attempts a best-effort logout.
- Do not execute Login() and Logout() in parallel on the same controller.

UC-07: Integrate a Custom Authorizable Server

AuthServerSdk::CAuthorizableServer is intended for server applications that provide their own endpoints but use Puma as the central authority.



The application server sets:

1. its product ID,
2. the connection to the central Puma server,
3. its own HTTP/WebSocket ports,
4. optionally, a feature file and TLS configuration,
5. then Start(), and Stop() during shutdown.

6. SDK Layer

6.1 AuthClientSdk

The AuthClientSdk::CAuthorizationController facade provides:

Area	Core operations
Connection	SetConnectionParam(), SetProductId()
Session	Login(), Logout(), GetToken()
Authorization	HasPermission(), GetTokenPermissions()
Bootstrap	SuperuserExists(), CreateSuperuser()
Users	List, read, create, delete, change password
Roles	List, read, create, delete, assign permissions
Groups	List, read, create, delete, assign users/roles
PAT	Create, list, validate, and revoke

ServerConfig contains the host, HTTP port, WebSocket port, and optional TLS settings. Roles and permissions are bound to the application configured with SetProductId().

6.2 AuthServerSdk

The server SDK encapsulates an authorizable HTTP/WebSocket server. Its network connection to the Puma backend is separate from the ports on which the custom server serves clients. In distributed installations, both connection directions must therefore be configured and secured.


6.3 UI Components

Puma includes widgets and QML components for login and administration. They use the same authentication and administration interfaces. A custom interface must not replace server-side permission checks.

7. LDAP/Windows Domain Login

7.1 How It Works

On Windows, the current ImtCore implementation uses the Windows domain functions, in particular verification through LogonUser. It is therefore designed for Windows/Active Directory environments and is not a generally configurable OpenLDAP client.



After a successful first domain login, Puma:

- creates an internal user record,
- marks the authentication system as LDAP,
- imports the SID, display name, and email address where available,
- creates the product-specific `Guest` and `Default` roles if necessary,
- assigns the default role for the product to the user.

Administrators can then assign additional Puma roles and groups to the mirrored user. The password continues to be verified against the Windows domain.

7.2 Enabling and Disabling

`LdapEnabled` is enabled in Puma's default settings and is provided through the **LDAP** settings section. If only local Puma accounts are used, the function should be disabled to avoid unnecessary domain checks and misleading messages.

7.3 Prerequisites

- Puma runs on Windows.
- The server can reach the domain and a domain controller.
- The operating system, DNS, and trust relationship are configured correctly.
- The user uses a login accepted by Windows, typically `DOMÄNE\benutzer`.
- LDAP is enabled in Puma.


7.4 Troubleshooting

Symptom	Check
Domain login fails, local login works	Check domain connectivity, DNS, time, login format, and <code>LdapEnabled</code>
User is created twice	Check for a consistent login format and SID resolution
User has insufficient permissions after first login	Check the default role and additional role/group assignments
Local logins produce domain errors in the log	Disable LDAP if it is not required
Linux server does not authenticate against AD	The current implementation is Windows-specific


8. Personal Access Tokens (PAT)

8.1 Usage

PATs are long-lived credentials for automation, CI/CD, monitoring services, and service-to-service communication. A PAT belongs to a user, contains a product ID, and has explicit permission scopes.



8.2 Life Cycle



A token is valid if it exists, is active, has not been revoked, and has not expired. Revoked records remain visible in the list and are reported as inactive.

8.3 Create a PAT


Precondition: The owner or an administrator is logged in with a session.

1. Assign a purpose-specific name, for example CI Produktion Lesen.
2. Specify the target user and product ID.
3. Select only the minimum necessary scopes.
4. Set an expiration date in ISO 8601 format whenever possible.
5. Store the secret in a secret store immediately.
6. Do not copy the secret into source code, build logs, or tickets.

Anonymous callers may not create PATs. A regular user can manage their own PATs, but not those of other users. Administrators can manage PATs belonging to other users.

8.4 Use a PAT

The SDK data model distinguishes between `TokenType::Session` and `TokenType::PersonalAccessToken`. For non-interactive access, the PAT is validated using `ValidatePersonalAccessToken()`; the application then uses only the returned scopes and additionally verifies the product context.



8.5 Revoke a PAT


1. Identify the token by name, product, creation time, and last use.
2. Revoke the token ID.
3. Validation must then fail.
4. If secret exposure is suspected, check dependent systems and logs.
5. Issue a replacement PAT with a reduced scope and a new expiration date.

8.6 Known Interface Characteristic

The current GraphQL validation response returns the user ID and scopes, but not the token ID. Consequently, `ValidatePersonalAccessToken()` currently cannot reconstruct the `productId` in the validation result. The issuing or consuming system must additionally know and verify the product context.

9. Operations and Security

9.1 Responsibilities




9.2 Regular Checks

- Remove or lock users who no longer have a current business need.
- Review roles and groups according to the principle of least privilege.
- Revoke old, unused, or expired PATs.
- Assign administrator permissions to named individuals.
- Back up the database and settings; test recovery.
- Monitor certificate expiration.
- Investigate failed logins and unusual token use.
- Keep the server and ImtCore/Puma components up to date.

9.3 Backup and Recovery

A consistent backup includes at least the database and Puma settings. Certificates and keys must be backed up separately with special protection. After recovery, test database migrations, login, roles, groups, session handling, and PAT validation in a controlled environment.

10. Troubleshooting



Problem	Probable cause	Action
Connection refused	Incorrect host/port or server not started	Check the HTTP and WS ports and the process
TLS error	Certificate is not trusted or name is incorrect	Check the certificate chain, host name, and time
Login fails	Credentials, account status, or LDAP	Check the authentication path systematically
HasPermission() remains false	Incorrect product ID or missing role	Check the product ID and effective roles
User operation returns an empty ID	Login already exists or permissions are missing	Check uniqueness and administrator permissions
PAT creation returns an empty secret	Not logged in, incorrect owner, or empty scopes	Check the session, user ID, and scopes
PAT is invalid	Revoked, expired, or modified	Check the token metadata and reissue
Settings are lost	Missing write permissions	Check the path and service account

11. Acceptance Checklists

Server

- ☐ Appropriate database variant selected
- ☐ Database connection and migration successful
- ☐ HTTPS and WSS active with a valid certificate
- ☐ Ports and firewall documented
- ☐ Backup and recovery tested
- ☐ Log monitoring configured

Permission Model

- ☐ Unique product ID defined
- ☐ Permission IDs documented
- ☐ Roles modeled by tasks rather than individuals
- ☐ Groups created for recurring teams
- ☐ Personalized administrator accounts configured
- ☐ Negative tests performed for denied actions

LDAP

- ☐ Windows and domain prerequisites met
- ☐ First domain login tested
- ☐ SID and user data imported correctly
- ☐ Default role checked
- ☐ LDAP disabled if not required

PAT

- ☐ Least-privilege scopes assigned
- ☐ Expiration date set
- ☐ Secret stored only in the secret store
- ☐ Revocation tested
- ☐ Rotation and responsible person documented

12. Further Documentation

- [AuthClientSdk reference](#)
- [AuthServerSdk reference](#)
- [Dependencies](#)
- [Puma security policy](#)
- [Compact presentation](#)