# Index


IE Autospriter Interface	2
Closed form	
Step 1: Global Parameters (CHANGED)	2
Step 2: Shading Nodes	
Step 3: Camera	
Step 4: Animation	4
Weapon Collection(NEW)	5
Step 5: Final	5
Requirements	6
Helpful Insights(CHANGED)	7
Save file Cycles 4.0	9
Render Engine	9
Camera settings	10
Sun	10
Plane	11
Area	11
Save file EEVEE 4.0	11
Render Engine	11
Plane	12
Demo files 4.0	13
Shape	13
Shader Nodes	13
Bones	14
Troubleshooting/FAQ	15
RuntimeError - context is incorrect	15
OSError – incorrect directory	
"Save at" path empty, what happens?	17
How can time performance be increased?	17
Usage of GPU power	17
Alter sampling parameters	
Use Decimate Modifier	18
Change Render Engine	19

**Note:** The content of this manual may change and therefore may not be applicable to every version of IE AutoSpriter. I'm also not a professional Blender user or Blender add-on developer. I learn by doing.


# **IE Autospriter Interface**

This Blender add-on automates the process of rendering sprites specifically for Infinity Engine animations. The workflow is divided into logical steps to guide the user, though the sequence of the first four steps is flexible. Step 5 initiates the rendering process.

#### **Closed form**



**Step 1: Global Parameters (CHANGED)** 




This step defines general settings that apply across the entire sprite rendering process.

• **Save at:** Defines the directory where the generated sprite files will be saved.

 Prefix: A user-definable modder prefix that will be added to the beginning of the sprite file names

- **Resref (Resource Reference):** This is the freely definable part of the sprite file name. Other parts of the file names are fixed and automatically generated by the add-on.
- **Object List:** This must be the armature that contains the NLA tracks. The NLA tracks contain all the animations for the armature (essentially, your creature's animation).
- **Use Weapon Collection:** This activates the "Weapon Collections" section from "Step 4: Animation".
- **Resolution X:** This refers to the image width resolution
- Resolution Y: This refers to the image height resolution
- **Every X frame:** Saves every xth frame as a sprite. This can be useful, for example, when there are too many frames to save as sprites.


### **Step 2: Shading Nodes**



**This optional** step allows for the addition of specific shaders to the material shading setup. This is crucial for Infinity Engine sprites, which require indexed color palettes.

**Shader Node String Inputs:** These input fields are used to specify the names of existing shader nodes within the material. The new, automatically added shader nodes will be placed and connected between these specified nodes.


## Step 3: Camera



This step manages the output folders and defines which camera orientations will be rendered.

• **Orientation Folders:** These checkboxes determine whether sprites for a specific orientation will be rendered and saved into their corresponding designated folders. If a checkbox is not activated, sprites for that particular orientation will be ignored and not rendered.


### **Step 4: Animation**



This step defines which animations (Blender Actions) should be rendered and how they are named in the output.


- **Animation(Blender Action):** This refers to the type of animation, corresponding to an "Action" in Blender (e.g., "A1" for Attack Animation 1).
- **Checkbox:** If activated, the specified animation type (e.g., "A1") will be appended to the sprite file name.
- **String Input Field:** The name entered in this input field must precisely match the name of the corresponding Action in Blender.

#### Weapon Collection(NEW)



- **Creature Collection:** Specifies the name of the Blender collection containing the main creature model. This is an absolutely necessary input!
- **A, B, C, etc. (String inputs)**: Define the names of the Blender collections for each weapon type (e.g., "axe", "bow", "club"). The key names(A,B,C, etc.) are also used as wovl (weapon overlay) identifiers in filenames.
- **Use A, Use B, Use C, etc.**: Enable or disable rendering of sprites for each specific weapon collection.

### Step 5: Final



This is the concluding step that triggers the rendering process.

**Render:** Upon activation, this step initiates the rendering and saving of all sprites according to the settings configured in the preceding steps.

# Requirements


It is necessary that the animation is listed in the **Armature** within the **Animation** object. This means that under **Animation** the actions are collected in the **NLA Tracks** (see example in the image below).



The reason for this is that **IE AutoSpriter uses this list to sequentially specify actions (type of animation) to render**.

In addition, the names of the animation folders in **step 4** must exactly match the names found in the animation object (see **NLA Tracks**).

The blend file needs the following setup:




- **Camera**: This is needed to render the creature model.
- **Armature**: This has already been discussed.
- **Plane**: This is needed to create a shadow for the creature model.

• **Area**: This is a light source that should be adjusted as desired.

• **Sun**: This is needed to create a shadow on the **Plane**.


# **Helpful Insights(CHANGED)**

The different angles of the creature model are not created by moving the camera, but by rotating the model while the camera remains in a fixed position.




The objects in the collection have a number of specific important parameters that are not covered here, as the details can be found in the save files (these may be covered in later versions of IE AutoSpriter).

To view the rendering progress and elapsed time, go to "**Toggle System Console**" (see image below). This should be done **BEFORE** rendering, as rendering makes it impossible to interact with Blender.



After rendering, the creature's position is reset to the position before rendering started.




Each weapon to be rendered requires its own collection. This is (at the moment) only required for type E000. Everything else, such as area, camera, plane, and sun, can or should be outside of other subcollections. Depending on the lighting (sun), the weapon rendering may contain shadows of both the weapon and the creature. This shouldn't be a problem, since the creature and weapon shadows are merged when the BAM files are combined anyway, and since the weapon and creature shadows (must) be the same black color, the difference shouldn't be visible. This is only theoretical, as no tests have been conducted so far.

# Save file Cycles 4.0


Found in "IE-AutoSpriter-\save files\!\_Template\_CYCLES\_Blender\_4.0.blend"

## **Render Engine**





The rendering engine is set to Cycles (instead of EEVEE). This allows the "**Plane**" object to be rendered transparently without the "**Sun**" object losing its ability to cast shadows.

The render settings for the engine is as follows(see next image below):




## **Camera settings**






The camera settings can be adjusted to suit your personal preferences if needed. For example, the camera angle is set to 60°, although I've heard arguments for 45°. **After seeing someone else compare an image** of a custom character animation and an in-game animation at 45° and 60°, **I decided to go with 60**°. The rendering resolution is set to **256px to 256px**(px stands for pixels) and frame rate to **30fps**(frames per second).

#### Sun






These settings are optional but worked reasonably well (**lumens 10,000 and Z-distance 3m**), but will likely need to be adjusted depending on the model that needs to be rendered.

#### **Plane**

The object "**Plane**" is used to capture the shadow cast by sunlight on an object. To prevent the plane from being included in rendering without losing the shadow, the "**Transparent**" switch is enabled under "**Rend** → **Film**" checked(see screenshot above).



#### Area

The "Area" object is a purely optional light source. Its main purpose is to make the model's texture more visible.

## Save file EEVEE 4.0

Found in "IE-AutoSpriter-\save files\!\_Template\_CYCLES\_Blender\_4.0.blend"


### **Render Engine**




The rendering engine is set to Cycles (instead of EEVEE). This significantly <u>reduces rendering time</u> compared to Cycles. However, it also brings its own challenges for the "**Plane**".

#### **Plane**


The object "**Plane**" is used to capture the shadow cast by sunlight on an object. To make everything work, the layer has its own material and shading nodes within it (see image below).



Furthermore the render setting in section "**Film**" is also set as follows:



Another very important setting is the "**Blend Mode**" in the "**Settings**" section, which is selected as "**Alpha Blend**".



This was realized with the help of the following video: <u>How to make a shadow catcher in Blender 4.0 Cycles and Eevee by MK Graphics</u>.

### Demo files 4.0


Found in "IE-AutoSpriter-\demos\blend4.0\

- !\_Demo\_CYCLES\_Blender\_4.0.blend
- !\_Demo\_EEVEE\_Blender\_4.0.blend

It serves as a very simple example and is used for performance testing of IE AutoSpriter.

### **Shape**

The model is a simple cube (or cuboid, perhaps more accurately)




This doesn't mean the small one within the large one, but the large cuboid.

#### **Shader Nodes**

Here, too, the following shading nodes are activated (see next image below):


- Manually added "Cube Texture": This is a renamed "Image Texture" node and defines the
  color turquoise.
- "**Gradient Texture**": Creates the dark-to-light gradient.
- "Magic Texture": Creates the eye pattern on the surface.
- The "**Principled BSDF**" and "**Material Output**" nodes are created automatically when a new material is created for the cube object.
- The "**Brightness/Contrast**" and "**Mix Shader**" nodes are created connected in the optional step 2 of IE AutoSpriter. They contain selfdefined default values, which can also be seen in the next image below. It is used to prevent the model from containing the color black

(rgb(0,0,0)) because this special black is used for transparency in the animation by the Infiniyt Engine




#### **Bones**

The Armature contains only one bone(see image below). It is the the grey cuboid.



Checking the "**In Front**"checkbox sets it to always visible. And the shape is "**unusual**" because it is a B-bone (see image below).



# Troubleshooting/FAQ

#### RuntimeError - context is incorrect

If you are experiencing an error very similar to the following after pressing "RENDER":

```
Python: Traceback (most recent call last):
    File "C:\Users\<username>\AppData\Roaming\Blender Foundation\Blender\4.0\
    scripts\addons\ie_autospriter.py", line 246, in execute
        bpy.ops.object.select_all(action='DESELECT')
    File "<Drive letter>:\Blender 4.0\4.0\scripts\modules\bpy\ops.py", line 109,
in __call__
    ret = _op_call(self.idname_py(), kw)
RuntimeError: Operator bpy.ops.object.select_all.poll() failed, context is
incorrect
```

This can then be resolved by switching to the **Layout** or **Script** window. At this point, I'm not

entirely sure why the **Animation** window doesn't accept pressing the Render button in step 5, but **it seems to be related to the user's window context**.



### **OSError – incorrect directory**

This is actually **fixed and shouldn't happen anymore**. Please download the latest version!

If you are experiencing an error very similar to the following after pressing "RENDER":

Python: Traceback (most recent call last):

File "<Drive letter>:\Blender 4.0\4.0\python\lib\os.py", line 215, in makedirs

makedirs(head, exist\_ok=exist\_ok)

File "<Drive letter>:\Blender 4.0\4.0\python\lib\os.py", line 215, in makedirs

makedirs(head, exist\_ok=exist\_ok)

File "<Drive letter>:\Blender 4.0\4.0\python\lib\os.py", line 225, in makedirs

mkdir(name, mode)

OSError: [WinError 123] Die Syntax für den Dateinamen, Verzeichnisnamen oder die Datenträgerbezeichnung ist falsch: "\\\'

This may be due to the incorrect "Save at" path (see the next image below). This happens especially when the default directory is selected, which is available after pressing the folder icon.



This can be prevented by manually navigating from the local drive to the desired folder one by one, by typing the path manually or, which is quickest, by copying the path from your folder explorer and pasting it into IE AutoSpriter (see next image below).




# "Save at" path empty, what happens?

This saves the animation folders and their contents directly to the Blender project path. However, it's more human-readable to include this path in the "Save as" option.

### How can time performance be increased?


Testresults can be found here.

#### **Usage of GPU power**



This option can be found under  $Edit \rightarrow Preferences... \rightarrow System$ . However, the change  $\underline{didn't}$  result in any performance improvements on my PC.

# Alter sampling parameters



You can find this in the editor window under Render (camera icon)  $\rightarrow$  Sampling  $\rightarrow$  Render.


Increasing the "**Noise Threshold**" and reducing the "**Max. Samples**" should improve the time performance.

Further reducing the "**Max. Samples**" (e.g., to 256) should certainly be possible without any significant loss in sprite quality, but increasing the "**Noise Threshold**" may not be as effective. Users will have to test for themselves what works best for them.


#### **Use Decimate Modifier**

**This should only be considered as a last resort** as it will definitely reduce model quality. Decimate Modifier can be used as follows:


1. Choose your model in this particular case cube



2. Press "**Add Modifier**" and select Generate → Decimate




3. **Reducing Ratio** will improve performance time(see testexample)



## **Change Render Engine**

A blend save file and demo regarding EEVEE is available with the latest version.

Switching to EEVEE will significantly reduce rendering time, but this is not currently supported by the template save files that ship with IE AutoSpriter and may be added later in the development process.



Here is the specific IE AutoSpriter test result for EEVEE