This chapter describes the macros, functions, and methods used to read LOOPS objects from and print LOOPS objects to file storage, hash array storage, and the user display.

17.1	Reading Objects		
		This section	describes the functions to read LOOPS objects.
	Name	Туре	Description
	\$	NLambda Function	Returns a pointer to the object; does not evaluate its argument.
	\$!	Function	Returns a pointer to the object; evaluates its argument.
	\$C	NLambda Function	Gets the class record.
			ions use the Common Lisp form # , in the return display. This form ad-time evaluation and is briefly described here.
	Form	Description	
	#, <form></form>	Reads <for< td=""><td>m>, evaluates it, and returns that value.</td></for<>	m>, evaluates it, and returns that value.
	#,(\$& <form>)</form>	Form in which	ch instances appear if they are not prettyprinted.
	#,(\$C className)	Similar to #, already exis	(\$ className), except that it creates the class if it does not t.
(\$ name)			[NLambda Function]
	Purpose/Behavior:	evaluate na	pointer to the LOOPS object specified by <i>name</i> and does not <i>me</i> . If no object exists for <i>name</i> , NIL is returned. If * PRINT -set to T, the object will be prettyprinted in the Executive window.
	Arguments:	name	A LOOPS name.

Pointer to a LOOPS object or NIL; see Behavior.

In line 18, name is an instance. The value is returned and the **DEFINST** form is printed.

In line 19, name is a class whose class name is returned and printed.

In line 20, **NotAnObject** has not been declared as a LOOPS object and therefore returns NIL.

18 — (\$ Window1)

#, (\$& Window (NEW0.1Y%:.;h.eN6 . 495))

Returns:

Example:

19←(\$ Window) #,(\$C Window)

20←(\$ NotAnObject)

NIL

(**\$!** name) [Lambda Function]

> Purpose/Behavior: Returns a pointer to the LOOPS object specified by name where name is

evaluated. If no object exists for name, NIL is returned. If *PRINT-PRETTY*

is set to T, the object will be prettyprinted in the Executive window.

Evaluates to a valid LOOPS name. Arguments: name

Returns: Pointer to a LOOPS object or NIL; see Behavior.

(\$C name) [NLambda Function]

> Purpose: Allows forward references to classes.

> > Use (\$ name) instead of (\$C name).

Behavior: Varies according to the arguments.

If there is a class record for name, the function returns the class name.

If there is no class record for *name*, the function attempts to create the class. This differs from the behavior of (\$ name) which does not attempt any initialization if no LOOPS object is found.

Arguments: name A LOOPS name.

Returns: Value depends on the arguments; see Behavior.

Example: If name is not a LOOPS object, as shown in line 21, \$C defines and returns a

class for name, as shown in line 22. Line 23 shows the default class which is created in the Common Lisp Executive by \$C when no class is found for

name.

21←(\$ aCompletelyNewClass)

NIL

22←(\$C aCompletelyNewClass) #, (\$C aCompletelyNewClass)

 $23 \leftarrow (\leftarrow (\$C aCompletelyNewClass) PP)$

aCompletelyNewClass

(DEFCLASS aCompletelyNewClass (MetaClass Člass)

(Supers Tofu))

17.2 PRINT FLAGS

17.2 PRINT FLAGS

17.2 Print Flags

This section describes three variables that affect the way that objects are printed in LOOPS:

- ObjectDontPPFlag
- ObjectAlwaysPPFlag
- *PRINT-PRETTY*

All these variables have a default value of NIL.

The **ObjectDontPPFlag** and **ObjectDontPPFlag** variables affect how contained objects are printed and are used to override the ***PRINT-PRETTY***, which affects how the top-level objects are printed. (See the *Interlisp-D Reference Manual* for more information on the ***PRINT-PRETTY***.) These variables interact as follows:

- If ObjectDontPPFlag is NIL and *PRINT-PRETTY* is T, objects are prettyprinted.
- ObjectDontPPFlag is T overrides *PRINT-PRETTY* is T.
- ObjectAlwaysPPFlag is T overrides *PRINT-PRETTY* is NIL.

ObjectDontPPFlag [Variable]

Purpose/Behavior:

Used internally to prevent recursive printing of objects. If **ObjectDontPPFlag** is set to a non-NIL value, and **ObjectAlwaysPPFlag** is set to NIL, only the object name is printed. If this flag is NIL, all of the information contained within an instance is printed. The setting of this flag interacts with *PRINT-PRETTY* as shown in the examples below.

ObjectAlwaysPPFlag

[Variable]

Purpose/Behavior:

Controls printing the long form of all instances. When this variable is set to a non-NIL value, the long form of all instances are printed. This is the same form generated by (←obj PP). The ObjectAlwaysPPFlag overrides the effect of the ObjectDontPPFlag. Printing the long form of instances can lead to infinite loops or very long printouts. For example, if you have an object referencing another object which in turn references the first object, printing causes an infinite loop. If you have references to other LOOPS objects in the object you are printing, the long form of every object that can be reached from the top object is printed.

Example:

This example shows the interaction of all print flags.

```
23←(SETQ *PRINT-PRETTY* NIL)
NIL

24←(SETQ ObjectDontPPFlag NIL)
NIL

25←(← ($ Window) New 'Window2)
#,($& Window (NEW0.1Y%:.;h.eN6 . 502))

26←(← ($ Window2) Shape)
(47 145 99 89)

27←($ Window2)
#,($& Window (NEW0.1Y%:.;h.eN6 . 502))
```

Change the value of *PRINT-PRETTY* to T.

```
28←(SETQ *PRINT-PRETTY* T)
T
29←($ Window2)
(DEFINST (Window2 (NEW0.1Y%:.;h.eN6 . 502))
```

```
(left 47)
(bottom 145)
(width 99)
(height 89))
```

• Change the value of **ObjectDontPPFlag** to T.

```
30←(SETQ ObjectDontPPFlag T)
T
31←($ Window2)
#,($& Window (NEW0.1Y%:.;h.eN6 . 502))
```

· Assume the following commands have been entered:

```
(DefineClass 'PPTest)
(← ($ PPTest) AddIV 'testIV)
(← ($ PPTest) New 'PPTest1)
(← ($ PPTest) New 'PPTest2)
(←@ ($ PPTest1) testIV ($ PPTest2))
(←@ ($ PPTest2) testIV ($ PPTest1))
(SETQ *PRINT-PRETTY* T)
(SETQ ObjectDontPPFlag T)
(SETQ ObjectAlwaysPPFlag T)
```

· Print the instances.

```
53←($ PPTest1)
(DEFINST PPTest (PPTest1 (NEW0.1Y%:.;h.eN6 . 502))
```

• Reset the *PRINT-PRETTY* and print the instances again.

```
54←(SETQ *PRINT-PRETTY* NIL)
NIL

55←($ PPTest1)
#,($& PPTest (NEW0.1Y%:.;h.eN6 . 513))
```

17.3 PRINTING CLASSES

17.3 PRINTING CLASSES

17.3 Printing Classes

This section describes the methods used to print classes and information about classes.

Name	Туре	Description
FileOut	Method	Prints long pretty form of the class to a file or a display stream.
PP	Method	Prettyprints the class definition to a file or a display stream.
PP!	Method	Prints the information about the class from all levels of inheritance.
PPV!	Method	Prints the variable information about the class from all levels of inheritance.

 $(\leftarrow self \, FileOut \, file)$ [Method of Class]

Purpose: Prints the long pretty form of the class to a file or to display stream.

Behavior: Prints a **DEFCLASS** form for the class self. The **DEFCLASS** form, which is

the way classes are defined, always includes the name of the class, the

MetaClass, and the Supers. If there are ClassVariables and

InstanceVariables defined for the class, these along with their values are also included in the **DEFCLASS** form. **FileOut** formats the output with special fonts

and tab positions.

Arguments: self A class.

file The stream on which self is to be printed. If NIL, or not given,

prints to the TTYDisplayStream.

Returns: self

Categories: Classes

Specializations: Class, Method

Example: This example shows the **DEFCLASS** form for **TestClass**. If a **DEFCLASS**

form cannot be generated for self, a Break occurs with the message "var is

not defined as a class. Type OK to ignore this class and go on."

```
24←(← ($ TestClass) FileOut)
(DEFCLASS TestClass
    (MetaClass Class Edited%: (* --) )
    (Supers Object)
    (InstanceVariables (testIV 1234 testProp1 1 testProp2 2 doc (* --))))
```

(← self PP file) [Method of Class]

Purpose: Prettyprints LOOPS **OBJECT.CLASS.PP** to a file or to display stream.

Behavior: Prettyprints the class on *file*, if provided. If *file* is not given, look first to the

PPDefault, which is by default the Common Lisp Executive Window, and then to the **TTYDisplayStream**. The output is printed and formatted by the method

Class.FileOut.

Arguments: self A pointer to a class.

#,(\$C TestClass)

file Stream to prettyprint to.

Returns: Name of class.

Categories: Class
Specializes: Object

Example: This example shows a call to **PP** on the class **SupersBrowser**, which uses

the TTYDISPLAYSTREAM as the default output stream.

(InstanceVariables (title "Supers browser")))

SupersBrowser

 $(\leftarrow self \, \mathsf{PP}! \, file)$ [Method of Class]

Purpose: Prints the information about LOOPS **OBJECT.CLASS.PP** from all levels of

inheritance.

Behavior: Prints a listing of the following items along with any applicable documentation,

values and arguments for each item: MetaClass, Supers, Instance

Variables, Class Variables, Prototypes, and Methods.

Prints the information on *file*, if provided. If *file* is not given, look first to the **PPDefault**, which is by default the Common Lisp Executive Window, and then

to the TTYDisplayStream.

Arguments: self A pointer to a class.

file Stream to print to.

Returns: self

Categories: Classes

Specializes: Object

Example: This example shows a partial output of the call to **PP!** on the class

SupersBrowser which uses the TTYDISPLAYSTREAM as the default output

stream. The dots indicate additional information.

```
27←(← ($ SupersBrowser) PP!)
```

#,(\$ SupersBrowser)

MetaClass and its Properties

Class Edited: (* smL 11-Jun-86 13:18) doc Browses upwards from a class to all of its supers.

Supers

(ClassBrowser IndexedObject LatticeBrowser --)

Instance Variable Descriptions

left NIL doc left position of window

bottom NIL doc

bottom position of window

width 64 doc

outer width of window, including border

height 32 doc

outer height of window, including border

.

Class Variables

RightButtonItems ((Close (Close --)

)) Snap Paint --) doc

Items to be done if Right button is selected

.

Methods

AddCategoryMenu ClassBrowser.AddCategoryMenu

doc NIL args NIL

AddNewCV ClassBrowser.AddNewCV

doc NIL args NIL

```
doc NIL args NIL
                                AddNewMethod ClassBrowser.AddNewMethod
                              doc NIL args NIL
                              #,($C SupersBrowser)
(← self PPV! file)
                                                                                  [Method of Class]
                  Purpose:
                              Prints the variable information about the class from all levels of inheritance.
                  Behavior:
                              Similar to (← self PP! file), except that only the MetaClass, Supers list and
                              information about Class Variables and Instance Variables is printed.
                Arguments:
                              self
                                         A pointer to a class.
                              file
                                         Stream to print to.
                   Returns:
                              self
                 Categories:
                              Classes
                Specializes:
                              Object
                              This example shows a partial output of the call to PPV! on the class SupersBrowser which used the TTYDISPLAYSTREAM as the default output
                  Example:
                              stream. The dots indicate additional information.
                              28 \leftarrow (\leftarrow (\$ SupersBrowser) PP!)
                              #,($ SupersBrowser)
                              MetaClass and its Properties
                                Class Edited: (* smL 11-Jun-86 13:18) doc
                              Browses upwards from a class to all of its
                              supers.
                              Supers
                                 (ClassBrowser IndexedObject LatticeBrowser --)
                              Instance Variable Descriptions
                                left NIL doc left position of window
                                bottom NIL doc
                              bottom position of window
                                width 64 doc
                              outer width of window, including border
                                height 32 doc
                              outer height of window, including border
                              Class Variables
                                RightButtonItems ((Close (Close --)
                              )) Snap Paint --) doc
                              Items to be done if Right button is selected
                              #,($C SupersBrowser)
```

AddNewIV ClassBrowser.AddNewIV

17.4 PRINTING OBJECTS

17.4 PRINTING OBJECTS

17.4 Printing Objects

	This section	n describes the	methods for	printing	LOOPS	objects.
--	--------------	-----------------	-------------	----------	-------	----------

Name	Туре	Description
PrintOn	Method	Provides the default print function for LOOPS objects.
FileOut	Method	Prettyprints a LOOPS instance.
PP	Method	Prettyprints an object to a file or display stream.
PP!	Method	Prints all the information about the instance from all levels of inheritance.
PPV!	Method	Prints the variable information about the instance from all levels of inheritance.

 $(\leftarrow$ self **PrintOn** file) [Method of Object]

Purpose: Provides the default print function for LOOPS objects.

Behavior: Returns a form suitable for the Lisp function **DEFPRINT**, which produces the

standard LOOPS object print form #,(\$ objname). (See the Lisp Release Notes and the Interlisp-D Reference Manual for more information on

DEFPRINT.)

Arguments: self A LOOPS object.

file A stream to print to.

Returns: ("#," \$ ObjectName)

Categories: Object

Example: This example shows the results of calling **PrintOn** with the instance,

Window1.

 $28 \leftarrow (\leftarrow (\$ Window1) PrintOn)$

("#," \$ Window1)

 $(\leftarrow$ self **FileOut** file) [Method of Object]

Purpose: Prettyprints a LOOPS instance.

Behavior: If an object is found for self, this method prints the **DEFINST** form for the

object to the file. For a description of **FileOut** where self is a class, see

Section 17.3 "Printing Classes."

The **DEFINST** form always includes the name of the class to which the object belongs and the UID for the object. Names attached to the object and **InstanceVariables** bindings for the object are also included in the **DEFINST**

form. FileOut formats the output with special fonts and tab positions.

Arguments: self A LOOPS object.

file Stream to print to.

Returns: self

Categories: Instances

Example: This example shows the **DEFINST** forms for the object **Window1**.

29←(← (\$ Window1) FileOut)

```
(DEFINST Window (Window1 (
NEW0.1Y%:.;h.eN6 . 495))
        (left 288)
        (bottom 242)
        (width 331)
        (height 149))
#,($& Window (NEW0.1Y%:.;h.eN6 . 495))
```

 $(\leftarrow self \, \mathsf{PP} \, file)$ [Method of Object]

Purpose: Prettyprints an object to a file or display stream.

Behavior: Temporarily sets the **ObjectDontPPFlag** to prevent infinite loops in the print.

Prettyprints the output with special fonts and tab positions and prints the **DEFINST** form of the object. If *file* is not given, look first to the **PPDefault**, which is by default the Common Lisp Executive Window, and then to the

TTYDisplayStream.

Arguments: self A LOOPS object.

file Stream to print to.

Returns: Name of object.

Categories: Object Specializations: Class

Example: This example shows the results of sending the instance Window1 the

message **PP**.

```
30←(← ($ Window1) PP)
(DEFINST Window (Window1 (
NEW0.1Y%:.;h.eN6 . 495))
        (left 288)
        (bottom 242)
        (width 331)
        (height 149))
#,($& Window (NEW0.1Y%:.;h.eN6 . 495))
```

(← self **PP!** file) [Method of Object]

Purpose: Prints the information about the instance from all levels of inheritance.

Behavior: Prints a listing of the following items along with any applicable documentation,

values and arguments for the each item: Instance Variables, Class

Variables, and Methods.

If file is not given, look first to the **PPDefault**, which is by default the Common

Lisp Executive Window, and then to the TTYDisplayStream

Arguments: self A LOOPS object.

file Stream to print to.

Returns: self

Categories: Object

Specializations: Class

Example: This example shows a partial output of a call to **PP!** on the instance **Window1**.

Dots indicate additional information.

(← self PPV! file)

Purpose:

Behavior:

Arguments:

Returns:

Categories:

Example:

Specializations:

```
31 \leftarrow (\leftarrow (\$ Window1) PP!)
#,($ Window1)
Instance Variables
  left NIL doc left position of window
  bottom NIL doc
bottom position of window
  width 12 doc
outer width of window, including border
  height 12 doc
outer height of window, including border
Class Variables
  RightButtonItems ((Close (Close --)
)) Snap Paint --) doc
Items to be done if Right button is selected
Methods
  AfterMove Window. AfterMove doc NIL
args NIL
#,($& Window (NEW0.1Y%:.;h.eN6 . 495))
                                                 [Method of Object]
Prints the variable information about the instance from all levels of inheritance.
Similar to (← self PP! file) except that only the information about the Class
Variables and Instance Variables is printed.
           A LOOPS object.
self
file
           Stream to print to.
self
Object
Class
This example shows a partial output of a call to PPV! on the instance
LCDInstance. Dots indicate additional information.
31 \leftarrow (\leftarrow (\$ Window1) PPV!)
#,($ Window1)
Instance Variables
  left NIL doc left position of window
  bottom NIL doc
bottom position of window
  width 12 doc
outer width of window, including border
  height 12 doc
outer height of window, including border
```

```
Class Variables
RightButtonItems ((Close (Close (Close --)
)) Snap Paint --) doc
Items to be done if Right button is selected
.
.
.
#, ($& Window (NEW0.1Y%:.;h.eN6 . 495))
```

17.5 PRINTING ACTIVE VALUES

17.5 PRINTING ACTIVE VALUES

17.5 Printing Active Values

This section describes methods and variables used for printing active values. For more information on active values, see Chapter 8, Active Values.

(← self AVPrintSource)

[Method of ActiveValue]

Purpose: Constructs a form used by **DEFPRINT** to write active values to files.

Behavior: An annotated Value determines how it prints out by sending the

AVPrintSource message to its wrapped ActiveValue.

The default method in **ActiveValue** returns a list of the form:

("#,"\$AV className avNames(ivName value propName value ...)(ivName ...) ...)

which causes the annotated Value to print out as

#,(\$AV className avNames(ivName value propName value ...)(ivName ...) ...)

Arguments: self An ActiveValue

Returns: A form suitable for use by the Interlisp-D function **DEFPRINT**. Result should

be a pair of the form (item1 . item2); item1 will be printed using **PRIN1**, and item2 will be printed using **PRIN2** (see the *Lisp Release Notes* and the

Interlisp-D Reference Manual description of **DEFPRINT**).

In the return list,

className Name of the class of the ActiveValue.

avNames List of names of self; the last element being the unique identifier

(UID) of self

(ivName value propName value ...)

List that describes the state of the instance variables of the

ActiveValue.

Categories: Instances of the ActiveValue class

Example: The following command gets a pointer to an active value:

32←(GetValueOnly (\$ Window1) 'window) #,(\$AV LispWindowAV ((N^W0.1Y%:.;h.Lh9 . 503)) (localState

{WINDOW}#374,55554))

The following shows the result of an **AVPrintSource** message. (This is typically passed on to **DEFPRINT** within the internals of the system.)

33←(←(GetValueOnly (\$ Window1) 'window) AVPrintSource) ("#," \$AV LispWindowAV ((N^W0.1Y%:.;h.Lh9 . 503)) (localState {WINDOW}#374,55554))

DefaultActiveValueClassName

(Variable)

Purpose:

The class **ExplicitFnActiveValue** is the default class for active values. This class mimics the previous style of LOOPS active values (see Appendix A, Previous Active Values). For specialized applications, you may want a different class of active value to use for this purpose.

17.6 PRINTING METHODS

17.6 PRINTING METHODS

17.6 Printing Methods	1	7.6	Printing	Methods
-----------------------	---	-----	-----------------	----------------

This section describes the following methods used to print methods:

1	Name	Туре	Description	
ı	PPDefault	Variable	Identifies where the output for prettyprinting is sent.	
ı	PPMethod	Method	Prettyprints the method for a class.	
ı	MethodDoc	Method	Prints the documentation for the method for a class.	
ı	MethodSummary	Method	Prints a summary of the methods attached to a class.	
PPDefault				[Variable]

Purpose:

Bound to a window used as the default output stream for the methods **PPMethod**, **MethodDoc**, and **MethodSummary**. Initially set to the Common Lisp Executive Window.

(← self PPMethod selector)

[Method of Class]

Purpose:

Prettyprints the method specified by selector for the class self.

Behavior:

If selector is not specified, this opens a menu of the methods attached to the class self. The method, as chosen either from the menu or passed to the method in selector, is prettyprinted to the primary output stream. If self is not a class, a break occurs with the error,"(\leftarrow (\$ self) **PPMethod** selector) not

understood."

The output is sent to the value of the variable **PPDefault**, which is by default the Common Lisp Executive Window.

Arguments: self A LOOPS

selector

A LOOPS object.

Method to print.

Returns:

Class.Selector

Categories:

Classes

Example:

This example shows the results of prettyprinting the method **Shape** on the class **Window** using **PPMethod**.

```
35←(← ($ Window) PPMethod 'Shape)

(Method ((Window Shape) self newRegion noUpdateFlg) (* ...)

"Shapes outside of region to specified shape."

( self Shape1 [OR newRegion (GETREGION NIL NIL (WINDOWPROP (@ window) 'REGION]
```

with (Window Shape) bold.

noUpdateFlg))

(← self MethodDoc selector)

[Method of Class]

Purpose:

Prints the documentation for the method specified by *selector* for the class

self.

Behavior:

If selector is not specified, this opens a menu of all methods attached to the class from all levels of inheritance. When you choose an item, the

documentation for that method, the arguments needed, and the class defining the method are prettyprinted to the **PPDefault** window, which is by default the Common Lisp Executive Window. You can continue to make selections from

the menu or press a mouse button outside the menu to stop.

Arguments:

self A pointer to a class.

selector

Method to be printed.

Returns: NIL

1412

Categories:

Class

Example:

This example shows the output from calling **MethodDoc** for the class **LoopsIcon**. Three methods were chosen from the menu in succession: **AfterMove**, **BrowseObject**, and **Clear**. **BrowseObject** is attached to **Window** so the class where it is defined is not explicitly listed. **AfterMove** and **Clear** are defined, respectively, on the classes **NonRectangularWindow** and **Window**.

36←(← (\$ LoopsIcon) MethodDoc)

class: LoopsIcon (from NonRectangularWindow)

selector: AfterMove

args: NIL

doc: The window has been moved. Update the

left and bottom.

class: LoopsIcon selector:

BrowseObject args: NIL

doc: Put up a browser starting on selected

object.

class: LoopsIcon (from Window) selector:

Clear args: NIL

doc: Calls CLEARW on window.

(← self MethodSummary dontPrintFlg printFile)

[Method of Class]

Purpose: Prints a summary of the methods attached to the class self.

Behavior: Prettyprints the documentation from the classes directly attached to the class

self. Printing is done to the file printFile. If printFile is not specified,

MethodSummary prints to the **PPDefault** window, which is by default the Common Lisp Executive Window. If the **ObjectDontPPFIg** is T, the output is

not displayed in pretty format.

Arguments: self A pointer to a class.

dontPrintFlg

If non-NIL, does not prettyprint.

printFile File to print to.

Returns: NIL
Categories: Class

Example: This example shows the results of sending the message **MethodSummary** to

the class **IconWindow**. Only information about the methods defined at the

class IconWindow are printed.

17.7 UNIQUE IDENTIFIERS (UIDS)

17.7 UNIQUE IDENTIFIERS (UIDS)

17.7 Unique Identifiers (UIDs)

Unique Identifiers (UIDs) are used to store and retrieve objects. In general, objects do not have UIDs, with the following exceptions:

- When an object is named.
- · When an instance of an indexed object is created, it gets a UID.
- When an object is printed.

The following table shows the functions in this section.

Name	Type	Description
HasUID?	Function	Returns the UID for a specified object.
UID	Function	Returns the UID for a specified object and creates a UID for the object if one does not already exist.
GetObjFromUID	Function	Retrieves the LOOPS object records.
MapObjectUID	Function	Applies a function to every LOOPS object that has a UID.

(HasUID? obj) [Function]

Purpose: Returns the UID for obj.

Behavior: If the *obj* has a UID, the function returns the UID. If *obj* is an object but has no

UID, it returns NIL. If *obj* is not an object, it generates an error with the

message, "ARG NOT OBJECT."

Arguments: *obj* A LOOPS object.

Returns: The UID for obj.

Example: Line 39 shows the results of calling HasUID? for an instance Window1, line

40 for a class **Window**, and line 41 for a new instance of **Window**.

39←(HasUID? (\$ Window1)) (NEW0.1Y%:.;h.eN6 . 495) 40←(HasUID? (\$ Window)) (NEW0.1Y%:.;h.eN6 . 255) 41←(HasUID? (← (\$ Window) New)) NIL

11.7

(UID obj) [Function]

Purpose: Returns UID for obj. If object does not have UID, this function creates a UID

for the obj.

Behavior: If the object has a UID, this function returns the UID; otherwise it creates a

UID for the object.

Arguments: *obj* A LOOPS object.

Returns: The UID for obj.

Example: Line 45 shows the results of calling UID with the class **Object**. Line 46 shows

the results of calling UID with an instance which does not have a UID.

45←(UID (\$ Object)) (NEW0.1Y%:.;h.eN6 . 7) 46←(UID (← (\$ Window) New)) (NEW0.1Y%:.;h.eN6 . 519)

(GetObjFromUID uid)

[Function]

Purpose: Retrieves the LOOPS object records of object whose UID is *uid*.

Behavior: Returns the object associated with a UID, or returns NIL if uid is not a valid

UID.

Arguments: *uid* The internal identifier.

Returns: Pointer to the object.

Example: In this example, Window1UID was previously set to the UID for the instance

Window1. GetObjFromUID retrieves the record for Window1 using Window1UID and prettyprints the DEFINST form for Window1 to the

TTYDisplayStream.

42←(SETQ Window1UID (UID (\$ Window1] (NEW0.1Y%:.;h.eN6 . 495)
43←GetObjFromUID Window1UID)

#,(\$& Window (NEW0.1Y%:.;h.eN6 . 495)

(MapObjectUID fn) [Function]

Purpose: Applies the function *fn* to every LOOPS object.

Behavior: Maps the function *fn* to every UID object that has a UID.

Arguments: fn Function to be applied.

Returns: Used as a side effect only.

Example: This example:

This example shows a partial listing of the results of applying the user-defined function **PPUID** (see line 47) to every LOOPS object using **MapObjectUID**. **PPUID** prints the UID of *obj* to the **TTY** display stream. A complete output of this call to **MapObjectUID** lists the UID for every LOOPS object currently defined in the system.

```
45←(DEFINEQ (PPUID (LAMBDA (OBJ) (PRIN2 (UID OBJ)))))
(PPUID)

46←PP PPUID
FNS definition for PPUID:
(PPUID
[LAMBDA (OBJ) **COMMENT**
(PRIN2 (UID OBJ])

47←(MapObjectUID 'PPUID)
(NEW0.1Y%::;h.Lh9 . 526)(NEW0.1Y%::;h.Lh9 . 527)
(NEW0.1Y%::;h.Lh9 . 524)(NEW0.1Y%::;h.Lh9 . 525)
(NEW0.1Y%::;h.Lh9 . 522)(NEW0.1Y%::;h.Lh9 . 523)
.
.
.
.
.
.
. *<Hash-Table @ 66,72106>
```

[This page intentionally left blank]