#### Smart Pointers in C++

Aleksandra R. Glesaaen aleksandra@glesaaen.com

September 24th 2014

#### Literature

- [1] Boost c++ library.
  http://www.boost.org.
- [2] C++ reference.
  http://cppreference.com.
- [3] E. Gamma, R. Helm, R. Johnson, and J. Vlissides. Design Patterns: Elements of Reusable Object-Oriented Software. Pearson Education, 1994.
- [4] S. Meyers.
  More Effective C++: 35 New Ways to Improve Your Programs and Designs.
  Pearson Education, 1995.
- [5] S. Meyers.
  Effective C++: 55 Specific Ways to Improve Your Programs and Designs.
  Pearson Education, 2005.
- [6] H. Sutter. Gotw #89 solution: Smart pointers. http://herbsutter.com/2013/05/29/gotw-89-solution-smart-pointers/.

## What are smart pointers?

Objects designed to act like pointers, but provide extended functionality. Example of the proxy pattern [3].

```
MyClass * ptr = new MyClass();
ptr->Function();
delete ptr;
```

Smart pointers can manipulate three aspects of pointer behaviour:

- Construction
- Dereferencing
- Destruction

### Why use smart pointers?

Primarily to avoid memory leaks, which can come from a myriad of different sources;

```
Memory leak sources

MyClass * ptr = new MyClass();
//... (1)
ptr->Function(); //(2)
//...
delete ptr; //(3)
```

- 1. Might have multiple return paths
- 2. Might throw an exception
- 3. One might simply forget to free the resource

## Why use smart pointers?

Primarily to avoid memory leaks, which can come from a myriad of different sources;

```
Memory leak sources

MyClass * ptr = new MyClass();
//... (1)
ptr->Function(); //(2)
//...
delete ptr; //(3)
```

- 1. Might have multiple return paths
- 2. Might throw an exception
- 3. One might simply forget to free the resource

Solution: Wrap the resource in a class which frees it on destruction.

## Types of smart pointers

Smart pointers where one object singularly owns a resource  $% \left( 1\right) =\left( 1\right) \left( 1\right) \left$ 

Smart pointers where the resource is shared by multiple objects.

Shared smart pointers utilising the *copy-on-write* technique.

## Smart pointer implementations

All following smart pointers do "garbage collection", but they differ in how they are assigned:

std	boost	Qt
std::unique_ptr		
std::shared_ptr	boost::shared_ptr	QSharedPointer
std::weak_ptr	boost::weak_ptr	QWeakPointer
std::auto_ptr	boost::scoped_ptr	QScopedPointer

# Example: std::unique\_ptr

```
MyClass * CreateObject()
 std::unique_ptr < MyClass > new_object(new MyClass());
 //...
 };
int main()
 std::unique_ptr < MyClass > p1( CreateObject() );
 std::unique_ptr < MyClass > p2 = CreateObject(); - Compilation error!
 //...
 std::unique_ptr <MyClass > q1 = p1; ← Compilation error!
 std::unique_ptr < MyClass > q2 = std::move(p1); ← OK!
 //...
```

# Example: std::shared\_ptr and std::weak\_ptr

```
std::shared_ptr < MyClass > p1 (new MyClass());
std::shared_ptr < MyClass > p2 = p1;
  std::shared_ptr < MyClass > p3 = p2;
  std::weak_ptr < MyClass > wp = p2;
  if(auto p = wp.lock()) {
  // ...
// ...
```


# Example: std::shared\_ptr and std::weak\_ptr

```
std::shared_ptr<MyClass> p1(new MyClass()); ← use count: 1
if(auto p = wp.lock()) {
// ... ←
                use count: 4
                 — use count: 2
```

# Example: std::shared\_ptr and std::weak\_ptr

```
std::weak_ptr<MyClass> wp;
  std::shared_ptr < MyClass > sp =
        std::make_shared < MyClass > ();
  wp = sp;
  if(auto wsp = wp.lock()) {
  // ...
if(wp.expired()) {
 // Managed resource has been deleted
```

std::unique\_ptr symbolises owning a resource.




The resource can be shared through references or raw pointers

std::unique\_ptr symbolises owning a resource.




The resource can be shared through references or raw pointers

std::shared\_ptr on the other hand symbolises sharing a
resource with other objects.




The resource can still be shared through pointers and references, but also using the std::shared\_ptr copy constructor and copy assignment operator.

std::shared\_ptr on the other hand symbolises sharing a
resource with other objects.



The resource can still be shared through pointers and references, but also using the std::shared\_ptr copy constructor and copy assignment operator.

std::shared\_ptr on the other hand symbolises sharing a
resource with other objects.



The resource can still be shared through pointers and references, but also using the std::shared\_ptr copy constructor and copy assignment operator.

## Example: Abstract Factory 1

```
class ShapeFactory
  Shape * CreateShape() = 0;
};
class CircleFactory : public ShapeFactory
  Shape * CreateShape()
    std::unique_ptr < Shape > shape_ptr(new Circle());
                      The pointer will be deleted if
                      something happens in between
    return shape_ptr.release();
 };
};
```

Hope that whoever takes ownership over the newly created Shape object manages it properly.

### Example: Abstract Factory 2

```
class ShapeFactory
 std::unique_ptr <Shape > CreateShape() = 0;
};
class CircleFactory : public ShapeFactory
 std::unique_ptr <Shape > CreateShape()
   std::unique ptr <Shape > shape ptr(new Circle());
   // ...
   };
};
```

The new owner of the Shape object is forced to manage its memory properly.

#### Problems with explicit new's: #1

Consider creating a std::shared\_ptr with a new statement

```
Naïve construction

std::shared_ptr<MyClass> ptr(new MyClass());

pass pointer
```



The constructors are called separately and the compiler cannot optimise memory location.

#### Problems with explicit new's: #2

```
void ProcessObject(std::shared_ptr<MyClass> obj,
                      int process_id);
ProcessObject(std::shared_ptr < MyClass > (new MyClass()),
                GetProcessID());
                      MyClass
                                                GetProcessID()
                    constructor
        std::shared_ptr
                                                   MyClass
                            GetProcessID()
                                                  constructor
           constructor
                                     std::shared_ptr
        GetProcessID()
                                        constructor
```

#### Problems with explicit new's: #2

```
void ProcessObject(std::shared_ptr<MyClass> obj,
                      int process_id);
ProcessObject(std::shared_ptr < MyClass > (new MyClass()),
                GetProcessID());
                      MyClass
                                                GetProcessID()
                    constructor
        std::shared_ptr
                                                   MyClass
                            GetProcessID()
                                                  constructor
           constructor
                                     std::shared_ptr
        GetProcessID()
                                        constructor
```

Create using std::make\_unique and std::make\_shared

Both these problems can be remedied by using std::make\_shared and std::make\_unique (C++14).

Constructor calls cannot be intertwined with the GetProcessID()
anymore.

Create using std::make\_unique and std::make\_shared

#### Guideline

Don't use explicit new, delete, and owning \* pointers, except in rare cases encapsulated inside the implementation of a low-level data structure.

Herb Sutter [6]

#### Match constructors with destructors

Smart pointers have a control block which also keeps track of an allocator and a deleter

```
std::shared_ptr constructor

template <class Type, class Deleter, class Alloc>
std::shared_ptr(Type * p, Deleter d, Alloc a);
```

Very important that the deleter doesn't throw.

## Passing smart pointers

There are many options for passing smart pointers to functions (and classes).

```
Passing smart pointers

void foo(MyClass *);
void foo(MyClass &);
void foo(std::unique_ptr<MyClass>);
void foo(std::unique_ptr<MyClass> &);
void foo(std::shared_ptr<MyClass>);
void foo(std::shared_ptr<MyClass> &);
```


All of these has a distinct meaning, use them to express yourself.

Using smart pointers and polymorphic classes as template arguments works as expected because one of the smart pointer constructors read:

```
template < class T, class U>
std::shared_ptr < T > (const std::shared_ptr < U > &)
```

This costructor can be used to convert between std::shared\_ptr's if U\* is implicitly convertible to T\*.

Assume we have a class hierarchy:



Where Derived overloads the print() function but not the const variant.

```
std::shared_ptr<Derived> d_ptr =
    std::make_shared<Derived>();

std::shared_ptr<Base> b_ptr = d_ptr;
std::shared_ptr<const Base> b_const_ptr = d_ptr;

std::shared_ptr<Derived> d_err_ptr = b_ptr; \top Compilation error
std::shared_ptr<Base> b_err_ptr = b_const_ptr; \top Compilation error
b_ptr->print(); \top Calls Derived::print()
b_const_ptr->print(); \top Calls Base::print()const

//use count: 3
```

```
std::shared ptr < Derived > d ptr =
  std::make shared < Derived > ():
std::shared_ptr <Base> b_ptr = d_ptr;
std::shared_ptr<const Base> b_const_ptr = d_ptr;
std::shared ptr <Derived > d new ptr =
  std::dynamic_pointer_cast < Derived > (b_ptr); \leftarrow OK!
std::shared_ptr <Base> b_new_ptr =
  std::const_pointer_cast <Base > (b_const_ptr); ← OK!
d_new_ptr -> sum(); 		 Calls Derived::sum()
b new ptr→print(); ← Calls Derived::print()
//use count: 5
```

# Smart pointers and the STL

- Smart pointers can be stored in the STL containers.
- However, not all algorithms work with the resulting containers.
  - E.g. std::unique\_ptr is MoveConstructible and MoveAssignable
  - ▶ But not CopyConstructable or CopyAssignable

Thus if an algorithm requires CopyConstructability and a std::unique\_ptr is given, it should fail to compile.

std::auto\_ptr on the other hand is a bit more unreliable.

# The boost pointer container library

Library inteded to provide a STL-like library for single ownership pointers.

#### Advantages

- Simplifies the container-of-pointer syntax.
- Notational convenience
  - Dereferencing an iterator returns a dereferenced pointer
- ► Introduces "Clonability" to do deep copies.
- Faster and has a small memory overhead.

#### Disadvantages

- Not very compatible with the algorithm library
- Not as flexible as a container of smart pointers

#### Summary

- ► Use smart pointers to manage dynamic resources so that they are freed when they aren't used anymore.
  - Use std::unique\_ptr to signal singular ownership
  - Use std::shared\_ptr to signal shared ownership
  - Use std::weak\_ptr to signal uncommitted shared ownership
- Avoid using explicit new and delete statements, and explicit ownership of raw pointers.