

Set up Astra Control Center

Astra Control Center

NetApp March 21, 2022

This PDF was generated from https://docs.netapp.com/us-en/astra-control-center/get-started/add-cluster-reqs.html on March 21, 2022. Always check docs.netapp.com for the latest.

Table of Contents

t up Astra Control Center	1
Add a license for Astra Control Center	1
Add cluster	2
Add a storage backend	3
Add a bucket	4
What's next?	5
Prerequisites for adding a cluster	6
Add a custom TLS certificate	11

Set up Astra Control Center

Astra Control Center supports and monitors ONTAP and Astra Data Store as the storage backend. After you install Astra Control Center, log in to the UI, and change your password, you'll want to set up a license, add clusters, manage storage, and add buckets.

Tasks

- · Add a license for Astra Control Center
- Add cluster
- · Add a storage backend
- · Add a bucket

Add a license for Astra Control Center

You can add a new license using the UI or API to gain full Astra Control Center functionality. Without a license, your usage of Astra Control Center is limited to managing users and adding new clusters.

What you'll need

When you downloaded Astra Control Center from the NetApp Support Site, you also downloaded the NetApp license file (NLF). Ensure you have access to this license file.



To update an existing evaluation or full license, see Update an existing license.

Add a full or evaluation license

Astra Control Center licenses measure CPU resources using Kubernetes CPU units. The license needs to account for the CPU resources assigned to the worker nodes of all the managed Kubernetes clusters. Before you add a license, you need to obtain the license file (NLF) from the NetApp Support Site.

You can also try Astra Control Center with an evaluation license, which lets you use Astra Control Center for 90 days from the date you download the license. You can sign up for a free trial by registering here.



If your installation grows to exceed the licensed number of CPU units, Astra Control Center prevents you from managing new applications. An alert is displayed when capacity is exceeded.

Steps

- 1. Log in to the Astra Control Center UI.
- 2. Select Account > License.
- Select Add License.
- 4. Browse to the license file (NLF) that you downloaded.
- Select Add License.

The **Account > License** page displays the license information, expiration date, license serial number, account ID, and CPU units used.



If you have an evaluation license, be sure you store your account ID to avoid data loss in the event of Astra Control Center failure if you are not sending ASUPs.

Add cluster

To begin managing your apps, add a Kubernetes cluster and manage it as a compute resource. You have to add a cluster for Astra Control Center to discover your Kubernetes applications. For Astra Data Store preview, you want to add the Kubernetes app cluster that contains applications that are using volumes provisioned by Astra Data Store preview.



We recommend that Astra Control Center manage the cluster it is deployed on first before you add other clusters to Astra Control Center to manage. Having the initial cluster under management is necessary to send Kubemetrics data and cluster-associated data for metrics and troubleshooting. You can use the **Add Cluster** feature to manage a cluster with Astra Control Center.

When Astra Control manages a cluster, it keeps track of the cluster's default StorageClass. If you change the StorageClass using kubectl commands, Astra Control reverts the change. To change the default StorageClass in a cluster managed by Astra Control, use one of the following methods:



- Use the Astra Control API PUT /managedClusters endpoint, and assign a different default StorageClass with the DefaultStorageClass parameter
- Remove the cluster from Astra Control management and re-add it with a different default StorageClass selected



What you'll need


Before you add a cluster, review and perform the necessary prerequisite tasks.

Steps

- 1. From the **Dashboard** in the Astra Control Center UI, select **Add** in the Clusters section.
- 2. In the Add Cluster window that opens, upload a kubeconfig.yaml file or paste the contents of a kubeconfig.yaml file.



The kubeconfig.yaml file should include only the cluster credential for one cluster.






If you create your own kubeconfig file, you should define only one context element in it. See Kubernetes documentation for information about creating kubeconfig files.

- 3. Provide a credential name. By default, the credential name is auto-populated as the name of the cluster.
- 4. Select Configure storage.
- 5. Select the storage class to be used for this Kubernetes cluster, and select Review.



You should select a Trident storage class backed by ONTAP storage or Astra Data Store.



Review the information, and if everything looks good, select Add cluster.

Result

The cluster enters the **Discovering** status and then changes to **Running**. You have successfully added a Kubernetes cluster and are now managing it in Astra Control Center.



After you add a cluster to be managed in Astra Control Center, it might take a few minutes to deploy the monitoring operator. Until then, the Notification icon turns red and logs a **Monitoring Agent Status Check Failed** event. You can ignore this, because the issue resolves when Astra Control Center obtains the correct status. If the issue does not resolve in a few minutes, go to the cluster, and run oc get pods -n netapp-monitoring as the starting point. You will need to look into the monitoring operator logs to debug the problem.

Add a storage backend

You can add a storage backend so that Astra Control can manage its resources. Managing storage clusters in Astra Control as a storage backend enables you to get linkages between persistent volumes (PVs) and the storage backend as well as additional storage metrics.

You can add a discovered storage backend by navigating prompts from the Dashboard or the Backends menu.

What you'll need

You have added a cluster and it is managed by Astra Control.



The managed cluster has a supported backend attached to it that can be discovered by Astra Control.

• For Astra Data Store preview installations: You have added your Kubernetes app cluster.



After you add your Kubernetes app cluster for Astra Data Store, the cluster appears as unmanaged in the list of discovered backends. You must next add the compute cluster that contains Astra Data Store and underlies the Kubernetes app cluster. You can do this from **Backends** in the UI. Select the Actions menu for the cluster, select Manage, and add the cluster. After the cluster state of unmanaged changes to the name of the Kubernetes cluster, you can proceed with adding a backend.

Steps

- 1. Do one of the following:
 - From Dashboard:
 - a. From the Dashboard Storage backend section, select Manage.
 - b. From the Dashboard Resource Summary > Storage backends section, select Add.
 - From Backends:
 - a. In the left navigation area, select **Backends**.
 - b. Select Manage.
- 2. Do one of the following depending on your backend type:
 - Astra Data Store:
 - i. Select the **Astra Data Store** tab.
 - ii. Select the managed compute cluster and select Next.
 - iii. Confirm the backend details and select **Manage storage backend**.
 - ONTAP:
 - i. Enter the ONTAP admin credentials and select Review.
 - ii. Confirm the backend details and select Manage.

The backend appears in available state in the list with summary information.



You might need to refresh the page for the backend to appear.

Add a bucket

Adding object store bucket providers is essential if you want to back up your applications and persistent storage or if you want to clone applications across clusters. Astra Control stores those backups or clones in the object store buckets that you define.

When you add a bucket, Astra Control marks one bucket as the default bucket indicator. The first bucket that you create becomes the default bucket.

You don't need a bucket if you are cloning your application configuration and persistent storage to the same cluster.

Use any of the following bucket types:

- NetApp ONTAP S3
- NetApp StorageGRID S3

Generic S3



Although Astra Control Center supports Amazon S3 as a Generic S3 bucket provider, Astra Control Center might not support all object store vendors that claim Amazon's S3 support.

For instructions on how to add buckets using the Astra Control API, see Astra Automation and API information.

Steps

- 1. In the left navigation area, select Buckets.
 - a. Select Add.
 - b. Select the bucket type.



When you add a bucket, select the correct bucket provider and provide the right credentials for that provider. For example, the UI accepts NetApp ONTAP S3 as the type and accepts StorageGRID credentials; however, this will cause all future app backups and restores using this bucket to fail.

c. Create a new bucket name or enter an existing bucket name and optional description.



The bucket name and description appear as a backup location that you can choose later when you're creating a backup. The name also appears during protection policy configuration.

- d. Enter the name or IP address of the S3 endpoint.
- e. If you want this bucket to be the default bucket for all backups, check the Make this bucket the default bucket for this private cloud option.



This option does not appear for the first bucket you create.

f. Continue by adding credential information.

Add S3 access credentials

Add S3 access credentials at any time.

Steps

- 1. From the Buckets dialog, select either the **Add** or **Use existing** tab.
 - a. Enter a name for the credential that distinguishes it from other credentials in Astra Control.
 - b. Enter the access ID and secret key by pasting the contents from your clipboard.

What's next?

Now that you've logged in and added clusters to Astra Control Center, you're ready to start using Astra Control Center's application data management features.

- Manage users
- Start managing apps
- Protect apps

- Clone apps
- · Manage notifications
- Connect to Cloud Insights
- · Add a custom TLS certificate

Find more information

- Use the Astra Control API
- Known issues

Prerequisites for adding a cluster

You should ensure that the prerequisite conditions are met before you add a cluster. You should also run the eligibility checks to ensure that your cluster is ready to be added to Astra Control Center.

What you'll need before you add a cluster

- One of the following types of clusters:
 - Clusters running OpenShift 4.6, 4.7, or 4.8, which has Astra Trident StorageClasses backed by Astra Data Store or ONTAP 9.5 or later
 - Clusters running Rancher 2.5
 - Clusters running Kubernetes 1.19 to 1.21 (including 1.21.x)

Make sure your clusters have one or more worker nodes with at least 1GB RAM available for running telemetry services.



If you plan to add a second OpenShift 4.6, 4.7, or 4.8 cluster as a managed compute resource, you should ensure that the Astra Trident Volume Snapshot feature is enabled. See the official Astra Trident instructions to enable and test Volume Snapshots with Astra Trident.

- An Astra Trident volumesnapshotclass object that has been defined by an administrator. See the Astra Trident instructions to enable and test Volume Snapshots with Astra Trident.
- Ensure that you have only a single default storage class defined for your Kubernetes cluster.

Run eligibility checks

Run the following eligibility checks to ensure that your cluster is ready to be added to Astra Control Center.

Steps

1. Check the Trident version.

```
kubectl get tridentversions -n trident
```

If Trident exists, you see output similar to the following:

NAME VERSION trident 21.04.0

If Trident does not exist, you see output similar to the following:

error: the server doesn't have a resource type "tridentversions"



If Trident is not installed or the installed version is not the latest, you need to install the latest version of Trident before proceeding. See the Trident documentation for instructions.

2. Check if the storage classes are using the supported Trident drivers. The provisioner name should be csi.trident.netapp.io. See the following example:

kubectl get sc

NAME PROVISIONER RECLAIMPOLICY

VOLUMEBINDINGMODE ALLOWVOLUMEEXPANSION AGE

ontap-gold (default) csi.trident.netapp.io Delete

Immediate true 5d23h

thin kubernetes.io/vsphere-volume Delete

Immediate false 6d

Create an admin-role kubeconfig

Ensure that you have the following on your machine before you do the steps:

- kubectl v1.19 or later installed
- An active kubeconfig with cluster admin rights for the active context

Steps

- 1. Create a service account as follows:
 - a. Create a service account file called astracontrol-service-account.yaml.

Adjust the name and namespace as needed. If changes are made here, you should apply the same changes in the following steps.

astracontrol-service-account.yaml

```
apiVersion: v1
kind: ServiceAccount
metadata:
  name: astracontrol-service-account
  namespace: default
```

b. Apply the service account:

```
kubectl apply -f astracontrol-service-account.yaml
```

- 2. Grant cluster admin permissions as follows:
 - a. Create a ClusterRoleBinding file called astracontrol-clusterrolebinding.yaml.

Adjust any names and namespaces modified when creating the service account as needed.

```
<strong>astracontrol-clusterrolebinding.yaml</strong>
```

```
apiVersion: rbac.authorization.k8s.io/v1
kind: ClusterRoleBinding
metadata:
   name: astracontrol-admin
roleRef:
   apiGroup: rbac.authorization.k8s.io
   kind: ClusterRole
   name: cluster-admin
subjects:
   - kind: ServiceAccount
   name: astracontrol-service-account
   namespace: default
```

b. Apply the cluster role binding:

```
kubectl apply -f astracontrol-clusterrolebinding.yaml
```

3. List the service account secrets, replacing <context> with the correct context for your installation:

```
kubectl get serviceaccount astracontrol-service-account --context
<context> --namespace default -o json
```

The end of the output should look similar to the following:

```
"secrets": [
{ "name": "astracontrol-service-account-dockercfg-vhz87"},
{ "name": "astracontrol-service-account-token-r59kr"}
]
```

The indices for each element in the secrets array begin with 0. In the above example, the index for astracontrol-service-account-dockercfg-vhz87 would be 0 and the index for astracontrol-service-account-token-r59kr would be 1. In your output, make note of the index for the service account name that has the word "token" in it.

- 4. Generate the kubeconfig as follows:
 - a. Create a create-kubeconfig.sh file. Replace TOKEN_INDEX in the beginning of the following script with the correct value.

```
<strong>create-kubeconfig.sh</strong>
```

```
# Update these to match your environment.
# Replace TOKEN INDEX with the correct value
# from the output in the previous step. If you
# didn't change anything else above, don't change
# anything else here.
SERVICE ACCOUNT NAME=astracontrol-service-account
NAMESPACE=default
NEW CONTEXT=astracontrol
KUBECONFIG FILE='kubeconfig-sa'
CONTEXT=$(kubectl config current-context)
SECRET NAME=$(kubectl get serviceaccount ${SERVICE ACCOUNT NAME} \
 --context ${CONTEXT} \
  --namespace ${NAMESPACE} \
  -o jsonpath='{.secrets[TOKEN INDEX].name}')
TOKEN DATA=$(kubectl get secret ${SECRET NAME} \
  --context ${CONTEXT} \
 --namespace ${NAMESPACE} \
 -o jsonpath='{.data.token}')
TOKEN=$(echo ${TOKEN DATA} | base64 -d)
# Create dedicated kubeconfig
# Create a full copy
kubectl config view --raw > ${KUBECONFIG FILE}.full.tmp
```

```
# Switch working context to correct context
kubectl --kubeconfig ${KUBECONFIG FILE}.full.tmp config use-context
${CONTEXT}
# Minify
kubectl --kubeconfig ${KUBECONFIG FILE}.full.tmp \
  config view --flatten --minify > ${KUBECONFIG FILE}.tmp
# Rename context
kubectl config --kubeconfig ${KUBECONFIG FILE}.tmp \
  rename-context ${CONTEXT} ${NEW CONTEXT}
# Create token user
kubectl config --kubeconfig ${KUBECONFIG FILE}.tmp \
  set-credentials ${CONTEXT}-${NAMESPACE}-token-user \
  --token ${TOKEN}
# Set context to use token user
kubectl config --kubeconfig ${KUBECONFIG FILE}.tmp \
  set-context ${NEW CONTEXT} --user ${CONTEXT}-${NAMESPACE}-token-
user
# Set context to correct namespace
kubectl config --kubeconfig ${KUBECONFIG FILE}.tmp \
  set-context ${NEW CONTEXT} --namespace ${NAMESPACE}
# Flatten/minify kubeconfig
kubectl config --kubeconfig ${KUBECONFIG FILE}.tmp \
  view --flatten --minify > ${KUBECONFIG FILE}
# Remove tmp
rm ${KUBECONFIG FILE}.full.tmp
rm ${KUBECONFIG FILE}.tmp
```

b. Source the commands to apply them to your Kubernetes cluster.

```
source create-kubeconfig.sh
```

5. (Optional) Rename the kubeconfig to a meaningful name for your cluster. Protect your cluster credential.

```
chmod 700 create-kubeconfig.sh
mv kubeconfig-sa.txt YOUR_CLUSTER_NAME_kubeconfig
```

What's next?

Now that you've verified that the prerequisites are met, you're ready to add a cluster.

Find more information

- Trident documentation
- Use the Astra Control API

Add a custom TLS certificate

You can remove the existing self-signed TLS certificate and replace it with a TLS certificate signed by a Certificate Authority (CA).

What you'll need

- Kubernetes cluster with Astra Control Center installed
- Administrative access to a command shell on the cluster to run kubectl commands
- Private key and certificate files from the CA

Remove the self-signed certificate

- 1. Using SSH, log in to the Kubernetes cluster that hosts Astra Control Center as an administrative user.
- 2. Find the TLS secret associated with the current certificate using the following command, replacing <ACCdeployment-namespace> with the Astra Control Center deployment namespace:

```
kubectl get certificate -n <ACC-deployment-namespace>
```

3. Delete the currently installed secret and certificate using the following commands:

```
kubectl delete cert cert-manager-certificates -n <ACC-deployment-
namespace>
kubectl delete secret secure-testing-cert -n <ACC-deployment-namespace>
```

Add a new certificate

1. Use the following command to create the new TLS secret with the private key and certificate files from the CA, replacing the arguments in brackets <> with the appropriate information:

```
kubectl create secret tls <secret-name> --key <private-key-filename>
--cert <certificate-filename> -n <ACC-deployment-namespace>
```

2. Use the following command and example to edit the cluster Custom Resource Definition (CRD) file and change the <code>spec.selfSigned</code> value to <code>spec.ca.secretName</code> to refer to the TLS secret you created earlier:

```
kubectl edit clusterissuers.cert-manager.io/cert-manager-certificates -n
<ACC-deployment-namespace>
....
#spec:
# selfSigned: {}

spec:
ca:
secretName: <secret-name>
```

3. Use the following command and example output to validate that the changes are correct and the cluster is ready to validate certificates, replacing ACC-deployment-namespace with the Astra Control Center deployment namespace:

```
kubectl describe clusterissuers.cert-manager.io/cert-manager-
certificates -n <ACC-deployment-namespace>
. . . .
Status:
  Conditions:
    Last Transition Time: 2021-07-01T23:50:27Z
    Message:
                            Signing CA verified
                           KeyPairVerified
    Reason:
    Status:
                            True
    Type:
                            Ready
Events:
                            <none>
```

4. Create the certificate.yaml file using the following example, replacing the placeholder values in brackets <> with appropriate information:

```
apiVersion: cert-manager.io/v1
kind: Certificate
metadata:
   name: <certificate-name>
   namespace: <ACC-deployment-namespace>
spec:
   secretName: <certificate-secret-name>
   duration: 2160h # 90d
   renewBefore: 360h # 15d
   dnsNames:
   - <astra.dnsname.example.com> #Replace with the correct Astra Control
Center DNS address
   issuerRef:
     kind: ClusterIssuer
     name: cert-manager-certificates
```

5. Create the certificate using the following command:

```
kubectl apply -f certificate.yaml
```

6. Using the following command and example output, validate that the certificate has been created correctly and with the arguments you specified during creation (such as name, duration, renewal deadline, and DNS names).

```
kubectl describe certificate -n <ACC-deployment-namespace>
. . . .
Spec:
  Dns Names:
    astra.example.com
  Duration: 125h0m0s
  Issuer Ref:
    Kind:
               ClusterIssuer
    Name:
               cert-manager-certificates
  Renew Before: 61h0m0s
  Secret Name: <certificate-secret-name>
Status:
  Conditions:
    Last Transition Time: 2021-07-02T00:45:41Z
                           Certificate is up to date and has not expired
    Message:
    Reason:
                           Ready
    Status:
                           True
    Type:
                           Ready
  Not After:
                           2021-07-07T05:45:41Z
  Not Before:
                           2021-07-02T00:45:41Z
  Renewal Time:
                           2021-07-04T16:45:41Z
  Revision:
Events:
                           <none>
```

7. Edit the ingress CRD TLS option to point to your new certificate secret using the following command and example, replacing the placeholder values in brackets <> with appropriate information:

```
kubectl edit ingressroutes.traefik.containo.us -n <ACC-deployment-
namespace>
. . . .
# tls:
   options:
     name: default
   secretName: secure-testing-cert
#
   store:
     name: default
tls:
   options:
     name: default
   secretName: <certificate-secret-name>
   store:
     name: default
```

- 8. Using a web browser, browse to the deployment IP address of Astra Control Center.
- 9. Verify that the certificate details match the details of the certificate you installed.
- 10. Export the certificate and import the result into the certificate manager in your web browser.

Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.