

Arquitetura de Redes

LABORATORY GUIDE


Objectives

- Deployment of a DHCP server
- Deployment of a DNS server

DHCP

1. Construct the network below, using as DHCP server a Debian server. Configure all static IPv4 addresses (Servers, Router and SWL3 interfaces) and deploy a routing mechanism. <u>Test full connectivity between devices before proceeding.</u>

Important: A wrongly (or forgotten) active DHCP server in a network can create severe connection issues to users. After this guide, disable or uninstall the DHCP server.



2. At the DHCP server, install package isc-dhcp-server: apt-get install isc-dhcp-server

Edit file /etc/default/isc-dhcp-server to define the interfaces where DHCP messages are received: INTERFACES="eth0"

Edit file /etc/dhcp/dhcpd.conf to create IPv4 address pools to all (V)LAN:

option domain-name-servers 10.0.100.1;

subnet 10.0.1.0 netmask 255.255.255.0 {

range 10.0.1.10 10.0.1.200;

option routers 10.0.1.1;}

subnet 10.0.2.0 netmask 255.255.255.0 {

range 10.0.2.10 10.0.2.200;

option routers 10.0.2.1;}

subnet 10.0.3.0 netmask 255.255.255.0 {

range 10.0.3.10 10.0.3.200;

option routers 10.0.3.2;}

subnet 10.0.100.0 netmask 255.255.255.0 {

range 10.0.100.10 10.0.100.200;

option routers 10.0.100.2;}

(Re)Start the DHCP server: sudo service isc-dhcp-server restart

Check the file /var/log/syslog to inspect and solve possible errors.

3. At all L3 interfaces of Routers/SWL3 (with terminals) configure the DHCP relay agent to send DHCP requests to the central DHCP server:

Router(config)# service dhcp

Router(config)# interface vlan 1

Router(config-if)# ip helper-address 10.0.100.1

- 4. Activate DHCP in interfaces of all (V)LAN terminal devices. Check the obtained IPv4 addresses.
- 5. Repeat steps 1 to 4 for IPv6, using the configuration file dhcpd6.conf and the activation of the managed flag on Router Advertisements and router relay agent command:

Router(config-if)# ipv6 nd managed-config-flag

Router(config-if)# ipv6 dhcp relay destination <ipv6 addr DHCP>

DNS

```
6. At the DNS server, install package bind9: apt-get install bind9
Assuming that you own the domain ar.com configure your DNS server to act as a master server (zone) for
that domain. Start by creating the definition of the zone with the associated statements (zone specific
parameters), edit the file /etc/bind/named.conf.local (with root privileges) and add the following definition:
zone "ar.com" in{
                                //statement to define the zone as master
 type master:
 file "/etc/bind/db.ar.com";
                                        //location of the zone file with the records
Create the file /etc/bind/db.ar.com (with root privileges) and add the following contents:
        604800
$TTL
$ORIGIN ar.com.
        IN
                SOA
                        ns1.ar.com. adm.ar.com. (
                           2
                                        ; Serial
                        604800
                                        ; Refresh
                         86400
                                        ; Retry
                                        ; Expire
                        2419200
                        604800)
                                        ; Negative Cache TTL
                NS
        IN
                        ns1.ar.com.
        IN
                        10.0.100.1
                Α
v1sw1
        IN
                        10.0.1.1
                AAAA
v1sw1
        IN
                        2001:0:1::1
        IN
                                server1
                MX
                        10
@
lns1
        IN
                Α
                        10.0.100.1
server1 IN
                Α
                        10.0.100.1
server2 IN
                CNAME server1
Verify if your zone file it is correctly defined:
named-checkzone ar.com db.ar.com
Restart your DNS server:
service bind9 restart
Using a Linux terminal, test the configuration of your DNS by performing the following DNS queries:
dig @10.0.100.1 ar.com
dig @10.0.100.1 v1sw1.ar.com
dig @10.0.100.1 v1sw1.ar.com AAAA
dig @10.0.100.1 server1.ar.com
dig @10.0.100.1 server2.ar.com
dig @10.0.100.1 ar.com MX
Analyze the output of the dig commands.
```

```
configure the
                                             IPv4
                                                    reverse
                                                               DNS
                                                                       mapping
                                                                                                domain.
                                                                                                           Add
              zone to
                                                                                   of
                                                                                        your
                                                                                                                  to
/etc/bind/named.conf.local the following zone definition:
zone "1.0.10.in-addr.arpa" in{
type master:
file "/etc/bind/db.10.0.1.rev"; };
Create the file /etc/bind/db.10.0.1.rev (with root privileges) and add the following contents:
$TTL
       604800
$ORIGIN 1.0.10.in-addr.arpa.
       IN
                SOA
@
                        ns1.ar.com. adm.ar.com. (
                                        ; Serial
                           2
                        604800
                                        ; Refresh
                         86400
                                        ; Retry
                        2419200
                                        ; Expire
                                        ; Negative Cache TTL
                        604800)
       IN
             NS
                   ns1.ar.com.
        IN
              PTR
                    v1sw1.ar.com.; qualified name
11
         IN
              PTR
                     vlan1-11.ar.com.
12
         IN
              PTR
                     vlan1-12.ar.com.
Restart your DNS server:
service bind9 restart
Using your PC, test your configuration with the commands:
host 10.0.1.1 10.0.100.1
```

host 10.0.1.2 10.0.100.1 host 10.0.1.11 10.0.100.1 host 10.0.1.12 10.0.100.1