

Module 7: IPv4 Address Subnetting

Introduction to Networks v7.0 (ITN)




Network Segmentation

Official (Open) Network Segmentation

Broadcast Domains and Segmentation

- Many protocols use broadcasts or multicasts (e.g., ARP use broadcasts to locate other devices, hosts send DHCP discover broadcasts to locate a DHCP server.)
- Switches propagate broadcasts out all interfaces except the interface on which it was received.





- The only device that stops broadcasts is a router.
- Routers do not propagate broadcasts.
- Each router interface connects to a broadcast domain and broadcasts are only propagated within that specific broadcast domain.

Network Segmentation

Problems with Large Broadcast Domains

- A problem with a large broadcast domain is that these hosts can generate excessive broadcasts and negatively affect the network.
- The solution is to reduce the size of the network to create smaller broadcast domains in a process called subnetting.
- Dividing the network address 172.16.0.0 /16 into two subnets of 200 users each: 172.16.0.0 /24 and 172.16.1.0 /24.
- Broadcasts are only propagated within the smaller broadcast domains.








Official (Open) Network Segmentation

Reasons for Segmenting Networks

- Subnetting reduces overall network traffic and improves network performance.
- It can be used to implement security policies between subnets.
- Subnetting reduces the number of devices affected by abnormal broadcast traffic.
- Subnets are used for a variety of reasons including by:







Subnet an IPv4 Network



Subnet an IPv4 Network Subnet on an Octet Boundary

- Networks are most easily subnetted at the octet boundary of /8, /16, and /24.
- Notice that using longer prefix lengths decreases the number of hosts per subnet.

Prefix Length	Subnet Mask	Subnet Mask in Binary (n = network, h = host)	# of hosts
/8	255 .0.0.0	nnnnnnn .hhhhhhhh.hhhhhhhh.hhhhhhhh 1111111 .00000000.0000000.00000000	16,777,214
/16	255.255 .0.0	nnnnnnn.nnnnnnn .hhhhhhhh.hhhhhhh 1111111.1111111 .00000000.0000000	65,534
/24	255.255.255 .0	nnnnnnn.nnnnnnn.nnnnnnn.hhhhhhh 1111111.11111111.1111111.00000000	254

Subnet an IPv4 Network Subnet on an Octet Boundary (Cont.)

• In the first table 10.0.0.0/8 is subnetted using /16 and in the second table, a /24 mask.

Subnet Address (256 Possible Subnets)	Host Range (65,534 possible hosts per subnet)	Broadcast
10.0.0.0/16	10.0 .0.1 - 10.0 .255.254	10.0.255.255
10.1.0.0/16	10.1 .0.1 - 10.1 .255.254	10.1 .255.255
10.2 .0.0/ 16	10.2 .0.1 - 10.2 .255.254	10.2 .255.255
10.3.0.0/16	10.3 .0.1 - 10.3 .255.254	10.3 .255.255
10.4 .0.0/ 16	10.4 .0.1 - 10.4 .255.254	10.4 .255.255
10.5 .0.0/ 16	10.5 .0.1 - 10.5 .255.254	10.5 .255.255
10.6.0.0/16	10.6 .0.1 - 10.6 .255.254	10.6.255.255
10.7.0.0/16	10.7 .0.1 - 10.7 .255.254	10.7 .255.255
10.255 .0.0/ 16	10.255 .0.1 - 10.255 .255.254	10.255 .255.255

Subnet Address (65,536 Possible Subnets)	Host Range (254 possible hosts per subnet)	Broadcast
10.0.0.0/24	10.0.0 .1 - 10.0 .0.254	10.0.0.255
10.0.1.0/24	10.0.1 .1 - 10.0.1 .254	10.0.1 .255
10.0.2.0/24	10.0.2 .1 - 10.0.2 .254	10.0.2 .255
10.0.255.0/24	10.0.255 .1 - 10.0.255 .254	10.0.255 .255
10.1.0.0/24	10.1.0 .1 - 10.1.0 .254	10.1.0 .255
10.1.1.0/24	10.1.1 .1 - 10.1.1 .254	10.1.1 .255
10.1.2.0/24	10.1.2 .1 - 10.1.2 .254	10.1.2 .255
10.100.0.0/24	10.100.0 .1 - 10.100.0 .254	10.100.0 .255
10.255.255.0/24	10.255.255 .1 - 10.255.255 .254	10.255.255 .255

Subnet an IPv4 Network Subnet within an Octet Boundary

Refer to the table to see six ways to subnet a /24 network.

Prefix Length	Subnet Mask	Subnet Mask in Binary (n = network, h = host)	# of subnets	# of hosts
/25	255.255.255.128	nnnnnnn.nnnnnnnn.nnnnnnn. n hhhhhh 11111111.11111111.11111111. 1 0000000	2	126
/26	255.255.255.192	nnnnnnn.nnnnnnnn.nnnnnnn. nn hhhhh 11111111.11111111.111111111. 11 000000	4	62
/27	255.255.255.224	nnnnnnn.nnnnnnnn.nnnnnnn. nnn hhhhh 11111111.11111111.11111111. 111 00000	8	30
/28	255.255.255.240	nnnnnnn.nnnnnnn.nnnnnnn. nnnn hhhh 11111111.11111111.111111111. 1111 0000	16	14
/29	255.255.255.248	nnnnnnn.nnnnnnnn.nnnnnnn. nnnn hhh 11111111.11111111.111111111. 11111 000	32	6
/30	255.255.255.252	nnnnnnn.nnnnnnnn.nnnnnnn. nnnnnn hh 11111111.11111111.111111111.1 11111 00	64	2



Subnet a Slash 16 and a Slash 8 Prefix

Subnet a Slash 16 and a Slash 8 Prefix

Create Subnets with a Slash 16 prefix

 The table highlights all the possible scenarios for subnetting a /16 prefix.

	<u> </u>			
Prefix Length	Subnet Mask	Network Address (n = network, h = host)	# of subnets	# of hosts
/17	255.255. 128 .0	nnnnnnn.nnnnnnnn. n hhhhhhh.hhhhhhh 11111111.11111111. 1 0000000.00000000	2	32766
/18	255.255. 192 .0	nnnnnnn.nnnnnnnn. nn hhhhhh.hhhhhhh 11111111.111111111. 11 000000.00000000	4	16382
/19	255.255. 224 .0	nnnnnnnn.nnnnnnn. nnn hhhhh.hhhhhhh 11111111.111111111. 111 00000.00000000	8	8190
/20	255.255. 240 .0	nnnnnnnn.nnnnnnnn. nnn hhhh.hhhhhhh 11111111.111111111. 1111 0000.00000000	16	4094
/21	255.255. 248 .0	nnnnnnnn.nnnnnnnn. nnnnn hhh.hhhhhhh 11111111.11111111111111000.00000000	32	2046
/22	255.255. 252 .0	nnnnnnnn.nnnnnnnn. nnnnnn hh.hhhhhh 11111111.111111111. 111111 00.00000000	64	1022
/23	255.255. 254 .0	nnnnnnnn.nnnnnnnn. nnnnnnn h.hhhhhhh 11111111.111111111. 1111111 0.00000000	128	510
/24	255.255. 255.0	nnnnnnnn.nnnnnnnn. nnnnnnnn .hhhhhhh 11111111.111111111. 11111111 .00000000	256	254
/25	255.255. 255.128	nnnnnnnn.nnnnnnnn. nnnnnnnn.n hhhhhh 11111111.11111111111111111111111	512	126
/26	255.255. 255.192	nnnnnnnn.nnnnnnnn. nnnnnnnn.nn hhhhh 11111111.1111111111111111111111000000	1024	62
/27	255.255. 255.224	nnnnnnnn.nnnnnnnn. nnnnnnnn.nnn hhhhh 11111111.111111111111111111111100000	2048	30
/28	255.255 .255.240	nnnnnnn.nnnnnnn. nnnnnnnn.nnnn hhhh 11111111.1111111111111111111110000	4096	14
/29	255.255. 255.248	nnnnnnn.nnnnnnnn. nnnnnnnn.nnnn hhh 11111111.1111111111111111111111000	8192	6
/30	255.255. 255.252	nnnnnnn.nnnnnnn. nnnnnnn.nnnnn hh	16384	2


cisco

Create 100 Subnets with a Slash 16 prefix

Consider a large enterprise that requires at least 100 subnets and has chosen the private address 172.16.0.0/16 as its internal network address.

- The figure displays the number of subnets that can be created when borrowing bits from the third octet and the fourth octet.
- Notice there are now up to 14 host bits that can be borrowed (i.e., last two bits cannot be borrowed).

To satisfy the requirement of 100 subnets for the enterprise, 7 bits (i.e., 2^7 = 128 subnets) would need to be borrowed (for a total of 128 subnets).




Create 1000 Subnets with a Slash 8 prefix

Consider a small ISP that requires 1000 subnets for its clients using network address 10.0.0.0/8 which means there are 8 bits in the network portion and 24 host bits available to borrow toward subnetting.

- The figure displays the number of subnets that can be created when borrowing bits from the second and third.
- Notice there are now up to 22 host bits that can be borrowed (i.e., last two bits cannot be borrowed).

To satisfy the requirement of 1000 subnets for the enterprise, 10 bits (i.e., 2¹⁰=1024 subnets) would need to be borrowed (for a total of 128 subnets)




Subnet to Meet Requirements

Subnet Private versus Public IPv4 Address Space

Enterprise networks will have an:

- Intranet A company's internal network typically using private IPv4 addresses.
- DMZ A companies internet facing servers.
 Devices in the DMZ use public IPv4 addresses.
- A company could use the 10.0.0.0/8 and subnet on the /16 or /24 network boundary.
- The DMZ devices would have to be configured with public IP addresses.



Minimize Unused Host IPv4 Addresses and Maximize Subnets

There are two considerations when planning subnets:

- The number of host addresses required for each network
- The number of individual subnets needed

Prefix Length	Subnet Mask	Subnet Mask in Binary (n = network, h = host)	# of subnets	# of hosts
/25	255.255.255.128	nnnnnnn.nnnnnnnn.nnnnnnn. n hhhhhhh 11111111.11111111.11111111. 1 0000000	2	126
/26	255.255.255.192	nnnnnnn.nnnnnnnn.nnnnnnn. nn hhhhhh 11111111.11111111.11111111. 11 000000	4	62
/27	255.255.255.224	nnnnnnn.nnnnnnnn.nnnnnnn.nnhhhhh 11111111.11111111.11111111. 111 00000	8	30
/28	255.255.255.240	nnnnnnn.nnnnnnnn.nnnnnnn.nnnhhhh 11111111.11111111.11111111. 1111 0000	16	14
/29	255.255.255.248	nnnnnnn.nnnnnnnnnnnnnnnnnnnnnhhh 11111111.111111111.11111111.11111000	32	6
/30	255.255.255.252	nnnnnnn.nnnnnnnn.nnnnnnn. nnnnnn hh 11111111.11111111.11111111. 111111 00	64	2



Subnet to Meet Requirements

Example: Efficient IPv4 Subnetting

In this example, corporate headquarters has been allocated a public network address of 172.16.0.0/22 (10 host bits) by its ISP providing 1,022 host addresses.

- There are five sites and therefore five internet connections which means the organization requires 10 subnets with the largest subnet requires 40 addresses.
- It allocated 10 subnets with a /26 (i.e., 255.255.255.192) subnet mask.

