# Package 'binsreg'

June 11, 2021

, -
Type Package
Title Binscatter Estimation and Inference
<b>Date</b> 2021-06-10
Version 0.3.0
Author Matias D. Cattaneo, Richard K. Crump, Max H. Farrell, Yingjie Feng
Maintainer Yingjie Feng <yingjief@princeton.edu></yingjief@princeton.edu>
Description Provides tools for statistical analysis using the binscatter methods developed by Cattaneo, Crump, Farrell and Feng (2021a) <arxiv:1902.09608> and Cattaneo, Crump, Farrell and Feng (2021b) <arxiv:1902.09615>. Binscatter provides a flexible way of describing the mean relationship between two variables based on partitioning/binning of the independent variable of interest. binsreg(), binsqreg() and binsglm() implement binscatter least squares regression, quantile regression and generalized linear regression respectively, with particular focus on constructing binned scatter plots. They also implement robust (pointwise and uniform) inference of regression functions and derivatives thereof. binstest() implements hypothesis testing procedures for parametric functional forms of and nonparametric shape restrictions on the regression function. binspwc() implements hypothesis testing procedures for pairwise group comparison of binscatter estimators. binsregselect() implements data-driven procedures for selecting the number of bins for binscatter estimation. All the commands allow for covariate adjustment, smoothness restrictions and clustering.  Depends R (&gt;= 3.1)</arxiv:1902.09615></arxiv:1902.09608>
License GPL-2
Encoding UTF-8
LazyData true
Imports ggplot2, sandwich, quantreg, splines, matrixStats
Roxygen list(old_usage = TRUE)
RoxygenNote 7.1.1
R topics documented:
binsreg-package binsglm binspwc binsqreg 1 binsreg 1

Index 27

Binsreg Package Document binsreg-package

#### **Description**

Binscatter provides a flexible, yet parsimonious way of visualizing and summarizing large data sets and has been a popular methodology in applied microeconomics and other social sciences. The binsreg package provides tools for statistical analysis using the binscatter methods developed in Cattaneo, Crump, Farrell and Feng (2021a). binsreg implements binscatter least squares regression with robust inference and plots, including curve estimation, pointwise confidence intervals and uniform confidence band. binsqreg implements binscatter quantile regression with robust inference and plots, including curve estimation, pointwise confidence intervals and uniform confidence band. binsglm implements binscatter generalized linear regression with robust inference and plots, including curve estimation, pointwise confidence intervals and uniform confidence band. binstest implements binscatter-based hypothesis testing procedures for parametric specification of and nonparametric shape restrictions on the unknown function of interest. binspwc implements hypothesis testing procedures for pairwise group comparison of binscatter estimators. binsregselect implements data-driven number of bins selectors for binscatter implementation using either quantilespaced or evenly-spaced binning/partitioning. All the commands allow for covariate adjustment, smoothness restrictions, and clustering, among other features.

The companion software article, Cattaneo, Crump, Farrell and Feng (2021b), provides further implementation details and empirical illustration. For related Stata and R packages useful for nonparametric data analysis and statistical inference, visit https://nppackages.github.io/.

## Author(s)

Matias D. Cattaneo, Princeton University, Princeton, NJ. <cattaneo@princeton.edu>.

Richard K. Crump, Federal Reserve Bank of New York, New York, NY. <richard.crump@ny.frb.org>.

Max H. Farrell, University of Chicago, Chicago, IL. <max.farrell@chicagobooth.edu>.

Yingjie Feng (maintainer), Princeton University, Princeton, NJ. <pingjief@princeton.edu>.

#### References

Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2021a: On Binscatter. Working Paper.

Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2021b: Binscatter Regressions. Working Paper.

binsglm Data-Driven Binscatter Generalized Linear Regression with Robust Inference Procedures and Plots

### **Description**

binsglm implements binscatter generalized linear regression with robust inference procedures and plots, following the results in Cattaneo, Crump, Farrell and Feng (2021a). Binscatter provides a flexible way of describing the relationship between two variables, after possibly adjusting for other covariates, based on partitioning/binning of the independent variable of interest. The main purpose of this function is to generate binned scatter plots with curve estimation with robust pointwise confidence intervals and uniform confidence band. If the binning scheme is not set by the user, the companion function binsregselect is used to implement binscatter in a data-driven way. Hypothesis testing about the function of interest can be conducted via the companion function binstest.

## Usage

```
binsglm(y, x, w = NULL, data = NULL, at = NULL, family = gaussian(),
  deriv = 0, nolink = F, dots = c(0, 0), dotsgrid = 0,
  dotsgridmean = T, line = NULL, linegrid = 20, ci = NULL,
  cigrid = 0, cigridmean = T, cb = NULL, cbgrid = 20, polyreg = NULL,
  polyreggrid = 20, polyregcigrid = 0, by = NULL, bycolors = NULL,
  bysymbols = NULL, bylpatterns = NULL, legendTitle = NULL,
  legendoff = F, nbins = NULL, binspos = "qs", binsmethod = "dpi",
  nbinsrot = NULL, samebinsby = F, nsims = 500, simsgrid = 20,
  simsseed = 666, vce = "HC1", cluster = NULL, level = 95,
  noplot = F, dfcheck = c(20, 30), masspoints = "on", weights = NULL,
  subset = NULL, plotxrange = NULL, plotyrange = NULL)
```

#### **Arguments**

у	outcome variable. A vector.
X	independent variable of interest. A vector.
W	control variables. A matrix, a vector or a formula.
data	an optional data frame containing variables in the model.
at	value of w at which the estimated function is evaluated. The default is at="mean", which corresponds to the mean of w. Other options are: at="median" for the median of w, at="zero" for a vector of zeros. at can also be a vector of the same length as the number of columns of w (if w is a matrix) or a data frame containing the same variables as specified in w (when data is specified). Note that when w="mean" or w="median", all factor variables (if specified) are excluded from the evaluation.
family	a description of the error distribution and link function to be used in the generalized linear model. (See family for details of family functions.)
deriv	derivative order of the regression function for estimation, testing and plotting. The default is deriv=0, which corresponds to the function itself. If nolink=TRUE, deriv cannot be greater than 1.
nolink	if true, the function within the inverse link function is reported instead of the conditional mean function for the outcome.
dots	a vector. $dots=c(p,s)$ sets a piecewise polynomial of degree p with s smoothness constraints for point estimation and plotting as "dots". The default is $dots=c(0,0)$ , which corresponds to piecewise constant (canonical binscatter)
dotsgrid	number of dots within each bin to be plotted. Given the choice, these dots are point estimates evaluated over an evenly-spaced grid within each bin. The default is dotsgrid=0, and only the point estimates at the mean of x within each bin are presented.

dotsgridmean

If true, the dots corresponding to the point estimates evaluated at the mean of x within each bin are presented. By default, they are presented, i.e., dotsgridmean=T.

line

a vector. line=c(p,s) sets a piecewise polynomial of degree p with s smoothness constraints for plotting as a "line". By default, the line is not included in the plot unless explicitly specified. Recommended specification is line=c(3,3), which adds a cubic B-spline estimate of the regression function of interest to the binned scatter plot.

linegrid

number of evaluation points of an evenly-spaced grid within each bin used for evaluation of the point estimate set by the line=c(p,s) option. The default is linegrid=20, which corresponds to 20 evenly-spaced evaluation points within each bin for fitting/plotting the line.

ci

a vector. ci=c(p,s) sets a piecewise polynomial of degree p with s smoothness constraints used for constructing confidence intervals. By default, the confidence intervals are not included in the plot unless explicitly specified. Recommended specification is ci=c(3,3), which adds confidence intervals based on cubic B-spline estimate of the regression function of interest to the binned scatter plot.

cigrid

number of evaluation points of an evenly-spaced grid within each bin used for evaluation of the point estimate set by the ci=c(p,s) option. The default is cigrid=1, which corresponds to 1 evenly-spaced evaluation point within each bin for confidence interval construction.

cigridmean

If true, the confidence intervals corresponding to the point estimates evaluated at the mean of x within each bin are presented. The default is cigridmean=T.

cb

a vector. cb=c(p,s) sets a the piecewise polynomial of degree p with s smoothness constraints used for constructing the confidence band. By default, the confidence band is not included in the plot unless explicitly specified. Recommended specification is cb=c(3,3), which adds a confidence band based on cubic B-spline estimate of the regression function of interest to the binned scatter plot.

cbgrid

number of evaluation points of an evenly-spaced grid within each bin used for evaluation of the point estimate set by the cb=c(p,s) option. The default is cbgrid=20, which corresponds to 20 evenly-spaced evaluation points within each bin for confidence interval construction.

polyreg

degree of a global polynomial regression model for plotting. By default, this fit is not included in the plot unless explicitly specified. Recommended specification is polyreg=3, which adds a cubic (global) polynomial fit of the regression function of interest to the binned scatter plot.

polyreggrid

number of evaluation points of an evenly-spaced grid within each bin used for evaluation of the point estimate set by the polyreg=p option. The default is polyreggrid=20, which corresponds to 20 evenly-spaced evaluation points within each bin for confidence interval construction.

polyregcigrid

number of evaluation points of an evenly-spaced grid within each bin used for constructing confidence intervals based on polynomial regression set by the polyreg=p option. The default is polyregcigrid=0, which corresponds to not plotting confidence intervals for the global polynomial regression approximation.

by

a vector containing the group indicator for subgroup analysis; both numeric and string variables are supported. When by is specified, binsreg implements estimation and inference by each subgroup separately, but produces a common

binned scatter plot. By default, the binning structure is selected for each subgroup separately, but see the option samebinsby below for imposing a common binning structure across subgroups.

bycolors an ordered list of colors for plotting each subgroup series defined by the option

by.

by symbols an ordered list of symbols for plotting each subgroup series defined by the option

by.

bylpatterns an ordered list of line patterns for plotting each subgroup series defined by the

option by.

legendTitle String, title of legend.

legendoff If true, no legend is added.

nbins number of bins for partitioning/binning of x. If not specified, the number of bins

is selected via the companion function binsregselect in a data-driven, optimal

way whenever possible.

binspos position of binning knots. The default is binspos="qs", which corresponds to

quantile-spaced binning (canonical binscatter). The other options are "es" for evenly-spaced binning, or a vector for manual specification of the positions of

inner knots (which must be within the range of x).

binsmethod method for data-driven selection of the number of bins. The default is binsmethod="dpi",

which corresponds to the IMSE-optimal direct plug-in rule. The other option is:

"rot" for rule of thumb implementation.

nbinsrot initial number of bins value used to construct the DPI number of bins selector.

If not specified, the data-driven ROT selector is used instead.

samebinsby if true, a common partitioning/binning structure across all subgroups specified

by the option by is forced. The knots positions are selected according to the option binspos and using the full sample. If nbins is not specified, then the number of bins is selected via the companion command binsregselect and

using the full sample.

nsims number of random draws for constructing confidence bands and hypothesis test-

ing. The default is nsims=500, which corresponds to 500 draws from a standard

Gaussian random vector of size [(p+1)\*J - (J-1)\*s].

simsgrid number of evaluation points of an evenly-spaced grid within each bin used for

evaluation of the supremum (or infimum) operation needed to construct confidence bands and hypothesis testing procedures. The default is simsgrid=20, which corresponds to 20 evenly-spaced evaluation points within each bin for

approximating the supremum (or infimum) operator.

simsseed seed for simulation.

vce Procedure to compute the variance-covariance matrix estimator. Options are

- "const" homoskedastic variance estimator.
- "HC0" heteroskedasticity-robust plug-in residuals variance estimator without weights.
- "HC1" heteroskedasticity-robust plug-in residuals variance estimator with hc1 weights. Default.
- "HC2" heteroskedasticity-robust plug-in residuals variance estimator with hc2 weights.
- "HC3" heteroskedasticity-robust plug-in residuals variance estimator with hc3 weights.

cluster cluster ID. Used for compute cluster-robust standard errors.

level nominal confidence level for confidence interval and confidence band estima-

tion. Default is level=95.

noplot If true, no plot produced.

> adjustments for minimum effective sample size checks, which take into account number of unique values of x (i.e., number of mass points), number of clusters, and degrees of freedom of the different stat models considered. The default is dfcheck=c(20,30). See Cattaneo, Crump, Farrell and Feng (2021b) for more

details.

masspoints how mass points in x are handled. Available options:

• "on" all mass point and degrees of freedom checks are implemented. De-

- "noadjust" mass point checks and the corresponding effective sample size adjustments are omitted.
- "nolocalcheck" within-bin mass point and degrees of freedom checks are omitted.
- "off" "noadjust" and "nolocalcheck" are set simultaneously.
- "veryfew" forces the function to proceed as if x has only a few number of mass points (i.e., distinct values). In other words, forces the function to proceed as if the mass point and degrees of freedom checks were failed.

weights an optional vector of weights to be used in the fitting process. Should be NULL or a numeric vector. For more details, see 1m.

Optional rule specifying a subset of observations to be used.

a vector. plotxrange=c(min, max) specifies a range of the x-axis for binscatter plot. Observations outside the range are dropped in the plot.

a vector. plotyrange=c(min, max) specifies a range of the y-axis for binscatter plot. Observations outside the range are dropped in the plot.

#### Value

A ggplot object for binscatter plot.

A list containing data for plotting. Each item is a sublist of data frames for each group. Each sublist may contain the following data frames:

- data.dots Data for dots. It contains: x, evaluation points; bin, the indicator of bins; isknot, indicator of inner knots; mid, midpoint of each bin; and fit, fitted values.
- data.line Data for line. It contains: x, evaluation points; bin, the indicator of bins; isknot, indicator of inner knots; mid, midpoint of each bin; and fit, fitted values.
- data.ci Data for CI. It contains: x, evaluation points; bin, the indicator of bins; isknot, indicator of inner knots; mid, midpoint of each bin; ci.l and ci.r, left and right boundaries of each confidence intervals.
- data.cb Data for CB. It contains: x, evaluation points; bin, the indicator of bins; isknot, indicator of inner knots; mid, midpoint of each bin; cb.1 and cb.r, left and right boundaries of the confidence band.
- data.poly Data for polynomial regression. It contains: x, evaluation points; bin, the indicator of bins; isknot, indicator of inner knots; mid, midpoint of each bin; and fit, fitted values.

dfcheck

subset

plotxrange plotyrange

bins\_plot

data.plot

data.polyci Data for confidence intervals based on polynomial regression. It contains: x, evaluation points; bin, the indicator of bins; isknot, indicator of inner knots; mid, midpoint of each bin; polyci.l and polyci.r, left and right boundaries of each confidence intervals.

cval.by

A vector of critical values for constructing confidence band for each group.

opt

A list containing options passed to the function, as well as N.by (total sample size for each group), Ndist.by (number of distinct values in x for each group), Nclust.by (number of clusters for each group), and nbins.by (number of bins for each group), and byvals (number of distinct values in by).

#### Author(s)

Matias D. Cattaneo, Princeton University, Princeton, NJ. <cattaneo@princeton.edu>.

Max H. Farrell, University of Chicago, Chicago, IL. <max.farrell@chicagobooth.edu>.

Yingjie Feng (maintainer), Princeton University, Princeton, NJ. <yingjief@princeton.edu>.

#### References

Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2021a: On Binscatter. Working Paper. Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2021b: Binscatter Regressions. Working Paper.

#### See Also

binsregselect, binstest.

# **Examples**

```
x <- runif(500); d <- 1*(runif(500)<=x)
## Binned scatterplot
binsglm(d, x, family=binomial())</pre>
```

binspwc

Data-Driven Pairwise Group Comparison using Binscatter Methods

# Description

binspwc implements hypothesis testing procedures for pairwise group comparison of binscatter estimators, following the results in Cattaneo, Crump, Farrell and Feng (2021a). If the binning scheme is not set by the user, the companion function binsregselect is used to implement binscatter in a data-driven way. Binned scatter plots based on different methods can be constructed using the companion functions binsreg, binsqreg or binsglm. Hypothesis testing about the function of interest can also be conducted via the companion function binstest.

#### **Usage**

```
binspwc(y, x, w = NULL, data = NULL, estmethod = "reg",
  family = gaussian(), quantile = NULL, deriv = 0, by = NULL,
  pwc = c(3, 3), testtype = "two-sided", lp = Inf, bins = c(0, 0),
  bynbins = NULL, binspos = "qs", binsmethod = "dpi", nbinsrot = NULL,
  samebinsby = FALSE, nsims = 500, simsgrid = 20, simsseed = 666,
  vce = NULL, cluster = NULL, dfcheck = c(20, 30), masspoints = "on",
  weights = NULL, subset = NULL, numdist = NULL, numclust = NULL, ...)
```

## Arguments

1p

y outcome variable. A vector.

x independent variable of interest. A vector.

w control variables. A matrix, a vector or a formula.

data an optional data frame containing variables used in the model.

estmethod estimation method. The default is estmethod="reg" for tests based on binscat-

ter least squares regression. Other options are "qreg" for quantile regression and "glm" for generalized linear regression. If estmethod="glm", the option

family must be specified.

family a description of the error distribution and link function to be used in the gener-

alized linear model when estmethod="glm". (See family for details of family

functions.)

quantile the quantile to be estimated. A number strictly between 0 and 1.

derivative order of the regression function for estimation, testing and plotting.

The default is deriv=0, which corresponds to the function itself.

by a vector containing the group indicator for subgroup analysis; both numeric and

string variables are supported. When by is specified, binsreg implements estimation and inference by each subgroup separately, but produces a common binned scatter plot. By default, the binning structure is selected for each subgroup separately, but see the option samebinsby below for imposing a common

binning structure across subgroups.

pwc a vector. pwc=c(p,s) sets a piecewise polynomial of degree p with s smooth-

ness constraints for testing the difference between groups. The default is pwc=c(3,3), which corresponds to a cubic B-spline estimate of the function of interest for

each group.

testtype type of pairwise comparison test. The default is testtype="two-sided", which

corresponds to a two-sided test of the form  $H0: mu_1(x)=mu_2(x)$ . Other options are: testtype="left" for the one-sided test form  $H0: mu_1(x) \le mu_2(x)$  and testtype="right" for the one-sided test of the form  $H0: mu_1(x) \ge mu_2(x)$ .

an Lp metric used for (two-sided) parametric model specification testing and/or shape restriction testing. The default is lp=Inf, which corresponds to the sup-

norm of the t-statistic. Other options are 1p=q for a positive integer q.

bins A vector. Degree and smoothness for bin selection.

bynbins a vector of the number of bins for partitioning/binning of x, which is applied

to the binscatter estimation for each group. If not specified, the number of bins is selected via the companion function binsregselect in a data-driven way

whenever possible.

binspos position of binning knots. The default is binspos="qs", which corresponds to

quantile-spaced binning (canonical binscatter). The other options are "es" for evenly-spaced binning, or a vector for manual specification of the positions of

inner knots (which must be within the range of x).

binsmethod method for data-driven selection of the number of bins. The default is binsmethod="dpi",

which corresponds to the IMSE-optimal direct plug-in rule. The other option is:

"rot" for rule of thumb implementation.

nbinsrot initial number of bins value used to construct the DPI number of bins selector.

If not specified, the data-driven ROT selector is used instead.

by the option by is forced. The knots positions are selected according to the option binspos and using the full sample. If nbins is not specified, then the number of bins is selected via the companion command binsregselect and

if true, a common partitioning/binning structure across all subgroups specified

using the full sample.

nsims number of random draws for constructing confidence bands and hypothesis testing. The default is nsims=500, which corresponds to 500 draws from a standard

Gaussian random vector of size [(p+1)\*J - (J-1)\*s].

number of evaluation points of an evenly-spaced grid within each bin used for evaluation of the supremum (or infimum) operation needed to construct confidence bands and hypothesis testing procedures. The default is simsgrid=20, which corresponds to 20 evenly-spaced evaluation points within each bin for

approximating the supremum (or infimum) operator.

simsseed seed for simulation.

> procedure to compute the variance-covariance matrix estimator. For least squares regression and generalized linear regression, the allowed options are the same as that for binsreg or binsqreg. For quantile regression, the allowed options

are the same as that for binsqreg.

cluster cluster ID. Used for compute cluster-robust standard errors.

> adjustments for minimum effective sample size checks, which take into account number of unique values of x (i.e., number of mass points), number of clusters, and degrees of freedom of the different stat models considered. The default is dfcheck=c(20,30). See Cattaneo, Crump, Farrell and Feng (2021b) for more

details.

how mass points in x are handled. Available options: masspoints

> • "on" all mass point and degrees of freedom checks are implemented. Default.

- "noadjust" mass point checks and the corresponding effective sample size adjustments are omitted.
- "nolocalcheck" within-bin mass point and degrees of freedom checks are
- "off" "noadjust" and "nolocalcheck" are set simultaneously.
- "veryfew" forces the function to proceed as if x has only a few number of mass points (i.e., distinct values). In other words, forces the function to proceed as if the mass point and degrees of freedom checks were failed.

an optional vector of weights to be used in the fitting process. Should be NULL or a numeric vector. For more details, see 1m.

subset optional rule specifying a subset of observations to be used.

numdist Number of distinct for selection. Used to speed up computation.

samebinsby

simsgrid

vce

dfcheck

weights

numclust Number of clusters for selection. Used to speed up computation.

... optional arguments to control bootstrapping if estmethod="qreg" and vce="boot".

See boot.rq.

#### Value

stat A matrix. Each row corresponds to the comparison between two groups. The

first column is the test statistic. The second and third columns give the corre-

sponding group numbers. The null hypothesis is  $mu_i(x) \le mu_j(x)$ ,  $mu_i(x) = mu_j(x)$ ,

or  $mu_i(x)>=mu_j(x)$  for group i (given in the second column) and group j (given in the third column). The group number corresponds to the list of group

names given by opt\$byvals.

pval A vector of p-values for all pairwise group comparisons.

opt A list containing options passed to the function, as well as N. by (total sample

size for each group), Ndist.by (number of distinct values in x for each group), Nclust.by (number of clusters for each group), and nbins.by (number of bins

for each group), and byvals (number of distinct values in by).

#### Author(s)

Matias D. Cattaneo, Princeton University, Princeton, NJ. <cattaneo@princeton.edu>.

Richard K. Crump, Federal Reserve Bank of New York, New York, NY. <richard.crump@ny.frb.org>.

 $Max\ H.\ Farrell, University\ of\ Chicago,\ Chicago,\ IL.\ \verb|\color| sax.farrell@chicagobooth.edu|>.$ 

Yingjie Feng (maintainer), Princeton University, Princeton, NJ. <yingjief@princeton.edu>.

## References

Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2021a: On Binscatter. Working Paper.

Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2021b: Binscatter Regressions. Working Paper.

## See Also

binsregselect, binstest.

### **Examples**

```
x \leftarrow runif(500); y \leftarrow sin(x)+rnorm(500); t \leftarrow 1*(runif(500)>0.5) ## Binned scatterplot binspwc(y,x, by=t)
```

binsqreg	Data-Driven Binscatter Quantile Regression with Robust Inference
	Procedures and Plots

## **Description**

binsqreg implements binscatter quantile regression with robust inference procedures and plots, following the results in Cattaneo, Crump, Farrell and Feng (2021a). Binscatter provides a flexible way of describing the relationship between two variables, after possibly adjusting for other covariates, based on partitioning/binning of the independent variable of interest. The main purpose of this function is to generate binned scatter plots with curve estimation with robust pointwise confidence intervals and uniform confidence band. If the binning scheme is not set by the user, the companion function binsregselect is used to implement binscatter in a data-driven way. Hypothesis testing about the function of interest can be conducted via the companion function binstest.

#### Usage

```
binsqreg(y, x, w = NULL, data = NULL, at = NULL, quantile = 0.5,
  deriv = 0, dots = c(0, 0), dotsgrid = 0, dotsgridmean = T,
  line = NULL, linegrid = 20, ci = NULL, cigrid = 0, cigridmean = T,
  cb = NULL, cbgrid = 20, polyreg = NULL, polyreggrid = 20,
  polyregcigrid = 0, by = NULL, bycolors = NULL, bysymbols = NULL,
  bylpatterns = NULL, legendTitle = NULL, legendoff = F, nbins = NULL,
  binspos = "qs", binsmethod = "dpi", nbinsrot = NULL, samebinsby = F,
  nsims = 500, simsgrid = 20, simsseed = 666, vce = "nid",
  cluster = NULL, level = 95, noplot = F, dfcheck = c(20, 30),
  masspoints = "on", weights = NULL, subset = NULL, plotxrange = NULL,
  plotyrange = NULL, ...)
```

## Arguments

У	outcome variable. A vector.
x	independent variable of interest. A vector.
W	control variables. A matrix, a vector or a formula.
data	an optional data frame containing variables in the model.
at	value of w at which the estimated function is evaluated. The default is at="mean", which corresponds to the mean of w. Other options are: at="median" for the median of w, at="zero" for a vector of zeros. at can also be a vector of the same length as the number of columns of w (if w is a matrix) or a data frame containing the same variables as specified in w (when data is specified). Note that when w="mean" or w="median", all factor variables (if specified) are excluded from the evaluation.
quantile	the quantile to be estimated. A number strictly between 0 and 1.
deriv	derivative order of the regression function for estimation, testing and plotting. The default is deriv=0, which corresponds to the function itself.
dots	a vector. $dots=c(p,s)$ sets a piecewise polynomial of degree p with s smoothness constraints for point estimation and plotting as "dots". The default is $dots=c(0,0)$ , which corresponds to piecewise constant (canonical binscatter)

dotsgrid number of dots within each bin to be plotted. Given the choice, these dots are

point estimates evaluated over an evenly-spaced grid within each bin. The default is dotsgrid=0, and only the point estimates at the mean of x within each

bin are presented.

dotsgridmean If true, the dots corresponding to the point estimates evaluated at the mean of x

within each bin are presented. By default, they are presented, i.e., dotsgridmean=T.

line a vector. line=c(p,s) sets a piecewise polynomial of degree p with s smoothness constraints for plotting as a "line". By default, the line is not included in the

plot unless explicitly specified. Recommended specification is line=c(3,3), which adds a cubic B-spline estimate of the regression function of interest to the

binned scatter plot.

linegrid number of evaluation points of an evenly-spaced grid within each bin used for evaluation of the point estimate set by the line=c(p,s) option. The default is

 ${\tt linegrid=20, which \ corresponds \ to \ 20 \ evenly-spaced \ evaluation \ points \ within}$ 

each bin for fitting/plotting the line.

a vector. ci=c(p,s) sets a piecewise polynomial of degree p with s smoothness constraints used for constructing confidence intervals. By default, the confidence intervals are not included in the plot unless explicitly specified. Recommended specification is ci=c(3,3), which adds confidence intervals based on

ter plot.

ci

cbgrid

cigrid number of evaluation points of an evenly-spaced grid within each bin used for

evaluation of the point estimate set by the ci=c(p,s) option. The default is cigrid=1, which corresponds to 1 evenly-spaced evaluation point within each

cubic B-spline estimate of the regression function of interest to the binned scat-

bin for confidence interval construction.

cigridmean If true, the confidence intervals corresponding to the point estimates evaluated

at the mean of x within each bin are presented. The default is cigridmean=T.

cb a vector. cb=c(p,s) sets a the piecewise polynomial of degree p with s smoothness constraints used for constructing the confidence band. By default, the confi-

dence band is not included in the plot unless explicitly specified. Recommended specification is cb=c(3,3), which adds a confidence band based on cubic B-

spline estimate of the regression function of interest to the binned scatter plot.

number of evaluation points of an evenly-spaced grid within each bin used for evaluation of the point estimate set by the cb=c(p,s) option. The default is cbgrid=20, which corresponds to 20 evenly-spaced evaluation points within

each bin for confidence interval construction.

polyreg degree of a global polynomial regression model for plotting. By default, this fit

is not included in the plot unless explicitly specified. Recommended specification is polyreg=3, which adds a cubic (global) polynomial fit of the regression

function of interest to the binned scatter plot.

polyreggrid number of evaluation points of an evenly-spaced grid within each bin used

for evaluation of the point estimate set by the polyreg=p option. The default is polyreggrid=20, which corresponds to 20 evenly-spaced evaluation points

within each bin for confidence interval construction.

polyregcigrid number of evaluation points of an evenly-spaced grid within each bin used for constructing confidence intervals based on polynomial regression set by the

polyreg=p option. The default is polyregcigrid=0, which corresponds to not plotting confidence intervals for the global polynomial regression approxima-

tion.

by a vector containing the group indicator for subgroup analysis; both numeric and

string variables are supported. When by is specified, binsreg implements estimation and inference by each subgroup separately, but produces a common binned scatter plot. By default, the binning structure is selected for each subgroup separately, but see the option samebinsby below for imposing a common

binning structure across subgroups.

by colors an ordered list of colors for plotting each subgroup series defined by the option

by.

by symbols an ordered list of symbols for plotting each subgroup series defined by the option

by.

bylpatterns an ordered list of line patterns for plotting each subgroup series defined by the

option by.

legendTitle String, title of legend.

legendoff If true, no legend is added.

nbins number of bins for partitioning/binning of x. If not specified, the number of bins

is selected via the companion function binsregselect in a data-driven, optimal

way whenever possible.

binspos position of binning knots. The default is binspos="qs", which corresponds to

quantile-spaced binning (canonical binscatter). The other options are "es" for evenly-spaced binning, or a vector for manual specification of the positions of

inner knots (which must be within the range of x).

binsmethod method for data-driven selection of the number of bins. The default is binsmethod="dpi",

which corresponds to the IMSE-optimal direct plug-in rule. The other option is:

"rot" for rule of thumb implementation.

nbinsrot initial number of bins value used to construct the DPI number of bins selector.

If not specified, the data-driven ROT selector is used instead.

samebinsby if true, a common partitioning/binning structure across all subgroups specified

by the option by is forced. The knots positions are selected according to the option binspos and using the full sample. If nbins is not specified, then the number of bins is selected via the companion command binsregselect and

using the full sample.

nsims number of random draws for constructing confidence bands and hypothesis test-

ing. The default is nsims=500, which corresponds to 500 draws from a standard

Gaussian random vector of size [(p+1)\*J - (J-1)\*s].

simsgrid number of evaluation points of an evenly-spaced grid within each bin used for

evaluation of the supremum (or infimum) operation needed to construct confidence bands and hypothesis testing procedures. The default is simsgrid=20, which corresponds to 20 evenly-spaced evaluation points within each bin for

approximating the supremum (or infimum) operator.

simsseed seed for simulation.

vce Procedure to compute the variance-covariance matrix estimator (see summary.rq for more details). Options are

- "iid" which presumes that the errors are iid and computes an estimate of the asymptotic covariance matrix as in KB(1978).
- "nid" which presumes local (in quantile) linearity of the the conditional quantile functions and computes a Huber sandwich estimate using a local estimate of the sparsity.

 "ker" which uses a kernel estimate of the sandwich as proposed by Powell (1991).

• "boot" which implements one of several possible bootstrapping alternatives for estimating standard errors including a variate of the wild bootstrap for clustered response. See boot.rq for further details.

cluster

cluster ID. Used for compute cluster-robust standard errors.

level

nominal confidence level for confidence interval and confidence band estimation. Default is level=95.

noplot

If true, no plot produced.

dfcheck

adjustments for minimum effective sample size checks, which take into account number of unique values of x (i.e., number of mass points), number of clusters, and degrees of freedom of the different stat models considered. The default is dfcheck=c(20,30). See Cattaneo, Crump, Farrell and Feng (2021b) for more details.

masspoints

how mass points in x are handled. Available options:

- "on" all mass point and degrees of freedom checks are implemented. Default.
- "noadjust" mass point checks and the corresponding effective sample size adjustments are omitted.
- "nolocalcheck" within-bin mass point and degrees of freedom checks are omitted
- "off" "noadjust" and "nolocalcheck" are set simultaneously.
- "veryfew" forces the function to proceed as if x has only a few number of mass points (i.e., distinct values). In other words, forces the function to proceed as if the mass point and degrees of freedom checks were failed.

weights

an optional vector of weights to be used in the fitting process. Should be NULL or a numeric vector. For more details, see lm.

subset

optional rule specifying a subset of observations to be used.

plotxrange

a vector. plotxrange=c(min,max) specifies a range of the x-axis for plotting. Observations outside the range are dropped in the plot.

plotyrange

a vector. plotyrange=c(min,max) specifies a range of the y-axis for plotting. Observations outside the range are dropped in the plot.

optional arguments to control bootstrapping. See boot.rq.

## Value

bins\_plot

A ggplot object for binscatter plot.

data.plot

A list containing data for plotting. Each item is a sublist of data frames for each group. Each sublist may contain the following data frames:

- data.dots Data for dots. It contains: x, evaluation points; bin, the indicator of bins; isknot, indicator of inner knots; mid, midpoint of each bin; and fit, fitted values.
- data.line Data for line. It contains: x, evaluation points; bin, the indicator of bins; isknot, indicator of inner knots; mid, midpoint of each bin; and fit, fitted values.
- data.ci Data for CI. It contains: x, evaluation points; bin, the indicator of bins; isknot, indicator of inner knots; mid, midpoint of each bin; ci.l and ci.r, left and right boundaries of each confidence intervals.

• data.cb Data for CB. It contains: x, evaluation points; bin, the indicator of bins; isknot, indicator of inner knots; mid, midpoint of each bin; cb.1 and cb.r, left and right boundaries of the confidence band.

- data.poly Data for polynomial regression. It contains: x, evaluation points; bin, the indicator of bins; isknot, indicator of inner knots; mid, midpoint of each bin; and fit, fitted values.
- data.polyci Data for confidence intervals based on polynomial regression. It contains: x, evaluation points; bin, the indicator of bins; isknot, indicator of inner knots; mid, midpoint of each bin; polyci.l and polyci.r, left and right boundaries of each confidence intervals.

cval.by A vector of critical values for constructing confidence band for each group.

opt

A list containing options passed to the function, as well as N.by (total sample size for each group), Ndist.by (number of distinct values in x for each group), Nclust.by (number of clusters for each group), and nbins.by (number of bins for each group), and byvals (number of distinct values in by).

#### Author(s)

Matias D. Cattaneo, Princeton University, Princeton, NJ. <cattaneo@princeton.edu>.

Richard K. Crump, Federal Reserve Bank of New York, New York, NY. <richard.crump@ny.frb.org>.

Max H. Farrell, University of Chicago, Chicago, IL. <max.farrell@chicagobooth.edu>.

Yingjie Feng (maintainer), Princeton University, Princeton, NJ. <yingjief@princeton.edu>.

#### References

Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2021a: On Binscatter. Working Paper.

Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2021b: Binscatter Regressions. Working Paper.

#### See Also

binsregselect, binstest.

#### **Examples**

```
x <- runif(500); y <- sin(x)+rnorm(500)
## Binned scatterplot
binsqreg(y,x)</pre>
```

binsreg

Data-Driven Binscatter Least Squares Regression with Robust Inference Procedures and Plots

#### **Description**

binsreg implements binscatter least squares regression with robust inference procedures and plots, following the results in Cattaneo, Crump, Farrell and Feng (2021a). Binscatter provides a flexible way of describing the mean relationship between two variables, after possibly adjusting for other covariates, based on partitioning/binning of the independent variable of interest. The main purpose of this function is to generate binned scatter plots with curve estimation with robust pointwise confidence intervals and uniform confidence band. If the binning scheme is not set by the user, the companion function binsregselect is used to implement binscatter in a data-driven (optimal) way. Hypothesis testing about the regression function can be conducted via the companion function binstest.

## Usage

```
binsreg(y, x, w = NULL, data = NULL, at = NULL, deriv = 0,
  dots = c(0, 0), dotsgrid = 0, dotsgridmean = T, line = NULL,
  linegrid = 20, ci = NULL, cigrid = 0, cigridmean = T, cb = NULL,
  cbgrid = 20, polyreg = NULL, polyreggrid = 20, polyregcigrid = 0,
  by = NULL, bycolors = NULL, bysymbols = NULL, bylpatterns = NULL,
  legendTitle = NULL, legendoff = F, nbins = NULL, binspos = "qs",
  binsmethod = "dpi", nbinsrot = NULL, samebinsby = F, nsims = 500,
  simsgrid = 20, simsseed = 666, vce = "HC1", cluster = NULL,
  level = 95, noplot = F, dfcheck = c(20, 30), masspoints = "on",
  weights = NULL, subset = NULL, plotyrange = NULL)
```

#### **Arguments**

dotsgridmean

у	outcome variable. A vector.
x	independent variable of interest. A vector.
W	control variables. A matrix, a vector or a formula.
data	an optional data frame containing variables used in the model.
at	value of w at which the estimated function is evaluated. The default is at="mean", which corresponds to the mean of w. Other options are: at="median" for the median of w, at="zero" for a vector of zeros. at can also be a vector of the same length as the number of columns of w (if w is a matrix) or a data frame containing the same variables as specified in w (when data is specified). Note that when w="mean" or w="median", all factor variables (if specified) are excluded from the evaluation.
deriv	derivative order of the regression function for estimation, testing and plotting. The default is deriv=0, which corresponds to the function itself.
dots	a vector. $dots=c(p,s)$ sets a piecewise polynomial of degree p with s smoothness constraints for point estimation and plotting as "dots". The default is $dots=c(0,0)$ , which corresponds to piecewise constant (canonical binscatter)
dotsgrid	number of dots within each bin to be plotted. Given the choice, these dots are point estimates evaluated over an evenly-spaced grid within each bin. The default is dotsgrid=0, and only the point estimates at the mean of x within each bin are presented.

If true, the dots corresponding to the point estimates evaluated at the mean of x within each bin are presented. By default, they are presented, i.e., dotsgridmean=T.

line

a vector. line=c(p,s) sets a piecewise polynomial of degree p with s smoothness constraints for plotting as a "line". By default, the line is not included in the plot unless explicitly specified. Recommended specification is line=c(3,3), which adds a cubic B-spline estimate of the regression function of interest to the binned scatter plot.

linegrid

number of evaluation points of an evenly-spaced grid within each bin used for evaluation of the point estimate set by the line=c(p,s) option. The default is linegrid=20, which corresponds to 20 evenly-spaced evaluation points within each bin for fitting/plotting the line.

ci

a vector. ci=c(p,s) sets a piecewise polynomial of degree p with s smoothness constraints used for constructing confidence intervals. By default, the confidence intervals are not included in the plot unless explicitly specified. Recommended specification is ci=c(3,3), which adds confidence intervals based on cubic B-spline estimate of the regression function of interest to the binned scatter plot.

cigrid

number of evaluation points of an evenly-spaced grid within each bin used for evaluation of the point estimate set by the ci=c(p,s) option. The default is cigrid=1, which corresponds to 1 evenly-spaced evaluation point within each bin for confidence interval construction.

cigridmean

If true, the confidence intervals corresponding to the point estimates evaluated at the mean of x within each bin are presented. The default is cigridmean=T.

cb

a vector. cb=c(p,s) sets a the piecewise polynomial of degree p with s smoothness constraints used for constructing the confidence band. By default, the confidence band is not included in the plot unless explicitly specified. Recommended specification is cb=c(3,3), which adds a confidence band based on cubic B-spline estimate of the regression function of interest to the binned scatter plot.

cbgrid

number of evaluation points of an evenly-spaced grid within each bin used for evaluation of the point estimate set by the cb=c(p,s) option. The default is cbgrid=20, which corresponds to 20 evenly-spaced evaluation points within each bin for confidence interval construction.

polyreg

degree of a global polynomial regression model for plotting. By default, this fit is not included in the plot unless explicitly specified. Recommended specification is polyreg=3, which adds a cubic (global) polynomial fit of the regression function of interest to the binned scatter plot.

polyreggrid

number of evaluation points of an evenly-spaced grid within each bin used for evaluation of the point estimate set by the polyreg=p option. The default is polyreggrid=20, which corresponds to 20 evenly-spaced evaluation points within each bin for confidence interval construction.

polyregcigrid

number of evaluation points of an evenly-spaced grid within each bin used for constructing confidence intervals based on polynomial regression set by the polyreg=p option. The default is polyregcigrid=0, which corresponds to not plotting confidence intervals for the global polynomial regression approximation.

by

a vector containing the group indicator for subgroup analysis; both numeric and string variables are supported. When by is specified, binsreg implements estimation and inference by each subgroup separately, but produces a common binned scatter plot. By default, the binning structure is selected for each subgroup separately, but see the option samebinsby below for imposing a common binning structure across subgroups.

by colors an ordered list of colors for plotting each subgroup series defined by the option

by.

by symbols an ordered list of symbols for plotting each subgroup series defined by the option

by.

bylpatterns an ordered list of line patterns for plotting each subgroup series defined by the

option by.

legendTitle String, title of legend.

legendoff If true, no legend is added.

nbins number of bins for partitioning/binning of x. If not specified, the number of bins

is selected via the companion function binsregselect in a data-driven, optimal

way whenever possible.

binspos position of binning knots. The default is binspos="qs", which corresponds to

quantile-spaced binning (canonical binscatter). The other options are "es" for evenly-spaced binning, or a vector for manual specification of the positions of

inner knots (which must be within the range of x).

binsmethod method for data-driven selection of the number of bins. The default is binsmethod="dpi",

which corresponds to the IMSE-optimal direct plug-in rule. The other option is:

"rot" for rule of thumb implementation.

nbinsrot initial number of bins value used to construct the DPI number of bins selector.

If not specified, the data-driven ROT selector is used instead.

samebinsby if true, a common partitioning/binning structure across all subgroups specified

by the option by is forced. The knots positions are selected according to the option binspos and using the full sample. If nbins is not specified, then the number of bins is selected via the companion command binsregselect and

using the full sample.

nsims number of random draws for constructing confidence bands and hypothesis test-

ing. The default is nsims=500, which corresponds to 500 draws from a standard

Gaussian random vector of size [(p+1)\*J - (J-1)\*s].

simsgrid number of evaluation points of an evenly-spaced grid within each bin used for

evaluation of the supremum (or infimum) operation needed to construct confidence bands and hypothesis testing procedures. The default is simsgrid=20, which corresponds to 20 evenly-spaced evaluation points within each bin for

approximating the supremum (or infimum) operator.

simsseed seed for simulation.

vce Procedure to compute the variance-covariance matrix estimator. Options are

- "const" homoskedastic variance estimator.
- "HC0" heteroskedasticity-robust plug-in residuals variance estimator without weights.
- "HC1" heteroskedasticity-robust plug-in residuals variance estimator with hc1 weights. Default.
- "HC2" heteroskedasticity-robust plug-in residuals variance estimator with hc2 weights.
- "HC3" heteroskedasticity-robust plug-in residuals variance estimator with hc3 weights.

level nominal confidence level for confidence interval and confidence band estimation. Default is level=95.

noplot

If true, no plot produced.

dfcheck

adjustments for minimum effective sample size checks, which take into account number of unique values of x (i.e., number of mass points), number of clusters, and degrees of freedom of the different stat models considered. The default is dfcheck=c(20,30). See Cattaneo, Crump, Farrell and Feng (2021b) for more details.

masspoints

how mass points in x are handled. Available options:

- "on" all mass point and degrees of freedom checks are implemented. Default
- "noadjust" mass point checks and the corresponding effective sample size adjustments are omitted.
- "nolocalcheck" within-bin mass point and degrees of freedom checks are omitted
- "off" "noadjust" and "nolocalcheck" are set simultaneously.
- "veryfew" forces the function to proceed as if x has only a few number of mass points (i.e., distinct values). In other words, forces the function to proceed as if the mass point and degrees of freedom checks were failed.

weights

an optional vector of weights to be used in the fitting process. Should be NULL or a numeric vector. For more details, see 1m.

subset

Optional rule specifying a subset of observations to be used.

plotxrange

a vector. plotxrange=c(min,max) specifies a range of the x-axis for plotting. Observations outside the range are dropped in the plot.

plotyrange

a vector. plotyrange=c(min,max) specifies a range of the y-axis for plotting. Observations outside the range are dropped in the plot.

## Value

bins\_plot

A ggplot object for binscatter plot.

data.plot

A list containing data for plotting. Each item is a sublist of data frames for each group. Each sublist may contain the following data frames:

- data.dots Data for dots. It contains: x, evaluation points; bin, the indicator of bins; isknot, indicator of inner knots; mid, midpoint of each bin; and fit, fitted values.
- data.line Data for line. It contains: x, evaluation points; bin, the indicator of bins; isknot, indicator of inner knots; mid, midpoint of each bin; and fit, fitted values.
- data.ci Data for CI. It contains: x, evaluation points; bin, the indicator of bins; isknot, indicator of inner knots; mid, midpoint of each bin; ci.l and ci.r, left and right boundaries of each confidence intervals.
- data.cb Data for CB. It contains: x, evaluation points; bin, the indicator of bins; isknot, indicator of inner knots; mid, midpoint of each bin; cb.1 and cb.r, left and right boundaries of the confidence band.
- data.poly Data for polynomial regression. It contains: x, evaluation points; bin, the indicator of bins; isknot, indicator of inner knots; mid, midpoint of each bin; and fit, fitted values.
- data.polyci Data for confidence intervals based on polynomial regression. It contains: x, evaluation points; bin, the indicator of bins; isknot, indicator of inner knots; mid, midpoint of each bin; polyci.l and polyci.r, left and right boundaries of each confidence intervals.

20 binsregselect

cval.by A vector of critical values for constructing confidence band for each group.

opt

A list containing options passed to the function, as well as N.by (total sample size for each group), Ndist.by (number of distinct values in x for each group), Nclust.by (number of clusters for each group), and nbins.by (number of bins for each group), and byvals (number of distinct values in by).

## Author(s)

Matias D. Cattaneo, Princeton University, Princeton, NJ. <cattaneo@princeton.edu>.

Max H. Farrell, University of Chicago, Chicago, IL. <max.farrell@chicagobooth.edu>.

Yingjie Feng (maintainer), Princeton University, Princeton, NJ. <yingjief@princeton.edu>.

#### References

```
Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2021a: On Binscatter. Working Paper. Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2021b: Binscatter Regressions. Working Paper.
```

#### See Also

binsregselect, binstest.

## **Examples**

```
x <- runif(500); y <- sin(x)+rnorm(500)
## Binned scatterplot
binsreg(y,x)</pre>
```

binsregselect

Data-Driven IMSE-Optimal Partitioning/Binning Selection for Binscatter

## Description

binsregselect implements data-driven procedures for selecting the number of bins for binscatter estimation. The selected number is optimal in minimizing integrated mean squared error (IMSE).

#### Usage

```
binsregselect(y, x, w = NULL, data = NULL, deriv = 0, bins = c(0, 0), binspos = "qs", binsmethod = "dpi", nbinsrot = NULL, simsgrid = 20, savegrid = F, vce = "HC1", useeffn = NULL, cluster = NULL, dfcheck = c(20, 30), masspoints = "on", weights = NULL, subset = NULL, norotnorm = F, numdist = NULL, numclust = NULL)
```

binsregselect 21

#### **Arguments**

outcome variable. A vector. У

independent variable of interest. A vector. Х

control variables. A matrix, a vector or a formula. W

data an optional data frame containing variables used in the model.

derivative order of the regression function for estimation, testing and plotting. deriv

The default is deriv=0, which corresponds to the function itself.

bins a vector. bins=c(p,s) set a piecewise polynomial of degree p with s smooth-

> ness constraints for data-driven (IMSE-optimal) selection of the partitioning/binning scheme. The default is bins=c(0,0), which corresponds to piecewise constant

(canonical binscatter).

binspos position of binning knots. The default is binspos="qs", which corresponds to

quantile-spaced binning (canonical binscatter). The other options is "es" for

evenly-spaced binning.

binsmethod method for data-driven selection of the number of bins. The default is binsmethod="dpi",

which corresponds to the IMSE-optimal direct plug-in rule. The other option is:

"rot" for rule of thumb implementation.

initial number of bins value used to construct the DPI number of bins selector. nbinsrot

If not specified, the data-driven ROT selector is used instead.

number of evaluation points of an evenly-spaced grid within each bin used for simsgrid

> evaluation of the supremum (or infimum) operation needed to construct confidence bands and hypothesis testing procedures. The default is simsgrid=20, which corresponds to 20 evenly-spaced evaluation points within each bin for

approximating the supremum (or infimum) operator.

savegrid If true, a data frame produced containing grid.

procedure to compute the variance-covariance matrix estimator. Options are

• "const" homoskedastic variance estimator.

- "HC0" heteroskedasticity-robust plug-in residuals variance estimator without weights.
- "HC1" heteroskedasticity-robust plug-in residuals variance estimator with hc1 weights. Default.
- "HC2" heteroskedasticity-robust plug-in residuals variance estimator with hc2 weights.
- "HC3" heteroskedasticity-robust plug-in residuals variance estimator with hc3 weights.

effective sample size to be used when computing the (IMSE-optimal) number of useeffn

bins. This option is useful for extrapolating the optimal number of bins to larger

(or smaller) datasets than the one used to compute it.

cluster cluster ID. Used for compute cluster-robust standard errors.

dfcheck adjustments for minimum effective sample size checks, which take into account

> number of unique values of x (i.e., number of mass points), number of clusters, and degrees of freedom of the different stat models considered. The default is dfcheck=c(20,30). See Cattaneo, Crump, Farrell and Feng (2021b) for more

how mass points in x are handled. Available options: masspoints

> • "on" all mass point and degrees of freedom checks are implemented. Default.

vce

22 binsregselect

• "noadjust" mass point checks and the corresponding effective sample size adjustments are omitted.

- "nolocalcheck" within-bin mass point and degrees of freedom checks are omitted.
- "off" "noadjust" and "nolocalcheck" are set simultaneously.
- "veryfew" forces the function to proceed as if x has only a few number of mass points (i.e., distinct values). In other words, forces the function to proceed as if the mass point and degrees of freedom checks were failed.

weights an optional vector of weights to be used in the fitting process. Should be NULL

or a numeric vector. For more details, see 1m.

subset optional rule specifying a subset of observations to be used.

norotnorm if true, a uniform density rather than normal density used for ROT selection.

numdist number of distinct for selection. Used to speed up computation.

numclust number of clusters for selection. Used to speed up computation.

#### Value

nbinsrot.poly ROT number of bins, unregularized.
nbinsrot.regul ROT number of bins, regularized.
nbinsrot.uknot ROT number of bins, unique knots.

nbinsdpi DPI number of bins.

nbinsdpi.uknot DPI number of bins, unique knots.

opt A list containing options passed to the function, as well as total sample size n,

number of distinct values Ndist in x, and number of clusters Nclust.

data.grid A data frame containing grid.

#### Author(s)

Matias D. Cattaneo, Princeton University, Princeton, NJ. <cattaneo@princeton.edu>.

Richard K. Crump, Federal Reserve Bank of New York, New York, NY. <richard.crump@ny.frb.org>.

Max H. Farrell, University of Chicago, Chicago, IL. <max.farrell@chicagobooth.edu>.

Yingjie Feng (maintainer), Princeton University, Princeton, NJ. <yingjief@princeton.edu>.

#### References

Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2021a: On Binscatter. Working Paper. Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2021b: Binscatter Regressions. Working Paper.

#### See Also

binsreg, binstest.

# Examples

```
x <- runif(500); y <- sin(x)+rnorm(500)
est <- binsregselect(y,x)
summary(est)</pre>
```

binstest	Data-Driven Nonparametric Shape Restriction and Parametric Model
	Specification Testing using Binscatter

#### **Description**

binstest implements binscatter-based hypothesis testing procedures for parametric functional forms of and nonparametric shape restrictions on the regression function estimators, following the results in Cattaneo, Crump, Farrell and Feng (2021a). If the binning scheme is not set by the user, the companion function binsregselect is used to implement binscatter in a data-driven way and inference procedures are based on robust bias correction. Binned scatter plots based on different methods can be constructed using the companion functions binsreg, binsqreg or binsglm.

## Usage

```
binstest(y, x, w = NULL, data = NULL, estmethod = "reg",
  family = gaussian(), quantile = NULL, deriv = 0, testmodel = c(3, 3),
  testmodelparfit = NULL, testmodelpoly = NULL, testshape = c(3, 3),
  testshape1 = NULL, testshaper = NULL, testshape2 = NULL, lp = Inf,
 bins = c(0, 0), nbins = NULL, binspos = "qs", binsmethod = "dpi",
 nbinsrot = NULL, nsims = 500, simsgrid = 20, simsseed = 666,
  vce = NULL, cluster = NULL, dfcheck = c(20, 30), masspoints = "on",
 weights = NULL, subset = NULL, numdist = NULL, numclust = NULL, ...)
```

### **Arguments**

У	outcome variable. A vector.
X	independent variable of interest. A vector.
W	control variables. A matrix, a vector or a formula.
data	an optional data frame containing variables used in the model.
estmethod	estimation method. The default is estmethod="reg" for tests based on binscatter least squares regression. Other options are "qreg" for quantile regression and "glm" for generalized linear regression. If estmethod="glm", the option family must be specified.
family	a description of the error distribution and link function to be used in the generalized linear model when estmethod="glm". (See family for details of family functions.)
quantile	the quantile to be estimated. A number strictly between 0 and 1.
deriv	derivative order of the regression function for estimation, testing and plotting. The default is deriv=0, which corresponds to the function itself.
testmodel	a vector. testmodel=c(p,s) sets a piecewise polynomial of degree p with s smoothness constraints for parametric model specification testing. The default is testmodel=c(3,3), which corresponds to a cubic B-spline estimate of the regression function of interest for testing against the fitting from a parametric model specification.
testmodelparfi	t

testmodelparfit

a data frame or matrix which contains the evaluation grid and fitted values of the model(s) to be tested against. The column contains a series of evaluation points

at which the binscatter model and the parametric model of interest are compared with each other. Each parametric model is represented by other columns, which must contain the fitted values at the corresponding evaluation points.

testmodelpoly degree of a global polynomial model to be tested against.

testshape a vector. testshape=c(p,s) sets a piecewise polynomial of degree p with s

smoothness constraints for nonparametric shape restriction testing. The default is testshape=c(3,3), which corresponds to a cubic B-spline estimate of the

regression function of interest for one-sided or two-sided testing.

testshapel a vector of null boundary values for hypothesis testing. Each number a in the

vector corresponds to one boundary of a one-sided hypothesis test to the left of

the form H0:  $\sup_x mu(x) \le a$ .

testshaper a vector of null boundary values for hypothesis testing. Each number a in the

vector corresponds to one boundary of a one-sided hypothesis test to the right of

the form H0:  $\inf_x mu(x) >= a$ .

testshape2 a vector of null boundary values for hypothesis testing. Each number a in the

vector corresponds to one boundary of a two-sided hypothesis test ofthe form

H0:  $\sup_x |mu(x)-a|=0$ .

lp an Lp metric used for (two-sided) parametric model specification testing and/or

shape restriction testing. The default is lp=Inf, which corresponds to the supnorm of the t-statistic. Other options are lp=q for a positive integer q.

bins Degree and smoothness for bin selection.

nbins number of bins for partitioning/binning of x. If not specified, the number of bins

is selected via the companion function binsregselect in a data-driven, optimal

way whenever possible.

binspos position of binning knots. The default is binspos="qs", which corresponds to

quantile-spaced binning (canonical binscatter). The other options are "es" for evenly-spaced binning, or a vector for manual specification of the positions of

inner knots (which must be within the range of x).

binsmethod method for data-driven selection of the number of bins. The default is binsmethod="dpi",

which corresponds to the IMSE-optimal direct plug-in rule. The other option is:

"rot" for rule of thumb implementation.

nbinsrot initial number of bins value used to construct the DPI number of bins selector.

If not specified, the data-driven ROT selector is used instead.

nsims number of random draws for constructing confidence bands and hypothesis test-

ing. The default is nsims=500, which corresponds to 500 draws from a standard

Gaussian random vector of size [(p+1)\*J - (J-1)\*s].

simsgrid number of evaluation points of an evenly-spaced grid within each bin used for

evaluation of the supremum (or infimum) operation needed to construct confidence bands and hypothesis testing procedures. The default is simsgrid=20, which corresponds to 20 evenly-spaced evaluation points within each bin for

approximating the supremum (or infimum) operator.

simsseed seed for simulation.

vce procedure to compute the variance-covariance matrix estimator. For least squares

regression and generalized linear regression, the allowed options are the same as that for binsreg or binsqreg. For quantile regression, the allowed options

are the same as that for binsqreg.

dfcheck

adjustments for minimum effective sample size checks, which take into account number of unique values of x (i.e., number of mass points), number of clusters, and degrees of freedom of the different stat models considered. The default is dfcheck=c(20,30). See Cattaneo, Crump, Farrell and Feng (2021b) for more details.

masspoints

how mass points in x are handled. Available options:

- "on" all mass point and degrees of freedom checks are implemented. Default.
- "noadjust" mass point checks and the corresponding effective sample size adjustments are omitted.
- "nolocalcheck" within-bin mass point and degrees of freedom checks are omitted.
- "off" "noadjust" and "nolocalcheck" are set simultaneously.
- "veryfew" forces the function to proceed as if x has only a few number of mass points (i.e., distinct values). In other words, forces the function to proceed as if the mass point and degrees of freedom checks were failed.

weights

an optional vector of weights to be used in the fitting process. Should be NULL or a numeric vector. For more details, see 1m.

subset

optional rule specifying a subset of observations to be used.

numdist

Number of distinct for selection. Used to speed up computation.

numclust

Number of clusters for selection. Used to speed up computation.

. . .

optional arguments to control bootstrapping if estmethod="qreg" and vce="boot".

See boot.rq.

#### Value

testshapeL Results for testshapel, including: testvalL, null boundary values; stat. shapeL, test statistics; and pval. shapeL, p-value. Results for testshaper, including: testvalR, null boundary values; stat.shapeR, testshapeR test statistics; and pval. shapeR, p-value. testshape2 Results for testshape2, including: testval2, null boundary values; stat.shape2, test statistics; and pval. shape2, p-value. testpoly Results for testmodelpoly, including: testpoly, the degree of global polynomial; stat.poly, test statistic; pval.poly, p-value. testmodel Results for testmodelparfit, including: stat.model, test statistics; pval.model, p-values. A list containing options passed to the function, as well as total sample size n, opt number of distinct values Ndist in x, number of clusters Nclust, and number of bins nbins.

## Author(s)

Matias D. Cattaneo, Princeton University, Princeton, NJ. <cattaneo@princeton.edu>.

Richard K. Crump, Federal Reserve Bank of New York, New York, NY. <richard.crump@ny.frb.org>.

Max H. Farrell, University of Chicago, Chicago, IL. <max.farrell@chicagobooth.edu>.

Yingjie Feng (maintainer), Princeton University, Princeton, NJ. <yingjief@princeton.edu>.

## References

Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2021a: On Binscatter. Working Paper. Cattaneo, M. D., R. K. Crump, M. H. Farrell, and Y. Feng. 2021b: Binscatter Regressions. Working Paper.

## See Also

binsreg, binsregselect.

# Examples

```
x <- runif(500); y <- sin(x)+rnorm(500)
est <- binstest(y,x, testmodelpoly=1)
summary(est)</pre>
```

# **Index**

```
_PACKAGE (binsreg-package), 2
binsglm, 2, 2, 7, 23
binspwc, 2, 7
binsqreg, 2, 7, 9, 11, 23, 24
binsreg, 2, 7, 9, 15, 22-24, 26
binsreg-package, 2
binsregselect, 2, 3, 5, 7, 9-11, 13, 15, 16, 18, 20, 20, 23, 26
binstest, 2, 3, 7, 10, 11, 15, 16, 20, 22, 23
boot.rq, 10, 14, 25
family, 3, 8, 23
formula, 3, 8, 11, 16, 21, 23
lm, 6, 9, 14, 19, 22, 25
summary.rq, 13
```