## Operating System Concepts

Lecture 2: Interaction with Hardware

Omid Ardakanian oardakan@ualberta.ca University of Alberta

#### Today's class

- Why study OS?
- Interaction between OS and hardware
  - CPU, registers, memory, device controllers, interrupt architecture,


## Why study OS?

- knowledge of how OS works is crucial for efficient and secure programming
  - OS code is efficient (runs fast using minimum resources), reliable (fails infrequently),
     complex (addresses various timing and concurrency issues), and secure
- studying OS is studying the design of large software systems
  - Windows Vista is more than 50 million lines of code
- studying OS makes you a better programmer!
  - teaches you how to make tradeoffs between performance and usability, performance and design simplicity, ....
  - teaches you how to manage complexity through appropriate abstractions (e.g., file system, process)
- it's an active area of research!
  - new application spaces: cloud, mobile and edge systems, embedded and real-time systems
  - SOSP: ACM Symposium on Operating Systems Principles
  - OSDI: USENIX Symposium on Operating Systems Design and Implementation

## OS is everywhere!



**Desktop & Laptop Computers** 




**Mobile Devices** 






O. Ardakanian, CMPUT379, 2025

#### Example: the client-server model



- each client can send a request to the server to perform some operation (e.g., running a query)
- server performs the operation upon receiving the request, and sends the results back to the client

#### Example: the client-server model



#### You will learn how OS

- allows multiple (local or remote) user programs to communicate with each other, sharing data
- handles concurrent requests
- supports access to shared data using atomic operations
- protects the system against malicious scripts


# Interfacing Hardware

### Components

- CPUs, registers, 3 levels of cache, memory, disk
- System bus connecting CPUs, controllers (disk, I/O), and memory
- I/O devices and controllers
  - more than one device can be attached to a single controller
  - CPU and device controllers run in parallel, yet they compete for memory cycles!
  - controller maintains local buffer and special-purpose registers
  - for each device controller, there's a device driver in OS that knows how to interact with the device controller (e.g. loading its registers before I/O begins)
  - controller notifies device driver (OS) via an interrupt (signal sent to CPU)

### Memory hierarchy — recap


- CPU fetches and runs instructions one at a time
  - registers are CPU's workspace
- Programmers desire a large amount of fast memory (expensive!)
  - an economical solution: a memory hierarchy organized into several levels;
     each level is smaller, faster, and more expensive per byte than the next
  - it takes advantage of locality and cost-performance tradeoffs



Memory hierarchy for a desktop and a laptop


## Memory hierarchy — recap

- Storage systems primarily differ in speed (access time), size and volatility
- Volatile storage loses its content when power is lost




#### Single-processor vs. multiprocessor systems

- Single-processor system contains a single general-purpose processor with one processing core
  - there might be several device-specific processors (for disk, keyboard, and graphics controllers)
     but they do not run user processes
- Multiprocessor system contains two (or more) processors each with a singlecore CPU
  - each processor has its own set of registers and cache but they all share the main memory
  - multiple processes can run simultaneously
    - increased throughput
  - load balancing might be necessary



## Multicore systems

- Multicore system has multiple cores residing on a single processor chip
  - each core has its own registers and L1 cache; L2 cache is shared between processing cores
  - it can be more efficient than a multiprocessor system, because on-chip communication is faster than inter-chip communication, and uses much less power
- N cores appear to OS as N CPUs



#### Multiprogramming and multitasking

#### Multiprogramming

- OS keeps several processes in memory simultaneously
- OS picks one of them for execution (scheduling);
   when that process terminates or has to wait (e.g., for I/O), OS runs another process on the CPU
- Unlike a non-multiprogrammed system, the CPU wouldn't be idle as long as at least one process has to execute
- This increases CPU utilization
- Multitasking is an extension of multiprogramming
  - CPU executes multiple processes by switching between them frequently to ensure reasonable response time (typically less than 1 second)
  - Choosing the process that runs next requires scheduling

process 2

process 3

process 4

max

#### How does multiprogramming work?

- When a process waits for I/O, multiprogramming allows CPU to execute another process, overlapping I/O and computation
  - the process waiting for I/O is added to the waiting queue of the I/O device (e.g., terminal, disks, video board, printer, network card)

#### Buffering

- data fills the local buffer of I/O device
- Interrupt handling
  - I/O events trigger a signal (known as interrupt)
  - control is then transferred to the OS
  - OS adds the process back into the ready queue

#### Interrupt


- <u>Definition</u>: a signal sent by a device controller to CPU's interrupt-request-line to inform that an event has occurred (e.g., I/O request completed)
  - each device controller has its own small processor that executes asynchronously with the main CPU
  - CPU senses the interrupt-request-line after executing every instruction
  - if a controller raises an interrupt, CPU stops whatever it was doing, catches the interrupt (reads the interrupt number), and dispatches it to the interrupt-handler (aka interrupt service routine) through the in-memory interrupt vector containing the starting addresses of all handlers;
    - interrupt number is an index into the interrupt vector
  - the interrupt-specific handler clears the interrupt by servicing the device
  - the handler also saves the state information of the interrupted program by storing registers and program counter; it restores the state after clearing the interrupt
    - necessary because the interrupt handler may need to modify the CPU state

0: 0x2ff080000 keyboard 1: 0x2ff100000 mouse 2: 0x2ff100480 timer 3: 0x2ff123010 Disk 1

starting address of the interrupt service routine

#### Interrupt-based asynchronous I/O

After I/O starts, control returns to user program without waiting for I/O completion



#### Interrupt handling — other considerations

- How to defer interrupt handling during the execution of a critical instruction sequence? two interrupt-request-lines
  - CPU has two interrupt-request-lines: non-maskable and maskable
  - device controllers raise an interrupt through the maskable line, CPU turns off this line before running critical instructions
  - the non-maskable line is reserved for hardware faults, such as unrecoverable memory errors
- What if there are more interrupt handlers than addresses available in the interrupt vector? interrupt chaining

each element in the interrupt vector points to the head of a list of interrupt handlers;
 handlers in this list are called one by one until the interrupt is cleared by one handler

0: 0x2ff080000 1: 0x2ff100000 2: 0x2ff100480 3: 0x2ff123010

Interrupt

#### Interrupt handling — other considerations

- How to defer interrupt handling during the execution of a critical instruction sequence? two interrupt-request-lines
  - CPU has two interrupt-request-lines: non-maskable and maskable
  - device controllers raise an interrupt through the maskable line
  - the non-maskable line is reserved for hardware faults such as unrecoverable memory errors
- What if there are more interrupt handlers than addresses available in the interrupt vector? interrupt chaining
  - each element in the interrupt vector points to the head of a list of interrupt handlers; handlers in this list are called one by one until the interrupt is cleared by one handler
- How to distinguish urgent events from non-urgent ones? interrupt priority levels
  - CPU defers the handling of low-level interrupts to handle a high-level interrupt

#### Trap

 <u>Definition</u>: a trap or exception is a <u>software-generated</u> interrupt caused by an error (e.g., division by zero) or a user request for OS service (i.e. <u>system call</u>)

0: 0x00080000

1: 0x00100000

2: 0x00100480

3: 0x00123010

Illegal address

Memory violation

Illegal instruction

System call

**Trap Vector** 

#### Protection

- Hardware has a status bit that indicates the current mode (user or kernel)
  - there could be more than two operation modes e.g., ARMv8 systems have seven modes
  - user programs run in the user mode
  - kernel code runs in the kernel mode with **full privileges** of hardware
- Operation modes provide the means for protecting OS from errant users
  - code could be buggy or malicious
- Examples of privileged instructions are I/O control, timer management, interrupt management; they can only run in the kernel mode
- Invoking a system call allows user program to run privileged instructions

