# **Virtual Memory**

#### **Chapter 9: Virtual Memory**

- Background
- Demand Paging
- Copy-on-Write
- Page Replacement
- Allocation of Frames
- Thrashing
- Memory-Mapped Files
- Allocating Kernel Memory
- Other Considerations
- Operating-System Examples

#### **Objectives**

- □ To describe the benefits of a virtual memory system
- ☐ To explain the concepts of demand paging, page-replacement algorithms, and allocation of page frames
- To discuss the principle of the working-set model
- To examine the relationship between shared memory and memory-mapped files
- □ To explore how kernel memory is managed

#### **Background**

- Code needs to be in memory to execute, but entire program rarely used
  - Error code, unusual routines, large data structures
- Entire program code not needed at same time
- Consider ability to execute partially-loaded program
  - Program no longer constrained by limits of physical memory
  - Each program takes less memory while running -> more programs run at the same time
    - Increased CPU utilization and throughput with no increase in response time or turnaround time
  - Less I/O needed to load or swap programs into memory -> each user program runs faster


#### **Background (Cont.)**

- Virtual memory separation of user logical memory from physical memory
  - Only part of the program needs to be in memory for execution
  - Logical address space can therefore be much larger than physical address space
  - Allows address spaces to be shared by several processes
  - More programs running concurrently
  - Less I/O needed to load or swap processes

#### **Background (Cont.)**


- □ Virtual address space logical view of how process is stored in memory
  - Usually start at address 0, contiguous addresses until end of space
  - Meanwhile, physical memory organized in page frames
  - MMU must map logical to physical
- Virtual memory can be implemented via:
  - Demand paging
  - Demand segmentation

#### **Virtual Memory That is Larger Than Physical Memory**




#### Virtual-address Space

- ☐ Usually design logical address space for stack to start at Max logical address and grow "down" while heap grows "up"
  - Maximizes address space use
  - Unused address space between the two is hole
    - No physical memory needed until heap or stack grows to a given new page
- ☐ Enables **sparse** address spaces with holes left for growth, dynamically linked libraries, etc
- System libraries shared via mapping into virtual address space




# **Shared Library Using Virtual Memory**



#### **Demand Paging**

- Could bring entire process into memory at load time
- Or bring a page into memory only when it is needed
  - Less I/O needed, no unnecessaryI/O
  - Less memory needed
  - Faster response
  - More users
- Similar to paging system with swapping (diagram on right)
- □ Page is needed ⇒ reference to it
  - □ invalid reference ⇒ abort
  - □ not-in-memory ⇒ bring to memory
- Lazy swapper never swaps a page into memory unless page will be needed
  - Swapper that deals with pages is a pager




#### **Basic Concepts**

- With swapping, pager guesses which pages will be used before swapping out again
- Instead of swapping, pager brings in only those pages into memory
- How to determine that set of pages?
  - Need new MMU functionality to implement demand paging
- If pages needed are already memory resident
  - No difference from non demand-paging
- If page needed and not memory resident
  - Need to detect and load the page into memory from storage


#### **Valid-Invalid Bit**

- With each page table entry a valid–invalid bit is associated (v ⇒ in-memory – memory resident, i ⇒ not-in-memory)
- Initially valid—invalid bit is set to i on all entries
- Example of a page table snapshot:



□ During MMU address translation, if valid—invalid bit in page table entry is i ⇒ page fault

#### Page Table When Some Pages Are Not in Main Memory




#### Page Fault

If there is a reference to a page, first reference to that page will trap to operating system:

#### page fault

- 1. Operating system looks at another table to decide:
  - □ Invalid reference ⇒ abort
  - Just not in memory
- Find free frame
- 3. Swap page into frame via scheduled disk operation
- Reset tables to indicate page now in memory
   Set validation bit = v
- 5. Restart the instruction that caused the page fault

# **Steps in Handling a Page Fault**



#### **Aspects of Demand Paging**

- Extreme case start process with no pages in memory
  - OS sets instruction pointer to first instruction of process, nonmemory-resident -> page fault
  - And for every page, page fault on first access
  - Pure demand paging
- Actually, a given instruction could access multiple pages -> multiple page faults
  - Consider fetch and decode of instruction which adds 2 numbers(C=A+B) from memory and stores result back to memory. If page fault occurs at storing C, then instruction restart includes fetch and decode of instruction, fetching operands again.
  - Pain decreased because of locality of reference
- Hardware support needed for demand paging
  - Page table with valid / invalid bit
  - Secondary memory (swap device with swap space)
  - Instruction restart

#### **Performance of Demand Paging**

- Stages in Demand Paging (worse case)
- 1. Trap to the operating system
- 2. Save the user registers and process state
- 3. Determine that the interrupt was a page fault
- 4. Check that the page reference was legal and determine the location of the page on the disk
- 5. Issue a read from the disk to a free frame:
  - 1. Wait in a queue for this device until the read request is serviced
  - 2. Wait for the device seek and/or latency time
  - 3. Begin the transfer of the page to a free frame
- 6. While waiting, allocate the CPU to some other user
- 7. Receive an interrupt from the disk I/O subsystem (I/O completed)
- 8. Save the registers and process state for the other user
- 9. Determine that the interrupt was from the disk
- 10. Correct the page table and other tables to show page is now in memory
- 11. Wait for the CPU to be allocated to this process again
- 12. Restore the user registers, process state, and new page table, and then resume the interrupted instruction

# Performance of Demand Paging (Cont.)

- Three major activities
  - Service the interrupt careful coding means just several hundred instructions needed
  - Read the page lots of time
  - Restart the process again just a small amount of time
- □ Page Fault Rate  $0 \le p \le 1$ 
  - $\Box$  if p = 0 no page faults
  - $\Box$  if p = 1, every reference is a fault
- Effective Access Time (EAT)

```
» EAT = (1 - p) x memory access time + p x page fault time
i.e., EAT = (1 - p) x memory access
+ p (page fault overhead
```

+ swap page out

+ swap page in )

#### **Demand Paging Example**

- Memory access time = 200 nanoseconds
- Average page-fault service time = 8 milliseconds
- □ EAT =  $(1 p) \times 200 + p$  (8 milliseconds) =  $(1 - p) \times 200 + p \times 8,000,000$ =  $200 + p \times 7,999,800$
- ☐ If one access out of 1,000 causes a page fault, then EAT = 8.2 microseconds.

This is a slowdown by a factor of 40!!

- □ If want performance degradation < 10 percent
  - 220 > 200 + 7,999,800 x p20 > 7,999,800 x p
  - p < .000025
  - < one page fault in every 400,000 memory accesses</p>


#### **Demand Paging Optimizations**

- □ Swap space I/O faster than file system I/O even if on the same device
  - Swap allocated in larger chunks, less management needed than file system
- Copy entire process image to swap space at process load time
  - Then page in and out of swap space
  - Used in older BSD Unix
- Mobile systems
  - Typically don't support swapping
  - Instead, demand page from file system and reclaim read-only pages (such as code)


#### **Copy-on-Write**

- Copy-on-Write (COW) allows both parent and child processes to initially share the same pages in memory
  - If either process modifies a shared page, only then is the page copied
- COW allows more efficient process creation as only modified pages are copied
- In general, free pages are allocated from a pool of zero-fill-on-demand pages
  - Pool should always have free frames for fast demand page execution
    - Don't want to have to free a frame as well as other processing on page fault
  - Why zero-out a page before allocating it?

# **Before Process 1 Modifies Page C**



# After Process 1 Modifies Page C




#### What Happens if There is no Free Frame?

- Memory frames used up by process pages
- □ Also, frames are demanded by the kernel, I/O buffers, etc
- How much to allocate to each?
- Overallocation of memory to processes results in no free frame when there is a page fault
  - Options for the OS: terminate process? swap out? replace the page?
  - Page replacement find some page in memory, but not really in use, page it out
    - Performance want an algorithm which will result in minimum number of page faults
- Same page may be brought into memory several times

#### Page Replacement

- Prevent over-allocation of memory by modifying page-fault service routine to include page replacement
- □ Use modify (dirty) bit to reduce overhead of page transfers only modified pages are written to disk
- Page replacement completes separation between logical memory and physical memory – large virtual memory can be provided on a smaller physical memory

# **Need For Page Replacement**



for user 2


for user 2

#### **Basic Page Replacement**

- 1. Find the location of the desired page on disk
- 2. Find a free frame:
  - If there is a free frame, use it
  - If there is no free frame, use a page replacement algorithm to select a victim frame
    - Write victim frame to disk if dirty
- 3. Bring the desired page into the (newly) free frame; update the page and frame tables
- 4. Continue the process by restarting the instruction that caused the trap

Note: now potentially 2 page transfers for page fault – increasing EAT

# Page Replacement




#### Page and Frame Replacement Algorithms

- ☐ Frame-allocation algorithm determines
  - How many frames to give each process
  - Which frames to replace
- Page-replacement algorithm
  - Want lowest page-fault rate on both first access and re-access
- Evaluate algorithm by running it on a particular string of memory references (reference string) and computing the number of page faults on that string
  - String is just page numbers, not full addresses
  - Repeated access to the same page does not cause a page fault
  - Results depend on number of frames available
- In all our examples, the reference string of referenced page numbers is


7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1

#### **Graph of Page Faults Versus The Number of Frames**



#### First-In-First-Out (FIFO) Algorithm


- □ Reference string: **7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1**
- □ 3 frames (3 pages can be in memory at a time per process)



15 page faults


- □ Can vary by reference string: consider 1,2,3,4,1,2,5,1,2,3,4,5
  - Adding more frames can cause more page faults!
    - Belady's Anomaly
- How to track ages of pages?
  - Just use a FIFO queue

# FIFO Illustrating Belady's Anomaly




#### **Optimal Algorithm**

- Replace page that will not be used for longest period of time
  - 9 is optimal for the example
- □ How do you know this?
  - Can't read the future
- Used for measuring how well your algorithm performs



#### Least Recently Used (LRU) Algorithm

- Use past knowledge rather than future
- Replace page that has not been used in the most amount of time
- Associate time of last use with each page




- □ 12 faults better than FIFO but worse than OPT
- Generally good algorithm and frequently used
- But how to implement?

#### LRU Algorithm (Cont.)

- Counter implementation
  - Every page entry has a counter; every time page is referenced through this entry, copy the clock into the counter
  - When a page needs to be changed, look at the counters to find smallest value
    - Search through table needed
- Stack implementation
  - Keep a stack of page numbers in a double link form:
  - Page referenced:
    - move it to the top
    - requires 6 pointers to be changed
  - But each update more expensive
  - No search for replacement
- LRU and OPT are cases of stack algorithms that don't have Belady's Anomaly

#### **Use Of A Stack to Record Most Recent Page References**






## **LRU Approximation Algorithms**

- LRU needs special hardware and still slow
- Reference bit
  - With each page associate a bit, initially = 0
  - When page is referenced bit set to 1
  - Replace any with reference bit = 0 (if one exists)
    - We do not know the order, however
- Second-chance algorithm
  - Generally FIFO, plus hardware-provided reference bit
  - Clock replacement
  - If page to be replaced has
    - Reference bit = 0 -> replace it
    - reference bit = 1 then:
      - set reference bit 0, leave page in memory
      - replace next page, subject to same rules

#### Second-Chance (clock) Page-Replacement Algorithm



#### **Enhanced Second-Chance Algorithm**

- Improve algorithm by using reference bit and modify bit (if available) in concert
- Take ordered pair (reference, modify)
- 1. (0, 0) neither recently used not modified best page to replace
- 2. (0, 1) not recently used but modified not quite as good, must write out before replacement
- 3. (1, 0) recently used but clean probably will be used again soon
- 4. (1, 1) recently used and modified probably will be used again soon and need to write out before replacement

#### **Counting Algorithms**

- Keep a counter of the number of references that have been made to each page
  - Not common
- Lease Frequently Used (LFU) Algorithm: replaces page with smallest count
- Most Frequently Used (MFU) Algorithm: based on the argument that the page with the smallest count was probably just brought in and has yet to be used

## **Page-Buffering Algorithms**

- Keep a pool of free frames, always
  - Then frame available when needed, not found at fault time
  - Read page into free frame and select victim to evict and add to free pool
  - When convenient, evict victim
- Possibly, keep list of modified pages
  - When backing store otherwise idle, write pages there and set to non-dirty
- Possibly, keep free frame contents intact and note what is in them
  - If referenced again before reused, no need to load contents again from disk
  - Generally useful to reduce penalty if wrong victim frame selected

#### **Allocation of Frames**

- Each process needs *minimum* number of frames
- □ Two major allocation schemes
  - fixed allocation
  - priority allocation
- Many variations

#### **Fixed Allocation**

- Equal allocation For example, if there are 100 frames (after allocating frames for the OS) and 5 processes, give each process 20 frames
  - Keep some as free frame buffer pool
- Proportional allocation Allocate according to the size of process
  - Dynamic as degree of multiprogramming, process sizes change

$$-s_i = \text{size of process } p_i$$

$$-S = \sum s_i$$

-m = total number of frames

$$-a_i =$$
allocation for  $p_i = \frac{s_i}{S} \times m$ 

$$m = 64$$

$$s_1 = 10$$

$$s_2 = 127$$

$$a_1 = \frac{10}{137} \times 62 \approx 4$$

$$a_2 = \frac{127}{137} \times 62 \approx 57$$

# **Priority Allocation**

- Use a proportional allocation scheme using priorities rather than size
- □ If process P<sub>i</sub> generates a page fault,
  - select for replacement one of its frames
  - select for replacement a frame from a process with lower priority number


#### Global vs. Local Allocation

- ☐ Global replacement process selects a replacement frame from the set of all frames; one process can take a frame from another
  - But then process execution time can vary greatly
  - But greater throughput so more common
- Local replacement each process selects from only its own set of allocated frames
  - More consistent per-process performance
  - But possibly underutilized memory

#### **Thrashing**

- ☐ If a process does not have "enough" pages, the page-fault rate is very high
  - Page fault to get page
  - Replace existing frame
  - But quickly need replaced frame back
  - This leads to:
    - Low CPU utilization
    - Operating system thinking that it needs to increase the degree of multiprogramming
    - Another process added to the system
- □ Thrashing = a process is busy swapping pages in and out


# **Thrashing (Cont.)**



#### **Demand Paging and Thrashing**

- Why does demand paging work?
  - **Locality model** 
    - Process migrates from one locality to another
    - Localities may overlap
- Why does thrashing occur?Σ size of locality > total memory size
  - Limit effects by using local or priority page replacement


#### **Locality In A Memory-Reference Pattern**



## **Working-Set Model**

- $\Delta$  = working-set window = a fixed number of page references Example: 10 references
- □ WSS<sub>i</sub> (working set size of Process  $P_i$ ) = total number of pages referenced in the most recent  $\Delta$  (varies in time)
  - $\square$  if  $\Delta$  too small will not encompass entire locality
  - $\square$  if  $\triangle$  too large will encompass several localities
  - □ if  $\Delta = \infty \Rightarrow$  will encompass entire program
- $\square$   $D = \Sigma WSS_i \equiv \text{total demand frames}$ 
  - Approximation of locality
- □ if D > m (total number of available frames)  $\Rightarrow$  Thrashing
- Policy if D > m, then suspend or swap out one of the processes page reference table

... 2615777751623412344434344413234443444...




# **Keeping Track of the Working Set**

- Approximate with interval timer + a reference bit
- $\square$  Example:  $\Delta = 10,000$ 
  - □ Timer interrupts after every 5000 time units
  - Keep in memory 2 bits for each page
  - Whenever a timer interrupts copy and sets the values of all reference bits to 0
  - If there is a page fault, check the reference bit and the two inmemory bits
    - If one of the bits in memory = 1 then page was used in the last 10000 to 15000 interval ⇒ page in working set
- Why is this not completely accurate?
- □ Improvement = 10 bits and interrupt every 1000 time units


# **Page-Fault Frequency**

- More direct approach than WSS
- Establish "acceptable" page-fault frequency (PFF) rate and use local replacement policy
  - If actual rate too low, process loses frame
  - If actual rate too high, process gains frame



#### **Working Sets and Page Fault Rates**

- n Direct relationship between working set of a process and its page-fault rate
- n Working set changes over time
- n Peaks and valleys over time



# **End of Chapter 9**