C1W3_Assignment

December 9, 2020

1 Week 3 Assignment: Implement a Quadratic Layer

In this week's programming exercise, you will build a custom quadratic layer which computes $y = ax^2 + bx + c$. Similar to the ungraded lab, this layer will be plugged into a model that will be trained on the MNIST dataset. Let's get started!

1.0.1 Imports

```
[2]: import tensorflow as tf from tensorflow.keras.layers import Layer import utils
```

1.0.2 Define the quadratic layer (TODO)

Implement a simple quadratic layer. It has 3 state variables: a, b and c. The computation returned is $ax^2 + bx + c$. Make sure it can also accept an activation function.

__init__

- call super(my_fun, self) to access the base class of my_fun, and call the __init__() function to initialize that base class. In this case, my_fun is SimpleQuadratic and its base class is Layer.
- self.units: set this using one of the function parameters.
- self.activation: The function parameter activation will be passed in as a string. To get the tensorflow object associated with the string, please use tf.keras.activations.get()

build The following are suggested steps for writing your code. If you prefer to use fewer lines to implement it, feel free to do so. Either way, you'll want to set self.a, self.b and self.c.

- a_init: set this to tensorflow's random_normal_initializer()
- a_init_val: Use the random_normal_initializer() that you just created and invoke it, setting the shape and dtype.

- The shape of a should have its row dimension equal to the last dimension of input_shape, and its column dimension equal to the number of units in the layer.
- This is because you'll be matrix multiplying x^2 * a, so the dimensions should be compatible.
- set the dtype to 'float32'
- self.a: create a tensor using tf. Variable, setting the initial_value and set trainable to True.
- b_init, b_init_val, and self.b: these will be set in the same way that you implemented a_init, a_init_val and self.a
- c_init: set this to tf.zeros_initializer.
- c_init_val: Set this by calling the tf.zeros_initializer that you just instantiated, and set the shape and dtype
 - shape: This will be a vector equal to the number of units. This expects a tuple, and remember that a tuple (9,) includes a comma.
 - dtype: set to 'float32'.
- self.c: create a tensor using tf.Variable, and set the parameters initial_value and trainable.
- call The following section performs the multiplication $x^2a + xb + c$. The steps are broken down for clarity, but you can also perform this calculation in fewer lines if you prefer. x_squared: use tf.math.square() x_squared_times_a: use tf.matmul().
- If you see an error saying InvalidArgumentError: Matrix size-incompatible, please check the order of the matrix multiplication to make sure that the matrix dimensions line up. -x_times_b: use tf.matmul(). x2a_plus_xb_plus_c: add the three terms together. activated_x2a_plus_xb_plus_c: apply the class's activation to the sum of the three terms.

```
[3]: # Please uncomment all lines in this cell and replace those marked with `# YOUR_

→ CODE HERE`.

# You can select all lines in this code cell with Ctrl+A (Windows/Linux) or _

→ Cmd+A (Mac), then press Ctrl+/ (Windows/Linux) or Cmd+/ (Mac) to uncomment.

class SimpleQuadratic(Layer):

def __init__(self, units=32, activation=None):
    '''Initializes the class and sets up the internal variables'''
    super(SimpleQuadratic, self).__init__()
    self.units = units
    self.activation = tf.keras.activations.get(activation)

def build(self, input_shape):
    '''Create the state of the layer (weights)'''
```

```
# a and b should be initialized with random normal, c (or the bias) \Box
→with zeros.
       # remember to set these as trainable.
       a init = tf.random normal initializer()
       b_init = tf.random_normal_initializer()
       c init = tf.zeros initializer()
       self.a = tf.Variable(name = "kernel",
                            initial_value = a_init(shape = (input_shape[-1],__
→self.units), dtype = 'float32'),
                            trainable = True)
       self.b = tf.Variable(name = "kernel",
                            initial_value = b_init(shape = (input_shape[-1],__
→self.units), dtype = 'float32'),
                            trainable = True)
       self.c = tf.Variable(name = "kernel",
                           initial_value = c_init(shape = (self.units,), dtype_
\hookrightarrow= 'float32'),
                           trainable = True)
   def call(self, inputs):
       '''Defines the computation from inputs to outputs'''
       result = tf.matmul(tf.math.square(inputs), self.a) + tf.matmul(inputs,
⇒self.b) + self.c
       return self.activation(result)
```

Test your implementation

```
[4]: utils.test_simple_quadratic(SimpleQuadratic)
```

All public tests passed

Train your model with the SimpleQuadratic layer that you just implemented.

```
Downloading data from https://storage.googleapis.com/tensorflow/tf-keras-
datasets/mnist.npz
11493376/11490434 [============ ] - Os Ous/step
Train on 60000 samples
Epoch 1/5
60000/60000 [============ ] - 12s 204us/sample - loss: 0.2695 -
accuracy: 0.9194
Epoch 2/5
accuracy: 0.9596- loss: 0.1316 - accuracy
Epoch 3/5
60000/60000 [============== ] - 12s 197us/sample - loss: 0.1022 -
accuracy: 0.9696
Epoch 4/5
60000/60000 [============== ] - 12s 198us/sample - loss: 0.0846 -
accuracy: 0.9734
Epoch 5/5
60000/60000 [============= ] - 12s 197us/sample - loss: 0.0725 -
accuracy: 0.9771- loss: 0.0721 - accuracy:
accuracy: 0.9761s - loss: 0.0967 - accuracy: 0. - ETA: 0s - loss: 0.0765 -
accuracy: 0.97
```