# 目 录

1	分析 resize 流程前的必要知识			
	1.1	nova 🕫	中的 RPC 机制	2
	1.2	重要的	9数据类型	2
		1.2.1	req	2
		1.2.2	context	2
		1.2.3	instance	2
2	nov	a-api 🏻	阶段	
3	nov	a-cond	luctor 部分	3
4	冷迁移			
	4.1	冷迁移	多中的 nova-conductor 部分	4
	4.2 冷迁移中的 nova-compute 部分			5
		4.2.1	目的主机上的操作: prep_resize	5
		4.2.2	源主机的操作: resize_instance	5
		4.2.3	目的主机上的操作: finish_resize	6
5	在线迁移			
	5.1	在线迁	E移中的 nova-conductor 部分	7
	5.2	在线迁	E移中的 nova-compute 部分	8
		5.2.1	目的主机上的操作: pre_live_migration	9
		5.2.2	源主机上的操作: live migration	12

# 1 分析 resize 流程前的必要知识

- 1.1 nova 中的 RPC 机制
- 1.2 重要的数据类型
- 1.2.1 req
- 1.2.2 context

```
# 根据 req 创建环境上下文 context
# context 是 nova/context.py中的 Request Context类
context = req.environ["nova.context"]
```

#### 1.2.3 instance

```
# 根据 req和 instance_id 创建 instance
       # instance是nova/context/instance.py中的Instance类
2
       instance = self._get_server(context, req, instance_id)
3
5
       instance_type
6
7
       flavor_id
       deltas
8
       quotas
9
       vm state
10
```

# 2 nova-api 阶段

#### 入口函数为:

```
# 这个函数在nova/api/openstack/compute/servers.py
def _resize(self, req, instance_id, flavor_id, **kwargs):
...
try:
# compute_api是nova/compute/api.py中的API类
self.compute_api.resize(context, instance, flavor_id, **kwargs)
...
```

### 进一步看 API.resize() 函数:

```
# nova/compute/api.py API.resize()
def resize(self, context, instance, flavor_id=None,

**extra_instance_updates):
```

```
# filter_properties与选择本地扩容或选择异地扩容有关
6
            filter_properties = {'ignore_hosts': []}
7
8
            if not CONF.allow_resize_to_same_host:
9
                filter_properties['ignore_hosts'].append(instance['host'])
10
11
            if (not flavor_id and not CONF.allow_migrate_to_same_host):
12
                filter_properties['ignore_hosts'].append(instance['host'])
13
14
16
            # scheduler_hint挺重要的,是nova-scheduler的参数
17
            scheduler_hint = {'filter_properties': filter_properties}
18
19
            self.compute_task_api.resize_instance(context, instance,
20
                    {\tt extra\_instance\_updates}\;,\;\; {\tt scheduler\_hint=scheduler\_hint}\;,
                    flavor=new_instance_type,
21
                    reservations=quotas.reservations or [])
1
       # nova/conductor/api.py ComputeTaskAPI.resize_instance()
        def resize_instance(self, context, instance, extra_instance_updates,
2
                            scheduler_hint, flavor, reservations):
3
            self.conductor_compute_rpcapi.migrate_server(
4
5
                context, instance, scheduler_hint, False, False, flavor,
6
                None, None, reservations)
       # nova/conductor/rpcapi.py ComputeTaskAPI.migrate_server()
1
2
        def migrate_server(self, context, instance, scheduler_hint, live, rebuild,
                      flavor, block_migration, disk_over_commit,
3
                      reservations=None):
4
            cctxt = self.client.prepare(version=version)
6
            return cctxt.call(context, 'migrate_server',
                               instance=instance , scheduler_hint=scheduler_hint ,
8
9
                               live=live, rebuild=rebuild, flavor=flavor_p,
                               block\_migration \!\!=\! block\_migration\;,
10
                               disk_over_commit=disk_over_commit,
11
                               reservations=reservations)
```

# 3 nova-conductor 部分

```
# nova/conductor/manager.py ComputeTaskManager.migrate_server()

def migrate_server(self, context, instance, scheduler_hint, live, rebuild,

flavor, block_migration, disk_over_commit, reservations=None):

if live and not rebuild and not flavor:

self._live_migrate(context, instance, scheduler_hint,

block_migration, disk_over_commit)

elif not live and not rebuild and flavor:
```

```
with compute_utils.EventReporter(context, 'cold_migrate',
instance_uuid):

self._cold_migrate(context, instance, flavor,
scheduler_hint['filter_properties'],
reservations)

...
```

# 4 冷迁移

### 4.1 冷迁移中的 nova-conductor 部分

```
1
        \#\ nova/conductor/manager.py\ Compute Task Manager.\_cold\_migrate()
2
        def _cold_migrate(self, context, instance, flavor, filter_properties,
                           reservations):
3
 4
            . . .
5
            try:
6
                # 选择目的主机
                hosts = self.scheduler_client.select_destinations(
                        context , request_spec , filter_properties)
9
                host\_state = hosts[0]
10
11
12
            try:
13
14
15
                (host, node) = (host_state['host'], host_state['nodename'])
16
                self.compute_rpcapi.prep_resize(
                     context, image, instance,
17
                     flavor, host,
                     reservations , request_spec=request_spec ,
19
                     filter_properties=filter_properties, node=node)
20
21
```

```
# nova/compute/rpcapi.py ComputeAPI.prep_resize()
1
        def prep_resize(self, ctxt, image, instance, instance_type, host,
2
3
                         reservations=None, request_spec=None,
                         filter\_properties\!=\!\!None, \ node\!=\!\!None):
4
5
            cctxt = self.client.prepare(server=host, version=version)
7
            cctxt.cast(ctxt, 'prep_resize',
                        instance=instance,
8
9
                        instance_type=instance_type_p,
10
                        image=image_p, reservations=reservations,
                        request_spec=request_spec ,
11
                        filter_properties=filter_properties,
12
                        node=node)
```

### 4.2 冷迁移中的 nova-compute 部分

### 4.2.1 目的主机上的操作: prep\_resize

```
1
        # nova/compute/manager.py ComputeManager.prep_resize()
2
        def prep_resize(self, context, image, instance, instance_type,
                          reservations\;,\; request\_spec\;,\; filter\_properties\;,\; node):
3
4
             with self._error_out_instance_on_exception(context, instance,
5
6
                                                             quotas=quotas):
8
                 trv:
                      self._prep_resize(context, image, instance,
10
                                          instance_type, quotas,
                                          request_spec, filter_properties,
11
12
                                          node)
13
1
        # nova/compute/manager.py ComputeManager._prep_resize()
        def _prep_resize(self, context, image, instance, instance_type,
2
                 quotas, request_spec, filter_properties, node):
3
4
5
             with \ {\tt rt.resize\_claim} \, (\, {\tt context} \, \, , \ {\tt instance} \, \, , \ {\tt instance\_type} \, \, , \\
6
                                    image_meta=image, limits=limits) as claim:
7
8
                 self.compute_rpcapi.resize_instance(
9
                          context, instance, claim.migration, image,
10
                          instance_type, quotas.reservations)
11
        # nova/compute/rpcapi.py ComputeAPI.resize_instance()
1
2
        def resize_instance(self, ctxt, instance, migration, image, instance_type,
                              reservations \!\!=\!\! None):
3
4
             cctxt = self.client.prepare(server=_compute_host(None, instance),
5
6
                     version=version)
             cctxt.cast(ctxt, 'resize_instance',
                         instance=instance, migration=migration,
8
```

### 4.2.2 源主机的操作: resize\_instance

10

```
# nova/compute/manager.py ComputeManager.resize_instance()
def resize_instance(self, context, instance, image,
reservations, migration, instance_type,
clean_shutdown=True):
...
with self._error_out_instance_on_exception(context, instance,
quotas=quotas):
```

image=image, reservations=reservations,

instance\_type=instance\_type\_p)

```
8
                 # 获得虚拟机块设备的信息
                 block\_device\_info = self.\_get\_instance\_block\_device\_info(
10
                                       context, instance, bdms=bdms)
11
                 # 关闭虚拟机并迁移虚拟机的增量文件
13
                 disk_info = self.driver.migrate_disk_and_power_off(
14
                          context , instance , migration.dest_host ,
15
                          instance_type, network_info,
16
                          block\_device\_info,
17
                          timeout, retry_interval)
18
19
                 {\tt self.compute\_rpcapi.finish\_resize} \, (\, {\tt context} \, , \, \, {\tt instance} \, , \, \,
20
                          migration, image, disk_info,
21
22
                          migration.dest_compute, reservations=quotas.reservations)
```

migrate\_disk\_and\_power\_off() 是源主机上将虚拟机迁移给目的主机的实现函数,主要利用了 libvirt API。这个函数的分析在《nova 调用 libvirt》中的"nova 扩容时对 libvirt 的调用"一节。

```
# nova/compute/rpcapi.py(690) ComputeAPI.finish_resize()

def finish_resize(self, ctxt, instance, migration, image, disk_info,

host, reservations=None):

...

cctxt = self.client.prepare(server=host, version=version)

cctxt.cast(ctxt, 'finish_resize',

instance=instance, migration=migration,

image=image, disk_info=disk_info, reservations=reservations)
```

### 4.2.3 目的主机上的操作: finish\_resize

```
# nova/compute/manager.py ComputeManager.finish resize()
1
2
        def finish_resize(self, context, disk_info, image, instance,
                           reservations, migration):
3
            quotas = quotas\_obj.\,Quotas.\,from\_reservations\,(\,context\,,
4
                                                             reservations,
                                                             instance=instance)
6
7
            trv:
8
                 self._finish_resize(context, instance, migration,
9
                                      disk_info, image)
10
```

```
image, resize_instance,
block_device_info, power_on)
...
```

# 5 在线迁移

### 5.1 在线迁移中的 nova-conductor 部分

```
# nova/conductor/manager.py ComputeTaskManager._live_migrate()

def _live_migrate(self, context, instance, scheduler_hint,

block_migration, disk_over_commit):

destination = scheduler_hint.get("host")

try:

live_migrate.execute(context, instance, destination,

block_migration, disk_over_commit)

...
```

```
# nova/conductor/tasks/live_migrate.py execute()
1
        def execute(context, instance, destination,
3
                 block_migration, disk_over_commit):
        task \, = \, Live Migration Task (\, context \, , \, \, instance \, , \, \,
4
                                    destination,
5
6
                                    block_migration,
7
                                    disk_over_commit)
       # TODO(johngarbutt) create a superclass that contains a safe_execute call
8
       return task.execute()
```

```
# nova/conductor/tasks/live_migrate.py LiveMigrationTask.execute()
1
        def execute(self):
2
            self._check_instance_is_running()
3
            self._check_host_is_up(self.source)
4
5
            if not self.destination:
                self.destination = self._find_destination()
7
            else:
8
9
                self._check_requested_destination()
10
            # TODO(johngarbutt) need to move complexity out of compute manager
11
            # TODO(johngarbutt) disk_over_commit?
12
13
            return self.compute_rpcapi.live_migration(self.context,
                    host=self.source,
14
                    instance=self.instance,
15
                    dest=self.destination,
16
                    block_migration=self.block_migration,
17
                    migrate_data=self.migrate_data)
18
```

```
# nova/compute/rpcapi.py ComputeAPI.live_migration()
def live_migration(self, ctxt, instance, dest, block_migration, host,
```

```
migrate_data=None):

...

cctxt = self.client.prepare(server=host, version=version)

cctxt.cast(ctxt, 'live_migration', instance=instance,

dest=dest, block_migration=block_migration,

migrate_data=migrate_data)
```

### 5.2 在线迁移中的 nova-compute 部分

```
1
       # nova/compute/manager.py ComputeManager.live_migration()
2
        def live_migration(self, context, dest, instance, block_migration,
3
                           migrate_data):
            """Executing live migration.
5
            :param context: security context
6
            :param instance: a nova.objects.instance.Instance object
            :param dest: destination host
            :param block_migration: if true, prepare for block migration
9
            :param migrate_data: implementation specific params
10
11
12
13
            \# NOTE(danms): since instance is not the first parameter, we can't
14
            # use @object_compat on this method. Since this is the only example,
15
            # we do this manually instead of complicating the decorator
16
            if not isinstance(instance, obj_base.NovaObject):
17
18
                expected = ['metadata', 'system_metadata'
                             'security_groups', 'info_cache'
19
                instance = objects.Instance. from db object(
20
                    context, objects.Instance(), instance,
21
22
                    expected_attrs=expected)
23
            # Create a local copy since we'll be modifying the dictionary
24
            migrate_data = dict(migrate_data or {})
25
26
            try:
                if block_migration:
27
                    block\_device\_info = self.\_get\_instance\_block\_device\_info(
28
29
                        context, instance)
                    disk = self.driver.get_instance_disk_info(
30
31
                        instance.name, block_device_info=block_device_info)
32
                else:
                    disk = None
33
34
                pre_migration_data = self.compute_rpcapi.pre_live_migration(
35
36
                    context, instance,
                    block_migration, disk, dest, migrate_data)
37
                migrate_data['pre_live_migration_result'] = pre_migration_data
38
39
            except Exception:
40
                with excutils.save_and_reraise_exception():
41
                    LOG. exception (_LE('Pre live migration failed at %s'),
42
                                   dest, instance=instance)
43
                    self._rollback_live_migration(context, instance, dest,
44
```

```
block_migration, migrate_data)
45
46
            # Executing live migration
47
            # live_migration might raises exceptions, but
48
            # nothing must be recovered in this version.
49
            self.driver.live_migration(context, instance, dest,
50
                                        self._post_live_migration,
51
                                        self._rollback_live_migration,
52
                                        block_migration, migrate_data)
```

#### 5.2.1 目的主机上的操作: pre\_live\_migration

```
def pre_live_migration(self, context, instance, block_migration, disk,
1
2
                                 migrate_data):
            """Preparations for live migration at dest host.
3
4
            :param context: security context
5
            :param instance: dict of instance data
            : param \ block\_migration: \ if \ true \,, \ prepare \ for \ block \ migration
            : param\ migrate\_data\colon\ if\ not\ None,\ it\ is\ a\ dict\ which\ holds\ data
8
9
                                   required for live migration without shared
10
                                   storage.
11
12
            block_device_info = self._get_instance_block_device_info(
13
14
                                  context , instance , refresh_conn_info=True)
15
            network_info = self._get_instance_nw_info(context, instance)
16
            {\tt self.\_notify\_about\_instance\_usage} (
17
                          context, instance, "live_migration.pre.start",
18
                          network_info=network_info)
19
20
            pre\_live\_migration\_data = self.driver.pre\_live\_migration(context,
21
                                              instance,
22
                                              block_device_info,
24
                                              network_info,
                                              disk.
25
26
                                              migrate_data)
27
            # NOTE(tr3buchet): setup networks on destination host
28
            self.network_api.setup_networks_on_host(context, instance,
29
                                                                  self.host)
30
31
            # Creating filters to hypervisors and firewalls.
32
            # An example is that nova—instance—instance—xxx,
33
            # which is written to libvirt.xml(Check "virsh nwfilter-list")
34
            # This nwfilter is necessary on the destination host.
35
36
            # In addition, this method is creating filtering rule
            # onto destination host.
37
            self.driver.ensure\_filtering\_rules\_for\_instance (instance \,,
38
                                                   network_info)
39
40
41
            self._notify_about_instance_usage(
```

```
context, instance, "live_migration.pre.end",
network_info=network_info)

return pre_live_migration_data
```

```
# nova/virt/libvirt/driver.py LibvirtDriver.pre_live_migration()
1
2
        def pre_live_migration(self, context, instance, block_device_info,
                                network_info , disk_info , migrate_data=None):
3
            """Preparation live migration."""
4
            # Steps for volume backed instance live migration w/o shared storage.
5
6
            is\_shared\_block\_storage = True
7
            is\_shared\_instance\_path \, = \, True
            is\_block\_migration = True
8
            instance\_relative\_path \, = \, None
9
10
            if migrate_data:
11
                is\_shared\_block\_storage = migrate\_data.get(
                          'is_shared_block_storage', True)
12
13
                is_shared_instance_path = migrate_data.get(
                          'is_shared_instance_path', True)
14
                is\_block\_migration = migrate\_data.get('block\_migration', \ True)
15
                instance_relative_path = migrate_data.get('instance_relative_path')
16
17
18
            if not (is_shared_instance_path and is_shared_block_storage):
                # NOTE(dims): Using config drive with iso format does not work
19
20
                # because of a bug in libvirt with read only devices. However
21
                \#\ one\ can\ use\ vfat\ as\ config\_drive\_format\ which\ works\ fine\ .
                # Please see bug/1246201 for details on the libvirt bug.
22
                if CONF. config drive format != 'vfat':
23
                     if configdrive.required_by(instance):
24
                         raise \ exception. No Live \underline{Migration For ConfigDrive In Lib Virt ()}
25
26
            if not is_shared_instance_path:
                \# NOTE(mikal): this doesn't use libvirt_utils.get_instance_path
28
                # because we are ensuring that the same instance directory name
29
                # is used as was at the source
30
                if \ instance\_relative\_path:
31
32
                     instance_dir = os.path.join(CONF.instances_path,
                                                   instance_relative_path)
33
34
                else:
35
                     instance_dir = libvirt_utils.get_instance_path(instance)
36
                if os.path.exists(instance_dir):
37
                     raise exception. Destination DiskExists (path=instance_dir)
38
39
                os.mkdir(instance_dir)
40
                 if not is_shared_block_storage:
                    # Ensure images and backing files are present.
42
                     self._create_images_and_backing(context, instance,
43
                                                       instance_dir, disk_info)
44
45
            if not (is_block_migration or is_shared_instance_path):
46
47
                # NOTE(angdraug): when block storage is shared between source and
                \# destination and instance path isn't (e.g. volume backed or rbd
48
                # backed instance), instance path on destination has to be prepared
49
50
```

```
# Touch the console.log file, required by libvirt.
 51
                  console_file = self._get_console_log_path(instance)
 52
                  libvirt_utils.file_open(console_file, 'a').close()
 53
 54
                 # if image has kernel and ramdisk, just download
 55
 56
                  # following normal way.
                  self._fetch_instance_kernel_ramdisk(context, instance)
 57
 58
             # Establishing connection to volume server.
 59
             block_device_mapping = driver.block_device_info_get_mapping(
 60
                  block_device_info)
 61
 62
             for vol in block_device_mapping:
                  connection_info = vol['connection_info']
 63
                  disk_info = blockinfo.get_info_from_bdm(
 64
                      CONF. libvirt.virt_type, vol)
 65
 66
                  self._connect_volume(connection_info, disk_info)
 67
             if is_block_migration and len(block_device_mapping):
 68
                 # NOTE(stpierre): if this instance has mapped volumes,
                  # we can't do a block migration, since that will
 70
                 # result in volumes being copied from themselves to
 71
                  # themselves, which is a recipe for disaster.
 72
                 LOG. error (
 73
                      _LE('Cannot block migrate instance %s with mapped volumes') \%
 74
                      instance.uuid)
 75
 76
                  raise exception. MigrationError(
                      _('Cannot block migrate instance %s with mapped volumes') %
 77
                      instance.uuid)
 78
 80
             # We call plug_vifs before the compute manager calls
             \#\ ensure\_filtering\_rules\_for\_instance , to ensure bridge is set up
 81
             # Retry operation is necessary because continuously request comes,
 82
             # concurrent request occurs to iptables, then it complains.
 83
             {\tt max\_retry} = {\tt CONF.live\_migration\_retry\_count}
 84
             for cnt in range(max_retry):
 85
 86
                  try:
 87
                      self.plug_vifs(instance, network_info)
                      break
 88
                  except processutils.ProcessExecutionError:
 89
 90
                      if cnt = max_retry - 1:
 91
                          raise
                      else:
 92
                          LOG.warn(_LW('plug_vifs() failed %(cnt)d. Retry up to '
 93
 94
                                         '%(max_retry)d.'),
                                    { 'cnt ': cnt,
 95
                                      'max_retry': max_retry},
 96
 97
                                    instance=instance)
                          greenthread.sleep(1)
 98
99
             res_data = {'graphics_listen_addrs': {}}
100
             res\_data \left[ \ 'graphics\_listen\_addrs \ '] \left[ \ 'vnc \ ' \right] \ = CONF. \ vncserver\_listen
101
             res_data['graphics_listen_addrs']['spice'] = CONF.spice.server_listen
102
103
             return res_data
104
```

### 5.2.2 源主机上的操作: live\_migration

```
# nova/compute/manager.py ComputeManager.live_migration()
1
        def live_migration(self, context, dest, instance, block_migration,
2
                            migrate_data):
3
            """Executing live migration.
4
5
            :param context: security context
6
            :param instance: a nova.objects.instance.Instance object
            :param dest: destination host
8
            :param block_migration: if true, prepare for block migration
9
            :param migrate_data: implementation specific params
10
11
            22 22 22
12
13
            # NOTE(danms): since instance is not the first parameter, we can't
14
            # use @object_compat on this method. Since this is the only example,
15
            # we do this manually instead of complicating the decorator
16
            if not isinstance(instance, obj_base.NovaObject):
17
                expected = ['metadata', 'system_metadata',
18
                             'security_groups', 'info_cache']
19
                instance = objects.Instance._from_db_object(
20
21
                    context, objects.Instance(), instance,
22
                    expected_attrs=expected)
23
            # Create a local copy since we'll be modifying the dictionary
24
25
            migrate_data = dict(migrate_data or {})
26
            try:
27
                if block_migration:
                    block\_device\_info = self.\_get\_instance\_block\_device\_info(
29
                         context, instance)
                    disk = self.driver.get_instance_disk_info(
30
31
                         instance.name, block_device_info=block_device_info)
32
                else:
                    disk = None
33
34
35
                pre_migration_data = self.compute_rpcapi.pre_live_migration(
                     context, instance,
36
                    block migration, disk, dest, migrate data)
37
                migrate_data['pre_live_migration_result'] = pre_migration_data
38
39
            except Exception:
40
                with excutils.save_and_reraise_exception():
41
                    LOG. exception (_LE('Pre live migration failed at %s'),
42
                                   dest, instance=instance)
43
                     self._rollback_live_migration(context, instance, dest,
44
                                                    block_migration, migrate_data)
46
            # Executing live migration
47
48
            # live_migration might raises exceptions, but
            # nothing must be recovered in this version.
49
            self.driver.live_migration(context, instance, dest,
50
                                        self._post_live_migration,
51
52
                                         self._rollback_live_migration,
53
                                        block_migration, migrate_data)
```

```
# nova/virt/libvirt/driver.py LibvirtDriver.live_migration()
1
        def live_migration(self, context, instance, dest,
2
3
                            post_method, recover_method, block_migration=False,
                            migrate_data=None):
            """Spawning live_migration operation for distributing high-load.
5
6
7
            :param context: security context
8
            :param instance:
                nova.db.sqlalchemy.models.Instance object
9
                instance object that is migrated.
10
            :param dest: destination host
11
            : param \ post\_method:
12
                post operation method.
13
                expected \ nova.compute.manager.\_post\_live\_migration.
14
15
            :param recover_method:
                recovery method when any exception occurs.
16
17
                expected nova.compute.manager._rollback_live_migration.
            :param block_migration: if true, do block migration.
18
            :param migrate_data: implementation specific params
19
20
21
22
            # 'dest' will be substituted into 'migration_uri' so ensure
23
            # it does't contain any characters that could be used to
24
25
            # exploit the URI accepted by libivrt
            if not libvirt_utils.is_valid_hostname(dest):
26
27
                raise exception.InvalidHostname(hostname=dest)
            greenthread.spawn(\,self.\_live\_migration\,,\ context\,,\ instance\,,\ dest\,,
29
                               post_method, recover_method, block_migration,
30
31
                               migrate_data)
```

```
# nova/virt/libvirt/driver.py LibvirtDriver._live_migration()
1
        def _live_migration(self, context, instance, dest, post_method,
2
                              recover_method, block_migration=False,
3
4
                              migrate_data=None):
            """Do live migration.
5
6
            :param context: security context
            :param instance:
8
                 nova.db.sqlalchemy.models.Instance object
9
10
                 instance object that is migrated.
11
            :param dest: destination host
            : param \ post\_method:
12
13
                 post operation method.
                 expected \ nova.compute.manager.\_post\_live\_migration.
14
            :param recover_method:
15
                recovery method when any exception occurs.
16
                 expected \ nova.compute.manager.\_rollback\_live\_migration\,.
17
18
            :param block_migration: if true, do block migration.
            : param\ migrate\_data \colon implementation\ specific\ params
19
20
21
            # Do live migration.
22
23
            trv:
```

```
if block_migration:
24
                    flaglist = CONF.libvirt.block_migration_flag.split(',')
25
                else:
26
                    flaglist = CONF.libvirt.live_migration_flag.split(',')
27
                flagvals = [getattr(libvirt, x.strip()) for x in flaglist]
29
                logical_sum = reduce(lambda x, y: x | y, flagvals)
30
                dom = self._lookup_by_name(instance["name"])
31
32
                pre_live_migrate_data = (migrate_data or {}).get(
33
                                             'pre_live_migration_result', {})
34
35
                listen_addrs = pre_live_migrate_data.get('graphics_listen_addrs')
36
                37
                                           None)
38
39
40
                if migratable_flag is None or listen_addrs is None:
                    self._check_graphics_addresses_can_live_migrate(listen_addrs)
41
                    dom.migrateToURI(CONF.libvirt.live_migration_uri % dest,
42
43
                                      logical_sum,
                                      None.
44
                                      CONF. libvirt.live_migration_bandwidth)
45
                else:
46
                    old_xml_str = dom.XMLDesc(migratable_flag)
47
                    new_xml_str = self._correct_listen_addr(old_xml_str,
48
49
                                                              listen_addrs)
50
                    try:
                        {\tt dom.migrateToURI2(CONF.libvirt.live\_migration\_uri~\%~dest}\,,
51
                                           None,
53
                                           new_xml_str,
                                           logical_sum,
54
                                           None.
55
                                           C\!O\!N\!F.\ lib virt.live\_migration\_bandwidth)
                    except libvirt.libvirtError as ex:
57
                        # NOTE(mriedem): There is a bug in older versions of
58
59
                        \#\ libvirt\ where\ the\ VIR\_DOMAIN\_XML\_MIGRATABLE\ flag\ causes
60
                        \#\ virDomainDefCheckABIStability\ to\ not\ compare\ the\ source
                        # and target domain xml's correctly for the CPU model.
61
62
                        # We try to handle that error here and attempt the legacy
63
                        \#\ migrate To URI\ path , which could fail if the console
                        # addresses are not correct, but in that case we have the
64
                        \# _check_graphics_addresses_can_live_migrate check in place
65
                        # to catch it.
66
67
                        # TODO(mriedem): Remove this workaround when
                        \# Red Hat BZ \#1141838 is closed.
68
                        error_code = ex.get_error_code()
69
                        if error_code == libvirt.VIR_ERR_CONFIG_UNSUPPORTED:
70
                            LOG.warn(_LW('An error occurred trying to live '
71
                                          'migrate. Falling back to legacy live '
72
                                          'migrate flow. Error: %s'), ex,
73
                                      instance=instance)
74
                            self._check_graphics_addresses_can_live_migrate(
75
76
                                listen_addrs)
77
                            dom.migrateToURI(
                                CONF. libvirt.live_migration_uri \% dest,
78
                                 logical_sum,
79
```

```
80
                                    C\!O\!N\!F.\ lib virt.live\_migration\_bandwidth)
81
                           else:
82
                                raise
83
84
             except Exception as e:
85
                  with excutils.save_and_reraise_exception():
86
                      LOG.error(_LE("Live Migration failure: %s"), e,
87
                                  instance=instance)
88
                      recover\_method(context\,,\ instance\,,\ dest\,,\ block\_migration)
89
90
             post\_method(context\,,\ instance\,,\ dest\,,\ block\_migration\,,
91
                           migrate\_data)
92
```