# **Introduction to Operating Systems**

#### What's an OS?

The OS is a layer between applications and hardware to ease development.

- · Abstraction. provides abstraction for applications:
- o manages + hides hardware details
- o uses low-level interfaces (not available to applications)
- multiplexes hardware to multiple programs (virtualization)
- o makes hardware use efficient for applications
- Protection
- from processes using up all resources (accounting, allocation)
- o from processes writing into other processes memory
- · Resource Management.
  - o manages + multiplexes hardware resources
- o decides between conflicting requests for resource use
- o goal: efficient + fair resource use
- Control.
  - o controls program execution
  - o prevents errors and improper computer use

### → no universally accepted definition

#### **Hardware Overview**

- Bus: CPU(s)/devices/memory (conceptually) connected to common bus
- o CPU(s)/devices competing for memory cycles/bus
- o all entities run concurrently
- o today: multiple buses
- · Device controller: has local buffer and is in charge of particular device
- Interplay:
- 1. CPU issues commands, moves data to devices
- 2. Device controller informs APIC that it has finished operation
- 3. APIC signals CPU
- 4. CPU receives device/interrupt number from APIC, executes handler




Figure 1: Traditional bus design.




Figure 2: Modern bus design.

# Central Processing Unit (CPU) — Operation

- · Principle:
- 1. *fetches* instructions from memory,
- 2. executes them
- During execution: (meta-)data is stored in CPU-internal registers, i.e.
- o general purpose registers
- floating point registers
- o instruction pointer (IP)
- stack pointer (SP)program status word (PSW)

### **CPU** — Modes of Execution

- User mode (x86: Ring 3/CPL 3):
  - only non-privileged instructions may be executed
  - o cannot manage hardware → protection
- Kernel mode (x86: Ring O/CPL 0):
- o all instructions allowed
- o can manage hardware with privileged instructions




Figure 3: The different protection layers in the ring model.

# Random Access Memory (RAM)

- Principle: keeps currently executed instructions + data
- · Connectivity:
  - o today: CPUs have built-in memory controller
  - o CPU caches: "wired" to CPU
  - RAM: connected via pins
  - o PCI-E switches: connected via pins

#### Caches

- Problem: RAM delivers instructions/data slower than CPU can execute
- · Locality principle:
- o spatial locality: future refs often near previous accesses (e.g. next byte in array)
- o temporal locality: future refs often at previously accessed ref (e.g. loop counter)
- Solution: caching helps mitigating this memory wall
  - 1. copy used information temporarily from slower to faster storage
  - 2. check faster storage first before going down memory hierarchy
- 3. if not found, data is copied to cache and used from there
- · Access latency:
  - o register: ~1 CPU cycle
  - o L1 cache (per core): ~4 CPU cycles
  - ∘ L2 cache (per core pair): ~12 CPU cycles
  - o  $L3 \, cache/LLC$  (per uncore): ~28 CPU cycles (~25 GiB/s)
  - DDR3-12800U RAM: ~28 CPU cycles + ~ 50ns (~12 GiB/s)

# Device controlling

- Device controller: controls device, accepts commands from OS via device driver
- Device registers/memory:
  - o control device by writing device registers
  - o read status of device by reading device registers
- o pass data to device by reading/writing device memory
- Device registers/memory access:
- port-mapped IO (PMIO): use special CPU instructions to access port-mapped registers/memory
- 2. memory-mapped IO (MMIO):
  - o use same address space for RAM and device memory
  - o some addresses map to RAM, others to different devices
  - o access device's memory region to access device registers/memory
- 3. **Hybrid**: some devices use hybrid approaches using both

# Summary

- The OS is an abstraction layer between applications and hardware (multiplexes hardware, hides hardware details, provides protection between processes/users)
- The CPU provides a **separation** of User and Kernel mode (which are required for an OS to provide protection between applications)
- CPU can execute commands faster than memory can deliver instructions/data
   — memory hierarchy mitigates this memory wall, needs to be carefully managed by OS to minimize slowdowns
- device drivers control hardware devices through PMIO/MMIO
- Devices can signal the CPU (and through the CPU notify the OS) through interrupts

# **OS** Concepts

#### **OS** Invocation

- OS Kernel does not always run in background!
- · Occasions invoking kernel, switching to kernel mode:
- 1. System calls: User-Mode processes require higher privileges
- 2. Interrupts: CPU-external device sends signal
- 3. Exceptions: CPU signals unexpected condition

### System Calls — Motivation

- Problem: protect processes from one another
- Idea: Restrict processes by running them in user-mode
- → Problem: now processes cannot manage hardware,...
- who can switch between processes?
- o who decides if process may open certain file?
- → Idea: OS provides services to apps
- 1. app calls system if service is needed (syscall)
- 2. OS checks if app is allowed to perform action
- 3. if app may perform action and hasn't exceeded quota, OS performs action in behalf of app in kernel mode

# System Calls — Examples

- fd = open(file, how,...) open file for read/write/both
- documented e.g. in man 2 write
- overview in man 2 syscalls

# System Calls vs. APIs

- Syscalls: interface between apps and OS services, limited number of well-defined entry points to kernel
- APIs: often used by programmers to make syscalls (e.g. printf library call uses write syscall)
- · common APIs: Win32, POSIX, C API

# System Calls — Implementation

- Trap Instruction: single syscall interface (entry point) to kernel
- o switches CPU to kernel mode, enters kernel in same way for all syscalls
- o system call dispatcher in kernel then acts as syscall multiplexer
- Syscall Identification: number passed to trap instruction
- o Syscall Table maps syscall numbers to kernel functions
- o Dispatcher decides where to jump based on number and table
- programs (e.g. stdlib) have syscall number compiled in!
- → never reuse old syscall numbers in future kernel versions

## Interrupts

- · Devices: use interrupts to signal predefined conditions to OS
- reminder: device has "interrupt line" to CPU (e.g. device controller informs CPU that operation is finished)
- Programmable Interrupt Controller: manages interrupts
  - o interrupts can be *masked* (queued, delivered when interrupt unmasked)
- o queue has finite length → interrupts can get lost
- Examples:
- 1. *timer-interrupt*: periodically interrupts processes, switches to kernel → can then switch to different processes for fairness
- 2. *network interface card* interrupts CPU when packet was received → can deliver packet to process and free NIC buffer
- Interrupt process:
- CPU looks up interrupt vector (= table pinned in memory, contains addresses of all service routines)
- CPU transfers control to respective interrupt service routine in OS that handles interrupt
- $\rightarrow$  interrupt service routine must first save interrupted process's state (instruction pointer, stack pointer, status word)

## **Exceptions**

- Motivation: unusual condition → impossible for CPU to continue processing
- **Exception** generated within CPU:
- 1. CPU interrupts program, gives kernel control
- 2. kernel determines reason for exception
- 3. if kernel can resolve problem → does so, continues faulting instruction
- 4. kills process if not

 Difference to Interrupts: interrupts can happen in any context, exceptions always occur asynchronous and in process context

# OS Concepts — Physical Memory

- up to early 60s:
- o programs loaded and run directly in physical memory
- $\circ$  program too large  $\rightarrow$  partitioned manually into *overlays*
- o OS: swaps overlays between disk and memory
- o different jobs could observe/modify each other

# OS Concepts — Address Spaces

- Motivation: bad programs/people need to be isolated
- Idea: give every job the illusion of having all memory to itself
- o every job has own address space, can't name addresses of others
- o jobs always and only use virtual addresses

# Virtual Memory — Indirect Addressing

- MMU: every CPU has built-in memory management unit (MMU)
- Principle: translates virtual addresses to physical addresses at every load/store
   → address translation protects one program from another
- · Definitions:
- o Virtual address: address in process' address space
- o Physical address: address of real memory

# Virtual Memory — Memory Protection

- · Kernel-only Virtual Addresses
  - o kernel typically part of all address spaces
- o ensures that apps can't touch kernel memory
- Read-only virtual addresses: can be enforced by MMU
  - o allows safe sharing of memory between apps
- Execute Disable: can be enforced by MMU
  - o makes code injection attacks harder

## Virtual Memory — Page Faults


- Motivation: not all addresses need to be mapped at all times
- o MMU issues page fault exception when accessed virtual address isn't mapped
- OS handles page faults by loading faulting addresses and then continuing the program
- → memory can be over-committed: more memory than physically available can be allocated to application
- Illegal addresses: page faults also issued by MMU on illegal memory accesses

# OS Concepts — Processes

- Process: program in execution ("instance" of program)
- each process is associated with
  - Process Control Block (PCB): contains information about allocated resources
  - o virtual Address Space (AS):
    - all (virtual) memory locations a program can name
  - starts at 0 and runs up to a maximum
  - address 123 in AS1 generally ≠ address 123 in AS2
  - indirect addressing → different ASes to different programs
  - → protection between processes


# OS Concepts — Address Space Layout

- Sections: address spaces typically laid-out in different sections
- o memory addresses between sections illegal
- o illegal addresses → page fault (segmentation fault)
- o OS usually kills process causing segmentation fault
- Important sections:
- Stack: function history, local variables
- o Data: Constants, static/global variables, strings
- o Text: Program code



# OS Concepts — Threads

- **Thread**: represents execution state of process (≥ 1 thread per process)
  - IP: stores currently executed instruction (address in text section)
  - SP: stores address of stack top (> 1 threads  $\rightarrow$  multiple stacks!)
  - o *PSW*: contains flags about execution history (e.g. last calculation was  $0 \to used$  in following jump instruction)
  - o more general purpose registers, floating point registers,...




## OS Concepts — Policies vs. Mechanisms

- Mechanism: implementation of what is done (e.g. commands to write to HDD)
- Policy: rules which decide when what is done and how much (e.g. how often, how
  many resources are used,...)
- → mechanisms can be reused even when policy changes

# OS Concepts — Scheduling

- Motivation: multiple processes/threads available → OS needs to switch between them (for multitasking)
- Scheduler: decides which job to run next (policy) tries to
  - o provide fairness
  - o meet performance goals
  - o adhere to priorities
- Dispatcher: performs task-switching (mechanism)



## OS Concepts — Files

- Motivation: OS hides peculiarities of file storage, programmer uses deviceindependent files/directories
- **Files**: associate *file name* and *offset* with bytes
- **Directories**: associate *directory names* with directory names or file names
- File System: ordered block collection
- o main task: translate (dir name + file name + offset) to block
- $\verb| o programmer uses file system operations to operate on files (\verb| open, read, seek|) \\$
- processes can communicate directly through special named pipe file (used with same operations as any other file)

# OS Concepts — Directory Tree

- **Directories**: form *directory tree*/*file hierarchy* → structure data
- Root Directory: topmost directory in tree
- Path Name: used to specify file

# OS Concepts — Mounting

- Unix: common to orchestrate multiple file systems in single file hierarchy
- file systems can be mounted on directory
- Win: manage multiple directory hierarchies with drive letters (e.g. C:\Users)

# OS Concepts — Storage Management

- OS: provides uniform view of information storage to file systems
- o Drivers: hide specific hardware devices → hides device peculiarities
- $\circ$  general interface abstracts physical properties to logical units  $\rightarrow$  block
- Performance: OS increases I/O performance:
- o Buffering: Store data temporarily while transferred
- o Caching: Store data parts in faster storage
- Spooling: Overlap one job's output with other job's input

#### Summary

- **OS**: provides abstractions for and protection between applications
- Kernel: does not always run certain events invoke kernel
- o syscall: process asks kernel for service
- o interrupt: device sends signal that OS has to handle
- o exception: CPU encounters unusual situation
- Processes: encapsulate resources needed to run program in OS
- o threads: represent different execution states of process
- o address space: all memory process can name
- o resources: allocated resources, e.g., open files
- · Scheduler decides which process to run next when multi-tasking
- Virtual Memory implements address spaces, provides protection between processes