Doradus Administration

1. Overview

This document provides configuration and operation guidelines for the Doradus database management system. It provides information on the following topics:

- Deploying Doradus in a minimal environment.
- Expanding the deployment to accommodate additional capacity.
- Security considerations and configuration.
- Cassandra and Doradus configuration options.
- Monitoring Doradus and Cassandra via JMX.

The following documents are also available:

- **Doradus Data Model and Query Language**: Provides a detailed description of the core Doradus data model, query language (DQL), and object and aggregate query commands.
- **Doradus OLAP Database**: Describes the features, data model extensions, and REST commands specific to the Doradus OLAP service.
- **Doradus Spider Database**: Describes the features, data model extensions, and REST commands specific to the Doradus Spider service.

1.1. Recent Changes

The following changes were made to reflect new features for the v2.2 release:

• Doradus now uses Cassandra 2.x and can use either the Thrift or CQL API. Information has been added to configure both Cassandra and Doradus to use CQL.

July 16, 2014 Page 1 of 36

2. Installing and Running Doradus

Doradus and Cassandra are both pure Java applications and can run on Windows, Linux, and OS X as console applications. On Windows, both can run as Windows services. Doradus can also be embedded within another application, meaning it runs in the same JVM. Though not documented here, Doradus and Cassandra can be set up to run as daemon services on Linux and OS X.

Doradus currently does not have source or binary bundles ready to download. (Coming soon: Maven builds!) The source code is available on Github: see the README file for general information about the project structure. When Doradus is compiled, it assumes a folder structure such as this:

```
/Doradus
/bin - for binary scripts
/config - for doradus.yaml and log4j.properties
/lib - for doradus.jar and other dependent jar files
```

In this example, the folder /Doradus is the home folder, referred to throughout this document as {doradus_home}. Java 1.7 and Cassandra must be installed independently. In this document, Cassandra's home folder is referred to as {cassandra home}.

2.1. Running Doradus Stand-Alone

Doradus can be run as a console application with a script in the {doradus_home}/bin directory such as this:

```
java -cp "../lib/*:../config/*" com.dell.doradus.core.DoradusServer
```

This is assumes Java 1.7 is visible in the script's path. The files doradus.yaml and log4j.properties must be visible in the JVM's resource path, although their location can be set with the JVM defines -Ddoradus.config and -Dlog4j.configuration respectively. Example:

```
java -Dlog4j.configuration=file:/Doradus/mylog4j.properties \
    -Ddoradus.config=file:/Doradus/mydoradus.yaml \
    ...
```

Most doradus.yaml parameters can be overridden with command line arguments by prepending a "-" to the parameter name. For example, doradus.yaml defines restport: 1123, which sets the REST API listening port number. To override this to 5711, add the command line argument:

```
java -cp "../lib/*:../config/*" com.dell.doradus.core.DoradusServer -restport 5711
```

On Windows, Doradus can also be installed and managed as a service using the Apache Commons Daemon component. See http://commons.apache.org/proper/commons-daemon/procrun.html for more information.

Doradus assumes that Cassandra is started independently. Doradus connects to Cassandra at the dbhost address(es) and dbport number defined in doradus.yaml. If no configured Cassandra nodes are available when Doradus starts, it will reattempt to connect every 30 seconds. Until a connection is successful, most REST API calls will return a 503 Service Unavailable response.

Doradus expects Cassandra version 2.0 or higher. It can connect to Cassandra using either the Thrift or CQL API, but there are upgrade limitations for existing databases created with previous Doradus versions. Cassandra API options are described in the section **Configuration Parameters in doradus.yaml**.

July 16, 2014 Page 2 of 36

2.2. Embedding Doradus In Another Application

Some applications may want to embed Doradus in the same JVM process. One way to do this is to call the static main method, passing a String[] that provides runtime arguments. Example:

```
import com.dell.doradus.core.DoradusServer;
...
String[] args = new String[] {"-restport", "5711"};
DoradusServer.main(args);
```

This example overrides the doradus.yaml parameter restport, setting it to 5711. When main() is called, Doradus starts all internal services and the storage_services configured in doradus.yaml. However, main() does not return until the process receives a shutdown signal (e.g., Ctrl-C or System.exit() is called).

Alternatively, Doradus can be started with the method startEmbedded(), which returns as soon as all internal services are initialized and started. This method accepts the same args parameter as main() plus a second String[] that allows the selective initialization of services. Example:

```
String[] args = new String[] {"-restport", "5711"};
String[] services = new String[] {OLAPService.class.getName(), RESTService.class.getName()};
DoradusServer.startEmbedded(args, services);
```

This example also overrides the restport parameter, and it starts Doradus with the OLAP storage service and the REST service. Other optional services, such as the Task Manager service, are not initialized. Regardless of the services requested, Doradus always initializes required internal services such as the DB service (persistence layer) and schema service. The optional services that may be requested through the services parameter are:

- com.dell.doradus.mbeans.MBeanService: Provides the JMX interface. If this service is not initialized, JMX usage metrics and administrative commands will not be available.
- com.dell.doradus.service.rest.RESTService: Provides the Jetty-based REST API. If this service is not initialized, Doradus will not accept REST commands. However, initialized services can be called directly via their service APIs.
- com.dell.doradus.service.taskmanager.TaskManagerService: Provides the Task Manager service. If this service is not initialized, background tasks such as data aging will not be performed.
- com.dell.doradus.service.olap.OLAPService: Provides the OLAP storage service. If this service is not
 initialized, new OLAP applications cannot be created and existing OLAP applications, if any, cannot
 be accessed.
- com.dell.doradus.service.spider.SpiderService: Provides the Spider storage service. If this service is not initialized, new Spider applications cannot be created and existing Spider applications, if any, cannot be accessed.

The full package name of each service must be passed in the services parameter. At least one storage service must be initialized otherwise startEmbedded() will throw a RuntimeException. If multiple storage services are provided, the first one becomes the default for new applications created via the same Doradus instance that do not explicitly declare a storage service.

July 16, 2014 Page 3 of 36

Doradus Administration

Note that multiple Doradus instances can be launched for the same Cassandra cluster with different service sets. For example, a direct-load application could embed Doradus, initializing only the storage service that it requires, while another stand-alone instance of Doradus can be executed with full services.

When Doradus is started with the startEmbedded() method, it returns as soon as all requested services are initialized and running. Doradus can be gracefully shutdown by calling the shutDown method. Example:

```
DoradusServer.shutDown();  // gracefully shutdown and return
```

Alternatively, Doradus can be gracefully shutdown and terminate the JVM process by calling stopServer. Example:

```
DordusServer.stopServer(null); // gracefully shutdown and call System.exit()
```

The parameter passed to stopServer() is a String[], but it is ignored.

July 16, 2014 Page 4 of 36

3. Deployment Guidelines

This section provides recommendations for deploying and configuring Doradus to meet various operational objectives. We start by describing the basic components of the Doradus architecture.

3.1. Basic Architecture

The basic components used by Doradus are illustrated below:




Figure 1 - Basic Doradus Components

These components are:

- Application: This is a Doradus client application, which performs schema commands, updates objects, and submits queries using the Doradus REST API.
- Monitor Application: Doradus provides the JMX API to monitor resource usage and to perform
 certain administrative functions such as requesting backups. A JMX application such as JConsole
 can be used to invoke JMX functions.
- Doradus Server: This is the core Doradus component, which processes REST and JMX requests. It communicates with Cassandra using either the Thrift API or CQL API. The doradus.yaml file is the primary Doradus configuration file.
- Cassandra Server: This is the core Cassandra component, which provides persistence, replication, elasticity, and other database services. Cassandra's primary configuration comes from the cassandra.yam1 file. Cassandra stores data in various data and log files.

July 16, 2014 Page 5 of 36

3.2. Minimal Configuration

Doradus uses the Cassandra NoSQL database engine for persistence, scalability, and availability. Compared to traditional relational database systems, which scale *vertically*, NoSQL databases such as Cassandra scale *horizontally*. This means that they do not require high-end servers, SAN storage, RAID configurations, and fiber channel but instead utilize a cluster of low cost, "shared nothing" servers.

Each server within a cluster is referred to a *node*. Each node adds processing capabilities to the cluster via local processes, and it adds storage capacity via locally-attached disk. For smaller deployments and testing environments, a single node can be used that runs one instance each of the Doradus Server and Cassandra Server. For a minimal level of protection, the data and log files should reside on redundant disks (e.g., RAID level 1). This is depicted below:




Figure 2 – Single Node Configuration

The workload that this minimal configuration can handle depends on many factors: hardware, database size, update volume, and average query size. By default, Doradus is configured with a maximum internal thread limit of 200. Tests show that a single Doradus server can handle twice that number of simultaneous client connections (400). More connections may be possible in some cases; fewer if the average client demand is higher. (Software configuration options are described later.)

One or more application processes are assumed to reside on separate, network-near servers. In many cases, the application server process can also reside on the same node.

3.3. Two Node Configuration

To provide failure resiliency in a production deployment, at least two nodes should be used. Each node requires a Cassandra Server instance and local disk, and Cassandra must be configured with a *replication factor* of 2 (RF=2). In this configuration, there is no need for mirrored disks since each node contains a

July 16, 2014 Page 6 of 36

complete copy of all data. At least one node must run a Doradus Server instance. This configuration is illustrated below:




Figure 3 - Basic 2 Node Cluster: RF=2

As shown, the single Doradus Server instance receives all REST commands and JMX requests. It is configured to connect to both Cassandra instances by defining the doradus.yaml parameter dbhost as a list of both addresses. Subsequently, Doradus distributes requests to both nodes, providing load balancing. The Cassandra nodes are configured with replication factor 2 (RF=2) so that each holds an identical set of data. Should one Cassandra server instance fail, all services can be supported by the surviving node.

Multiple Doradus instances can be used in the same cluster. A typical configuration is to deploy a Doradus instance on each node but configure it to use all Cassandra instances. In a 2-node configuration, this provides full redundancy and protection against any single process or machine failure. A fully redundant 2-node configuration is show below:

July 16, 2014 Page 7 of 36




Figure 4 - Fully Redundant 2 Node Cluster: RF=2

When multiple Doradus instances are used in the same cluster, they are *peers*: any request can be sent to any instance. If a node fails, applications can redirect requests to any available instance. Doradus instances also communicate with each other to distribute background worker tasks and coordinate schema changes.

3.4. Expanding the Cluster

Additional nodes can be added to a cluster to increase processing and storage capacity. With a 3-node cluster, the recommended configuration is to use RF=2. Cassandra will distribute the data evenly within the cluster using a random partition scheme. An example 3-node cluster is illustrated below:

July 16, 2014 Page 8 of 36




Figure 5 - Expanded Cluster: 3 Nodes, RF=2

In this configuration, every record is stored on a primary node according to its key, but RF=2 causes the record to be replicated to one other node. Hence, each node will have roughly 2/3's of the database's total records. Full database services are available if any single process or node fails. Each Doradus instance is configured to distribute requests among all Cassandra instances.

Going further up the scalability ladder, below is an example of a 5-node configuration with RF=3:




Figure 6 - Expanded Cluster: 5 Nodes, RF=3

In this example, RF=3 means that every record will be stored on a primary node and then replicated to two other nodes. This means each node has roughly 3/5's of all data. Up to 2 nodes can fail and all database services will remain available. This provides increased scalability and fault tolerance.

July 16, 2014 Page 9 of 36

3.5. Multi-Data Center Deployments

Larger deployment topologies are also possible. Cassandra clusters can scale to hundreds of nodes. Each Cassandra node can also be configured with a specific *rack* and *data center* assignment. A rack is usually network-near to other racks in the same data center but independently powered. Data centers are geographically dispersed. With rack and data center awareness, Cassandra can use a replication policy that ensures maximum availability should a node, rack, or entire data center fail. An example of a multi-rack/multi-data center deployment is shown below:




Figure 7 - Multi-Data Center Deployment

Advanced configurations such as these are beyond the scope of this document, but information about Cassandra configuration is publicly available.

3.6. Hardware Recommendations

Server class hardware is recommended for Doradus cluster nodes, though "commodity x86" based servers are sufficient, as opposed to high-end servers. The recommended hardware for each node is summarized below:

- Dual guad core Xeon processors with HT (8 cores, 16 virtual CPUs)
- 32GB of memory
- 2 x 1Gbit NICs
- 4 x hard disks (or more)

Software configuration for effectively using CPUs is described later. Two NICs are recommended, configured as follows:

- Internode traffic: Each node should have one NIC dedicated for traffic to other nodes. Cassandra will use this connection for replication and coordination. This NIC should be given a static IP address since each node will be configured to know the IP address of other nodes.
- External traffic: The other NIC should be dedicated for outbound traffic with applications.

July 16, 2014 Page 10 of 36

A minimum of 4 hard disks are recommended, used as follows:

- Disk 1: Operating system and software (i.e., C: drive)
- Disk 2: Cassandra commit log
- Disks 3 and 4: Cassandra data files (2)

The software and commit log disks do not have to be large. The size and number of disks used for Cassandra data files depend on the volume of data expected. A minimum of two disks is recommended to allow parallel I/Os and improved bandwidth. When more data capacity is required for a node, added disks should be allocated to additional data files. Because resiliency is provided by internode replication, configuring disks with RAID is unnecessary.

Virtualized hosts are possible but some Cassandra experts <u>suggest</u> that virtualization adds a 5-15% performance penalty.

3.7. Security Considerations

This section describes security considerations that should be observed when Doradus is used to store sensitive data. Details on configuring specific Doradus and Cassandra options, such as enabling TLS for the Doradus REST protocol, are described later in sections **Doradus Security Options** and **Cassandra Security Options**.

Within the Doradus architecture, application data is stored on disk and transferred across a network. Additionally, certain configuration files contain options such as passwords and must thereby be treated as sensitive. The following diagram illustrates the files and protocols (APIs) that have potential security considerations:




Figure 8 - Files and Protocols with Security Considerations

July 16, 2014 Page 11 of 36

3.7.1. Protocols

The protocols used by Doradus and Cassandra and their security considerations are summarized below:

- **Doradus REST API**: This is the primary protocol used by applications to update and query objects. Doradus does not provide application-level security features: an application that can successfully connect to Doradus can update and access all objects. However, Doradus allows the REST API to be configured to use TLS (SSL), and it can restrict connections to those that provide a specific client-side certificate.
- **Doradus JMX API**: Doradus uses the standard Java Management Extensions (JMX) protocol for monitoring and to perform operational functions such as backup and recovery. Though application data is not transferred over the JMX API, access to it can be restricted to prevent unintended operational functions. The JMX API can be secured with authentication and/or TLS.
- Cassandra API: There are two application protocols for Cassandra: Thrift and CQL. Doradus can use either protocol: see the section Configuration Parameters in doradus.yaml. Both protocols support TLS for encryption, however Doradus does not yet support this. If protected Doradus-to-Cassandra communication is desired, Doradus can be configured to use simple user/password-based authorization.
- Cassandra JMX API: Cassandra also uses the JMX protocol for monitoring and to perform certain
 operational functions. JMX can be configured to require authorization and/or to encrypt data using
 TLS.
- Cassandra Gossip API: This is an inter-node communication protocol used by Cassandra to replicate data, coordinate schema changes, and perform other activities. The protocol can be configured to use TLS for encryption, however, because of the high-volume nature of this protocol, encryption is not recommended except for cross-data center communication.

3.7.2. Configuration and Data Files

The configuration and data files used by Doradus and Cassandra and their security considerations are summarized below:

- Doradus configuration files: The primary Doradus configuration file is doradus.yaml. This file and several "properties" files (e.g., passwd.properties, log4j.properties) are stored in the folder {doradus_home}/config. These files should be considered sensitive and secured from unauthorized access.
- Cassandra configuration files: The primary Cassandra configuration file is cassandra.yaml. This file and other secondary configuration files are stored in the folder {cassandra_home}/conf. These files should be considered sensitive and secured from unauthorized access.
- Cassandra data files: All application data is stored in Cassandra data files, which reside in various folders as described in the section Setting Cassandra Data File Locations. The data in these files is unencrypted and should be secured from unauthorized access.

July 16, 2014 Page 12 of 36

3.7.3. Best Practices

The recommendation best practices for security Doradus and Cassandra protocols and files are summarized below:

- Cluster subset: Deploy Doradus/Cassandra nodes on a subnet that is restricted from outside access.
 If applications reside outside of the subset, enable routing rules that restrict access to the Doradus REST API port.
- Doradus REST API: Secure the Doradus REST API by configuring it to use TLS. Create a client
 certificate that is used to restrict access to authorized applications as describe in the section
 Securing the Doradus REST API.
- **Doradus JMX API**: Use basic user ID/password authentication as described in section **Securing the Doradus JMX API**.
- Cassandra Thrift API: Use basic authentication as described in section Securing the Thrift Protocol.
- Cassandra JMX API: Use basic user ID/password authentication as described in section Securing the Cassandra CQL Protocol

The CQL API offers encryption via TLS, but Doradus does not yet support it. This section will be updated when Doradus can use CQL over TLS.

- Securing the Cassandra JMX Protocol.
- **Doradus and Cassandra configuration files**: Secure the folders in which Doradus and Cassandra are installed, including their bin and conf or config folders.
- Cassandra data files: Secure the Cassandra data file folders with permissions that restrict access to the user ID under which the Cassandra process executes. For stronger security, encrypt the data within the file system, e.g., by using the Encrypted File System (EFS) on Windows.

July 16, 2014 Page 13 of 36

4. Doradus Configuration and Operation

This section provides recommendations for runtime and configuration options for the Doradus server.

4.1. Runtime Memory

The default JVM memory is probably for a Doradus Server doing anything important. Also, tests have shown that *growing* a Java process's memory can be very disruptive, therefore, we recommend setting both the minimum and maximum memory parameters to the same value. 4GB is a good value to start with. Example:

```
java -Xms4G -Xmx4G -cp "../lib/*:../config/*" com.dell.doradus.core.DoradusServer
```

4.2. Doradus Configuration Files

The following are the primary Doradus configuration files within the {doradus home}/config folder:

- doradus.yam1: This file provides global configuration parameters. Typically only a few parameters merit modification from their defaults.
- log4j.properties: This file controls logging features of the Doradus instance.
- passwd.properties: This file contains the user ID and password used when the Thrift protocol is configured to require authentication.

4.2.1. Setting Doradus Logging Options

Doradus logs messages about its operation using the log4j logging facility. Logging options are define in the file log4j-server.properties. One option you might consider changing is:

```
log4j.rootLogger=INFO, console, file
```

This sets the global logging level to INFO, and it sends log messages to both the console (stdout) and a "file" appender. If Doradus is run as a service, the duplicate output to "console" is unnecessary, so this parameter should be removed. Also, in diagnostic situations, you might want to change the INFO keyword to DEBUG to generate additional logging messages. Note that DEBUG log level causes log files to grow more quickly.

The log4j-server.properties file also defines the following option:

```
log4j.appender.file.File=doradus.log
```

This option sends the "file" log appender to a log file called doradus.log in the Doradus server's runtime directory. If you wish log files to be stored with another name and/or in another location, modify this option with a new relative or absolute file name.

Two other options to consider:

```
log4j.appender.file.maxBackupIndex=50
log4j.appender.file.maxFileSize=20MB
```

These options cause the log file to grow up to 20MB, at which point it is renamed with a numeric extension (.1, .2, etc.) and a new file is started. Up to 50 files are retained (up to 1GB total log data), at which point the oldest file is removed. Modify these options to increase or decrease the number and size of log files stored.

July 16, 2014 Page 14 of 36

4.2.2. Doradus Security Options

Doradus does not store any application data; all data is stored by the Cassandra database service. Securing Doradus from unauthorized access requires securing its configuration files at the network protocols.

4.2.2.1. Securing the Doradus REST API

By default, the Doradus REST API uses unencrypted HTTP. Because Doradus provides no application-level security, any process that connect to the Doradus REST port is allowed to perform all schema, update, and query commands. The REST API can be secured by enabling TLS (SSL), which encrypts all traffic and uses mutual authentication to restrict access to specific clients. Optionally, client authentication can be enabled to restrict connections to only those whose certificates have been registered at the server. The process for securing the REST port with TLS is defined below:

1) Enable TLS by setting the tls parameter in the doradus.yaml file to true. Example:

```
tls: true
```

2) Create a certificate for use by the Doradus server and store it in a keystore file. You can use the keytool utility included with the JRE. An overview of the process to create a self-signed certificate is outline here:

http://docs.oracle.com/javase/6/docs/technotes/quides/security/jsse/JSSERefGuide.html#CreateKeystore

3) Set the keystore parameter in the doradus.yam1 file to the location of the **keystore** file, and set the keystorepassword parameter to the file's password. Example:

```
keystore: config/keystore
keystorepassword: mykspassword
```

4) If client authentication will be used, create a certificate for each client application and import them into a **truststore** file. (See the same article referenced above.) Set the truststore parameter in the doradus.yaml file to the location of the keystore file, and set the truststorepassword parameter to the file's password. Example:

```
truststore: config/truststore
truststorepassword: mytspassword
```

5) To require client authentication, set the clientauthentication parameter in the doradus.yaml file. This requires REST API connections to use mutual authentication. Example:

```
clientauthentication: true
```

6) The cipher algorithms allowed by the REST API when TLS is enabled is controlled via the tls_cipher_suites parameter. The default list includes the algorithms recommended for FIPS compliance. The actual algorithms allowed by REST API is a subset of the listed algorithms and those actually available to the JVM in which Doradus is running. The cipher algorithm list can be tailored, for example, to only allow 256-bit symmetrical encryption. Example:

```
tls_cipher_suites:
```

- TLS_DHE_DSS_WITH_AES_256_CBC_SHA
- TLS_DHE_RSA_WITH_AES_256_CBC_SHA
- TLS_RSA_WITH_AES_256_CBC_SHA
- TLS_ECDHE_ECDSA_WITH_AES_256_CBC_SHA

July 16, 2014 Page 15 of 36

Doradus Administration

```
- TLS_ECDHE_RSA_WITH_AES_256_CBC_SHA
- TLS ECDH ECDSA WITH AES 256 CBC SHA
```

- TLS_ECDH_RSA_WITH_AES_256_CBC_SHA

Custom algorithms can also be used as long as installed with the JVM used to run Doradus.

With the steps above, Doradus will use TLS for its REST API port, optionally requiring mutual authentication. Clients must connect to the REST port using TLS. If client authentication is enabled, they must submit a certificate that was added to the truststore. Each client must also support one of the configured cipher algorithms.

4.2.2.2. Securing the Doradus JMX API

Doradus supports the Java Management Extensions (JMX) protocol for monitoring Doradus and performing certain administrative commands. JMX can be secured with authorization and/or encryption, however, security JMX security is disabled in the {doradus_home}/bin/doradus-server.bat file included with Doradus. The common JMX options are defined in variables at the top of the file as shown below:

```
set JMX_PORT=9999
set JMX_SSL=false
set JMX_AUTHENTICATE=false
```

These options are summarized below:

- JMX_PORT: This variable sets the com.sun.management.jmxremote.port define in the JVM, which is the port number that the remote JMX clients must use. As shown, port 9999 is the default used for Doradus.
- JMX_SSL: This variable sets the com.sun.management.jmxremote.ssl define in the JVM. When set to true, it requires remote clients to use SSL (TLS) to connect to the JMX port. When SSL is enabled, additional options are available to require remote clients to have a client-side certificate.
- JMX_AUTHENTICATE: This variable sets the com.sun.management.jmxremote.authenticate define in the JVM. When set to true, it requires remote clients to provide a user ID and password in order to connect. Additional parameters are required to define allowed user IDs and passwords and the locations of the corresponding files.

Because JMX is a standard and external documentation is available for securing JMX, details for using SSL and/or authentication are not covered here. See for example the following:

http://docs.oracle.com/javase/6/docs/technotes/guides/management/agent.html

Though not shown above, here is another useful option: On multi-homed systems, java.rmi.server.hostname can be set to a specific IP address, causing JMX to bind to that address instead of the default one. For example:

```
set JAVA_OPTS=
...
-Djava.rmi.server.hostname=10.1.82.121^
```

This causes the JMX port to bind to address 10.1.82.121.

July 16, 2014 Page 16 of 36

4.2.2.3. Using a Secured Thrift API

As described in the section **Securing the Thrift Protocol**, by default Cassandra's Thrift API is not secured. Encrypted communication for this protocol is available, but Doradus currently does not support it. Instead, basic user id/password authentication can be added to the Thrift API.

To use basic authentication, Doradus must be configured to use user ID and password that Cassandra will recognize. By default, in the Doradus script {doradus_home}/bin/doradus-server.bat sets the following JVM define to identify the file that contains the Cassandra database user ID and password:

```
-Dpasswd.properties=passwd.properties
```

The passwd.properties file resides in the {doradus_home}/config folder. You should edit it to contain two lines that define the user ID and password:

```
dbusername=Doradus
dbpassword=changeit
```

The value of dbusername and dbpassword should match the user ID/password you defined in Cassandra's configuration, as described in the section **Securing the Thrift Protocol**.

Next, tell Doradus to use the an authentication class by setting the dbauthenticator parameter in the doradus.yaml file. Example:

```
dbauthenticator: com.dell.doradus.service.db.SimpleAuthenticator
```

Once these parameters are set and Cassandra is appropriately configured, Doradus will use this authentication mechanism for all connections using the Thrift API.

4.2.3. Configuring Doradus for Clusters

Multiple instances of Cassandra and/or Doradus can be used in the same cluster. As described in the section **Deployment Guidelines**, a recommended practice is to deploy an instance of both Doradus and Cassandra on each node. Then, each Doradus instance should be configured to contact all Cassandra nodes. This provides load balancing and fault tolerance in case a Cassandra node fails.

The Cassandra instance(s) to which each Doradus instance connects is defined in the dbhost parameter in its doradus.yaml file. This parameter should be set to a comma-separated list of host names or (preferably) IP addresses of Cassandra instance hosts. For example:

```
dbhost: 10.1.82.146, 10.1.82.147, 10.1.82.148
```

This example tells the corresponding Doradus instance to use three Cassandra instances. Doradus will distribute connections across these nodes for load balancing.

4.2.4. Configuration Parameters in doradus.yaml

This section describes the parameters that can be set in the doradus.yam1 file. Except as discussed in the previous sections, most of these parameters can be left at their default value. However, there are some values that you should change for clustered configurations, to enable OLAP caching, etc.

July 16, 2014 Page 17 of 36

4.2.4.1. Doradus Service Parameters

The storage_services parameter defines which storage services are initialized when Doradus is started as a standalone application (e.g., as a service or console app). At least one storage service must be defined. The first storage service listed becomes the default for new applications created without explicitly declaring a storage service. Example:

```
storage_services:
    - com.dell.doradus.service.spider.SpiderService
    - com.dell.doradus.service.olap.OLAPService
```

This initializes both the Spider and OLAP services, making the Spider service the default for new applications.

4.2.4.2. Cassandra Keyspace Parameters

These parameters control the initial creation of the Cassandra *Keyspace* used by Doradus. A single Keyspace is created by Doradus and used to hold all ColumnFamilies used by Doradus applications. When the Doradus server starts, if the configured Keyspace does not exist, it is created using the parameters configured below.

```
keyspace: 'Doradus'
ks_defaults:
    - strategy_class: SimpleStrategy
    - strategy_options:
          - replication_factor: "1"  # enclose this value in quotes
          - durable_writes: true
```

The keyspace parameter is the keyspace name and defaults to 'Doradus'. The ks_defaults parameter defines parameters passed to Cassandra to create the Keyspace. All parameters accepted by Cassandra are allowed and are passed "as is". Note that parameters should be indented and begin with a dash (-). When used, subparameters such as the replication_factor passed to strategy_options, should be further indented. Numeric values should be enclosed in quotes.

When the Doradus server starts, if its configured Keyspace already exists, its parameters are not modified to match values in doradus.yaml. It is safe to use Cassandra tools such as cassandra-cli to modify Keyspace parameters when needed.

See Cassandra documentation for information about Keyspace parameters.

4.2.4.3. Cassandra ColumnFamily Parameters

The cf_defaults parameter is used when Doradus creates a new ColumnFamily. All values recognized by Cassandra are allowed and are passed "as is". Parameters must begin with a dash (-), and sub-parameters should be further indented. Empty values should be specified with a pair of quotes. Example:

```
cf_defaults:
    - compression_options:
          - sstable_compression: ""  # use empty string for "none"
          - gc grace seconds: 3600
```

July 16, 2014 Page 18 of 36

After a ColumnFamily is created, Doradus does not modify its parameters to match values in doradus.yaml. It is safe to use Cassandra tools such as cassandra-cli to modify ColumnFamily parameters when needed.

See Cassandra documentation for information about ColumnFamily parameters.

4.2.4.4. Cassandra Connection Parameters

These parameters control connections to the Cassandra database using the Thrift or CQL APIs:

dbhost: 'localhost'

This parameter configures the host name(s) or address(es) of the Cassandra node(s) that the Doradus server connect to. Static IP addresses are preferred over host names. If a comma-separated list of hosts is provided, Doradus will connect to each one in round-robin fashion, allowing load balancing and failover.

dbport: 9160

This is the Cassandra Thrift or CQL API port number. Change this value if Cassandra's port is using something other than 9160. (Cassandra should use the same port on all nodes.)

jmxport: 7199

Change this value if Cassandra's JMX port is using something other than 7199. (Cassandra should use the same port on all nodes.)

dbauthenticator:

As described in section **4.2.2.3** Using a Secured Thrift API, this parameter should be set to the fully qualified class name of the authenticator class to use when the Cassandra Thrift API is configured to require authentication. The default is null, which means no authentication.

```
db timeout millis: 60000
```

This is the socket-level Cassandra database connection timeout in milliseconds. It is applicable to both the Thrift and CQL APIs. This time is used both when connecting to Cassandra and when performing read/write operations. If a connect, read, or write request is not received within this time, the connection is closed and a retry is initiated. Note, however, that Cassandra has its own RPC timeout value, which defaults to 10 seconds. This means that read and write operations will typically based on Cassandra's value and not this one.

```
db_connect_retry_wait_millis: 30000
```

This is the Cassandra database (Thrift) initial connection retry wait in milliseconds. It is applicable to both the Thrift and CQL APIs. If an initial connection to Cassandra times-out (see db_timeout_millis above), Doradus waits this amount of time before trying again. Doradus keeps retrying indefinitely under the assumption that Cassandra may take a while to start.

```
max_commit_attempts: 10
```

This is the maximum number of times Doradus will attempt to perform a Cassandra update operation before aborting the operation. (See also retry_wait_millis).

July 16, 2014 Page 19 of 36

```
max_read_attempts: 3
```

This is the maximum number of times Doradus will attempt to perform a read operation before aborting the operation. (See also retry_wait_millis).

```
max_reconnect_attempts: 3
```

This is the maximum number of times Doradus will attempt to reconnect to Cassandra after a failure. A reconnect is performed if a read or update call fails. (See also retry_wait_millis).

```
retry wait millis: 5000
```

This is the time in milliseconds that Doradus waits after a failed update, read, or reconnect request call to Cassandra. This time is multiplied by the attempt number, which means Doradus waits a little longer after each successive failed call. (See also max_commit_attempts, max_read_attempts, and max_reconnect_attempts.)

```
use_cql: false
```

By default, Doradus uses the Thrift API to communicate with Cassandra. When this option is set to true, it uses the CQL API instead. CQL must be enabled in each Cassandra instance that Doradus connects via the cassandra.yaml file option start_native_transport: true. Additionally, the doradus.yaml file option dbport must be set to the CQL API's port (the default is 9042).

Note: A Doradus database created with the v2.1 or prior release must continue to use the Thrift API. New databases created with the v2.2 release can use either Thrift or CQL. Tests show that the Thrift API is a little faster for bulk data loading by about 3%. But over time, CQL may be faster due to the advantages of prepared statements. CQL is the recommended Cassandra API, and over time the Thrift API may be phased-out.

4.2.4.5. Doradus REST API Parameters

These parameters configure the Doradus REST API.

```
restaddr: 0.0.0.0
```

By default, the Doradus REST API binds to address 0.0.0.0, which means it accepts connections directed to any of the host's IP addresses (including "localhost"). Change this value if you want the REST API to accept connections on a specific IP address instead.

```
restport: 1123
```

This is the REST port that Doradus listens to. Change this to accept REST API connections on a different port.

```
maxconns: 200
```

This is the maximum number of connections that the Doradus server will service at one time. If more than this number of connections is received, each additional connection is queued but not serviced until an existing connection is closed. This value also controls the maximum size of the REST server thread pool.

```
tls: false
tls_cipher_suites:
```

July 16, 2014 Page 20 of 36

```
- TLS_DHE_DSS_WITH_3DES_EDE_CBC_SHA
```

clientauthentication: false keystore: config/keystore keystorepassword: changeit truststore: config/truststore truststorepassword: password

As described in the section **4.2.2** Doradus Security Options, these parameters should be set to configure TLS/SSL for the Doradus REST API and to restrict connections to authenticated clients.

```
max request size: 52428800
```

This parameter determines the maximum size of an input requested that is accepted. Requests larger than this are rejected and the socket is closed. The default is 50MB.

4.2.4.6. Doradus Query Parameters

These parameters configure defaults used for Doradus object and aggregate query parsing and execution.

```
search_default_page_size: 100
```

This value is the default query page size used when an object query does not specify the &s (page size) parameter.

```
aggr_separate_search: false
aggr_concurrent_threads: 0
dbesoptions_entityBuffer: 1000
dbesoptions_linkBuffer: 1000
dbesoptions_initialLinkBuffer: 10
dbesoptions_initialLinkBufferDimension: 1000
dbesoptions_initialScalarBuffer: 30
12r_enable: true
```

These parameters are set by the Doradus team and normally should not be changed.

4.2.4.7. OLAP Parameters

These parameters control the operation of the OLAP service:

```
olap cache size mb: 100
```

This parameter controls the memory size of the most-recently-used field cache. If this value is exceeded, older fields will be un-loaded from memory.

```
olap_loaded_segments: 0
```

This parameter controls the number of most-recently-used segment statistics structures cached. Statistics structures are needed to load segment fields; they are small and do not occupy much memory. If this value is zero, the default value is 1 million, which is sufficient even if your application performs many merges.

July 16, 2014 Page 21 of 36

```
olap_file_cache_size_mb: 100
```

When this value is non-zero, it enables OLAP "file" caching and sets the total size, in megabytes, of the cached data. OLAP uses virtual files to hold raw scalar values such as text values. Caching this data prevents round-trips to the database for certain types of queries. This value does not affect shard caching defined by other parameters.

```
olap_query_cache_size_mb: 100
```

When this value is non-zero, it enables recent query result caching and sets the total size, in megabytes, of the cached search results. Each cached result takes 1 bit per each object in the table.

```
olap_cf_defaults:
    - compression_options:
          - sstable_compression: "" # use empty string for "none"
          - gc_grace_seconds: 3600
```

This parameter is used to create the OLAP ColumnFamily. All parameters recognized by Cassandra are accepted and passed "as is". Parameters must be indented and begin with a "-"; sub-parameters must be further indented. The OLAP ColumnFamily is created when the server is first started for a new database. If the OLAP ColumnFamily already exists, it is not modified to match these parameters. See Cassandra documentation for details about these values.

One parameter worth highlighting is the OLAP ColumnFamily's gc_grace_seconds. This value controls how long deleted rows called "tombstones" are retained with data tables (called *sstables*) before they are truly deleted during a compaction cycle. The default is 864,000 seconds or 10 days, which provides lots of time for a failed node to recover and learn about deletions it may have missed. However, the OLAP service deletes many rows when it merges a shard, and these rows consume disk space. Moreover, they consume memory because active sstables are memory-mapped (mmap-ed) by Cassandra. This can cause excessive memory usage.

A much smaller gc_grace_seconds value is recommended for the OLAP CF, somewhere between 3600 (a hour) and 86400 (1 day). This causes tombstones to be deleted more quickly, freeing-up disk space and reducing memory usage.

4.2.4.8. Spider Parameters

These parameters control the operation of the Spider server:

```
batch_mutation_threshold: 10000
```

Defines the maximum number of mutations a batch update will queue before flushing to the database. After the mutations are generated for each object in a batch update, Spider checks to see if this threshold has been met and flushes the current mutation batch if it has. Larger values improve performance by reducing Cassandra round trips, but they require larger API buffer sizes. The default is 10,000.

4.2.4.9. Background Tasks Parameters

```
max_node_tasks: 2
```

July 16, 2014 Page 22 of 36

Defines the maximum number of tasks that can be launched concurrently on one Doradus node. If there is no node that can launch a task since all the nodes are busy with max_node_tasks each, then the task is skipped, and may be scheduled next time.

task_exec_delay: 5

Defines the minimum interval (in seconds) between the scheduled time and actual start of the task. This delay is used for Doradus nodes to synchronize and to decide which node would perform the task. After this initial delay, the task may be delayed once more for maximum task_exec_delay seconds, so actual time interval between scheduled time and actual task start time may be between task_exec_delay and 2 * task_exec_delay seconds.

task_restarts: 2

Number of attempts to restart a task if it was interrupted due to an internal error. The task will not be restarted if an external error (like server node fault) occurs.

```
check_interrupting_interval: 10
```

Defines the interval (in seconds) between consequent analysis of whether a task that is executing by this node was interrupted by user request.

default_schedule:

Global default schedule used for all tasks for all applications and tables. The value is a cron expression (example: " $0\ 0\ 31\ 10\ *$ "). The default is null, which means no tasks are automatically scheduled.

4.3. Managing Doradus via JMX

Doradus extends the Java JMX API with monitoring and administration features. JMX functions can be accessed with off-the-shelf JMX applications such as JConsole, which is bundled with the Java SDK. JMX functions are available from two MXBean objects:

- com.dell.doradus.ServerMonitor: This MXBean provides information about the Doradus server including its configuration, start time, and statistics about REST commands.
- com.dell.doradus.StorageManager: This MXBean provides information used by the Doradus Task Manager to conduct background tasks. It also provides operations for modifying tasks and to execute Cassandra backup and recovery tasks.

JMX functions only collect and return information when the Doradus MBean service (com.dell.doradus.mbeans.MBeanService) has been initialized. This is always the case when the server is started as a standalone process but optional when Doradus is embedded within another application.

4.3.1. ServerMonitor

ServerMonitor provides the following attributes:

Attribute Name	Description
AllRequests	Provides a composite set of values about REST API requests such as the total
	number of requests, the number of failed requests, and the reason of the last

July 16, 2014 Page 23 of 36

	request failure.
ConnectionsCount	The current number of REST API connections.
DatabaseLink	Indicates if the Cassandra database being accessed is local (1), remote (2), or not yet known (0).
RecentRequests	A composite value set similar to AllRequests but for REST API requests made since the last time RecentRequests was accessed.
ReleaseVersion	The Doradus Server release version.
ServerConfig	Lists configuration doradus.yaml settings, including value overridden by runtime arguments.
StartTime	Provides the start time of the Doradus server as a Date.getTime() value.
Throughput	Provides a histogram of REST API request response times in seconds for various sampling rates (e.g., 1 minute, 5 minutes, 15 minutes.)
WorkingDirectory	The working directory of the Doradus server.

4.3.2. StorageManager

StorageManager is operative only when the Task Manager service has been initialized (com.dell.doradus.service.taskmanager.TaskManagerService). This is always the case when the server is started as a standalone process but optional when Doradus is embedded within another application. StorageManager provides the following attributes:

Attribute Name	Description
AppNames	The Doradus application names known to the Task Manager.
GlobalDefaultSettings	The global task schedule settings, which are used for tasks that do not have a more specific (e.g., application- or table-specific) schedule default. The global schedule is usually "never", meaning no default schedule is applied to tasks.
JobList	The list of tasks currently executing.
NodesCount	The number of Cassandra nodes in the cluster.
OS	The operating system of the Doradus server.
OperationMode	The operation mode of the first connected Cassandra mode (NORMAL, LEAVING, JOINING, etc.)
RecentJob	Attributes about the most recent job executed through the StorageManager interface.
ReleaseVersion	The Doradus server release version.
StartMode	The execution mode of the first connected Cassandra node: 1 (FOREGROUND), 2 (BACKGROUND), or 0 (UNKNOWN).

The StorageManager MXBean also provides operations that perform basic administrative functions, summarized below:

Operation Name	Description
getJobByID	Get the status of a job with a specific ID.
startCreateSnapshot	Start a task to create a backup snapshot of the first Cassandra node
	connected to the Doradus server, assigning the snapshot a name.
startDeleteSnapshot	Delete a backup snapshot with a given name.
startRestoreFromSnapshot	Restore the Cassandra node connected to the Doradus server from a
	given snapshot game.
sendInterruptTaskCommand	Interrupt an executing task with a given name, belonging to a given
	application.

July 16, 2014 Page 24 of 36

Doradus Administration

sendSuspectSchedulingCommand	Suspend the scheduling of a task with a given name, belonging to a given application.
sendResumeSchedulingCommand	Resume the scheduling of a task with a given name, belonging to a given application.
getAppSettings	Get the default task schedule settings for a given application name.
getTaskStatus	Get the status of a task with a given name, belonging to a given application.

July 16, 2014 Page 25 of 36

5. Cassandra Configuration and Operation

This section describes the key configuration optional available for Cassandra. Not all options are covered – only common options and those that warrant modification in certain situations. Note that Cassandra options change from release to release. The options described here are relevant to the Cassandra 2.x release. Also, only options relevant to Windows installations are described.

5.1. Cassandra Script Files

Within the folder {cassandra_home}/bin, the following are the key scripts that can be used to launch Cassandra and various tools:

- cassandra.bat: This is the script file bundled with Cassandra to launch it from a command console. You can use this instead of {doradus_home}/bin/doradus-cassandra.bat file that is bundled with the Doradus (see the section Error! Reference source not found.). If you run Cassandra with this file, it efines Java runtime parameters you may wish to change such as memory usage and JMX protocol authentication.
- cassandra-cli.bat: This script file runs the Cassandra command line interface (CLI) tool. It can be used to perform low-level queries and to modify certain Cassandra schema options.
- nodetool.bat: This script launches the Cassandra nodetool utility, which can perform various
 Cassandra monitoring and operational commands: determining cluster status, forcing compaction,
 rebuilding a node, etc.

The bin folder contains .bat files for other tools as well. Except for cassandra.bat, most of the script files can run with the parameter "-?" to get help information.

5.1.1. Setting Cassandra Runtime Memory

By default, Cassandra is set to use only 1GB of memory. This is OK for testing on a developer workstation, but for production work, 8GB to 16GB of memory is recommended. This is controlled by the -xms and -xmx parameters. Within the {cassandra_home}/bin/cassandra.bat, these values are explicitly defined and can be modified as shown below:

```
set JAVA_OPTS=^
-Xms8G^
-Xmx8G^
```

For use by Doradus, 8GB is the recommended minimum memory. If the machine has 32GB of physical memory or more, 16GB is the recommended memory allocated to Cassandra.

5.1.2. Disabling Assertions

The Java runtime option -ea (or -enableassertions) is used to enable diagnostic "assert" statements in Java applications. It is useful in development/debugging environments since additional internal checking is performed, but it has a small performance cost. It should be disabled in production environments to eliminate the performance cost. This can be done by simply removing the -ea option in JVM options or replacing it with -da (or -disableassertions). In both the Cassandra script files {doradus_home}/bin/doradus-cassandra_bat and {cassandra_home}/bin/cassandra.bat, assertions are declared in the set JAVA_OPTS statement as shown below:

July 16, 2014 Page 26 of 36

```
set JAVA_OPTS=-ea^
```

5.2. Cassandra Configuration Files

The following are the primary Cassandra configuration files in the {cassandra_home}/conf folder:

- cassandra.yam1: This file provides global configuration options. There are a lot of options in this file, but only a few typically require modification from their defaults.
- log4j-server.properties: This file controls logging features of the Cassandra instance.

The following sections describe the options most commonly modified.

5.2.1. Setting Cassandra Logging Options

Cassandra logs messages about its operation using the log4j logging facility. The file that controls logging options is {cassandra_home}/conf/log4j-server.properties. The one option you should change is shown below:

```
log4j.appender.R.File=/var/log/cassandra/system.log
```

You should change this line to use a valid folder path where logs will be kept. The initial log file will be called system.log. When a log file becomes full (default is 20MB), it is renamed with a numeric suffix (e.g., ".1", ".2"). When 50 files are created, the oldest files are removed.

The other option you may want to modify under specific situations is:

```
log4j.rootLogger=INFO,stdout,R
```

This line sets the global logging level to INFO. In certain diagnostic situations, you might want to change the INFO keyword to DEBUG to generate additional logging messages. Note that DEBUG log level causes log files to grow quickly and slow down Cassandra.

5.2.2. Setting Cassandra Data File Locations

Cassandra creates three kinds of data files: commit logs, SSTables, and saved caches. (Somewhat confusingly, the SSTable files are sometimes called "data files" even though all three kinds of files hold data.) The folder path of each file kind is defined in cassandra.yam1. You should change all of the following folder options:

```
commitlog_directory: /var/lib/cassandra/commitlog
```

Set this option to the folder where commit logs should be stored. It should be a different disk than any of the SSTable disks (see below). Multiple commit logs are created in this folder, but they are deleted when they become obsolete, so typically commit logs do not require a lot of space.

Set this option to at least one root folder where SSTable files are to be stored. SSTables are the primary files containing application data. Each folder is listed on a secondary line, indented and beginning with a dash. Multiple data folders are recommended for better performance (see below).

July 16, 2014 Page 27 of 36

saved_caches_directory: /var/lib/cassandra/saved_caches

Set this option to a valid folder name where Cassandra will save key and row caches that it builds. It can be the same disk as the commit log or where software is installed, but it shouldn't be one of the SSTable disks. The size of disk space for caches depend on cache option settings.

When updates are sent to Cassandra, they are first written to a commit log file. The commit files are "replayed" when a restart occurs, thereby providing recovery for updates that may not have been written to an SSTable file. Because commit logs are removed when they are no longer needed, they typically do not use much disk space.

After updates are written to the commit log, they are stored in memory and eventually sorted and flushed to disk as SSTables. Each SSTable is represented by multiple files including data, hash, and index files. When Cassandra is configured with multiple data file directories, it flushes each SSTable to the directory that has the most available space. Therefore, best practices for the commit log and SSTable files are:

- 1. Each SSTable folder should reside on a separate disk. This allows concurrent I/Os: a separate I/O can be initiated for each disk
- 2. Each SSTable disk should be of the same size and used solely for SSTables. This prevents disk contention with other files, and it allows all disks to grow at the same rate.
- 3. The commit log folder should reside on its own disk. Because data is flushed quickly as it is received, the commit log folder can receive a high volume of I/O, hence it should use its own disk to prevent contention with SSTable files. The disk does not have to be large since commit logs are discarded fairly quickly.

5.2.3. Cassandra Security Options

As described in the **Security Considerations** section, Cassandra does not encrypt its commit log or data files. Disk files must be protected through operating system-level file security or encryption (e.g., Windows EFS). This section describes how to protect Cassandra's communication protocols: Thrift, CQL, JMX, and Gossip.

5.2.3.1. Securing the Thrift Protocol

The Thrift API is the primary protocol that applications such as Doradus use to communicate with Doradus. By default, Thrift uses an unencrypted connection and allows any process to connect and authenticate. To prevent unauthorized applications from directly accessing Cassandra, you should secure the Thrift API. Cassandra supports TLS-encrypted communication for the Thrift protocol, but Doradus does not currently support it. However, there are two ways to prevent unauthorized access to Cassandra's Thrift API.

One way to secure the Thrift connections is to deploy Doradus and Cassandra on a subnet and disallow access to the Thrift port (default 9160) from outside the subnet. This allows free communication between Doradus, Cassandra, and tools used on the subnet, whose access can be restricted to authorized administrators.

Alternatively, you can use Cassandra's configurable capability for its authorization and authentication modules. The modules that provide authentication (who can connect) and authorization (what each connection is allowed to do) are defined in the file {cassandra_home}/conf/cassandra.yaml as shown below:

Authentication backend, implementing IAuthenticator; used to identify users

July 16, 2014 Page 28 of 36

Doradus Administration

```
# Out of the box, Cassandra provides org.apache.cassandra.auth.{AllowAllAuthenticator,
# PasswordAuthenticator}.
#
# - AllowAllAuthenticator performs no checks - set it to disable authentication.
# - PasswordAuthenticator relies on username/password pairs to authenticate
# users. It keeps usernames and hashed passwords in system_auth.credentials table.
# Please increase system_auth keyspace replication factor if you use this authenticator.
authenticator: AllowAllAuthenticator

# Authorization backend, implementing IAuthorizer; used to limit access/provide permissions
# Out of the box, Cassandra provides org.apache.cassandra.auth.{AllowAllAuthorizer,
# CassandraAuthorizer}.
# - AllowAllAuthorizer allows any action to any user - set it to disable authorization.
# - CassandraAuthorizer stores permissions in system_auth.permissions table. Please
# increase system_auth keyspace replication factor if you use this authorizer.
authority: AllowAllAuthorizer
```

As shown, the default authenticator is AllowAllAuthenticator, which allows any process to connect, and the default authority is AllowAllAuthorizer, which allows each connection to perform any Thrift command.

A simple user ID/password-based mechanism can be used as described in the cassandra.yam1 file comments. PasswordAuthenticator can be used to provide password-protected access to Cassandra. Although CassandraAuthorizer can be used to control the types of access allowed by each user, Doradus requires full access to the database so it can make schema changes and read/write data. Therefore, you can change the authenticator to PasswordAuthenticator to restrict access to a password protected, Doradus-specific user while leaving the authority as AllowAllAuthorizer so that all permissions are allowed for the Doradus user.

Below is an outline of the steps required to use this strategy:

1. While Cassandra is not running, update the cassandra.yaml file to change the authenticator to PasswordAuthenticator. Example:

```
authenticator: PasswordAuthenticator
```

2. Save the file and start Cassandra. Because it requires at least one super user, Cassandra will create a default user "cassandra" with password "cassandra". You can see this in its log with a message such as the following:

```
INFO 09:11:10,659 PasswordAuthenticator created default user 'cassandra'
```

3. Run the CQL shell application (cqlsh) in Cassandra's bin directory, logging on with the default user. Example:

```
cd {cassandra_home}/bin
cqlsh -u cassandra -p cassandra
Connected to Test Cluster at localhost:9160.
[cqlsh 3.1.2 | Cassandra 1.2.6 | CQL spec 3.0.0 | Thrift protocol 19.36.0]
Use HELP for help.
```

4. Create a new super user for Doradus. Then, change the password for the default 'cassandra' to something obscure so that it can no longer be used. Example:

```
cqlsh> create user SuperDory with password 'Alpha1' superuser;
cqlsh> alter user cassandra with password 'Ajcj2846%!6';
```

July 16, 2014 Page 29 of 36

You can verify that the new user has been created by querying the users ColumnFamily in the system_auth Keyspace. Example:

- 5. As described in the previous section **Using a Secured Thrift API**, be sure to update doradus.yaml to set dbauthenticator to com.dell.doradus.server.SimpleAuthenticator, and set the dbuser and dbpassword options in passwd.properties to match the new user and password created above.
- 6. Start Doradus. It will use the new user ID and password you defined for all Cassandra connections.

Note that in a multi-node cluster, you should also increase the replication factor of the system_auth Keyspace so that records in the users ColumnFamily are replicated to multiple systems. This can be done with the following CQL command:

```
ALTER KEYSPACE "system_auth" WITH REPLICATION = {'class':'SimpleStrategy', 'replication_factor':3};
```

For more information on using the PasswordAuthenticator, see Cassandra documentation such as the following:

http://www.datastax.com/documentation/cassandra/1.2/webhelp/index.html#cassandra/security/security_config_native_authenticate_t.html

5.2.3.2. Securing the Cassandra CQL Protocol

The CQL API offers encryption via TLS, but Doradus does not yet support it. This section will be updated when Doradus can use CQL over TLS.

5.2.3.3. Securing the Cassandra JMX Protocol

Cassandra supports the Java Management Extensions (JMX) protocol for monitoring and controlling Cassandra processes. JMX can be secured with authorization and/or encryption, however, JMX security is disabled in the {cassandra_home}/bin/cassandra.bat file that is included with Doradus. The common JMX options are defined in the JAVA_OPTS environment variable as shown below:

```
REM ***** JAVA options *****
set JAVA_OPTS=-ea^
...
-Dcom.sun.management.jmxremote.port=7199^
-Dcom.sun.management.jmxremote.ssl=false^
-Dcom.sun.management.jmxremote.authenticate=false^
```

These options are summarized below:

• port: This sets the port number that the remote JMX clients must use. As shown, port 7199 is the default used for Cassandra.

July 16, 2014 Page 30 of 36

- ss1: When set to true, this option requires remote clients to use SSL (TLS) to connect to the JMX port. When SSL is enabled, additional options are available to require remote clients to have a client-side certificate.
- authenticate: When set to true, this option requires remote clients to provide a user ID and password in order to connection. Additional parameters are required to define allowed user IDs and passwords and the locations of the corresponding files.

Because JMX is a standard and external documentation is available for securing JMX, details for using SSL and/or authentication are not covered here. See for example the following:

http://docs.oracle.com/javase/6/docs/technotes/guides/management/agent.html

Though not shown above, here is another useful option: On multi-homed systems, the define java.rmi.server.hostname can be set to cause JMX to bind to a specific IP address instead of the default one. For example:

```
set JAVA_OPTS=-Djava.rmi.server.hostname=10.1.82.121^
```

This causes the JMX port to bind to address 10.1.82.121.

5.2.3.4. Securing the Cassandra Gossip Protocol

In a multi-node cluster, each Cassandra node communicates with peer nodes using the Gossip protocol. For non-encrypted connections, the Gossip protocol uses a TCP port defined by the following cassandra.yaml option:

```
storage port: 7000
```

When SSL is enabled for the Gossip protocol, the following cassandra.yaml file option defines the port number used:

```
ssl storage port: 7001
```

All nodes in a cluster should be configured to use the same storage_port and ss1_storage_port. To prevent eavesdropping or unauthorized disruptions, the gossip protocol should be secured in production environments. However, because the protocol is used for high-performance operations such as replicating data between nodes, encryption is not recommended except for communication between remote locations.

For co-located nodes, the easiest way to secure the Gossip API is to deploy all Cassandra nodes on the same subnet and disallow access to the Gossip port from outside the subnet.

In large Cassandra deployments where multiple "racks" or "data centers" are deployed, each having some number of Cassandra nodes, the Gossip protocol can be secured for cross-rack or cross-data center communication. This is done with the following options in the cassandra.yaml file:

encryption options:

internode_encryption: none
keystore: conf/.keystore
keystore_password: cassandra
truststore: conf/.truststore
truststore_password: cassandra

July 16, 2014 Page 31 of 36

Doradus Administration

Internode encryption (over the Gossip API) is enabled or disabled by the setting of the internode_encryption option. The following options are recognized:

- none: This disables all inter-node encryption, meaning Cassandra nodes use unencrypted communication using the defined storage_port.
- all: This enables encryption for all inter-node communication using the defined ssl storage port.
- rack: This uses non-encrypted communication for nodes defined to be in the same rack (cabinet) and encrypted communication between nodes defined to be in different racks.
- dc: This uses non-encrypted communication for nodes defined to be in the same data center and encrypted communication between nodes defined to be in different data centers.

When any encryption is enabled for the Gossip protocol, all authentication, key exchange, and data transfer occurs with TLS v1 using RSA 1024 bit keys. This encryption suite is referred to as TLS_RSA_WITH_AES_128_CBC_SHA. This requires that keystore and truststore files are defined and initialized. These files are password-protected using the keystore_password and truststore_password options. Instructions for creating these files can be found publicly, such as in this link:

 $\underline{http://docs.oracle.com/javase/6/docs/technotes/guides/security/jsse/JSSERefGuide.html \#CreateKeystore$

5.2.4. Configuring Cassandra for Clusters

By default, Cassandra assumes that it is operating as a stand-alone node. It must be configured to operate in a cluster. The following cassandra.yaml options affect a node's participation in a cluster:

- cluster_name: All nodes in the cluster must have the same name, which differentiates the cluster from other nodes that might be working in the same network or even on the same machine. The default name is "Test Cluster", so you should change this to something else like "Doradus Cluster".
- initial_token: This value defines the beginning range of key values for which the node will be the primary owner. It is not set by default, and it *may* be valid to leave it unset when configuring a new node. However, for a "balanced" cluster, you will need to set this value for each node.
- seeds: Seeds are IP addresses of neighboring nodes that this node can contact using the gossip protocol. The addresses provide only an initial set: after a node is running, it will memorize the addresses of other nodes in the network and contact them when necessary. The seeds are therefore necessary for the initial execution of a new node. Cassandra provides a generalized "seed provider" interface, but the built-in "simple seed provider" is sufficient for most situations.
- listen_address: This is the IP address that tells other nodes what IP address to use to communicate to this node. To participate in a cluster, you must change this from its default of "localhost". A host name can be used but is not recommended. The "any address" 0.0.0.0 will not work. You should use a static IP address visible to all other nodes. If the machine is multi-homed, a non-externally visible address (192.x or 10.x) is a good choice.
- partitioner: Beginning with the Cassandra 1.2 release, the default for this parameter is now Murmur3Partitioner. This random partitioning algorithm is more efficient than the older RandomPartitioner scheme, although the two are incompatible. All nodes in the cluster should use

July 16, 2014 Page 32 of 36

the same partitioning scheme. If you upgrade from an older Cassandra release, you'll need to ensure this parameter matches your existing value.

For more details on Cassandra configuration options, see http://wiki.apache.org/cassandra/Operations. The Wiki site also has information on topics such as:

- Adding new nodes to an existing cluster
- Migrating from the older to newer random partitioning scheme
- Recovering a node that has died
- Removing a node from the cluster
- Changing a cluster's replication factor
- Deploying larger clusters within multiple racks (cabinets) and even data centers

In addition to the Wiki site, there are several online sources and books on Cassandra configuration such as:

- The Cassandra web site http://cassandra.apache.org/ and especially the Operations page: http://wiki.apache.org/cassandra/Operations
- The Planet Cassandra user community site: http://planetcassandra.org/
- The Datastax web site http://www.datastax.com/ and its online documents.
- Books such as <u>Cassandra: The Definitive Guide</u> and <u>Cassandra High Performance Cookbook</u>

5.2.5. Other Cassandra Configuration Options

In addition to the options described in this section, there are other options in the cassandra.yaml file that you might want to change in certain circumstances. Here a list of the most common options:

- concurrent_reads: This value controls how many outstanding read operations are allowed at once. A recommended value is 16 times the number of data disks used.
- concurrent_writes: This value controls how many outstanding write operations are allowed at once. A recommended value is 8 times the number of cores present on the machine.

The next option is common to both the Thrift and CQL APIs:

• rpc_address: This value controls the address(es) to which Cassandra binds when listening for client connections. The same value is used to control both the Thrift and CQL APIs. The value localhost will allow only local connections. A specific IP address can be used, or the address 0.0.0.0 can be used to cause Cassandra to accept connections on all network interfaces.

The next options are specific to the Thrift API:

• start rpc: When true, this option causes Cassandra to initialize the Thrift API.

July 16, 2014 Page 33 of 36

Doradus Administration

- rpc_port: This is the Thrift API port that applications such as Doradus connect to. You can change it from its default of 9160, but it should be the same on all nodes. (And you must configure Doradus to know what port to use.)
- thrift_framed_transport_size_in_mb: This value controls the maximum size of a Thrift message that Cassandra will accept. The default (16MB) is often too small for Doradus applications that use "batch updates". A good idea is to increase this to 160MB.

The next options are specific to the CQL API:

- start_native_transport: When this option is true, Cassandra initializes the CQL API.
- native_transport_port: This is the CQL API port that applications such as Doradus connect to. You
 can change it from its default of 9042, but it should be the same on all nodes. If you configure
 Doradus to use the CQL API, its configuration must match this value.

5.3. Monitoring Cassandra

Cassandra supports the JMX protocol to provide monitoring capabilities. In addition to the normal Java parameters that can be monitored via JMX (memory usage, CPU usage, classes loaded, etc.), Cassandra implements numerous additional MBeans ("management beans"), which provide insights into core Cassandra operations and status. A detailed description of the Cassandra-specific MBeans can be found here:

http://wiki.apache.org/cassandra/JmxInterface

Generic JMX tools can be used to monitor Cassandra, including the JConsole tool that is bundled with the Java JDK. To use JConsole, install the Java SE 6 JDK and run jconsole.exe from the bin directory. JConsole will automatically find all Java processes on the current machine and offer to connect to them. If the Cassandra process you want to monitor is executing on a remote machine, select the Remote Process button and enter the host name or IP address and JMX port number of the remote Cassandra process you want to connect to. Example:

July 16, 2014 Page 34 of 36




Figure 9 - JConsole New Connection Dialog

If the remote JMX process is secured with authentication, enter the Username and Password with which JMX has been configured. When JConsole connects, it offers several panes for examining generic Java metrics as well as the Cassandra-specific MBeans. Below is an example of the Overview pane for a Cassandra process:

July 16, 2014 Page 35 of 36




Figure 10 - JConsole Overview Pane

Although JConsole can access Cassandra-specific MBeans, it provides generic UI widgets for accessing these functions. Furthermore, although JConsole can connect to multiple JMX-enabled processes at once, it does not provide integrated, cross-process metrics.

To get more detailed information about Cassandra information from a cluster perspective, there are a number of third party tools becoming available. See, for example, OpsCenter, which is available from Datastax:

http://www.datastax.com/

July 16, 2014 Page 36 of 36