
# ENCE360 Operating Systems



# Memory Management


#### Virtual Memory for More Memory

MOS Ch 4




#### In the beginning...

- All addressing physical
- Single process
- Spatial separation between the operating system and user program
- Very little safeguards



#### Single user, single program






#### Problem 1: multiple programs

- More than one process running at a time
- Protection needed between address spaces
- Protection from operating system
- Address space small




## Solution 1: Monoprogramming

- OS fixed into low addresses
- Programs compiled with *fixed* address space
- Poor solution:
  - Only certain combinations of programs can be run
  - External fragmentation
  - Operating system not protected



#### Multi-user, single program



main memory

# 4

#### Solution 2: base-limit address

- Virtual address space of 0 to P<sub>limit</sub>-1
- Processor given P<sub>base</sub> and P<sub>limit</sub> when this process switched into context
- Hardware (CPU) converts:
  - Address  $A_p = A_v + P_{base}$
  - Trap if  $A_p >= P_{limit}$




#### Base-limit problems


- Wasteful:
  - entire process loaded (locality)
  - External fragmentation
- P<sub>limit</sub> dictates total address space size
  - Write small programs, OR
  - Manage memory yourself (write out intermediate results)

# The "Manchester" Solution

- Divorce virtual address from physical memory
- Allow arbitrary address contiguous space
   (e.g. 32bits 4GB)
   (e.g. 64bits 18 million Terabytes (18 Exabytes))
- Virtual address space does not really exist anywhere
  - Physical memory mapped to currently used portion of address space



# Virtual Memory That is Larger Than Physical Memory




# Virtual Memory Paging

- Memory (V and P) divided up into pages of 512 to 8192 bytes
- MMU: V page mapped to physical using page table
  - E.g. specialised direct-mapped cache (no tag)
  - Data in cache is physical page number
  - Add page number to low bytes of V address (byte number) to get physical address
  - Treats physical memory as a fully-associative cache of the virtual address space (page table instead of tags)



#### Example: Linear Page Table






#### Page Table Entry (PTE) Contents

- Usually 32 bits:
  - Page frame number
  - Present/absent? bit
  - Modified? bit
  - Referenced? bit
  - Caching Disabled? bit
- OS records where other pages can be found




#### More problems

- Linear page table not feasible for big address spaces
- Use a tree: "hierarchical page table"
  - Most virtual pages are empty
  - Index the V address space
  - "Page table descriptor" nodes
  - Include nodes for resident pages only
  - Locality of reference assumed




#### Hierarchical page table




#### Translation Lookaside Buffer

- Cache of translations, stored in CPU/MMU (often the same)
- Look in TLB first. If failed, go to page table
- Needs to know context:
  - Invalidate on context switch OR
  - Store context too (just like cache)
  - Usually split Instruction/Data
- Small, fully associative (parallel search), hardwired (99% hit)




## Paging with TLB

(Translation Lookaside Buffer)





#### **Pentium**





# And if that's not enough...

- UltraSPARC: translation storage buffer (TSB)
  - If TLB (on CPU) miss, go to TSB
  - TSB controlled by OS, helped by hardware
  - If TSB lookup fails, go to page table (no hardware help)
- OS has to help!
  - Manage TSB according to exact format
  - Manage page table however it sees fit


# Still not fast enough?

Virtual addresses getting *huge* (physical memory relatively smaller - e.g. 32bit 2GB RAM with 4B page table entries in 4K page size => **4GB page table per process**)

#### Invert the page table: one page table for all processes

- One entry per physical page
- If TLB misses, look up inverted page table
- If not there (so not in memory) page fault occurs
- Hashing on virtual page number
- Decreases memory needed to store each page table, but increases time needed to search the table when a page reference occurs.


#### **Inverted Page Table**



Comparison of a traditional **page table per process** (above left) with one single **inverted page table for all processes** (right)


#### Inverted Page Table (hash table)

one single global inverted page table for all processes (pid=process ID, p=virtual page number, i=physical frame address, d=offset)



# Sharing memory pages

- If multiple processes need same memory pages, map to same physical memory
- Problem if one process wants to modify its copy
- Windows was: "copy-on-write"
  - Share same copy initially
  - On write, copy to new location, update one copy only
  - Also called "lazy evaluation"



## Shared pages example



ed 2

ed 3

data 1

process P<sub>1</sub>

data 3

process P3

3 4 6 1 page table

for P<sub>1</sub>

ed 1 3 ed 2 4 6 ed 3

2 page table for  $P_3$ 

ed 1 ed 2 ed 3 data 2

page table for  $P_2$ process P2

3

4

6

9

10

data 1

data 3

ed 1

ed 2

ed 3

data 2

#### Address space divison

- Some memory should not be cached (e.g. device registers)
- Some memory should not be mapped to virtual addresses (e.g. kernel)
- E.g. MIPS R2000
  - 2GB cached, mapped user segment
  - 512MB cached, unmapped kernel segment
  - 512MB uncached, unmapped kernel segment
  - 1GB cached, mapped kernel segment

# Segmentation

- Virtual address needs managing by OS
- Solution: "segmentation"
  - Multiple virtual address spaces
  - Handled by the hardware (MMU)
  - Separate into logical units:
    - Program
    - Variables
    - Stack
    - Heap, etc.

## Page Faults

- Only a subset of the V address space can fit in memory (working set)
- Access to non-resident address (page) signals a "page fault" exception
- Instruction "rolled back"
- Page fetched from disk, instruction executed again
- Other work (processes) done during the wait

#### Page Replacement Algorithms

- 4
  - Page fault forces choice
    - which page must be removed
    - make room for incoming page
  - Modified page must first be saved
    - unmodified just overwritten

- Better not to choose an often used page
  - will probably need to be brought back in soon

#### Optimal Page Replacement Algorithm



- Replace page needed at the farthest point in future
  - Optimal but unrealizable

- Estimate by ...
  - logging page use on previous runs of process
  - although this is impractical

#### Not Recently Used Page Replacement Algorithm



- Each page has Reference bit, Modified bit
  - bits are set when page is referenced, modified
- Pages are classified
  - not referenced, not modified
  - not referenced, modified
  - 3. referenced, not modified
  - 4. referenced, modified
- NRU removes page at random
  - from lowest numbered non empty class

#### FIFO Page Replacement Algorithm




- Maintain a linked list of all pages
  - in order they came into memory

Page at beginning of list replaced


- Disadvantage
  - page in memory the longest may be often used

#### Second Chance Page Replacement Algorithm



- Operation of a second chance
  - pages sorted in FIFO order
  - Page list if fault occurs at time 20, <u>A</u> has R bit set (numbers above pages are loading times)

#### The Clock Page Replacement Algorithm




#### Least Recently Used (LRU)




- Assume pages used recently will used again soon
  - throw out page that has been unused for longest time
- Must keep a linked list of pages
  - most recently used at front, least at rear
  - update this list every memory reference !!
- Alternatively keep counter in each page table entry
  - choose page with lowest value counter
  - periodically zero the counter

#### The Working Set Page Replacement Algorithm



- The working set is the set of pages used by the k most recent memory references
- w(k,t) is the size of the working set at time, t

#### The WSClock Page Replacement Algorithm



Operation of the WSClock algorithm

Review	of Page	Replacement	Algorithms

TREVIEW OF Fug.	e replacement / ligoriciiiis
Algorithm	Comment
Optimal	Not implementable, but useful as a benchmark

NRU (Not Recently Used)	Very crude
	NAC-1-1-11

WSClock

Nho (Not necently osed)	very crude
FIFO (First-In, First-Out)	Might throw out important pages

Second chance	Big improvement over FIFO
011-	Deallalla

Clock	Realistic					
LRU (Least Recently Used)	Excellent, but difficult to implement exactly					


tho (Least necently used)	Excellent, but difficult to implement exactly
NFU (Not Frequently Used)	Fairly crude approximation to LRU

NFU (Not Frequently Used)	Fairly crude approximation to LRU
Aging	Efficient algorithm that approximates LRU well

LRU (Least Recently Used)	Excellent, but difficult to implement exactly
NFU (Not Frequently Used)	Fairly crude approximation to LRU
Aging	Efficient algorithm that approximates LRU well
Working set	Somewhat expensive to implement

Good efficient algorithm

# Modeling Page Replacement Algorithms Belady's Anomaly



	0	1	2	3	0	1	4	0	1	2	3	4	
Youngest page	0	1	2	3	3	3	4	0	1	2	3	4	
		0	1	2	2	2	3	4	0	1	2	3	
Oldest page			0	1	1	1	2	3	4	0	1	2	
				0	0	0	1	2	3	4	0	1	
	Р	Р	Р	Р			Р	Р	Р	Р	Р	Р	10 Page faults
						(b)							

- FIFO with 3 page frames
- FIFO with 4 page frames
- Ps show which page references show page faults

### Page Fault Handling



#### Hardware traps to kernel

- General registers saved
- 3. OS determines which virtual page needed
- 4. OS checks validity of address, seeks page frame
- 5. If selected frame is dirty, write it to disk
- 6. OS brings schedules new page in from disk
- Page tables updated
- Faulting instruction backed up to when it began
- Faulting process scheduled
- 7. Registers restored
- Program continues

### Cleaning Policy

- Need for a background process, paging daemon
  - periodically inspects state of memory
- When too few frames are free
  - selects pages to evict using a replacement algorithm
- It can use same circular list (clock)
  - as regular page replacement algorithm, but with different pointer

### Implementation Issues

Operating System Involvement with Paging



#### Four times when OS involved with paging:

- Process creation
  - determine program size
  - create page table
- 2. Process execution
  - MMU reset for new process
  - TLB flushed
- 3. Page fault time
  - determine virtual address causing fault
  - swap target page out, needed page in
- Process termination time
  - release page table, pages

# Swapping

- Separate to paging
- Entire context (process) unloaded from memory, stored on disk
- Totally OS controlled
- Reduces page thrashing but huge performance hit for offending process

## Page size

### Small page size:

- Advantages
  - less internal fragmentation
  - better fit for various data structures, code sections
  - less unused program in memory
- Disadvantages
  - programs need many pages, larger page tables

## Page size

- Tradeoff between speed and efficiency:
  - Larger page size = more read per disk access
  - Smaller page size means less wastage
- Depends on use:
  - Scattered memory addresses: smaller page size is better
  - Contiguous memory addresses: larger page

### OS designer issues


- Page replacement
- Memory division
  - sharing
  - caching
- Page/Swap file management
- Controlling thrashing (careful memory access)
- TLB replacement (e.g. MIPS R2000)

## Summary

- Paging allows memory to do more:
  - Exceed physical memory size
  - Run multiple processes efficiently
- Complex set of caches etc to keep speed up
- Hardware and OS both heavily involved
- Like caching, OS can be optimised to minimise page faulting

### **Example Exam Question**

The 32-bit SPARC architecture uses a 3-level page table as illustrated below.



- (a) List *one* advantage and *one* disadvantage of using this type of page table.
- (b) Calculate **how many bytes are required for the page table** of a process on a SPARC system with a **5MByte** text segment, a **20MByte** data segment, and a **16MByte** stack. Assume that the text segment starts at 0x0, that the data segment follows the text segment, and that the stack grows down from 0XFFFFFFFF. Level 1 nodes are **1024 bytes** each, level 2 and 3 nodes are **256 bytes** each. *Show your working.*



## Solution: (a)

#### **Advantages:**


- Takes up less space than a 2 or 1 level page table
- Not all of the address space needs to be in memory at once, only the pages that are required.

#### **Disadvantages:**

- Slower to look up than a 2 or 1 page table.
- Can become large and complex. (A better option may be to invert the page table so there is one entry for each physical frame.)

### Solution: (b)

How much memory can a L1, L2, L3 page/node address?



- A level 3 page addresses 64 x 4KB pages
  - = **256KB** (in the red ellipse above)
- A level 2 page addresses 64 x 64 x 4KB pages
  - = **16MB** (in the green ellipse)
- A level 1 page addresses all 32bit virtual memory (4GB)

### Solution: (b)

How many L1, L2, L3 pages/nodes are needed?

**Level 1 pages** 

Need only one level 1 page/node

### **Level 2 pages**

For 5MB text + 20MB data (from 0x0 to 25MB)

Need 25MB/16MB(L2 page) rounded up

= two level 2 pages (which can access **16MB** each)

#### For 16MB stack

Need only one level 2 (16MB) page

Need total of three level 2 pages/nodes

### Solution: (b)

How many L1, L2, L3 pages/nodes are needed?

### Level 3 pages

#### For 5MB text + 20MB data

Need 25MB/256KB(L3 page)

= 100 level 3 pages (which can access 256KB each)

#### For 16MB stack

Need 16MB/256KB(L3 page)

= 64 level 3 pages

#### Need total of 164 level 3 pages/nodes

# Solution: (b) What is the total memory used?

The question stated that "Level 1 nodes are **1024** bytes each, level 2 and 3 nodes are **256** bytes each".


### Page table size (total memory used):

```
1 L1 node + 3 L2 nodes + 164 L3 nodes
```

$$= 1024 + 768 + 41984$$
 bytes

= 43,776 bytes









- Virtualisation: feature of multi-core chips
  - designed to run multiple operating systems simultaneously.
- **Teloportation**: Virtual Machine is temporarily stopped and then resumed on a different computer
- Products: Parallels, VirtualBox, Virtual Iron, Virtual PC, Hyper-V, Vmware KVM, QEMU, Adeos, Mac-on-Linux, Win4BSD, Win4Lin Pro, vBlade