

Ideal case

MesoNH Tutorial Class 12-15 November 2024



REAL CASE



Interests

- theorical study :
 from initial idealised fields
 in 1D,2D,3D configuration
 in cartesian geometry or conformal projection
- tests of validation

How does it work?


The user

- 1. specifies an uniform atmosphere from a profile
- 2. can add a perturbation
- 3. initializes the surface fields : idealised or realistic

Uniform state

Vertical profile defined by :


some layers with constant Brunt-Väisälä frequency, wind and humidity at the interfaces: CIDEAL='CSTN'



or data from a radio-sounding : CIDEAL='RSOU'

Analytical perturbations

on thermodynamic fields



- on potential temperature : white noise for LES simulations
- on non-divergent components of the wind

namelist $&NAM_PERT_PRE$ to modify according to the user's needs : routine set_perturb.f90

Forcing terms

1D chronological serie to impose a large-scale environment :

- constant translation of the domain, geostrophic forcing (u_{frc}, v_{frc})
- vertical transport : w_{frc}
- ▶ horizontal transport : $\frac{\partial \theta}{\partial x}\Big|_{frc}$, $\frac{\partial \theta}{\partial y}\Big|_{frc}$, $\frac{\partial r_v}{\partial x}\Big|_{frc}$, $\frac{\partial r_v}{\partial y}\Big|_{frc}$
- ▶ newtonian force : u_{frc} , v_{frc} , θ_{frc} , r_{vfrc}
- ► tendency : $\frac{\partial \theta}{\partial t}\Big|_{frc}$, $\frac{\partial r_v}{\partial t}\Big|_{frc}$, $\frac{\partial u}{\partial t}\Big|_{frc}$, $\frac{\partial v}{\partial t}\Big|_{frc}$

Surface fields

- Orography (namelist &NAM_CONF_PRE) :
 - idealised : flat (CZS='FLAT'), sinusoidal (CZS='SINE') or bell-shaped (CZS='BELL')
 - real : discretised (CZS='DATA') or read in a MesoNH PGD file
- Physiographic data (land-sea mask, type of cover SST, LAI, lay, sand...)
 - idealised : uniform
 - realistic : MesoNH PGD
- Prognostic fields (ground temperatures TG_SURF, _ROOT _DEEP, water contents WG_SURF, _ROOT _DEEP)
 - idealised : uniform
 - realistic : from a file from an operational model or from a MesoNH file

PREP_IDEAL_CASE

PREP_IDEAL_CASE

- computation of the horizontal grid (cartesian or conformal)
 and vertical one
- interpolation of the atmospheric fields with respect to :
 - hydrostatic balance
 - possible geostrophic balance
 - ightharpoonup correction of u, v, w by the pressure solver

to verify the ground condition and the anelastic constraint


- computation of the profiles of the reference state (anelastic approximation)
- writing in a NetCDF file of all the fields necessary for a simulation (prognostic : u, v, w, θ, r_v diagnostic P, surface fields)

Choice of the horizontal grid

- number of points : $IMAX = 2^p * 3^q * 5^r$, $JMAX = 2^s * 3^t * 5^u$
- meshes : DELTAX, DELTAY (in meters)

1 2 3 4 5 6 8 9 10 12 15 16 18 20 24 25 27 30 32 36 40 45 48 50 54 60 64 72 75 80 81 90 96 100 108 120 125 128 135 144 150 160 162 180 192 200 216 225 240 243 250 256 270 288 300 320 324 360 375 384 400 405 432 450 480 486 500 512 540 576 600 625 640 648 675 720 729 750 768 800 810 864 900 960 972 1000 1024 1080 1125 1152 1200 1215 1250 1280 1296 1350 1440 1458 1500 1536 1600 1620 1728 1800 1875 1920 1944 2000 2025 2048 2160 2187 2250 2304 2400 2430 2500 2560 2592 2700 2880 2916 3000 3072 3125 3200 3240 3375 3456 3600 3645 3750 3840 3888 4000 4050 4096 4320 4374 4500 4608 4800 4860 5000 5120 5184 5400 5625 5760 5832 6000 6075 6144 6250 6400 6480 6561 6750 6912 7200 7290 7500 7680 7776 8000 8100 8192 8640 8748 9000 9216 9375 9600 9720 10000 10125 10240 10368 10800 10935 11250 11520 11664 12000 12150 12288 12500 etc.


- Domain geometry
 - a cartesian geometry (LCARTESIAN=T): Earth sphericity isn't take in account (for small scale phenomena),
 - conformal projection.



Choice of the vertical grid

number of points : KMAX discretisation :

- manual : list of levels ZHAT(1), ZHAT(2),..., ZHAT(NKMAX)
- or analytical (logarithmic with z) : Computation of ZHAT from :



```
\begin{array}{l} \_ \ \Delta Z \ \text{at ground (ZDZGRD)} \\ \_ \ \Delta Z \ \text{at top (ZDZTOP)} \\ \_ \ STRetching \ (0 \leq \Delta Z^{k+1}/\Delta Z^k < 10\%) : \\ ZSTRGRD \ \text{for} \ z \in [0,\ ZZMAX\_STRGRD] \\ ZSTRTOP \ \text{for} \ z > ZZMAX\_STRGRD \end{array}
```

Vertical grid

A program is available on the website (Miscellaneous section)

```
&NAM VER GRID NKMAX=30, number of points in Z
                     YZGRID_TYPE='FUNCTN', FUNCTN or MANUAL
                     ZDZGRD=60., ZDZTOP=700., \Delta Z at ground/at top
                     ZZMAX_STRGRD=2500., Height for streching change
                     ZSTRGRD=9., ZSTRTOP=7. /streching at ground/at top
                Enter nb of levels KMAX and the level ZMAX STRGRD:
               30 2500
                Enter mesh size at groud and at the top:ZGRD, ZTOP
               60 700
                 Enter low- and high- level stretching: SGRD, STOP:
                                         60.0000000
                                                            60.0000000
                altitude
                altitude
                                         125.400002
                                                            65.4000015
                altitude
                                         196.686005
                                                            71.2860031
                                         274.387756
                altitude
                                                            77.7017517
                altitude
                                         359.082672
                                                            84.6949158
                                         451.400146
                altitude
                                                            92.3174744
                altitude
                                         552.026184
                                                           100.626038
                                         661.708557
                altitude
                                 10 :
                                                            109.682373
                altitude
                                         781.262329
                                                            119.553772
                                 12 :
                altitude
                                         911.575928
                                                            130.313599
                                 13 :
                altitude
                                         1053.61780
                                                            142.041870
                altitude
                                 14 :
                                         1208.44348
                                                            154.825684
                                 15 :
                altitude
                                         1377.20349
                                                          168.760010
                                         1561.15186
                altitude
                                 16 :
                                                            183.948364
                altitude
                                 17 :
                                         1761.65552
                                                            200.503662
                altitude
                                 18 :
                                         1980.20447
                                                            218.548950
                altitude
                                 19
                                         2218.42285
                                                             238.218384
```

PRE_IDEA1.nam

```
&NAM_DIMn_PRE NIMAX=30, NJMAX=30 / number of points in i and i
&NAM_CONF_PRE LCARTESIAN=.TRUE., cartesian geometry
                  CEONSYS='LHE', choice of equation system
                  CZS='BELL', choice of orography
                  CIDEAL='CSTN', type of initialisation of the atmosphere
                  LPERTURB=.T. / add perturbation
&NAM_GRIDH_PRE XDELTAX=4 .E3, XDELTAY=4.E3, mesh in X and Y
                 XHMAX=1000., XAX=10.E3, XAY=10.E3 define
                 NIZS=16, NJZS=16/
                                                              the hell
&NAM_VER_GRID NKMAX=24, number of vertical levels
                 ZDZGRD=500., ZDZTOP=500. / \Delta Z at top and at ground
&NAM_PERT_PRE CPERT_KIND='TH', type of perturbation
                  XAMPLITH=1.5, max amplitude for \theta
                  XCENTERZ=1500., height for \Delta\theta_{max}
size of perturbationXRADX=10.E3.XRADY=10.E3.XRADZ=600.
```

```
&NAM_LUNITh CINIFILE='BILAN.1' / name of output file
&NAM_LBCn_PRE CLBCX = 2*"OPEN",
                    CLBCY = 2*"OPEN" / lateral boundary conditions
&NAM_VPROF_PRE CTYPELOC='IJGRID', variables to defined the profile
                   NILOC=10. NJLOC=10. localisation of vertical profile
                   LGEOSBAL=.FALSE. / no geostrophic balance
CSTN
                                date
2000 01 01 0.
                                number of levels
2
                                \theta_{v} at ground
285.
                                P at ground
100000.
                                height at all levels
0. 20000.
                                zonal wind component at all levels
10. 10.
                                meridian wind component at all levels
0. 0.
                                relative humidity at all levels
0. 0.
```

0.01

Brünt-Vaisala frequency at all layers

MODEL

EXSEG1.nam

```
&NAM_LUNITO CINIFILE = "BILAN.1" / initial file
&NAM_DYNn XTSTEP = 40., time step (s)
           CPRESOPT = "CRESI", LITRADJ = T, pressure solver
          LHORELAX_UVWTH = T, LHORELAX_RV = T,
horizontal
          NRIMX = 6, NRIMY = 6, XRIMKMAX = 0.0005,
relaxation
           LVE RELAX = T, vertical relaxation
&NAM_ADVn CUVW_ADV_SCHEME = "WENO_K" , advection scheme for U, V
           NWENO_ORDER=5 , CTEMP_SCHEME='RK53'
           CMET_ADV_SCHEME = "PPM_01", f_{or} \theta_{,r,TKE}
&NAM_PARAMn CCLOUD = "ICE3", CTURB = "TKEL",
               microphysic turbulence
              CDCONV = "KAFR", CSCONV = "NONE",
               deep convection shallow convection
              CRAD = "ECMW" / radiative scheme
```

```
&NAM_PARAM_KAFRn XDTCONV = 300., NICE = 1,
parameters for convection KAFR LDIAGCONV = F /
&NAM_PARAM_RADn XDTRAD = 1800., XDTRAD_CLONLY = 900.,
parameters for radiative scheme LCLEAR_SKY = F /
&NAM_TURBn CTURBDIM = "1DIM", CTURBLEN = "BL89",
turbulence LSUBG_COND = F,
            LTURB FLX = F. LTURB DIAG = F /
parameters
&NAM_LBCn CLBCX = 2*"OPEN", CLBCY = 2*"OPEN" /
&NAM_CONF CCONF = "START", configuration START or RESTA
           CEQNSYS = "LHE", Equation system
           NMODEL = 1, NVERB = 5, number of models / verbosity
           CEXP = "CTRLO", CSEG = "SEGO1",
           LLG = T /
&NAM_DYN XSEGLEN = 10800., segment length (s)
          XASSELIN = 0.2, LCORIO = T,
          XALKTOP = 0.001, XALZBOT = 14000. /
           parameters for vertical relaxation
```

```
&NAM_BACKUP XBAK_TIME(1,1) = 3600, output files
            XBAK\ TIME(1,2) = 7200,\ XBAK\_TIME(1,3) = 10800/
&NAM_BUDGET CBUTYPE='CART', XBULEN=600., XBUWRI=1800.
 narameters NBUIL=50, NBUIH=60, NBUJL=50,
           NBUJH=65, NBUKL=2, NBUKH=10,
 for
            LBU_KCP=F, LBU_ICP=T, LBU_JCP=T /
 BUDGET
&NAM_BU_RTH_LBU_RTH=T, CBULIST_RTH(1)="ALL" budget for 0
&NAM_CONFIO LCDF4=T LLFIOUT=T LLFIREAD=F /10 netcdf/FM
&NAM_LES / LES diagnostics
&NAM SERIES / temporal series
&NAM_BLANKn /
```

Name of output file

Output files from the run are named :

CEXP.NMODEL.CSEG.OOn

CEXP et CSEG must have EXACTLY 5 characters

Example:

CTRL0.1.SEG01.001 CTRL0.1.SEG01.002 CTRL0.1.SEG01.003

CTRLO.1.SEG01.000

synchronous files

all the variables at a given time

time-series files

temporal series, budget....



Simulations with SURFEX

PRE IDEA1.nam: