TL; DR

TODO:

## 0.1 Structure

- EffectableComponents are ActorComponents that allow for delegation (effects). They have predefined places called "Outlets" that allow for code modification. Think of Outlets like electrical outlets waiting to be plugged into.
  - Let's use StatsComponent as an example. Say we want a Pokémon-style "Adamant" nature (+10% PhA/-10%SpA). One such place for modification is in the function RecalculateStats. TODO: Update picture!

```
pvoid UStatsComponent::RecalculateStats(const bool bResetCurrent)
{
    for(FStat* Stat : StatsArray)
    {
        ExecuteBeforeRecalculateStats(Stat, bResetCurrent);
        Stat->Update(GetLevel(), bResetCurrent);
        ExecuteAfterRecalculateStats(Stat, bResetCurrent);
    }
}
```

- Outlet arrays are variables inside of EffectableComponents. They hold Outlets whose delegates execute when needed.
  - TODO: Update this! Let's use StatsComponent's AfterRecalculateStatsArray in our example. In this case, after stats are recalculated (say, on level-up), the base PhA would increase by 10% and the base SpA would decrease by 10% (additively):

```
UStatsComponent::FRecalculateStatsDelegate AdamantRecalculateDelegate;
AdamantRecalculateDelegate.BindLambda(InFunctor [StatsComponent](FStat* Stat, bool bResetCurrent) > Void
{
    // +10% PhA
    if ( Stat->Name() == StatsComponent->PhysicalAttack.Name())
    {
        Stat->ModifyValue( Modifier 10, EStatValueType::Permanent, EModificationMode::AddPercentage);
        if (bResetCurrent)
            Stat->ModifyValue( Modifier 10, EStatValueType::Current, EModificationMode::AddPercentage);
    }

// -10% SpA
    if ( Stat->Name() == StatsComponent->SpecialAttack.Name())
    {
        Stat->ModifyValue( Modifier -10, EStatValueType::Permanent, EModificationMode::AddPercentage);
        if (bResetCurrent)
        Stat->ModifyValue( Modifier -10, EStatValueType::Current, EModificationMode::AddPercentage);
    }
});
StatsComponent->AfterRecalculateStatsArray.Add(AdamantRecalculateDelegate);
```

• EffectComponents are ActorComponents that plug into Outlets. These come in many forms, but an easy example is a Buff. TODO: Describe how this happens with pictures!

## 0.2 List of EffectableComponents and Outlets

The following tables show all implemented EffectableComponents and their delegate arrays. Note the "base name" indicates existence of:

- 1. the delegate signature FBaseNameSignature;
- 2. the private before/after arrays of Outlets: TArray<FBaseNameOutlet> BeforeBaseName; and
- 3. a function for each before/after to execute the arrays: ExecuteBeforeBaseName (...).
- 4. AddBeforeBaseName, a function to add an Outlet to the private array BeforeBaseName (which also puts it in the right order based on priority).

Note that the philosophy applies to what is *probable* rather than what is *possible*. Hence the list meant to be practical rather than exhaustive.

## Table 1:

Outlets for

UAffinitiesComponent

TODO: Todo

• • •

Table 2: Outlets for ULevelComponent

## GetBaseExpYield

► Before const float OriginalYield,

float& ReturnedYield

► After const float OriginalYield,

const float ReturnedYield

#### GetCXP

► Before const uint32 OriginalCXP,

int32& ReturnedCXP

Note: ReturnedCXP is int32% instead of uint32% for Blueprint

compatability.

► After const uint32 OriginalCXP

const int32 ReturnedCXP

*Note:* ReturnedCXP is const int32 instead of const uint32 for

Blueprint compatability.

## **GetExpYield**

► Before const float OriginalYield,

float& ReturnedYield,

const uint16 DefeatedLevel,
const uint16 VictoriousLevel

Note: "Defeated" and "Victorious" levels are provided for flexibility

(e.g., in case you want to yield exp differently based on level difference, although technically you could always back-calculate the level difference based on the equation and OriginalYield).

Continued on next page

Table 2: Outlets for ULevelComponent (Continued)

► After const float OriginalYied,

const float ReturnedYield,
const uint16 DefeatedLevel,
const uint16 VictoriousLevel

Note: "Defeated" and "Victorious" levels are provided for symmetry

with respect to the Before delegate (since ReturnedValue is already calculated, I can't think of why you would need them,

but you never know!).

#### **GetMaxLevel**

► Before const uint16 DefaultMax,

int32& AttemptedMax

Note: DefaultMax is defined in the code. It should normally be 100, but

may change for certain subclasses (e.g., a UBossLevelComponent may have a max of 200 instead). Also, AttemptedMax is int32&

instead of uint16% for Blueprint compatability.

► After const uint16 DefaultMax

const int32 ReturnedMax

## **GetMinLevel**

▶ Before const uint16 DefaultMin,

int32% AttemptedMin

Note: DefaultMin is defined in the code. It should normally be 1, but

may change for certain subclasses (e.g., a UEggLevelComponent

may have a min of 0 instead for whatever reason). Also, AttemptedMin is int32& instead of uint16& for Blueprint

compatability.

► After const uint16 DefaultMin

const int32 ReturnedMin

#### SetBaseExpYield

▶ Before const float OldYield.

float& AttemptedYield

► After const float OldYield

const float NewYield

Continued on next page

Table 2: Outlets for ULevelComponent (Continued)

#### **SetCXP**

▶ Before const uint32 OldCXP,

int32& AttemptedCXP

Note: AttemptedCXP is int32& instead of uint32& for Blueprint

compatability.

► After const uint32 OldCXP

const uint32 NewCXP

Note: UStatsComponent subscribes to this in order to change stats on

level change.

\_\_\_\_\_\_

Table 3: Outlets for UStatsComponent

## RandomizeStats

► Before const EStatEnum TargetStat,

const FStatRandParams OriginalParams,

FStatRandParams& ParamsToBeUsed

► After const EStatEnum TargetStat,

const FStatRandParams OriginalParams,

const FStatRandParams UsedParams

Note: The EStatEnum is not the acutal FStat. To get the FStat (such

as FHealth), use UStatsComponent::GetStat(EStatEnum).

#### RecalculateStats

▶ Before const EStatEnum TargetStat,

 $\verb|const| bool bResetCurrent|,$ 

const float OriginalCurrent,
const float OriginalPermanent

► After const EStatEnum TargetStat,

const bool bResetCurrent,


const float OriginalCurrent,

const float OriginalPermanent

# 0.3 Making Your Own Outlet

As an example, let's use GetBaseExpYield. (You can imagine that this is an important Outlet for tweaking levelling curves.) Here's what to do:

- 1. Plan ahead. I would sincerely recommend you writing down what parameters your Outlet Before and After delegates take on paper. We go to a few files and it's easy to be inconsistent.
- 2. Go to the right directory. We want to place the Outlet inside of ULevelComponent, so we'll start with that directory. If yours doesn't contain an "Outlets" directory, create one and place your Outlet(s) there.
- 3. Copy + paste file. The easiest way is to copy + paste pre-existing Outlets. In this example, we'll copy + paste SetCXPOutlet.h and name the new file GetBaseExpYield.h.



Note: this includes both BeforeGetBaseExpYield and AfterGetBaseExpYield functionality. You don't have to make two different files!

- 4. **Replace old name.** Open the new file and you'll still see the base name "SetCXP" everywhere. The easiest way is to do a find+replace "SetCXP" → "GetBaseExpYield". This replaces everything from the .generated include to the delegate signatures. If you're curious, you can look more in-depth and replace instances one-by-one.
- 5. **Declare delegate signatures.** In this case, we want the Before delegate signature to take two arguments: the original, unmodified yield and the one that will be returned from the GetBaseExpYield function.

You should also set the After signature in the same manner. Note: yours might use more than two parameters or different parameter types. Modify accordingly.

6. **Declare** Outlet **functions.** In order to be able to call ExecuteBefore on your Outlet, you need to tell it a few things. The figure below displays a few things in red you should look at:

```
DECLARE_OUTLET_FUNCTIONS_TwoParams (Before, FBeforeGetBaseExpYieldDelegate, BeforeDelegates, Delegate, const float, float&);
```

• Whether it's a Before or After type Outlet. This affects execution based on priority:

### **Priorities**

The lower the priority, the farther away it is from execution. If two priorities are tied, the older effect is executed first. Order is set externally by UEffectsComponent TODO: fact check this. Order:

- Intrinsic Before delegates (no UEffect affiliated)
- Before delegates:
  - \* Priority 1
  - \* Priority 2.a (older)
  - \* Priority 2.b (newer)
  - \* ...
- [Function executes]
- After delegates:
  - \* ...
  - \* Priority 2.b (newer)
  - \* Priority 2.a (older)
  - \* Priority 1
- Intrinsic After delegates (have the final say)

As an example, consider two delegates: one that says you can't take damage no matter what (call the UBuff "Invincible") and another that says damage against you can't be avoided no matter what (call the UDebuff "Weakened"). What happens when the target takes damage? Well, it depends on priority:

- They're probably subscribed to the Before delegate in UStatsComponent called ModifyStatOutlet with the target FStat being Health.
- Note that they're both Before delegates.
- Let's say Invincible has Priority 100 and Weakened has Priority 150.
   The result is the target takes damage because:
  - 1) Invincible first sets the damage to zero.
  - 2) Weakened then sets the damage to no less than its original value.
- If Weakened has lower Priority, the result is flipped and the target takes no damage.

- The parameters you defined in the delegate's signature. I know, I know—anytime you repeat code, you're probably doing something wrong. The biggest issue here is the UHT. The main (but not only) issue is that you can't have UPROPERTYs inside macros or the property won't register. If you have a better way of automating this, tell me!
- Don't forget the After variant's delegates, which should probably be const.
- 7. Check number of parameters. I make a point of this because I find it's my most common error. Make sure your declared signature and declared Outlet function macros have the correct number of params (two in our case). Explicitly, you might need to use DECLARE\_DYNAMIC\_DELEGATE\_FourParams(...).
- 8. **Declare** UPROPERTY. Inside the UEffectableComponent (in this example, ULevelComponent), declare the Outlet as a variable. Note that it's custom to have this UPROPERTY as public and in the "Outlets" category. It's also a good idea to comment the UPROPERTY with the parameters.

Note: I use Rider, so it imports #includes automatically. Make sure yours does, too.

9. **Implement.** Now it's time to place your Outlet in the appropriate place(s). For our example, it's pretty simple: place it inside of GetBaseExpYield in ULevelComponent's .cpp file.

Note that you might have to do things like cache original values.

10. A note on complementary delegates. If you create a Before Outlet, you should also create an After Outlet. The biggest difference might be the delegate signature (e.g., reference "&" to const).

An example where this would be necessary is an animation delegate. You only want to fire a "bonus exp" animation *after* the amount of exp has been determined, checked, and is now constant.

In some cases, it may not be necessary to have both Before and After delegates in a function. If you want only one delegate type, or three, or ten, the system is flexible enough to handle it. However, it's recommended to K.I.S.S.

# 0.4 Making Your Own Effects

Suppose you want to make your own effect from scratch. TODO: todo