
# Chapter 3: Processes



#### **Outline**

- Process Concept
- Process Scheduling
- Operations on Processes
- Interprocess Communication
- IPC in Shared-Memory Systems
- IPC in Message-Passing Systems
- Examples of IPC Systems
- Communication in Client-Server Systems

# **Objectives**

- Identify the separate components of a process and illustrate how they are represented and scheduled in an operating system.
- Describe how processes are created and terminated in an operating system, including developing programs using the appropriate system calls that perform these operations.
- Describe and contrast interprocess communication using shared memory and message passing.
- Design programs that uses pipes and POSIX shared memory to perform interprocess communication.
- Describe client-server communication using sockets and remote procedure calls.
- Design kernel modules that interact with the Linux operating system.


### **Process Concept**

- An operating system executes a variety of programs that run as a process.
- Process a program in execution; process execution must progress in sequential fashion. No parallel execution of instructions of a single process
- Multiple parts
  - O The program code, also called **text section**
  - Current activity including program counter, processor registers
  - Stack containing temporary data
    - Function parameters, return addresses, local variables
  - Data section containing global variables
  - Heap containing memory dynamically allocated during run time


# Process Concept (Cont.)

- Program is passive entity stored on disk (executable file);
   process is active
  - Program becomes process when an executable file is loaded into memory
- Execution of program started via GUI mouse clicks, command line entry of its name, etc.
- One program can be several processes
  - Consider multiple users executing the same program

# **Process in Memory**




# Memory Layout of a C Program



#### **Process State**

- As a process executes, it changes state
  - New: The process is being created
  - Running: Instructions are being executed
  - Waiting: The process is waiting for some event to occur.
  - Ready: The process is waiting to be assigned to a processor
  - Terminated: The process has finished execution

# Diagram of Process State



### Process Control Block (PCB)

Information associated with each process(also called **task control block**)

- Process state running, waiting, etc.
- Program counter location of instruction to next execute
- CPU registers contents of all process-centric registers
- CPU scheduling information- priorities, scheduling queue pointers
- Memory-management information memory allocated to the process
- Accounting information CPU used, clock time elapsed since start, time limits
- I/O status information I/O devices allocated to process, list of open files


process state
process number
program counter
registers
memory limits
list of open files

#### **Threads**

- So far, process has a single thread of execution
- Consider having multiple program counters per process
  - Multiple locations can execute at once
    - Multiple threads of control -> threads
- Must then have storage for thread details, multiple program counters in PCB
- Explore in detail in Chapter 4

### Process Representation in Linux


Represented by the C structure task\_struct




### **Process Scheduling**

- Process scheduler selects among available processes for next execution on CPU core
- Goal -- Maximize CPU use, quickly switch processes onto CPU core
- Maintains scheduling queues of processes
  - Ready queue set of all processes residing in main memory, ready and waiting to execute
  - **Wait queues** set of processes waiting for an event (i.e., I/O)
  - Processes migrate among the various queues

# Ready and Wait Queues




# Representation of Process Scheduling



#### CPU Switch From Process to Process

A **context switch** occurs when the CPU switches from one process to another.



#### **Context Switch**

- When CPU switches to another process, the system must save the state of the old process and load the saved state for the new process via a context switch
- Context of a process represented in the PCB
- Context-switch time is pure overhead; the system does no useful work while switching
  - The more complex the OS and the PCB □ the longer the context switch
- Time dependent on hardware support
  - Some hardware provides multiple sets of registers per CPU 

    multiple contexts loaded at once

# Multitasking in Mobile Systems

- Some mobile systems (e.g., early version of iOS) allow only one process to run, others suspended
- Due to screen real estate, user interface limits iOS provides for a
  - O Single **foreground** process- controlled via user interface
  - Multiple background processes— in memory, running, but not on the display, and with limits
  - Limits include single, short task, receiving notification of events, specific long-running tasks like audio playback
- Android runs foreground and background, with fewer limits
  - O Background process uses a **service** to perform tasks
  - O Service can keep running even if background process is suspended
  - O Service has no user interface, small memory use

# Operations on Processes


- System must provide mechanisms for:
  - Process creation
  - Process termination

#### **Process Creation**

- Parent process create children processes, which, in turn create other processes, forming a tree of processes
- Generally, process identified and managed via a process identifier (pid)
- Resource sharing options
  - Parent and children share all resources.
  - Children share subset of parent's resources
  - Parent and child share no resources
- Execution options
  - Parent and children execute concurrently
  - Parent waits until children terminate


# Process Creation (Cont.)

- Address space
  - Child duplicate of parent
  - Child has a program loaded into it



- UNIX examples
  - fork() system call creates new process
  - exec() system call used after a fork() to replace the process' memory space with a new program
  - Parent process calls wait () waiting for the child to terminate

### A Tree of Processes in Linux



# C Program Forking Separate Process

```
#include <sys/types.h>
#include <stdio.h>
#include <unistd.h>
int main()
pid t pid;
   /* fork a child process */
   pid = fork();
   if (pid < 0) { /* error occurred */
      fprintf(stderr, "Fork Failed");
      return 1;
   else if (pid == 0) { /* child process */
      execlp("/bin/ls", "ls", NULL);
   else { /* parent process */
      /* parent will wait for the child to complete */
      wait(NULL);
      printf("Child Complete");
   return 0;
```

### Creating a Separate Process via Windows API

```
#include <stdio.h>
#include <windows.h>
int main(VOID)
STARTUPINFO si:
PROCESS_INFORMATION pi;
   /* allocate memory */
   ZeroMemory(&si, sizeof(si));
   si.cb = sizeof(si);
   ZeroMemory(&pi, sizeof(pi));
   /* create child process */
   if (!CreateProcess(NULL, /* use command line */
     "C:\\WINDOWS\\system32\\mspaint.exe", /* command */
    NULL, /* don't inherit process handle */
    NULL, /* don't inherit thread handle */
    FALSE, /* disable handle inheritance */
    0, /* no creation flags */
    NULL, /* use parent's environment block */
    NULL, /* use parent's existing directory */
     &si,
     &pi))
      fprintf(stderr, "Create Process Failed");
      return -1;
   /* parent will wait for the child to complete */
   WaitForSingleObject(pi.hProcess, INFINITE);
   printf("Child Complete");
   /* close handles */
   CloseHandle(pi.hProcess);
   CloseHandle(pi.hThread);
```

#### **Process Termination**

- Process executes last statement and then asks the operating system to delete it using the exit() system call.
  - Returns status data from child to parent (via wait())
  - Process' resources are deallocated by operating system
- Parent may terminate the execution of children processes using the abort () system call. Some reasons for doing so:
  - Child has exceeded allocated resources
  - Task assigned to child is no longer required
  - The parent is exiting, and the operating systems does not allow a child to continue if its parent terminates

#### **Process Termination**

- Some operating systems do not allow child to exists if its parent has terminated.
   If a process terminates, then all its children must also be terminated.
  - o cascading termination. All children, grandchildren, etc., are terminated.
  - The termination is initiated by the operating system.
- The parent process may wait for termination of a child process by using the wait() system call. The call returns status information and the pid of the terminated process

```
pid = wait(&status);
```

- If no parent waiting (did not invoke wait()) process is a zombie
- If parent terminated without invoking wait(), process is an orphan

# Android Process Importance Hierarchy

- Mobile operating systems often have to terminate processes to reclaim system resources such as memory. From most to least important:
  - Foreground process
  - Visible process
  - Service process
  - Background process
  - Empty process
- Android will begin terminating processes that are least important.

### Multiprocess Architecture – Chrome Browser

- Many web browsers ran as single process (some still do)
  - O If one web site causes trouble, entire browser can hang or crash
- Google Chrome Browser is multiprocess with 3 different types of processes:
  - Browser process manages user interface, disk and network I/O
  - Renderer process renders web pages, deals with HTML, Javascript. A new renderer created for each website opened
    - Runs in **sandbox** restricting disk and network I/O, minimizing effect of security exploits
  - O Plug-in process for each type of plug-in




### Interprocess Communication

- Processes within a system may be independent or cooperating
- Cooperating process can affect or be affected by other processes, including sharing data
- Reasons for cooperating processes:
  - Information sharing
  - Computation speedup
  - Modularity
  - Convenience
- Cooperating processes need interprocess communication (IPC)
- Two models of IPC
  - Shared memory
  - Message passing

#### **Communications Models**

(a) Shared memory. (b) Message passing.



#### Producer-Consumer Problem

- Paradigm for cooperating processes:
  - producer process produces information that is consumed by a consumer process
- Two variations:
  - unbounded-buffer places no practical limit on the size of the buffer:
    - Producer never waits
    - Consumer waits if there is no buffer to consume
  - bounded-buffer assumes that there is a fixed buffer size
    - Producer must wait if all buffers are full
    - Consumer waits if there is no buffer to consume

#### IPC – Shared Memory

- An area of memory shared among the processes that wish to communicate
- The communication is under the control of the users processes not the operating system.
- Major issues is to provide mechanism that will allow the user processes to synchronize their actions when they access shared memory.
- Synchronization is discussed in great details in Chapters 6 & 7.

# Bounded-Buffer – Shared-Memory Solution

Shared data

```
#define BUFFER_SIZE 10

typedef struct {
    . . .
} item;

item buffer[BUFFER_SIZE];
int in = 0;
int out = 0;
```

Solution is correct, but can only use **BUFFER\_SIZE-1** elements

### Producer Process – Shared Memory

```
item next produced;
while (true) {
   /* produce an item in next produced */
   while (((in + 1) % BUFFER SIZE) == out)
       ; /* do nothing */
   buffer[in] = next produced;
   in = (in + 1) % BUFFER SIZE;
```

# Consumer Process – Shared Memory

```
item next consumed;
while (true) {
   while (in == out)
        ; /* do nothing */
   next consumed = buffer[out];
   out = (out + 1) % BUFFER SIZE;
    /* consume the item in next consumed */
```

# What about Filling all the Buffers?

- Suppose that we wanted to provide a solution to the consumer-producer problem that fills all the buffers.
- We can do so by having an integer counter that keeps track of the number of full buffers.
- Initially, counter is set to 0.
- The integer counter is incremented by the producer after it produces a new buffer.
- The integer **counter** is and is decremented by the consumer after it consumes a buffer.

#### Producer

```
while (true) {
   /* produce an item in next produced */
   while (counter == BUFFER SIZE)
       ; /* do nothing */
   buffer[in] = next produced;
   in = (in + 1) % BUFFER SIZE;
   counter++;
```

#### Consumer

```
while (true) {
   while (counter == 0)
       ; /* do nothing */
   next consumed = buffer[out];
   out = (out + 1) % BUFFER SIZE;
        counter--;
   /* consume the item in next consumed */
```

#### **Race Condition**

counter++ could be implemented as

```
register1 = counter
register1 = register1 + 1
counter = register1
```

• counter-- could be implemented as

```
register2 = counter
register2 = register2 - 1
counter = register2
```

Consider this execution interleaving with "count = 5" initially:

```
S0: producer execute register1 = counter {register1 = 5}
S1: producer execute register1 = register1 + 1 {register1 = 6}
S2: consumer execute register2 = counter {register2 = 5}
S3: consumer execute register2 = register2 - 1 {register2 = 4}
S4: producer execute counter = register1 {counter = 6}
S5: consumer execute counter = register2 {counter = 4}
```

### Race Condition (Cont.)

- Question why was there no race condition in the first solution (where at most N - 1) buffers can be filled?
- More in Chapter 6.

# IPC – Message Passing

- Processes communicate with each other without resorting to shared variables
- IPC facility provides two operations:
  - o send(message)
  - o receive(message)
- The *message* size is either fixed or variable

# Message Passing (Cont.)

- If processes *P* and *Q* wish to communicate, they need to:
  - Establish a *communication link* between them
  - O Exchange messages via send/receive
- Implementation issues:
  - O How are links established?
  - Can a link be associated with more than two processes?
  - O How many links can there be between every pair of communicating processes?
  - O What is the capacity of a link?
  - O Is the size of a message that the link can accommodate fixed or variable?
  - O Is a link unidirectional or bi-directional?

# Implementation of Communication Link

#### Physical:

- Shared memory
- Hardware bus
- Network

#### Logical:

- Direct or indirect
- Synchronous or asynchronous
- Automatic or explicit buffering

#### **Direct Communication**

- Processes must name each other explicitly:
  - send (*P, message*) send a message to process P
  - O receive(Q, message) receive a message from process Q
- Properties of communication link
  - Links are established automatically
  - A link is associated with exactly one pair of communicating processes
  - O Between each pair there exists exactly one link
  - The link may be unidirectional, but is usually bi-directional

#### **Indirect Communication**

- Messages are directed and received from mailboxes (also referred to as ports)
  - Each mailbox has a unique id
  - O Processes can communicate only if they share a mailbox
- Properties of communication link
  - Link established only if processes share a common mailbox
  - A link may be associated with many processes
  - Each pair of processes may share several communication links
  - Link may be unidirectional or bi-directional

# Indirect Communication (Cont.)

#### Operations

- Create a new mailbox (port)
- Send and receive messages through mailbox
- Delete a mailbox

#### Primitives are defined as:

- $\circ$  send(A, message) send a message to mailbox A
- O receive(A, message) receive a message from mailbox A

# Indirect Communication (Cont.)

#### Mailbox sharing

- $P_1$ ,  $P_2$ , and  $P_3$  share mailbox A
- $OP_1$ , sends;  $P_2$  and  $P_3$  receive
- O Who gets the message?

#### Solutions

- Allow a link to be associated with at most two processes
- Allow only one process at a time to execute a receive operation
- Allow the system to select arbitrarily the receiver. Sender is notified who the receiver was.

# Synchronization

#### Message passing may be either blocking or non-blocking

- Blocking is considered synchronous
  - O Blocking send -- the sender is blocked until the message is received
  - O Blocking receive -- the receiver is blocked until a message is available
- Non-blocking is considered asynchronous
  - Non-blocking send -- the sender sends the message and continue
  - O Non-blocking receive -- the receiver receives:
    - A valid message, or
    - Null message
- Different combinations possible
  - If both send and receive are blocking, we have a rendezvous

# Producer-Consumer: Message Passing

 Producer message next produced; while (true) { /\* produce an item in next produced \*/ send(next produced); Consumer message next consumed; while (true) { receive (next consumed) /\* consume the item in next consumed \*/

### Buffering

- Queue of messages attached to the link.
- Implemented in one of three ways
  - Zero capacity no messages are queued on a link.
     Sender must wait for receiver (rendezvous)
  - Bounded capacity finite length of n messages
     Sender must wait if link full
  - Unbounded capacity infinite length Sender never waits

# Examples of IPC Systems - POSIX

#### POSIX Shared Memory

- Process first creates shared memory segment
  shm\_fd = shm\_open(name, O CREAT | O RDWR, 0666);
- Also used to open an existing segment
- Set the size of the object

```
ftruncate(shm fd, 4096);
```

- O Use mmap () to memory-map a file pointer to the shared memory object
- Reading and writing to shared memory is done by using the pointer returned by mmap ().

#### IPC POSIX Producer

```
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <fcntl.h>
#include <sys/shm.h>
#include <sys/stat.h>
int main()
/* the size (in bytes) of shared memory object */
const int SIZE = 4096;
/* name of the shared memory object */
const char *name = "OS";
/* strings written to shared memory */
const char *message_0 = "Hello";
const char *message_1 = "World!";
/* shared memory file descriptor */
int shm fd;
/* pointer to shared memory obect */
void *ptr;
   /* create the shared memory object */
   shm fd = shm_open(name, O_CREAT | O_RDWR, 0666);
   /* configure the size of the shared memory object */
   ftruncate(shm_fd, SIZE);
   /* memory map the shared memory object */
   ptr = mmap(0, SIZE, PROT_WRITE, MAP_SHARED, shm_fd, 0);
   /* write to the shared memory object */
   sprintf(ptr, "%s", message_0);
   ptr += strlen(message_0);
   sprintf(ptr, "%s", message_1);
   ptr += strlen(message_1);
   return 0:
```

#### IPC POSIX Consumer

```
#include <stdio.h>
#include <stdlib.h>
#include <fcntl.h>
#include <sys/shm.h>
#include <sys/stat.h>
int main()
/* the size (in bytes) of shared memory object */
const int SIZE = 4096;
/* name of the shared memory object */
const char *name = "OS";
/* shared memory file descriptor */
int shm fd;
/* pointer to shared memory obect */
void *ptr;
   /* open the shared memory object */
   shm fd = shm_open(name, O_RDONLY, 0666);
   /* memory map the shared memory object */
   ptr = mmap(0, SIZE, PROT_READ, MAP_SHARED, shm_fd, 0);
   /* read from the shared memory object */
   printf("%s",(char *)ptr);
   /* remove the shared memory object */
   shm_unlink(name);
   return 0;
```

# Examples of IPC Systems - Mach

- Mach communication is message based
  - O Even system calls are messages
  - Each task gets two ports at creation Kernel and Notify
  - O Messages are sent and received using the mach\_msg() function
  - Ports needed for communication, created via

```
mach_port_allocate()
```

- Send and receive are flexible; for example four options if mailbox full:
  - Wait indefinitely
  - Wait at most n milliseconds
  - Return immediately
  - Temporarily cache a message

### Mach Messages

```
#include<mach/mach.h>

struct message {
    mach_msg_header_t header;
    int data;
};

mach port t client;
mach port t server;
```

# Mach Message Passing - Client

```
/* Client Code */
struct message message;
// construct the header
message.header.msgh_size = sizeof(message);
message.header.msgh_remote_port = server;
message.header.msgh_local_port = client;
// send the message
mach_msg(&message.header, // message header
  MACH_SEND_MSG, // sending a message
  sizeof(message), // size of message sent
  0, // maximum size of received message - unnecessary
  MACH_PORT_NULL, // name of receive port - unnecessary
  MACH_MSG_TIMEOUT_NONE, // no time outs
  MACH_PORT_NULL // no notify port
```

# Mach Message Passing - Server


```
/* Server Code */
struct message message;

// receive the message
mach_msg(&message.header, // message header
    MACH_RCV_MSG, // sending a message
    0, // size of message sent
    sizeof(message), // maximum size of received message
    server, // name of receive port
    MACH_MSG_TIMEOUT_NONE, // no time outs
    MACH_PORT_NULL // no notify port
);
```

# Examples of IPC Systems – Windows

- Message-passing centric via advanced local procedure call (LPC) facility
  - Only works between processes on the same system
  - Uses ports (like mailboxes) to establish and maintain communication channels
  - Communication works as follows:
    - The client opens a handle to the subsystem's connection port object.
    - The client sends a connection request.
    - The server creates two private **communication ports** and returns the handle to one of them to the client.
    - The client and server use the corresponding port handle to send messages or callbacks and to listen for replies.

#### Local Procedure Calls in Windows




# **Pipes**

- Acts as a conduit allowing two processes to communicate
- Issues:
  - O Is communication unidirectional or bidirectional?
  - On the case of two-way communication, is it half or full-duplex?
  - Must there exist a relationship (i.e., *parent-child*) between the communicating processes?
  - Can the pipes be used over a network?
- Ordinary pipes cannot be accessed from outside the process that created it. Typically, a parent process creates a pipe and uses it to communicate with a child process that it created.
- Named pipes can be accessed without a parent-child relationship.

### **Ordinary Pipes**

- Ordinary Pipes allow communication in standard producer-consumer style
- Producer writes to one end (the write-end of the pipe)
- Consumer reads from the other end (the read-end of the pipe)
- Ordinary pipes are therefore unidirectional
- Require parent-child relationship between communicating processes



### Named Pipes

- Named Pipes are more powerful than ordinary pipes
- Communication is bidirectional
- No parent-child relationship is necessary between the communicating processes
- Several processes can use the named pipe for communication
- Provided on both UNIX and Windows systems


# Communications in Client-Server Systems

- Sockets
- Remote Procedure Calls

#### Sockets

- A socket is defined as an endpoint for communication
- Concatenation of IP address and port a number included at start of message packet to differentiate network services on a host
- The socket 161.25.19.8:1625 refers to port 1625 on host 161.25.19.8
- Communication consists between a pair of sockets
- All ports below 1024 are *well known*, used for standard services
- Special IP address 127.0.0.1 (loopback) to refer to system on which process is running

### **Socket Communication**



#### Sockets in Java

- Three types of sockets
  - Connection-oriented (TCP)
  - Connectionless (UDP)
  - MulticastSocket class data can be sent to multiple recipients
- Consider this "Date" server in Java:

```
import java.net.*;
import java.io.*;
public class DateServer
  public static void main(String[] args) {
     try {
       ServerSocket sock = new ServerSocket(6013);
       /* now listen for connections */
       while (true) {
          Socket client = sock.accept();
          PrintWriter pout = new
           PrintWriter(client.getOutputStream(), true);
          /* write the Date to the socket */
          pout.println(new java.util.Date().toString());
          /* close the socket and resume */
          /* listening for connections */
          client.close();
     catch (IOException ioe)
       System.err.println(ioe);
```

#### Sockets in Java

#### The equivalent Date client

```
import java.net.*;
import java.io.*;
public class DateClient
  public static void main(String[] args) {
    try {
       /* make connection to server socket */
       Socket sock = new Socket("127.0.0.1",6013);
       InputStream in = sock.getInputStream();
       BufferedReader bin = new
          BufferedReader(new InputStreamReader(in));
       /* read the date from the socket */
       String line;
       while ( (line = bin.readLine()) != null)
          System.out.println(line);
       /* close the socket connection*/
       sock.close();
     catch (IOException ioe)
       System.err.println(ioe);
```


#### Remote Procedure Calls

- Remote procedure call (RPC) abstracts procedure calls between processes on networked systems
  - O Again uses ports for service differentiation
- Stubs client-side proxy for the actual procedure on the server
- The client-side stub locates the server and **marshalls** the parameters
- The server-side stub receives this message, unpacks the marshalled parameters, and performs the procedure on the server
- On Windows, stub code compile from specification written in Microsoft Interface Definition Language (MIDL)


### Remote Procedure Calls (Cont.)

- Data representation handled via External Data Representation
   (XDL) format to account for different architectures
  - O Big-endian and little-endian
- Remote communication has more failure scenarios than local
  - Messages can be delivered exactly once rather than at most once
- OS typically provides a rendezvous (or matchmaker) service to connect client and server

#### **Execution of RPC**



# End of Chapter 3



#### Producer-Consumer Problem

- Paradigm for cooperating processes:
  - producer process produces information that is consumed by a consumer process
- Two variations:
  - unbounded-buffer places no practical limit on the size of the buffer:
    - Producer never waits
    - Consumer waits if there is no buffer to consume
  - bounded-buffer assumes that there is a fixed buffer size
    - Producer must wait if all buffers are full
    - Consumer waits if there is no buffer to consume

### Cooperating Processes

- Independent process cannot affect or be affected by the execution of another process
- Cooperating process can affect or be affected by the execution of another process
- Advantages of process cooperation
  - Information sharing
  - Computation speed-up
  - Modularity
  - Convenience

# Synchronization

- Message passing may be either blocking or non-blocking
  - O Blocking is considered synchronous
    - Blocking send -- the sender is blocked until the message is received
    - Blocking receive -- the receiver is blocked until a message is available
  - Non-blocking is considered asynchronous
    - Non-blocking send -- the sender sends the message and continue
    - Non-blocking receive -- the receiver receives:
    - A valid message, or
    - Null message
  - Different combinations possible
    - If both send and receive are blocking, we have a rendezvous