Ibis GMI User's Guide

http://www.cs.vu.nl/ibis

November 16, 2009

1 Introduction

TODO

Since Ibis GMI is built on top of the Ibis Portability Layer (IPL), the Ibis GMI release contains the Ibis communication library, which contains implementations of the IPL. Parts of this manual may look familiar for readers that are familiar with the Ibis communication library.

2 Compiling the examples

The example applications for GMI are provided with the Ibis GMI distribution, in the examples directory. For convenience, the examples are already compiled.

If you change the examples, you will need to recompile them. This requires the build system ant ¹. Running ant in the examples directory compiles the examples, and rewrites the class files for use with Ibis GMI.

If, for some reason, it is not convenient to use *ant* to compile your application, or you have only class files or jar files available for parts of your application, it is also possible to first compile your application to class files or jar files, and then process those using the *gmic* script. This script can be found in the Ibis GMI bin directory. It takes either directories, class files, or jar files as parameter, and processes those, possibly rewriting them. In case of a directory, all class files and jar files in that directory or its subdirectories are processed. The command sequence

creates a lib directory and stores the resulting class files there, in a jar-file called gmi-examples.jar. The GMI_HOME environment variable must be set to the location of the Ibis GMI installation.

¹http://ant.apache.org

3 An Ibis GMI run

Before discussing the running of an Ibis GMI application, we will discuss services that are needed by the Ibis communication library.

3.1 The pool

A central concept in Ibis is the *Pool*. A pool consists of one or more Ibis instances, usually running on different machines. Each pool is generally made up of Ibises running a single distributed application. Ibises in a pool can communicate with each other, and, using the registry mechanism present in Ibis, can search for other Ibises in the same pool, get notified of Ibises joining the pool, etc. To coordinate Ibis pools a so-called *Ibis server* is used.

3.2 The Ibis Server

The Ibis server is the Swiss-army-knife server of the Ibis project. Services can be dynamically added to the server. By default, the Ibis communication library comes with a registry service. This registry service manages pools, possibly multiple pools at the same time.

In addition to the registry service, the server also allows Ibises to route traffic over the server if no direct connection is possible between two instances due to firewalls or NAT boxes. This is done using the Smartsockets library of the Ibis project.

The Ibis server is started with the <code>gmi-server</code> script which is located in the <code>bin</code> directory of the Ibis GMI distribution. Before starting an Ibis GMI application, an Ibis server needs to be running on a machine that is accessible from all nodes participating in the Ibis GMI run. The server listens to a TCP port. The port number can be specified using the <code>--port</code> command line option to the <code>gmi-server</code> script. For a complete list of all options, use the <code>--help</code> option of the script. One useful option is the <code>--events</code> option, which makes the registry print out events.

3.2.1 Hubs

The Ibis server is a single point which needs to be reachable from every Ibis instance. Since sometimes this is not possible due to firewalls, additional *hubs* can be started to route traffic, creating a routing infrastructure for the Ibis GMI instances. These hubs can be started by using gmi-server script with the --hub-only option. In addition, each hub needs to know the location of as many of the other hubs as possible. This information can be provided by using the --hub-addresses option. See the --help option of the gmi-server script for more information.

3.3 Running the example: preliminaries

When the Ibis server is running, the Ibis GMI application itself can be started. There are a number of requirements that need to be met before Ibis (and thus Ibis GMI) can be started correctly. In this section we will discuss these in detail.

Several of the steps below require the usage of *system properties*. System properties can be set in Java using the -D option of the java command. Be sure to use appropriate quoting for your command interpreter.

As an alternative to using system properties, it is also possible to use a java properties file ². A properties file is a file containing one property per line, usually of the format property = value. Properties of Ibis can be set in such a file as if they were set on the command line directly.

Ibis and Ibis GMI will look for a file named ibis.properties in the current working directory, on the class path, and at a location specified with the ibis.properties.file system property.

3.3.1 Add jar files to the classpath

The Ibis GMI implementation is provided in a single jar file: gmi.jar, appended with the version of Ibis GMI, for instance gmi-2.2. jar. Ibis GMI interfaces to Ibis using the Ibis Portability Layer, or *IPL*. Both Ibis GMI and the IPL depend on various other libraries. All jar files in \$GMI_HOME/lib need to be on the classpath.

3.3.2 Configure Log4j

Ibis and Ibis GMI use the Log4J library of the Apache project to print debugging information, warnings, and error messages. This library must be initialized. A configuration file can be specified using the log4j.configuration system property. For example, to use a file named log4j.properties in the current directory, use the following command line option: -Dlog4j.configuration=file:log4j.properties. For more info, see the log4j website ³.

3.3.3 Set the location of the server and hubs

To communicate with the registry service, each Ibis instance needs the address of the Ibis server. This address must be specified by using the ibis.server.address system property. The full address needed is printed on start up of the Ibis server.

For convenience, it is also possible to only provide an address, port number pair, e.g. machine.domain.com:5435 or even simply a host, e.g. localhost. In this case, the default port number (8888) is implied. The port number provided must match the one given to the Ibis server with the --port option.

When additional hubs are started (see Section 3.2.1), their locations must be provided to the Ibis instances. This can be done using the ibis.hub.addresses property. Ibis expects a comma-separated list of addresses of hubs. Ibis will use the first reachable hub on the list. The address of the Ibis server is appended to this list automatically. Thus, by default, the Ibis server itself is used as the hub.

3.3.4 Set the name and size of the pool

Each Ibis instance belongs to a pool. The name of this pool must be provided using the ibis.pool.name property. With the help of the Ibis server, this name is then used to locate other Ibis instances which belong to the same pool. Since the Ibis server can service multiple pools simultaneously, each pool must have a unique name.

It is possible for pools to have a fixed size. In these so-called *closed world* pools, the number of Ibises in the pool is also needed to function correctly. This size must

²http://java.sun.com/j2se/1.5.0/docs/api/java/util/Properties.html

³http://logging.apache.org/log4j

be set using the ibis.pool.size property. This property is normally not needed. When it is needed, but not provided, Ibis will print an error.

3.3.5 The gmi-run script

To simplify running an Ibis GMI application, a gmi-run script is provided with the distribution. This script can be used as follows

```
gmi-run java-flags class parameters
```

The script performs the first two steps needed to run an Ibis GMI application. It adds all required jar files to the class path, and configures log4j. It then runs <code>java</code> with any command line options given to it. Therefore, any additional options for Java, the main class and any application parameters must be provided as if <code>java</code> was called directly.

The gmi-run script needs the location of the Ibis GMI distribution. This must be provided using the GMI_HOME environment variable.

3.4 Running an example on Unix-like systems

This section is specific for Unix-like systems. In particular, the commands presented are for a Bourne shell or bash.

We will now run the TSP example. All code below assumes the GMI_HOME environment variable is set to the location of the Ibis GMI distribution.

First, we will need an Ibis server. Start a shell and run the gmi-server script:

```
$ $GMI_HOME/bin/gmi-server --events
```

By providing the --events option the server prints information on when Ibis instances join and leave the pool.

Next, we will start the application two times. Run the following command in two different shells:

```
$ CLASSPATH=$GMI_HOME/examples/lib/gmi-examples.jar \
$GMI_HOME/bin/gmi-run \
-Dibis.server.address=localhost \
-Dibis.pool.size=2 -Dibis.pool.name=test \
tsp.Main $GMI_HOME/examples/src/tsp/table_15.1
```

This sets the CLASSPATH environment variable to the jar file of the application, and calls gmi-run. You should now have two running instances of your application. One of them should print:

```
cities 15
minimum = 3162
```

The other will print a count-down of the number of jobs, followed by the time used. As said, the gmi-run script is only provided for convenience. To run the application without gmi-run, the command below can be used. Note that this only works with Java 6. For Java 1.5, you need to explicitly add all jar files in \$GMI_HOME/lib to the classpath.

```
$ java \
    -cp \
    $GMI_HOME/lib/'*':$GMI_HOME/examples/lib/gmi-examples.jar \
    -Dibis.server.address=localhost \
    -Dibis.pool.name=test -Dibis.pool.size=2 \
    -Dlog4j.configuration=file:$GMI_HOME/log4j.properties \
    tsp.Main $GMI_HOME/examples/src/tsp/table_15.1
```

3.5 Running an example on Windows systems

We will now run the TSP example on a Windows XP system. All code below assumes the GMI_HOME environment variable is set to the location of the Ibis GMI distribution.

To set environment variable on Windows, right-click on the 'My Computer' icon, 'Properties', 'Advanced' tab, 'Environment Variables' button. There, you can add variables to either the User variables or the System variables.

First, we will need an Ibis server. Start a command prompt window and run the gmi-server script:

```
C:\DOCUME~1\Temp> "%GMI_HOME%"\bin\qmi-server --events
```

Note the quoting, which is needed when GMI_HOME contains spaces.

By providing the --events option the server prints information on when Ibis instances join and leave the pool.

Next, we will start the application two times. One instance will act as both an "GMI server" and an "GMI client", the other one will be an "GMI client". Ibis GMI will determine who is who automatically. Therefore we can using the same command line for both server and client. Run the following commands in two different shells:

```
C:\DOCUME~1\Temp> cd %GMI_HOME%\examples
C:...> set CLASSPATH=lib\gmi-examples.jar
C:...> "%GMI_HOME%"\bin\gmi-run
    "-Dibis.server.address=localhost"
    "-Dibis.pool.size=2" "-Dibis.pool.name=test"
    tsp.Main src\tsp\table_15.1
```

This sets the CLASSPATH environment variable to the jar file of the application, and calls gmi-run. You should now have two running instances of your application. One of them should print:

```
cities 15
minimum = 3162
```

or something similar.

As said, the gmi-run script is only provided for convenience. To run the application without gmi-run, the commands below can be used. Note that this only works with Java 6. For Java 1.5, you need to explicitly add all jar files in %GMI_HOME%\lib to the classpath.

```
C:\DOCUME~1\Temp> cd %GMI_HOME%\examples
C:...> java
    -cp "%GMI_HOME%\lib\*";lib\gmi-examples.jar
    -Dibis.server.address=localhost
    -Dibis.pool.name=test -Dibis.pool.size=2
    -Dlog4j.configuration=file:"%GMI_HOME%"\log4j.properties
    tsp.Main src\tsp\table_15.1
```

4 Further Reading

The Ibis web page http://www.cs.vu.nl/ibis lists all the documentation and software available for Ibis, including papers, and slides of presentations.

For detailed information on developing an Ibis GMI application see the Ibis GMI Programmers Manual, available in the docs directory of the Ibis GMI distribution.