# CSC/CPE 138 COMPUTER NETWORKING FUNDAMENTALS

Lecture 3\_2: Transport Layer
Slides adapted from
Computer Networking: A Top-Down Approach, Kurose Ross, 8th Edition
Department of Computer Science
SPRING 2024

All material copyright 1996-2023., J.F Kurose and K.W. Ross, All Rights Reserved



### Lecture 3\_2: Transport Layer Continued



- TCP Round trip time
- TCP Retransmissions
- TCP Flow Control
- TCP Connection Management
- TCP Congestion Control



### TCP segment structure




ACK: seq # of next expected byte; A bit: this is an ACK

length (of TCP header).
Internet checksum

C, E: congestion notification


TCP options

RST, SYN, FIN: connection management



### TCP sequence numbers, ACKs





simple telnet scenario

### TCP round trip time, timeout



- Q: how to set TCP timeout value?
- longer than RTT, but RTT varies!
- too short: premature timeout, unnecessary retransmissions
- too long: slow reaction to segment loss

#### Q: how to estimate RTT?


- SampleRTT: measured time from segment transmission until ACK receipt
  - ignore retransmissions
- SampleRTT will vary, want estimated RTT "smoother"
  - average several recent measurements, not just current SampleRTT

### TCP round trip time, timeout



```
EstimatedRTT = (1-\alpha)*EstimatedRTT + \alpha*SampleRTT
```

- <u>e</u>xponential <u>w</u>eighted <u>m</u>oving <u>a</u>verage (EWMA)
- influence of past sample decreases exponentially fast
- typical value:  $\alpha$  = 0.125




Sample RTT and Estimated RTT

### TCP round trip time, timeout



- timeout interval: EstimatedRTT plus "safety margin"
  - large variation in **EstimatedRTT**: want a larger safety margin



■ DevRTT: EWMA of SampleRTT deviation from EstimatedRTT:

DevRTT = 
$$(1-\beta)$$
\*DevRTT +  $\beta$ \*|SampleRTT-EstimatedRTT| (typically,  $\beta = 0.25$ )






#### Given

- Estimated RTT = 380msec
- Deviation RTT = 30 msec
- Next measured RTT is 350 msec
- $\alpha = 0.125$
- $\beta = 0.25$

#### Compute

- Estimated RTT
- Deviation RTT
- TCP Timeout



RTT EXAMPLE DIAGRAM



### Sample Question-Solution

```
EstimatedRTT = (1-\alpha)*EstimatedRTT + \alpha*SampleRTT
= (1-0.125)*380+0.125*350 = 376.25

DevRTT = (1-\beta)*DevRTT + \beta*|SampleRTT-EstimatedRTT|
= (1-0.25)*30 + 0.25* |350-380| = 30

Timeout Interval = EstimatedRTT + 4*DevRTT
= 376.25 + 4* 30 = 496.25
```

### TCP Sender (simplified)



# event: data received from application

- create segment with seq #
- seq # is byte-stream number of first data byte in segment
- start timer if not already running
  - think of timer as for oldest unACKed segment
  - expiration interval:TimeOutInterval

#### event: timeout


- retransmit segment that caused timeout
- restart timer

#### event: ACK received


- if ACK acknowledges previously unACKed segments
  - update what is known to be ACKed
  - start timer if there are still unACKed segments

### TCP: retransmission scenarios






lost ACK scenario



premature timeout

### TCP: retransmission scenarios





cumulative ACK covers for earlier lost ACK

### TCP fast retransmit




#### TCP fast retransmit

if sender receives 3 additional ACKs for same data ("triple duplicate ACKs"), resend unACKed segment with smallest seq #


 likely that unACKed segment lost, so don't wait for timeout

Receipt of three duplicate ACKs indicates 3 segments received after a missing segment – lost segment is likely. So retransmit!



SACRAMENTO STATE

Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?




receiver protocol stack

SACRAMENTO STATE

Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?








Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?

Application removing data from TCP socket buffers

application process TCP socket receiver buffers **TCP** code code from sender

receiver protocol stack





Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?

Application removing data from TCP socket

### process buffers TCP socket receiver buffers **TCP** code code from sender

application


receiver protocol stack

#### -flow control

receiver controls sender, so sender won't overflow receiver's buffer by transmitting too much, too fast




- TCP receiver "advertises" free buffer space in rwnd field in TCP header
  - RcvBuffer size set via socket options (typical default is 4096 bytes)
  - many operating systems auto-adjust
     RcvBuffer
- sender limits amount of unACKed ("in-flight") data to received rwnd
- guarantees receive buffer will not overflow



TCP receiver-side buffering



- TCP receiver "advertises" free buffer space in rwnd field in TCP header
  - RcvBuffer size set via socket options (typical default is 4096 bytes)
  - many operating systems auto-adjust
     RcvBuffer
- sender limits amount of unACKed ("in-flight") data to received rwnd
- guarantees receive buffer will not overflow




TCP segment format

### TCP connection management



before exchanging data, sender/receiver "handshake":

- agree to establish connection (each knowing the other willing to establish connection)
- agree on connection parameters (e.g., starting seq #s)



```
application

connection state: ESTAB
connection Variables:
  seq # client-to-server
      server-to-client
  rcvBuffer size
  at server, client

network
```


```
Socket clientSocket =
  newSocket("hostname", "port number");
```


```
Socket connectionSocket =
  welcomeSocket.accept();
```

### Agreeing to establish a connection



#### 2-way handshake:






# **Q**: will 2-way handshake always work in network?

- variable delays
- retransmitted messages (e.g. req\_conn(x)) due to message loss
- message reordering
- can't "see" other side

# 2-way handshake scenarios





# TCP 3-way handshake



#### Client state


serverSocket.listen(1) clientSocket = socket(AF INET, SOCK STREAM) LISTEN LISTEN clientSocket.connect((serverName, serverPort)) choose init seq num, x send TCP SYN msq SYNSFNT SYNbit=1, Seq=x choose init seq num, y send TCP SYNACK SYN RCVD msg, acking SYN SYNbit=1, Seq=y ACKbit=1; ACKnum=x+1 received SYNACK(x) indicates server is live; **ESTAB** send ACK for SYNACK; this segment may contain ACKbit=1, ACKnum=y+1 client-to-server data received ACK(y) indicates client is live **ESTAB** 

#### Server state

serverSocket = socket(AF INET, SOCK STREAM) serverSocket.bind(('', serverPort)) connectionSocket, addr = serverSocket.accept()

# A human 3-way handshake protocol





### Closing a TCP connection



- client, server each close their side of connection
  - send TCP segment with FIN bit = 1
- respond to received FIN with ACK
  - on receiving FIN, ACK can be combined with own FIN
- simultaneous FIN exchanges can be handled

### Question



You are developing a reliable transport control protocol and the protocol requires you to establish a connection between a client and a server before they can start communicating. You plan to send a connection request and wait for an acknowledgment to build a connection. Discuss the potential problems you observe in to 2-way connection transport control protocol. Provide diagrams to prove your claim.

#### Answer :

- Problem of half open connection
- Problem of duplicate data being accepted

### **Principles of Congestion Control**



#### Congestion:

• informally: "too many sources sending too much data too fast for network to handle"

- manifestations:
  - long delays (queueing in router buffers)
  - packet loss (buffer overflow at routers)
- different from flow control!
- a top-10 problem!




too many senders, sending too fast

flow control: one sender too fast for one receiver




#### Simplest scenario:


- one router, infinite buffers
- input, output link capacity: R
- two flows
- no retransmissions needed



Q: What happens as arrival rate  $\lambda_{in}$  approaches R/2?




maximum per-connection throughput: R/2



large delays as arrival rate  $\lambda \iota \nu \epsilon$  approaches capacity




- one router, *finite* buffers
- sender retransmits lost, timed-out packet
  - application-layer input = application-layer output:  $\lambda_{in} = \lambda_{out}$
  - transport-layer input includes retransmissions :  $\lambda'_{in} \ge \lambda_{in}$






#### Idealization: perfect knowledge

sender sends only when router buffers available








#### Idealization: some perfect knowledge


- packets can be lost (dropped at router) due to full buffers
- sender knows when packet has been dropped: only resends if packet known to be lost






#### Idealization: some perfect knowledge

- packets can be lost (dropped at router) due to full buffers
- sender knows when packet has been dropped: only resends if packet known to be lost









#### Realistic scenario: un-needed duplicates

- packets can be lost, dropped at router due to full buffers – requiring retransmissions
- but sender times can time out prematurely, sending two copies, both of which are delivered








#### Realistic scenario: un-needed duplicates

- packets can be lost, dropped at router due to full buffers – requiring retransmissions
- but sender times can time out prematurely, sending two copies, both of which are delivered



#### "costs" of congestion:


- more work (retransmission) for given receiver throughput
- unneeded retransmissions: link carries multiple copies of a packet
  - decreasing maximum achievable throughput




- *four* senders
- multi-hop paths
- timeout/retransmit

 $\underline{\mathbf{Q}}$ : what happens as  $\lambda_{in}$  and  $\lambda_{in}$  increase?

A: as red  $\lambda_{in}$  increases, all arriving blue pkts at upper queue are dropped, blue throughput  $\rightarrow$  0








#### another "cost" of congestion:


when packet dropped, any upstream transmission capacity and buffering used for that packet was wasted!


## Causes/costs of congestion: insights





- throughput can never exceed capacity
- delay increases as capacity approached
- loss/retransmission decreases effective throughput
- un-needed duplicates further decreases effective throughput
- upstream transmission capacity / buffering wasted for packets lost downstream
















### End-end congestion control:

- no explicit feedback from network
- congestion inferred from observed loss, delay
- approach taken by TCP








# Network-assisted congestion control:

- routers provide direct feedback to sending/receiving hosts with flows passing through congested router
- may indicate congestion level or explicitly set sending rate
- TCP ECN, ATM, DECbit protocols



## TCP congestion control: AIMD



 approach: senders can increase sending rate until packet loss (congestion) occurs, then decrease sending rate on loss event

### Additive Increase <u>Multiplicative</u> <u>Decrease</u> increase sending rate by 1 cut sending rate in half at maximum segment size every each loss event RTT until loss detected TCP sender Sending rate **AIMD** sawtooth behavior: probing for bandwidth

time

3-40

### TCP AIMD: more



#### Multiplicative decrease detail: sending rate is


- Cut in half on loss detected by triple duplicate ACK (TCP Reno)
- Cut to 1 MSS (maximum segment size) when loss detected by timeout (TCP Tahoe)

#### Why AIMD?

- AIMD a distributed, asynchronous algorithm has been shown to:
  - optimize congested flow rates network wide!
  - have desirable stability properties

## TCP congestion control: details





#### TCP sending behavior:

 roughly: send cwnd bytes, wait RTT for ACKS, then send more bytes


TCP rate 
$$\approx \frac{\text{cwnd}}{\text{RTT}}$$
 bytes/sec

- TCP sender limits transmission: LastByteSent- LastByteAcked < cwnd
- cwnd is dynamically adjusted in response to observed network congestion (implementing TCP congestion control)

### TCP slow start



- when connection begins, increase rate exponentially until first loss event:
  - initially **cwnd** = 1 MSS
  - double cwnd every RTT
  - done by incrementing cwnd for every ACK received
- summary: initial rate is slow, but ramps up exponentially fast



### TCP: from slow start to congestion avoidance




Q: when should the exponential increase switch to linear?

A: when **cwnd** gets to 1/2 of its value before timeout.

#### Implementation:


- variable ssthresh
- on loss event, **ssthresh** is set to 1/2 of **cwnd** just before loss event



### TCP CUBIC




- Is there a better way than AIMD to "probe" for usable bandwidth?
- Insight/intuition:
  - W<sub>max</sub>: sending rate at which congestion loss was detected
  - congestion state of bottleneck link probably (?) hasn't changed much
  - after cutting rate/window in half on loss, initially ramp to to  $W_{max}$  faster, but then approach  $W_{max}$  more slowly



### TCP CUBIC




- K: point in time when TCP window size will reach W<sub>max</sub>
  - K itself is tunable
- increase W as a function of the cube of the distance between current time and K
  - larger increases when further away from K
  - smaller increases (cautious) when nearer K
- TCP CUBIC default in Linux, most popular TCP for popular Web servers



## TCP and the congested "bottleneck link"




 TCP (classic, CUBIC) increase TCP's sending rate until packet loss occurs at some router's output: the bottleneck link



## TCP and the congested "bottleneck link"




- TCP (classic, CUBIC) increase TCP's sending rate until packet loss occurs at some router's output: the bottleneck link
- understanding congestion: useful to focus on congested bottleneck link



## Delay-based TCP congestion control



Keeping sender-to-receiver pipe "just full enough, but no fuller": keep bottleneck link busy transmitting, but avoid high delays/buffering



#### Delay-based approach:

- RTT<sub>min</sub> minimum observed RTT (uncongested path)
- uncongested throughput with congestion window cwnd is cwnd/RTT<sub>min</sub>

```
if measured throughput "very close" to uncongested throughput increase cwnd linearly /* since path not congested */ else if measured throughput "far below" uncongested throughout decrease cwnd linearly /* since path is congested */
```

## Delay-based TCP congestion control




- congestion control without inducing/forcing loss
- maximizing throughout ("keeping the just pipe full...") while keeping delay low ("...but not fuller")
- a number of deployed TCPs take a delay-based approach
  - BBR deployed on Google's (internal) backbone network

## Explicit congestion notification (ECN)



TCP deployments often implement *network-assisted* congestion control:


- two bits in IP header (ToS field) marked by network router to indicate congestion
  - policy to determine marking chosen by network operator
- congestion indication carried to destination
- destination sets ECE bit on ACK segment to notify sender of congestion
- involves both IP (IP header ECN bit marking) and TCP (TCP header C,E bit marking)



### TCP fairness



Fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K




### Q: is TCP Fair?



### Example: two competing TCP sessions:


- additive increase gives slope of 1, as throughout increases
- multiplicative decrease decreases throughput proportionally



#### Is TCP fair?

A: Yes, under idealized assumptions:

- same RTT
- fixed number of sessions only in congestion avoidance





- TCP Round trip time
- TCP Retransmissions
- TCP Flow Control
- TCP Connection Management
- TCP Congestion Control



## End of Lecture 3\_2