


Lab – Configuring Advanced EIGRP for IPv4 Features (Instructor Version)

Instructor Note: Red font color or Gray highlights indicate text that appears in the instructor copy only.

Topology



Addressing Table

Device	Interface	IP Address	Subnet Mask	Default Gateway
R1	G0/0	192.168.1.1	255.255.255.0	N/A
	S0/0/0 (DCE)	192.168.12.1	255.255.255.252	N/A
	S0/0/1	192.168.13.1	255.255.255.252	N/A
	Lo1	192.168.11.1	255.255.255.252	N/A
	Lo5	192.168.11.5	255.255.255.252	N/A
	Lo9	192.168.11.9	255.255.255.252	N/A
	Lo13	192.168.11.13	255.255.255.252	N/A
R2	G0/0	192.168.2.1	255.255.255.0	N/A
	S0/0/0	192.168.12.2	255.255.255.252	N/A
	S0/0/1 (DCE)	192.168.23.1	255.255.255.252	N/A
	Lo1	192.168.22.1	255.255.255.252	N/A
R3	G0/0	192.168.3.1	255.255.255.0	N/A
	S0/0/0 (DCE)	192.168.13.2	255.255.255.252	N/A
	S0/0/1	192.168.23.2	255.255.255.252	N/A
	Lo1	192.168.33.1	255.255.255.252	N/A
	Lo5	192.168.33.5	255.255.255.252	N/A
	Lo9	192.168.33.9	255.255.255.252	N/A
	Lo13	192.168.33.13	255.255.255.252	N/A
PC-A	NIC	192.168.1.3	255.255.255.0	192.168.1.1
РС-В	NIC	192.168.2.3	255.255.255.0	192.168.2.1
PC-C	NIC	192.168.3.3	255.255.255.0	192.168.3.1

Objectives

Part 1: Build the Network and Configure Basic Device Settings

Part 2: Configure EIGRP and Verify Connectivity

Part 3: Configure Summarization for EIGRP

- Configure EIGRP for automatic summarization.
- Configure manual summarization for EIGRP.

Part 4: Configure and Propagate a Default Static Route

Part 5: Fine-Tune EIGRP

- Configure bandwidth utilization for EIGRP.
- Configure the hello interval and hold timer for EIGRP.

Part 6: Configure EIGRP Authentication

Background / Scenario

EIGRP has advanced features to allow changes related to summarization, default route propagation, bandwidth utilization, metrics, and security.

In this lab, you will configure automatic and manual summarization for EIGRP, configure EIGRP route propagation, fine-tune EIGRP metrics, and use MD5 authentication to secure EIGRP routing information.

Note: The routers used with CCNA hands-on labs are Cisco 1941 Integrated Services Routers (ISRs) with Cisco IOS Release 15.2(4)M3 (universalk9 image). Other routers and Cisco IOS versions can be used. Depending on the model and Cisco IOS version, the commands available and output produced might vary from what is shown in the labs. Refer to the Router Interface Summary Table at this end of the lab for the correct interface identifiers.

Note: Ensure that the routers have been erased and have no startup configurations. If you are unsure, contact your instructor.

Instructor Note: Refer to the Instructor Lab Manual for the procedures to initialize and reload devices.

Required Resources

- 3 Routers (Cisco 1941 with Cisco IOS Release 15.2(4)M3 universal image or comparable)
- 3 PCs (Windows 7, Vista, or XP with terminal emulation program, such as Tera Term)
- Console cables to configure the Cisco IOS devices via the console ports
- Ethernet and serial cables as shown in the topology

Part 1: Build the Network and Configure Basic Device Settings

In Part 1, you will set up the network topology and configure basic settings on the PC hosts and routers.

- Step 1: Cable the network as shown in the topology.
- Step 2: Configure PC hosts.
- Step 3: Initialize and reload the routers as necessary.
- Step 4: Configure basic settings for each router.
 - a. Disable DNS lookup.
 - b. Configure device name as shown in the topology.
 - c. Assign **cisco** as the console and vty passwords.
 - d. Assign class as the privileged EXEC password.
 - e. Configure logging synchronous to prevent console messages from interrupting command entry.
 - f. Configure the IP address listed in the Addressing Table for all interfaces.
 - **Note**: Do **NOT** configure the loopback interfaces at this time.
 - g. Copy the running configuration to the startup configuration.

Part 2: Configure EIGRP and Verify Connectivity

In Part 2, you will configure basic EIGRP for the topology and set bandwidths for the serial interfaces.

Note: This lab provides minimal assistance with the actual commands necessary to configure EIGRP. However, the required commands are provided in Appendix A. Test your knowledge by trying to configure the devices without referring to the appendix.

Step 1: Configure EIGRP.

a. On R1, configure EIGRP routing with an autonomous system (AS) ID of 1 for all directly connected networks. Write the commands used in the space below.

R1(config)# router eigrp 1
R1(config-router)# network 192.168.1.0
R1(config-router)# network 192.168.12.0 0.0.0.3
R1(config-router)# network 192.168.13.0 0.0.0.3

b. For the LAN interface on R1, disable the transmission of EIGRP hello packets. Write the command used in the space below.

R1(config-router)# passive-interface g0/0

c. On R1, configure the bandwidth for S0/0/0 to 1024 Kb/s and the bandwidth for S0/0/1 to 64 Kb/s. Write the commands used in the space below. **Note**: The **bandwidth** command only affects the EIGRP metric calculation, not the actual bandwidth of the serial link.

R1(config)# interface s0/0/0
R1(config-if)# bandwidth 1024
R1(config-if)# interface s0/0/1
R1(config-if)# bandwidth 64

- d. On R2, configure EIGRP routing with an AS ID of 1 for all networks, disable the transmission of EIGRP hello packets for the LAN interface, and configure the bandwidth for S0/0/0 to 1024 Kb/s.
- e. On R3, configure EIGRP routing with an AS ID of 1 for all networks, disable the transmission of EIGRP hello packets for the LAN interface, and configure the bandwidth for S0/0/0 to 64 Kb/s.

Step 2: Test connectivity.

All PCs should be able to ping one another. Verify and troubleshoot if necessary.

Note: It may be necessary to disable the PC firewall to ping between PCs.

Part 3: Configure Summarization for EIGRP

In Part 3, you will add loopback interfaces to R1, enable EIGRP automatic summarization on R1, and observe the effects on the routing table for R2. You will also add loopback interfaces on R3.

Step 1: Configure EIGRP for automatic summarization.

a. Issue the **show ip protocols** command on R1. What is the default status of automatic summarization in EIGRP?

```
R1# show ip protocols
*** IP Routing is NSF aware ***
Routing Protocol is "eigrp 1"
 Outgoing update filter list for all interfaces is not set
 Incoming update filter list for all interfaces is not set
 Default networks flagged in outgoing updates
 Default networks accepted from incoming updates
 EIGRP-IPv4 Protocol for AS(1)
   Metric weight K1=1, K2=0, K3=1, K4=0, K5=0
   NSF-aware route hold timer is 240
   Router-ID: 192.168.13.1
   Topology: 0 (base)
     Active Timer: 3 min
     Distance: internal 90 external 170
     Maximum path: 4
     Maximum hopcount 100
     Maximum metric variance 1
 Automatic Summarization: disabled
 Maximum path: 4
 Routing for Networks:
   192.168.1.0
   192.168.12.0/30
   192.168.13.0/30
 Passive Interface(s):
   GigabitEthernet0/0
 Routing Information Sources:
   Gateway
              Distance Last Update
   192.168.12.2
                               00:30:16
   192.168.13.2
                         90
                                 00:30:16
 Distance: internal 90 external 170
```

Automatic network summarization is disabled.

- b. Configure the loopback addresses on R1.
- c. Add the appropriate network statements to the EIGRP process on R1. Record the commands used in the space below.

R1(config)# router eigrp 1

```
R1(config-router) # network 192.168.11.0 0.0.0.3
R1(config-router) # network 192.168.11.4 0.0.0.3
R1(config-router) # network 192.168.11.8 0.0.0.3
R1(config-router) # network 192.168.11.12 0.0.0.3
```

d. On R2, issue the **show ip route eigrp** command. How are the loopback networks represented in the output?

```
R2# show ip route eigrp
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
      N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
      E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route
Gateway of last resort is not set
D
      192.168.1.0/24 [90/3014400] via 192.168.12.1, 00:14:58, Serial0/0/0
D
      192.168.3.0/24 [90/2172416] via 192.168.23.2, 00:11:18, Serial0/0/1
      192.168.11.0/30 is subnetted, 4 subnets
         192.168.11.0 [90/3139840] via 192.168.12.1, 00:00:14, Serial0/0/0
\Box
D
         192.168.11.4 [90/3139840] via 192.168.12.1, 00:00:14, Serial0/0/0
D
         192.168.11.8 [90/3139840] via 192.168.12.1, 00:00:14, Serial0/0/0
D
         192.168.11.12 [90/3139840] via 192.168.12.1, 00:00:14, Serial0/0/0
      192.168.13.0/30 is subnetted, 1 subnets
         192.168.13.0 [90/41024000] via 192.168.23.2, 00:06:11, Serial0/0/1
\Box
                      [90/41024000] via 192.168.12.1, 00:06:11, Serial0/0/0
```

All subnetworks are listed in the routing table output.

e. On R1, issue the auto-summary command inside the EIGRP process.

```
R1(config) # router eigrp 1
R1(config-router) # auto-summary
R1(config-router) #

*Apr 14 01:14:55.463: %DUAL-5-NBRCHANGE: EIGRP-IPv4 1: Neighbor 192.168.13.2
(Serial0/0/1) is resync: summary configured

*Apr 14 01:14:55.463: %DUAL-5-NBRCHANGE: EIGRP-IPv4 1: Neighbor 192.168.12.2
(Serial0/0/0) is resync: summary configured

*Apr 14 01:14:55.463: %DUAL-5-NBRCHANGE: EIGRP-IPv4 1: Neighbor 192.168.13.2
(Serial0/0/1) is resync: summary up, remove components
R1(config-router) #67: %DUAL-5-NBRCHANGE: EIGRP-IPv4 1: Neighbor 192.168.12.2
(Serial0/0/0) is resync: summary up, remove components

*Apr 14 01:14:55.467: %DUAL-5-NBRCHANGE: EIGRP-IPv4 1: Neighbor 192.168.12.2
(Serial0/0/0) is resync: summary up, remove components

*Apr 14 01:14:55.467: %DUAL-5-NBRCHANGE: EIGRP-IPv4 1: Neighbor 192.168.13.2
(Serial0/0/1) is resync: summary up, remove components
```

How does the routing table on R2 change?

```
R2# show ip route eigrp
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
```

```
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
      N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
      E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
      P - periodic downloaded static route
Gateway of last resort is not set
     192.168.1.0/24 [90/3014400] via 192.168.12.1, 00:01:13, Serial0/0/0
     192.168.3.0/24 [90/2172416] via 192.168.23.2, 00:15:58, Serial0/0/1
     192.168.11.0/24 is subnetted, 1 subnets
        192.168.11.0 [90/3139840] via 192.168.12.1, 00:01:13, Serial0/0/0
     192.168.12.0/24 is variably subnetted, 3 subnets, 3 masks
        192.168.12.0/24 [90/41536000] via 192.168.23.2, 00:01:13, Serial0/0/1
     192.168.13.0/24 is variably subnetted, 2 subnets, 2 masks
        192.168.13.0/24 [90/41024000] via 192.168.12.1, 00:01:13, Serial0/0/0
D
D
        192.168.13.0/30 [90/41024000] via 192.168.23.2, 00:01:13, Serial0/0/1
```

The 192.168.11.0 networks are summarized at their classful boundary.

Step 2: Configure manual summarization for EIGRP.

- a. Configure the loopback addresses on R3.
- b. Add the appropriate network statements to the EIGRP process on R3.
- c. On R2, issue the **show ip route eigrp** command. How are the loopback networks from R3 represented in the output?

```
R2# show ip route eigrp
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
      N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
      E1 - OSPF external type 1, E2 - OSPF external type 2
       i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
      ia - IS-IS inter area, * - candidate default, U - per-user static route
       o - ODR, P - periodic downloaded static route, H - NHRP, 1 - LISP
       + - replicated route, % - next hop override
Gateway of last resort is not set
      192.168.1.0/24 [90/3014400] via 192.168.12.1, 00:11:50, Serial0/0/0
D
      192.168.3.0/24 [90/2172416] via 192.168.23.2, 00:26:35, Serial0/0/1
      192.168.11.0/24 is subnetted, 1 subnets
         192.168.11.0 [90/3139840] via 192.168.12.1, 00:11:50, Serial0/0/0
D
     192.168.12.0/24 is variably subnetted, 3 subnets, 3 masks
D
        192.168.12.0/24 [90/41536000] via 192.168.23.2, 00:11:50, Serial0/0/1
     192.168.13.0/24 is variably subnetted, 2 subnets, 2 masks
D
        192.168.13.0/24 [90/41024000] via 192.168.12.1, 00:11:50, Serial0/0/0
D
        192.168.13.0/30 [90/41024000] via 192.168.23.2, 00:11:50, Serial0/0/1
```

192.168.33.0/30 is subnetted, 3 subnets

```
D 192.168.33.0 [90/2297856] via 192.168.23.2, 00:00:19, Serial0/0/1
D 192.168.33.4 [90/2297856] via 192.168.23.2, 00:00:19, Serial0/0/1
D 192.168.33.8 [90/2297856] via 192.168.23.2, 00:00:19, Serial0/0/1
D 192.168.33.12 [90/2297856] via 192.168.23.2, 00:00:19, Serial0/0/1
```

All subnetworks are listed in the routing table.

d. Determine the summary EIGRP route for the loopback addresses on R3. Write the summary route in the space below.

192.168.33.0 255.255.255.240

e. For the serial interfaces on R3, issue the **ip summary-address eigrp 1** *network address subnet mask* command to manually summarize the networks.

```
R3(config)# interface s0/0/0
R3(config-if)# ip summary-address eigrp 1 192.168.33.0 255.255.255.240
R3(config-if)# exit
R3(config)# interface s0/0/1
R3(config-if)# ip summary-address eigrp 1 192.168.33.0 255.255.255.240
*Apr 14 01:33:46.433: %DUAL-5-NBRCHANGE: EIGRP-IPv4 1: Neighbor 192.168.13.1 (Serial0/0/0) is resync: summary configured
*Apr 14 01:33:46.433: %DUAL-5-NBRCHANGE: EIGRP-IPv4 1: Neighbor 192.168.23.1 (Serial0/0/1) is resync: summary configured
```

How does the routing table on R2 change?

```
R2# show ip route eigrp
```

```
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2
i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
ia - IS-IS inter area, * - candidate default, U - per-user static route
o - ODR, P - periodic downloaded static route, H - NHRP, 1 - LISP
+ - replicated route, % - next hop override
```

Gateway of last resort is not set

```
D
     192.168.1.0/24 [90/3014400] via 192.168.12.1, 00:21:32, Serial0/0/0
     192.168.3.0/24 [90/2172416] via 192.168.23.2, 00:36:17, Serial0/0/1
D
      192.168.11.0/24 is subnetted, 1 subnets
D
        192.168.11.0 [90/3139840] via 192.168.12.1, 00:21:32, Serial0/0/0
     192.168.12.0/24 is variably subnetted, 3 subnets, 3 masks
D
         192.168.12.0/24 [90/41536000] via 192.168.23.2, 00:21:32, Serial0/0/1
      192.168.13.0/24 is variably subnetted, 2 subnets, 2 masks
        192.168.13.0/24 [90/41024000] via 192.168.12.1, 00:21:32, Serial0/0/0
         192.168.13.0/30 [90/41024000] via 192.168.23.2, 00:21:32, Serial0/0/1
D
      192.168.33.0/28 is subnetted, 1 subnets
D
         192.168.33.0 [90/2297856] via 192.168.23.2, 00:02:51, Serial0/0/1
```

The 192.168.33.0 networks are summarized with a /28 mask.

Part 4: Configure and Propagate a Default Static Route

In Part 4, you will configure a default static route on R2 and propagate the route to all other routers.

- a. Configure the loopback address on R2.
- b. Configure a default static route with an exit interface of Lo1.

```
R2(config)# ip route 0.0.0.0 0.0.0.0 Lo1
```

c. Use the **redistribute static** command within the EIGRP process to propagate the default static route to other participating routers.

```
R2(config) # router eigrp 1
R2(config-router) # redistribute static
```

d. Use the **show ip protocols** command on R2 to verify the static route is being distributed.

```
R2# show ip protocols
*** IP Routing is NSF aware ***
Routing Protocol is "eigrp 1"
 Outgoing update filter list for all interfaces is not set
 Incoming update filter list for all interfaces is not set
 Default networks flagged in outgoing updates
 Default networks accepted from incoming updates
 Redistributing: static
 EIGRP-IPv4 Protocol for AS(1)
   Metric weight K1=1, K2=0, K3=1, K4=0, K5=0
   NSF-aware route hold timer is 240
   Router-ID: 192.168.23.1
   Topology: 0 (base)
     Active Timer: 3 min
     Distance: internal 90 external 170
     Maximum path: 4
     Maximum hopcount 100
     Maximum metric variance 1
 Automatic Summarization: disabled
 Maximum path: 4
 Routing for Networks:
   192.168.2.0
   192.168.12.0/30
   192.168.23.0/30
 Passive Interface(s):
   GigabitEthernet0/0
 Routing Information Sources:
   Gateway Distance Last Update
   192.168.12.1
192.168.23.2
                                00:13:20
                       90
                        90
                                00:13:20
```

Distance: internal 90 external 170

e. On R1, issue the **show ip route eigrp | include 0.0.0.0** command to view statements specific to the default route. How is the static default route represented in the output? What is the administrative distance (AD) for the propagated route?

```
R1# show ip route eigrp | include 0.0.0.0

Gateway of last resort is 192.168.12.2 to network 0.0.0.0

D*EX 0.0.0.0/0 [170/3139840] via 192.168.12.2, 00:06:27, Serial0/0/0
```

As an externally learned EIGRP route:

```
D*EX 0.0.0.0/0 [170/3139840] via 192.168.12.2, 00:06:27, Serial0/0/0
```

The administrative distance is 170 as it is an external EIGRP route.

Part 5: Fine-Tune EIGRP

In Part 5, you will configure the percentage of bandwidth that can be used by an EIGRP interface and change the hello interval and hold timers for EIGRP interfaces.

Step 1: Configure bandwidth utilization for EIGRP.

 a. Configure the serial link between R1 and R2 to allow only 75 percent of the link bandwidth for EIGRP traffic.

```
R1(config) # interface s0/0/0
R1(config-if) # ip bandwidth-percent eigrp 1 75
R2(config) # interface s0/0/0
R2(config-if) # ip bandwidth-percent eigrp 1 75
```

b. Configure the serial link between R1 and R3 to allow 40 percent of the links bandwidth for EIGRP traffic.

Step 2: Configure the hello interval and hold timer for EIGRP.

a. On R2, use the **show ip eigrp interfaces detail** command to view the hello interval and hold timer for EIGRP.

R2# show ip eigrp interfaces detail

EIGRP-IPv4 Interfaces for AS(1)

```
Xmit Queue PeerQ Mean Pacing Time Multicast
                                                                                Pending
Interface
                    Peers Un/Reliable Un/Reliable SRTT Un/Reliable Flow Timer
                                                                                Routes
                                     0/0 1
Se0/0/0
                      1
                              0/0
                                                        0/15
                                                                      50
                                                                                   Ω
 Hello-interval is 5, Hold-time is 15
 Split-horizon is enabled
 Next xmit serial <none>
 Packetized sent/expedited: 29/1
 Hello's sent/expedited: 390/2
 Un/reliable mcasts: 0/0 Un/reliable ucasts: 35/39
 Mcast exceptions: 0 CR packets: 0 ACKs suppressed: 0
 Retransmissions sent: 0 Out-of-sequence rcvd: 0
 Topology-ids on interface - 0
 Interface BW percentage is 75
 Authentication mode is not set
                                               1 0/16
                                      0/0
                      1
                              0/0
                                                                        5.0
                                                                                    Ω
 Hello-interval is 5, Hold-time is 15
 Split-horizon is enabled
```

```
Next xmit serial <none>
Packetized sent/expedited: 34/5
Hello's sent/expedited: 382/2
Un/reliable mcasts: 0/0 Un/reliable ucasts: 31/42
Mcast exceptions: 0 CR packets: 0 ACKs suppressed: 2
Retransmissions sent: 0 Out-of-sequence rcvd: 0
Topology-ids on interface - 0
Authentication mode is not set

What is the default value for hello time?

5 seconds

What is the default value for hold time?
```

b. Configure S0/0/0 and S0/0/1 interfaces on R1 to use a hello interval of 60 seconds and a hold time of 180 seconds in that specific order.

```
R1(config)# interface s0/0/0
R1(config-if)# ip hello-interval eigrp 1 60
R1(config-if)# ip hold-time eigrp 1 180
R1(config)# interface s0/0/1
R1(config-if)# ip hello-interval eigrp 1 60
R1(config-if)# ip hold-time eigrp 1 180
```

- c. Configure the serial interfaces on R2 and R3 to use a hello interval of 60 seconds and a hold time of 180 seconds.
- d. Use the **show ip eigrp interfaces detail** command on R2 to verify configuration.

```
R2# show ip eigrp interfaces detail
```

```
EIGRP-IPv4 Interfaces for AS(1)
                          Xmit Queue PeerQ Mean Pacing Time Multicast Pending
Interface
                   Peers Un/Reliable Un/Reliable SRTT Un/Reliable Flow Timer Routes
                    1 0/0 0/0 1 0/15 50
Se0/0/0
 Hello-interval is 60, Hold-time is 180
 Split-horizon is enabled
 Next xmit serial <none>
 Packetized sent/expedited: 38/1
 Hello's sent/expedited: 489/4
 Un/reliable mcasts: 0/0 Un/reliable ucasts: 40/48
 Mcast exceptions: 0 CR packets: 0 ACKs suppressed: 0
 Retransmissions sent: 0 Out-of-sequence rcvd: 0
 Topology-ids on interface - 0
 Interface BW percentage is 75
 Authentication mode is not set
                                                        0/16
                     1 0/0 0/0
                                                1
                                                                     50
 Hello-interval is 60, Hold-time is 180
 Split-horizon is enabled
 Next xmit serial <none>
 Packetized sent/expedited: 45/5
 Hello's sent/expedited: 481/2
 Un/reliable mcasts: 0/0 Un/reliable ucasts: 46/55
 Mcast exceptions: 0 CR packets: 0 ACKs suppressed: 2
 Retransmissions sent: 0 Out-of-sequence rcvd: 0
 Topology-ids on interface - 0
 Authentication mode is not set
```

Part 6: Configure EIGRP Authentication

In Part 6, you will create an authentication key on all routers and configure router interfaces to use MD5 authentication for EIGRP message authentication.

Step 1: Configure authentication keys.

 a. On R1, use the key chain name command in global configuration mode to create a key chain with the label EIGRP-KEYS.

```
R1(config) # key chain EIGRP-KEYS
R1(config-keychain) # key 1
R1(config-keychain-key) # key-string cisco
```

- b. Complete the configuration on R2 and R3.
- c. Issue the show key chain command. You should have the same output on every router.

Step 2: Configure EIGRP link authentication.

a. Apply the following commands to active EIGRP authentication on the serial interfaces on R1.


```
R1# conf t
R1(config)# interface s0/0/0
R1(config-if)# ip authentication key-chain eigrp 1 EIGRP-KEYS
R1(config-if)# ip authentication mode eigrp 1 md5
R1(config-if)# interface s0/0/1
R1(config-if)# ip authentication key-chain eigrp 1 EIGRP-KEYS
R1(config-if)# ip authentication mode eigrp 1 md5
```

- b. Activate EIGRP authentication on the serial interfaces on R2 and R3.
- c. On R2, use the **show ip eigrp interfaces detail** command to verify authentication.

R2# show ip eigrp interfaces detail

```
EIGRP-IPv4 Interfaces for AS(1)
                           Xmit Queue PeerQ Mean Pacing Time Multicast
                                                                                  Pending
                    Peers Un/Reliable Un/Reliable SRTT Un/Reliable Flow Timer
Interface
                                                                                  Routes
                      1
                                      0/0 1 0/23
 Hello-interval is 60, Hold-time is 180
 Split-horizon is enabled
 Next xmit serial <none>
 Packetized sent/expedited: 30/5
 Hello's sent/expedited: 1163/5
 Un/reliable mcasts: 0/0 Un/reliable ucasts: 25/34
 Mcast exceptions: 0 CR packets: 0 ACKs suppressed: 0
 Retransmissions sent: 0 Out-of-sequence rcvd: 0
 Topology-ids on interface - 0
 Authentication mode is md5, key-chain is "EIGRP-KEYS"
                                                            0/15
                      1
                              0/0
                                      0/0
                                                   2
                                                                         50
 Hello-interval is 60, Hold-time is 180
 Split-horizon is enabled
 Next xmit serial <none>
 Packetized sent/expedited: 31/1
 Hello's sent/expedited: 1354/3
 Un/reliable mcasts: 0/0 Un/reliable ucasts: 28/34
```

```
Mcast exceptions: 0 CR packets: 0 ACKs suppressed: 4
Retransmissions sent: 0 Out-of-sequence rcvd: 0
Topology-ids on interface - 0
Authentication mode is md5, key-chain is "EIGRP-KEYS"
```



Router Interface Summary Table

Router Interface Summary						
Router Model	Ethernet Interface #1	Ethernet Interface #2	Serial Interface #1	Serial Interface #2		
1800	Fast Ethernet 0/0 (F0/0)	Fast Ethernet 0/1 (F0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)		
1900	Gigabit Ethernet 0/0 (G0/0)	Gigabit Ethernet 0/1 (G0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)		
2801	Fast Ethernet 0/0 (F0/0)	Fast Ethernet 0/1 (F0/1)	Serial 0/1/0 (S0/1/0)	Serial 0/1/1 (S0/1/1)		
2811	Fast Ethernet 0/0 (F0/0)	Fast Ethernet 0/1 (F0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)		
2900	Gigabit Ethernet 0/0 (G0/0)	Gigabit Ethernet 0/1 (G0/1)	Serial 0/0/0 (S0/0/0)	Serial 0/0/1 (S0/0/1)		

Note: To find out how the router is configured, look at the interfaces to identify the type of router and how many interfaces the router has. There is no way to effectively list all the combinations of configurations for each router class. This table includes identifiers for the possible combinations of Ethernet and Serial interfaces in the device. The table does not include any other type of interface, even though a specific router may contain one. An example of this might be an ISDN BRI interface. The string in parenthesis is the legal abbreviation that can be used in Cisco IOS commands to represent the interface.

Appendix A: Configuration Commands

Router R1

```
R1(config) # router eigrp 1
R1(config-router) # network 192.168.1.0
R1(config-router) # network 192.168.12.0 0.0.0.3
R1(config-router) # network 192.168.13.0 0.0.0.3
R1(config-router) # network 192.168.11.0 0.0.0.3
R1(config-router) # network 192.168.11.4 0.0.0.3
R1(config-router) # network 192.168.11.8 0.0.0.3
R1(config-router) # network 192.168.11.12 0.0.0.3
R1(config-router) # network 192.168.11.12 0.0.0.3
R1(config-router) # passive-interface g0/0
R1(config) # int s0/0/0
R1(config-if) # bandwidth 1024
R1(config-if) # int s0/0/1
R1(config-if) # bandwidth 64
```

Router R2

```
R2(config) # router eigrp 1
R2(config-router) # network 192.168.2.0
R2(config-router) # network 192.168.12.0 0.0.0.3
R2(config-router) # network 192.168.23.0 0.0.0.3
R2(config-router) # passive-interface q0/0
```

```
R2(config) # int s0/0/0
R2(config-if) # bandwidth 1024
```

Router R3

```
R3(config) # router eigrp 1
R3(config-router) # network 192.168.3.0
R3(config-router) # network 192.168.13.0 0.0.0.3
R3(config-router) # network 192.168.23.0 0.0.0.3
R3(config-router) # network 192.168.33.0 0.0.0.3
R3(config-router) # network 192.168.33.4 0.0.0.3
R3(config-router) # network 192.168.33.8 0.0.0.3
R3(config-router) # network 192.168.33.12 0.0.0.3
R3(config-router) # network 192.168.33.12 0.0.0.3
R3(config-router) # passive-interface g0/0
R3(config) # int s0/0/0
R3(config-if) # bandwidth 64
```

Device Configs - R1, R2, and R3

Router R1

```
R1#show run
Building configuration...
Current configuration: 2378 bytes
version 15.2
service timestamps debug datetime msec
service timestamps log datetime msec
no service password-encryption
hostname R1
boot-start-marker
boot-end-marker
enable secret 4 06YFDUHH61wAE/kLkDq9BGho1QM5EnRtoyr8cHAUg.2
no aaa new-model
no ip domain lookup
ip cef
no ipv6 cef
multilink bundle-name authenticated
key chain EIGRP-KEYS
key 1
key-string cisco
```

```
redundancy
interface Loopback1
ip address 192.168.11.1 255.255.255.252
interface Loopback5
ip address 192.168.11.5 255.255.255.252
interface Loopback9
ip address 192.168.11.9 255.255.255.252
interface Loopback13
ip address 192.168.11.13 255.255.255.252
interface Embedded-Service-Engine0/0
no ip address
shutdown
interface GigabitEthernet0/0
ip address 192.168.1.1 255.255.255.0
duplex auto
speed auto
interface GigabitEthernet0/1
no ip address
shutdown
duplex auto
speed auto
interface Serial0/0/0
bandwidth 1024
ip address 192.168.12.1 255.255.255.252
ip authentication mode eigrp 1 md5
ip authentication key-chain eigrp 1 EIGRP-KEYS
ip bandwidth-percent eigrp 1 75
ip hello-interval eigrp 1 60
ip hold-time eigrp 1 180
clock rate 2000000
interface Serial0/0/1
bandwidth 64
ip address 192.168.13.1 255.255.255.252
ip authentication mode eigrp 1 md5
ip authentication key-chain eigrp 1 EIGRP-KEYS
ip bandwidth-percent eigrp 1 40
ip hello-interval eigrp 1 60
ip hold-time eigrp 1 180
```

```
router eigrp 1
network 192.168.1.0
network 192.168.11.0 0.0.0.3
network 192.168.11.4 0.0.0.3
network 192.168.11.8 0.0.0.3
network 192.168.11.12 0.0.0.3
network 192.168.12.0 0.0.0.3
network 192.168.13.0 0.0.0.3
auto-summary
passive-interface GigabitEthernet0/0
ip forward-protocol nd
no ip http server
no ip http secure-server
control-plane
1
line con 0
password cisco
logging synchronous
login
line aux 0
line 2
no activation-character
no exec
transport preferred none
transport input all
transport output pad telnet rlogin lapb-ta mop udptn v120 ssh
stopbits 1
line vty 0 4
password cisco
login
transport input all
scheduler allocate 20000 1000
end
Router R2
Building configuration...
Current configuration: 2223 bytes
version 15.2
service timestamps debug datetime msec
service timestamps log datetime msec
no service password-encryption
```

```
hostname R2
boot-start-marker
boot-end-marker
enable secret 4 06YFDUHH61wAE/kLkDq9BGho1QM5EnRtoyr8cHAUg.2
no aaa new-model
no ip domain lookup
ip cef
no ipv6 cef
multilink bundle-name authenticated
key chain EIGRP-KEYS
key 1
 key-string cisco
!
redundancy
interface Loopback1
ip address 192.168.22.1 255.255.255.252
interface Embedded-Service-Engine0/0
no ip address
shutdown
interface GigabitEthernet0/0
ip address 192.168.2.1 255.255.255.0
duplex auto
speed auto
interface GigabitEthernet0/1
no ip address
shutdown
duplex auto
speed auto
interface Serial0/0/0
bandwidth 1024
ip address 192.168.12.2 255.255.255.252
ip authentication mode eigrp 1 md5
ip authentication key-chain eigrp 1 EIGRP-KEYS
ip bandwidth-percent eigrp 1 75
ip hello-interval eigrp 1 60
ip hold-time eigrp 1 180
```

```
interface Serial0/0/1
ip address 192.168.23.1 255.255.255.252
ip authentication mode eigrp 1 md5
ip authentication key-chain eigrp 1 EIGRP-KEYS
ip hello-interval eigrp 1 60
ip hold-time eigrp 1 180
clock rate 2000000
!
router eigrp 1
network 192.168.2.0
network 192.168.12.0 0.0.0.3
network 192.168.23.0 0.0.0.3
redistribute static
passive-interface GigabitEthernet0/0
ip forward-protocol nd
no ip http server
no ip http secure-server
ip route 0.0.0.0 0.0.0.0 Loopback1
!
!
control-plane
!
line con 0
password cisco
logging synchronous
login
line aux 0
line 2
no activation-character
no exec
transport preferred none
transport input all
transport output pad telnet rlogin lapb-ta mop udptn v120 ssh
stopbits 1
line vty 0 4
password cisco
login
transport input all
scheduler allocate 20000 1000
```

! end

Router R3

```
R3#show run
Building configuration...
Current configuration: 2456 bytes
version 15.2
service timestamps debug datetime msec
service timestamps log datetime msec
no service password-encryption
hostname R3
boot-start-marker
boot-end-marker
!
!
enable secret 4 06YFDUHH61wAE/kLkDq9BGho1QM5EnRtoyr8cHAUg.2
no aaa new-model
memory-size iomem 15
no ip domain lookup
ip cef
no ipv6 cef
key chain EIGRP-KEYS
key 1
 key-string cisco
!
!
redundancy
interface Loopback1
ip address 192.168.33.1 255.255.255.252
interface Loopback5
ip address 192.168.33.5 255.255.255.252
interface Loopback9
ip address 192.168.33.9 255.255.255.252
interface Loopback13
ip address 192.168.33.13 255.255.255.252
interface Embedded-Service-Engine0/0
```

```
no ip address
shutdown
interface GigabitEthernet0/0
ip address 192.168.3.1 255.255.255.0
duplex auto
speed auto
interface GigabitEthernet0/1
no ip address
shutdown
duplex auto
speed auto
interface Serial0/0/0
bandwidth 64
ip address 192.168.13.2 255.255.255.252
ip authentication mode eigrp 1 md5
ip authentication key-chain eigrp 1 EIGRP-KEYS
ip bandwidth-percent eigrp 1 40
ip hello-interval eigrp 1 60
ip hold-time eigrp 1 180
ip summary-address eigrp 1 192.168.33.0 255.255.255.240
clock rate 2000000
interface Serial0/0/1
ip address 192.168.23.2 255.255.255.252
ip authentication mode eigrp 1 md5
ip authentication key-chain eigrp 1 EIGRP-KEYS
ip summary-address eigrp 1 192.168.33.0 255.255.255.240
ip hello-interval eigrp 1 60
ip hold-time eigrp 1 180
ip summary-address eigrp 1 192.168.33.0 255.255.255.240
!
router eigrp 1
network 192.168.3.0
network 192.168.13.0 0.0.0.3
network 192.168.23.0 0.0.0.3
network 192.168.33.0 0.0.0.3
network 192.168.33.4 0.0.0.3
network 192.168.33.8 0.0.0.3
network 192.168.33.12 0.0.0.3
passive-interface GigabitEthernet0/0
ip forward-protocol nd
no ip http server
no ip http secure-server
```

```
control-plane
!
!
line con 0
password cisco
logging synchronous
login
line aux 0
line 2
no activation-character
no exec
transport preferred none
transport input all
transport output pad telnet rlogin lapb-ta mop udptn v120 ssh
stopbits 1
line vty 0 4
password cisco
login
transport input all
scheduler allocate 20000 1000
end
```