

# Chapter 2: Logical and Bit Operations and Integer Arithmetic

## Topics

- Logical Operations in C
  - &&, ||, and !
- Bit Shifting
  - << Left Shift
  - >> Right Shift (Logical and Arithmetic)
- Integer Representations
  - Unsigned and Two's Complement
- Integer Arithmetic and overflow

# Announcements

- **Data Lab is due Friday Sept 12 by 11:55 pm**
- **Recitation exercises #1 due next Monday 9/8**
  - hand in at your recitation
- **Extra TA office hours have been announced by email**
  - Thursdays 10:30-12:30 pm (Yogesh in CSEL)
  - Thursdays 3-5 pm (Pate in ECCS 123)
  - Fridays 10-12 noon (Abhishek in CSEL)
- **Essential that you read the textbook in detail & do the practice problems**
  - Read Chapter 2 (2.1-2.3)
  - Chapter 3 next week (3.1-3.11 and 3.13-3.14)

# Recap...

- **Byte ordering or Endianness – Little vs BigEndian**
  - Ints
  - Pointers
  - Characters
  - Strings
- **Boolean algebra on binary values**
  - &, |, ~, ^
  - Properties at times like but distinct from integer algebra
  - Applied to N-bit vectors or words
  - Contrast to logical operators &&, ||, !

# Logical vs Bitwise Operations in C

## • Logical Operators

- `&&` (AND), `||` (OR), `!` (NOT or “bang”)
  - View 0 as “False”
  - Anything nonzero as “True”
  - Always return 0 or 1
  - Early termination

## • Example code:

```
■ int x,y,z;  
....  
if( !((x==0) && (x>y)) || (z<256) ) {  
    ...  
    z = ~(x & y) | z;  
}
```

Each logical expression is either TRUE (1) or FALSE (0):

`(x==0)`  
`(x>y)`  
`((x==0) && (x>y))`  
`!((x==0) && (x>y))`  
`(z<256)`  
`!((x==0) && (x>y)) || (z<256)`

Compare to the bit-wise logical operations, where input, intermediate, and final values don't have to be 0 or 1

By the way, parentheses are your friend, and good programming practice

# Logical vs Bitwise Operations in C (2)

## Logical

- `!0x41` --> `0x00`
- `!0x00` --> `0x01`
- `!!0x41` --> `0x01`
- `0x69 && 0x55` --> `0x01`
- `0x69 || 0x55` --> `0x01`
- `p && *p` (avoids null pointer access)
  - \*p by itself could result in dereferencing a null pointer, causing an error, e.g. the line 'if (\*p)' will cause an error if p has not been set yet
  - So use 'if (p && \*p)', which first tests 'if p', and only if true (p is not null) will it proceed to the rest of the if test, i.e. try to dereference the pointer \*p

## Bitwise

- `~0x41` --> `0xBE`  
`~010000012` --> `101111102`
- `~0x00` --> `0xFF`  
`~000000002` --> `111111112`
- `0x69 & 0x55` --> `0x41`  
`011010012 & 010101012` -->  
`010000012`
- `0x69 | 0x55` --> `0x7D`  
`011010012 | 010101012` -->  
`011111012`

# Logical vs Bitwise Operations in C (3)

- Example code:

- int x,y;

- ...

- if (x) { ... do1(); ...}
  - if (!y) { ... do2(); ...}

This is shorthand for 'if (x!=0) {...}',  
So do1() is called only if x is non-zero,

- i.e. if x==1, then do1() is called,
- if x==137, do1() is called, ...
- if x==0, then do1() is not called.

do2() is called only if y is zero, i.e.  
This is equivalent to 'if (y==0) {...}'

- i.e. if y==0, then do2() is called,
- if y==1, then do2() is not called,
- if y==137, then do2() is not called...

# Shift Operations

Useful for multiplication and division by powers of 2


**Left Shift:**  $x \ll y$

- Shift bit-vector  $x$  left  $y$  positions
  - Throw away extra bits on left
  - Fill with 0's on right


**Right Shift:**  $x \gg y$

- Shift bit-vector  $x$  right  $y$  positions
  - Throw away extra bits on right
- Logical shift
  - Fill with 0's on left
- Arithmetic shift
  - Replicate most significant bit on left
  - Useful with two's complement integer representation

Example #1:  $x \ll 1$ ,  
left-shift by 1 bit



Example #2:  $y \gg 1$ ,  
right-shift by 1 bit



# Shift Operations

Useful for multiplication and division by powers of 2

**Left Shift:**  $x \ll y$

- Shift bit-vector  $x$  left  $y$  positions
  - Throw away extra bits on left
  - Fill with 0's on right

**Right Shift:**  $x \gg y$

- Shift bit-vector  $x$  right  $y$  positions
  - Throw away extra bits on right
- Logical shift
  - Fill with 0's on left
- Arithmetic shift
  - Replicate most significant bit on left
  - Useful with two's complement integer representation

Argument $x$	01100010
$\ll 3$	00010000
Log. $\gg 2$	00011000
Arith. $\gg 2$	00011000

Argument $x$	10100010
$\ll 3$	00010000
Log. $\gg 2$	00101000
Arith. $\gg 2$	11101000

# Shift Operations in C

- If your word x is signed, then it is not defined in C whether  $x \gg y$  will do an arithmetic or logical right shift on x
  - However, most implementations assume that a right shift on a signed quantity is an arithmetic right shift.
  - Example: If x is declared as an int, then ints are signed by default, so  $x \gg y$  should do an arithmetic right shift on x by y bits
- If your word is unsigned, then  $x \gg y$  will do a logical right shift on x
  - Example: If x is declared as an unsigned int, then  $x \gg y$  will do a logical right shift on x by y bits.

# Encoding Integers

- Signed and unsigned integers
- Let's start with unsigned integers, assuming only 4 bits (16 values):

$$\text{Decimal} = \sum_{i=0}^3 b_i * 2^i$$

bit in word corresponding to  $i$ 'th power of 2

For a  $w$ -bit word,

$$\text{Decimal} = \sum_{i=0}^{w-1} b_i * 2^i$$

- Book uses B2U for “Binary To Unsigned integer”

Unsigned 4-bit Integers	Decimal
1 1 1 1	15
1 1 1 0	14
1 1 0 1	13
1 1 0 0	12
1 0 1 1	11
1 0 1 0	10
1 0 0 1	9
1 0 0 0	8
0 1 1 1	7
0 1 1 0	6
0 1 0 1	5
0 1 0 0	4
0 0 1 1	3
0 0 1 0	2
0 0 0 1	1
0 0 0 0	0

$2^3 \quad 2^2 \quad 2^1 \quad 2^0$

# Representing Negative Integers?

- Simplest approach is to use the most significant bit as the sign bit: ‘1’ = negative, ‘0’ = positive
  - e.g. 0100 = +4, while 1100 = -4
  - This is called Sign-Magnitude
  - Unfortunately, this means we have both
    - a Positive Zero (0000 = +0) and
    - a Negative Zero (1000 = -0) !!!
  - This complicates integer arithmetic
- Another encoding approach: One’s complement

For a w-bit word,

$$\text{Decimal} = -b_{w-1} * (2^{w-1} - 1) + \sum_{i=0}^{w-2} b_i * 2^i$$

# Two's Complement

- Two's complement encodes signed integers (positive and negative)
- Easy to implement integer arithmetic with two's complement – unique zero
- Most significant (MS) bit is sign bit with weight  $-(2^{w-1})$ , i.e. -8 when  $w=4$  bits

**Example:** '1101'

$$= 1 * (-2^3) + 1 * 2^2 + 0 * 2^1 + 1 * 2^0 = -3$$

'1000' = -8, '1111' = -1 (not 15),  
zero is unique & zero

Signed 4-bit Integers

	sign	$-2^3$	$2^2$	$2^1$	$2^0$	Decimal
0	0	1	1	1	1	7
0	0	1	1	0	0	6
0	0	1	0	1	1	5
0	0	1	0	0	0	4
0	0	0	1	1	1	3
0	0	0	1	0	0	2
0	0	0	0	1	1	1
0	0	0	0	0	0	0
1	1	1	1	1	1	-1
1	1	1	1	0	0	-2
1	1	1	0	1	1	-3
1	1	1	0	0	0	-4
1	1	0	1	1	1	-5
1	1	0	1	0	0	-6
1	1	0	0	1	1	-7
1	1	0	0	0	0	-8

# Two's Complement

- Asymmetric range from -8 to +7
  - one more negative # than positive # !
- MS bit indicates sign
  - 1=>negative, 0=>non-negative

For a w-bit word,

$$\begin{aligned}\text{Decimal} = & -b_{w-1} * 2^{w-1} \text{ // MS sign Bit} \\ & + \sum_{i=0}^{w-2} b_i * 2^i \text{ // LS Bits}\end{aligned}$$

Book uses B2T for “Binary To Two’s Complement Integer”  
- 13 -

Signed 4-bit Integers

sign*( $-2^3$ )	$2^2$	$2^1$	$2^0$	Decimal
0	1	1	1	7
0	1	1	0	6
0	1	0	1	5
0	1	0	0	4
0	0	1	1	3
0	0	1	0	2
0	0	0	1	1
0	0	0	0	0
1	1	1	1	-1
1	1	1	0	-2
1	1	0	1	-3
1	1	0	0	-4
1	0	1	1	-5
1	0	1	0	-6
1	0	0	1	-7
1	0	0	0	-8

# Encoding Integers

## Unsigned

$$B2U(X) = \sum_{i=0}^{w-1} x_i \cdot 2^i$$

## Two's Complement

$$B2T(X) = -x_{w-1} \cdot 2^{w-1} + \sum_{i=0}^{w-2} x_i \cdot 2^i$$

```
short int x = 15213;
short int y = -15213;
```

- C short 2 bytes long

Most Significant Bit is in essence the Sign Bit

	Decimal	Hex	Binary
x	15213	3B 6D	00111011 01101101
y	-15213	C4 93	11000100 10010011

- For 2's complement, most significant bit indicates sign
  - 0 for nonnegative
  - 1 for negative
- Shortcut to get  $-x$  given  $x$ : complement  $x$  and add 1
  - i.e.  $-x = \sim x + 1$  in two's complement

# Encoding Example (Cont.)

<b>x =</b>	15213:	00111011	01101101
<b>y =</b>	-15213:	11000100	10010011

Weight	15213	-15213	
1	1	1	1
2	0	0	1
4	1	4	0
8	1	8	0
16	0	0	1
32	1	32	0
64	1	64	0
128	0	0	1
256	1	256	0
512	1	512	0
1024	0	0	1
2048	1	2048	0
4096	1	4096	0
8192	1	8192	0
16384	0	0	1
-32768	0	0	1
	<b>Sum</b>	<b>15213</b>	<b>-15213</b>

# Numeric Ranges

## Unsigned Values

- $U_{Min} = 0$   
000...0
- $U_{Max} = 2^w - 1$   
111...1

## Two's Complement Values

- $T_{Min} = -2^{w-1}$   
100...0
- $T_{Max} = 2^{w-1} - 1$   
011...1

## Other Values

- Minus 1  
111...1

## Values for $W = 16$

	Decimal	Hex	Binary
UMax	65535	FF FF	11111111 11111111
TMax	32767	7F FF	01111111 11111111
TMin	-32768	80 00	10000000 00000000
-1	-1	FF FF	11111111 11111111
0	0	00 00	00000000 00000000

unsigned  
two's complement  
both

# Values for Different Word Sizes

	W			
	8	16	32	64
UMax	255	65,535	4,294,967,295	18,446,744,073,709,551,615
TMax	127	32,767	2,147,483,647	9,223,372,036,854,775,807
TMin	-128	-32,768	-2,147,483,648	-9,223,372,036,854,775,808

## Observations

- $|TMin| = TMax + 1$ 
  - Asymmetric range
- $UMax = 2 * TMax + 1$

## C Programming

- `#include <limits.h>`
  - K&R App. B11
- Declares constants, e.g.,
  - `ULONG_MAX`
  - `LONG_MAX`
  - `LONG_MIN`
- Values platform-specific

# Unsigned Integer Addition

- **Example: 4-bit addition of 6 + 7**
  - Just as for decimal, there is a carry, e.g. 1 added to 1 causes a carry of a 1 to the next column
- **Example: 13 + 5**
  - Note that the last carry = 1 which shows that there is an overflow
- **How to detect overflow?**
  - See if the MS/final carry bit = 1

Decimal	Unsigned Binary
$\begin{array}{r} 1 \text{ (carry)} \\ 06 \\ +07 \\ \hline 13 \end{array}$	$\begin{array}{r} 110 \text{ (carry)} \\ 0110 \\ +0111 \\ \hline 1101 \end{array}$


Decimal	Unsigned Binary
$\begin{array}{r} 0 \text{ (carry)} \\ 13 \\ +05 \\ \hline 18 \end{array}$	$\begin{array}{r} 1101 \text{ (carry)} \\ 1101 \\ +0101 \\ \hline 10010 \end{array}$ = 2! (ignoring carry)

# Unsigned Modular Addition

Operands:  $w$  bits

True Sum:  $w+1$  bits

Discard Carry:  $w$  bits



## Standard Addition Function

- Ignores carry output

## Implements Modular Arithmetic

$$s = \text{UAdd}_w(u, v) = (u + v) \bmod 2^w$$


$$\text{UAdd}_w(u, v) = \begin{cases} u + v & u + v < 2^w \\ u + v - 2^w & u + v \geq 2^w \end{cases}$$

# Visualizing Ideal Integer Addition

## Integer Addition

- 4-bit integers  $u, v$
- Compute true sum  $\text{Add}_4(u, v)$
- Values increase linearly with  $u$  and  $v$
- Forms planar surface
- With 4-bit integers, the true sum could require 5 bits

$\text{Add}_4(u, v)$




# Visualizing Unsigned Modular Addition


## Wraps Around

- If true sum  $\geq 2^w$
- At most once

### True Sum



### Overflow



Example: '1111' + '0001' = '0000'!

# Two's Complement Addition

- Similar to unsigned addition with the carry rules
  - 1 added to 1 causes a carry of a 1 to the next column
- Note, here the final carry does not necessarily indicate overflow
  - In all examples, just the 4-bit result is correct, regardless of the carry
- In Two's complement, subtraction is same operation as addition!

Decimal	Signed Binary
$\begin{array}{r} -2 \\ +3 \\ \hline 1 \end{array}$	$\begin{array}{r} 1110 \text{ (carry)} \\ 1110 \\ +0011 \\ \hline 0001 \end{array}$
$\begin{array}{r} -5 \\ +3 \\ \hline -2 \end{array}$	$\begin{array}{r} 011 \text{ (carry)} \\ 1011 \\ +0011 \\ \hline 1110 \end{array}$
$\begin{array}{r} -4 \\ -3 \\ \hline -7 \end{array}$	$\begin{array}{r} 1100 \text{ (carry)} \\ 1100 \\ +1101 \\ \hline 1001 \end{array}$

# Two's Complement Overflow

- **Example:  $6 + 3$** 
  - Overflows the maximum positive value for 4-bit two's complement (+7)
- **Example:  $-7 - 3$** 
  - Overflows the maximum negative value for 4-bit two's complement (-8)
- **How to detect overflow?**
  - If the sign of the operands are the same and the sum is the *opposite* sign, then there is overflow in two's complement signed addition
  - In both examples, both operands are + or -, but the sum is the opposite sign


Decimal	Signed Binary
$\begin{array}{r} 6 \\ +3 \\ \hline 9 \end{array}$	$\begin{array}{r} 110 \text{ (carry)} \\ 0110 \\ +0011 \\ \hline 1001 \end{array}$ =-7 (Two's C)
$\begin{array}{r} -7 \\ -3 \\ \hline -10 \end{array}$	$\begin{array}{r} 1001 \text{ (carry)} \\ 1001 \\ +1101 \\ \hline 0110 \end{array}$ =+6 (Two's C)

# Two's Complement Modular Addition

Operands:  $w$  bits

True Sum:  $w+1$  bits

Discard Carry:  $w$  bits



## TAdd and UAdd have Identical Bit-Level Behavior

- Signed vs. unsigned addition in C:

```
int s, t, u, v;
```

```
s = (int) ((unsigned) u + (unsigned) v);
```

```
t = u + v
```

- Will give  $s == t$

Unsigned add UAdd

Signed add TAdd


# Visualizing Two's Complement Signed Addition

## Values

- 4-bit two's comp.
- Range from -8 to +7

## Wraps Around



- If  $\text{sum} \geq 2^{w-1}$ 
  - Becomes negative
  - At most once
- If  $\text{sum} < -2^{w-1}$ 
  - Becomes positive
  - At most once



# Characterizing TAdd

## Functionality

- True sum requires  $w+1$  bits
- Drop off carry bit
- Treat remaining bits as 2's comp. integer



$$TAdd_w(u, v) = \begin{cases} u + v + 2^w & u + v < TMin_w \text{ (NegOver)} \\ u + v & TMin_w \leq u + v \leq TMax_w \\ u + v - 2^w & TMax_w < u + v \text{ (PosOver)} \end{cases}$$

# Detecting 2's Comp. Overflow


## Task

- Given  $s = \text{TAdd}_w(u, v)$
- Determine if  $s = \text{Add}_w(u, v)$
- Example

```
int s, u, v;  
s = u + v;
```

## Claim

- Overflow iff either:
  - $u, v < 0, s \geq 0$  (NegOver)
  - $u, v \geq 0, s < 0$  (PosOver)



# **Supplementary Slides**

# C Puzzles - practice

- Taken from old exams
- Assume machine with 32 bit word size, two's complement integers
- For each of the following C expressions, either:
  - Argue that is true for all argument values
  - Give example where not true

## Initialization

```
int x = foo();  
  
int y = bar();  
  
unsigned ux = x;  
  
unsigned uy = y;
```

- $x < 0 \Rightarrow ((x*2) < 0)$
- $ux \geq 0$
- $x \& 7 == 7 \Rightarrow (x << 30) < 0$
- $ux > -1$
- $x > y \Rightarrow -x < -y$
- $x * x \geq 0$
- $x > 0 \&& y > 0 \Rightarrow x + y > 0$
- $x \geq 0 \Rightarrow -x \leq 0$
- $x \leq 0 \Rightarrow -x \geq 0$

# C Puzzle Answers

- Assume machine with 32 bit word size, two's comp. integers
- $TMin$  makes a good counterexample in many cases

<input type="checkbox"/> $x < 0$	$\Rightarrow$	$((x*2) < 0)$	<b>False:</b> $TMin$
<input type="checkbox"/> $ux \geq 0$			<b>True:</b> $0 = UMin$
<input type="checkbox"/> $x \& 7 == 7$	$\Rightarrow$	$(x << 30) < 0$	<b>True:</b> $x_1 = 1$
<input type="checkbox"/> $ux > -1$			<b>False:</b> 0
<input type="checkbox"/> $x > y$	$\Rightarrow$	$-x < -y$	<b>False:</b> $-1, TMin$
<input type="checkbox"/> $x * x \geq 0$			<b>False:</b> 30426
<input type="checkbox"/> $x > 0 \&& y > 0$	$\Rightarrow$	$x + y > 0$	<b>False:</b> $TMax, TMax$
<input type="checkbox"/> $x \geq 0$	$\Rightarrow$	$-x \leq 0$	<b>True:</b> $-TMax < 0$
<input type="checkbox"/> $x \leq 0$	$\Rightarrow$	$-x \geq 0$	<b>False:</b> $TMin$

# Two's Complement Shortcuts: Negation

**Claim: Following Holds for 2's Complement**

$$\sim x + 1 == -x$$

## Complement

- Observation:  $\sim x + x == 1111\dots11_2 == -1$

$$\begin{array}{r} x \boxed{1} \boxed{0} \boxed{0} \boxed{1} \boxed{1} \boxed{1} \boxed{0} \\ + \quad \sim x \boxed{0} \boxed{1} \boxed{1} \boxed{0} \boxed{0} \boxed{0} \boxed{1} \\ \hline -1 \boxed{1} \boxed{1} \boxed{1} \boxed{1} \boxed{1} \boxed{1} \boxed{1} \end{array}$$

## Increment

- $\sim x + \cancel{x} + \cancel{(-x + 1)} == \cancel{-1} + \cancel{(-x + 1)}$
- $\sim x + 1 == -x$

**Warning: Be cautious treating int's as integers**

# Negation == Complement then Increment

$x = 15213$

	Decimal	Hex	Binary
$x$	15213	3B 6D	00111011 01101101
$\sim x$	-15214	C4 92	11000100 10010010
$\sim x + 1$	-15213	C4 93	11000100 1001001 <b>1</b>
$y$	-15213	C4 93	11000100 10010011

0

	Decimal	Hex	Binary
0	0	00 00	00000000 00000000
$\sim 0$	-1	FF FF	11111111 11111111
$\sim 0 + 1$	0	00 00	00000000 00000000

# Two's Complement Shortcuts: Negation (2)

- Another way to calculate  $-x$  from  $x$  in Two's Complement:
  - Write decimal  $x$  in binary.
  - start at the LS bit of  $x$ , copying all zeros to  $y$  until first 1 is reached; copy that 1, and then flip all the remaining bits and copy them to  $y$ . Then  $y = -x$ .
  - For example:  $60 = 00111100_2$ . To calculate  $-60$ , copy all zeros to the right of the first 1, so  $y = 100_2$ . Then, flip all other bits and copy to  $y$ , so  $y = 11000100_2 = -128 + 64 + 4 = -60$ .