# ecalj manual

https://github.com/tkotani/ecalj

# February 23, 2015

### Abstract

An all-electron full-potential electronic structure calculation package available freely. This is based on the formulation in Refs. [Kotani et al.(2015)Kotani, Kino, and Akai] and [Kotani(2014)] (See Kotani2114QSGWinPMT.pdf and KotaniKinoAkai2015FormulationPMT.pdf at ecalj/Document/Manual/). In ecalj , we can do QSGW and related calculations based on the PMT=LAPW+LMTO method. To get minimum usage for ecalj, need to read up to Section .5 or Sec.6. (We can generate model Hamiltonian thru Wannier functions; not documented well yet...)

Be careful. This document still contain many bugs... We need your help on this manual.

#### Requirement

To support of our ecalj activity, we need your acknowledgment to **ecalj** in your publications in the manner shown in ecalj/README.md;

https://github.com/tkotani/ecalj/#we-need-acknowledgment-as such as:

- [1] ecalj package at https://github.com/tkotani/ecalj/. Its one-body part is developed based on Ref.[2].
- [2] LMsuit package at http://www.lmsuite.org/. Its GW part is adopted mainly from Ref.[1].

(as in the same manner of usual papers).

### Relation with LM suit at http://www.lmsuite.org/:

There is a full potential LMTO package (with a slightly different implementation of PMT) contained in **lmsuit**. In the package, there is the driver to use a modified version of the GW code in **ecalj** (GW part in **ecalj** is occasionally adopted in **lmsuit**). The FP-LMTO in **lmsuit** and **ecalj** have some similarities (for input files and outputs). Thus some part of its document in the web site is still applicable even to the ecalj package.

### Contributions

Main contributors to the ecalj package are (only a list of people who directly related to the code developments):

T.Kotani, Hiori Kino, Mark van Schilfggarde, Sergey Faleev, Takashi Miyake,

Seungwoo Jang, Manabu Usuda. They also contribute to this documents.

T.Kotani learned the LMTO-ASA-GW code by F.Aryasetiawan, which is on top of the Stuttgart's LMTO-ASA, mainly by van Schilfgarrde under O. Jepsen and O. K. Andersen

http://www2.fkf.mpg.de/andersen/LMTODOC/LMTODOC.html. FP-LMTO part is originally given by M.Methfessel, Mark van Schilfgaarde and their collaborators.

# Contents

1	Introduction								
	1.1 Uniqueness of the ecalj package	5							
	1.1.1 What do we expect for QSGW?	6							
	1.2 Rule in this manual	7							
	1.3 What can we do with the ecalj package?	7							
2	T 4 11								
2	Install           2.1 Binaries and Scripts	8							
	*	8							
	2.2 tests	8 9							
	2.5 Directory Structure	9							
3	LDA/GGA calculations and Plots	10							
	3.1 Write crystal structure file, ctrls $\dots \dots \dots \dots \dots \dots \dots$	10							
	3.2 Generate default ctrl from ctrls by ctrlgenM1.py	13							
	3.3 crystal structure checker: lmchk	13							
	3.4 ctrl file	14							
	3.5 Run LDA/GGA calculations, and get convergence $\ \ldots \ \ldots \ \ldots \ \ldots$	14							
	3.6 DOS, Band, PDOS plot	15							
	3.7 Useful samples: ecalj/MATERIAL/	17							
	3.8 How to add spin-orbit coupling?	18							
4	How to run QSGW calculation?	19							
4	4.1 GWinput	20							
	4.2 Run gwsc script	21							
	T.2 Ittill gwsc script	21							
5	gwsc script to perform QSGW	24							
	5.1 outputs of <b>gwsc</b>	24							
	5.2 Preparation stage of gwsc	25							
	5.3 Main stage of gwsc	25							
	5.4 Other functions (or scripsts)	26							
6	Cautions for usage	27							
•	6.1 lmf –help	32							
		-							
7	Wannier function	32							
	7.1 lwmatK1 and lwmatK2	33							
8	ctrl file details	33							
0	8.1 How to set local orbitals	36							
	0.1 110 0 00 100 100 100 100 100 100 100								
9	GWinput details								
	9.1 generate a templete of GWinput	39							
	9.2 overview of GWinput	39							
	9.3 General section	41							
	9.4 < QPNT> section	44							
	9.5 $$ set QPNT for eps mode (QforEPS section) $$	46							
	9.6 <product_basis> section</product_basis>	47							
	9.7 ANFcond (we can skip here since we do not check this option now. Need fix this if n	ecessary. 49							
10	Main Output Files of GW part	51							
	10.1 QPU	51							
	10.2 XCU	51							
	10.3 SEXU	51							
	10.4 SEXcoreU	51							
	10.5 SECU	52							
	10.6 TOTE UP (TOTE DN)	52							

	10.7 TOTE2.UP (TOTE2.DN)	
	$10.8 \ DOSACC.Ida \ldots \ldots$	
	10.9 DOSACC2.lda	
	10.10Core_ibas*_l*.chk	
	10.11VXCFP.chk	
	10.12The Fermi energies in this $GW$ code	52
11	mkGWIN_lmf2 and its I/O Files	54
	11.1 echo 0 lmfgw	54
	11.2 gwinit	54
	11.3 echo -100 $ qg4gw$	55
12	gwsc script and its I/O Files	56
	12.1 echo 0  lmfgw si	57
	12.2 echo 1 qg4gw	57
	12.3 echo 1 lmfgw si	57
	12.4 lmf2gw	58
	12.5 rdata4gw_v2	58
	12.6 echo 1 heftet	59
	12.7 hchknw	59
	12.8 echo 3 hbasfp0	59
	12.9 echo 0 hvccfp0	60
	12.10echo 3 hsfp0	60
	12.11echo 0 hsfp0	60
	12.12echo 1 hsfp0	60
	12.13echo 11 hx0fp0	60
	12.14echo 12 hsfp0	61
	12.15echo 0 hqpe	61
13	Check list for convergence on GW calculaitons	62
14	Linear response calculations	64
	14.1 eps_lmfh, epsPP_lmfh: the dielectric functions	
	14.2 epsPP_lmfh: the dielectric function(No LFC—faster)	65
	14.3 How to calculate correct dielectric function?	65
15	Used files	71
тэ	15.1 @MNLA_CPHI	. –
	15.2 CPHI and GEIG	
	10.4 Of the and Othors	( L

# $\bullet \mathbf{Reference}$

# 1 Introduction

The **ecalj** is an first-principles electronic-structure calculations package with some unique features. With **ecalj**, we can do not only standard calculations (LDA/GGA/LDA+U, relaxiation of atomic positions), but also the quasiparticle self-consistent GW calculations(QSGW), linear responses (charge and spin), Wannier functions (and U of them).

This is base on an unique one-body problem solver, the PMT method (=the Linearized APW+MTO method) [Kotani <u>et al.</u>(2015)Kotani, Kino, and Akai]. Thus we identify the QSGW method implemented in **ecalj** as the PMT-QSGW method. Introduction to the PMT-QSGW is given in Sec.1.1. Today "QSGW" is accepted as a standard procedure in the electronic structure calculations [?].

First, see README.md shown at https://github.com/tkotani/ecalj (or ecalj/README.md in the package). Free to download ecalj package from it, and use it. The QSGW code is version controlled by git.

The ecalj is related to a FP-LMTO package lmv7 seen at http://titus.phy.qub.ac.uk/packages/LMTO/fp.html. The lmv7 and ecalj are branched off at year 2009. After branched, main contributions are due to T.Kotani and Hiori Kino (NIMS) until now. We added new features: simple install and test; all codes are in f90 (no C compilar); new methods, especially PMT-QSGW; MPI parallelization for QSGW; simple usage with automatic setting of default files by python ver2; a small tool to convert VASP POSCASR to ecalj, and so on. PMT-QSGW shows more stable convergence than the previous version, FP-LMTO-GW <sup>1</sup>.

One-body part (PMT part), based on [Kotani et al.(2015)Kotani, Kino, and Akai] We can perform standard calculations such as LDA,GGA,LDA+U, atomic position relaxiation, and so on. In addition, the PMT part has an interface to perform GW (and QSGW) calculation: the one-body part can include a given non-local exchange-correlation potential stored in a file sigm.\*. The QSGW calculation is performed by a script gwsc, which has an iteration loop calling the one-body program (lmf) and many-body part (GW part) altenatively. The many-body part generate the file sigm.\*. See Fig.6 and around.

### Many-body part (GW part), based on [Kotani(2014)]

As the inputs for the GW calculation, we have to supply the eigenfunctions and the eigenvalues from the one-body part to the GW part. The eigenfuncions re-expanded by the two types of basis functions, the atomic-like argumentation functions in the muffin-tin(MT) spheres, and the plane-waves in the interstitial region, say, the interstitial plane-wave (IPW) hereafter. IPW is defined as the usual plane waves in the interstitial region, but zero within MTs'. The IPW+"atomic like functions within MTs" make 'a basis set to expand eigenfunctions'. See Eq.(17) of [Kotani(2014)].

We need another basis set to expand "product of eigenfuncions". That is, the mixed product bases (MPB)

[Kotani and van Schilfgaarde(2002), Friedrich <u>et al.</u>(2012)Friedrich, Betzinger, Schlipf, Blügel, and Schindlmayr], which consists of the two kinds of bases (caution: do not mixed up with the basis set for eigenfunctions); (i)the local atom-centered functions confined to MT spheres, so-called the product basis; (ii) IPW. The product-basis are calculated from products of solutions to the Schrödinger equation within the MT sphere. The Coulomb matrix v, the dynamically scened Coulomb interaction W, and so on, are expanded in the MPB. It can virtually span all the space made of product of eigenfunctions (but, in practical calculations, we need to reduce the size of the

<sup>&</sup>lt;sup>1</sup>In cases to treat magnetic systems which have intrinsic magnetic fluctuations, we may need to be careful about initial condition or mixing procedure to get convergence. In cases, we need to start from LDA+U results as initial condition from which we start QSGW. Let me know about such trouble.

space to reduce computational time). We include full energy-dependence of W. See Sec.3 of [Kotani(2014)].

Recently T.Kotani includes the Wannier function generator, which was originally developed by T.Miyake and H.Kino on top of previous version of GW part. Thus the Wannier functions (including effective interactions) can be generated in the PMT-QSGW.

# 1.1 Uniqueness of the ecalj package.

We will explain two unique points of ecalj .

### PMT:

Central part in an electronic structure packages is one-body problem solver. It means how to calculate eigenvalues/eigenfunctions for a given one-body potential. Inversely, we have to generate new one-body potential for given eigenfunctions/eigenvalues based on the density functional theory (DFT) in the LDA or GGA (In the followings, LDA means both of LDA and GGA). Then we can make the electron density self-consistent by iterations until converged, and obtain total energy of ground states. Then we can calculate atomic forces by perturbation. Based on such an one-body problem solver, we can implement kinds of methods; e.g, dielectric function, magnetic susceptibility, transport and so on. Furthermore, we can implement higher-level approximations such as the QSGW method explained below. An one-body problem solver (in linear methods) are characterized by

- (i) linear combinations of what basis set to represent eigenfunctions;
- (ii) how to represent electron density and one-body potential.

In ecalj, we use the PMT method [Kotani et al. (2015) Kotani, Kino, and Akai, Kotani and van Schilfgaarde (2010)] as the one-body problem solver. The PMT method is a new all-electron full potential method. It uses not only the augmented plane waves (APW) but also the muffin-tin orbitals (MTO) together, in addition to the local orbital (lo), to represent the eigenfunctions (no other methods use two kinds of augmented waves together). Thus eigenfunctions are expansed in the linear combinations of the APWs, MTOs, and the lo's. For electron density and the one-body potential, they are given by the three components representation. That is, the electron density (one-body potential) is divided into three components,

"smooth part + onsite muffin-tin (MT) part - counter part".

Here the counter part is in order to remove smooth part within MTs. This formalism (Soler-Williams formalism) is also used in the projected augmented wave (PAW) method [Soler and Williams(1989), Soler and Williams(1990)].

We now usually use highly localized MTOs together with APWs of low energy cutoff (3  $\sim$  4 Ry).<sup>2</sup> I think this is promising not only for efficient DFT/QSGW scheme, but also for kinds of applications in future. The MTOs can play a role of the Wannier functions.

#### QSGW:

In ecalj , we can perform the GW calculation. The usual GW approximation is so-called "one-shot GW" starting from LDA. It usually only calculates differences between the quasiparticle energies (QPEs) and the LDA eigenvalues by a perturbation (only diagonal part of self energy for the LDA eigenfunctions). Its ability is limited; it may fail when its starting point (eigenfunctions and eigenvalues supplied by LDA) is problematic. This is the reason whey we originally develope the QSGW method. The QSGW now becomes popular and taken as a possible candidate to go beyond current limieation of such GW and LDA/GGA [Bruneval and Gatti(2014)]. In principle, results given by QSGW do not depend on LDA anymore; the LDA are only used to prepare initial condition for self-consistency iteration cycle of the QSGW calculation <sup>3</sup>.

Usually the QPEs obtained by QSGW reproduce experiments better than LDA. For example, the band gap by GGA for GaAs is about 0.5 eV in contrast to the experimental value of

 $<sup>^{2}</sup>$  current implementation have not yet efficiently use this locality; this must allow us to speed up one-body problem solver.

<sup>&</sup>lt;sup>3</sup>Exactly speaking, we use LDA idea for efficient implementation of QSGW; thus obtained results are slightly dependent on the choice of LDA or GGA

 $1.69~{\rm eV}$  <sup>4</sup> On the other hand, the QSGW predicts about  $1.8\sim 1.9{\rm eV}$ , a few tenth of eV larger than experiment (for practical use, we sometimes use "hybrid functional between QSGW and LDA" so as to obtain smaller band gap). Even in the case of NiO and so on, the QSGW gives reasonable results (there is a tendency to give a little larger band gaps than experiments). This is in contrast to the case of the one-shot GW applied to NiO, where we can not have good agreement with experiments because the stating points in LDA is problematic.

The **ecalj** have other functions. LDA+U, atomic forces and relaxation (in GGA/LDA), core level spectroscopy and so on. In addition, we can calculate dielectric functions and magnetic responses from QPEs and the quasiparticle eigenfunctions given by LDA/QSGW. But total energy in QSGW is still in research (shown total energies in QSGW calculations are dummy now).

The QSGW calculations are very time-consuming; roughly speaking, it takes 10 or more times expensive than usual one-shot GW (although we can reduce computational time by choosing computational conditions). Thus the size of systems which we can treat is limited to ten atom in a cell or something, say, with a node of 16 cores; computation may require a week or so to have reasonable convergence. (heavy atoms require longer computational efforts, light atoms faster; non-magnetic systems are easier. We still have much room to accelerate the method, but not have done yet so much. Minimum MPI parallelization is implemented). The computational effort is  $\propto N^4$  in the most time-consuming part of QSGW.

### 1.1.1 What do we expect for QSGW?

Let us recall hybrid functionals such as B3LYP, and LDA+U. In hybrid functional methods, we use  $Vxc = (1-\alpha)*LDA+\alpha*(Fock exchange like term)$ , where  $\alpha$  is taken to be  $\sim 0.25$  usually <sup>5</sup>. The  $\alpha$  can be dependent on materials; for metals  $\alpha$  should be almost zero. For larger band gap insulator,  $\alpha$  becomes larger. <sup>6</sup> Despite of success of the functional, its ability is limited. For example, it is known that a hybrid functionals fail to describe metals such as bcc Fe. On the other hand, we have LDA+U method which succeeded to describe materials including localized electrons. However, it contains kinds of ambiguity and U is chosen by hand. The important part of the hybrid functional methods and LDA+U is the non-local potential. It is missing in the DFT. As we discussed above, they give some success but not satisfactory. We somehow need to have a method to determine high-quality non-local potential (a substitution of the exchange-correlation potential). It is the QSGW method.

Note two important aspects of non-local potential (missing character in the local potential used in DFT). One is the onsite non-locality; it is also taken into account by LDA+U model. However, note that relative shift of O(2p) band with respect to the center of 3d band is not in LDA+U. The other is the off-site non-locality (mainly between nearest neighbors), which may relate to LUMO-HOMO gap. A non-local potential can behave a projector which push down only the HOMO states (valence band) to lower energy. This can be in the hybrid functional but not in LDA+U.

In the QSGW, we determine such a non-local potential with the calculation of the GW method, in a self-consistent manner (we repeat GW calculations until converged). We can expect QSGW much more than hybrid methods/LDA+U. Very roughly speaking, because the QSGW automatically determine U of LDA+U, or alpha of the hybrid functionals. More accurately speaking, we determine not only  $G_0$  but also W (the screened Coulomb interaction) self-consistently. Here W corresponds to U and alpha. Thus QSGW gives reasonable results even if it is applied to metals such as Fe. For systems with metallic screening, it gives small non-locality (results are close to those of LDA). For systems with large band gap, QSGW gives large enough non-locality (like 0.25\*(Fock exchange)).

Since we now need to treat complex systems, e.g, metal on insulator, it is very essential to treat kinds of materials on a same footing.

<sup>&</sup>lt;sup>4</sup>We undo electron-phonon effect (0.06eV) and spin-orbit effect (0.11eV) from the true the experimental value 1.52 eV.

<sup>&</sup>lt;sup>5</sup>exactly speaking, we have range cutoff for Fock exchange term in the HSE funcional in addition

<sup>&</sup>lt;sup>6</sup>If you use  $\alpha = 1$  (Hartree-Fock limit), the band gap of Si becomes 20eV or something.

The main purpose of QSGW is to determine an one-particle effective Hamiltonian  $H^0$ , which describes the quasiparticle picture (or independent-particle picture) for the system we calculate. In other words, QSGW divide full many-body Hamiltonian H into  $H = H^0 + (H - H^0)$ . The screened Coulomb interaction W is determined self-consistently in the QSGW iteration cycle.

In comparison with LDA, we see differences;

- Band gap. QSGW tends to give slightly larger than experiments. It looks systematic.
- Band width. Usually, sp bands are enlarged (except very low density case such as Na).
   This is the case for homogeneous electron gas. As for localized bands like 3d electrons, they can be narrowed.
- Relative position of bands. e.g. O(2p) v.s. Ni(3d). More localized bands tends to get more deeper. Exchange splitting between up and down (like LDA+U) get larger. In cases such as NiO, magnetic moment become larger; closer to experimental values.
- Hybridization of 3d bands with others. QSGW tends to make eigenfunctions localized. However, reality is complexed, and not so simple in cases.

### 1.2 Rule in this manual

- This font is for executable file(program) or shell scripts.
- echo 3|hbasfp0 means doing hbasfp0 with the argument '3' supplied as the standard input (read(\*,\*) in fortran).
- This font is for files, directories, contents of files, or variables used in codes.
- ctrl.si,rst.si and so on mean the case of Si. You may need to replace the extention si for your case. (this extention is given by user. Lower case, number, and underscore [a-z0-9\_] are allowed.) In the followings, ctrl.\* means a file wish such an extension.
- There are files named foobarU and foobarD, which are for up spin (isp=1) and for down spin(isp=2), respectively; for example, SEXU and SEXD. We sometimes use foobarU to denote foobarU and foobarD together.
- k vector in the Brillowin zone is called as q or k.

# 1.3 What can we do with the ecali package?

At Feb.2015, what we can do is as follow. We have limited parallelization. (e.g. k point parallel).

- LDA/GGA LDA+U, calculations, atomic forces and relaxiation. Spin-orbit is included only for colinear spin-density cases.
- Quasi-particle(QP) energy in the 1st-itteration from LDA. (one-shot GW)
   Make band plot for LDA and the QP energies.
- Spectrum function of the self-energy  $\Sigma$ . Life time (imaginary part) of QPs.
- Dielectric function, and its inverse. (including local-field effect or not).
- QP self-consistent GW(QSGW)
- magnetic susceptibility.
- $\bullet$  Wannier function. (not only one-body part, but also effective interaction W and cRPA)

<sup>&</sup>lt;sup>7</sup>people often pronounce this "H-naught"

# 2 Install

Install and minimum tests are easy; even in a note PC, e.g., we can use gfortran in Ubuntu 14.04 on Thinkpad T420s for a test purpose. For productive runs, we may need multicores. Current implementation for parallelization by MPI is limited (not so much especially for the dielectric function part yet). Thus, probably, it may be not so efficient to use too many cores.

Follow the instruction of ecalj/README.md.

or we can see the same one at https://github.com/tkotani/ecalj/#install-and-test. We have a script ecalj/InsallAll.ifort and so on. This command installs ecalj and run a series of install tests automatically.

# 2.1 Binaries and Scripts

Binary and Scripts contained in ecalj are

#### • ctrlgenM1.py

Generate default input file ctrl.\* from the structure file ctrls.\*. The latter file only contains information of crystal structure.

#### • lmfa

Sphecial atom calculation as initial condition, and core charge

#### lmchk

Check atomic positions, crystal symmetry, and computational conditions.

- lmf and lmf-MPIK LDA/GGA,LDA+U calculations. (or we can use Vxc in QSGW instead). We mainly use lmf-MPI (k-parallel version) instead of lmf.
- PROCAR mode of lmf: Fat band mode.

```
mpirun -np 4 lmf-MPIK --mkprocar --band:fn=syml mgo gives PROCAR (Try an example /ecalj/MATERIALS/MgO_PROCAR/. Run ./job at the directory).
```

#### • gwsc

QSGW calculation

• job\_band\_nspin1,job\_band\_nspin2,job\_fermisurface,job\_tdos,job\_pdos band, fermi surface, tdos, pdos plot.

## • epsPP\_lmfh

Dielectric function without local field correction (LFC).

### • eps\_lmfh

Dielectric function with LFC

### $\bullet$ epsPP\_lmfh\_chipm

Non-interacting transverse spin polarization.

### • gw\_lmfh

One-shot GW calculation. This also show life-time of QPs (QPU\_lmf). (we need make it paralellized...)

### • genMLWF

Wannier functions and matrix elements of W on it. A implementation of cRPA included.

#### dqpu

A small python script to compare QPU.\* files (eigenvalues are compared) numerially. (Seungwoo say it cause "index error"; Need to fix dqpu if something strange).

#### 2.2 tests


Install.ifort run tests at ecalj/TestInstall.

In the following, si:gw\_lmfh means '>make si\_gw\_lmfh' at ecalj/TestInstall/; this test is performed with the Makefile at the directory.

si:gw\_lmfh/ Results: QPU
si:gwsc/ : QPU,log.si
gas:gwsc/ : QPU,log.gas

(These are just samples; not for practical calculaitons)

# 2.3 Directory structure



# 3 LDA/GGA calculations and Plots

Calculations are performed by following steps. These steps are detailed in the following subsections.

To identify a set of files used for a material we calculate, we use an extension to files. For example, files explained below are with extensions (only lower case allowed) of materials. For example, ctrls.cu and ctrl.cu. In this case cu is the extension. Any extension works. Other possible examples are ctrls.lagao3, ctrl.wgantest1, and so on.

- Write crystal structure file ctrls.\*, which contains crystal structure. It can be by hand, or convert it from POSCAR (in VASP). There is a tool to convert between POSCAR and ctrls.\* (See ecalj/StructureTool/README.txt for the tool. we have vasp2ctrl and ctrl2vasp. xxx Need to explain more xxx.)
- 2. Generate ctrl.\* from ctrls.\* by a script ctrlgenM1.py, <sup>8</sup>
  Here ctrl.\* is the main control file which contains all required information to perform calculations. ctrl.\* contains not only the content of ctrls.\*, but also other informations needed for calculations. If necessary, we edit the generated ctrl.\* file before next step.
- 3. Check crystal structure. **lmchk** is to confirm the crystal structure (space-group symmetry and so on). **lmchk** is applied not to ctrls.\* but to ctrl.\* . ctrls.\* never used in the following steps.
  - **CAUTION for a known bug!** : If a crystal structure is only slightly different from a structure with higher symmetry, the **lmchk** may give a wrong crystal symmetry. In such a case, you have to "standarize structure" by VESTA or some other tools. This occures e.g., when we use a structure numerically relaxed by VASP.
- 4. Run lmfa (calculations of spherical atoms (MT sites) in the cell). It also calculates core eigenfunctions and valence electron charge to set up initial condition. Then we run main calculation of LDA by lmf. It repeats iterations, and end up with converged results in LDA. Main result (electron density satisfying self-consistency) is stored in restart file rst.\* (binary file). It finished within a second.
- 5. Run LDA/GGA calculations. We can run the LDA/GGA calculation by **lmf** or **lmf**-MPIK (-MPIK meand kpoint parelell version).
- 6. Post processing.

Plot energy band, DOS, PDOS, by running scripts. We can use scripts **job\_band\_nspin1** or **job\_band\_nspin2** for band plot (need **syml.si** file (symmetry line for band plot)). We also have **job\_pdos**, **job\_tdos**, **job\_fermi** and so on for DOS, PDOS, fermi surfaces. Since we use gnuplot to plot them, meanings of obtained data is apparently clear.

# 3.1 Write crystal structure file, ctrls

Let me show some samples of crystal structure files  $\mathsf{ctrls.*}$  .

<sup>&</sup>lt;sup>8</sup>ctrlgenM1.py exists originally at ecalj/lm7K/ (ctrlgenM1.py was alreaday copied to your BINDIR= defined in ecalj/Install.ifort in the installation).

```
ALAT={a}
             PLAT=0 0.5 0.5 0.5 0.5 0.5 0.5 0
        SITE
             ATOM=Ga POS=0.0 0.0 0.0
             ATOM=As POS=0.25 0.25 0.25
        -----to here -----
{\bf SrTiO3:} \ {\tt ecalj/lm7K/TESTsamples/SrTiO3/ctrls.srtio3}
        -----from here ------
        %const da=0 au=0.529177
        %const d0=1.95/au a0=2*d0 v=a0^3 a1=v^(1/3)
        HEADER SrTiO3 cubic
        STRUC
               ALAT={a1} DALAT={da}
               PLAT=1 0 0 0 1 0 0 0 1
        SITE
              ATOM=Sr POS=1/2 1/2 1/2
              ATOM=Ti POS= 0
              ATOM=O POS=1/2 O
              ATOM=0 POS= 0 1/2 0
              ATOM=0 POS= 0 0 1/2
        -----to here ------
```

Lines starting from '#' are neglected as comment lines. Lines starting from '% const' define variables and set values (in these cases, da, alat, and bohr, and so on). Then the variable alat is referred to as {alat}; in the cu case, {alat} means 6.798. Lines not start from "#" nor "%" are main content in ctrls.\* . 9

Note that we have two tags of "categories" "STRUC" and "SITE". ("HEADER" tag is also; but it is just for user's memo shown in console output). These tags should start from the first column. Thus ctrls.\* is divided into multiple "categories". In a category, we have "tokens" such as ALAT, DLAT, PLAT. These under STRUC category. ALAT+DALAT specify unit of length in this ctrl file. These are in a.u. (= bohr radius=0.529177Å).

The unit cell is given by PLAT (as noted, ALAT+DALAT as unit). In the above example of GaAs, three primitive cell vectors specified by nine numbers after PLAT=; they give three primitive vectors; PLAT1=(0,0,0.5), PLAT2=(0.5, 0.0, 0.5), and PLAT3=(0.5, 0.5, 0). DALAT is convenient to change lattice constant; but it is fixed to be zero here; thus no effect in this example.

Note that SITE category can have multiple ATOM tokens. The number of ATOM token under SITE should be the same as number of atoms in the primitive cell. In the case of GaAs; SITE contain multiple ATOM tokens. POS= just next to ATOM is taken as subtokens under ATOM token. <sup>10</sup> In cases, we specify such subtokens as SITE\_ATOM\_POS.

In the SITE category, we place atoms (MT names) in the primitive cell. In these cases we use defaults atomic symbol (MT names) for ATOM. POS is in the Cartesian coordinate (in the unit of ALAT+DALAT).

To test ecalj, you may make a test directory and copy a ctrls.\* to your directory. If you have VESTA and ecalj/StructureTool/ installed, you can see its structure by

## \$ viewvesta ctrls.cu

(here \$ means command prompt).

NOTE: As written in ecalj/README, you have to install VESTA and viewvesta. Then set VESTA= at the top of ecalj/Structure/viewvesta, and make softlink to it. The command viewvesta(~/ecalj/StructureTool/viewvesta.py) generate POSCAR\_cu.vasp first, then send it to VESTA. viewvesta also accept POSCAR\_cu.vasp directly. Except names starting from ctrl and ctrls, viewvesta sends the name to VESTA directly. We need extension '.vasp' to recognize it is written in VASP

 $<sup>^9</sup>$ For these variables, we can overlay values when we start programs. For example, 'lmf -vdalat=0.1 si' means that alat is recorded in save.si file.

<sup>&</sup>lt;sup>10</sup>This may looks slightly uncomfortable since the end of range of ATOM is not clearly shown; it end just at the next ATOM token or new category.

format. We have samples in ~/ecalj/StructureTool/sample.

A tool vasp2ctr1 converts POSCAR\_.vasp to ctrls.. "-help" show a small help.

• ecalj/StructureTool/ is not tested well. Not believe it so much... We will fix it on your request. Another possible way is using cif2cell.

If you have a cif file, run

```
cif2cell foobar.cif -p vasp --vasp-cartesian --vasp-format=5
```

And convert POSCAR to ctrls. cif2cell is available from github.

In ctrls.srtio3, we use an expression 1/2 to give POS. We can use mathematical expression instead of values. Mathematical expressions such as "+-\*/ sqrt(...)" are recognized. (instead of 3\*\*2, use 3^2. Use parenthesis, and no space for an expression). We can use default atomic symbols (to check default atom name (MT name) type ctrlgenM1.py --showatomlist). Instead of such default symbols, we can use your own symbol as

```
SITE

ATOM=M1 POS=1/2 1/2 1/2

ATOM=M2 POS= 0 0 0

ATOM=0 POS=1/2 0 0

ATOM=0 POS= 0 1/2 0

ATOM=0 POS= 0 0 1/2

SPEC

ATOM=M1 Z=38

ATOM=M2 Z=22

ATOM=0 Z=8
```

. Then we have to add extra category SPEC where we set Z number. (You can use Z=37.5 for virtual crystal approximation, however, you can not do it in ctrls now. Edit it in ctrl file. Such a procedure will be explained in other place.xxx)

This is an example for Antiferro NiO:

```
#id = Ni0
%const bohr=0.529177 a=7.88
STRUC ALAT={a} PLAT= 0.5 0.5 1.0 0.5 1.0 0.5 0.5
SITE ATOM=Niup POS= .0 .0 .0
    ATOM=0 POS= 1.0 1.0 1.0
    ATOM=0 POS= .5 .5 .5
    ATOM=0 POS= 1.5 1.5 1.5
SPEC
   ATOM=Niup Z=28 MMOM=0 0 1.2 0
ATOM=Nidn Z=28 MMOM=0 0 -1.2 0
ATOM=0 Z=8 MMOM=0 0 0
```

In this case, we define Niup and Nidn sites. These are recognized as Ni atom because of given Z number in SPEC. The subtoken MMOM=Ms,Mp,Md,Mf... re to specify number of magnetic moments ( $\mu_B$ ) for s,p,d,f channels (difference of up - down electrons within MT sites) as initial condition. In this case, we set n(up)-n(down)=1.2 for Niup site for d channel. Even just one ATOM name is given by yourself, all ATOM in SPEC should be given (in this case SPEC for O should be given).

We can see other samples in ~/ecalj/lm7K/TESTsamples/\*/ctrls.\*. (we also have a sample generator. See later section.) Note that ctrls file is jut in order to generate default ctrl file in the followings. Not from ctrls but from ctrl, we can start calculations. (thus ctrls is not needed if we prepare ctrl file directory).

It is possible to add RELAX=001 after  $SITE\_ATOM\_POS$ ; this means structure relaxation along z-axis (also need to set DYN category

as seen at http://titus.phy.qub.ac.uk/packages/LMTO/tokens.html#DYNcat), but its defaults are given (but commented out) automatically in the ctrl file generated by the procedure described in the following section). We detail it in other place xxx.

After ctrl.\* is generated as shown below, we can run a command lmchk to check weather crystal structure is correctly given or not. It finish in a second. It show symmetry information, and so on used in the calculation.

**CAUTION!**: Positions of atoms are not necessarily fixed by ctrl.\* when you restart calculation with rst.\* file, because atomic positions are read from rst.\*. We need to pay attention when we use DYN option because lmf run may save relaxed atomic positions into the rst.\*. As "lmf -help" shows, lmf si --rs=1,1,1,0,0 can read atomic position from ctrl file.

# 3.2 Generate default ctrl from ctrls by ctrlgenM1.py

To run programs of lm7K (lmfa, lmf, lmchk) in ecalj, we need an input file ctrl.\*, which contains not only structures but also other settings. To generate ctrl.\* from ctrls.\*, we have a command "ctrlgenM1.py" (written in python 2.x and call fortran programs(lmfa,lmchk) internally). Two steps required to complete ctrl file: (i) we give reasonable options when we run ctrlgenM1.py. Then (ii) we may edit the ctrl file afterward. In anyway, ctrl file is the starting point of calculations; ctrls is required just in order to generate ctrl.

At first, try ctrlgenM1.py without arguments. It shows help. To generate ctrl from ctrl, type

```
$ ctrlgenM1.py cu --nk1=8
```

Here cu specify ctrls.cu. The option -nk1=8 means the number of division of the Brillouin zone for integration. It means 8x8x8 division. If we like to use 8x8x4, we have to supply three arguments -nk1=8 -nk2=8 -nk3=4. The above command gives following console output.

```
$ ctrlgenM1.py cu --nk1=8
=== INPUT arguments (--help gives default values) ===
--help Not exist
--showatomlist Not exist
--nspin=1
--nk=8
--xcfun=vwn !(bh,vwn,pbe)
--systype=bulk !(bulk,molecule)
--insulator Not exist !(do not set for --systype=molecule)
```

OK! A template of ctrl file, ctrlgen2.ctrl.cu, is generated.

As we see above, options which you specified are shown at the beginning of the console output (in this case -nk1=8). Others such as -nspin=1 are default settings. If we like to perform spin-polarized calculations, we add other option '-nspin=2' as

```
ctrlgenM1.py nio --nspin=2 --nk1=6
```

(NOTE: In the spin-polarized case, we need to set initial condition of size of magnetic moment at each atoms. Set it in ctrls.\* as in the previous section, or edit MMOM of ctrl file (MMOM=s p d f ...) to be like MMOM=0 0 1.2.). The ctrlgenM1.py generates ctrl file named as ctrlgenM1.ctrl.cu. To do calculations, copy it to ctrl.cu so that lmf can recognize it.

```
\verb|cp| ctrlgenM1.ctrl.cu| ctrl.cu|
```

### 3.3 crystal structure checker: lmchk

Do lmchk to confirm correct crystal structure is really given or not.

```
lmchk --pr60 cu
```

Then it reads ctrl.cu. --pr60 is an option of verbose. Bigger number gives more information.

• Lattice info, Space group symmetry operations (in lmf format), and their generators (these operations can be generated from a few of them.)

See http://titus.phy.qub.ac.uk/packages/LMTO/tokens.html#SYMGRPcat+ about how to represent the operations.

- Show atomic positions in ctrl file.
- Tabulate MT radius and distance between atomic sites.

(lmchk -help shows help, but difficult to see. Not need to read it first.)

lmchk is also shows atom (MT site) id (position and class (equivalent positions). This is needed to interpret PDOS.

#### CAUTION for a known bug! See 3 in Sec.3.:

### 3.4 ctrl file

It is not necessary to look into ctrl file first, although some details are explained in the generated ctrl file. Please compare obtained results by lmf with those by other packages or literatures; let me know if you find something strange or your questions.

It is necessary to edit ctrl file to use full ability of lmf. For example, LDA+U, atomic position relaxation, core level spectroscopy, Change setting of default MTO and lo, better mixing procedure for stable convergence; higher accuracy, and so on.

But a few of ctrl file is easy to modify. Search these words and read explanations embedded in ctrl file.

- (1)XCFUN (choice of XC—it is not need to repeat ctrlgenM1.py). It is also possible to change number of k points for sampling, to modify crystal structure slightly, and so on; all things needed are in ctrl. It is not needed to repeat ctrlgenM1.py again.
- (2)SO (to obtain correct dispersion around top of valence at Gamma for GaAs, we need to set SO=1 and NSPIN=2; it is possible to run it as one-shot after convergence with OPTIONS\_Q=band. and run by lmf gaas --rs=1,0).

lmf --input shows what can we write in ctrl file. But more than half are not for users, but for developers (or irrelevant now).

# 3.5 Run LDA/GGA calculations, and get convergence

Here we show how to get converged results from a ctrl file.

At first, we need initial guess of charge density. It can be given by a super position of atomic charge density. To obtain the charge density, we solve atoms first. It is by

### \$ lmfa gaas | tee llmfa

It takes just a few seconds. Here tee is a command of Linux. It keeps console output (standard output) to a file (llmfa in this case).

Then try

### \$ grep conf llmfa

. Then you see a key point that

```
conf:SPEC_ATOM= Ga : --- Table for atomic configuration ---
       isp l int(P) int(P)z
                                                       CoreConf
conf:
                                    Qval
                                              Ocore
         1
                      4
                         0
                                              6.000 \Rightarrow 1,2,3,
conf:
             0
                                    2.000
conf:
         1
             1
                      4
                         0
                                    1.000
                                             12.000 \Rightarrow 2,3,
                      4
conf:
          1
            2
                         3
                                   10.000
                                              0.000 =>
             3
                      4
                         0
                                    0.000
                                              0.000 =>
conf:
          1
conf:
          1
             4
                      5
                         0
                                    0.000
                                              0.000 =>
conf:----
conf:SPEC_ATOM= As : --- Table for atomic configuration ---
conf:
       isp
            1
                int(P) int(P)z
                                    Qval
                                              Qcore
                                                       CoreConf
                         0
conf:
         1
             0
                      4
                                    2.000
                                              6.000 \Rightarrow 1,2,3,
                        0
                      4
                                    3.000
                                             12.000 => 2,3,
conf:
         1 1
         1 2
                      4
                         3
                                   10.000
                                              0.000 =>
conf:
conf:
          1
             3
                      4
                         0
                                    0.000
                                              0.000 =>
conf:
          1 4
                      5 0
                                    0.000
                                              0.000 =>
```

conf:-----

This is an initial electron distribution, and how we divide core and valence. In this case core charge Qcore are (6 electron for s channel=1s,2s,3s and 12 electron for 2s and 3p). Core is not treated separately from valence electrons (frozen core approximation; we superpose rigid core density to make all-electron density). Qval means electrons for each s,p,d channels. The valence channels are 4s,4p,4d,4f (when we set EH=s,p,d,f). The int(P)z column is for local orbital. Thus we have 3d treated as local orbital. (ecal; can add one local orbital per l.)

isp means spin (1 or 2), since –nspin=1 for Ga and As, no isp=2 exist. In summary we have 4s,4p,4d,3d,4f as valence. This means we use corresponding number of MTOs and local orbitals

After lmfa, let us start main calculation.

```
$ lmf cu
```

In unix, we can save console output to llmf by \$ lmf cu | tee llmf. As it starts iteration calculations, it shows similar output again and again (it is a little too noisy now). Then you end up with self-consistent result as

```
it 8 of 30
                    ehf=
                           -3304.895853
                                           ehk=
                                                  -3304.895853
 From last iter
                   ehf=
                           -3304.895856
                                           ehk=
                                                  -3304.895855
 diffe(q) = 0.000003 (0.000007)
                                    tol= 0.000010 (0.000010)
                                                                more=F
c ehf=-3304.8958531 ehk=-3304.8958529
Exit O LMF
 CPU time:
              7.024s
                          Mon Aug 19 02:03:19 2013
```

it 8 of 30 means it stop at 8th iteration, although we set maximum number of iteration 30. Note that this number is given by ITER\_NIT=30 in ctrl.cu). ehf and ehk are the ground state energy in Ry. They are calculated in a little different procedure. Although they are different during iterations, it finally get to be the almost the same number. (But they can be slightly different even converged for large systems. But you don't need to care it so much). NOTE: ehk:Hohenberg-Kohn energy, ehf: Harris-Faulkner energy.

"grep diffe lllmf" shows how the changed of total energy (and charges) during iteration. diffe mean changes of energy with previous iteration, (q) is for electron density difference as well. See also save.\* file, which only show ehk and ehk obtained by each iteration.

"grep gap llmf" shows how the band gap changes (in the usual setting), two same numbers per iteration are shown now.

Thus we do have ground state energy. Although output of lmf is long, most of all are to monitor convergence (we will shrink it). As long as it converged well, you don't need to look into it in detail. Eigenvalues are shown as

```
bndfp: kpt 1 of 4, k= 0.00000 0.00000 0.00000 ndimh = 122
-1.2755 -1.2008 -1.2008 -0.2052 -0.2052 -0.2052 -0.0766 -0.0766 -0.0766
-0.0174 -0.0174 -0.0174 0.1094 0.1095 0.1095 0.2864 0.2864 0.4170
0.4170 0.4736 0.6445 0.6445 0.6445
```

This is at  $k=0.00000\ 0.00000\ 0.00000$ . (because of historical reason, two same bndfp: are shown in each iteration; two band path method). "Imf cu| grep -A6 BZWTS" shows the Fermi energy (for insulator, we see band gap). Deep levels which gives little dependence on k are core like levels. These are in Ry; zero level is not so meaningful (for convenience, it is simply determined from the potential at MT boundaries).

rst.\* contains is the main output which contains electron density. mix.\* is a mixing file (which keeps iteration history). When you restart lmf again, it read rst.cu and mix.cu. If you start from lmfa result, please remove them. We can do parallel calculation with lmf-MPIK, we can invoke it with mpirun -np 8 lmf-MPIK cu. It should give the same answer.

# 3.6 DOS, Band, PDOS plot

We already have script to plot dos, band, and pdos from the result of lmf self-consistent calculations. We have scripts

```
job_tdos, job_band_nspin1, job_band_nspin2, job_pdos
```

. Look into these scripts, and then you see how to plot them.

For total DOS plot, it is better to check ctrl file; BZ\_TETRA=1(this is default; thus make sure that BZ\_TETRA do not exist or BZ\_TETRA=1). In addition, it might be better to enlarge number of k point NKABC in ctrl file to have smooth curve. Then we do

### job\_tdos cu

This shows total DOS as The range of DOS and division of total DOS is given by DOSMAX




Figure 1: DOS(Cu)

and NPTS in ctrl. Edit tdos.cu.glt for gnulot for your presentation. Please look into job\_tdos file in your bin directory. It is a small script.

For band plot, we have to set symmetry lines along which we plot eigenvalues. Collections syml.\* are in ecalj/MATERIALS/. Choose and modify one of them and rename it. I will gather other samples soon. 'BZ wikipedia' or something else will help you to interpret it.

To do band plot, we need syml.cu in your directory.

\$ cp ~/ecalj/MATERIALS/Cu/syml.cu .

Then check syml.cu; it is

21	.5	.5	.5	0	0	0	L to Gamma	
21	0	0	0	1	0	0	Gamma to X	
0	0	0 0	0 (	0 0				

First line means, we calculate eigenvalues for  $\mathbf{k}$  points from  $\mathbf{k}=(0.5,0.5,0.5)$  to  $\mathbf{k}=(0,0,0)$ . "L to Gamma" is just a comment since program only read seven numbers for each line. Second line means, we calculate eigenvalues for  $\mathbf{k}$  points from  $\mathbf{k}=(0,0,0)$  to  $\mathbf{k}=(1,0,0)$ . 3rd line means calculation just stop here. Units of  $\mathbf{k}$  are in  $2\pi/\text{ALAT}$  (or  $2\pi/(\text{ALAT+DALAT})$  if DALAT exist.). A line starting from '#' is neglected (comment line).

To do band plot, run

### \$ job\_band\_nspin1 cu

. This is for nspin=1. job\_band\_nspin2 is for nspin=2 (These scripts try to determine the Fermi energy first. You may skip it in cases (but need to change the script)).

For PDOS plot,

It shows figures (number of figures are number of atoms in the cell) in gnuplot (they are written in the same position on X-window; move top one a little). The command  $job\_pdos$  is a little time-consuming because we use no symmetry to distinguish all lm channels. (PDOS is not yet implemented for SO=1 case; spin-orbit coupling  $\dot{L}\dot{S}$  is added.) We can edit script of gnuplot (pdos.site\*.\*.glt) for your purpose. To plot again, run

```
gnuplot -persist pdos.site001.cu.glt
```

In principle, meanings of all data files are shown (see at the bottom of console output about lm ordering in a line), thus not so difficult to rewrite \*.glt. For example, to plot eg and t2g separately. (NOTE: site id is shown by lmchk).




Figure 2: band plot(Cu)

WARNING: Usually lmf and so on recognize options such as -v option. For example, lmf gaas -vnspin=2' or 'lmf gaas -vso=1'. This option changes values of variables defined in % const section. This is recorded in save.\* file, and also shown at the top of console output. However, job\_tdos and so on, do not yet accept these options. Thus we need to modify ctrl file without using -v option. Or you need to write these option to these command by hand (we will fix this problem in future.)

#### Useful samples: ecalj/MATERIAL/ 3.7

Not only ecalj/lm7K/TestSamples (some of them are by older version), We have a material database in ecalj/MATERIALS/. Move to the directory, and type

# \$ ./job\_materials.py

Then it shows a help. You see

```
=== Materials in Materials.ctrls.database are:===
 2hSiC 3cSiC 4hSiC AlAs AlN AlNzb AlP AlSb
                                               Bi2Te3 C
     CdS
          CdSe
                CdTe
                     Ce Cu Fe GaAs GaAs_so
                     Hf02 Hg0 HgS HgSe HgTe
            GaSb
                  Ge
      TnNzb
            InP
                 InSb LaGaO3 Li MgO MgS MgSe
              PbTe
                   Si
                       SiO2c
                              Sn
                                 SrTiO3 SrVO3 YMn2
         ZnSe ZnTe ZrO2 wCdS wZnS
 7.nΩ
      ZnS
```

For these simple materials (now 57 materials), input files can be generated, and run them automatically by a command ./job\_materials.py below. The ctrls are stored in ecalj/MATERIALS/Materials.ctrls.database in a compact manner (in addition, options passed to ctrlgenM1.py and options to lmf-MPIK are included). See ecalj/MATERIALS/README about how to add new material to it; it is not difficult. The command ./job\_materials.py gives ctrls.\* for these materials from descriptions in the Materials.ctrls.database. And then it generates ctrl file by calling ctrlgenM1.py internally, and run lmfa lmf-MPIK successively (when no –noexec).

Try ./job\_materials.py Fe --noexec. (not fe but Fe as it shown above) at ecalj/MATERIALS/. Then it makes a directory Fe/ and set ctrl.fe (also ctrls.fe) in the directory. Without '-noexec', it does calculation for Fe successively. As for NiO and Fe, we see that ./job\_materials.py gives SPEC\_ATOM\_MMOM in generated ctrls and ctrl files. (Look into ctrls.fe; we need SPEC section when we add MMOM.)

Try job\_materials.py GaAs Si.

Then directories GaAs/ and Si/ are generated. See save.\* files containing total energies iteration by iteration. Starting from ctrl.\* in these directory, the command perform DFT calculations (Console output is stored in llmf, save.\* gives total energies. rst.\* contains self-consistent density, from which we can calculate energy bands and so on).

"./job\_materials --all --noexec" generates ctrls and ctrl files of these materials. "./job\_materials --all" do self-consistent LDA calculations for materials (it takes an hour or more. To change the number of cores for lmf-MPIK, set option -np (number of core). See help of ./job\_materials (type this without arguments).

To make band plot and so on for Fe, follow instructions already explained.

```
$ ./job_materials.py Fe (and need to type return)
  (If you like start over, remove Fe/ under it first).
  $ cd Fe
  $ ./job_materials.py fe
    (but it might be better to do --noexec, and observe Fe/ctrls.fe and
Fe/ctrl.fe first. grep conf llmf shows the initial electron distribution).
  $ cat save.fe (this shows total energies of each iteration. 'c ' at
the first column gives converged result. 'h ' is from atm file.)
        If it does not ends with 'c ...' line, something strange
occurs. see llmf (console out put of lmf is saved to llmf).
  $ cp ../syml.fe .
  $ job_band_nspin2 fe
        (As I said, this shell script do not yet accept
    options to lmf. Look into the script).
        (This calculate fermi energy first for safe; it takes
   some time)
  $ job_tdos fe
  $ job_pdos fe (as I said, this supress space-group symmetry, thus time consuming).
```

At the end of job\_pdos, we show a help which pdos data is where (In pdos file, we have 26 numbers a line; first is energy, 2-26 are pdos for s,p,d,f,g; which is which are shown in the help). See joblmf file also (it contains options to invoke lmf. This is shown in save.\*. In principle, options in joblmf should be passed to band plot and so on. But not yet implemented (it is not so difficult; I have to do it).

After doing ./job\_materials foobar, you may like move it back to original... In such a case, git works. At ecalj/, do

```
$ mv MATERIALS MATERIALS.bk
$ git checkout MATERIALS
```

Then you can see MATERIALS/ is moved back to just downloaded one.

# 3.8 How to add spin-orbit coupling?

```
Do LDA and/or QSGW with SO=0 first. Then apply the spin-orbit coupling by perturbation.
```

```
After converged with nspin=1 (or 2), create new directory and copy ctrl.gas, rst.gas, sigm.gas, QGpsi, to it. Then we set
```

```
nspin=2
  METAL=3 (usually this is default)
 SO=1 (this is ldots calculation off-diagonal elements included).
  Q=band (we do not change potential.)
in ctrl.gas.
Then run
>lmf gas >& llmf_SO
You can see "band gap with SO" by
> grep gap llmf_SO.
Then you can see two same lines.
  VBmax = 0.101949    CBmin = 0.236351    gap = 0.134402    Ry = 1.82786    eV
 VBmax = 0.101949    CBmin = 0.236351    gap = 0.134402    Ry = 1.82786    eV
(two lines per iteration is shown in metel mode).
This is the band gap with SO as a first-order perturbation
on top of the "QSGW without SO". When you use ctrl fil e generated by
ctrlgenM1.py. You can do the above procedure with
>lmf --rs=1,0 gas -vnit=1 -vso=1 -vnspin=2 -vmetal=3 --quit=band
(--rs=1,0 read rst.gas but not write rst.gas. Run lmf --help.
The switch -v (-vso=1 in this case) replaces so=0 with so=1.
This is recorded in save.gas file).
For band plot, you can use the same procedure
for the case without SO. (Look into the shell script job_band_nspin1.
You have to modify it so that
  '--rs=1,0 gas -vnit=1 -vso=1 -vnspin=2 -vmetal=3 --quit=band'
is added to arguments for >lmf --band:syml ...).
(this will be simplified in future...)
For given sigm file, it seems possible to do self-consisent SO calculations
with keeping sigm (then we do not set Q=band).
However, note that Vxc is fixed in QSGW,
it is not necessary better than the above procedure.
```

# 4 How to run QSGW calculation?

In the QSGW, we calculate a non-local exchange-correlation potential  $V^{\rm xc}({\bf r},{\bf r}')$ , by a procedure of GW calculation (very time-consuming part). Then difference  $V^{\rm xc}({\bf r},{\bf r}')V - V^{\rm LDA}_{\rm xc}({\bf r})\delta({\bf r}-{\bf r}')$  is stored into sigm.\* file. The potential file sigm is a key to perform QSGW calculations as seen in Fig.6. The sigm contains static non-local potential  $\Sigma_{\rm QSGW} - V^{\rm LDA}_{\rm xc}$ .

Then, we again do one-body calculation by lmf (or lmf-MPIK) where we add this sigm to one-body potential; when we run lmf or  $lmf\text{-MPIK}(k\text{-parellel}\ mpi\ version)$ , sigm is read and added to the one-body potential if we have  $HAM_RDSIG=12$  in ctrl.\*. Thus this means that we replace  $V_{xc}^{LDA}(\mathbf{r})\delta(\mathbf{r}-\mathbf{r}')$  with  $V^{xc}(\mathbf{r},\mathbf{r}')$ .

This iteration cycle is performed by a script "gwsc" as we explain later on. (In the default setting of ctrl.\* file, lmf try to read sigm.\* file as long as it exists. If not, do lmf or lmf-MPIK calculation.

To start QSGW calculation by **gwsc**, we need not only ctrl.si, but also another input file GWinput. Its template GWinput.tmp can be generated by the Step.2 as follows.

As a summary, you have to follow steps below in order to perform QSGW calculation.

Step 1. Perform from the Step.1 thru the Step.3 in Sec.?? (as same as the case of LDA/GGA). You don't need to perfrom lda calculation in advance, since **gwsc** perfrom LDA/GGA calculation at its beginning. (It means that we start from the one-body Hamiltonian  $H_0$ 

in LDA/GGA as initial condition. In cases, LDA/GGA give poor initial conditions for QSGW; in such a case, we may need another trick to prepare starting point.).

[Caution: We have to use the same LMXA (l in the expansion of eigenfunction in each MT) for all the MT spheres. (This is due to historical reason; we may need to fix this.)] xxx need to explain LMA xxx

### Step 2. Run the script mkGWIN\_lmf2.

The purpose of this script is to get GWinput.tmp. Other files generated are not used in the following stage.

#### Step 3. Edit GWinput.tmp and save it as GWinput.

GWinput is the input file describing the computational conditions for GW calculation. Usually, the default setting gives reasonable results. To reduce computational time, we may use lcutmx(atom)=2 for oxygen sites (this may be also other small atoms.). grep lcut GWinput -A1 shows lcutmx for each atomic sites) These step 2. and step 3. are just only to get GWinput.

Step 4. Run the script gwsc.

# 4.1 GWinput

In order to perform QSGW, one another input file GWinput (no extension) is necessary in addition to ctrl.\*. Thus all input files for QSGW is just two files, ctrl.\* and GWinput. A template GWinput can be generated by a script mkGWIN\_lmf2. You may have to modify it in cases for your purpose.

Let us start from ctrls.si;

```
#id = Si
%const bohr=0.529177 a= 5.43095/bohr
STRUC
     ALAT={a}
     PLAT=0 0.5 0.5 0.5 0.5 0.5 0.5 0
SITE
     ATOM=Si POS=0.0 0.0 0.0
     ATOM=Si POS=0.25 0.25 0.25
```

. Do ctrlgenM1.py si --tratio==1.0 --nk1=6 and copy ctrlgenM1.ctrl.si to ctrl.si. NOTE: the option --tratio=1.0 means we use touching MT; this can be checked by lmchk si; since defaults is almost unity (--tratio=0.97), this is irrelevant, just to explain options.

We have to write GWinput. The default is given automatically by a command mkGWIN\_lmf2;

```
$ lmfa si (lmfa is needed to do in advance).
$ mkGWIN_lmf2 si
.....
== Type three integers n1 n2 n3 for Brillowin Zone meshing for GW! ==
n1=
```

Then it pause and ask numbers. You have to type three numbers as 2+ return + 2+ return + 2+ return.

```
== Type three integers n1 n2 n3 for Brillowin Zone meshing for GW! ==
n1= 2
n2= 2
n3= 2
2 2 2
...(skip)...
OK! GWinput.tmp is generated!
```

Generated file is GWinput.tmp; you have to copy it to GWinput.

```
$ cp GWinput.tmp GWinput
```

These '2 2 2' you typed is reflected in a section 'n1n2n3 2 2 2' in GWinput. This means 2x2x2 (8 points in 1st BZ). You can edit it, and change it to e.g. 'n1n2n3 4 4 4' if you like to calculate self-energy on dense BZ mesh 8x8x8.

The template of GWinput is usually not so bad. But it may give a little expensive setting (or not very good enough in cases).

# 4.2 Run gwsc script

Let us perform QSGW calculation. For this purpose, we use a script gwsc. We need to do lmfa in advance. Then do (not need to do lmf);

```
gwsc (number of iteration+1) -np (number of nodes) (id of ctrl)
```

If (number of iteration+1)=0, it gives one-shot calculation from LDA. But it is different from the usual one-shot; since it calculates off-diagonal elements of self-energy also, we can plot energy band dispersion. In cases (for usual semiconductors), it can give rather reasonable results in comparison with experiments from practical point of view.

This is an example of one iteration of QSGW cycle. (now a little different but essentially similar)

```
takao@TT4:~/ecalj/test1$ gwsc 0 -np 2 si
gwsc 0 -np 2 si
### START gwsc: ITER= 0, MPI size= 2, TARGET= si
--- No sigm nor sigm. $TARGET files for starting ---
---- goto sc calculation with given sigma-vxc --- ix=,0
No sigm ---> LDA caculation for eigenfunctions
       Start mpirun -np 2 /home/takao/ecalj/TestInstall/bin/lmf-MPIK si > llmf_lda
OK! --> Start echo 0| /home/takao/ecalj/TestInstall/bin/lmfgw si > llmfgw00
OK! --> Start echo 1|/home/takao/ecalj/TestInstall/bin/qg4gw > lqg4gw
OK! --> Start echo 1|mpirun -np 2 /home/takao/ecalj/TestInstall/bin/lmfgw-MPIK si> 1lmfgwO1
OK! --> Start /home/takao/ecalj/TestInstall/bin/lmf2gw >llmf2gw
OK! --> Start echo 0|/home/takao/ecalj/TestInstall/bin/rdata4gw_v2 > lrdata4gw_v2
OK! --> Start echo 1 | /home/takao/ecalj/TestInstall/bin/heftet > leftet
OK! --> Start echo 1 | /home/takao/ecalj/TestInstall/bin/hchknw > lchknw
OK! --> Start echo 3| /home/takao/ecalj/TestInstall/bin/hbasfp0 > lbasC
OK! --> Start echo 3| mpirun -np 2 /home/takao/ecalj/TestInstall/bin/hvccfp0 > lvccC
OK! --> Start echo 3| mpirun -np 2 /home/takao/ecalj/TestInstall/bin/hsfp0_sc > lsxC
OK! --> Start echo O|/home/takao/ecalj/TestInstall/bin/hbasfp0 > 1bas
OK! --> Start echo 0| mpirun -np 2 /home/takao/ecalj/TestInstall/bin/hvccfp0 > lvcc
OK! --> Start echo 1 | mpirun -np 2 /home/takao/ecalj/TestInstall/bin/hsfp0_sc > lsx
OK! --> Start echo 11| mpirun -np 2 /home/takao/ecalj/TestInstall/bin/hx0fp0_sc > 1x0
OK! --> Start echo 2 | mpirun -np 2 /home/takao/ecalj/TestInstall/bin/hsfp0_sc > lsc
OK! --> Start echo O| /home/takao/ecalj/TestInstall/bin/hqpe_sc > lqpe
OK! --> == 0 iteration over ==
OK! --> Start mpirun -np 2 /home/takao/ecalj/TestInstall/bin/lmf-MPIK si > llmf_gwscend.0
OK! ==== All calclation finished for gwsc 0 -np 2 si ====
```

Here echo (integer) is readin in at the beginning of the code. To see it, please look into gwsc script (gwsc is at ecalj/fpgw/exec/ and copied to your bin/ by make install2). In anyway, this console output shows calculations finished normally.

Now we get rst.si and sigm.si file which contains (static version of) self-energy minims  $V_{\rm xc}^{\rm LDA}$ . What we did is the one-shot GW from LDA result; but note that we calculate not only diagonal elements but also off-diagonal elements.

We can write energy dispersion (band plot) in the same manner in LDA. To do it, we need rst.si, sigm.si, ctrl.si, QGpsi. (but QGpsi is quickly reproduced). After you have syml.si (e.g. in ecalj/MATERIALS/), Do

```
$ job_band_nspin1 si
```

You can observe large band gap as shown in the Fig.4.2. (To see it again, gnuplot bnds.gnu.si -p. All plots are in gnuplot, thus it is easy to replot it as you like).




Figure 3: Si, one-shot GW with off-diagonal elements

We have QPU file (and also QPD for spin=2), which contains content of the diagonal part of self-energy. It will be explained elsewhere.

You can make total DOS and PDOS plot by

```
$ job_tdos si
```

\$ job\_pdos si

CAUTION:pdos plot is not allowed for so=1. (even tdos-; ask to t.kotani.)

To get final QSGW results, we have to repeat iteration until eigenvalues are converged. Note that total energy shown by console output llmf (and also shown in save file) is not so meaningful in the QSGW; we just take it as an indicator to check convergence. Let us repeat 5 iteration more. "-np 2" means one core to use.

```
$ gwsc 5 -np 2 si
### START gwsc: ITER= 5, MPI size= 2, TARGET= si
--- sigm is used. sigm.$TARGET is softlink to it ---
--- goto sc calculation with given sigma-vxc --- ix=,0
we have sigm already, skip iter=0
---- goto sc calculation with given sigma-vxc --- ix=,1
...(skeip here) ...

OK! --> == 5 iteration over ==
OK! --> Start mpirun -np 2 /home/takao/ecalj/TestInstall/bin/lmf-MPIK si > llmf_gwscend.0
OK! ==== All calclation finished for gwsc 0 -np 2 si ====
```

Note that we do skip 0th iteration (it is for one-shot from LDA) since we start from rst.si and sigm.si given by one-shot LDA. Thus we do just five iterations. Information of eigenvalues are in QPU.(number)run files. (for magnetic systems with nspin=2), wee have QPD.(number)run also). Check it by ls;

```
$ 1s QPU.*run QPU.1run QPU.2run QPU.3run QPU.4run QPU.5run
```

(These are overwritten when we again repeat gwsc; be careful.) Note that QPUO.run was old one when you did 1-shot GW from LDA at the beginning. In anyway \*.0run are confusing files; remove them).

In order to check convergence calculations going well during iteration, do

```
$ grep gap llmf*
```

This shows how band gap changes in llmf.\*run files. In metal cases, we need to compare QPU file, magnetic moment or grep '[xc] save.\*; this shows end of lmf iteration. Energy is not so meaningful but can be indicator to convergence.

Let us check convergence of the QSGW calculations. For this purpose, it is convenient to take a difference of QPU(QPD) files by a script dqpu. These files are human readable. To compare QPU4.run and QPU5.run, do

# \$ dqpu QPU.3run QPU.4run

Then we see a list of numbers (these are the differences of values in QPU files). Then it shows at the bottom as

```
Error! Difference>2e-2 between: QPU.4run and QPU.5run
: sum(abs(QPU-QPD)) = 0.05736
```

but you don't need to care it so much. You rather need to check the difference of values. I can say most of all difference (especially around the Fermi energy are ) are almost 0.00eV or 0.01eV, we can judge QPEs are converged. If not converged well, you may need to repeat gwsc again. (when the size of two QPU files are different, dqpu stops.)




Figure 4: band plot(Si, QSGW one-shot test) and band(Si) (GGA)




Figure 5: band(GaAs), QSGW (test case)

# 5 gwsc script to perform QSGW

# 5.1 outputs of gwsc




Figure 6: Shell script gwsc to perform QSGW contains an iteration loop to make sigm (and eigenvalues, eigenfunctions) self-consistent. The iteration loop is written in ecalj/fpgw/exec/gwsc (a bash script). Exactly speaking, we have to pass all the requied data (not only eivenvalues and eigenfunctions, but also crystal structure,  $\mathbf{q} + \mathbf{G}$  vectors, symmetry information and so on) to GW part. The purpose of the GW part is to calculate  $\Sigma_{\text{QSGW}} - V_{\text{xc}}^{\text{LDA}}$ .

When  $\mathbf{gwsc}$  runs normally, it gives console output as follows. This is a case for  $\mathsf{ctrl.gaas}$  for

>gwsc 10 -np 24 gaas

- . Without arguments, typing  $\mathbf{gwsc}$  shows usage as
- >An example of usage: gwsc 5 -np 4 si, where 5 means 5+1 iterations
- . We recommend you do look into the script **gwsc**. It uses run\_arg, which is a special subroutine of bash; but not so difficult to understand it. (In the followings, we assume /home/binx/ is your bin directory at which we have all binaries for ecalj.)

```
### START gwsc: ITER= 10, MPI size= 24, TARGET= gaas
--- No sigm nor sigm. $TARGET files for starting
                                                  -- ix=,0
 ---- goto sc calculation for given sigma-vxc -
No sigm ---> LDA caculation for eigenfunctions
OK! --> Start echo --- | mpirun -np 24 /home/binx/lmf-MPIK gaas > llmf_lda
OK! --> Start echo 0 | /home/binx/lmfgw gaas > llmfgw00
OK! --> Start echo 1 | /home/binx/qg4gw > lqg4gw
OK! --> Start echo 1 | mpirun -np 24 /home/binx/lmfgw-MPIK gaas > llmfgw01
OK! --> Start echo --- | /home/binx/lmf2gw > llmf2gw
 ... (preparation stage ends here; start main stage) ...
OK! --> Start echo 0 | /home/binx/rdata4gw_v2 > lrdata4gw_v2
OK! --> Start echo 1
                        /home/binx/heftet
                                           > leftet
                        /home/binx/hchknw > lchknw
/home/binx/hbasfp0 > lbasC
OK! --> Start echo 1
OK! --> Start echo 3
OK! --> Start echo 3
                        mpirun -np 24 /home/binx/hvccfp0 > lvccC
                        mpirun -np 24 /home/binx/hsfp0_sc > lsxC
OK! --> Start echo 3
OK! --> Start echo 0
                        /home/binx/hbasfp0 > lbas
                        mpirun -np 24 /home/binx/hvccfp0 > lvcc
OK! --> Start echo 0 |
OK! --> Start echo 1 | mpirun -np 24 /home/binx/hsfp0_sc > lsx
OK! --> Start echo 11 | mpirun -np 24 /home/binx/hx0fp0_sc > 1x0
OK! --> Start echo 2 | mpirun -np 24 /home/binx/hsfp0_sc > lsc
OK! --> Start echo 0 | /home/binx/hqpe_sc > lqpe
OK! --> Start echo --- | mpirun -np 24 /home/binx/lmf-MPIK gaas > llmf_oneshot
  ... (this is the end of main stage) ...
== 0 iteration over == 
---- goto sc calculation for given sigma-vxc --- ix=,1
OK! --> Start echo --- | mpirun -np 24 /home/binx/lmf-MPIK gaas > 1lmf
OK! --> Start echo 0 | /home/binx/lmfgw gaas > llmfgw00
... (lines here omitted ) ...
OK! --> Start echo O | /home/binx/hqpe_sc > lqpe
== 1 iteration over ==
       (lines here omitted ). ..
== 2 iteration over ==
   ... (this repeat until ITER= 10(the first argument to gwsc) ) ...
```

This shows that **gwsc** invoke **lmf-MPIK**, **lmfgw**, **qg4gw**,... successively. **echo** 3|**hbasfp0** means running a fortran program **hbasfp0** with the argument '3' from the standard input (read(\*,\*) in fortran code). We can divide these successive calls to "preparation stage" and "main stage". Preparation stage is just to prepare eigenfunctions and so on which are requied for the "main stage" of GW calculaiton. At the end of "main stage", we have the potential file sigm.

As it shows, console output are going to l\* files.

# 5.2 Preparation stage of gwsc

At the end of this stage, we get required eigenfunctionscle, BZmesh data, and so on, which are required for the main stage. Note that **echo 0** |**lmfgw** means supply an integer to the fortran program **lmfgw** from standard input by read(\*,\*).

- lmf-MPIK (k-pararell version of lmf)

  This is the one-body calculation for given sigm.gaas. At the begining, we do not have sigm.gaas. In this case lmf-MPIK just perform LDA/GGA calculation.
- echo 0 |lmfgw:
  - Get some small information files to start  $\mathbf{qg4gw}$ . If you type just lmfgw, and observe what occurs. It shows a menu and pauses (asking you to supply an integer); then we supply 0 in this case. (If we do  $\mathbf{echo}$  0 |  $\mathbf{lmfgw}$ , no pause occurs.)
- echo 1 |qg4gw|: Get k points used in the GW calculations and the correponding G vectors. And what is the irreducible k point (See console output of qg4gw. gwsc keeps it in |qg4gw|).
  - Since we use the offset-Gamma method for BZ integration for  $G \times W$ , we need shifted mesh points to calculate W at offset-Gamma points. The  $\mathbf{q}$  vectors of offset-Gamma method is in Q0P file. (If you have two points in Q0P, we see two shifted mesh points in addition to regular mesh points.) Remember that cutoff of  $\mathbf{G}$  is given by QpGcut\_psi and QpGcut\_cou in  $\mathbf{GWinput}$ . (Based on the experiences, we use smaller QpGcut\_cou to reduce computational time. Explained in other section xxx).
- echo 1 | lmfgw-MPIK : Calculate the LDA eigenfunctions, eigenvalues, and  $\langle \psi | V_{\rm xc}^{\rm LDA} | \psi \rangle$  at the irreducible k points (shown at the bottom of output lqg4gw of qg4gw.)
- lmf2gw: store these datas into DATA4GW\_V2 and CphiGeig, whose I/O is controlled by a key subroutine gwinput\_v2.f.

### 5.3 Main stage of gwsc

We can start the main stage of *GW* calculation from these files; GWinput DATA4GW\_V2 CphiGeig QGpsi QGcou QOP QIBZ SYMOPS BZDATA HAMindex CLASS; these files contains eigenfunctions and so on in the manner of Eq.(17) of [Kotani(2014)], eigenvalues and other required informations. This is the starting point of the GW calculaiton.

- GWinput: computational conditions.
- $\bullet$  DATA4GW\_V2 : Crystal structures and so.
- CphiGeig: Eigenvalues and Eigenfunctions
- QGpsi: q and G vector for the eigenfunction(q means k in the previous section),
- QGcou: q and G vector for the Coulomb matrix
- QOP: q points near q=0 instead of q=0 (offset Gamma points)
- QIBZ: irreducible q points (This is also contained in BZDATA).
- SYMOPS: point group operation
- BZDATA: q points date (and tetrahedron weights if necessary) for BZ integrals.
- HAMindex: Hamiltonian index, all requied complex index for Hamiltonian of PMT method. (See the top of subroutine write\_hamindex in Im7K/subs/m\_hamindex.F. This is also in

fpgw/gwsrc/m\_hamindex.F. Identical files are in two different directory— it should be avoided in future.)

• CLASS: class information or atomic sites (equivalent sites).

With these files, we do the main stage as

- rdata4gw\_V2: Read DATA4GW\_V2 and so on, and decompose it into files required in the followings. And calculate PPOVL\* files (overlap matrix of interstitial plane waves. Because of technical reasons some different types of PPOVL\* with q-point index).
- heftet: Get the Fermi energy EFERMI by tetrahedron method. It is used in hx0fp0.
- hchknw: stores the number of required  $\omega$  points along real-axis into NW. (NW is not essentially used, but is supposed to exist in the followings.)
- echo 3|hbasfp0: gives the product basis for Core exchange.
- echo 0|hvccfp0: gives the Coulomb matrix for the Core exchange.
- echo 3|hsfp0\_sc : gives the Core exchange part of the self-energy. 11
- echo 0|hbasfp0: gives the product basis.
- echo 0|hvccfp0: gives the Coulomb matrix v.
- $\bullet$  echo 1|hsfp0\_sc : gives the exchange part of the self-energy.
- echo 11|hx0fp0\_sc : gives the correlated part of the screened Coulomb interaction W-v.
- echo 2|hsfp0\_sc : gives the correlated part of the self-energy.
- echo 0|hqpe\_sc: gather datas and write down final results into sigm, QPU, TOTE.UP files.

# 5.4 Other functions (or scripsts)

In addition to gw\_lmfh, there are some other additional scripts and functions.

- gw\_lmfh : The one-shot GW calculation. Lifetime(impact ionization rate) of QPs.
- gwsc : QSGW calculation explained here
- $\bullet \quad \mathbf{epsPP\_lmfh}, \ \mathbf{eps\_lmfh}: \ \mathrm{Dielectric} \ \ \mathrm{function} \ \ \mathrm{without} \ \ \mathrm{or} \ \ \mathrm{with} \ \ \mathrm{local-field} \ \ \mathrm{effects}.$
- run-mode 4 of **hsfp0**: to plot the spectrum function  $\Sigma(\omega)$ .(need to be fixed again probably).
- epsPP\_lmfh\_chipm: non-interacting spin susceptibility. One-degree of freedom like Rigid moment approx. After it ends, you need to do calj\_nlfc\_metal and/or calj\_summary\_mat to get the full spin susceptibility.
- genMLWF: Wannier function and its matix elements of the Screened Coulomb interaction.

<sup>&</sup>lt;sup>11</sup>Correlation part due to cores is neglected. In future, we will switch to a version without PB for core part to reduce computational time and for numerical accuracy.

# 6 Cautions for usage

1. == not meaningful total energy in QSGW===

Total energy shown in QSGW mode in current version is not meaningul. (just treat as an indicator to convergence).

2. == Do we use vwn or gga for QSGW? ===

In principle, QSGW results should not depends on vwn or gga (XCFUN=1 or 103 in ctrl). But there is minor dependence, because

- 1. frozen core density.
- 2. core eigenfunction.
- 3. radial basis funcitons
- 4. Slight numerical reason

(This is probably because Sigma-interpolation procedure But not exactly figured out yet  $\rightarrow$  affect about 0.02eV as for band gap for GaAs. ). In anyway, use vwn (HAM\_XCFUN=1) as standard. And such technical things affects, 0.05 eV level of error for band gap.

3. EH and EH2: For si, if EH and EH2 are the same, the following error occured.

```
fexit,fexit2,fexit3 error retval= -1
Exit -1 zhev_tk2: nev /=nevx something wrong.
```

The large EH, EH2 get to be meaningless. We usually use up to  $\sim 2$ . (If you use very large EH such as  $E \sim 10$ , I am not so sure wether it is )

4. The options about the product basis within MT. (SeungWoo's memo)

```
<PRODUCT_BASIS>
```

```
tolerance to remove products due to poor linear-independency 0.100000D-02 ! =tolopt
```

When the product basis are made, we may have poorly linear independent basis. For example, one in the set  $\{f_1, f_2, ..., f_n\}$  would be almost give by a linear-combination of others. We need to make the linear-independent set. Therefore, after calculating the overlap matrix  $\langle f_i|f_j\rangle$ . We do diagonalization, then we remove eigenvectors corresponding to small eigenvalues than tolopt. See the **hbasfp0** command in **gwsc** 

lcutmx(atom) = maximum l-cutoff for the product basis.

```
4 4 4 2 2 4 4
```

For  $\phi_1 \times \phi_2$  case,  $|l_1 - l_2| \le l_{tot} \le |l_1 + l_2|$ . So 'lcutmx' changes the maximum cutoff for the  $l_{tot}$ . The order is the same as the order of atoms in the **ctrl** file.

atom	1	$\mathtt{nnvv}$	nnc	
1	0	3	3	
1	1	3	2	
1	2	2	1	

'atom' means the atom number identifed in the ctrl file.

'l' is the angular momentum quantum number.

'nnvv' is the number of radial functions (valence) on the augmentation-waves.

'nnc' is the number of radial functions for core.

The latter two ones, 'nnvv' and 'nnc', will be understood more clearly if you see the following ones.

```
! Valence(1=yes,0=no)
at.om
        ٦
                  occ unocc
                               ! 5S_p
  1
        0
              1
                    1
                           1
                               ! 5S_d
  1
        0
              2
                    0
        0
              3
                          1
                               ! 4S_1
  1
                    1
  1
              1
                               ! 5p_p
              2
                    0
                          0
                               ! 5p_d
  1
        1
  1
              3
                    1
                          1
                               ! 4p_1
        1
```

Above options are about the product baiss within MT (Valence).

'atom' and 'l' are explained above. 'nnvv' for 'atom = 1 and l = 0' was '3' so this case we have 3 basis ('n = 1, 2, 3')

'n' is the degree of freedom of the radial function,  $\phi$ . 'n = 1' means  $\phi$ , 'n = 2' means  $\dot{\phi}$ , and 'n = 3' means kind of  $\ddot{\phi}$ , which the dot above the letter represents the differentiation with respect to the energy. So 'n = 1 and 2' is related to the linearization of the radial function and 'n = 3' is the local orbital which is restricted in MT. The local orbital can be modified changing 'PZ' in the **ctrl** file. Finally, the number of the basis which is needed for expanding eigenfunction is  $(l+1)^2 \times n$ .

'occ' and 'unocc' mean that we use only ones that checked as '1', in other words we neglects '0' cases for making product basis. Be careful for confusion with name 'occ' and 'unocc'. These don't mean that occupied or unocc. When making product basis,  $M = \phi_1 \times \phi_2$ , 'occ' corresponds to  $\phi_1$  and 'unocc' to  $\phi_2$ . For example,

```
atom 1 n occ unocc ! Valence(1=yes,0=no)

1 0 1 1 1 ! 5S_p -----

2 3 1 0 1 ! 4f_p
```

If the options are like the above, the product basis will be consists of  $(\phi_1 = \phi_{atom=1,l=0}) \times (\phi_2 = \phi_{atom=1,l=0})$ ,  $(\phi_{atom=1,l=0} \times \phi_{atom=2,l=3})$ . As you can see,  $(\phi_1 = \phi_{atom=2,l=3})$  is skipped.

In the **ctrl** file, 'EH' controls the l part. As for 'EH', (s, p, d, f) are used but **GWinput** file uses (s, p, d, f, g). 'EH': HEAD part. 'GWinput': contains TAIL part... need more explanation.

```
atom
        1
                 occ unocc
                             ForXO ForSxc ! Core (1=yes, 0=no)
  1
                   0
                         0
                                 0
                                             ! 1S ----
             2
                   0
                         0
                                 0
                                       0
                                             ! 2S
  1
        0
                         0
  1
             3
                   0
                                 0
                                       0
                                             ! 3S
        0
```

Above options are about the product basis within MT (Core).

'nnc' for 'atom = 1 and l = 0' was '3' so this case we have 3 basis ('n = 1, 2, 3')

Finally, for the convergence check, we can modify the following three things, (i) tolerance, (ii) lcutmx, and (iii) occ and unoccu.

```
== one show QSGW (not one-shot GW) == one-shot QSGW can be useful in cases.

As it contains off-diagonal part, we can resolve band tanglement problem in Ge (no band gap).
```

== Restart calculation in lda ==

```
lmf(lmf-MPIK) read rst.* in defaluts.
rst contains electron density.
If rst is already converged, it stops after two iteration.
rst contains atomic positions.
So, in order to read atomic positions change in ctrl,
Use options shown in lmf --help.
== Restart calculation in qsgw ==
 To remove mixsigm* (mixing for sigm), maybe required.
== iteration check ===
 First, watch console output of gwsc (do redirect to output file)
 Need to check OK! signs arrayed on 1st columns.
  gwsc iteration is time cosuming,
  So we need to check calculations are normally going on or not.
 Memory inefficiency.
 Set 'KeepEigen off' an 'KeepPPOVL' off.
  In fact, out code is still inefficient for memory usage.
 grep gap llmf ---> minimum gap at mesh point.
  see save.* ,or grep '[xc] ' save.*
  the end of iteration of lmf is shown as x or c.
  (if failed, QPU file.
  dqpu QPU.4run QPU.3run
  As for usual semi-conductor, accuracy abou t0.1 eV is limit of current implementation.
  Set vwn (xcfun=1) looks better (stable) for GW.
  $grep rms lqpe*
  shows
           ... rmsdel=2.44D-04
           ... rmsdel=4.91D-03
           ... rmsdel=2.44D-04
               rmsdel=3.37D-04
  If rsmdel is getteing to be smaller, it is on convergence path.
  (but in magnetic cases, it may give be too good even not yet going to
be converged..., beccause magnetic energy is so small)
  grep diffe llmf ---> difference of energies of each iteration.
  ehf (harris energy)
  ehk (Hohenberg kohn energy)
== emax cutoff for APWs. ==
 We can not use so many APWs in current version,
 because of overcompleteness (this is because null vector within MTs),
  In anyway, use pwemax=3 as standard (test it with 4 or 5).
```

To avoid failure of calculation, we may use smaller MT radius for alkali, and alkali-earth elements.

In feature, I think we can introduce pseudopotentials for these atoms only.

#### == Check Used MTO

Near begining of console output, what MTO you use is shown as: (GaAs case). sugcut: make orbital-dependent reciprocal vector cutoffs for tol= 1.00E-06

246040.		010100	- aopon		-Procur .cocor	0400110 10	 
spec	1	rsm	eh	gmax	last term	cutoff	
Ga	0*	1.13	-1.00	6.579	1.19E-06	1459	
Ga	1*	1.13	-1.00	7.028	1.26E-06	1807	
Ga	2*	1.13	-1.00	7.475	1.09E-06	2109	
Ga	3	1.13	-1.00	7.920	1.06E-06	2637	
Ga	0*	1.13	-2.00	6.579	1.19E-06	1459	
Ga	1*	1.13	-2.00	7.028	1.26E-06	1807	
Ga	2	1.13	-2.00	7.475	1.09E-06	2109	
As	0*	1.18	-1.00	6.300	2.13E-06	1243	
As	1*	1.18	-1.00	6.720	1.26E-06	1471	
As	2*	1.18	-1.00	7.140	1.37E-06	1837	
As	3	1.18	-1.00	7.558	1.05E-06	2229	
As	0*	1.18	-2.00	6.300	2.13E-06	1243	
As	1*	1.18	-2.00	6.720	1.26E-06	1471	
As	2	1.18	-2.00	7.140	1.37E-06	1837	

#### == gwsc cause error stop.

Have you ever changed MTO setting? Consistent with GWinput?

### == QSGW for Fe.

It is better to use 3p as core. Furthermore, 3d+4d as valence is better. Thus we need to set PZ=0,3.9,4.5

I also got aware that emax\_sigm should be large enough (4\$\sim\$5 Ry) to have smooth band dispersion. n1n2n3 can be 10x10x10.

### == RSRNGE: enlarge RSRNGE ===

Use RSRNGE=10 or so (in cases, RARNGE=20 or more is required), for large number of k points. Try and enlarge it if it fails with a message "Exit -1 rdsigm: Bloch sum deviates more than allowed tolerance (tol=5e-6)". We will have to make it automatic in future.

#### == QOP check

In cases, it is better to use QOPchoice=2 instead of default QOPchoice=1. (For slabs, QOPchoice=2 may be better; need check more. In anyway, it is problematic to use unbalanced k points for anisotropic cell). See Copmuter Physics Comm. 176(2007)1-13).

- === When calculation in LDA level fails === when calculation fails in LDA level.
  - (1) smaller MT
  - (2) fewer PW. smaller pwemax.

=== LDA+U ===
not yet written...

=== MAE by rotating crystal ===
(we have a sample at lm7K/TESTsmaples/MAEtest/, but only in GGA/LDA).

=== spin wave ===
J calculation.

====
If not stable convergence in gwsc, try to set

If not stable convergence in gwsc, try to set mixbeta 0.5 (and/or mixpriorit 3 or something) at the begining of sigma.

----

cleargw (directory):

(3) core as semicore.

This command clean up up intermediate files under (directory). This recursively into deeper level. Be careful, or edit it. I use it as '>cleargw .'

-----

Magnetic moment within MTs are shown as

charges: old smooth 17.240314 17.240740 0.000024 -0.000010 mmom1 6.207135 site 6.206590 1.062276 1.062991 <--- here mmom 2 6.207115 site 6.206834 -1.062323 -1.062958 <--- here mmom 1.172718 1.172918 site 3 0.000011 -0.000011 mmom 4 1.172718 1.172918 site 0.000011 -0.000011 mmom

In this case, MTsite1 has 1.062991 and MTsite2 has -1.062958. >grep 'lin mix' -A30 llmf

can take out this message (if console output is in llmf).

\_\_\_\_\_

```
ORBITAL MOMENT in pertubation:
-----
Try
>lmf nio --rs=1,0 -vso=1 --quit=band >llmf
After converged, try
>grep IORBTM -A20 llmf
Then llmf shows shows orbital moment in first order perturbation.
(Here --rs=1,0 read rst.* file but not change it. See >lmf --help.
--quit=band means quit just after band calculation.)
== EPS mode,
  Check Im part of chi0 is smoothly damping at high energy (typically
  1Ry or larger enengy range). If there is some large Im part remains,
  something strange (usually due to orthogonality problem of
  eigenfunctions when you set low q).
  Related source codes are in ecalj/lm7K/ .
  A command ecalj/lm7K/ctrlgenM1.py can generate 'standard input file (ctrl file)'
  just from a given crystal structure file called as ctrls file.
  Binaries are lmf and lmf-MPIK (MPI k-parelell verion).
```

# $6.1 \quad lmf - help$

lmf –help show option of –rs=(five numbers); this let lmf know how to read atm.\* file which is the initial atom file by lmfa.

# 7 Wannier function

xxxxxxxxx under construction xxxxxxxxxxxxxx (See also ecalj/fpgw/Wannier/README)...

We can generate Wannier functions (maximally localized Wannier Functions or similar) by a script **genMLWF**. Run examples in **ecalj/fpgw/MATERIALS/\*MLWF**. To run the script, we need to set options in GWinput. For initial condition, we need

```
MLWF>

# gaussian, nwf

1 1 1 1 1 # nphi(1:nwf)

9 14 2.0 1.0 phi,phidot and lamda(angs) of gaussian 1, #iphi(j,i),iphidot(j,i),r0g(j,i),wphi(j,i)

10 15 2.0 1.0 phi,phidot and lamda(angs) of gaussian 2

11 16 2.0 1.0 phi,phidot and lamda(angs) of gaussian 3

12 17 2.0 1.0 phi,phidot and lamda(angs) of gaussian 3

13 18 2.0 1.0 phi,phidot and lamda(angs) of gaussian 3

</MLWF>
```

In addition, we have some settings (energy windows and so on). This is the example of the initial conditions for Cu case. 5 is the number of Wannier function. The most left one means  $\phi$  index and the right one of it is  $\dot{\phi}$  index. They are writen in the **@MNLA\_CPHI** file.

Then we can run **genMLWF**. After it finished, we can analyze it results. (if you don't need Wannier funciton plot, You can skip a line of wanplot in genMLWF. Then we don't need to set **vis\_wan\_\*** options.)

### 7.1 lwmatK1 and lwmatK2

If you input the following command

```
>grep Wan lwmatK*
```

You will get the following results. (This case: Cu cases)

```
lwmatK1:
          Wannier
                               24.644475
                                            0.000000 eV
                          1
lwmatK1:
          Wannier
                     1
                          2
                               24.644576
                                            0.000000 eV
lwmatK1: Wannier
                          3
                               25.471361
                                            0.000000 eV
                     1
lwmatK1: Wannier
                          4
                               24.644575
                                            0.000000 eV
                     1
lwmatK1: Wannier
                     1
                          5
                               25.470946
                                            0.000000 eV
lwmatK2: Wannier
                               0.000000 eV
                                              -21.263759
                                                            -0.000000 eV
                          1
                     1
lwmatK2: Wannier
                          2
                     1
                                0.000000 eV
                                              -21.263839
                                                             0.000000 eV
lwmatK2: Wannier
                          3
                                0.000000 eV
                                              -21.931033
                                                            -0.000000 eV
                     1
lwmatK2: Wannier
                          4
                                0.000000 eV
                                              -21.263839
                                                            -0.000000 eV
                     1
lwmatK2: Wannier
                          5
                                0.000000 eV
                                              -21.930702
                                                            -0.000000 eV
```

# 8 ctrl file details

A ctrl file is usually generated from a ctrls file by the ctrlgenM1.py (a crystal structure file is not "ctrl" but "ctrls".). It contains self explanation. Here we give complementary explanations to it. Let us Look into a ctrl file. This is a head part of ctrl.cu generated by ctrlgenM1.py:

```
### This is generated by ctrlgenM1.py from ctrls
### For tokens, See http://titus.phy.qub.ac.uk/packages/LMTO/tokens.html.
### Do lmf --input to see all effective category and token ###
### It will be not so difficult to edit ctrlge.py for your purpose ###
VERS
        LM=7 FP=7
                         # version check. Fixed.
ΙO
        SHOW=T VERBOS=35 TIM=2,2
             # SHOW=T shows readin data (and default setting at the begining of
console output)
             # It is useful to check ctrl is read in correctly or not
               (equivalent with --show option).
             # larger VERBOSE gives more detailed console output.
SYMGRP find # 'find' evaluate space-group symmetry automatically.
             # Usually 'find is OK', but lmf may use lower symmetry
```

Note that # means comment lines. We can also use lines starting from % const ... to define variables and set constant.

We see "categories" such as VERS, IO, and so on. The beginning of categories are starting from the first column. Under categories, we have "tokens" such as VERBOSE. Thus we specify full name of token VERBOSE under category IO as IO\_VERBOSE.

- IO\_TIM is for debugging. It shows which subroutines are called and so on. Bigger number shows deeper subroutines.
- SYMGRP is a category without token under it; we set generators of space group (See explanation in previous paragraph). When we set find, it automatically calculate symmetry of crystal lattice. If we like to enforce symmetry, set some of generators which are shown by lmchk.

• We see ctrls is embedded in the ctrl by ctrlgenM1.py.

NL, NBAS(number of SITE) and NSPEC(number of SPEC) are automatically added by ctrlgenM1.py. It is possible to deform unit cell by adding optional tokens (it is possible to rotate PLAT for magnetic anisotropy calculation). See http://titus.phy.qub.ac.uk/packages/LMTO/tokens.html#For new calculations, it is better to find some examples first.

• SITE category: As for MT sites, we have two categories. (1)SPEC(species) and (2)SITE(specify centers of atoms(species) in primitive cell). As for SPEC, we specify MTs(radius, Z, MTOs on it) appeared in the cell. These are defined subtokens under SPEC\_ATOM=foobar (we have multiple SPEC\_ATOM=foobar).

Then we place these MTs at SITE sections in the cell. At SITE, we specify atomic sites (What SPEC\_ATOM is placed to positions by POS) in a primitive cell. We set POS= by direct form (Cartesian) but with the unit of ALAT+DLAT. Total number of SITE (number of tokens SITE\_ATOM) is the number of atoms in the primitive cell. Setting POS= under SITE\_ATOM=foobar means that we place MT named as foobar defined in SPEC\_ATOM=foobar. In addition, we can set SITE\_ATOM\_RELAX, if you like to find relaxed structure (we simultaneously set DYN category) in LDA. As for relaxation, see LaGaO\_relax/ctrl.lagao example, and read

http://titus.phy.qub.ac.uk/packages/LMTO/tokens.html#DYNcat.

The SITE\_ATOM=foobar (with same foobar with different POS) are not necessarily equivalent with respect to the space group operation of a system. Thus SITE\_ATOM=foobar are divided into "classes" which are connected by the operation. The lmf automatically judge "classes" (see also info by lmchk). Thus not need to specify it, but it may be better to check it. A sample is lmchk lagao at ~/ecalj/lm7K/TESTsamples/LaGaO\_relax

• SPEC category: In ctrls, we have not yet specified contents of SPEC; we have just given default symbols or only Z= when we use non-default names (shown by ctrlgenM1.py – showatomlist). The command ctrlgenM1.py adds default SPEC sections.

We have some SPEC\_ATOM, under which we give subtokens such as SPEC\_ATOM\_R(MT radius), SPEC\_ATOM\_Z(nucleus charge), cutoff parameters of angular momentum, and so on. These SPEC\_ATOM is referred to in SITE.

An example of SPEC category is

SPEC

```
ATOM=Fe Z=26 R=1.70

KMXA={kmxa} LMX=3 LMXA=4 NMCORE=1

PZ=0,3.9,4.5

EH=-1 -1 -1 -1 RSMH=0.85 0.85 0.85 0.85

EH2=-2 -2 -2 RSMH2=0.85 0.85 0.85

MMOM=0 0 2 0
```

```
ATOM=... (then the similar block of ATOM= are repeated.)
```

Under the token ATOM=Fe, we have subtokens SPEC\_ATOM\_Z,SPEC\_ATOM\_R, and so on.

Subtokens Z= is the nucleus charge and R= MT radius. Note that Fe is just a name to distinguish MT sphere in the cell. If you set SPEC\_ATOM\_Z=27, it is recognized as Co (since Z=27). LMX=3 is the maximum l of MTOs. Thus maximum l of MTO is l=3. The maximum of l to expand electron density and potential within MT is LMXA (in contrast to usual LAPW), we can use quite small LMXA such as LMXA=4. NMCORE=1 means we calculate core density without non magnetically-polarization. This can reduce computational confusion.

PZ is to set local orbital (if not, no local orbitals). EH and RSMH are to specify first set of MTOs. (We can check how local orbitals are set by lmfa explained in the next section). EH2 and RSMH2 are to specify second set of MTOs.

After PZ=, we have three numbers. These are numbers for s,p,d,f,g,... channels. Zero means not exist. You can use space or comma(,) as delimiter. Here not only the integer part of principle quantum number, but also the fractional part should be supplied (If PZ=0,3,4, it does not work.) Now PZ=3.9 for p and PZ=4.5 for d. This means we use local orbital for 3p, and local orbital for 4d (fractional parts (continuous principle quantum number) are large  $\sim 0.9$  for core like orbital, and smaller for extended orbital  $\sim 0.3$  or something. See Logarithmic Derivative Parameters at http://titus.phy.qub.ac.uk/packages/LMTO/lmto.html). This is a little confusing, thus we will explain this in appendix. See Sec.??.

EH(damping factor), and RSMH (where the smooth Hankel function bent) determines MTOs (or its envelope function as a smooth Hankel function). We now set four numbers for them. Thus we set MTOs s,p,d,f with EH=-1 and RSMH=0.85. Our current test shows that RSMH is one half of R (that is, 0.85=1.70/2, but minimum RSMH is 0.5) and not need to be dependent on s,p,d,f. (If LMX=2, s,p,d are allowed and no f MTOs.) EH is -1; not need to change except test purpose. In a similar manner, EH2 and RSMH2 for second set of MTOs are given. Just three numbers means these for s,p,d.

MMOM=s,p,d,f... gives initial condition of magnetic moment in  $\mu_B$  (number of up-down electron).

In cases such as As, the local orbital given by default ctrl is responsible of rather deep core, and it is not need to be treated as valence electrons. In such a case, we don't need local orbital.

In the case of AntiFerro-II NiO, it contains two NiO in a primitive cell. Thus it is reasonable to have two SPEC\_ATOM as Ni1 and Ni2, although subtokens under ATOM=Ni1 and ATOM=Ni2 (e.g. SPEC\_ATOM\_EH for them) are the same except initial condition of magnetic moment of MMOM=s,p,d,f... See example of NiO.

The minimum help of call Category\_token\_subtoken are listed with minimum explanation with

```
$ lmf --input
```

It gives a long output. But many of them are experimental and not need to manage them. A part of it is

```
Token Input cast (size,min)

......

STRUC_ALAT reqd r8 1, 1

Scaling of lattice vectors, in a.u.
```

This is an minimum explanation of it. "reqd" means "required" (no default). r8 means it read with real number, 1,1 means that ALAT=xxx should contain one number minimum (max is also one) (See also STRUC\_PLAT, and so on).

There are kinds of examples in ecalj packages. Please look into their ctrls.\* and ctrl.\* These are in lm7K/TESTsample/\* and ecalj/CMDsampls. In addition, ecalj/MATERIALS contain many samples (need a command); see a later subsection.

As for what is shown in \$ lmf --input, most of important tokens are already described in the ctrl file generated by ctrlgenM1.py. So, we don't need to care many options shown by it.

But we have not yet explained some useful feaures; STRUC category to deform crystal; DYN category for dynamics; LDA+U treatment; Adding background charge; Core-Hole treatments. We will prepare examples for it if requested.

```
http://titus.phy.qub.ac.uk/packages/LMTO/tokens.html#STRUCcathttp://titus.phy.qub.ac.uk/packages/LMTO/tokens.html#DYNcat
```

For QSGW calculation:

We need a setting in ctrl file to read sigm file (HAM\_SIGP). It is simplified now, and not need to care it so much. As we set RDSIG=12 in defaults, lmf read sigm file and add it to one-body potential as long as sigm.\* exist.

NOTE for old users: We now set SIGP[MODE=3 EMAX=9999.] in ctrl file to read self-energy in lmf (or lmf-MPIK). This is because we use very localized MTOs (similar with the Maxloc Wannier). Our test shows reasonable results and this simplify algorithms. In my previous version, we asked you to use SIGP[MODE=3 EMAX=2.0] where EMAX is a little (0.5Ry) less than emax\_sigm. If something strange occurs, try this setting).

• In principle, QSGW result should not depended on the choice of XCFUN. However, it can affect slightly. In our tests, it seems slightly better to use vwn (XCFUN=1) for QSGW calculations. (BUT need to check more...)

### 8.1 How to set local orbitals

```
As we stated, do "lmfa |grep conf" to check used MTO basis.

We have to set SPEC_ATOM_PZ=?,?,?

(they ordered as PZ=s,p,d,f,...) to set local orbitals.
```

```
lmv7 (originally due to ASA in Stuttgart) uses a special terminology
  "continious principle quantum number for each 1", which is just
  relatated to the logalismic derivative of radial funcitons at MT
  boundary. It is defined as
  P= principleQuantumNumber + 0.5-1/pi*atan(r* 1/phi dphi/dr),
  where phi is the radial function for each 1. For example,
  P= n.5 for l=0 of free electron (flat potential) because phi=r^0,
  P= n.25 for l=1 because phi=r^1;
  P= n.147584 for l=2 because phi=r^2; P=, n.102416 n.077979 for l=3,4.
  (Integer part can be changed). See Logarithmic Derivative Parameters in
  http://titus.phy.qub.ac.uk/packages/LMTO/lmto.html#section2
  Its fractioanl part 0.5-atan(1/phi dphi/dr) is closer to unity for
  core like orbital, but closer to zero for extended orbitals.
  Examples of choice:
  Ga p: in this case, choice 0 or choice 2 is recommended.
      We usually use lo for semi-core, or virtually unoccupied level.
     (0)no lo (4p as valence is default treatment without lo.)
        3p core, 4p valence, no lo: default.
       Then we have choice that lo is set to be for 3p,4p,5p.
     (1)3p lo ---> 4p val (when 3p is treated as valence)
        3d semi core, 4d valence
       Set PZ=0,3.9
        (P is not requied to set. *.9 for core like state. It is just an initial condition.)
     (2)5p lo ---> 4p val (PZ>P)
        Set PZ=0,5.5
        5.5 is just simply given by a guess (no method have yet
implemented for
        If 5.2 or something, it may fails
       because of poorness in linear-dependency. We may need to observe
       results should not change so much on the value of PZ.
     (3xxx)4p lo ---> 5p val (we don't use this usually. this is for test purpose)
        4p lo, 5p valence
        Set PZ=0,4.5 P=0,5.5 (In this case, set P= simultaneously).
        (NOTE: zero for s channel is to use defalut numbers for s)
  Ga d: (in this case, choice 0 or choice 1 is recommended).
     (0)no lo (3d core, 4d valecne, no lo: default.)
         Then we have choice that lo is set to be for 3d,4d,5d.
     (1) 3d lo ---> 4d val (when 3d is treated as valence)
         Set PZ=0,0,3.9 (P is not required to set)
     (2) 5d lo ---> 4d val (PZ>P)
         Set PZ=0,0,5.5
     (3xxx) 4d lo ---> 5d val (this is for test purpose)
         Set PZ=0,0,5.5 P=0,0,4.5
```

(NOTE: zero  $% \left( 1\right) =\left( 1\right) \left( 1\right) =\left( 1\right) \left( 1\right$ 

If you like to read from atm.ga file instead of rst file(if exist).

You have to do lmf --rs=1,1,0,0,1, for example. See lmf --help

Becase rst file keeps the setting of MTO, thus change in ctrl is not reflected without the above option to lmf.

\_\_\_\_\_

### 9 GWinput details

### 9.1 generate a templete of GWinput

As in the previous section, we need two input files ctrl.si and GWinput. In principle, these two determines final results uniquely. A template GWinput.tmp is generated by mkGWIN\_lmf2. Required files are

Input files

• ctrl.si: The control file for PMT method.

(Recently modified **mkGWIN\_lmf2** runs **lmfa** internally. If you use older version, do **lmfa** in advance).

Output files

• GWinput.tmp: A file including computational conditions for the GW calculation. In addition, it specifies the k poins for which you calculate the QP energy.

When you run  $mkGWIN\_lmf$ , it asks you to supply three numbers for BZ integration as == Type three integers n1 n2 n3 for Brillouin Zone meshing for GW! == n1=

Then you need to type a number e.g. as "2 Return" for n1. Then you need to repeat it for n2 and n3 as

n1= 2 | Return

n2= 2 | Return

n3= 2 Return

. These numbers specifies what k poins in BZ is used for BZ integration (In this case,  $2 \times 2 \times 2 = 8$  k point in the 1st BZ is used. Roughly speaking, we need  $4 \times 4 \times 4$  (or  $6 \times 6 \times 6$ ) to get band gap for Si and so on, with  $\approx 0.1$  eV accuracy.)

Then you have to edit GWinput.tmp and copy it to GWinput. We details the GWinput in later chapter.

We need to repeat mkGWIN\_lmf2 when you change MTO sections in ctrl file (adding PZ case, and so on).

### 9.2 overview of GWinput

(Because of historical reason, input file is different from ctrl.\*).

The main input files is  $\mathsf{GWinput}$ . This controls the setting of  $\mathsf{GWcalculation}$ . The file  $\mathsf{GWinput}$  consists of structures as

keyword1 data1

keyword2 data2

..

In each lines, it consists of keyword and data. Data can be sigle or plural. As for keywords, upper case or Lowercase is not distingushed. All keywords should start from 1st column (no space at head). Order of lines are irrelevant. As for logical variable, you can use anything "true, ok, .true. yes, on, 1, T" for .true., and anything "false, ng, .false., no, off, 0, F" for .false.

Or we have "tag sections" in GWinput specified by <PRODUCT\_BASIS>, <QPNT>, <PBASMAX>, <QforEPS>, and <QforEPSL>. (<PRODUCT\_BASIS> is requires for all kinds of calculations. <PBASMAX> is optional. <QforEPS> and/or <QforEPSL> are required for epsilon mode). It is like

```
<PRODUCT_BASIS>
tolerance to remove products
0.100000D-02 ! =tolopt
lcutmx(atom)
3 3
atom 1
...
</PRODUCT_BASIS>
```

. In these tag sections, you have to keep format for its own (usually numbers are read by free format read(\*,\*)).

The fundamental readin routine for GWinput is a subroutine getkeyvalue defined in gwsrc/keyvalue.F. getkeyvalue is a general and convenient readin routine in full use of the f90 features. Read a head part of the file and try to do "grep getkeyvalue \*.F" in gwsrc/or main/so as to see how to use it (test routine is main/kino\_input\_test.F.)

So the GWinput consists of three sections

- 1. General section
- 2. <PRODUCT\_BASIS> section
- 3. <QforEPS>,<QforEPSL> section (only effective for dielectric cuntion mode)
- 4. <QPNT> section (only effective for one-shot mode)
- 5. <PBASMAX> section (optional)

We will explain each by each in the followings.

### 9.3 General section

In genral section, it looks like

```
! #### From GWINO ##############
n1n2n3
               1
                    1
                         1 ! for BZ meshing in GW
QpGcut_psi
              4.000 !(See unit_2pioa for unit) |q+G| cutoff for eigenfunction.
QpGcut_cou
             3.000 !(See unit_2pioa for unit) |q+G| cutoff for Coulomb and W.
unit_2pioa off ! off --> a.u.; on--> unit of QpGcut_* are in 2*pi/alat
alpha_OffG
             1.000 !(a.u.) Used in auxially function in the offset-Gamma method.
!emax_chi0
             99999.000 !(Ry) emax cutoff for chi0 (Optional)
                3.000 !(Ry) emax cutoff for Sigma
emax_sigm
! ##### FREQUENCIES from GWIN_V2 ###############
        0.005000 !(a.u.) energy-mesh (bin width size) along real axis.
dw
           0.040 !(a.u.) energy-mesh is twiced at omg_c
omg_c
  ! coaser mesh for higher energy. Width get to be doubled at omg_c.
iSigMode
             3 ! QSGW mode switch for gwsc. use =3.
            10 ! Number of frequencies along Im axis. Used for integration to get Sigma_c
  ! E.g. try niw=6 and niw=12
delta
         -0.10D-05 !(a.u.) Broadening of x0. negative means tetrahedron method.
  ! used by hx0fp0. You get smeard x0 witth abs(delta).
          0.020000 !(a.u.) Mesh for numerical derivative to get the Z factor
deltaw
           0.003000 !(Ry) used by hsfp0. Keep esmr smaller than band gap for insulators
esmr
  ! Poles of G^LDA are treated as if they have width esmr in hsfp0.
  ! Change esmr for metals. See DOSACC*---especailly around Ef.
GaussSmear on ! Gaussian or Rectangular smearing for Pole of G^LDA with esmr for hsfp0.
```

### 1. BZ integration.

| n1n2n3 | 3 integers as  $N_1, N_2, N_3$  (no default); They are  $\geq 0$ .

Brillouin Zone mesh for integeration is determined by keywordsBZmesh and n1n2n3. Current version only allow regular mesh point including Gamma point for  $G \times W$ . But not that Chi\_RegQbz below allow you to use off-Gamma mesh for  $W(\omega)$  (and dielectric function mode).

We usually take '4 4 4', '6 6 6' or '8 8 8' for GaAs. For metal such as Fe, '10 10 10' or more is better.

Chi\_RegQbz = on (default): Use regular mesh (including gamma) for eps calculation.

Chi\_RegQbz = off: Use off-Gamma mesh (Not including gamma) for eps calculation.

(In cases, Chi\_RegQbz off gives faster convergence as for n1n2n3; not only for GW, but also for dielectric functions eps\_lmfh.)

#### 2. Plane wave $(\mathbf{q} + \mathbf{G})$ cutoff

QpGcut\_psi 1 real (no default)
QpGcut\_Cou 1 real (no default)
unit\_2pioa 1 logical (no defalt)

We have two cuoff for  $\mathbf{q} + \mathbf{G}$ . QpGcut\_psi is the cutoff of |q+G| for the IPW in the expansion of the eigenfunctions. QpGcut\_Cou is for the IPW of the interactions v, D, W.

Its unit is specified by unit\_2pioa; "off" means unit in a.u. and "on" means in unit of  $\frac{2\pi}{\text{alat}}$ . (alat is length scale unit in ctrl.\*).

Rule of thumb: QGcut\_psi is a little (usually 0.5 or so) larger than QpGcut\_cou. It becomes accurate if we use large QpGcut\_cou. But it enlarge size of IPW(interstitial plane wave) part of Mixed product basis. For test, try 2.7, 3.2, 3.7 for QGcut\_cou (and add 0.5 or 1 for QGcut\_psi). Larger one is expensive.

We expand eigenfunctions in the Muffin-tin division of the space. See Eq.[?] in Ref.[?]; in the current GW implementation, we use very simple form of eigenfunctions (not by the 3-component formalism in the [?]).

Thus the form of expansion is just related to the division of space; not directrly related to the difference among LAPW, LMTO, and PMT.

3. Eigenfunction within MTs (no parameters setting for them).

The radial functions (phi and phidot for each l), corresponding to the true parts, (= 2nd component in the 3-component formalism [?]), are automatically determined already in the one-body part of program lmf-MPIK.

4. Cutoff for used bands.

| emax\_chi0 |: 1 real (optional, default= $\infty$ ), in Ry

emax\_sigm: 1 real (optional, default= $\infty$ ; We usually use 3 Ry).

emax\_sigm is the maximum limit of the self-energy (measured from the Fermi energy).
See the paper [?] which shows how the results are affected by emax\_sigm. But in cases,
small emax\_sigm can give poor dispersion curve (slightly unnatural behavior) because of
sudden cutoff by emax\_sigm. However, we like to use smaller value to reduce computational time.

That is, larger is better, but expensive (And note that we simultaneously need to use empty spheres when we use large <code>emax\_sigm</code>, as shown in [?], ).

Generally speaking, accuracy less than  $\sim 0.1 \, \mathrm{eV}$  (for bandgap) is allowance of current technique. Probably, it may be possible to have better accuracy, but it may ask us to repeat many calculations with changing conditions to confirm stability.

These specify how many bands you use in  $\mathbf{hx0fp0}$  (for chi0) and in  $\mathbf{hsfp0}$  (for sigma). Higher bands above them are neglected.

5. Energy mesh related parameters.

 $\boxed{\mathtt{dw}}$ : 1 real (a.u.). Mesh width along real axis for  $W(\omega)$ .

omg\_c : 1 real (a.u.).

dw and omg\_c determines  $\omega$  mesh along real axis to calculate  $W(\omega)$ . In other words, dw and omg\_c specify real space bins which we accumulate imaginary part weight of polarization functions. dw is bin width at  $\omega=0$ , then bin width is twiced at omg\_c. (Energy mesh is getting coarser at higher energy; in other words, the bin width is quadratically larger.) This choice of getting coarser is because we think  $W(\omega)$  around  $\omega\sim0$  gives most important contribution to the GW approximation. If bins are too wide, dielectric function can be less accurate, but results are not necessarily so much affected. For metal, our code can capture Drude weight numerically. We do not need to be so sensitive to the choice of them usually.

delta: 1 real (a.u.). We usually use very small number as -1d-8 for gw\_lmfh, eps mode and so.

xxx does this really make the stabilization? xxx This is the size of  $\delta$  in denominator of  $\Pi$  (EQ.xxx). But (I think) we can (or can not) use it so as to make broadning for theoretical test (maybe not exactly corresponding to  $\delta$ ). or when you make calculation stabilized (Takao need to check this point again xxx!)

[Old note. Need check xxx: In gw\_lmf, it is used for broadening of x0 when it call hx0fp0. Then delta is  $\delta$  is EQ.32. The sign of delta is just used as a flag whether you use the tetrahedron method of dielectric constant [Rath and Freeman(1975)] or not; minus sign means "Use the tetrahedron method for D"; plus sign means you do it by simple sum. You can usually use this default setting. But it might be possible to use a larger value to smear the fine structures on the energy-dependence of W in cases. This might be necessary if W is so energy-dependent and dw is not so small to resolve the structure—but I don't know.]

### niw: 1 integer.

Number of integration points along the imaginary axis(FIG.1) to get  $\Sigma_c$ . See routines wint\* called from sxcf\*.F, which is called from the main routine hsfp0.m.F (or hsfp0.sc.m.F in the QSGW case). The integration points are  $i\omega'(n) = i(1/x(n) - 1)$ , where x(n) is the usual Gaussian-integration points for the interval [0,1]. In addition, we give the special analitical treatment for the peakey part at  $\omega' = 0$ . Out tests shows niw=6 for Si is good enough for 0.01 eV accuracy. The convergence as for niw is quite good. This integration scheme has been devloped by Ferdi Aryasetiawan. The number of points should be the one of 6,10,12,16,20,24,32,40,or 48. It is because we use a subroutine gauss in /gwsrc/mate.F prepared by Ferdi. We will replace better one in future. See II-F in Ref.I.

### GaussSmear : 1 logical

esmr: 1 real (Ry). Used by hsfp0 (and hsfp0.sc for QSGW).

Poles of the Green function  $G^{\mathrm{LDA}}$  are treated as if they have width esmr in hsfp0. If GaussSmear is on, each pole of  $G^{\mathrm{LDA}}$  is smeared by a Gaussian function with  $\sigma = \operatorname{esmr}$  in the calculation of hsfp0. If GaussSmear is off, we assume rectangular smearing for the poles. Usually it is necessary to take rather smaller value than band gap for insulators. Try to use 0.003 or so in the case of Si and GaussSmear=on.

For metal, this esmr is somehow related to how we capture the Fermi surface; In principle, we have to take the limit  $n1n2n3 \to \infty$  and  $esmr \to 0$ ). However, we may inevitably use some finite esmr to make calculations converged.)

deltaw: 1 real (a.u.) only for one-shot case.

deltaw is the interval for the numerical derivative  $\frac{\partial \Sigma(\omega)}{\partial \omega}$  in EQ.8. We calculate  $\langle \psi^{\mathbf{k}n} | \Sigma(\epsilon^{\mathbf{k}n} + \mathbf{deltaw}) | \psi^{\mathbf{k}n} \rangle$  and  $\langle \psi^{\mathbf{k}n} | \Sigma(\psi^{\mathbf{k}n} - \mathbf{deltaw}) | \psi^{\mathbf{k}n} \rangle$  in addition to  $\langle \psi^{\mathbf{k}n} | \Sigma(\epsilon^{\mathbf{k}n}) | \psi^{\mathbf{k}n} \rangle$ . From these values, we can calculate two Z (or second-derivative of  $\Sigma(\omega)$ ), as shown in SECU. It will help to see whether the used deltaw is O.K. or not.

### 6. Offset-gamma point.

QOPChoice 0:1 integer

QOP\_Choice gives how to determine the offset gamma points. Initially we take them as

- 1: —q— is ten times smaller than regular mesh.(default)
- 2: —q— is avarange in the Gamma cell (cell of BZ including Gamma point).

Then we choose only inequivalent  $\mathbf{q}$  points based on the point group symmetry. Obtained offset gamma points is given in Q0P file.

alpha\_offG corresponds to  $\alpha$  in EQ.48. alpha\_offG=1d0 is usually good in the sense that it seems to be almost a limit at  $\alpha \to 0$ . So you can usually fix it as alpha\_offG=1d0, and check the convergence as for n1n2n3.

#### 7. core orthogonalization (default=off)

CoreOrth 1 logical — recently, this option is not maintained — Better to use local orbital instead, so that core charge do not spill out.

If this is on, we enforce cores orthogonalied to valence  $\phi$  and  $\dot{\phi}$  (these appear in II-C in Ref.I). This procedure enforce the correct orthogonal condition, thus we have correct behavior for the dielectric function at  $\mathbf{q} \to 0$ . However, it may deform core functions too much, especially in the case of shallow 3d (or maybe 4d) cores. So we don't recommend use this option, even though then the orthogonality condition is somehow broken. Anyway you can check wether it affects to results or not by this switch.

### 8. QP self-consistent GW.

iSigMode 1 integer (nodefault).

This is required for QSGW calculation by the script **gwsc**. We have some possible ways to make GW self-consistent (how we determine  $V_{\rm xc}$  from calculated  $\Sigma(\omega)$ ). We now mostly use iSigMode=3.

3: Use Re
$$\frac{\sum_{nn'}(\epsilon_n) + \sum_{nn'}(\epsilon_{n'})}{2}$$
 (mode-A in [?]).

- 1: Use  $\Sigma_{nn'}(E_F) + \delta_{nn'}(\Sigma_{nn'}(\epsilon_n) \Sigma_{nn'}(E_F))$  (mode-B in [?]).
- 5: Use  $\delta_{nn'}\Sigma_{nn}(\epsilon_n)$  (Eigenvalue-only self-consistency, keeping the eigenfunction as given)).

See /gwsrc/sxcf\_fal2.sc.F, which is called from the main routine hsfp0\_sc (this is the routine to calculate self-energy)).

#### 9. Others

KeepEigen | 1 logical (default=on)

These are for memory usage. When KeepEigen is on, eigenfunctions (Eigen) are kept in memory during calculation. If you have not enough memory in your machine, use them off. Then you can save memory usage. However, then we may have too frequent access to files. So %CPU might get lower. Be careful to use these options.

Verbose 1 integer (default=0) If 0, it gives minimum standard output. If 40 or higher, it shows too much output. (these verbosity control is not well-organized yet).

10. LFC@Gamma | EIBZmode | multitet | are for test purpose.xxx

### 9.4 < QPNT > section

(only for one-shot GW. Not suitable to make band plot in BZ.) This section is to specify the q points and bands index for which you calculate the QP energies (QPE). An example is

Specify the q and band indeces, for which we evaluate the self-energy ---

3
15 16 17
\*\*\* q-points, which shoud be in qbz. See KPNTin1BZ.

Numbers are read by free format read(5,\*), thus the numbers should be separeted by space. At the next line to the first \*\*\*, you have to give two numbers used as flags. Both of them takes 0 or 1. 1st one is whether you calculate QPE for all q points (in IBZ) or not. If it is 1, you calculate QPE for all q. If it is 0, you calculate them only for q points specified within this file. In the case of metal where you want to calculate the Fermi energy for QPE, you need to calculate all the eigenvalues somehow above the Fermi energy (If you put 1, it is safer but too time-consuming). The second number is whether you calculate QPE for both spins or not. It is usually 0. In the case of antiferro material, it should be 1.

From the next line to the second \*\*\*, you have to specify the states for which you calculate the QPE. In this example, you calculate the 3 bands of QPE for 15th, 16th, and 17th eigenfunctions (they are ordered from the bottom).

From the next line to the third \*\*\*, you have to specify the q points. The first numbers of each line are dummy. In this case, you calcualte QPE for two q points. The third q point is neglected because 2 is given at first.

When you generate GWinput.tmp, you see all the possible q points are listed (these q points should be a part of the regular mesh points).

In the QSGW mode (gwsc), this section is neglected (then we calculate all QPE on regular mesh points); so its hsfp0 $_{sc}$  part is quite expensive (usually it takes time more than hx0fp0).

This overide setting in <QPNT>. (I think this switch may still work, but not checked recently).

AnyQ on (default is off)

If this is on, you can spefify any Q point which is not on the mesh point. For the purpose, we need to prepare eigenfunctions at extra  $\mathbf{k}$  points. But it is automatic. In order to make the computation efficient. Even in this case, from the computational view, it is better to choose  $\mathbf{q}$  on the two times finer devided mesh (or three times finer devided  $\mathbf{k}$  mesh). This is used for Fig.6 in Phys. Rev. B 74, 245125 (2006).

### 9.5 set QPNT for eps mode (QforEPS section)

For eps modes (scripts eps\_\*, which are for linear responses. See Sec.14), you have to specify q point in the following ways.

### 1. QforEPSIBZ on

Then all Q point in IBZ are used.

2. Use section as

<QforEPS>

0d0 0d0 0.01d0

0d0 0d0 0.02d0

0d0 0d0 0.04d0

0d0 0d0 0.08d0

</QforEPS>

In addition, you can specify Q points as

<QforEPSL>

0d0 0d0 0d0 1d0 0d0 0d0 8 0d0 0d0 0d0 .5d0 .5d0 0d0 8

</QforEPSL>

This is along the line—8 point along the line (not left-end q; so omitting 0 0 0). The first line means line  $(0d0\ 0d0\ 0d0)$ — $(1d0\ 0d0\ 0d0)$  is devided to 8. So we have 7 points,  $(0.125\ 0\ 0)$ ,  $(0.25\ 0\ 0)$ ,...  $(1\ 0\ 0)$ .

### 9.6 <PRODUCT\_BASIS> section

This section is to define product basis to expand W and so. Numbers are read by free format read(5,\*), thus the numbers should be separeted by space. The line number in this section is meaningful (you can not add comment lines).

```
<PRODUCT_BASIS>
 tolerance to remove products due to poor linear-independency
  0.100000D-04 ! =tolopt; larger gives smaller num. of product basis. See lbas and lbasC, which are out
 lcutmx(atom) = maximum 1-cutoff for the product basis.
                                                                      =4 is required for atoms with valence d, like
  atom
                      nnc ! nnvv: num. of radial functions (valence) on the augmentation-waves, nnc: num. fo
              nnvv
           0
                 23222222
n 1
                       2
0
0
0
1
          1
2
3
4
0
    122222
          1
2
3
4
1
                       0
  atom
                                     Valence(1=yes,0=no)
                     осс
                          unocc
          0
                                     4S_p
    1
                       1
                 2
                                     4S_d
4P_p
          Ó
    1
                       1
                             0
           1
                             1
                 2
                                     4P_d
                             0
    1
1
1
1
          1
2
2
3
                       0
                       1
                                     4D_p
                 2
3
1
                       0
                             0
                       1
                             1
    1
1
          34
                 2
                       0
                             0
                       Ŏ
                             Ŏ
                 2
    4
                       0
                             0
                 1212121212
          0
                       1
                             1
          0
                             0
                       1
                             0
          1
2
2
3
                       1
                       0
                             0
                       0
          3
                       0
                             0
                                    5g_p
5g_d
                       0
                             0
          4
                       0
                             0
          1
                 n
                                  ForXO ForSxc
  atom
                     осс
                                                     Core (1=yes, 0=no)
                          unocc
           0
                       0
                             0
                                      0
                                            0
                                                     18
                 1
2
3
                                                     2S
                                                     3S
                       Ō
                                      Ō
                             0
                                            0000
                                                     2P
3P
                 12
                       0
           0
                                                     18
</PRODUCT BASIS>
```

This section is read in the free format in fortran. So, e.g., 0.01 works as same as 0.10000D-01. The line order is important (you have to keep the order given by GWinput.tmp). Be careful atom atom id—lmf may re-order it and pass it to gw code. Look into LMTO file (generated by mkGWIN\_lmf2); which contains crystal structure information after such re-ordering by lmf. I used ! to make clear that things after ! are comments. But ! is not meaningful – just the expected numbers of datas separeted by blank(s) are read for each line from the begining of lines.

• 0.100000D-02 ! =tolopt controls a number of Product basis to expand the Coulomb interaction within MTs. tolopt is a criterion to remove the poorly linear-independent product basis. Note that the product basis, which is to expand the Coulomb interaction, is different from the basis to expand eigenfunction. In our experience, 0.100000D-02 (=0.001) is not so bad. If you like to reduce computational time use 0.01 or so, but a little dangerous in cases. With 0.0001, we can check stability on it. (note: By supplying multiple numbers, we can specify tolopt atom by atom. Remember lmchk gives atom ID.)

- lcutmx(atom) is the l cutoff of product basis for atoms in the primitive cell (do lmchk for atom id). In the case of Oxgen, we can usually use lcutmx=2 (need check by the diffence when you use lcutmx=2 or lcutmx=4). Then the computational time is reduced well.
- (dec2014:<PBASMAX> is not checked recently; see fpgw/main/hbasfp0.m.F and fpgw/gwsrc/basnfp.F).)
  You can use <PBASMAX> section to override this setting. It is given as

#### <PBASMAX>

- 1 5 5 5 3 3
- 2 5 5 3 2 3
- 3 3 3 2 2 2

#### </PBASMAX>

The first number is for atom index (fixed), and other are product basis for each l channel.

- The integer numbers in 4th line lcutmx gives the maximum angular momentum l for the
  procduct basis for each atomic site. In our experience, lcutmx=4 is required when the
  semi-core (or valence) 3d electors exist and we want to calculate the QP energies of
  them.
- Keep a block starting from " atom l nnvv nnc ..." as it originally generated in GWinput.tmp. It just shows that how many kinds of radial functions for cores and valence electrons for each atom and l. nnvv=2 in the case of  $\phi$  and  $\dot{\phi}$ ; nnvv=3 in the case to add the local orbital in addition.
- There are two blocks after the line "atom 1 n occ unocc :Valence(1=yes, 0=no)' and after "atom 1 n occ unocc ForXO ForSxc! Core (1=yes, 0=no)'. These are used to choose atomic basis to construct the product basis. The product basis are generated from the products of two atomic basis.

GWinput.tmp generated by  $\mathbf{mkGWIN}$ \_lmf2 contains labels on each orbitals as  $4S_p$ ,  $4S_d$ ,  $4P_p$ ... Here  $4S_p$  is for  $\phi_{4s}$ ;  $4S_d$  for  $\dot{\phi}_{4s}$ ;  $3D_1$  for  $\phi_{3d}^{local}$ . Capital letter just after the principle-quantum number means the orbital is used as 'Head of MTO'; lowercase means just used only as the 'tail of MTO'.

The switches for columns labeled as occ and unocc. take 0 (not included) or 1 (included). With the switch, we can construct two groups of orbitals, occ and unocc. In this sample GWIN\_V2 as for atom 1,  $\{\phi_{4s}, \dot{\phi}_{4s}, \phi_{4p}, \phi_{4d}, \phi_{3d}^{\text{local}}, \phi_{3s}^{\text{core}}, \phi_{3p}^{\text{core}}\}$  consist the group occ, and  $\{\phi_{4s}, \phi_{4p}, \phi_{4d}, \phi_{3d}^{\text{local}}, \phi_{4f}\}$  consists the group unocc. So the any product of combinations  $\{\phi_{4s}, \dot{\phi}_{4s}, \phi_{4p}, \phi_{4d}, \phi_{3d}^{\text{local}}, \phi_{3s}^{\text{core}}, \phi_{3p}^{\text{core}}\} \times \{\phi_{4s}, \phi_{4p}, \phi_{4d}, \phi_{3d}^{\text{local}}, \phi_{4f}\}$  are included as for the basis of the product basis. As for atom 2,  $\{\phi_{2s}, \phi_{2p}, \phi_{3d}\} \times \{\phi_{2s}, \phi_{2p}, \phi_{3d}, \phi_{4f}\}$  are included.

• Core section: (not worth to read, since we currently use no CORE2, A=B=C=0.)

Each line of the last section of Product BASIS forms

```
atom 1 n occ unocc ForXO ForSxc :CoreState(1=yes, 0=no)
1 2 1 A x B C
```

At first you have to understand the concept of CORE1 and CORE2 in EQ.35 Ref.I. However, in our recent calculations, we do not use "CORE2" generally. So, in such a case, set A=B=C=0. And treat shallow cores (above Efermi-2Ry or so ) as valence electron by "local orbital method" in lmf.

• Be careful. Current version is inconvenient... Need to repeat mkGWIN\_lmf2 to generate GWinput templete when you add PZ (local orbital).

[( Note: you can skip here if you don't use CORE2.)

Each of A,x,B,C takes 0 or 1. There are some possible combination of these switches:

- 1. If you take ( A x B C )= (1 0 1 1), then the core is included in core2. In other words, this core is treated in the same manner of the valence electron.
- 2. If you take ( A x B C )= (0 0 0 0), then the core is included in core1. The (exchange only) self-energy related to this core is included in SEXcore.
  C is the key switch which determine whether it is included in core1 or core2. There could be another option.
- 3. If you take (  $A \times B \ C$  )= (1 0 0 1). This core is in core2. But it is not included in the calculation of D and W. This core is only included for SEX and SEC calculations.

These three kinds of choices are reasonable ones but we can consider some another choice. In the following, we show how these switches (A,B,C) affect executions called from gw\_lmfh (esentially as same as gw\_lmf).

- hbasfp0(mode 3): Product basis for exchange due to core.
   We include the C=0 cores as a part of the product basis as if A=1 x=0.
- hsfp0(mode 3): exchange mode for core.  $\Sigma_x$  only due to the C=0 cores are calculated.
- hbasfp0 (model): Product basis.
   Only see the switch A and x. The product basis is generated from (occupied × unoccupied), where A=1 core is included as one of the occupied basis.
- hsfp0 (mode 1): exchange mode. Only see the switch C.  $\Sigma_x$  due to valence and due to C=1 cores are calculated.
- hx0fp (mode 1): W v calculation.
   Only see the switch B. W is calculates using all the valence and B=1 cores.
- hsfp0 (mode 2): correlation mode. Only see the switch C.  $\Sigma_c$  due to valence and due to C=1 are calculated.
- After you perform gw\_lmfh or anything, you find output files lbas by hbasfp0 (mode1), and/or lbasc by hbasfp0 (mode3) for core. These contains inportant informations about how many and how product basis are chosen. E.g. 'grep nbloch lbas' shows how many product basis are used in the calculations.

## 9.7 ANFcond (we can skip here since we do not check this option now. Need fix this if necessary.

This file is used in  $\mathbf{hx0fp0}$  in the calculation of W-v (or rather  $\Pi$  in the program) to specify the antiferro condition.

 ${f Note}$ : Now only for the case that (a translation vector + spin flip) is a symmetry operation.

This should be given by hand. For the cases of not antiferro, this file should not exist. Even if ANFcond does not exists for antiferro case, hx0fp0 works but it requires about two time computational efforts.

```
The existence of this file means the Antiferro condition is used for x0k

Product basis B({\bf r}-{\bf a}) is translated to B({\bf r}-{\bf a}-Af})= B({\bf r}-{\bf a}'-T_0})

1d0 1d0 1d0 ! Af=Antiferro translation vector in Cartesian.

1 2
2 1
3 4
4 3
```

The first line specifies the Antiferro translation vector. From the second line, we specify that atom i in the primitive cell is mapped to what atom j(i) in the cell with the opposite spin by the translation. In this case, j(1) = 2, j(2) = 1, j(3) = 4, j(4) = 3. You have to be careful as for the true atomic position used in the GW calculations can be different from the given atomic positions in ctrl.MnO. The true atomic positions is written in LMTO.

In the case of one-shot GW (gw\_lmf and gw\_lmfh), it may be better to set "up only" QPE, so that you only calcuate QPE of up spins at the same time.

In the case of gwsc, we just calculate QPE for up spins automatically (QPNT section is neglected).

### 10 Main Output Files of GW part

### 10.1 QPU

This is the main output<sup>12</sup> in human readable format.

An example of one-shot GW by  $\mathbf{gw\_lmfh}$ ) is (In the case of QSGW, Z (Z=1) is not shown):

```
_____
```

```
quasiparticle energies MAJORITY
```

E\_shift= 0.4263273221017709D+00 0.6075150850568627D+00 0.7046628446164018D+00 eV

```
q state SEx SExcore SEc vxc dSE dSEnoZ eLDA eQP eQPnoZ eHF Z 2Z*Simg ReS(elda 0.0 0.0 0.0 1 -29.56 -1.97 10.40 -20.22 -0.52 -0.90 -19.08 -19.42 -19.71 -30.81 0.58 0.95 -21.12 0.0 0.0 0.0 2 -30.52 -2.24 10.09 -21.53 -0.70 -1.14 -18.06 -18.58 -18.93 -29.72 0.61 0.96 -22.66 0.0 0.0 0.0 3 -20.67 -1.87 5.97 -16.85 0.19 0.28 -7.20 -6.83 -6.65 -13.32 0.67 0.66 -16.57
```

From the 6h line, we have the eigenvalue datas. All of the unit of energy is in eV. We should note that the zerolevel of these values eLDA eQP eQPnoZ can be changed by hqpe. This eLDA - E\_shift are the eigenvalues realtive to a Fermi energy determined by the smering method. Detailed value of eLDA is in TOTE2.UP. Detailed value of eLDA- E\_shift is in TOTE.UP.

```
q: k vector
state: Band index n, which is from the lowest eigenvalue (not include cores).
\mathtt{SEx:} = = \langle \Psi_{\mathbf{k}n} | \Sigma_{\mathbf{x}}^{\mathtt{core2} + \mathtt{valence}}(\mathbf{r}, \mathbf{r}') | \Psi_{\mathbf{k}n} \rangle
SExcore: = \langle \Psi_{\mathbf{k}n} | \Sigma_{\mathbf{x}}^{\text{core1}}(\mathbf{r}, \mathbf{r}') | \Psi_{\mathbf{k}n} \rangle
SEc: = \langle \Psi_{\mathbf{k}n} | \Sigma_{\mathbf{c}}^{\text{core}2+\text{valence}}(\mathbf{r}, \mathbf{r}', \epsilon_n(\mathbf{k})) | \Psi_{\mathbf{k}n} \rangle
vxc: LDA exchange correlation energy. \langle \Psi_{\mathbf{k}n} | V_{\mathrm{xc}}^{\mathrm{LDA}}([n_{\mathrm{total}}], \mathbf{r}) | \Psi_{\mathbf{k}n} \rangle
dSE: Z_{nk} \times dSEnoZ
\texttt{dSEnoZ: } \langle \Psi_{\mathbf{k}n} | \Sigma_{\mathbf{x}}^{\mathrm{core1}}(\mathbf{r}, \mathbf{r}') + \Sigma_{\mathbf{x}c}^{\mathrm{core2+valence}}(\mathbf{r}, \mathbf{r}', \epsilon_n(\mathbf{k})) | \Psi_{\mathbf{k}n} \rangle - \langle \Psi_{\mathbf{k}n} | V_{\mathbf{x}c}^{\mathrm{LDA}}([n_{\mathrm{total}}], \mathbf{r}) | \Psi_{\mathbf{k}n} \rangle
                  = SEx + SExcore + SEc - vxc
eLDA: LDA eigenvalues. \epsilon_n(\mathbf{k})
eQP: QP energy. \epsilon_n(\mathbf{k}) + dSE
eQPnoZ: QP energy without Z. \epsilon_n(\mathbf{k})+dSEnoZ
eHF: HF energy of 1st itteration. \epsilon_n(\mathbf{k}) + \text{SEx} + \text{SExcore} - \text{vxc}
Z: Z factor. Z_{n\mathbf{k}}
2Z*Simg: Quesi-particle life time. 2Z_{n\mathbf{k}} \times \text{Im}\langle \Psi_{\mathbf{k}n} | \Sigma_{\mathbf{c}}^{\text{core2+valence}}(\mathbf{r}, \mathbf{r}', \epsilon_n(\mathbf{k})) | \Psi_{\mathbf{k}n} \rangle
(Is this really the usual definition of the life time?—don't believe me)
ReS(elda): \operatorname{Re}\langle\Psi_{\mathbf{k}n}|\Sigma_{\mathbf{x}}^{\operatorname{core1}}(\mathbf{r},\mathbf{r}')+\Sigma_{\mathbf{x}c}^{\operatorname{core2}+\operatorname{valence}}(\mathbf{r},\mathbf{r}',\epsilon_{n}(\mathbf{k}))|\Psi_{\mathbf{k}n}\rangle
```

### 10.2 XCU

LDA exchange-correlation. Detailed data of above vxc.

### 10.3 SEXU

Exchange part of the self-energy due to valence electrons. Detailed data of above SEx.

### 10.4 SEXcoreU

Exchange part of the self-energy due to core. Detailed data of above SExcore.

<sup>&</sup>lt;sup>12</sup>Note that QPU also implies QPD and so on. U is for up D is for down spins.

#### 10.5 SECU

Correlation part of the self-energy. Detailed data of above SEc.

### 10.6 TOTE.UP (TOTE.DN)

This is a central output. It contains LDA and QP energies. These values are realtive to a Fermi energy determined by the smering method. It contains two kind of QP energies QP QPnoZ. The first line contains the Fermi energy in Ry determined by the smering method. It is also shown in the end of DOSACC.lda.

### 10.7 TOTE2.UP (TOTE2.DN)

This is a central output. It contains zerolevel shifts from TOTE.UP. The first line contains the Fermi energy in eV (= the Fermi energy in TOTE.UP but it is in Ry) and three energy shifts E\_shift, which are the same values in the 4th line of QPU.

Note that all \*.chk files are just to check calculations (not read in by successive executions).

#### 10.8 DOSACC.lda

This lists all the eigenvalues in accordent order. States with almost the same eigenvalues are degenerated states. The 4th column contains number of electrons up to the eigenvalue.

#### 10.9 DOSACC2.lda

This is similar with DOSACC.lda. But we remove the degeneracy.

### 10.10 Core ibas\* l\*.chk

Used core eigenfunctions.

### 10.11 VXCFP.chk

This contains eigenvalues and  $\langle \psi_{\mathbf{k}n} | V_{xc} | \psi_{\mathbf{k}n} \rangle$  in both units, Ry and eV. See below.

### 10.12 The Fermi energies in this GW code.

We mainly have two kinds of Fermi energy  $E_{\text{FEERMI}}^{\text{smear}}$   $E_{\text{FEERMI}}^{\text{tetra}}$ 

1. At first eigenvalues given by lmfgw is in VXCFP.chk. You can see

These are raw values. TOTE contains the eigenvalues but relative to a Fermi energy  $E_{\rm FEERMI}^{\rm smear}$  which is determined by the smearing method. It is also shown at the top part of output files lsx\_sf and lsc\_sf. And you also see the value at the end of DOSACC.lda.

This is the head of TOTE.UP;

Here  $E_{\rm FEERMI}^{\rm smear}$ =8.520283353474250E-003. From the second lines, they are LDA eigenvalues and QP energies (Z included and Z=1); they are relative to the  $E_{\rm FEERMI}^{\rm smear}$ .
-13.18843159 eV -  $E_{\rm FEERMI}^{\rm smear}$  (which should be translated into in eV) = -0.1330435686590073D+02 eV. Here -13.18843159 is the value in VXCFP.chk shown above.

- 2. There is the another Fermi energy  $E_{\text{FEERMI}}^{\text{tetra}}$ , which is used by mode 11 (or mode 1) of hx0fp0 in gw\_lmfh. It is determined by heftet and stored in EFERMI.
- 3. hqpe gives TOTE2.UP and QPU. They contains the same values. You can see eLDA eQP eQPnoZ Z not only in QPU but also in TOTE2.UP. At top lines of TOTE2.UP, you see

#### %head TOTE2.UP

```
43
             8 0.1159252712507000D+00
                                        0.7555207081466229D+00 0.6267572296579150D+00 0.60094
0.0000000
           0.0000000
                       0.0000000
                                    1
                                        1
                                           -0.1254883615775411D+02 -0.1260308616316985D+02
0.000000
           0.0000000
                       0.0000000
                                           -0.5783388983382487D-05 -0.2309903417430093D-05
0.0000000
           0.0000000
                       0.0000000
                                           -0.1369098933889923D-05 -0.6195200397129952D-07
                                    3
                                        1
0.000000
           0.0000000
                       0.0000000
                                            0.00000000000000D+00 0.000000000000D+00
```

,where a number in first line  $E_{\rm FEERMI}^{\rm smear} = 0.1159252712507000D + 00~{\rm eV} = 8.520283353474250E-003~{\rm Ry}$ , the same as the previous one. This is a case when you did hqpe with augment 4 (it means we set the 4th-band eigenvalue zero). Another 3 values in the first line are shifts from TOTE. Shown eshift(eLDA) =  $0.7555207081466229D + 00~{\rm eV}$ . E.g., the second line shows

-0.1254883615775411D+02 eV= -0.1330435686590073D+02(in TOTE) + eshift(eLDA) eV.

When you do **hqpemetal**, three shfifts at the first line in TOTE2.UP is determined so as to give the eigenvalues relative to the Fermi energies shown in EFERMI, EFERMI.QP1, and EFERMI.QPz=1. These are Fermi energies by tetrahedron method.

As for **gwband\_lmf**, it recalculates eigenvalues for all **q** along SYML. Then the default "zerolevel" =  $E_{\text{FEERMI}}^{\text{smear}}$  - eshift(lda). Because the eigenvalues given by this band-mode are presumably the same, we have

Shown LDA eigenvalue

- = -13.18843159(raw data by band mode—same as that in VXCFP.chk) zerolevel
- = (-13.18843159 EFERMIsmear) + eshift(lda).
- = -0.1330435686590073D + 02( this is in TOTE.UP) +eshift(lda)
- = -0.1254883615775411D + 02 (this is in TOTE2.UP).

It means that values in TOTE2.UP recovers. But if raw data by band mode is different from it, these is a trouble. It does not recover the values in TOTE2.UP(=QPU).

As for the QPE, we calculate the difference from LDA values in TOTE2.UP at first, and add the difference to the Shown LDA eigenvalue.

### 11 mkGWIN\_lmf2 and its I/O Files

(QPNT.chk contains irreducible k point for given n1 n2 n3; KPTin1BZ.gwinit.chk contain all k points in Brillowin Zone).

The purpose of the script **mkGWIN\_lmf2** is to give a template **GWinput.tmp**. The script is complicated because of historical reasons. However, its essential is simple; we calls three executions in this script as

```
echo 0 \mid \text{Imfgw si}
echo 1 \mid \text{gwinit}
echo -100 \mid \text{qg4gw}
. We explain each by each.
```

### 11.1 echo 0|lmfgw

— makes SYMOPS LATTC CLASS NLAindx.

```
Input files
```

• GWINO: This is a file, which contains your supplied n1 n2 n3 when you invoke the script. This file is given within the script of mkGWIN\_lmf2 (as "here document").

```
cat <<EOF >GWINO
n1 n2 n3
$n1 $n2 $n3
cut
4.0 3.0
alpha
1
Number of bands
999 99999.0
999 3.0
```

• ctrl.si: Master input file of lmf calculation.

Output files

- LATTC: contains the information of primitive translation vectors, lmxa and konf. See ??
- SYMOPS: The point group operations. See ??
- CLASS : Equivalent atomic positions are called as 'class'. This small file contains a map between atomic site and 'class'.
- NLAindx: This file contains indexes  $(p_{\text{valence}}, l, a)$  for orbitals in the MT.  $(p_{\text{valence}} \text{ is radial function index}, a \text{ is atomic site index})$ . Eigenfunctions are expanded in this order.
- Idima : Number of MTOs for each atomic site. (this is used only from hqpe\_sc—QSGW mode).
- ves\*: not meaninful at this stage
- rhoMT\*: not meanigful at this stage

### 11.2 gwinit

```
Get GWIN_V2.tmp and QPNT.tmp
Input files
GWIN0:
LATTC:
SYMOPS:
NLAindx:
Output files
GWIN_V2.tmp: A part of GWinput.tmp
QPNT.tmp: A part of GWinput.tmp
(KPNTin1BZ.gwinit.chk): check KPNT in the 1BZ.
```

If SYML exist, **gwinit** gives also a templete QPNTforSYML.tmp suitable for such SYML. Here SYML specify how to plot the energy band. See explanation for **bandplot** script.

Note that LATTC SYMOPS CLASS NLAindx are overwritten when you execute  $\mathbf{gw\_lmfh}$  because we repeat  $\mathbf{echo}$   $\mathbf{0}|\mathbf{lmf}$  at the head of  $\mathbf{gw\_lmfh}$ .

### $11.3 \quad echo \ \hbox{-} 100|qg4gw$

— Generate GWinput.tmp

Input files

- GWIN0 : (copy of GWIN0.tmp by **gwinit**)
- GWIN\_V2 : (copy of GWIN\_V2.tmp by **gwinit**)
- QPNT : (copy of QPNT.tmp by gwinit)

Output files

• GWinput : (this is copied to GWinput.tmp)

This command "echo -100|qg4gw" is a file convertor from these two files into GWinput. And it is copied to GWinput.tmp. (mkGIN\_lmf keeps GWinput if it exist before you invoke it.).

### 12 gwsc script and its I/O Files

In **gwsc**, we have a loop of QSGW self-consistency. Look into the **gwsc** script. In each iteration, we perform these fortran programs;

```
NO_MPI=O #this is used for non-mpi versions of fortran program.
### self-consistent calculation for given Sigma(self-energy) ###
        run_arg '---' $MPI_SIZE $nfpgw
                                       /lmf-MPIK
                                                    11mf $TARGET
llmfgw00 $TARGET
argin=0;
         run_arg $argin $NO_MPI $nfpgw
                                         /lmfgw
argin=1;
         run_arg $argin $NO_MPI
                               $nfpgw
                                         /qg4gw
                                                    lqg4gw
                                                            #Generate requied q+G v
                                        /lmfgw-MPIK llmfgw01 $TARGET
         run_arg $argin $MPI_SIZE $nfpgw
argin=1;
         run_arg '---' $NO_MPI
                                 $nfpgw
                                        /lmf2gw
                                                    llmf2gw #reform data for gw
argin=0; run_arg $argin $NO_MPI
                                 $nfpgw
                                        /rdata4gw_v2 lrdata4gw_v2 #prepare files
argin=1; run_arg $argin $NO_MPI $nfpgw
                                         /heftet
                                                     leftet # A file EFERMI for hx0fp0
argin=1; run_arg $argin $NO_MPI $nfpgw
                                         /hchknw
                                                     lchknw # A file NW, containing nw
 ## Core part of the self-energy (exchange only) ##
 argin=3; run_arg $argin $NO_MPI $nfpgw
                                         /hbasfp0
                                                     lbasC # Product basis generation
 argin=3; run_arg $argin $MPI_SIZE $nfpgw
                                         /hvccfp0
                                                     lvccC # Coulomb matrix for lbasC
 argin=3; run_arg $argin $MPI_SIZE $nfpgw
                                        /hsfp0_sc
                                                     lsxC # Sigma from core1
 ## Valence part of the self-energy Sigma ##
 argin=0; run_arg $argin $NO_MPI $nfpgw
                                         /hbasfp0
                                                     lbas # Product basis generation
         run_arg $argin $MPI_SIZE $nfpgw /hvccfp0
                                                     lvcc # Coulomb matrix for lbas
 argin=0;
 argin=1; run_arg $argin $MPI_SIZE $nfpgw /hsfp0_sc
                                                     lsx # Exchange Sigma
                                                     1x0 $1x0_para_option #x0 part
 argin=11; run_arg $argin $MPI_SIZE $nfpgw /hx0fp0_sc
 argin=2; run_arg $argin $MPI_SIZE $nfpgw /hsfp0_sc argin=0; run_arg $argin $NO_MPI $nfpgw /hqpe_sc
                                                     lsc #correlation Sigma
                                                     lqpe #all Sigma are combined.
 run_arg:
```

Here a subroutine of bash **run\_arg** was used, which is given in ecalj/lm7K; it just invoke a command with the argument  $\frac{\text{sargin}}{\text{this}}$  is read by  $\frac{\text{read}(*,*)}{\text{in fortran}}$ . In cases with  $\frac{\text{MPI\_SIZE}}{=0}$ , mpirun is invoked. Console out put go to  $1^*$  files. For example,

argin=2; run\_arg \$argin \$MPI\_SIZE \$nfpgw /hsfp0\_sc lsc #correlation Sigma invokes hsfp0\_sc with argument '2' by mpirun with the -np \$MPI\_SIZE. Console outputs are written into logfiles such as lqpe. \$nfpgw contains path to the execution binaries.

In the followins, We explain input/output files for each fortran program. Note that "echo 0|lmfgw" means invoking lmfgw with argin=0.

### 12.1 echo 0 lmfgw si

See Sec.11.1.

### 12.2 echo 1| qg4gw

This makes  $\mathbf{q}$  points, and  $\mathbf{G}$  vectors for these  $\mathbf{q}$ . ( $\mathbf{q}$  was  $\mathbf{k}$  in previous sections.) Main routine of qg4gw is fpgw/main/qg4gw.m.F and calls fpgw/gwsrc/mkqg.F

Input files

- GWinput :
- LATTC :
- SYMOPS :

Output files

- QGpsi: (bin) q and G vector for the eigenfunction.
- QGcou: (bin) q and G vector for the Coulomb matrix
- Q0P: offset- $\Gamma$  points which are the replacement of the q=0 points. See section??.
- QIBZ: q points in the Irreducible BZ.
- BZDATA: (bin) BZ data for integration (include tetrahedrons if necessary). See e.g. main/hx0fp0.sc.F and search "call read\_BZDATA", which is a readin routine of this file defined in rwbzdata.F.
- $\bullet$  KPTin1BZ.mkqg.chk : list of q in the 1st BZ for check.
- QBZ: q point in the 1st BZ.
- EPSwklm : Required information for the BZ integration (mainly in order to evaluate the weitht in the  $\Gamma$  cell). See Eq.xxx in [?].

### 12.3 echo 1|lmfgw si

```
Calculate eigenfunctions, eigenvalues and \langle \psi | H_{\rm KS} | \psi \rangle
```

Input files

- ctrl.si :
- rst.si: (bin) Restart file of the lmf calculation. It contains all informations
- sigm.si: (bin) If this exist and
- QGpsi,QGcou,Q0P::
- NLAindx : :

Output files

- gwa.si : (bin) atomic data
- gwb.si : (bin) band data
- gw1.si : (bin)  $\langle \psi | H_{\rm KS} | \psi \rangle$
- gw2.si : (bin)  $\langle \psi | H_{KS} V_{xc}(n_{total}) | \psi \rangle$ .
- vxc.si,evec.si : (bin) used in hqpe.sc.m.f as "v\_xc" and "evec").

vxc.si contains  $\langle \psi | V_{xc}(n_{total}) | \psi \rangle$  including off-diaonal part. evec.si contains eigenfunctions.

• normchk.si: norm check (only for check) This is like this

```
head -20 normchk.si
                    IPW(diag)
0.805123
                                                  Onsite(phi)
0.562573
       IPW
                                  Onsite(tot)
                                                                      Total
    0.436015
                                     0.563972
                                                                     0.999988
    0.339134
                     0.620353
                                     0.660515
                                                     0.656881
                                                                     0.999649
                                     0.660516
                                                     0.656882
    0.339133
                     0.620353
                                                                     0.999649
    0.339133
                     0.620353
                                     0.660516
                                                     0.656882
                                                                     0.999649
    0.507738
                     0.648515
                                     0.492040
                                                     0.487673
                                                                     0.999778
```

This check is sometimes important for debugging and to determine the cutoff parameter QGcut\_psi. The first line (corresponding to 1st band of 1st q point) means that total normalization almost unity = 0.999988 = 0.436015 + 0.563972. Because we expand the MTO by IPW, the normalization is a bit different from unity, especially for higher bands. You can see that it get closer to unity for larger QGcut\_psi, though it does not reach to unity because of some contribution of the higher angular momentum contribution within MT. [Values of Onsite(phi) are not correctly shown in the case when you use local orbital.]

Due to historical reason, data in vxc.si and exec.si and others contains duplicated data.

### 12.4 lmf2gw

All the required informations are stored into DATA4GW\_V2 and CphiGeig.

Input files

- gwa.si :
- gwb.si :
- gw1.si :
- gw2.si :
- Q0P :
- CLASS :
- NLAindx :

Output files

- DATA4GW\_V2: (bin) Main data for GW calculations.
  - I/O of DATA4GW\_V2 is controlled by gwinput.f, which contains detailed informtaions.
- CphiGeig: (bin) Eigenfunctions for GW calculations.
- VXCFP.chk: Eigenvalue and Vxc check (only used for check) It is like this;

### LDA exchange correlation ###

# qve	C	i	.kp	iband	eigen	VXC(ntotal)	VXC(nvalence)	eigen(eV)	VXC(ntotal)(eV)	VXC(nvalence)
0.0000	0.0000	0.0000	1	1	-0.68505346	-0.91850436	0.00000000	-9.32070032	-12.49698668	0.00000000
0.0000	0.0000	0.0000	1	2	0.19292662	-0.99853478	0.00000000	2.62492096	-13.58586453	0.00000000
0.0000	0.0000	0.0000	1	3	0.19292763	-0.99853469	0.00000000	2.62493477	-13.58586334	0.00000000
0.0000	0.0000	0.0000	1	4	0.19292777	-0.99853461	0.00000000	2.62493664	-13.58586222	0.00000000

Here VXC(nvalence) is not used now. The eigenvalue in eigen is in Ry.

— This is the end of the preparation stage. —

From here, the main stage.

### $12.5 \quad rdata4gw_v2$

— Read DATA4GW\_V2 and some files, and decompose it into files required in the following GW steps. (checked! dec2014)

Input files

- GWinput :
- DATA4GW\_V2 :
- CphiGeig:
- QGpsi :
- QGcou :
- Q0P :
- QIBZ :
- SYMOPS : points group operations.

Output files

- hbe.d : datasize
- Core\_ibas\*\_l\*.chk : core eigenfucntions just for check.
- LMTO: basic date for the crystal.
- EValue : (bin) valence eigen value
- ECORE : core data and core eigenvalues
- $\bullet$  CPHI : (bin) Coefficients of eigenfunctions as for the atomic-like argumentation waves in MTs'.
- GEIG: (bin) Coefficients of eigenfunctions as for IPW.
- PHIVC: (bin) All the radial functions.
- @MNLA\_CPHI: index set for CPHI. This is not reffered just a check write.
- @MNLA\_core : index set for core. This is not reffered just a check write.
- VXCFP: (bin) this is for diagonal elements of  $V_{\rm xc}^{\rm LDA}(n_{\rm total})$ .
- PPOVLI.\*: (bin) Overlap matrix of IPW. xxxxxxxxx

- PPOVLG.\*: (bin) PPOVLGOverlap matrix xxxxxxxxxxxx IPW. not exactly the the overlap matrix. see around line 500 in rdata4gw.m.f
- PPOVL0: (bin) xxxxxxxxxxxx
- HVCCIN: (bin) Required inputs for hvccfp0. Informations in this files.
- NQIBZ : q point info. Only used for paralell test mode.
- normchk.dia: Norm check. These numbers should be almost the same as those in normchk.si

These files are input for the folloing steps. The name of file fooU means that it relates to up-spin. We have fooD files in the case of spin-poralized calculation with nspin=2.

### 12.6 echo 1 heftet

— Get the Fermi energy EFERMI by tetrahedron method. It is used in hx0fp0.

Input files

- EVU :
- BZDATA :
- GWinput :
- ECORE : (dummy)
- SYMOPS : (dummy)
- LMTO :
- hbe.d :

Output files

- EFERMI: contains Fermi energy given by the tetrahedron method. It is used in hx0fp0 but not in hsfp0.
- DOSACC.Ida, DOSACC2.Ida: They are lists of the all the eigenvalues from the bottom. DOSACC2.Ida is a list to show only the un-degenerated eigenvalues. They are just check write. But it is an indicater for you to determi esmr in GWinput.

#### 12.7 hchknw

— Calculte the required number of  $\omega$  points along real axis.

This NW is not essentially used in **gw\_lmfh** (but required as a dummy file). Only used in **gw\_lmf**.

Input files

- BZDATA :
- GWinput :
- ECORE : (dummy)
- SYMOPS : (dummy)

Output files

• NW : contains number of  $\omega$  points.

### 12.8 echo 3|hbasfp0

— Make product basis.

Mode 3 is for the core states. It generate a product basis on each MT suitable to expand to calculate the exchange part due to core. See explanations for the input file of GWinput.

Input files

- LMTO :
- PHIVC :
- GWinput :

Output files

- BASFP\*: (bin) Product basis functions
- PPBRD\_V2\_\*: (bin) Radial integrals on each MT, symbolly cally written as  $\int \phi(r)\phi(r)B(r)dr$
- PHIV.chk: Valence radial functions (for check).

### 12.9 echo 0 hvccfp0

— Calculate the Coulomb matrix in the Mixed basis

Input files

- HVCCIN:
- Q0P :
- BASFP\* :

Output files

- VCCFP: The Coulomb matrix expanded in the mixed basis
- Mix0vec: This is used only for dielectric-constant calculation (mode 2 or 3 of hx0fp0). This contains the expansion of the plane wave exp(iqr) in the mixed basis. See Usuda's note.

### 12.10 echo 3|hsfp0

— Exchange part of the self-energy for the core

Input files

- GWIN\_V2,LMTO,ECORE :
- CLASS :
- hbe.d :
- Q0P :
- PPBRD\_V2\_\* :
- CPHI :
- GEIG:
- VCCFP:
- PPOVL :

Output files

• SEXcoreU: The core part of the exchange self-energy for **q** and band index specified in <QPNT>. See 10.

### 12.11 echo 0|hsfp0

— Make product basis for the valence part.

### 12.12 echo 1|hsfp0

— Exchange part of the self-energy for the valence part.

Output files

- XCU: The LDA exchange self-energy for q and band index specified in <QPNT>. See 10.
- $\bullet$  SEXU : The valece part of the exchange self-energy for  ${\bf q}$  and band index specified in  $<\mathtt{QPNT}>.$  See 10.

### 12.13 echo 11|hx0fp0

— Screened Coulomb interaction W(sergey mode)

Input files

- GWinput, LMTO, ECORE, EVU:
- NW: dummy
- hbe.d :
- Q0P :
- PPBRD\_V2\_\* :
- CPHI,GEIG :
- PPOVL:
- VCCFP:
- ANFcond : (optional) This file is to specify antiferro condition. This should not exist for other cases. This file should be given by hand.

Output files

- WV.d : size of the dielectric function
- WVR: (bin) W-v in the expansion of mixed basis along the real axis

• WVI: (bin) W-v in the expansion of mixed basis along the imaginary axis

### 12.14 echo 12|hsfp0

— Corrlation part of the self-energy(sergey mode)

Input files

- GWinput, LMTO, ECORE, SYMOPS: These are readin by genallcf\_v3.
- CLASS, hbe.d, EVU, Q0P :
- PPBRD\_V2\_\* :

Radial integrals on each MT, symbolically written as  $\int \phi(r)\phi(r)B(r)dr$ . These are generated by hbasfp0.

- CPHI,GEIG:
- PPOVL:
- WV.d, WVR, WVI :

Output files

ullet SECU: The corrlation part of the self-energy for  ${\bf q}$  and band index specified in <QPNT>. See 10.

### 12.15 echo 0|hqpe

— Summarize the output

Input files

• SEXcoreU,XCU,SEXU,SECU : See 10.

Output files

- QPU: The QP energies and related value summary in human interface. See 10.
- TOTE : The detailed values of the QP energies. See 10.
- TOTE2: The detailed values of the QP energy. See 10. This is used for bndplot.

NOTE: For example, if you do {echo 4\$\\$hqpe}{hqpe}, it just shift zero level of QPE, so that 4th line (counted from top) eigenvalue (in QPU) is to be zero.

### 13 Check list for convergence on GW calculations

Results could be dependent on cutoff parameters in GWinput. In my opition, generally speaking, it is so easy to have convergence more than  $\sim 0.1 \mathrm{eV}$  for band gap...

### • Number of k points n1n2n3

Probably  $4 \times 4 \times 4$  (or  $6 \times 6 \times 6$ ) are reasonable choice for insulator in the case of two atoms such as GaAS. In other words, "used periodic cell volume" =  $4 \times 4 \times 4 \times 4 \times 4$  (# of atoms) × (Volume per atom)". For example, for  $2 \times 2^3 = 16$  atoms per cell, we can use  $2 \times 2 \times 2$  instead of  $4 \times 4 \times 4$  (this is the same as in the case of LDA).

For metals,  $12 \times 12 \times 12$  or more per atom may be required. But it depends on case by case.

• MTO's and APWs. Basis for eigenfunctions.

If we like to get "best converged results, we may need to use large enough MTO's. (I think the default setting is reasonable; but there is a room to change MTO settings in ctrl.\*.). But, in cases, we can not use large APW cutoff (pwemax) more than  $3.0 \sim 4.0$  Ry because of poor linear dependency of basis set (calculation in LDA level fails). In such a case, we need to use "smaller MT radius R=". Then we may need semi-core as local orbital when "its spillout in the outside of MTs is too large".

In GWinput, we can set the number of unoccupied states which you take into account by <code>emax\_chi0</code>, <code>emax\_sigm</code> nband\_chi0, and nband\_sigm. But we usually unset them except <code>emax\_sigm</code> for <code>gwsc</code>.

(We may need a kind of completeness of the basis set; the completeness could be important from the view of 'Coulomb hole' picture.)

NOTE: Current PMT-QSGW method [?] expand the static version of self-energy of QSGW just in the basis of MTO's (no APWs). Thus the expansion can be unsatisfactory (it depends on case by case, and requied convergence). In such a case, we inevitably have to use empty spheres (MTO's) which is for empty region.

#### • Cores.

We usually use all cores as **core1** (exchang only core). If necessary, it is better to treat shallow cores by the local orbitals (such cores are treated as valence).

If we treat cores by **core2** (not only for exchange, but also in dielectric functions), we have to be careful about the core wave orthogonalization with respect to valence eigenfuncitons; this is a little complicated; probably it is better not to use **core2**).

(This is related to CoreOrth (only for core2). If it affects so much, D function might be too poor due to the poor orthogonality condition between core and valence.) (NOTE: CoreOrth is not maintained recently)

- QpGcut\_psi IPW cutoff to expand eigenfunctions in the interstitial region. We usually use QpGcut\\_psi 4.0. Usually not so bad. Larger is better but expensive. You may test calculations with QpGcut\\_psi 3.0, and how much difference of results.
- QpGcut\_cou IPW cutoff to expand the Coulomb interaction in the interstitial region (Mixed product basis(MPB) consist of this IPW and PB). interstitial region. We usually use QpGcut\\_cou 3.0. Usually not so bad. Larger is better but expensive. You may test calculations with QpGcut\\_cou 2.5, and how much difference of results.
- Product basis section.

At least, lcutmx=4 will be necessary for atoms with d electrons. (but lcutmx=2 look reasonable for oxygen, for example).

#### • esmr

In our experience, esmr=0.003000 (default) is reasonable. But there is a room to check stability on it for metals. In prinicple, for larger n1n2n3, we can use smaller esmr.

### • dw, omg\_c | niw

It will be worth to try to check how much the results changed due to them. But usually dw=0.005, omg\_c=0.04 is not so bad a choice. As for niw=10 seems to be not so bad usually, but it is safer to check the convergence on it (test cases with niw=6,10,12,16).

- $\bullet$  deltaw.  $\sim 0.01$  a.u. will be not so bad. See two Z values shown in SXCU. It is better to try to check how about the dependence on this.
- chi\_regqbz off. (on is default). If off, we use off-Gamma mesh (Gamma point is between mesh points) for dielectirc functions when we perform GW or QSGW. "chi\_regqbz off" may accelarate convergence on number of k points.

### 14 Linear response calculations

With these scripts for linear response calculations, eps\*, we can calculate **q**-dependent dielectric function  $\epsilon(\omega, \mathbf{q})$  (and v, W) (and  $\chi$  for spin fluctuation). But (because of numerical reason), we can not use  $\mathbf{q} = 0$  limit. (if  $|\mathbf{q}|$  is too small, we have numrical problem, zero divided by zero, because we have not implemented the version to use  $\mathbf{q} = 0$ .)

#### • eps\_lmfh

Dielectric function epsilon with local field correction. Expensive calculation (we may need to reduce number of wing parts in future...).

- epsPP\_lmfh epsilon without local field correction.  $1 \langle e^{i\mathbf{q}\mathbf{r}}|v|e^{i\mathbf{q}\mathbf{r}}\rangle\langle e^{i\mathbf{q}\mathbf{r}}|\left(\chi^0\right)|e^{i\mathbf{q}\mathbf{r}}\rangle$
- epsPP\_lmfh\_chipm

For spin susceptibility. This essentially calculate non-interacting spin susceptibility. Then it is used for the calculation of full spin susceptibility with util/calj\_\*.F programs (small quick programs). See spin wave paper. See spin susceptibility section Sec.??.

- (not maintained now; we will recover this)eps\_lmfh\_chipm
   This gives full non-inteacting spin susceptibility. Testing. We have to determine U (stoner I) for the determination of full spin susceptibility. TDLDA? or so?
- (This is old mode --- not maintained) epsPP\_lmfh\_chipm\_q For spin susceptibility, spin susceptibility  $\langle e^{iqr}|\chi(q,\omega)|e^{iqr}\rangle$  In this script, You have to assign that isp=1 is majority, isp=2 is minority. This is with long wave approximation.
- We use the histogram method (the Hilbert transformation method); we first calculate its imaginary parts with the tetrahedron technique for dielectric functions. Then we get its real part by the Hilbert transformation.

You need to choose dw,omg\_c. The width of histrgram bins are getting larger when omega gets larger. dw is the size of histogram-bin width at omega=0. At omega=omg\_c, its width gets twiced.

To plot dielectric function with reasonable resolution, it might be better to set  $dw \ 0.001$  and  $omg_c \ 0.1$  for example. You may have to choose small enough omega for spin wave mode as 0.001 Ry (Or smaller). omg\_c is given like 0.05 Ry or so. But sometimes it can be like 1Ry. • epsPP\_lmfh only calculation an matrix element of dielectric function for exp(iqr). Thus very faster than eps\_lmfh mode. It uses a a special product basis set for cases without inversion (problem is in how to expand exp(iqr) in the MPB; the product basis is not from phi and phidot, but from spherical bessel functions).

In \*\_lmfh\_\* modes( I now use little for \*\_lmf\_\* modes), you can use small enough delta. Use small enough delta (=-1e-8 a.u.) for spin wave modes (also you can use it for dielectric function and GW). This is necessary because pole is too smeared if you use larger delta.

### 14.1 eps\_lmfh, epsPP\_lmfh: the dielectric functions

You can invoke the script, e.g. as "eps\_lmfh si".

Specify  ${f q}$  point in <QforEPS> or so. Mesh for  $\omega$  is specified by  ${f dw}$ , omg\_c

The obtained datas are in EPS\*.dat and EPS\*.nlfc.dat. EPS\*.nlfc.dat contains the result without local-field correction EPS\*.dat contains the result with local-field correction (this is generated only for eps\_lmfh. Both of them contains

 $\mathbf{q}(1:3), \, \omega, \, \mathrm{Re}(\epsilon) \, \mathrm{Im}(\epsilon), \, \mathrm{Re}(1/\epsilon), \, \mathrm{In}(1/\epsilon)$  in each line.

• This code works OK only for  $\mathbf{q}$  is near 0. Be careful for  $\mathbf{q} \to 0$  limit. Too small  $\mathbf{q}$  can give strange spectrum at high energy (real part is affected by it)

Because  $\mathbf{q} \to 0$  gives too large cancelation effects (the denominator and numerator go to zero—it means we need very accurate orthogonalization between occupied and unoccupied states). This is a kind of disadvantage of our method (though there is an advantage— our code can calculate dielectric function even for metal as far as you use large enough number of  $\mathbf{k}$  point.)

- The calculaten of dielectric functions usually requires so many k point. For example, for Si, n1 n2 n3 = 4 4 4 is too small. It gives too large dielectric constants  $\sim 19.4$  though the converged value should be  $\sim 13$ . (we need 10x10x10 or more like 20x20x20 for some reasonable results). For GaAs, we observed that reasonable  $\epsilon(\omega)$  requires rather large number of  $\mathbf{q}$  points lke 15x15x15 or 20x20x20 for  $\boxed{\text{n1n2n3}}$ . This is too time-consuming to get result (but you can use "very small product basis" (just sp poralization for this purpose; it makes speed up so much). Or, you can calculate " $\epsilon(\omega)$  without LFC". See section for  $\mathbf{eps\_PP\_Imfh}$ .
- Core orthogonalization problem (only when core2 is used) ——CoreOrth is not maintained recently ——CoreOrth gives so serious effect for  $\epsilon(\omega)$ , if you include some cores as "core2" in the product basis setting. (This means that you includes transitions from "core2 to valence" in the calculation of  $\epsilon(\omega)$ ).

Then you have to use "CoreOrth on". Without it, you will have rather large imaginary part at rather high energy Such transitions from core to higher valence bands is artifical due to the incomplete orthogonality between core and the higher bands. However, shallower d semi-core might be deformed too much by this option. Try to plot Core\_\*.chk files, which contains core radial functions. Anyway, it is better to treat shallow core as valence by "local orbital".

### 14.2 epsPP\_lmfh: the dielectric function(No LFC—faster)

You can calculate  $\epsilon$  without LFC by **epsPP\_lmfh**. It is very faster than **eps\_lmfh**.

To calculate  $\epsilon(\mathbf{q}, \omega)$  without LFC accurately, the best basis set for the expantion of the Coulomb matrix within MT is apparently not the product basis, but the bessel functions corresponding to the plane waves  $\exp(i\mathbf{q}\mathbf{r})$ . We use such a basis in this mode. However, our experience shows that the changes are little even with the usual product basis (we don't describe this here).

### 14.3 How to calculate correct dielectric function?

(this subsection is essentially ok... but need to clean it up. dec2014)

There are prolems to calculate correct epsilon. At first, we talk about epsPP\_lmfh, which is No LFC. Main problem are

Roughly speaking, 20x20x20 is required for not-so-bad results for Fe and Ni. It is better to do 30x30x30 to see convergence check.

However, in the case of ZB-MnAs (maybe because of simple structure around Ef), it requires less  ${\bf q}$  points.

```
figs are for GaAs.
fig001: n1n2n3 convergence for Chi_RegQbz = on case.
fig002: n1n2n3 convergence for Chi_RegQbz = off case.
(Chi_RegQbz in explained in General section in this manual).
```

<sup>1.</sup> Convergence for number of k point(specified by n1n2n3).

As you see, k points convergence looks a little better in Chi\_RegQbz=off (mesh not including gamma). However a little ploblem is that its thereshold around 0.5eV is too high and slowly changing.

fig003: Alouanis'(from Arnaud) vs. ''Chi\_RegQbz = on'' vs. ''Chi\_RegQbz = off''
As you see, the threshold of the Red line (20x20x20 Chi\_RegQbz=on) and Alouani's
are almost the same, but the red line is too oscilating at the low energy part.
On the other hand, ''Chi\_RegQbz = off'' in Green broken line is not so satisfactory
at the low energy part.

fig.gas\_eps\_kconf.pdf shows the convergence behavior of epsilon for

2.\$q \to 0\$ convergence (this is related to whether Chi\_RegQbz=on or off).
 If you use very small q like q=0.001 is GaAs, it can cause a problem.
 Use q=0.01 or larger (maybe q=0.02 or more is safer).
 Very small q can give numerical error for high-energy region.

In fig004, we show the high energy tail part of Im \$\epsilon(\omega)\$ for GaAs case. At q=0.01 (this means q= 2\*pi/alat \* (0 0 0.01)), the imaginary part is a little too large. Less than 80eV, q=0.02 gives good results when compared with other high q results, though it still has noise above 80eV.

In fig005, I showed the same results compared with Alouani's (his is up to 40eV). Both gives rather good agreements. As you see, q=0.06 or above might be necessary to get reasonable convergence for high energy part abouve 40eV.

We have to be careful for this poorness in high energy part--- it may effect low-energy Re[\$\epsion\$] through KK relation. However this can be very small ehough.

In fig.gas\_eps\_qconv.jpg, we checked the convergence of eps ( $\odots$  omega=0,q) for q \to 0. As you see, it gives convergence, however, q=0.01 is a little out of curve---this should be because of the poorness in the high energy part. so q=0.02 or q=0.03 is safer, and you can get eps within 1 percent accuracy.

3. Including Core for dielectric constant is dangerous. It can cause very poor results if you include core part in GWinput. You need to include core just as valence (with local orbital).

In fig008, we showed core effects. It starts from  $\approx 16eV$  (this is core to conduction transition).

fig007 showd the check about the  ${\bf q}$  point dependence---even with large  ${\bf q}$ , it would not change.

These shows that the core excitation can have larger energy range.

This is in contrast to the valence case

(then the most of excitaion is limited to less than  $10\mathrm{eV}$ ).

We have to be careful for such high-energy exciation... The LMTO basis might be not so good for high energy.

4. basis set.

Use QpGcut\_psi \approx 3.0 a.u. or so (as same as GW calculation).

In the case of epsPP\* mode,
QpGcut\_cou can be very small--- In our codes now,
ngc>=1 should be for all q vector shown in lqg4gw02 (output of echo 2|qg4gw).

[In principle, it should be only for the q vector for which we calculate epsilon.
But there is a technical poorness in our code--(maybe) a problem here; the plane-wave part of the eigenfunction generated

-- eps\_lmfh: including LFC ------To include eps with LFC, do eps\_lmfh.
But lcutmx=2 seems to be good enough to get 0.5 percent error (maybe better than this).
Test it 10x10x10 or so. (I need to repeat if necessary).
Further you can use smaller QpGcut\_cou like 2.2 or so,
with rather smaller product basis (up to p timed d, not including f).


Note: epsPP\_lmfh is designed to use good basis to calculate eps without LFC. This is usually in agreement with what you obtained by eps\_lmfh; however it can give slight difference when you use small product basis.


---Summary ------So in conclusion, I think a best way to do is


1. set q=0.02 [q=2pi/alat(0 0 0.02)] or so for GaAs case. If you want to check, do q=0.03 and q=0.06 also.


''Chi\_RegQbz = off'' is better for matrials like GaAs with direct gap.

- 2. You can use small QpGcut\_cou but all ngc should be one or more.
- 3. As for the Product basis setting in epsPP\* scripts, only lcutmx and tolerance (this can be like 0.001 or so) are relevant. E.g. set lcutmx=4 or so.
- 4. Do nk=20 18 16 and take interpolarion to determine eps(omega=0, q=0).
- 5. To get eps with LFC, set QpGcut\_cut as xxx, and set lcutmx=2 where (occupied sp) \timex (unoccupied spd) are included. But correct EPS\*.nolfc.d is rather from epsPP\_lmfh script.









# gas<sub>e</sub>ps0<sub>b</sub>z2<sub>1</sub>61616<sub>4</sub> High energy part (numerical error)




fig004

0.4




fig005





fig007



### 15 Used files

### 15.1 @MNLA\_CPHI

m	n	l ibas			
0	1	0	1	1	1
0	2	0	1	2	2
-1	1	1	1	3	3
0	1	1	1	4	3
1	1	1	1	5	3
-1	2	1	1	6	4
0	2	1	1	7	4
1	2	1	1	8	4
-2	1	2	1	9	5
-1	1	2	1	10	5
0	1	2	1	11	5

m is a magneite quantum number, n is the dgree of freedom which means  $1:\phi,2:\dot{\phi}$ , and 3: local orbital. I is the orbital angular quantum number. The match of orbitals and m number is shown by **job\_pdos** command. The folloiwing number is the number of atom. And the next is the numerating number. It corresponds to the number in GWinput which is the most left one in the initial conditions.

### 15.2 CPHI and GEIG

We exapnd the eigenfunctions as the sum of the augmentation parts in MTs and the PW parts in the interstitial region:

$$\Psi_{\mathbf{k}n} = \sum_{\mathbf{R}u} \alpha_{\mathbf{R}u}^{\mathbf{k}n} \phi_{\mathbf{R}u}^{\mathbf{k}}(\mathbf{r}) + \sum_{\mathbf{G}} \beta_{\mathbf{G}}^{\mathbf{k}n} P_{\mathbf{G}}^{\mathbf{k}}(\mathbf{r})$$

Here, **CPHI** contains the information of  $\alpha_{\mathbf{R}u}^{\mathbf{k}n}$  and **GEIG** contains  $\beta_{\mathbf{G}}^{\mathbf{k}n}$ .

### References

- [Kotani et al. (2015) Kotani, Kino, and Akai] T. Kotani, H. Kino, and H. Akai, Journal of the Physical Society of Japan 84, 034702 (2015).
- $[ \text{Kotani}(2014) ] \ \text{T.} \qquad \text{Kotani}, \qquad \text{J. Phys. Soc. Jpn. } \textbf{83}, \ 094711 \ [11 \ \text{Pages}] \ (2014), \\ \text{WOS:} 000340822100029.$
- [Kotani and van Schilfgaarde(2002)] T. Kotani and M. van Schilfgaarde, Solid State Communications 121, 461 (2002).
- [Friedrich et al. (2012) Friedrich, Betzinger, Schlipf, Blügel, and Schindlmayr]
   C. Friedrich, M. Betzinger, M. Schlipf, S. Blügel, and A. Schindlmayr,
   Journal of physics. Condensed matter: an Institute of Physics journal 24, 293201 (2012).
- [Kotani and van Schilfgaarde(2010)] T. Kotani and M. van Schilfgaarde, Physical Review B **81**, 125117 (2010) [5 pages] (2010).
- [Soler and Williams(1989)] J. M. Soler and A. R. Williams, Phys. Rev. B 40, 1560 (1989).
- [Soler and Williams (1990)] J. M. Soler and A. R. Williams, Phys. Rev. B 42, 9728 (1990).
- [Bruneval and Gatti(2014)] F. Bruneval and M. Gatti, in First Principles Approaches to Spectroscopic Properties of Complex Materials, Vol. 347, edited by C. Di Valentin, S. Botti, and M. Cococcioni (Springer Berlin Heidelberg, Berlin, Heidelberg, 2014) pp. 99–135.
- [Rath and Freeman (1975)] J. Rath and A. Freeman, Phys. Rev. B 11, 2109 (1975).