



KTU ASSIST

a ktu students community

www.ktuassist.in



KTU STUDY MATERIALS



**APJ ABDUL KALAM
TECHNOLOGICAL UNIVERSITY**

DOWNLOAD KTU ASSIST APP FROM PLAYSTORE

KTU ASSIST | www.ktuassist.in

MODULE 2

ASSEMBLERS

- * Assemblers convert assembly language into machine language.

Fundamental functions of assembler

- * Translating mnemonic opcode to mc lang equivalences.
- * Assign mc addresses to symbolic labels use by the programmer.

Assembler Directives/PSEUDO INSTRUCTIONS

The assembler must also processes statements called statement directives. These stmts are not translated into mc instructions instead they provide instructions to the assembler itself.

e.g: Declarations, START, BYTE, . . .

START: Specify the name and starting address for the program

END: Indicate the end of the source pgm.

BYTE: Generate char/ hexadecimal constants

WORD: Generate one word integer constant
RESERVE BYTE: Reserve the indicated no: of bytes for a data area

RESERVE WORD: Reserve the indicated no: of words for a data area.

SIC ASSEMBLER

- 1: Convert mnemonic opcode to their m/c lang equivalent
- 2: convert symbolic operands to their equivalent m/c address
- 3: Build m/c instructions in proper format
- 4: Convert data constants specified in the source pgm into their internal m/c representations.
- 5: Write object pgm and assembly list file

Format of object code

- Header - Pgmn name
- Text
- End

Header \rightarrow Pgmn name

Starting address 18-13
length 14-19

Text \rightarrow Starting address 1
length of object code 2-7
obj. code 8-9
14-19

End \rightarrow address in pgmn where execution is to begin 2-7

eg: obj. code: HCOPY 100-1000,00107A
Length: 14-19
• TA 0010001E,141033
• E1001000

eg: JLT MOVECH when reached at MOVECH assemble keeps it as blank. Then reached for execution at the MOVECH, it will be filled

MOVECH

The problem with conversion of symbolic operands to m/c address comes when there is a forward reference. A fwd reference is the reference to the label ie defined later in the pgm. Hence we use a two pass assemble.

The first pass scans the source pgm for label definitions and assigns addresses. Second pass perform actual translation.

FC's of 2 pass assemble.

Pass 1 (define symbols)

- 1: Assign address to all symbols in program
- 2: Save the address assigned to all labels for use in pass two.
- 3: Perform some processing of assembly directives

Pass 2 (assemble instructions & generate obj. programs)

1: assemble instructions

- 2: Generate data values define by BYTES, WORD, ...
- 3: Perform processing of assembly directives not done in pass one

4: Write object program and assembly listing

e.g. MOVECH LDA ALPHA Symb.name

ALPHA WORD 1 ass. directive

Op code, ass. dire - predefined

Symb. name, label - defined by programmer.

op code, ass. dire → ASSEMBLER → M6 lang equiv

Symbolic-label, name → ASSEMBLER → gen. will generate m6 address

Then creates object code:

e.g. LDA ALPHA obj. code → 00000303 / 00000000

Registers to destination

* Two types of assemblers

a) 1 pass assembler

b) MULTI-PASS → 2 pass assembler

main() what is main heading in multi-pass?

{ int a; } good use of bracket

int b = c; assigned first among declared is the problem

int c = 100; forward reference.

a = b + c; }

DATA SECTION

* In 1-pass assembler forward referencing is not possible. So we use multi-pass assembler

Assembly data structures

Two types of symbols for Assembler

1) op code → OBTAB

2) Symbolic names → SYMTAB

3rd

OPTAB: is used to lookup mnemonic opcodes and translates them to their m/c language equivalent.

SYMTAB: is used to store addresses assigned to label

LOCCTR: (Location Counter): is a variable is used to help the assignment of addresses.

Locctr is initialized to the beginning address specified in the Start Stmt. After each source statement is processed the length of the asse. instrn or data area is added to the LOCCTR. So, Even if we reach a label in source pgm the current value of LOCCTR is the addr. of the label.

OPTAB

opcode	m/c lang
ass. direct	instrn format length

SYMTAB

Symb	m/c address
	(nor flag)
	Type
	length

- Predefined
- Hash table.

- Blank table. first
- Program's initial data
- Hash table.

Pass 1:

In pass 1 ^{check} whether opcode is in OPTAB

Pass 2:

In pass 2 writes its equivalent machine language into object code.

SYMBTAB:

In pass 3 sym.name, and its name enter then in pass-2 it is written to objectcode.

TW
During pass-1 OBTAB is used to look up and validate operatn code in the source pgm. In pass-2 it is used to translate the opcode to machine language.

During pass-1 of assemble labels are entered into symbtab as they come in the source pgm along with their assigned address from LOCCTR also During pass-2 Symbols used as operands are looked up in symbtab to obtain the address to be inserted in the assemble instructions.

Pass-1 writes an intermediate file.

that contains each source statement together with its assign indicators, error indicators etc.. This file is used to input to Pass-2. This working copy of the source Pgm. can also be used to retain the results & certain operations that may be performed during pass-1. As there need not be pc" & pass-2 by pointers into OPTAB & SYMTAB may be retained for each opcode and symbol used.

Line Loc Source Stmt Obj. Code.

000 Loop CLEAR X

label opcode operand

eg: LOC
000 START 0000
LDA #5
STA ALPHA
LDCH #90
STCH

At First Pass 1.

- Location fills
- opcode check whether it includes it or not
- symtab fill Variable Entered (ALPHA).

- Implement assembly directives.
- After pass 1 there will be an intermediate file.
- At pass-2
- OPTAB - Translates to machine language
- SYMTAB - machine address

Fig 2.4 (a) Pass-1 algorithm.

Fig 2.4 (b) Pass-2

Machine Dep Assembly Features.

op m Base/pc addressing mode. plb=1
op #c Immediate i=1 n=0
op @m indirect i=0 n=1
op m,n index addressing mode. x=1
TOP:m extended i="000" e=1

→ Predefined numbers of registers.

A	0	00000000
X	1	01000000
L	2	10000000
B	4	00000000
S	4	00000000
T	5	00000000
F	6	00000000
PC	8	00000000

Address Translation:

eg1

0000 FIRST STL RETADR Program defined label
 0003 ^{Program}
^{defn}
^{label} OP VARIABLE
 :
 0030 RETADR RESW 1

Opcode	n	i	x	b	p	e	displacement
	1	1	0	0	1	0	

displa = Target address - PC. ^{address of next instruc}

$$TA = PC + displa$$

$$\text{displacement} = 0030 - 0003 \\ = 002D. = 020 \text{ (hexadecimal)}$$

$$\text{opcode} = \begin{array}{cccccc} 0001 & 01 & 00 & & 0000 & 0010 & 1101 \\ \hline 0001 & 0111 & 0010 & & & & \end{array}$$

eg2. Base Register

12	LDB #LENGTH	STCH	154
13	BASE LENGTH		
:			
100	0033 LENGTH RESW 1		
105	0036 BUFFER RESB 1		
:			
160	104E STCH BUFFER, X -54.0036		
165			

Opcode	n	i	x	b	p	e	displacement
	1	1	1	1	0	0	003

$$TA = B + \text{disp}$$

$$\text{dis} = TA - B \\ = 036 - 033 = 003$$

0101	01	00	111	00	003
------	----	----	-----	----	-----

0101	0111	1100	003
5	7	C	

24/8/17 0006 CLOOP + JSUB RDREC

0017 J CLOOP - PC relative addressing mode.
 001A ENDFIL LDA EOF
 opcode - JSUB, J, LDA

(format: address label opcode)

J 13C

Opcode	n	i	x	b	p	e	disp
	0	1	1	1	0	0	-

$$\text{displacement} = TA - PC \\ = 006 - 001A \\ = 006 - 001A-1100 \\ = 006 - 001A-0010 \\ = 006 - 0010 \\ = 0000$$

0000 0000 0110 -

2' complement of

$$\begin{array}{r} 0000 \quad 0001 \quad 1010 \\ \underline{-} \quad \underline{\underline{000}} \quad \underline{\underline{+}} \\ 1111 \quad 1110 \quad 0110 \end{array}$$

disp = TA - PC

$$= 0006 - 01A$$

$$\begin{array}{r} 0000 \quad 0000 \quad 0110 \\ + \quad 1111 \quad 1110 \quad 0110 \\ \hline 1111 \quad 1110 \quad 1100 \end{array}$$

F E C

Opcode	n	i	x	b	P	e	displacement
0011 11	0	0	1	0	FEC		
0011 1110	0010						FEC

• Immediate

Q1 0020 LDA #3

Q2 1030 +LDT #4096.

LDA | 00

A1 Extended and immediate addressing mode

Opcode	n	i	x	b	P	e	displ
0000 00	0	01	0	0	0	0	003

displacement b = 3

$$= 003$$

0

Opcode = 0000 0000 0000 0000 0000 0011
0 1 0 0 0 3

Q2 1030 +LDT #4096 LDT | 74

4 Extended and immediate addressing mode

Target address = value at location.

Opcode	n	i	x	b	P	e	displacement
0100 0000	1001	0	100				

displacement = 4096

0100 0000 1001 0110

convert 4096 to hexadecimal.

$$= (1000)_16$$

$$2^{12} = 4096$$

$$(100000000000)_2$$

16	4096
16	256
16	16
16	1 0

Since it is extended use format & therefore displacement have 6 bits.

opcode	n	i	n	b	P	e	display	hex
0111 0100	0	1	0	0	0	1	←	00 3000
								0000 0000

0111 0101 0001 01000 → 0000 - 3000

- Immediate + PC - Relative

0003 LDB #LENGTH.
 0006 :
 0033 LENGTH RESW !
 LDA 00
 LDB 78, 68
 LDT 674.

$$dis = TA - PC$$

$$= 033 - 006$$

- max disp
- 1) IF \$AM (Instruction format and Addressing)
 - 2) Program Relocation.

modification record

ALP using assembler

```

PROG START: AND opcode 0000
0000 LDS #3 → 6D0003
0000 LDT #30 - 75001E11 0000
0003 LDX #00 - 050000 0000
0006 LOOP LDA ARR1,X - 03A014
0009 ADD ARR2,X
000C STA ARR3,X
000F ADDR S,X - 9041, T015
0012 CMPR X,T - A015
0014 JLT LOOP
0016 END PROG! 0010-1110
0019 ARR1 RESW 10 1010 1110
0020 ARR2 RESW 10
0040 ARR3 RESW 10
0060
  
```

LDS	66	JLT	38
LDA	00	ADD	18
LDT	74	ADDR	90
LDX	04	CMPR	A0
STA	0C		



- LDS #3

LDA ARRI,X.

0016 JLT LOOP

$$\text{displacement} = 0.9 - 0.9$$

$$\text{opcode} = 38 \rightarrow 0011$$

13/01/17

FIRST LDS #3

Opcode	n	i	x	b	Pc	displacement
0	1	0	0	0	0	3

D110 1100

0110 1101 0000 .0000 0000 0011
↓ ↓ ↓ ↓ ↓ ↓
7 2 8 8 8 3

→ LDT #60

Opcode	<i>h</i>	<i>i</i>	<i>r</i>	<i>b</i>	<i>p</i>	<i>e</i>	displacement
74	0	1	0	0	0	0	3C

0111 0100

0111 0101 0000 0000 0011 1101
↓ ↓ ↓ ↓ ↓ ↓
1 5 8 0 3 C

$\rightarrow \text{LDX } \#0$

Opcode	n	i	x	b	P	e	displacement
04	0	1	0	0	0	0	0

0000 0100
~~0000 0100 0000 0000 0000 0000~~

$\downarrow \quad \downarrow \quad \downarrow \quad \downarrow \quad \downarrow \quad \downarrow$
~~0 5 6 0 0 0~~

 $\rightarrow \text{STX SUM}$

$$\text{displacement} = TA - PC \\ = 0033 - 000C$$

0 0 3 3
~~0000 0000 0011 0011~~

2's complement of 0000C:

0000 0000 0000 1100
 $\downarrow \quad \downarrow \quad \downarrow \quad \downarrow$
~~0 0 0 C~~
~~0000 0000 0011 0011~~
~~0000 0000 0000 1100~~

$$TA - PC = 033 - 00C$$

$$= 027$$

Opcode	n	i	x	b	P	e	displacement
10	0	0	0	0	0	0	027

0001 0000

12-27-13-2027

$\rightarrow \text{LOOP LDA ARR1,X} - 03AFF1$
 $\text{ADD SUM} - 18\ 2021$
 $\text{STA SUM} - 0E201F$

14-6-14 LDT-14, LDA-00, ADDR=90, SUB-7C

STA-OC,

$\rightarrow \text{LDT NUM}$

Pc-addressing mode

Opcode	n	i	x	b	P	e	displacement
74	1	1	0	0	1	0	0

$$\text{displacement} = TA - PC = 007D - 005B$$

0 0 5 B (2's complement)

$0101 \ 1011$

$1010 \ 0101$ 2's - PC

$1D \rightarrow 0111 \ 1101 = TA$

$1010 \ 0101 +$

$0000 \ 0010$

$02 \ 42$

Displacement = 022

110010 ?

A) ~~11022~~

2) LDA ALPHA

opcode for LDA = 00

displacement = TA - PC

= 0011 - 005E

0 0 5 E

0000 0101 1110

1111 1010 0010 2's complement

1111 1110 0000

* * 0 0 5 E

0000	0111	0001
1111	1010	0010
0000	0001	0011
0	1	3

Opcode	n	i	x	b	P	e	displacement
00	1	1	0	0	1	0	013

1) 032013

3) ADDR T A - 9050.

4) SUB #8

immediate addressing mode

displacement = 8

+ 1000

SUB = 1 C \Rightarrow 0001 1100

Opcode	n	i	x	b	P	e	displacement
0001	0	0	0	0	0	0	1000

0001 1100

1 D 0 8 0 0 8

STA SUMI
 opcode = 0C
 = 0000 1100 1000 0000
 displacement = TA - PC
 = 0074 - 0066
 Displacement = 0000 0110 0110 0110
 1111 1001 1010 2's complement
 0000 0111 0010 0
 1111 1001 1010
 0000 0000 1110
 ↓ ↓ ↓
 0 0 E
 Address field
 1000 COPY START' 1000
 1000 EOF BYTE C'EOF'
 1008 THREE WORD 3
 1006 ZERO WORD 0
 1009 RETADR RESW 1
 100C LENGTH RESW 1
 100F BUFFER RESB 4096
 200F FIRST STL RETADR
 JSOB RDREC
 LENGTH LDA LENGTH
 COMP ZERO
 2012
 2015

201B JEO ENDFIL
 201E JSUB WRREC
 2021 J CLOOP
 2024 ENDFIL LDA EDF
 2027 STA BUFFER
 202A EDA THREE
 202D STA LENGTH
 2030 JSUB WRREC
 2033 LDL RETADR
 2036 RSUB ADDR-90, STA-0C.
 JSUB-48, COMP-28, JEQ=30, J=36
 LDL-08, RSUB-4C, STL-14, SUB-1C
 LDT-74, LDA-00, ADDR-90, STA-0C.
 Displacement = TA - RC
 = 1029 - 2012
 0010 0000 0001 0010
 1101 1111 1110 110 2's

STL READRR

11111111 101
 00000000 1001
 11111110 1110
 E F F 8

$$\begin{aligned} \text{Displacement} &= TA \\ &= 1009 \end{aligned}$$

opcode	n	i	x	b	P	e	displacement
0001	0	0	0	1	0	1009	

0001 0100

0001 0100 = 0010 + 1009
 ↓ ↓
 1 401 DATA 36 module

16/9/17 Machine Independent features


- 1) Program blocks
- 2) Control sections.
- Any machine can use program block as well as control sections.

Program blocks
 Segments of code which are rearranged within a single object program blocks.

Assembler directives

START	END
BYTE	RESB
WORD	RESW
BASE	NO BASE
USE	

- A program can be divided into different blocks, it is used for correct arrangement & rearrange the program.
- A block without assemble directive (USE) then that block is default.



There is a LOCCTR for each block.

BLK name	BLK NO	SADAL	LENGTH
default	0	0000	0100
ABLK	1	0103	0000
BBLCK	2	0000	0000



Opcode	n	i	α	b	p	e	displacement
00	1-1	0	0	1	0		

$$\text{displacement} = T_A - P_C$$

$$TA = TA + \text{Starting add of stack.}$$


= 0003 + 0066
 = 0069
 displacement = 0069 - 0009
 = 0060
 0110 0116
 0011
 0110 1000
 0110 1001
 STL 14
 000 0 STL RETADR
 003 6
 RETADR RESW 1
 000
 31K 0 0000
 BLK 1 0066
 001 0100
 code n i x b p e dis
 1 1 0 0 1 0 . 068
 TA = TA + stacking of stack
 = 0000 + 0066
 = 0066
 esp = TA - PC = 0066 - 0003
 = 0063

opcode	n	i	x	b	P	e	disp	0000 0000 0011	1111 1111 110b
00	11	00	10	063					
0000 00 00					1111	1111	1101		
0000 00 11	0010	063	0000	0110	0110				
(0 3, 2, 063)				1111	1111	1101			
				0000	0110	0011			

CONTROL SECTIONS

Three data structures are used they are

1. Control Section [SECT]
2. External definition [EXTDEF]
3. External reference [EXTREF]



In control section records are

- 1) Header
- 2) Text
- 3) End

4) Modification record

5) Define record

6) Refer record

7) External symbol record

DEFINE RECORD

1 D

2-7 Name of external symbol defined in

8-13 Relative addr within this CS

14-73 Name and addrs of other external symbols.

eg: D BUFFER A 00033, BUFFER D, 001033

REFER RECORD

1 R

2-7 Name of internal symbol referred in this

8-73 Name of other internal set symbols

eg: RN RDREC, WRREC

MODIFICATION RECORD

1 M

2-7 Starting address

8-9 Length of field to be modified

10 +/-

11-16 External symbol whose value is to be modified

eg: M 00000A 105, + RDREC.

- Difference b/w Program blocks and control sections
- Program blocks have a continuity.
- A control section is a logical unit of its own & not continuous.

Assembler directive of program block - USE

1. " Control section - CSECT

Object record

H₁

T₁

⋮

En 0000

→ Assembler directive of Control section.

1. CSECT
2. (External definition) EXTDEF.
3. (External Reference) EXTREF

EXTDEF BUFFER LENGTH
EXTREF RDREC WRREC
⋮
+JSUB RDREC

RDREC (CSECT)
- EXTDEF BUFFER, LENGTH
⋮
+STX LENGTH

In I section we define buffer and length.

Eg: 0003 CLOOP +JSUB RDREC

EXTDEF BUFFER, LENGTH
EXTREF RDREC, WRREC

⋮
+ BUFFER RESW 1
LENGTH RESB 1
0003 CLOOP +JSUB RDREC

Displacement = 0

Opcode | n | ix | b | P | c | displacement

00000000 00000000 00000000

0100 1000

0100 1000 0001 0000 0000 0000
↑ ↓ 1 000.00

4/2 0017 STCH BUFFERIX
displacement = 0.

opcode	n	i	r	b	p	e	displacement
--------	---	---	---	---	---	---	--------------

STCH 111001 00000

0101 0100

0101 0111 1001 00000

5 7 9 00000

ASSEMBLER DESIGN

OPTIONS BUILT 41010 8000

I) ONE PASS ASSEMBLER

a) Load and Go.

Create opcode


0003 CLOOP + JSUB RDREC

:

0014 J000 CLOOP ←

0017 ENDFL

Displacement = TA - PC



opcode | n | i | r | b | p | e | displacement

1 1 0 0 1 0

0011 1111 0010 FCC

Object code:

COPY START 1000

1000 → 4B100000

→ 3202016

→ 945000

→ 587FCC

→ COPY 1000

TA 4B10000 3202016 945000 587FCC

EN 1000

4/10/17 ASSEMBLER DESIGN OPTIONS

Single Pass

load & Go

Assembler

Ass. that produces intx

Code.

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→

→


→

→

→

→

→



→ LOAD AND GO ASSEMBLER :-

Forward referencing has to be handled well

mem addrs	contents
2013	-----
201A	100948
201D	00100C
201F	-----

100C LENGTH REW
2013 +JSUB RDREC

201F +JSUB RDREC

FFF EXTDEF RDREC.

Symb Value

LENSE	100C	---
RDREC	*!	→ 2013 → 201F

- RDREC is an external symbol
its address is unknown so we put address as 4B100000
CONTENT
4BL ---

- In the Value column we create a linked list and save it where ever we use the RDREC
- When we reached at * fill the blank spaces with FFF.

PN 92, 93, 95

0017 LDA = 'EOF'

0030 * = 'EOF'

Literal - without using variable directly equating

LDA BUFFER.

BUFFER RESB 'EOF'

- To create object code for literal.

Op | n | i | z | b | p | e | displacement
00 1 0 0 1 0 0 16
disp = 030 - 01A
= 016

LDA 00

0030 * = EOF (maximum value of WORD)
Here write the ASCII value of E, O, F

Alphabet	ASCII
A	41
E	45
F	46
O	4F
Z	5A

0033 BUFFER RESB 4096

1033 BUFFERID EQU *

1000 MAXLEN EQU BUFFERNO-BUFFER.

ASSEMBLER

Single
Multipass - Indirect
Label Int code

Multipass Assemblers

ALPHA EQU BETA

BETA RES1

BETA EQU DELTA

DELTA RES1

To fill symbol table we need to pass many times

Multipass assembler Some statements can't be resolved by 2-pass assembler. In multipass assembler we resolve forward reference with as many passes as needed. Multipass assembler use link list to keep track of whose value depends on an undefined symbol.

HALFS2 EQU MAXLEN/2

MAXLEN EQU BUFFEND-BUFFER


PREVBT EQU BUFFER-1

⋮

1034 BUFFER RESB 4096

BUFFEND EQU * (literal)

After in pass 1 we get value of buffer and buffend. In next pass we get the value of maxlen and prevbt. In 3rd pass we get HALFS2. We need 3 passes. Every pass it will be updated.



In first length we get.

In source program it is literal but in symbol table it's undefined

→ After 1st & 2nd Statement

HALFS2	\$1
BUFFER	*1034 → MAXLEN
BUFFEND	*1034 → MAXLEN
MAXLEN	\$2 BUFFER - BUFFEND → HALFS2 / \$0

\$1 and \$2 are no. of variable depend on it.

→ After 3rd statement

HALFS2	\$1
BUFFER	*1034
BUFFEND	*1034 → MAXLEN
MAXLEN	\$2 BUFFER - BUFFEND → MAXLEN
PREVBT	\$1 1033 → HALFS2 / \$0

HALFSZ	800
BUFFER	1034
BUFFEND	2034
MAXLEN	1000
PREVBT	\$1 1033

Microprocessor ~~is~~ developed MASM

- software tool
- to assemble assembly language

Four segments

Code → CS

Data → DS, ES, FS, GS by default DS using ASSUME Others can be used

Constant →

Stack → SS

Jump is used for skipping a set of stmt.

Two types of jump

- 1) Near
- 2) far

Near

JMP SHORT TARGET

within same control
section

assembled using CS

It occupies 2-3 Bytes

With 128 Bytes jump is
called near jump.

Far long.

JMP FAR PTR TARGET.

- within diff different control sections
- assembled using any other segments
- It occupies 5 Bytes.

0001	11110000
0001	11110000
- More than 128 bytes

0001	11110000
0001	11110000



END