

# **STDCL**

# A Simplified C Interface for OpenCL

revision 1.1

Copyright © 2009-2011 Brown Deer Technology, LLC

Verbatim copying and distribution of this entire document is permitted in any medium, provided this notice is preserved.

## **Contents**

- Name
- Version
- Synopsis
- Description
- Application Programming Interface (API)
  - Default Contexts
  - Dynamic CL Program Loader
  - Memory Management
  - Kernel Management
  - Synchronization
  - Environment Variables
- Examples
- Manual Pages

# Name

STDCL - Standard Compute Layer Interface

## Version

```
STDCL_VERSION_STR
STDCL VERSION HEX
```

# **Synopsis**

```
#include <stdcl.h>
Link with -lstdcl.
 Default Contexts
       stddev, stdcpu, stdgpu, stdrpu
 Dynamic CL Program loader
       clopen(), clsym(), clclose()
 Memory Management
       clmalloc(), clfree(), clsizeofmem(), clmsync(), clmattach(),
       clmdetach()
 Kernel Management
       clndrange init1d(), clndrange init2d(), clndrange init3d(),
       clarg set(), clarg set local(), clarg set global(),
       clfork()
 Synchronization
       clflush(), clwait()
 Environment Variables
       STDDEV, STDCPU, STDGPU, STDRPU
```

# **Description**

OpenCL provides a host-side API that allows the careful management of memory and processes on heterogeneous computing platforms. The level of control is more typically reserved for conventional operating systems (memory management, process management, synchronization, etc.). Although this granularity of control is necessary to support the expansive industry objectives for which OpenCL was designed, the granularity of control and verbose nature of the API proves to be tedious within the context of typical software application development. The steps required for a simple Hello World OpenCL program are tedious and repetitive from a programmer's perspective. Moreover, some semantics introduced by OpenCL have more natural and familiar constructs within traditional UNIX programming that can greatly simplify the use of the API and prove more efficient. As an example, opaque memory buffers are more naturally managed as memory allocations; modern UNIX-like operating systems are more than capable of employing memory virtualization sufficient to allow control over memory consistency.

STDCL provides a simplified C interface to OpenCL designed in a style familiar to traditional UNIX/C programmers. The design and implementation of STDCL is inspired by familiar APIs designed for different purposes, e.g., stdio.h (for default contexts), dlopen (for managing OpenCL kernels), malloc (as a replacement for creating opaque memory buffers), and fork (as a replacement to "enqueueing commands on the command queue"). In every detail, the approach is to avoid introducing new inventive syntax and

semantics in favor of exploiting permutations of more familiar syntax and semantics from traditional UNIX. Whether the effort succeeds is for the programmer to decide.

# **Application Programming Interface (API)**

The STDCL interface provides support for <u>default contexts</u>, <u>dynamic CL program loader</u>, <u>memory management</u>, <u>kernel execution</u>, and <u>asynchronous operations</u>. In addition, <u>environment variables</u> provide run-time control over certain aspects of the interface. The STDCL interface is discussed in detail below.

## **Default Contexts**

STDCL provides several default contexts similar to the default I/O streams provided by stdio. These default contexts are defined to include the most typical use-cases. Each default context is of type CONTEXT, which is defined as a superset of the OpenCL type cl\_context. The following default contexts are provided:

## CONTEXT\* stddev;

All devices for a given platform supported by the OpenCL API.

## CONTEXT\* stdcpu;

All multi-core CPU processors for a given platform supported by the OpenCL API.

## CONTEXT\* stdgpu;

All many-core GPU processors for a given platform supported by the OpenCL API.

## CONTEXT\* stdrpu;

All reconfigurable processors for a given platform supported by the OpenCL API.

# **Dynamic CL Program Loader**

STDCL provides a convenient interface for dynamically loading CL programs and accessing OpenCL kernels. The functions clopen(), clsym() and clclose() are designed to mirror the semantics of the more familiar functions dlopen(), dlsym() and dlclose() used to access the Linux dynamic loader. The following functions are provided for dynamically loading CL programs and accessing OpenCL kernels:

```
void* clopen( CONTEXT* cp, const char* filename, int flags);
```

This call opens a file containing the source or binary program defining one or more OpenCL kernels and performs the steps necessary to create and build the OpenCL program object. A handle is returned that can be used in subsequent calls to access the actual kernels in the program. The handle is valid within the CONTEXT specified by **cp**.

If **filename** is a NULL pointer then a handle to the OpenCL program(s) embedded in the host program executable is returned. (See the tool clld for a description of how to embed OpenCL source and binary programs into a host program executable.)

The **flags**argument allows control over the behavior of the function. The flag CLLD\_NOW instructs the call to perform all of the steps involved with creating and building the program; the flag CLLD\_LAZY instructs the call to defer these steps until the handle is first used. The call accepts a flag set to 0 in which case the default behavior (CLLD NOW) is used.

```
cl_kernel clsym( CONTEXT* cp, void* handle, const char* symbol, int flags);
```

This call takes a **handle** returned from a call to clopen() and returns the OpenCL kernel specified by **symbol**. The OpenCL kernel is created within the CONTEXT specified by **cp**.

The argument **flags** allows control over the behavior of the function. The flag CLLD\_NOW instructs the call to perform all of the steps involved with creating the kernel; the flag CLLD\_LAZY instructs the call to defer these steps until the kernel is first used. The call accepts a flag set to 0 in which case the default behavior (CLLD\_NOW) is used.

```
int clclose( CONTEXT* cp, void* handle);
```

This call decrements the reference count on the associated handle. If the reference count drops to zero then the associated OpenCL program source or binary is unloaded and the associated file is closed. Under normal usage this call is used to safely release the OpenCL programs created by a call to clopen().

## Memory Management

STDCL provides functions for allocating and managing memory that may be shared between the host and OpenCL co-processor devices. Memory may be allocated with clmalloc() and used transparently as the global memory for kernel execution on a OpenCL device. The programmer uses a single pointer representing the allocated memory which may be re-attached to various CL contexts using clmattach() and clmdetach(). Memory consistency can be maintained using the clmsync() function which synchronizes memory between the host and OpenCL co-processor devices. The following functions are provided for OpenCL memory management.

```
void* clmalloc( CONTEXT* cp, size_t size, int flags);
```

This call allocates memory suitable for sharing between OpenCL co-processor devices within a CL context. The size of the allocation is specified in bytes. The memory is not cleared. The last argument is used to pass flags to control the behavior of function. The flag CL\_MEM\_DETACHED may be used to allocate memory that is not attached to a CL context in which case **cp** must be 0. If **flags** is 0 the default behavior is to allocate memory attached to a specified CL context.

```
void clfree( void* ptr);
```

This call frees memory allocated with clmalloc(). The memory specified by **ptr** can be either attached or detached from a CL context. Calling clfree() with **ptr** equal to 0 is considered an error.

```
size_t clsizeofmem(void* ptr);
```

This call returns the size in bytes of the memory allocated with clmalloc().

```
cl event clmsync( CONTEXT* cp, unsigned int devnum, void* ptr, int flags);
```

This call is used to synchronize memory between the host platform and OpenCL co-processor devices. The memory specified by **ptr** must have been allocated by clmalloc() and associated with a CL context.

The behavior of <code>clmsync()</code> is controlled by the **flags** argument which must be set with either <code>CL\_MEM\_HOST</code> or <code>CL\_MEM\_DEVICE</code>. These flags are mutually exclusive and it is an error to set both or none. In addition the flags <code>CL\_EVENT\_WAIT</code> and <code>CL\_EVENT\_NOWAIT</code> control the blocking behavior for the call. For a blocking call the flag <code>CL\_EVENT\_RELEASE</code> may be specified to force the call to release and <code>OpenCL</code> events created as a result of the call. If the flag <code>CL\_EVENT\_RELEASE</code> is not specified the programmer is responsible for releasing the returned event with the <code>OpenCL</code> call

```
clReleaseEvent().
The following examples demonstrate typical uses of clmsync():
Non-blocking sync to device memory:
    clmsync(stdgpu,0,ptr,CL MEM DEVICE|CL EVENT NOWAIT);
Non-blocking sync to host memory:
    clmsync(stdgpu,0,ptr,CL MEM HOST|CL EVENT NOWAIT);
```

Blocking sync to device memory:

```
clmsync(stdgpu,0,ptr,CL MEM DEVICE|CL EVENT WAIT);
```

Blocking sync to host with release of event:

```
clmsync(stdgpu,0,ptr,CL MEM HOST|CL EVENT WAIT|CL EVENT RELEASE);
```

```
int clmattach( CONTEXT* cp, void* ptr );
```

This call is used to attach memory allocated by clmalloc() to a CL context. In order to change the attachment of memory from one CL context to another, the memory must first be unattached using a call to clmdetach (). It is an error to call with a ptr to memory that is already attached to a CL context.

```
int clmdetach( void* ptr );
```

This call is used to detach memory from a CL context. The memory must have been allocated by clmalloc().

# **Kernel Management**

STDCL provides simplified interfaces for setting up the index-space and arguments for kernel execution. Executing a kernel on an OpenCL co-processor device is supported using clfork() which allows blocking and non-blocking execution behavior. The following functions are provided for OpenCL kernel management.

```
clndrange t clndrange init1d( gtoff0,gtsz0,ltsz0);
clndrange t clndrange init2d( gtoff0,gtsz0,ltsz0, gtoff1,gtsz1,ltsz1);
clndrange_t clndrange_init3d( gtoff0,gtsz0,ltsz0, gtoff1,gtsz1,ltsz1,
gtoff2,gtsz2,ltsz2);
```

The clindrange init\*() functions are used to initialize a variable of type clindrange t used to store the OpenCL index-space over which a kernel is to execute. These functions will be implemented as macros to allow for struct initialization in C. The arguments gtoff, gtsz and ltsz represent the global offset, global size and local size of the index-space for a given dimension, respectively. As an example, the following initializes a two dimensional OpenCL NDRange with no offsets over a global index space of size 512 by 2048 with a local work group size of 4 by 16:

```
clndrange t ndr = clndrange init2d(0,512,40,2048,16);
void clarg set( CONTEXT* cp, cl kernel krn, unsigned int argnum, Tn arg );
```

This call is used to set the argument of an OpenCL kernel for arguments of intrinsic non-pointer type that are to be passed by value. The size of the argument is inferred from the type of the argument and may be a vector type, e.g., cl float4.

```
void clarg set global (CONTEXT* cp, cl kernel krn, unsigned int argnum,
```

```
void* ptr );
```

This call is used to set the argument of an OpenCL kernel for arguments that are pointers to global memory as defined in the OpenCL specification. The memory must have been allocated by clmalloc() in the appropriate CL context of the kernel.

```
void clarg_set_local( CONTEXT* cp, cl_kernel krn, unsigned int argnum,
size t sizeb);
```

This call is used to set the argument of an OpenCL kernel for arguments that are pointers to local memory as defined in the OpenCL specification. Local memory of size **sizeb** bytes will be allocated for use by the OpenCL kernel.

```
cl_event clfork( CONTEXT* cp, unsigned int devnum, cl_kernel krn,
clndrange* ndr, int flags );
```

This call is used to execute a kernel on the OpenCL co-processor device specified by **devnum**. The arguments for the kernel must be set prior to the call to clfork() using the clarg\_set\*() functions described above. The kernel is executed over an index-space of work-items defined by **ndr**.

The behavior of clfork() may be controlled using the flags CL\_EVENT\_WAIT or CL\_EVENT\_NOWAIT. Specifying the flag CL\_EVENT\_NOWAIT will cause clfork() to return immediately. Specifying the flag CL\_EVENT\_WAIT will cause clfork() to block until the kernel execution is complete. Including the flag CL\_EVENT\_RELEASE will cause the event associated with the kernel execution to be released for blocking calls to clfork(). If the flag CL\_EVENT\_RELEASE is not specified the programmer is responsible for releasing the returned event with the OpenCL call clreleaseEvent().

The following examples demonstrate typical uses of clfork():

Blocking execution of a kernel on device number 0:

```
clfork( stdgpu, 0, my krn, &ndr, CL EVENT WAIT);
```

Non-blocking execution of a kernel on device number 2 automatically releasing the associated event:

```
clfork( stdgpu, 2, my krn, &ndr, CL EVENT NOWAIT|CL EVENT RELEASE);
```

## **Synchronization**

STDCL provides functions for synchronization to manage the inherently asynchronous operations enabled by OpenCL per device within each CL context.

```
int clflush( CONTEXT* cp, unsigned int devnum, int flags );
```

This call is used to flush all commands enqueued in the command queue associated with the OpenCL device specified by the device number **devnum** within the specified CL context. For typical OpenCL implementations this is necessary to force the execution of commands without blocking on the host. A call to clflush() is non-blocking and will return immediately. At present the argument **flags** should be set to 0.

```
cl event clwait( CONTEXT* cp, unsigned int devnum, int flags );
```

This call is used to block on the completion of all commands enqueued in the command queue associated with the OpenCL device specified by the device number **devnum** within the specified CL context.

The **flags** argument is used to control the behavior of the call as follows. The flag

CL\_KERNEL\_EVENT will cause the call to block on completion of all enqueued kernel events enqueued by calls to clfork(). the flag CL\_MEM\_EVENT will cause the call to block on completion of all enqueued memory events enqueued by call to clmsync(). The flags CL\_KERNEL\_EVENT and CL\_MEM\_EVENT may be combined in a single call. Including the flag CL\_EVENT\_RELEASE will cause all OpenCL events to be released before clwait() returns. If the flag CL\_EVENT\_RELEASE is not specified the programmer is responsible for releasing all events with the OpenCL call clReleaseEvent().

The following examples demonstrate typical uses of clwait ():

Block on completion of all kernel execution events on OpenCL device number 0 releasing all events:

```
clwait( stdgpu, 0, CL_KERNEL_EVENT|CL_EVENT_RELEASE );
```

Block on completion of all memory events on OpenCL device number 2 releasing all events:

```
clwait ( stdgpu, 2, CL MEM EVENT | CL EVENT RELEASE );
```

Block on completion of all kernel and memory events on OpenCL device number 2 releasing all events:

```
clwait ( stdgpu, 2, CL KERNEL EVENT | CL MEM EVENT | CL EVENT RELEASE );
```

## **Environment Variables**

The run-time behavior of STDCL can be controlled using environment variables as follows.

```
STDDEV, STDCPU, STDGPU, STDRPU
```

Each default CL context is can be controlled by the associated environment variable. A value of 0 will disable the CL context. A non-zero value will set a limit on the number of devices used for the CL context.

# **Examples**

The following example shows the use of STDCL for a simple program that adds two vectors on a GPU or a CPU:

```
/* example #1 */
#include <stdio.h>
#include <strings.h>
#include <stdcl.h>

#define SIZE 1024

int main()
{
   int i;

   CONTEXT* cp = (stdgpu)? stdgpu : stdcpu;

   void* clh = clopen(cp, "add_vec.cl",CLLD_NOW);
   cl_kernel k_addvec = clsym(cp, clh, "addvec_kern", CLLD_NOW);
   float* aa = (float*)clmalloc(cp,SIZE*sizeof(float),0);
```

```
float* bb = (float*)clmalloc(cp,SIZE*sizeof(float),0);
   float* cc = (float*)clmalloc(cp,SIZE*sizeof(float),0);
   for(i=0;i<SIZE;i++) {</pre>
      aa[i] = 111.0f * i;
      bb[i] = 222.0f * i;
   }
  bzero(cc,SIZE*sizeof(float));
   clndrange t ndr = clndrange init1d(0,SIZE,64);
   clmsync(cp,0,aa,CL MEM DEVICE|CL EVENT NOWAIT);
   clmsync(cp,0,bb,CL MEM DEVICE|CL EVENT NOWAIT);
   clarg set global(cp,k addvec,0,aa);
   clarg set global(cp,k addvec,1,bb);
   clarg set global(cp,k addvec,2,cc);
   clfork(cp,0,k addvec,&ndr,CL EVENT NOWAIT);
   clmsync(cp,0,cc,CL MEM HOST|CL EVENT NOWAIT);
   clwait(cp,0,CL MEM EVENT|CL KERNEL EVENT|CL EVENT RELEASE);
   for(i=0;i \le SIZE;i++) printf("%f %f %f\n",aa[i],bb[i],cc[i]);
   if (aa) clfree(aa);
   if (bb) clfree(bb);
   if (cc) clfree(cc);
  clclose(cp, clh);
}
The following example shows the use of STDCL for a simple program that adds two vectors on two GPU:
/* example #2 */
#include <stdio.h>
#include <strings.h>
#include "stdcl.h"
#define SIZE 1024
int main()
   int i,n;
  CONTEXT* cp = stdgpu;
   void* clh = clopen(cp, "add_vec.cl",CLLD_NOW);
   cl_kernel k_addvec = clsym(cp, clh, "addvec_kern", CLLD_NOW);
   float* aa[2];
```

```
float* bb[2];
float* cc[2];
aa[0] = (float*)clmalloc(cp,SIZE*sizeof(float)/2,0);
aa[1] = (float*)clmalloc(cp,SIZE*sizeof(float)/2,0);
bb[0] = (float*)clmalloc(cp,SIZE*sizeof(float)/2,0);
bb[1] = (float*)clmalloc(cp,SIZE*sizeof(float)/2,0);
cc[0] = (float*)clmalloc(cp,SIZE*sizeof(float)/2,0);
cc[1] = (float*)clmalloc(cp,SIZE*sizeof(float)/2,0);
for(i=0;i<SIZE/2;i++) {
   aa[0][i] = 111.0f * i;
   aa[1][i] = 111.0f * (SIZE/2 + i);
   bb[0][i] = 222.0f * i;
   bb[1][i] = 222.0f * (SIZE/2 + i);
}
bzero(cc[0],SIZE*sizeof(float));
bzero(cc[1],SIZE*sizeof(float));
clndrange t ndr = clndrange init1d(0,SIZE/2,64);
clmsync(cp,0,aa[0],CL MEM DEVICE|CL EVENT NOWAIT);
clmsync(cp,1,aa[1],CL MEM DEVICE|CL EVENT NOWAIT);
clmsync(cp,0,bb[0],CL MEM DEVICE(CL EVENT NOWAIT);
clmsync(cp,1,bb[1],CL MEM DEVICE|CL EVENT NOWAIT);
clarg set global(cp,k addvec,0,aa[0]);
clarg set global(cp,k addvec,1,bb[0]);
clarg set global(cp,k addvec,2,cc[0]);
clfork(cp,0,k addvec,&ndr,CL EVENT NOWAIT);
clmsync(cp,0,cc[0],CL MEM HOST|CL EVENT NOWAIT);
clflush(cp, 0, 0);
clarg set global(cp,k addvec,0,aa[1]);
clarg set global(cp,k addvec,1,bb[1]);
clarg set global(cp,k addvec,2,cc[1]);
clfork(cp,1,k addvec,&ndr,CL EVENT NOWAIT);
clmsync(cp,1,cc[1],CL MEM HOST|CL EVENT NOWAIT);
clflush(cp, 1, 0);
clwait(cp,0,CL MEM EVENT|CL KERNEL EVENT|CL EVENT RELEASE);
clwait(cp,1,CL MEM EVENT|CL KERNEL EVENT|CL EVENT RELEASE);
for(i=0;i<SIZE/2;i++) printf("%f %f %f\n",aa[0][i],bb[0][i],cc[0][i]);
for(i=0;i<SIZE/2;i++) printf("%f %f %f\n",aa[1][i],bb[1][i],cc[1][i]);
if (aa[0]) clfree(aa[0]);
if (aa[1]) clfree(aa[1]);
```

```
if (bb[0]) clfree(bb[0]);
if (bb[1]) clfree(bb[1]);
if (cc[0]) clfree(cc[0]);
if (cc[1]) clfree(cc[1]);

clclose(cp,clh);
```

# **Manual Pages**

overview	stdcl(3)
dynamic loader	clopen(3), clsym(3), clclose(3)
memory management	clmalloc(3), clfree(3), clsizeofmem(3), clmsync(3), clmattach(3), clmdetach(3)
kernel management	<pre>clndrange_init1d(3), clndrange_init2d(3), clndrange_init3d(3), clarg_set(3), clarg_set_global(3), clarg_set_local(3), clfork(3)</pre>
asynchronous operations	clflush(3), clwait(3)

```
STDLC(3) Standard Compute Layer (CL) Manual STDLC(3)
```

```
NAME

stdcl - standard compute layer (CL) library functions

SYNOPSIS

#include <stdcl.h>

CONTEXT* stddev;
CONTEXT* stdcpu;
CONTEXT* stdcpu;
CONTEXT* stdcpu;
Link with -lstdcl.
```

## DESCRIPTION

The standard compute layer (CL) library (libstdcl) provides a simplified interface to OpenCL designed to support the most typical use-cases in a style inspired by familiar and traditional UNIX APIs for C programming.

libstdcl provides managed OpenCL contexts identified with a context pointer that is generally provided as an argument to library functions that transparently manage OpenCL constructs such as contexts, devices, memory, kernels and events in a manner that simplifies their use.

Default Contexts

libstdcl provides several default contexts similar to the default I/O streams provided by stdio. The following default contexts are provided:

stddev All devices for a given platform supported by the OpenCL API.

stdcpu All multi-core CPU processors for a given platform supported by the OpenCL API.

stdgpu All many-core GPU processors for a given platform supported by the OpenCL API.

stdrpu All reconfigurable processors for a given platform supported by the OpenCL API.

## Dynamic CL Program Loader

libstdcl provides a convenient interface for dynamically loading CL programs and accessing CL kernels. Using the tool clld CL program source and binary files can be embedded within special ELF sections linked against other object files on the host platform to generate a single executable. The set of functions clopen(), clsym(), clclose() provide a convenient interface capable of dynamically loading CL programs embedded within the executable as well as from an external file. CL programs.

## Memory Management

libstdcl provides functions for allocating and managing memory that may be shared between the host and CL co-processor devices. Memory may be allocated with clmalloc() and used transparently as the global memory for kernel execution on a CL device. The programmer uses a single pointer representing the allocated memory which may be re-attached to various CL contexts using clmattach() and clmdetach(). Memory consistency can be maintained using the clmsync() function which synchronizes memory between host and CL co-processor device.

## Kernel Management

libstdcl provides simplified interfaces for setting up the index-space and arguments for kernel execution. Executing a kernel on a particular CL co-processor device is supported using clfork() which allows blocking and non-blocking execution behavior.

## Synchronization

libstdcl provides event management per device within each context to simplify the management of asynchronous multi-device operations. The function clwait() can be used to block on selected events within one of several per-device event lists managed transparently.

#### EXAMPLE

The following example shows a very simple program for calculating the outer product of two vectors using a GPU:

```
#include <stdcl.h>
int main() {
     int n = 1024;
     cl float* aa = (cl float*) clmalloc(stdgpu, n, 0);
     cl float* bb = (cl float*)clmalloc(stdgpu,n,0);
     cl float* cc = (cl float*)clmalloc(stdgpu,n,0);
     /* initialize aa and bb */
    void* h = clopen(stdgpu, "outer prod kern.cl",0);
     cl kernel krn = clsym(stdgpu,h,"outer prod kern");
     clndrange t ndr = clndrange init1d(0,n,4);
     clarg set(krn,0,n);
     clarg set global(krn,1,aa);
     clarg set global(krn,2,bb);
     clarg set global(krn,3,cc);
     clfork(stdgpu,0,krn,ndr,CL EVENT NOWAIT);
     clmsync(stdgpu,0,cc,CL EVENT NOWAIT);
     clwait(stdgpu,0,CL ALL EVENTS|CL EVENT RELEASE);
     clclose(h);
     clfree(aa);
     clfree(bb);
    clfree(cc);
}
```

## ENVIRONMENT

Executables that use the libstdcl library are affected by environment variables that control the behavior of the API. The environment variables STDDEV, STDCPU, STDGPU, STDRPU may be set to pass a string used to control the behavior of the respective default contexts when a program is executed. Each string may contain one or more colon-separated clauses.

As an example, the following would force the stdgpu context to use the ATI Stream platform:

```
setenv STDGPU platform name="ATI STREAM"
```

A context can be disabled by setting the respective envinoment varia for example, the following will disable the stddev context: The allowed clauses are platform and context dependent.

## AUTHOR

Written by David Richie.

### REPORTING BUGS

Report bugs to <support@browndeertechnology.com>

## COPYRIGHT

Copyright (C) 2009 Brown Deer Technology, LLC. Licensed under the GNU Lesser General Public License version 3. There is NO WARRANTY to the extent permitted by law.

## SEE ALSO

clld(1), clopen(3), clsym(3), clclose(3), clmalloc(3), clmsync(), clfork(3), clwait(3)

"libstdcl-1.0"

2010-8-12

STDLC(3)

CLOPEN(3)

Standard Compute Layer (CL) Manual

CLOPEN(3)

## NAME

clopen, clsym, clclose, clerror, claddr - programming interface to dynamic CL loader

## SYNOPSIS

#include <stdcl.h>

void\* clopen( CONTEXT\* cp, const char\* filename, int flags);

cl\_kernel clsym( CONTEXT\* cp, void\* handle, const char\* symbol, int
flags);

int claddr( CONTEXT\* cp, void\* addr, CL info\* info);

char\* clerror( void );

int clclose( CONTEXT\* cp, void\* handle);

Link with -lstdcl.

## DESCRIPTION

The functions clopen(), clsym(), clclose(), and clerror() implement an interface for dynamically loading compute layer (CL) kernels.

The function clopen() loads the CL source or binary program file named by the NULL-terminated string filename and returns an opaque handle that may be used as a reference in subsequent calls. If filename is a NULL pointer then a handle for the main program executable is returned.

The function clsym() takes a handle to a CL source or binary program and a NULL-terminated symbol name and returns the associated CL kernel. A CL context pointer must be specified to identify the appropriate CL kernel to return. If handle is NULL then all CL programs loaded into the specified CL context are searched.

The function clclose() decrements the reference count on the associated handle. If the reference count drops to zero then the CL program is unloaded. The function clclose() returns the reference count on success and -1 on error.

The function clerror() returns a human readable string describing the most recent error that has occurred as a result of a call to any of the functions clopen(), clsym(), clclose() since the last call to clerror(). If no error has occured NULL is returned.

The function claddr() takes as an argument a CL kernel and tries to resolve the name and file where it is located. Information is returned in the cl kernel info structure:

```
struct cl kernel info {
     const char* cli fname;
     CONTEXT* cli cp;
     unsigned int cli devnum;
     const char* cli kname;
};
```

If no matching kernel is found the fields are set to NULL. claddr() returns zero on error and non-zero on success.

## EXAMPLE AUTHOR

Written by David Richie.

#### REPORTING BUGS

Report bugs to <support@browndeertechnology.com>

#### COPYRIGHT

Copyright (C) 2009 Brown Deer Technology, LLC. Licensed under the GNU Lesser General Public License version 3 (LGPLv3). There is NO WARRANTY to the extent permitted by law.

### SEE ALSO

clld(1), clload(3), stdcl(3)

libstdcl-1.0 2010-8-12 CLOPEN(3)

#### NAME

clmalloc, clfree, clsizeofmem - Allocate and free dynamic memory with CL bindings for use with co-processor devices

#### SYNOPSIS

```
#include <stdcl.h>
void* clmalloc( CONTEXT* cp, size_t size, int flags);
void clfree( void* ptr);
size_t clsizeofmem(void* ptr);
Link with -lstdcl.
```

#### DESCRIPTION

clmalloc() allocates memory suitable for sharing between compute layer (CL) co-processor devices within a CL context. clmalloc() allocates size bytes and returns a pointer to the allocated memory. The memory is not cleared. If size is 0, then clmalloc() returns a unique pointer value that can later be safely passed to clfree().

clfree() frees the memory space pointed to by ptr, which must have been returned by a previous call to clmalloc(). Otherwise, or if clfree(ptr) has already been called before, the behavior is undefined. It is considered an error to call clfree(ptr) if ptr is 0 or NULL.

clsizeofmem() returns the size of the allocated memory associated with ptr. If ptr does not reference memory allocated by a call to clmalloc(), and for which clfree() has not been called, the behavior is undefined.

## RETURN VALUE

If successful clmalloc(3) returns a pointer to the allocated memory that is suitably aligned and suitable for sharing with CL co-processor devices. On error, returns NULL.

clfree() returns no value.

clsizeofmem() returns the size in bytes of the memory pointed to by ptr.

## AUTHOR

Written by David Richie.

#### REPORTING BUGS

Report bugs to <support@browndeertechnology.com>

## COPYRIGHT

Copyright (C) 2009 Brown Deer Technology, LLC. Licensed under the GNU Lesser General Public License version 3 (LGPLv3). There is NO WARRANTY to the extent permitted by law.

libstdcl-1.0 2010-8-12 CLMALLOC(3)

CLMSYNC(3)

Standard Compute Layer (CL) Manual

CLMSYNC(3)

#### NAME

clmsync - Synchronize memory between host and co-processor device

## SYNOPSIS

#include <stdcl.h>

cl\_event clmsync( CONTEXT\* cp, unsigned int devnum, void\* ptr, int
flags);

Link with -lstdcl.

## DESCRIPTION

clmsync() is used to synchronize memory between the host and a compute layer (CL) co-processor device. The memory pointed to by ptr must have been created using a call to clmalloc() and associated with a CL context.

The behavior of clmsync() is controlled by the flags argument which must be set with either CL\_MEM\_HOST or CL\_MEM\_DEVICE. These flags are mutually exclusive and it is an error to set both or none. The following flags may be used:

## CL MEM HOST

clmsync() will sync the memory on the host.

## CL MEM DEVICE

clmsync() will sync the memory on the device.

## CL EVENT WAIT

clmsync() will block until the operation has completed.

## CL EVENT NOWAIT

clmsync() will return immediately. The programmer must ensure
that the operation has completed using clwait() or clwaitev().

## CL EVENT RELEASE

Used with CL\_EVENT\_WAIT to force clmsync() to release the CL event generated by the operation. If this flag is not used the programmer is responsible for releasing the returned event using clReleaseEvent(). This flag has no effect when CL\_EVENT\_NOWAIT is used.

## RETURN VALUE

On error clmsync() will return (cl event) (-1) and errno is set appro-

priately.

#### AUTHOR

Written by David Richie.

#### REPORTING BUGS

Report bugs to <support@browndeertechnology.com>

#### COPYRIGHT

Copyright (C) 2009 Brown Deer Technology, LLC. Licensed under the GNU Lesser General Public License version 3 (LGPLv3). There is NO WARRANTY to the extent permitted by law.

#### SEE ALSO

clwait(3), clwaitev(3), clmalloc(3), clfree(3), stdcl(3)

2010-8-12 libstdcl-1.0 CLMSYNC(3)

CLMATTACH(3)

Standard Compute Layer (CL) Manual CLMATTACH(3)

NAME

clmattach, clmdetach - Attach and detach memory from a CL context

## SYNOPSIS

#include <stdcl.h>

int clmattach( CONTEXT\* cp, void\* ptr );

int clmdetach( void\* ptr );

Link with -lstdcl.

## DESCRIPTION

clmattach() is used to attach memory to a compute layer (CL) context. The memory pointed to by ptr must be allocated with clmalloc() and suitable for sharing between the host and CL co-processor devices. order to change the attachment of memory from one CL context to another, the memory must first be unattached using a call to clmdetach(). It is an error to pass clmattach() memory that is already attached to a CL context.

clmdetach() is used to detach memory from a CL context. The memory pointed to by ptr must be allocated with clmalloc() and suitable for sharing between the host and CL co-processor devices.

If ptr does not point to memory allocated by clmalloc() the behavior of clmattach() and clmdetach() is undefined.

## RETURN VALUE

Both clmattach() and clmdetach() return 0 on success. On error, -1 is

returned and errno is set appropriately.

#### AUTHOR

Written by David Richie.

#### REPORTING BUGS

Report bugs to <support@browndeertechnology.com>

#### COPYRIGHT

Copyright (C) 2009 Brown Deer Technology, LLC. Licensed under the GNU Lesser General Public License version 3 (LGPLv3). There is NO WARRANTY to the extent permitted by law.

#### SEE ALSO

clmalloc(3), clfree(3), clmsync(3), malloc(3), stdcl(3)

libstdcl-1.0 2010-8-12 CLMATTACH(3)

CLNDRANGE INIT(3) Standard Compute Layer (CL) Manual CLNDRANGE INIT(3)

## NAME

clndrange\_init1d, clndrange\_init2d, clndrange\_init3d - Initialize the
index-space (NDRange) for the execution of a CL kernel

#### SYNOPSIS

#include <stdcl.h>

clndrange t clndrange init1d( gtoff0,gt0,lt0);

clndrange t clndrange init2d( gtoff0, gt0, lt0, gtoff1, gt1, lt1);

clndrange\_t clndrange\_init3d( gtoff0,gt0,lt0, gtoff1,gt1,lt1,
gtoff2,gt2,lt2);

## DESCRIPTION

clndrange\_init() family of macros are used to initialize an object of type clndrange\_t that defines the index-space for the execution of a CL kernel. The values of gtoffn, gtn, ltn define the global index offset, global index range and local index range, respectively, for dimension n. The index-space defines the work-group and work-item partitioning for the kernel execution.

## EXAMPLES

The initialization of a 1-D index-space of 16 work-items with work-group size of 2 and no global offset:

clndrange t ndr = clndrange init1d( 0,16,2 );

The initialization of a 2-D index-space of 64 by 128 work-items with work-group size of 2 by 4 with a global work-item offset of 32,64:

clndrange t ndr = clndrange init1d( 32,64,2,64,128,4 );

**AUTHOR** 

Written by David Richie.

### REPORTING BUGS

Report bugs to <support@browndeertechnology.com>

#### COPYRIGHT

Copyright (C) 2009 Brown Deer Technology, LLC. Licensed under the GNU Lesser General Public License version 3 (LGPLv3). There is NO WARRANTY to the extent permitted by law.

#### SEE ALSO

clndrange set(3), clfork(3), stdcl(3)

libstdcl-1.0

2010-8-12

CLNDRANGE INIT(3)

CLARG SET(3)

Standard Compute Layer (CL) Manual

CLARG\_SET(3)

NAME

clarg set, clarg set global, clarg set local - Set CL kernel arguments

#### SYNOPSIS

#include <stdcl.h>

void clarg\_set( CONTEXT\* cp, cl\_kernel krn, unsigned int argnum, Tn arg)
void clarg\_set\_global( CONTEXT\* cp, cl\_kernel krn, unsigned int argnum,
void clarg\_set\_local( CONTEXT\* cp, cl\_kernel krn, unsigned int arg sizeb);

## DESCRIPTION

clarg\_set(), clarg\_set\_global() and clarg\_set\_local() are used to set
the argnum argument of the CL kernel krn prior to kernel execution.

clarg\_set() is used for setting arguments of intrinsic type such as
cl\_int, cl\_float or cl\_float4, etc. For clarg\_set() Tn can be any
valid scalar or vector type.

clarg\_set\_global is used for setting arguments of pointers to global memory where ptr points to memory that was allocated using a call to clmalloc() and attached to the CL context of the target kernel.

clarg\_set\_local() is used for setting arguments of pointers to local memory where sizeb indicates the size in bytes of the local memory that is to be allocated.

AUTHOR

Written by David Richie.

### REPORTING BUGS

Report bugs to <support@browndeertechnology.com>

#### COPYRIGHT

Copyright (C) 2009 Brown Deer Technology, LLC. Licensed under the GNU Lesser General Public License version 3 (LGPLv3). There is NO WARRANTY to the extent permitted by law.

#### SEE ALSO

clfork(3), clsym(3), clmalloc(3), stdcl(3)

libstdcl-1.0 2010-8-12 CLARG SET(3)

\_\_\_\_

CLFORK(3) Standard Compute Layer (CL) Manual CLFORK(3)

NAME

clfork - Execute a CL kernel

#### SYNOPSIS

#include <stdcl.h>

cl\_event clfork( CONTEXT\* cp, unsigned int devnum, cl\_kernel krn, clndrange t\* ndr, int flags);

Link with -lstdcl.

## DESCRIPTION

clfork() is used to execute a CL kernel on a specified compute layer (CL) co-processor device. The arguments for the kernel must be set prior to the call to clfork() using the clarg\_set\*() functions. The kernel is executed over an index-space of work-items defined by ndr.

The behavior of clfork() can be controlled using the following flags:

CL EVENT WAIT

clfork() will block until the operation has completed.

## CL EVENT NOWAIT

 ${\it clfork}()$  will return immediately. The programmer must ensure that the operation has completed using  ${\it clwait}()$  or  ${\it clwaitev}()$ .

## CL EVENT RELEASE

Used with CL\_EVENT\_WAIT to force clfork() to release the CL event generated by the operation. If this flag is not used the programmer is responsible for releasing the returned event using clReleaseEvent(). This flag has no effect when CL\_EVENT\_NOWAIT is used.

#### RETURN VALUE

On error clfork() will return (cl\_event)(-1) and errno is set appropriately.

#### AUTHOR

Written by David Richie.

#### REPORTING BUGS

Report bugs to <support@browndeertechnology.com>

#### COPYRIGHT

Copyright (C) 2009 Brown Deer Technology, LLC. Licensed under the GNU Lesser General Public License version 3 (LGPLv3). There is NO WARRANTY to the extent permitted by law.

## SEE ALSO

clarg\_set(3), clndrange\_init(3), clndrange\_set(3), clwait(3),
clwaitev(3), stdcl(3)

libstdcl-1.0 2010-8-12 CLFORK(3)

CLFLUSH(3) Standard Compute Layer (CL) Manual

CLFLUSH(3)

#### NAME

clflush - Flush the CL command queue

## SYNOPSIS

#include <stdcl.h>

int clflush( CONTEXT\* cp, cl\_uint devnum, int flags);

Link with -lstdcl.

## DESCRIPTION

clflush() is used to flush the OpenCL command queue for device number devnum within a CL context. For certain OpenCL implementations this is necessary to initiate operations to be executed asynchronously.

The flags argument is reserved for future use and presently ignored.

#### RETURN VALUE

On error clflush() will return (cl\_event)(-1) and errno is set appropriately.

### AUTHOR

Written by David Richie.

## REPORTING BUGS

Report bugs to <support@browndeertechnology.com>

#### COPYRIGHT

Copyright (C) 2010 Brown Deer Technology, LLC. Licensed under the GNU Lesser General Public License version 3 (LGPLv3). There is NO WARRANTY to the extent permitted by law.

#### SEE ALSO

clfork(3), clmsync(3), clwait(3), stdcl(3)

libstdcl-1.0 2010-8-12

CLWAIT(3)

Standard Compute Layer (CL) Manual

CLWAIT(3)

CLFLUSH(3)

NAME

clwait - Block on one or more CL events

#### SYNOPSIS

#include <stdcl.h>

cl event clwait( CONTEXT\* cp, cl uint devnum, int flags);

Link with -lstdcl.

## DESCRIPTION

clwait() is used to block on the completion of one or more outstanding events for device number devnum within a CL context. The type of events are specified by selecting one or more event lists as described below.

One or more event lists may be selected using a combination of the following flags:

## CL KERNEL EVENT

Block on events in the ordered kernel event list.

#### CL MEM EVENT

Block on events in the ordered memory event list.

Note that if both kernel and memory event lists are specified, the kernel event list has first priority. Specifically, clwait() will first block on all outstanding kernel events and subsequently block on all outstanding memory events.

The behavior of clwait() can be controlled using the following flags:

## CL EVENT RELEASE

Force clwait() to release all events on upon completion for all events on which it blocks. If this flag is not used the programmer is responsible for releasing the returned event using clReleaseEvent().

## RETURN VALUE

On error clwait() will return (cl\_event)(-1) and errno is set appropriately.

## AUTHOR

Written by David Richie.

## REPORTING BUGS

Report bugs to <support@browndeertechnology.com>

#### COPYRIGHT

Copyright (C) 2009 Brown Deer Technology, LLC. Licensed under the GNU Lesser General Public License version 3 (LGPLv3). There is NO WARRANTY to the extent permitted by law.

## SEE ALSO

clfork(3), clmsync(3), clwaitev(3), stdcl(3)

libstdcl-1.0 2010-8-12 CLWAIT(3)