
Corporate Finance

Lecture 10: Valuation & Capital Budgeting for Levered Firms

Yuan Shi ©

HSBC Business School Peking University







Outlines

Three approaches to value levered firms/projects

Applicational details of the WACC approach

Unlever-Lever

Divisional cost of capital

Pure play



Valuation for Levered Firms

Valuation in presence of debt financing:


- Adjusted Present Value Approach
- Flows to Equity Approach
- Weighted Average Cost of Capital Approach

Same foundation: *Discount Cash Flow*

Match cash flows with the proper discount rate


Same valuation approaches apply to capital budgeting.





$$APV = NPVU + NPVF$$

- The value of a project to the firm can be thought of as the value of the project to an unlevered firm (NPVU) plus the present value of the financing side effects (NPVF).
- There are four side effects of financing:
 - The Tax Shield of Debt
 - The Costs of *Issuing* New Securities (flotation costs)
 - The Costs of Financial Distress
 - Subsidies to Debt Financing (borrow at tax-free rate from government)



2. Flow to Equity Approach

- Discount the *cash flow* from the project *to the* <u>equity</u> <u>holders</u> of the levered firm at the cost of <u>levered equity</u> <u>capital,</u> r_E .
- There are three steps in the FTE Approach:
 - Step One: Calculate the levered cash flows (LCFs)
 - LCF = PCF After-tax Interest Expenses
 - Recall: $PCF=(S-C-D)x(1-t)+D-Capex-\Delta NWC$
 - Step Two: Calculate r_E .
 - Step Three: Value the levered cash flows at r_E .



3. WACC Approach


$$WACC = \frac{D}{V} \cdot (1 - \tau) \cdot r_D + \frac{E}{V} \cdot r_E$$

- To find the value of the project, discount the <u>unlevered cash flows (free cash flow)</u> at the <u>weighted</u> <u>average cost of capital</u>.
- In practice, the WACC Approach, by far, is the <u>most widely</u> used valuation method.




Example: Three Approaches

Consider a project of the Pearson Company. The timing and size of the incremental *after-tax cash flows* for an all-equity firm are:




The unlevered cost of equity is r_A = 10%.

Project NPV for all-equity firm is
$$-\$1,000 + \frac{\$100}{10\%} = \$0$$
.



Example: 1. APV Approach

- Now, imagine the firm finances the project with \$600 of permanent debt at $r_D = 8\%$.
- Pearson's tax rate is 40%, so they have an interest tax shield worth $\tau D = 0.4 \times \$600 = \240 .
- The net present value of the project under leverage is:
- APV = NPVU + NPVF = \$0 + \$240 = \$240.
- So, Pearson should accept the project with debt.



Example: 2. FTE Approach

Step One: Calculate the levered cash flows (LCFs)

- Since the firm is using \$600 of debt, the equity holders only have to provide \$400 of the initial \$1,000 investment.
- Thus, the initial cash flow to equity holders is $CF_0 = -\$400$.
- Each period, the equity holder must pay interest expense. The after-tax interest expense is $$600 \times 8\% \times (1 0.4) = 28.8 .
- Thus, the levered cash flow of each period is \$100 \$28.8 = \$71.2



Example: 2. FTE Approach

Step Two: Calculate r_E

First, the debt ratio of the project:

•
$$V = \frac{\$100}{10\%} + 240 = 1240;$$

$$\frac{D}{E} = \frac{600}{1240 - 600} = 0.9375$$

• Then, apply M&M#2:
$$r_E = r_A + \frac{D}{E}(1 - \tau)(r_A - r_D)$$

•
$$r_E = 10\% + 0.9375 \times (1 - 0.4) \times (10\% - 8\%) = 11.125\%$$

Step Three: Value the levered cash flows at r_E

•
$$NPV = -\$400 + \frac{\$71.2}{11.125\%} = \$240$$



Example: 3. WACC Approach

- First, find: $WACC = \frac{D}{V} \cdot (1 \tau) \cdot r_D + \frac{E}{V} \cdot r_E$.
- $WACC = \frac{600}{1240} \times (1 0.4) \times 8\% + \frac{640}{1240} \times 11.125\% = 8.0645\%$
- To find the value of the project, discount the <u>unlevered</u> <u>cash flows</u> at the weighted average cost of capital.
- $NPV = -\$1000 + \frac{\$100}{8.0645\%} = \$240.$



Summary of Three Approaches

• 1.
$$APV = \sum_{t=1}^{\infty} \frac{UCF_t}{(1+r_A)^t} - I_0 + NPV_F$$
,


• where I_0 is the initial investment, and NPV_F is the additional value impact of debt.

• 2.
$$NPV_{FTE} = \sum_{t=1}^{\infty} \frac{LCF_t}{(1+r_E)^t} - (I_0 - D_0),$$

• where I_0 is the initial investment, and D_0 is the amount borrowed.

• 3.
$$NPV_{wacc} = \sum_{t=1}^{\infty} \frac{UCF_t}{(1+wacc)^t} - I_0$$





- Three approaches can also be applied to capital budgeting problems for the projects with non-perpetual cash flows.
 - They might not give the exact same valuation.
- WACC is the most commonly used by far.
- FTE has appeal for a firm deeply in debt.
- APV is used if the level of debt is known over the project's life.
 - APV is frequently used for special situations like LBOs and leases.






- For capital budgeting decisions, we care about the <u>expected WACC</u> going forward.
- How to estimate WACC?

•
$$WACC = \frac{D}{V} \cdot (1 - \tau) \cdot r_D + \frac{E}{V} \cdot r_E$$

- We need to know the expected return on equity, expected return on debt, and <u>expected capital structures</u>.
- Tax rates:
 - If you are a passive analyst, use firm's current tax rate
 - If you are a decision maker, use marginal rather than average tax rate

14




1. At Target Capital Structure

When the company is close to the target capital structure:

- One can directly plug the *current debt ratios* into the WACC formula.
- For the cost of equity, one can apply the CAPM:

$$E(r_E) = r_f + \beta_E(r_m - r_f)$$

• where β_E is usually estimated from the recent stock returns.




1. At Target Capital Structure

- The cost of debt can be represented by the yield-tomaturity of corporate bonds outstanding.
- If the company has no bonds trading, one could look for the YTM of a company with similar default risk in the same industry.
- Default risk could be measured using Altman's Z-score, given by the following formula:
- Z = 0.012*(Working Capital/Total Assets) + 0.014*(Retained Earnings/Total Assets) + 0.033*(EBIT/ Total Assets) + 0.006*(Market Value of Equity/ Book Value of Total Liabilities) + 0.009*(Sales/ Total Assets).



2. Changing Capital Structure

- However, if the *recent* capital structure is very different from the target capital structure, then other methods are needed.
- This is because the **beta of equity** that we estimate at today's capital structure will be very different from its value at the target capital structure.
 - Implicit assumption: capital structure converges to the target level in the near future.
 - Thus, the cost of equity we estimate using current beta will be very different than when the debt ratio is at the target level.



2. Changing Capital Structure

- We can adopt the concept of expected return of unlevered equity, $E(r_A)$.
- Recall:

$$WACC = r_A \cdot (1 - \tau \cdot \frac{D}{V})$$

• If we know expected r_A and the target level of $\frac{D}{V}$, we can find out WACC under the target capital structure.



Unlever-Relever Approach

- 1. Estimate r_E and r_D under current capital structure
 - r_E usually by estimating β_E using recent past returns and applying CAPM
 - r_D usually using the average interest rate of current debts; if no debt outstanding, using the interest rate of comparable firms
- 2. **Un-lever**: find r_A according to M&M#2

•
$$r_E = r_A + \frac{D}{E}(1 - \tau)(r_A - r_D)$$

- Note D/E is the current leverage ratio
- 3. Re-lever: find WACC under the new capital structure

•
$$WACC = r_A \cdot (1 - \tau \cdot \left(\frac{D}{V}\right)')$$

• Or,
$$r_E' = r_A + \left(\frac{D}{E}\right)' (1 - \tau)(r_A - r_D)$$
 and $WACC = \left(\frac{E}{V}\right)' r_E' + \left(\frac{D}{V}\right)' r_D (1 - \tau)$

• Note (D/E)' or (D/V)' refer to the new capital structure