

Chapter 9: Virtual Memory





Background

- Code needs to be in memory to execute, but entire program rarely used
 - Error code, unusual routines, large data structures
- Entire program code not needed at same time
- Consider ability to execute partially-loaded program
 - Program no longer constrained by limits of physical memory
 - Each program takes less memory while running -> more programs run at the same time
 - Increased CPU utilization and throughput with no increase in response time or turnaround time
 - Less I/O needed to load or swap programs into memory -> each user program runs faster






Background (Cont.)

- Virtual memory separation of user logical memory from physical memory
 - Only part of the program needs to be in memory for execution
 - Logical address space can therefore be much larger than physical address space
 - Allows address spaces to be shared by several processes
 - Allows for more efficient process creation
 - More programs running concurrently
 - Less I/O needed to load or swap processes





Virtual Memory That is Larger Than Physical Memory








Virtual-address Space

- Usually design logical address space for stack to start at Max logical address and grow "down" while heap grows "up"
 - Maximizes address space use
 - Unused address space between the two is hole
 - 4 No physical memory needed until heap or stack grows to a given new page
- Enables sparse address spaces with holes left for growth, dynamically linked libraries, etc
- System libraries shared via mapping into virtual address space
- Shared memory by mapping pages readwrite into virtual address space
- Pages can be shared during fork(),
 speeding process creation









Demand Paging

- Could bring entire process into memory at load time
- Or bring a page into memory only when it is needed
 - Less I/O needed, no unnecessary I/O
 - Less memory needed
 - Faster response
 - More users
- Similar to paging system with swapping (diagram on right)
- Page is needed ⇒ reference to it
 - invalid reference ⇒ abort
 - not-in-memory ⇒ bring to memory
- Lazy swapper never swaps a page into memory unless page will be needed
 - Swapper that deals with pages is a pager








Basic Concepts

- With swapping, pager guesses which pages will be used before swapping out again
- Instead, pager brings in only those pages into memory
- How to determine that set of pages?
 - Need new MMU functionality to implement demand paging
- If pages needed are already memory resident
 - No difference from non demand-paging
- If page needed and not memory resident
 - Need to detect and load the page into memory from storage
 - 4 Without changing program behavior
 - 4 Without programmer needing to change code






Valid-Invalid Bit


- With each page table entry a valid–invalid bit is associated (v ⇒ in-memory – memory resident, i ⇒ not-in-memory)
- Initially valid-invalid bit is set to i on all entries
- Example of a page table snapshot:


77 <u> </u>	Frame #	valid-i	nvalid bit
3.		V	
N.		V	
		V	
		i	
	* * *		
		i	
		i	
	page tabl	le	

 During MMU address translation, if valid–invalid bit in page table entry is i ⇒ page fault




Page Table When Some Pages Are Not in Main Memory











Page Fault

 If there is a reference to a page, first reference to that page will trap to operating system:


page fault

- 1. Operating system looks at internal table in the process control block to decide:
 - Invalid reference ⇒ abort
 - Just not in memory
- 2. Find free frame
- 3. Swap page into frame via scheduled disk operation
- Reset tables to indicate page now in memory Set validation bit = v
- 5. Restart the instruction that caused the page fault






Steps in Handling a Page Fault







Aspects of Demand Paging



- Extreme case start process with no pages in memory
- 3 (9=3)
- OS sets instruction pointer to first instruction of process, nonmemory-resident -> page fault
- And for every other process pages on first access
- Pure demand paging
- Actually, a given instruction could access multiple pages page faults
 - Consider fetch and decode of instruction which adds 2 humbers from memory and stores result back to memory
 - Pain decreased because of locality of reference
- Hardware support needed for demand paging
 - Page table with valid / invalid bit
 - Secondary memory (swap device with swap space)
 - Instruction restart





Demand Paging Example

Memory access time = 200 nanoseconds

- Effective Access
 Time:
- Average page-fault service time = 8 milliseconds
- EAT = $(1 p) \times 200 + p (8 \text{ milliseconds})$ = $(1 - p \times 200 + p \times 8,000,000)$ = $200 + p \times 7,999,800$
- If one access out of 1,000 causes a page fault, then
 EAT = 8.2 microseconds.

This is a slowdown by a factor of 40!!

- If want performance degradation < 10 percent
 - 220 > 200 + 7,999,800 x p
 20 > 7,999,800 x p
 - p < .0000025
 - < one page fault in every 400,000 memory accesses






Page Replacement


- Prevent over-allocation of memory by modifying pagefault service routine to include page replacement
- Use modify (dirty) bit to reduce overhead of page transfers – only modified pages are written to disk
- Page replacement completes separation between logical memory and physical memory – large virtual memory can be provided on a smaller physical memory







Need For Page Replacement














Basic Page Replacement


- 1. Find the location of the desired page on disk
- 2. Find a free frame:
 - If there is a free frame, use it
 - If there is no free frame, use a page replacement algorithm to select a victim frame
 - Write victim frame to disk if dirty
- 3. Bring the desired page into the (newly) free frame; update the page and frame tables
- Continue the process by restarting the instruction that caused the trap


Note now potentially 2 page transfers for page fault – increasing EAT






Page Replacement





memory






Page and Frame Replacement Algorithms


- Frame-allocation algorithm determines
 - How many frames to give each process
 - Which frames to replace
- Page-replacement algorithm
 - Want lowest page-fault rate on both first access and re-access
- Evaluate algorithm by running it on a particular string of memory references (reference string) and computing the number of page faults on that string
 - String is just page numbers, not full addresses
 - Repeated access to the same page does not cause a page fault
 - Results depend on number of frames available
- In all our examples, the reference string of referenced page numbers is

7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1






Graph of Page Faults Versus The Number of Frames








First-In-First-Out (FIFO) Algorithm

- Reference string: 7,0,1,2,0,3,0,4,2,3,0,3,0,3,2,1,2,0,1,7,0,1
- 3 frames (3 pages can be in memory at a time per process)




- 15 page faults
- Can vary by reference string: consider 1,2,3,4,1,2,5,1,2,3,4,5
 - Adding more frames can cause more page faults!
 - 4 Belady's Anomaly
- How to track ages of pages?
 - Just use a FIFO queue






FIFO Illustrating Belady's Anomaly








Optimal Algorithm


- Replace page that will not be used for longest period of time
 - 9 is optimal for the example
- How do you know this?
 - Can't read the future
- Used for measuring how well your algorithm performs






Least Recently Used (LRU) Algorithm

- Use past knowledge rather than future
- Replace page that has not been used in the most amount of time
- Associate time of last use with each page




- 12 faults better than FIFO but worse than OPT
- Generally good algorithm and frequently used
- But how to implement?




Thrashing

- If a process does not have "enough" pages, the page-fault rate is very high
 - Page fault to get page
 - Replace existing frame
 - But quickly need replaced frame back
 - This leads to:
 - 4 Low CPU utilization
 - 4 Operating system thinking that it needs to increase the degree of multiprogramming
 - 4 Another process added to the system
- Thrashing ≡ a process is busy swapping pages in and out





Thrashing (Cont.)





End of Chapter 9

