NETWORK SIMULATOR

NS2

JUST THE NEEDED STUFF:D

COMPONENTS

Any network simulation includes:

- tcl script to specify ns file.tcl
 - Nodes
 - > Links
 - > Traffic
 - > Scheduling
- **tr** Trace files
 - Trace file to trace the whole simulation and for analysis (post processing)
 - Trace file for nam (network animation) nam file.nam
- awk scripts for analysis/performance evaluation awk -f file.awk file.tr
- Graph for graphical representation of the analysis xgraph file.txt

TRACE FILE

WIRED - invoke by trace-all
Nam file - invoke by namtrace-all

event	time	from node	to node	pkt type	pkt size	flags	fid	src addr	dst addr	seq num	pkt id
		+ 1.3	5576 2	3 tcp	1000	1	0.0 3	.0 29 1	99		

WIRELESS - has different formats. Additional trace information can be turned ON/OFF

Old format trace-all

r 1.728405901 _2_ RTR --- 10 message 32 [0 ffffffff 8 800] [energy 999.820034 ei 0.172 es 0.000 et 0.001 er 0.007] ------ [8:255 -1:255 32 0]

New format (so much more information) use-newtrace

s -t 1.000000000 -Hs 20 -Hd -2 -Ni 20 -Nx 249.70 -Ny 319.00 -Nz 0.00 -Ne 90.000000 -Nl AGT -Nw --- -Ma 0 -Md 0 -Ms 0 -Is 20.0 -Id 4.0 -It cbr -Il 512 -If 0 -Ii 1 -Iv 32 -Pn cbr -Pi 0 -Po 0

Nam file namtrace-all-wireless

We used old format in lab. Use format depending on the need. This is just 1 example. Many formats are there in old and new formats.

TRACE FILE FORMAT

WIRED 1. Event

- + enqueue
- dequeue
- **d** dropped
- **r** received

- + 1.35576 2 3 tcp 1000 ----- 1 0.0 3.0 29 199
- Data is sent in the form of packets
- Every link has a queue into which packets are enqueued

11. Sequence number – A packet *can* have a sequence number

- Packets are then dequeued from the queue and transmitted through the link
- When queue is full, packets are not accepted and/or dropped
- **2. Time** Time at which the record is made from the simulation (accurate up to 5 to 6 decimals). That's pretty much why trace files are HUGE!
- **3,4. Source, Dest Node** Source node and destination node of the packet (intermediate source and destination)
- **5.** Packet type tcp, cbr, ack, etc.
- 6. Packet size in bytes
- 7. Flag 7 flag strings are available (don't bother)

 '-' is used if disabled
- 8. Flow ID usually specified by us using fid_

12. Packet ID – every packet has a unique ID assigned to it when generated

(to be processed in that sequence)

9, 10. Source, Destination Address – in the form *address.port* (node.port)

TRACE FILE FORMAT WIRELESS

Old trace format

s 0.032821055 _1_ RTR --- 0 message 32 [0 0 0 0] ----- [1:255 -1:255 32 0]

<u>Column</u>	<u>Function</u>									
1	Action s (send), r (receive), d (dropped) There are no enqueue/dequeue actions since there are no links									
2	Time									
3	Node at which action occurs									
4	Layer (PHY, MAC, LL, AGT, etc.)									
5	Flag									
6	Sequence number									
7	Packet type (CBR, RTS, DSR, etc.)									
8	Size of packet at current layer									
[9 10 11 12]	[duration in mac layer destination source mac type]									

OLD WIRELESS TRACE (cont) s 0.032821055 _1_ RTR --- 0 message 32 [0 0 0 0] ------ [1:255 -1:255 32 0]

13 to 19 Flags (including energy)

[20 21 22 23] [source destination ttl header next hop]

```
NEW WIRELESS TRACE s -t 1.0000000000 -Hs 20 -Hd -2 -Ni 20 -Nx 249.70 -Ny 319.00 -Nz 0.00 -Ne 90.000000 -Nl AGT -Nw --- -Ma 0 -Md 0 -Ms 0 -Is 20.0 -Id 4.0 -It cbr -Il 512 -If 0 -Ii 1 -Iv 32 -Pn cbr -Pi 0 -Po 0
```

- s (send), r (receive), d (dropped), f (forward)
- -t (time)
- -H (next hop info)
- -N (node properties x y z coordinates of node position, energy level, etc.)
- -M (Packet info at mac level)
- -I (Packet info at IP level)
- -P (Packet info at Application level)

XGRAPH xgraph filename

Operates on a file with 2 columns (x and y coordinates) separated by a space. We create this file from the trace file.

- Plot multiple graphs together xgraph file1 file2 file3
- Specify the dimensions of the graph geometry 800x400 (it chooses an appropriate geometry if not specified)
- Specify that it is a bar graph -bar
- Specify the bar width -brw 1
- Specify there should be no lines -nl (usually used with bar graphs)
- Specify a title -t string

PERFORMANCE METRICS WIRED

• Throughput - Average transform rate (amount of data that moved successfully from one node to another in a given time period)

throughput = total bits received by the destination
Time of observation

• Packet Delivery Ratio = packets received

Packets sent

While computing packets for wireless, ensure layer is AGT

- Packet Loss Ratio = packets dropped (or) packets sent received
 Packets sent

PERFORMANCE METRICS WIRED

• Fairness - to determine if users are receiving a fair share of resources

$$\frac{(\sum_{i=1}^{n} t_i)^2}{n * \sum_{i=1}^{n} (t_i)^2}$$

T_i – throughput of ith communication n – no of communications

- Control overhead = No of control packets

 Total no of packets
- Hop Count no of hops required to reach the destination from the source (can be calculated from the trace file by keeping track of the no of packets 'sent')

AWK SCRIPTS

2 ways for computation of parameters – AWK script using trace file, procedure in the tcl script (AWK scripts are needed for all metrics other than throughput)

An AWK script has 3 parts

- BEGIN executed prior to text processing. Usually for initialization of variables (global)
- Content Computation part which processes the text file
- END gets executed at the end

The only statements we 'll use are IF ELSE, basic arithmetic operations and print statements. Similar to C

- We 'll run the awk script on our trace file, every line of the trace file runs through the script
- Execution: awk –f awkfile.awk tracefile.tr > outputfile
- Pass arguments from tcl script : awk -v var=value -f awkfile.awk tracefile.tr

Example 1: THROUGHPUT

```
BEGIN {
          recvsize=0;
          currenttime=0;
     event = $1;
     toNode = $4;
     currenttime = $2;
     if(event =="r" && toNode=="5" ) {
          recvsize+=$6;
printf("%f %f\n", currenttime, (8*recvsize)/(100000*currenttime);
END {
```

TIPS

- To print 1 value, *printf* statement is specified in the END part
- Values from trace file are accessed as \$column
- No separate initialization for arrays is needed (you can just assign a value as delay[i]=val)

While executing in the terminal,

- > will write/replace the output to a new/existing file
- >> will append the output to a file

Example 2 : PACKET LOSS RATIO

```
BEGIN {
          pksend=0;
          pktrec=0;
          currenttime=0;
          event = $1;
          toNode = $4;
          fromNode = $3;
          currenttime = $2;
          if(event =="r" && (toNode=="9" || toNode=="5"))
                    pktrec++;
```

```
if (event=="+" && (fromNode=="1" | | fromNode=="2"))
                     pksend++;
   if (pksend > 0)
     printf("%f %f\n",currenttime,(pksend-pktrec)/pksend);
END {
```

Example 3 : END TO END DELAY

```
BEGIN {
         pksend=0;
         pktrec=0;
         currenttime=0;
        tdelay=0;
         event = $1;
         toNode = $4;
         fromNode = $3;
         currenttime = $2;
```

```
if(event =="r" && (toNode=="5" || toNode=="4"))
    tdelay+=currenttime-starttime[$11];
if (event=="+" && (fromNode=="1" || fromNode=="2"))
     starttime[$11]=currenttime;
printf("%f %f\n",currenttime,tdelay);
END {
```

Example 4 : HOPCOUNT

```
BEGIN {
Hopcount=0;
 If($1=="+" && $3!=srcNode && $5="tcp") {
         Hopcount++;
END{
print Hopcount;
```

Example 5 : ENERGY (wireless)

```
BEGIN {
  energy=0;
}
{
    If ($2<now){
      energy+=$22+$20+$18+$16;
}
END{
    print energy
}</pre>
```

srcNode and now are passed as arguments from the TCL script

TCL BASICS

- Every program starts with creating a Simulator object and ends with invoking the simulator
- A variable is declared using set <var_name> <var_value>

```
set n 5 set X_ set y $x
```

- If value is not specified after variable name, it returns the value of the variable
- A variable is accessed using \$
- exec to execute a command

exec nam out.nam

We exit the program by exit 0

set ns [new Simulator] #rest of the program \$ns run

FILES

- Any file needs to be created before we can write data into it
- Can be created in write (w) or append (a) access
- We set a file handler (variable) for the file and then access it
- we use **puts** to write data into a file from the tcl script

```
set file1 [open test.txt w]

set x 2 this prints 1 2 3 in test.txt

set y 3

puts $file1 "1 $x $y"
```

Creating trace files

set trfile [open out.tr w]
\$ns trace-all \$trfile
set namfile [open out.nam w]
\$ns namtrace-all \$namfile

SCHEDULING AND FINISH

- Every simulation has a finish procedure, which is called at the end
- Procedures are declared using proc
- We need to flush all buffers and close the trace files (in the example we instruct the finish procedure to execute the nam file before exiting)

```
proc finish {} {
    global ns trfile namfile
    $ns flush-trace
    close $namfile
    close $trfile
    exec nam out.nam &
    exit 0
}
```

- We need to schedule events and procedures we create
- The time and the event/procedure is specified within " "

```
<simulator object> at <time> <event>
```

```
$ns at 0.5 "$ftp start"
$ns at 3 "$ftp stop"
$ns at 3.1 "finish"
```

NODES AND LINKS

- Nodes are created using node set n0 [\$ns node] (a node n0 is created)
- To change shape of a node \$n0 shape box (circle/hexagon/box) circle by default
- To change color of a node \$n0 color red (color is case insensitive red/Red)
- To attach a label to a node \$n0 label "I am node 0"
- Links are created as \$ns duplex-link \$n0 \$n1 2Mb 10ms DropTail
 - Link type can be simplex/duplex
 - Queue type can be DropTail/SFQ/RED etc
 - Link Bandwidth needs to be specified in Mb
 - propagation delay needs to be specified in ms

Here a duplex link of BW 1Mbps and delay of 10ms is created between n0 and n1

LINKS AND QUEUES

• Orientation of links - left, right, up, down, left-up, right-down etc.

- specified using **op**

\$ns duplex-link-op \$n0 \$n1 orient down

Refer this link for queue types goo.gl/MWEKGo

Each queue type has its own default buffer size

\$ns queue-limit \$n0 \$n1 100 (queue size is set to 100 packets for this specific queue)

Queue/RED set queue-limit 200 (for specific class of queues)

Queue set limit_ 5 (all queues)

Queue statistics can be analyzed using queue monitor

(actually pretty useful, but we don't utilize it. Refer internet)

TRANSMISSIONS - AGENT

- An agent needs to be attached to a node to enable transmission
- There are around 28 agents like TCP, UDP, TCPSink, etc.
- TCP Connection is established before transmission of data
- UDP Connectionless transfer of data
- STEP 1 : Create an instance of the agent (source) set tcp1 [new Agent/TCP]
- STEP 2: Attach the agent to a node \$ns attach-agent \$n0 \$tcp1
- Similarly TCPSink agent is created for the destination. Null agent for UDP
- STEP 3: Connect the source and the sink \$ns connect \$tcp1 \$sink1
- STEP 4: Flow id can be set (used to specify colors/analysis) \$tcp1 set fid_ 1

TRANSMISSIONS - APPLICATION

- Now that transport protocol is specified, we need to create the application
- Applications can be FTP, Telnet, Traffic (CBR, Exponential, Pareto, Trace)
 (In our examples, we usually use FTP with TCP and CBR with UDP)
- We need to create an instance of the application and attach it to the agent

```
set cbr2 [new Application/Traffic/CBR]
$cbr2 attach-agent $udp2
```

• We can additionally specify packet size and rate for CBR (Constant Bit Rate) traffic

```
$cbr2 set packetSize_ 1024
$cbr2 set rate_ 1Mb
```

ADDITIONAL TCL TIPS

We implement mac protocols in the bus topology Csma or Csma/Cd

set lan [\$ns newLan "\$n1 \$n2 \$n3 \$n4 \$n5" 0.1Mb 50ms LL Queue/DropTail MAC/Csma Channel]

• Using loops/conditions (it is very convenient to use for loops for node/link creation)

```
while { $i < 10 } {
set node($i) [$ns node]
set i [expr $i+1]
}
```

```
for { set i 0 } { $i < 10 } { set i [expr $i+2] } { puts $i }
```

```
if { condition } {
  if - body
  } else {
  else - body
  }
```

- Executing an expression expr (\$i+1)%7
- To select a random number (between 0 and 19) expr { int(rand()*20 }

WIRELESS NETWORKS

Wireless networks require extra lines of code to

- Create god
- Create topography object
- Configure wireless nodes

```
Inbuilt source codes works only with ns_ (hence we usually create a simulator object like this) set ns_ [new Simulator]
```

Trace commands

```
$ns_ trace-all $trfile
$ns_ namtrace-all-wireless $namfile $val(x) $val(y)
$ns_ eventtrace-all
```

(x and y are the dimensions of your network topology)

GOD & TOPOLOGY

- General Operation Director stores information about each node
- Hence no of nodes must be specified while creation to reserve space
- We use **create-god <no of nodes> set god_ [create-god \$val(nn)]** (god_ is used when using inbuilt source codes, similar to ns_)

We use a flat-grid topology for wireless

NODE CONFIGURATION

- We need to configure the nodes before creating them
- We usually set default values for all our properties beforehand

SETTING UP VALUES

Channel to be used. We use a wireless channel for our network


set val(chan) Channel/WirelessChannel;

Signal propagation type – can be Two Ray Ground or Shadowing

set val(prop) Propagation/TwoRayGround;

Physical layer type

set val(netif) Phy/WirelessPhy;



multipath

path loss

SHADOWING

NODE CONFIGURATION (cont)

Link layer type set val(II) LL; Medium Access control - 802_11 (csma/ca for wireless), Tdma, etc set val(mac) Mac/802_11; Type of antenna (ns2.35 has support only for omni antenna) set val(ant) Antenna/OmniAntenna; Type of interface queue — DropTail, DropTail/PriQueue set val(ifq) Queue/DropTail; Routing Protocol – DSR, AODV, DSDV, FLOODING Interface queue length set val(rp) DumbAgent; set val(ifqlen) 50;

(DumbAgent is used when no routing is required)

OTHER VALUES

No of nodes in the network set val(nn) 20;

Value of network dimensions

```
set val(x) 500;
set val(y) 400;
```

We use two arbitrary variables to refer to our mobility and transmission files generated using **setdest** and **cbrgen** files

```
set val(cp) "trans_10";
set val(sc) "dest_10";
```

To include these in our program, add these lines after node creation

```
source $val(cp)
source $val(sc)
```

NODE CONFIGURATION

We use the values defined previously to configure our nodes

```
$ns_ node-config -adhocRouting $val(rp)\
                                                   adhoc routing protocol
                 -IIType $val(II)\
                                                   link layer
                 -macType $val(mac)\
                                                   medium access control
                 -ifqType $val(ifq)\
                                                   type of interface queue
                 -ifqLen $val(ifqlen)\
                                                   queue length
                 -antType $val(ant)\
                                                   antenna
                 -propType $val(prop)\
                                                   propagation type
                 -phyType $val(netif)\
                                                   physical layer
                 -channelType $val(chan)\
                                                   channel
                 -topolnstance $topo\
                                                   topography instance for the network
                 -agentTrace ON\
                                                   tracing at agent level
                 -routerTrace OFF\
                                                   tracing at router level
                                                   tracing at mac level
                 -macTrace ON\
                 -movementTrace OFF
                                                   mobile node movement logging
```

NODE CONFIGURATION

When accessing energy of the nodes, we include the following

```
energy model is enabled
-energyModel "EnergyModel"\
-initialEnergy 1000\
                                  initial energy for each node
                                  power for receiving 1 packet
-rxPower 1.0\
                                  power for transmitting 1 packet
-txPower 1.0\
-sleepPower 0.5\
                                  power consumed during sleep state
-transitionPower 0.2\
                                  power consumed during state transition from sleep to idle
                                  time taken during transition
-transitionTime 0.001\
                                  power consumed during idle state
-idlePower 0.1
```

(Default values will be used for the powers if not specified)

trace file while using energy model: [energy 998.9992 ei 1.000 es 0.000 et 0.000 er 0.001]

ei – energy consumption in IDLE state es – energy consumption in SLEEP state et – energy consumed in transmission er – energy consumed in receiving

energy – residual energy

NODES

Now that node configuration is done, we do the following to create our wireless network

- Create the node (similar to wired network)
- Set up their positions (set up the x, y, and z coordinates and their initial positions)
- Set their mobility (we usually randomize the node's mobility)
- Set up transmission (either ftp or cbr traffic similar to wired)

NODE CREATION

```
for {set i 0} {$i < $val(nn)} {incr i} {
    set node_($i) [$ns_ node]
} creates nn nodes - node_(0), node_(1),...node_(nn-1)</pre>
```

NODES

POSITION

```
$node_(0) set X_ 283
                                           node location
                                                                This has to be done for every node.
$node_(0) set Y_ 425
$node_(0) set Z_ 0
                                           z coordinate is always 0
$ns initial_node_pos $node_(0) 30
                                           node size
for {set i 0} {$i < 5 } {incr i} {
        $node_($i) set X_ [expr rand()*500]
         $node_($i) set Y_ [expr rand()*500]
        $node_($i) set Z_ 0.0
        $ns initial_node_pos $node_($i) 20
To set node radius: $n0 radius 20
                                            sets radius of n0 as 20
To set distance: $god_set-dist 3 4 2
                                            sets distance between node 3 and 4 as 2 hops
```

NODES

MOBILITY

```
$ns at 1.2 "$n0 setdest 300 200 20" at 1.2, n0 will start moving to (300,200,20)
$n0 random-motion 1 random motion is enabled by 1 and disabled by 0
To generate random node positions and mobility, we use setdest file. Execute as ./setdest
```

TRANSMISSIONS

Similarly, random transmissions can be generated using **cbrgen** file. Execute as **ns cbrgen** (1 less than the total nodes must be specified in cbrgen)

Transmissions can be generated manually also, just like wired networks

```
set udp [new Agent/UDP]
$ns attach-agent $node_(0) $udp
set null [new Agent/Null]
$ns attach-agent $node_(1) $null
$ns connect $udp $null
```

```
set cbr [new Application/Traffic/CBR]
$cbr attach-agent $udp
$cbr set packetSize_ 1024
$cbr set interval_ 0.1
$ns at 1.0 "$cbr start"
$ns at 5.0 "$cbr stop
```

ADDITIONAL TIPS

• Control overhead = RTS or CTS packets

Total packets

Calculating overhead for different routing protocols involves different control packets. Refer your trace file and write your awk scripts

- Received Signal Strength = Transmission Power

 Distance bet source and node
- To get the x co-ordinate of node 0, [\$n0 set X_]
- To disable RTS or CTS, Mac/802_11 set RTSThreshold_ 1000
 (RTS is used for all packets greater than size 1000)
 Thus to enable RTS for all packets, Mac/802_11 set RTSThreshold_ 0 (Similarly for CTS)
- To simulate flooding, the sample flooding.tcl file is used. (sample tcl files are available in ~ns/ns-2.35/tcl/ex/)

ADDITIONAL TIPS

- While calculating PDR or PLR in wireless, packets in the AGT level must be considered (AgentTrace must be ON)
- Jitter is the time delay for a packet the time difference between when the packet is sent and when it is received
- In case of Packet Delivery (or Loss) **Ratio**, we divide the received packets by total packets sent. In case of **Rate**, we divide by the time
- MANET (Mobile Adhoc Network) all nodes are mobile and they use an adhoc routing protocol (no central coordinator) like AODV, DSDV, DSR
- VANET (Vehicular Adhoc Network) and WSN (Wireless Sensor Network) are types of MANETs
- VANET characterized by high node mobility and rapid topology changes

ADDITIONAL TIPS

• WSN – consists of multiple sensor nodes. Sense power needs to be specified for sensor nodes. Communication range and sensing range need to be specified.

```
$val(netif1) set CSThresh_ 2.28289e-11; #sensing range of 500m
$val(netif1) set RXThresh_ 2.28289e-11; #communication range of 500m
```

- Commonly used Routing protocols for wired networks, \$ns rtproto DV (or LS)
 Distance Vector Routing routing tables are sent to neighbors
 Link State Routing information about the whole topology is known
- Commonly used Routing protocols for wireless networks AODV, DSR, DSDV
 TABLE DRIVEN all route information is maintained in the routing table DSDV
 ON-DEMAND/EVENT DRIVEN routing table contains information only about routes currently in use

AODV (periodic routing packets) **DSR** (routing packets are sent only when necessary)